Computer Systems Organization

Druhan Rajiv Shah

Spring - 2023

Contents

	Textbooks	2
	Grading	2
1	Introduction	2
	How is this different?	2
2	Computer System structure	2
	Overall structure	2
	CPU	2
	Dynamic RAM	3
	Register file	3
	Running an executable	3
	Processor-Memory gap	3
	RAM types	3
	More RAM types!	3
	OS Cameo	3
3	Computer Arithmetic	3
	Numerical representation	3
	Words	3
	Enter Jonathan Swift?	4
	ASCII what you did there	4
	3.1 Boolean operations	4
	Basic operators	4
	More representation	4
	Conversion between religions—wait no, I mean systems	4
	Words of a feather flock together	4
	This operation's a success, doc!	5
	Fraction representation	5
	Float like a butterfly	5
	How to not float	5
	I could be bounded in a nut shell	.5
	Operate like a surgeon?	6
4	SimpleRISC Assembly	6
5	ARM Assembly	6
ß	v86 Assambly	6

Course Structure

The first half (upto, but not including Assembly code) will be taught by Suryajith Chillara, while the second half will be taught by Girish Verma.

Textbooks

- Computer Systems: A Programmer's Perspective Bryant & O'Hallon
- Computer Systems Organization Patterson & Henessey

Topics The ranges in the parentheses are sections in the first textbook.

- Computer Arithmetic (2.1 2.3)
- Assembly language (3.4 3.7)
- Processor architecture and design (4.1 4.5)
- Memory hierarchy (6.1 6.4)
- System calls: Intro to process control (8.2 8.4)

Grading

Assignments (Programming-based) - 20%

Deep Quizzes - 20%

Midsem Lab Exam - 15%

Endsem - 25%

Endsem Lab Exam - 20%

1 Introduction

How is this different? In previous courses we studied how computers worked in a sort of abstract way, without actually worrying about what goes on under the table. This 'under the table' stuff is exactly what we will be discussing in this course.

2 Computer System structure

Overall structure In a typical system, there are several functional sections, like the CPU, which contains the Program counter, register file and ALU; I/O Bridge, controllers, adapters and Main memory; each of which is interconnected through buses. These buses transfer fixed-side chunks of bytes (called words).

Now, all of the information is contained in bits (which, recall, are just states of low vs high voltage). The bandwidth of these buses is what determines the word length of the system. This would be more familiar as whether a system has a 32-bit or 64-bit architecture.

Note, the difference between a controller and an adapter is whether it is directly connected to the motherboard or not. So, mouse and keyboard ports are termed controllers, while a monitor or a display would need an adapter. Earlier, RAMs used to be connected using adapters as opposed to controllers.

CPU A CPU contains a PC, a register file and an ALU. Program counters are necessary for parallel processing of instructions. An ALU is self-explanatory and does most of the calculation here. Note that this is what CPUs looked like a good while ago. Nowadays it's a lot more complicated.

What CPUs do essentially, is they Load data from the RAM into the register; Store a copy form the register to the main memory; Operate by copying contents of a register to the ALU and load the output back into the register; and Jump by extracting a word from instrutions and overwrite into the PC. (Load, Store, Operate, Jump is gonna be a recurring theme in formalizations)

Dynamic RAM The main memory is organized into a linear array of bytes, each with its unique address (recall CPro). The Program Counter back in the CPU points to the current instruction in the main memory.

Register file It's a small storage device that contains a collection of word-sized registrs, each with unique names.

Running an executable First, the system accepts the input of the command from the USB controllers, dumps it into the main memory and then processes it, loads the instructions from the disk into main memory, and finally runs each of the instructions in sequence.

Processor-Memory gap Moore's law says that the processing power doubles every constant amount of time (paraphrase :P).

RAM types The damage this causes can be mitigated by involving Cache memories and Registers, both of which are implemented using Static RAMs, which use flip-flops as opposed to capacitors and transistors in DRAM. DRAMs have a constant recharging of the capacitors, the rate of which is called the refresh rate of the DRAM. However, SRAMs use flip-flops which are significantly more stable. This makes SRAMs more complicated to design while making them significantly faster. This is also why SRAMs are used inside he CPU, while the main memory uses DRAM.

Note that both SRAMs and DRAMs are both volatile, meaning that the moment the system is shut down, the information stored in the RAM is destroyed.

More RAM types! There is a hierarchy of 7 types of RAMs, which are labelled from L0 to L6.

The faster, more efficient types of RAM also happen to be way more expensive than their cheaper counterparts and use more energy, which is why we need to optimize where we use each type of RAM and how much it would cost.

OS Cameo Operating Systems behave as a sort of middleman between the Application programs and the hardware of the system. They have two main purposes:

- To protect the hardware from misuse by runaway programs
- To provide a simple and uniform mechanism for programs to manipulate complicated and varied hardware devices (this is done through abstractions that are handled by device drivers)

The abstraction reaches comical levels when considering the implementation of a mouse and a keyboard as simply reading from a file associated with each (on Linux at least)! This is not too slow because these files are specially implemented to be a part of the main memory instead of disk, so reading and writing these files is not too slow.

The abstraction for running a program is a Process. This is convenient to handle concurrency of processes.

3 Computer Arithmetic

Numerical representation We usually use bit representations of numbers, which is convenient because storing information in bits is a lot more efficient because of the 'ON/HIGH' versus 'OFF/LOW' states. This was especially useful back in the days of punch card programming.

However, the representation is rather verbose. (In fact, base b is $\mathcal{O}\left(\frac{\log b}{\log a}\right)$ times as verbose as base a representation). On top of that, we are used to using base 10 due to the languages we speak and the writing systems we use. Conversion from base 10 to base 2 and vice versa is rather cumbersome.

To overcome this, we use the hexadecimal system instead, which has the added consequence of making conversion from binary to hexadecimal much more convenient. In fact, for a compiler, you can save some computation power and use a lookup table instead of calculating the conversion each time at the cost of a tiny amount of space.

Words Word size is a measure of the size of integer and pointer data.

Note that this means 32-bit computers have a hard limit on the size of virtual memory because there are only $2^{32} \approx 4 \times 10^9$ possible address indices.

Enter Jonathan Swift? The Lilliputian argument of Big-Endians vs Little-Endians is still strong in bit representations as well, because whether the first bit should be for the most or least significant bit respectively. *e.g.* Sun, IBM machines prefer the Big-Endian approach, while Intel machines prefer the Little-Endian approach.

The Big-Endian vs Little-Endian approach also applies to memory location indexing. Here the Little-Endian approach would require the least significant digits in the hexadecimal form of an address or integer to be stored and processed earlier in the memory.

Now this is dangerous because multiple machines which use different approaches in the same system could possibly lead to disaster if not spotted.

ASCII what you did there Strings can now be represented as strings of integers, each of which corresponds to each character. The generally accepted system of encoding the characters as integers is called the American Standard Code for Information Interchange (ASCII). However, there is also Unicode which is gaining more popularity over time.

3.1 Boolean operations

Basic operators The standard NOT, AND, OR and XOR are also used nowadays for bit operations in computers, even though the notation used is different from that used in Propositional Logic (because of the character set allowed by ASCII). These operations can be applied on bit vectors bit-by-bit to make 'bitwise' operators.

Additionally, \oplus , \wedge , \neg can be thought of as +, \times , negation in the Boolean Ring.

As a bonus, bit vectors can be used to represent subsets (obviously), so the operators behave analogously to set operations in the Power Set Ring.

More representation Pure binary representation can only store nonnegative integers. If we were to store negative numbers as well, we would need alternative methods. One possibility is the signed n-bit notation, which assigns a sign bit at the cost of absolute range.

Another possibility, which is more often used, is the 2's complement encoding, which makes operations a lot simpler. Recall DSM.

$$\begin{aligned} & \text{Signed 2's complement}: \text{B2T}_w\left(\vec{x}\right) = -x_{w-1} \cdot 2^{w-1} + \sum_{i=0}^{w-2} x_i \cdot 2^i \\ & \text{Unsigned representation}: \text{B2U}_w\left(\vec{x}\right) = \sum_{i=0}^{w-1} x_i \cdot 2^i \end{aligned}$$

Clearly, both of these functions are bijective over w-bit numbers.

Conversion between religions—wait no, I mean systems We can define $T2B_w = B2T_w^{-1}$ and $U2B_w = B2U_w^{-1}$ to be the inverses of the functions as above. Clearly these are more functions that covert from one representation to another. Now the conversion from signed to unsigned representations is going to cause some pain, but it is very much possible using these functions. Obtaining an intuition of these conversions is going to be necessary!

Words of a feather flock together Conversion of numbers from a higher-bit representation to lower is very messy and can lead to losses. However, converting from lower-bit numbers to higher ones is possible and very common. Suppose we convert a signed w-bit number to w'-bit number, where w' > w, then we must have that:

$$[x_{w-1}, x_{w-2}, \dots, x_0] = [x_{w'-1}, x_{w'-2}, \dots, x_0]$$

 $\Rightarrow x_i = x_{w-1} \quad \forall w' > i \ge w$

This can be proved by considering positive and negative representations respectively. Understandably, the unsigned representation can just be converted by prepending zeroes in the beginning.

Also, it is relatively easily to see that truncating numbers is essentially taking the number modulo a power of 2. However, note that this gives us a strictly unsigned representation. Thus, if we wish to truncate a number x down to k bits, we will have to compute the value $U2T_k \left(B2U_k(x \mod 2^k)\right)$

Interestingly this can lead to some serious security flaws. See FreeBSD's getpeername vulnerability.

This operation's a success, doc! Operations on integers are not very hard to implement. However, the overflow situations need to be handled carefully. For unsigned integers, the overflow is simple as the number simply wraps around, essentially implementing a modulo operation after the addition. Signed representations are a little messier as they have to consider cases of positive and negative overflow.

We have

$$x + {}_{w}^{u} y = \begin{cases} x + y & x + y < 2^{w} \\ x + y - 2^{w} & 2^{w} \le x + y \le 2^{w+1} \end{cases}$$

For the signed two's complement case, things become spicier:

$$x + {}^{t}_{w} y = U2T_{w} (T2U_{w}(x) + {}^{u}_{w} T2U_{w}(y))$$

It can be proved that unsigned and signed multiplication can be computed identically as $x \cdot y \mod 2^k$ for k-bit integers.

Fraction representation Naturally, the mathematical definition of the base-n representation can account for fractional numbers. The powers simply extend in the negative direction.

Now, the challenge is to determine how to represent fractions with a fixed number of bits. If we use a fixed number of bits for the fractional part, then we cannot represent fractions of arbitrary precision. Instead, there will be some granularity, so to speak. We have to attain some middle ground, as far as possible.

Float like a butterfly... Now, the modern approach is the 'floating point', which uses the so-called 'scientific notation'. Each number is represented as follows:

$$N = (-1)^s \cdot M \cdot 2^E$$

Where, s, M, E are respectively, the sign bit, the 'mantissa' (also called the 'significand') and the exponent. Note that $1 \le M \le 2$.

Now, in the bit-representation of such numbers, the standard for 32-bit floating point numbers is 1 sign bit, 8 (e-)bits for $E + 2^{k-1} - 1$, and the remaining 23 (f-)bits for M - 1. Note that, when the e-bits are all 0, the f-bits now represent M as it is. This is called the denormalized representation, while normalized is when the e-bits aren't all 0 or all 1. This distinction is convenient to compare two floating point numbers and allow for greater precision. This becomes clear when looking at the bounds of normalized and denormalized numbers.

Additionally, when the e-bits are all 1, the convention is to use this for very specific values and not to store actually numerical values. When e-bits are all 1 and f-bits are all 0, it is used to represent $\pm \infty$. When e-bits are all 1 and f-bits are not all 0, it is used to represent NaN.

How to not float Obtaining a number in the decimal form from its floating point representation is rather involved, but necessary as we shall see. We denote by e, f the numbers obtained from interpreting the e-bits and the f-bits as in the floating point representation (Note they are not directly E and M). In the denormalized case, i.e. when the e-bits are not all zero or all one,

$$\begin{split} E &= e - 2^{k-1} + 1 \\ M &= 1 + f \quad \text{ where } f \in [0,1) \end{split}$$

In the normalized case, i.e. when the e-bits are all 0,

$$E = 2 - 2^{k-1}$$
$$M = f$$

Here, the $2^{k-1}-1$ in the calculation of E is called the 'bias' term.

I could be bounded in a nut shell Calculating the largest and smallest possible k-bit normalised and denormalised numbers is a fun exercise (which will soon be added here).

...Operate like a surgeon? Floating point multiplication is extremely straightforward.

Suppose we have

$$(-1)^s \cdot M \cdot 2^E = ((-1)^{s_1} \cdot M_1 \cdot 2^{E_1}) \times ((-1)^{s_2} \cdot M_2 \cdot 2^{E_2})$$

Then, it is fairly easy to see that

$$s = s_1 \oplus s_2$$

$$E = E_1 + E_2 + c$$

$$M = \frac{M_1 \cdot M_2}{2^c}$$

Where c is the number of right shifts required to ensure $M_1 \cdot M_2$ fits in the 23-bit width in the floating point representation (Okay, a bit too fancy, it's either 0 or 1 :P). If E exceeds the 8-bit limit, then there is an overflow returned.

Now, floating point addition is a bit more involved. Suppose we have

$$(-1)^s \cdot M \cdot 2^E = ((-1)^{s_1} \cdot M_1 \cdot 2^{E_1}) + ((-1)^{s_2} \cdot M_2 \cdot 2^{E_2})$$

Then, we note that (assuming $E_1 \geq E_2$)

$$E = E_2 + c$$

$$(-1)^s \cdot M = \frac{((-1)^{s_1} \cdot M_1) \cdot 2^{E_1 - E_2} + ((-1)^{s_2} \cdot M_2)}{2^c}$$

Here, s, M are computed using standard signed integer align and addition. Then, c is again the number of shifts required to fit M in the bit limit (now this isn't limited to 0 and 1). Again, if E exceeds the bit limit, then an overflow is returned.

- 4 SimpleRISC Assembly
- 5 ARM Assembly
- 6 x86 Assembly