Package 'ebvnetcdf'

May 6, 2021

111ay 0, 2021
Title Working with EVB NetCDFs
Version 0.0.1
Description This package can be used to easily access the data of the EBV NetCDFs which can be downloaded here: portal.geobon.org. It also provides some basic visualization of the data. Advanced users can build their own NetCDFs with the EBV standard using this package.
License `use_mit_license()`, `use_gpl3_license()` or friends to pick a license
Encoding UTF-8
LazyData true
Roxygen list(markdown = TRUE)
RoxygenNote 7.1.1
BiocViews
Imports checkmate, colorspace, gdalUtils, graphics, HDF5Array, jsonlite, lattice, memuse, methods, ncdf4, raster, rhdf5, rgdal, sp, stats, stringr, utils, withr
Depends R (>= 2.10)
R topics documented:
EBV NetCDF properties-class

Index		18
	wrld_simpl	17
	ebv_properties	
	ebv_plot_map	
	ebv_plot_indicator	15
	ebv_ncdf_write_attribute	14
	ebv_ncdf_entity_attributes	
	ebv_ncdf_create	
	ebv_ncdf_add_data	11
	ebv_data_write	
	ebv_data_read_shp	8
	ebv_data_read_bb	7
	ebv_data_read	6
	ebv_data_change_res	5
	ebv_data_analyse	
	ebv_datacubepaths	3

EBV NetCDF properties-class

EBV NetCDF Properties class (S4)

Description

EBV NetCDF Properties class (S4)

Value

S4 class containing the EBV NetCDF Properties

Slots

```
general Named list. Elements: title, description, ebv_class, ebv_name, ebv_subgroups, creator spatial Named list. Elements: srs, epsg, resolution, extent, dimensions temporal Named list. Elements: units, t_delta, timesteps, timesteps.natural metric Named list. Elements: standard_name, description scenario Named list. Elements: standard_name, description entity Named list. Elements: standard_name, description, unit, type, fillvalue, value_range
```

Note

If the properties class holds e.g. no scenario information this is indicated with an element called status in the list.

ebvnetcdf 3

ebvnetcdf Wa

Working with EVB NetCDFs

Description

This package can be used to easily access the data of the EBV NetCDFs which can be downloaded from the Geobon Portal. It also provides some basic visualization of the data. Advanced users can build their own NetCDFs with the EBV standard using this package.

Details

This package contains three main usecases: accessing the data and visualising the data from the portal and creating your own data in the EBV NetCDF standard. All function have a corresponding naming pattern: ebv_data_ for data reading, ebv_plot_ for visualisation and ebv_netcdf_ for creating a NetCDF.

ebv_datacubepaths

Get datacubepaths of EBV NetCDF

Description

Get the paths to the datacubes of the EBV NetCDF to access the data.

Usage

```
ebv_datacubepaths(filepath, verbose = FALSE)
```

Arguments

filepath Character. Path to the NetCDF file.

verbose Logical. Default: FALSE. Turn on all warnings by setting it to TRUE.

Value

Dataframe containing the paths to access the datacubes and descriptions of scenario, metric and entity if existing.

```
file <- system.file(file.path("extdata","cSAR_idiv_v1.nc"), package="ebvnetcdf")
datacubes <- ebv_datacubepaths(file)</pre>
```

4 ebv_data_analyse

ebv_data_analyse

Get a simple explorative analysis of an EBV NetCDF datacube

Description

Get basic measurements of the data, including min, max, mean, sd, n, #NAs, q25, q50, q75 (no mean for categorical data).

Usage

```
ebv_data_analyse(
   filepath,
   datacubepath,
   subset = NULL,
   timestep = 1,
   at = TRUE,
   epsg = 4326,
   numerical = TRUE,
   na.rm = TRUE,
   verbose = FALSE
)
```

Arguments

filepath	Character. Path to the NetCDF file.
datacubepath	Character. Path to the datacube (use ebv_datacubepaths()).
subset	Optional if you want measurements on a smaller subset. Possible via the path to a shapefile (character) or the indication of a bounding box (vector of four numeric values) defining the subset. Else the whole area is analysed.
timestep	Integer. Choose one or several timesteps (vector).
at	Logical. Optional. Default: TRUE. Only relevant if the subset is indicated by a shapefile. See ebv_data_read_shp().
epsg	Numeric. Optional. Only relevant if the subset is indicated by a bounding box and the coordinate reference system differs from WGS84. See ebv_data_read_bb().
numerical	Logical. Default: TRUE. Change to FALSE if the data covered by the NetCDF contains categorical data.
na.rm	Logical. Default: TRUE. NA values are removed in the analysis. Change to FALSE to include NAs.
verbose	Logical. Default: FALSE. Turn on all warnings by setting it to TRUE.

Value

Returns a named list containing the measurements.

See Also

```
ebv_data_read_bb() and ebv_data_read_shp() for the usage of subsets.
```

ebv_data_change_res 5

Examples

```
file <- system.file(file.path("extdata","cSAR_idiv_v1.nc"), package="ebvnetcdf")
datacubes <- ebv_datacubepaths(file)
data.global.year <- ebv_data_analyse(file, datacubes[1,1], timestep=c(1:12))
data.germany.1900 <- ebv_data_analyse(file, datacubes[1,1], c(5,15,47,55), timestep=1)</pre>
```

ebv_data_change_res

Change the resolution of the data of an EBV NetCDF

Description

Change the resolution of one datacube of a EBV NetCDF based on another EBV NetCDF or a given resolution. This functions writes temporary files on your disk. Speficy a directory for these setting via options('temp_directory'='/path/to/temp/directory').

Usage

```
ebv_data_change_res(
    filepath_src,
    datacubepath_src,
    resolution,
    outputpath,
    timestep = 1,
    method = "average",
    return.raster = FALSE,
    overwrite = FALSE,
    ignore.RAM = FALSE,
    verbose = FALSE
)
```

Arguments

filepath_src Character. Path to the NetCDF file whose resolution should be changed. datacubepath_src

Character. Path to the datacube (use ebv_datacubepaths()) whose resolution

should be changed..

resolution Either the path to an EBV NetCDF file that determines the resolution (character)

or the resolution defined directly (numeric). The vector defining the resolution directly must contain three elements: the x-resolution, the y-resolution and the

corresponding epsg.

outputpath Character. Set path to write data as GeoTiff on disk. timestep Integer. Choose one or several timesteps (vector).

method Character. Default: Average. Define resampling method. Choose from: "near", "bilinear", "cubic", "cul

and "q3". For detailed information see: gdalwarp.

return.raster Logical. Default: FALSE. Set to TRUE to directly get the corresponding raster

object.

overwrite Logical. Default: FALSE. Set to TRUE to overwrite the outputfile defined by

'outputpath'.

ignore.RAM Logical. Default: FALSE. Checks if there is enough space in your memory to

read the data. Can be switched off (set to TRUE).

verbose Logical. Default: FALSE. Turn on all warnings by setting it to TRUE.

6 ebv_data_read

Value

Default: returns the outputpath of the GeoTiff with the new resolution. Optional: return the raster object with the new resolution.

Examples

```
#define temp directory
options('temp_directory'=system.file("extdata/", package="ebvnetcdf"))
file <- system.file(file.path("extdata","cSAR_idiv_v1.nc"), package="ebvnetcdf")
datacubes <- ebv_datacubepaths(file)
res1 <- system.file(file.path("extdata","rodinini_001.nc"), package="ebvnetcdf")
res2 <- c(1,1,4326)
out <- file.path(system.file(package='ebvnetcdf'),"extdata","changeRes.tif")
#ebv_data_change_res(file, datacubes[1,1], res1, out, c(1,6))
#d <- ebv_data_change_res(file, datacubes[1,1], res2, NULL, 3, method='max', return.raster=TRUE)</pre>
```

ebv_data_read

Read datasube from an EBV NetCDF

Description

Read one or more layers from one datacube of the NetCDF file. Decide between in-memory array, in-memory raster or an array-like object (DelayedMatrix) pointing to the on-disk NetCDF file. Latter is useful for data that exceeds your memory.

Usage

```
ebv_data_read(
   filepath,
   datacubepath,
   timestep,
   delayed = TRUE,
   sparse = FALSE,
   raster = FALSE,
   ignore.RAM = FALSE,
   verbose = FALSE
```

Arguments

filepath Character. Path to the NetCDF file.

datacubepath Character. Path to the datacube (use ebv_datacubepaths()).

timestep Integer. Choose one or several timesteps (vector).

delayed Logical. Default: TRUE. Returns data as DelayedMatrix object. More timesteps are not returned as a 3D array but as a list of the DelayedMatrix (one matrix per band).

sparse Logical. Default: FALSE. Set to TRUE if the data contains a lot empty raster cells. Only relevant for DelayedMatrix. No further implementation by now.

raster Logical. Default: FALSE. Set to TRUE and 'delayed' to FALSE to get a raster.

If both arguments are set to FALSE the function returns an array.

ebv_data_read_bb 7

ignore.RAM Logical. Default: FALSE. Checks if there is enough space in your memory to

read the data. Can be switched off (set to TRUE).

verbose Logical. Default: FALSE. Turn on all warnings by setting it to TRUE.

Value

Array, Raster or DelayedMatrix object containing the data of the corresponding datacube and timestep(s).

Note

For working with the DelayedMatrix take a look at DelayedArray::DelayedArray() and the DelayedArray-utils.

Examples

```
file <- system.file(file.path("extdata","cSAR_idiv_v1.nc"), package="ebvnetcdf")
datacubes <- ebv_datacubepaths(file)
#cSAR.delayedarray <- ebv_data_read(file, datacubes[1,1], c(1,6), delayed=T, sparse=T)
#cSAR.raster <- ebv_data_read(file, datacubes[1,1], 1, delayed = F, raster = T)
#cSAR.array <- ebv_data_read(file, datacubes[1,1], c(1,1,3), delayed = F, raster = F)</pre>
```

ebv_data_read_bb

Read subset (bounding box) of one datacube of an EBV NetCDF

Description

Read a subset of one or more layers from one datacube of the NetCDF file. Subset definition by a bounding box.

Usage

```
ebv_data_read_bb(
   filepath,
   datacubepath,
   bb,
   outputpath = NULL,
   timestep = 1,
   epsg = 4326,
   overwrite = FALSE,
   ignore.RAM = FALSE,
   verbose = FALSE
```

Arguments

filepath Character. Path to the NetCDF file.

datacubepath Character. Path to the datacube (use ebv_datacubepaths()).

bb Integer Vector. Definition of subsset by bounding box: c(xmin, xmax, ymin, ymax).

8 ebv_data_read_shp

outputpath	Character. Default: NULL, returns the data as a raster object in memory. Optional: set path to write subset as GeoTiff on disk.
timestep	Integer. Choose one or several timesteps.
epsg	Integer. Default: 4326 (WGS84). Change accordingly if your bounding box coordinates are based on a different coordinate reference system.
overwrite	Logical. Default: FALSE. Set to TRUE to overwrite the outputfile defined by 'outputpath'.
ignore.RAM	Logical. Default: FALSE. Checks if there is enough space in your memory to read the data. Can be switched off (set to TRUE).
verbose	Logical. Default: FALSE. Turn on all warnings by setting it to TRUE.

Value

Returns a raster object if no outputpath is given. Otherwise the subset is written onto the disk and the ouputpath is returned.

Note

In case the epsg of the Bounding Box and the NetCDF differ, the data is returned based on the epsg of the NetCDF Dataset.

See Also

```
ebv_data_read_shp() for subsetting via shapefile.
```

Examples

```
file <- system.file(file.path("extdata","cSAR_idiv_v1.nc"), package="ebvnetcdf")
datacubes <- ebv_datacubepaths(file)
out <- file.path(system.file(package='ebvnetcdf'),"extdata","subset_bb.tif")
bb_wgs84 <- c(5,15,47,55)
bb_utm32 <- c(271985, 941837, 5232640, 6101151)
#cSAR.germany <- ebv_data_read_bb(file, datacubes[1], bb_wgs84, timestep = c(1,4,12))
#path <- ebv_data_read_bb(file, datacubes[1], bb_wgs84, out, timestep = c(2,3))
#path <- ebv_data_read_bb(file, datacubes[1], bb_utm32, out, timestep=1, epsg=32632, overwrite=T)</pre>
```

ebv_data_read_shp

Read subset (shapefile) of one datacube of an EBV NetCDF

Description

Read a subset of one or more layers from one datacube of the NetCDF file. Subset definition by a shapefile. This functions writes temporary files on your disk. Specify a directory for these setting via options('temp_directory'='/path/to/temp/directory').

ebv_data_read_shp 9

Usage

```
ebv_data_read_shp(
   filepath,
   datacubepath,
   shp,
   outputpath = NULL,
   timestep = 1,
   at = TRUE,
   overwrite = FALSE,
   ignore.RAM = FALSE,
   verbose = FALSE
)
```

Arguments

filepath

datacubepath Character. Path to the datacube (use ebv_datacubepaths()). Character. Path to the shapefile defining the subset. shp Character. Default: NULL, returns the data as a raster object in memory. Opoutputpath tional: set path to write subset as GeoTiff on disk. timestep Integer. Choose one or several timesteps (vector). Logical. Default: TRUE, all pixels touched by the polygon(s) will be updated. at Set to FALSE to only include pixels that are on the line render path or have center points inside the polygon(s). Logical. Default: FALSE. Set to TRUE to overwrite the outputfile defined by overwrite 'outputpath'.

ignore.RAM Logical. Default: FALSE. Checks if there is enough space in your memory to

Character. Path to the NetCDF file.

read the data. Can be switched off (set to TRUE).

verbose Logical. Default: FALSE. Turn on all warnings by setting it to TRUE.

Value

Returns a raster object if no outputpath is given. Otherwise the subset is written onto the disk and the ouputpath is returned.

See Also

```
ebv_data_read_bb() for subsetting via bounding box.
```

```
#define temp directory
options('temp_directory'=system.file("extdata/", package="ebvnetcdf"))
file <- system.file(file.path("extdata","cSAR_idiv_v1.nc"), package="ebvnetcdf")
datacubes <- ebv_datacubepaths(file)
shp <- system.file(file.path("extdata","subset_germany.shp"), package="ebvnetcdf")
#cSAR.germany <- ebv_data_read_bb(file, datacubes[1], shp)</pre>
```

10 ebv_data_write

ebv_data_write	Write the extracted data on your disk as a GeoTiff
	33

Description

After you extracted data from the EBV NetCDF and worked with it this function gives you the possibility to write it to disk as a GeoTiff. This functions writes temporary files on your disk. Specify a directory for these setting via options ('temp_directory'='/path/to/temp/directory').

Usage

```
ebv_data_write(
  data,
  filepath,
  datacubepath,
  outputpath,
  overwrite = FALSE,
  verbose = FALSE
)
```

Arguments

data	Your data object. May be raster, array, DelayedMatrix or list of DelayedMatrix (see return values of ebv_data_read())
filepath	Character. Path to the NetCDF file you read the data from. Used for the detection of properties as spatial extent and epsg.
datacubepath	Character. Path to the datacube you got the data from. Used for the detection of properties as data type and nodata value.
outputpath	Character. Set the path where you want to write the data to disk as a GeoTiff.
overwrite	Locigal. Default: FALSE. Set to TRUE to overwrite the outputfile defined by 'outputpath'.
verbose	Logical. Default: FALSE. Turn on all warnings by setting it to TRUE.

Value

Returns the outputpath.

Note

Not yet implemented for subsets of the data (only whole spatial coverage of the corresponding EBV NetCDF).

```
#define temp directory
options('temp_directory'=system.file("extdata/", package="ebvnetcdf"))
file <- system.file(file.path("extdata","cSAR_idiv_v1.nc"), package="ebvnetcdf")
datacubes <- ebv_datacubepaths(file)
data <- ebv_data_read(file, datacubes[1,1], 1)
# WORK WITH YOUR DATA
out <- system.file(file.path("extdata","write_data.tif"), package="ebvnetcdf")
#ebv_data_write(data, file, datacubes[1,1], out)</pre>
```

ebv_ncdf_add_data 11

ebv_ncdf_add_data

Add data to a self-created EBV NetCDF

Description

Add data to the self-created EBV NetCDF from GeoTiffs.

Usage

```
ebv_ncdf_add_data(
   filepath_nc,
   filepath_tif,
   datacubepath,
   timestep = 1,
   band = 1,
   ignore.RAM = FALSE,
   verbose = FALSE
)
```

Arguments

filepath_nc	Character. Path to the self-created NetCDF file.
filepath_tif	Character. Path to the GeoTiff file containing the data.
datacubepath	Character. Path to the datacube (use ebv_datacubepaths()).
timestep	Integer. Default: 1. Define to which timestep or timesteps the data should be added. If several timesteps are given they have to be in a continuous order. Meaning $c(4,5,6)$ is right but $c(2,5,6)$ is wrong.
band	Integer. Default: 1. Define which band(s) to read from GeoTiff. Can be several. Don't have to be in order as the timesteps definition requires.
ignore.RAM	Logical. Default: FALSE. Checks if there is enough space in your memory to read the data. Can be switched off (set to TRUE).
verbose	Logical. Default: FALSE. Turn on all warnings by setting it to TRUE.

Value

Adds data to the EBV NetCDF. Check your results using ebv_data_read() and/or ebv_data_analyse().

Note

If the data exceeds your memory the RAM check will throw an error. No block-processing or other method implemented so far. Move to a machine with more capacities for the moment if needed.

```
file <- system.file(file.path("extdata","cSAR_new.nc"), package="ebvnetcdf")
tif <- system.file(file.path("extdata","cSAR_write_ts234.tif"), package="ebvnetcdf")
# datacubes <- ebv_datacubepaths(file)
ts <- c(2:4)
band <- c(1:3)
#ebv_ncdf_add_data(file, tif, datacubepaths[1,1], ts, band)</pre>
```

ebv_ncdf_create

Description

Create the core structure of the EBV NetCDF based on the json from the Geobon Portal API. Data and attributes will be added afterwards. See ebv_ncdf_add_data() and ebv_ncdf_entity_attributes() for the next steps.

Usage

```
ebv_ncdf_create(
   jsonpath,
   outputpath,
   entities.no = 0,
   epsg = 4326,
   extent = c(-180, 180, -90, 90),
   fillvalue = NULL,
   prec = "double",
   overwrite = FALSE,
   verbose = FALSE
)
```

Arguments

jsonpath	Character. Path to the json file downloaded from the Geobon Portal API.
outputpath	Character. Set path where the NetCDF file should be created.
entities.no	Integer. Default: 0. Indicates how many entities there are per metric.
epsg	Integer. Default: 4326 (WGS84). Defines the coordinate reference system via the corresponding epsg code.
extent	Numeric. Default: $c(-180,180,-90,90)$. Defines the extent of the data: $c(xmin, xmax, ymin, ymax)$.
fillvalue	Numeric. Value of the missing data in the array. Not mandatory but should be defined!
prec	Character. Default: 'double'. Precision of the data set. Valid options: 'short' 'integer' 'float' 'double' 'char' 'byte'.
overwrite	Logical. Default: FALSE. Set to TRUE to overwrite the outputfile defined by 'outputpath'.
verbose	Logical. Default: FALSE. Turn on all warnings by setting it to TRUE.

Value

Creates the NetCDF file at the 'outputpath' location.

Note

To check out the results take a look at your NetCDF file with Panoply provided by the NASA.

Examples

```
json <- system.file(file.path("extdata","1.json"), package="ebvnetcdf")
out <- file.path(system.file(package='ebvnetcdf'),"extdata","sCAR_new.nc")
#ebv_ncdf_create(json, out, 3, fillvalue=-3.4E38)</pre>
```

```
ebv_ncdf_entity_attributes
```

Add datacube attributes to an EBV NetCDF

Description

Add standard_name, description and fillvalue to an entitiy/datacube of a self-created EBV NetCDF. First use ebv_ncdf_create() to create a NetCDF afterwards use this function to add attributes.

Usage

```
ebv_ncdf_entity_attributes(
   filepath,
   datacubepath,
   standard_name,
   description,
   fillvalue = NULL,
   verbose = FALSE
)
```

Arguments

filepath	Character. Path to the self-created NetCDF file.
datacubepath	Character. Path to the datacube (use ebv_datacubepaths()).
standard_name	Value of the standard_name attribute.
description	Character. Value of the description attribute.
fillvalue	Numeric. Value of the fillvalue attribute.
verbose	Logical. Default: FALSE. Turn on all warnings by setting it to TRUE.

Value

Adds attributes to NetCDF at datacube level. Check results using ebv_properties()

```
file <- system.file(file.path("extdata","cSAR_new.nc"), package="ebvnetcdf")
# datacubes <- ebv_datacubepaths(file)
sn <- 'non forest birds species'
desc <- 'Changes in bird diversity at the grid cell level caused by land-use'
fv <- -3.4E38
#ebv_ncdf_entity_attributes(file, datacubes[1,1], sn, desc, fv)</pre>
```

```
ebv_ncdf_write_attribute
```

Write a new attribute value to an EBV NetCDF

Description

Write a new attribute value to an EBV NetCDF. Not all attributes can be changed. Some are always created automatically, e.g. the crs, time and var_entity datasets. In this case you have to re-create the NetCDF file.

Usage

```
ebv_ncdf_write_attribute(
    filepath,
    attribute_name,
    value,
    levelpath = NULL,
    verbose = FALSE
)
```

Arguments

filepath Character. Path to the NetCDF file.

attribute_name Character. Name of the attribute that should be changed.

value New value that should be assigned to the attribute.

levelpath Character. Default: NULL. Indicates the location of the attribute. The default

means that the attribute is located at a global level. If the attribute is located at the datacubelevel just add the datacubepath. For the metric level the value may be 'metric00' or 'scenario00/metric00'. This path depends on whether the

NetCDF hierarchy has scenarios or not.

verbose Logical. Default: FALSE. Turn on all warnings by setting it to TRUE.

Value

Adds the new value to the attribute. Check your results using ebv_properties().

```
file <- system.file(file.path("extdata","cSAR_new.nc"), package="ebvnetcdf")
attribute1 <- 'standard_name'
value1 <- 'mammals'
level1 <- 'metric00'
#ebv_ncdf_write_attribute(file, attribute1, value1, level1)
attribute2 <- '_FillValue'
value2 <- -999
level2 <- 'metric00/entity00'
#ebv_ncdf_write_attribute(file, attribute2, value2, level2)
attribute3 <- 'creator'
value3 <- 'Jane Doe'
#ebv_ncdf_write_attribute(file, attribute3, value3)</pre>
```

ebv_plot_indicator 15

ebv_plot_indicator

Plot the average over time of one datacube of an EBV NetCDF

Description

Plot the average (y-axis) of one datacube of a EBV NetCDF over time (x-axis). If the datacube has only one timestep a single mean value is returned.

Usage

```
ebv_plot_indicator(
  filepath,
  datacubepath,
  color = "dodgerblue4",
  verbose = FALSE
)
```

Arguments

filepath Character. Path to the NetCDF file.

datacubepath Character. Path to the datacube (use ebv_datacubepaths()).

color Character. Default: dodgerblue4. Change to any color known by R grDevices::colors()

verbose Logical. Default: FALSE. Turn on all warnings by setting it to TRUE.

Value

Plots a line plot and returns a vector of the average. If the data encompasses only one timestep a single mean is returned.

Examples

```
file <- system.file(file.path("extdata","cSAR_idiv_v1.nc"), package="ebvnetcdf")
datacubes <- ebv_datacubepaths(file)
ebv_plot_indicator(file, datacubes[1,1])</pre>
```

ebv_plot_map

Map plot of an EBV NetCDF

Description

Map plot of the data of one timestep in one datacube of an EBV NetCDF. This functions sometimes writes temporary files on your disk. Speficy a directory for these setting via options('temp_directory'='/path/to/temp/directory'=

16 ebv_properties

Usage

```
ebv_plot_map(
   filepath,
   datacubepath,
   timestep = 1,
   countries = TRUE,
   col.rev = TRUE,
   classes = 5,
   ignore.RAM = FALSE,
   verbose = FALSE
)
```

Arguments

filepath Character. Path to the NetCDF file. datacubepath Character. Path to the datacube (use ebv_datacubepaths()). timestep Integer. Choose one timestep. Logical. Default: TRUE. Simple country outlines will be plotted on top of the countries raster data. Disable by setting this option to FALSE. col.rev Logical. Default: TRUE. Set to FALSE if you want the color ramp to be the other way around. classes Integer. Default: 5. Define the amount of classes (quantiles) for the symbology. Currently restricted to maximum 15 classes. Logical. Default: FALSE. Checks if there is enough space in your memory to ignore.RAM read the data. Can be switched off (set to TRUE).

Logical. Default: FALSE. Turn on all warnings by setting it to TRUE.

Value

Plots a map.

verbose

Note

Uses the country outlines data from the maptools package.

Examples

```
file <- system.file(file.path("extdata","cSAR_idiv_v1.nc"), package="ebvnetcdf")
datacubes <- ebv_datacubepaths(file)
ebv_plot_map(file, datacubes[1,1], timestep=9, classes=7)</pre>
```

ebv_properties Read properties of EBV NetCDF

Description

Structured access to all attributes of the NetCDF file.

wrld_simpl 17

Usage

```
ebv_properties(filepath, datacubepath = NULL, verbose = FALSE)
```

Arguments

filepath Character. Path to the NetCDF file.

datacubepath Character. Optional. Path to the datacube (use ebv_datacubepaths()). verbose Logical. Default: FALSE. Turn on all warnings by setting it to TRUE.

Value

S4 class containing information about file or file and datacube depending on input.

Examples

```
file <- system.file(file.path("extdata","cSAR_idiv_v1.nc"), package="ebvnetcdf")
datacubes <- ebv_datacubepaths(file)
prop_file <- ebv_properties(file)
prop_dc <- ebv_properties(file, datacubes[1,1])</pre>
```

wrld_simpl

Simple outlines of world countries

Description

Simple outlines of world countries

Usage

```
wrld_simpl
```

Format

A Spatial Polygons Data Frame with 246 elements

Source

Data imported from the maptools package: data(wrld_simpl, package='maptools')

Index

```
* datasets
    wrld_simpl, 17
DelayedArray::DelayedArray(), 7
EBV NetCDF properties-class, 2
ebv_data_analyse, 4
ebv_data_analyse(), 11
ebv_data_change_res, 5
ebv_data_read, 6
ebv_data_read(), 10, 11
ebv_data_read_bb, 7
ebv_data_read_bb(), 4, 9
ebv_data_read_shp, 8
ebv_data_read_shp(), 4, 8
ebv_data_write, 10
ebv_datacubepaths, 3
ebv_datacubepaths(), 4-7, 9, 11, 13, 15-17
ebv_ncdf_add_data, 11
ebv_ncdf_add_data(), 12
ebv_ncdf_create, 12
ebv_ncdf_create(), 13
ebv\_ncdf\_entity\_attributes, 13
ebv_ncdf_entity_attributes(), 12
ebv_ncdf_write_attribute, 14
ebv_plot_indicator, 15
ebv_plot_map, 15
ebv_properties, 16
ebv_properties(), 13, 14
ebvnetcdf, 3
grDevices::colors(), 15
wrld_simpl, 17
```