ECCO Modeling Utilities (EMU)

User Guide

Ichiro Fukumori, Ou Wang, and Ian Fenty

DRAFT

November 10, 2022

1. Introduction

This document describes computational tools to analyze the ocean model underlying the ECCO ocean state estimate Version 4 release 4 (V4r4).

The tools include the following (Table 1);

- 1. Sampling Tool
- 2. Perturbation Tool (forward gradient)
- 3. Adjoint Tool (adjoint gradient)
- 4. Convolution Tool (adjoint gradient decomposition)
- 5. Budget Tool
- 6. Tracer Tool (passive tracer and its adjoint)

The tools utilize the flux-forced version of ECCO's Version 4 release 4 (V4r4) ocean model described in Wang et al. [2021], hereafter simply the *model*.

	Tool	Description	
1	Sampling	Extract time-series of <i>user-specified quantity</i> .	
2	Perturbation	Computes model's response to change in <u>user-specified</u> <u>forcing</u> (forward gradient).	
3	Adjoint	Computes sensitivity of <u>user-specified quantity</u> to different forcing (adjoint gradient).	
4	Convolution	Computes convolution of adjoint gradients with corresponding forcing (adjoint gradient decomposition).	
5	Budget	Extract variables and fluxes underlying the budget of	
6	Tracer	Computes evolution of <u>user-defined passive tracer</u> and/or <u>its adjoint</u> .	

Table 1: ECCO Modeling Utilities (EMUs)

2. What the Tools do

2.1. Sampling Tool

The Sampling Tool extracts time-series of a user-defined variable of the model, hereafter the Objective Function (J). The Objective Function can simply be one of the standard state variables v (Table 2) at a particular model grid point or a user-defined linear function (combination, transformation) of these variables (e.g., spatial integral, steric sea level). In its general form, the Objective Function is written as,

$$J(t) = \sum_{i} \alpha_{i} \sum_{\mathbf{x}} \mathbf{T}_{i}(\mathbf{x}) v_{i}(\mathbf{x}, t)$$
(1)

Here, t is time, α is a scalar multiplication factor (scaling), **T** is a linear operator (weight) in space (**x**), and subscript i distinguishes different variables. (The Tool allows the Objective Function to be a combination of any number of variables.)

The Sampling Tool is useful for assessing the fidelity of V4r4; e.g., comparison to observations.

Index	Variable	Unit	Description	temporal mean
1	ssh	m	dynamic sea level	daily & monthly
2	obp	m	ocean bottom pressure (unit in equivalent sea level)	daily & monthly
3	theta	°C	potential temperature	monthly
4	salt	PSU	salinity	monthly
5	uvel	m/s	i-direction velocity	monthly
6	vvel	m/s	j-direction velocity	monthly

Table 2: Standard model state variables (v) available as daily and/or monthly means.

2.2. Perturbation Tool

The Perturbation Tool computes the model's response to changes in forcing (aka control); i.e., forward gradient,

$$\frac{\partial v(\mathbf{x},t)}{\partial \phi(\mathbf{r},s)} \tag{2}$$

Here, the numerator $v(\mathbf{x},t)$ is a standard state variable (Table 2) at location \mathbf{x} and time t.

 $\phi(\mathbf{r}, s)$ in the denominator, chosen by the user, is a particular forcing (Table 3) at a specific location \mathbf{r} and time s. The Perturbation Tool computes this gradient for all standard state variables v (Table 2) at different locations \mathbf{x} and time t of the model.

The gradients are useful for studying the ocean's response to change in forcing and for assessing the accuracy of the model's adjoint gradients (Adjoint Tool, Section 2.3).

Index	Variable Name	Unit	Description
1	empmr	kg/m ² /s	upward freshwater flux
2	pload	N/m ²	downward surface pressure load
3	qnet	W/m^2	net upward heat flux
4	qsw	W/m ²	net upward shortwave radiation
5	saltflux	$g/m^2/s$	net upward salt flux
6	spflx	g/m ² /s	net downward salt plume flux
7	tauu	N/m ²	westward wind stress
8	tauv	N/m ²	southward wind stress

Table 3: Model Forcing (ϕ). Forcing perturbation is defined weekly.

The Perturbation Tool computes the gradient (Eq 2) as differences of the state (ν) between model integrations with and without the forcing perturbation, divided (normalized) by the amplitude of that perturbation. Namely,

$$\frac{v(\mathbf{x},t;\phi') - v(\mathbf{x},t;\phi)}{\delta\phi} \approx \frac{\partial v(\mathbf{x},t)}{\partial \phi(\mathbf{r},s)}$$
(3)

Here on the left-hand-side, the model's forcing used in deriving the state is noted parametrically, i.e., $v(\mathbf{x},t;\phi)$ denotes model state v at location \mathbf{x} and time t using forcing ϕ . ϕ' is identical to ϕ except at location \mathbf{r} and time s where it has been perturbed by $\delta\phi$, viz.,

$$\phi'(\mathbf{r},s) = \phi(\mathbf{r},s) + \delta\phi \tag{4}$$

The user choses $\delta \phi$ among the different controls that are available (Table 3), its magnitude, spatial location (\mathbf{r}), and specific instant (s) defined at 7-day intervals, starting from 12Z January 01, 1992, which is the starting instant of ECCO V4r4. The model time-step is 1-hour and the forcing perturbation is interpolated linearly in time. The Tool integrates the model with the perturbation and evaluates the gradient (Eq 3) as daily and/or monthly means corresponding to the standard model state (Table 2). The second term in the numerator on the left-hand-side of Eq 3 is pre-computed as part of the Tool's installation (Section 4).

2.3. Adjoint Tool

The Adjoint Tool computes the model's sensitivity to different forcing; i.e., adjoint gradient,

$$\frac{\partial J(t_g)}{\partial \phi(\mathbf{r}, s)} \tag{5}$$

Here the numerator $J(t_g)$ is a user-defined scalar quantity of the model, i.e., the Objective Function as described in Section 2.1 (Eq 1), at a particular time t_g . The denominator $\phi(\mathbf{r},s)$ is a forcing (Table 3) at location \mathbf{r} and time s.

Adjoint gradients are useful for studying the sensitivity of the model to different forcing, including identification of forcing responsible for the model's variation (Decomposition Tool, Section 2.4).

The Tool allows J to be chosen as a particular state variable at a specific location \mathbf{x} or, more generally, a user-defined linear function of the state such as a spatial integral as in the Sampling Tool (Eq 1). In time, J for this Tool is based on monthly means; for example, J could be an average of a particular month or an average over a longer period based on monthly means such as a particular year or over the entire period of V4r4. Using the adjoint of the model, the Adjoint Tool computes this gradient for different controls ϕ (Table 3) at different locations \mathbf{r} and time s. As in the Perturbation Tool (Section 2.2), controls (ϕ) are defined weekly, starting from 12Z January 01, 1992, that are interpolated linearly in time.

Adjoint gradients (Eq 5) are closely related to forward gradients (Eq 2). The two tools differ in whether it is the numerator or the denominator that is fixed (with the other one varying). Whereas the Perturbation Tool computes the gradients for a particular denominator, the Adjoint Tool computes the gradients for a particular numerator. Otherwise, the two gradients are mathematically the same for corresponding numerators and denominators. (Numerical differences arise from approximations.)

2.4. Convolution Tool

The Convolution Tool computes the convolution between a set of adjoint gradients and their corresponding forcing.

2.5. Budget Tool

The Budget Tool extracts time-series of a user-defined variable and the fluxes underlying its temporal evolution.

2.6. Tracer Tool

The Tracer Tool computes the temporal evolution of a user-defined passive tracer or its adjoint.

3. How to use the Tools

Before using the Tools, create and change to directory **USRDIR** (name as desired) in which the Tools' computation will take place. The tools are designed to be run one by one.

Simultaneous executions should be run in separate **USRDIR** directories to avoid conflict among the Tools' execution.

pfe25>mkdir USRDIR

pfe25>cd USRDIR

User commands and input are noted in RED. System prompts, file names, directories, and variables are indicated by CYAN. (File names and directories are in **bold**.) pfe25> denotes Unix prompt on NAS Pleiades. Descriptions of the prompts are **highlighted in bold italic**.

3.1. Sampling Tool

a) Set up user interface (files used in step b below).

Replace **FORUSERDIR** below to where the Tool is installed (what was specified in step 15 of "Section 4 Installing the Tools"); On NAS Pleiades the Tool can be found in /nobackup/ifukumor/ECCO_tools/emu.

```
pfe25>source FORUSERDIR/setup_samp.csh
```

```
... Setting up ECCO V4r4 Sampling Tool ... See FORUSERDIR/README_samp
```

b) Extract time-series of the quantity of interest (Objective Function) by running program **samp.x** and responding to its prompts.

The example below extracts monthly-mean time-series of dynamic sea level at a model grid point closest to 148°W 73.1°N, which is model grid point (85, 604).

```
pfe27>samp.x
```

Extracting model time-series ...

```
Define objective function (OBJF) ...

Available VARIABLES are ... List of variables for Objective Function. cf Table 2

1) SSH (m)
2) OBP (equivalent sea level m)
3) THETA (deg C)
4) SALT (PSU)
5) UV (m/s)

Monthly or Daily mean ... (m/d)?
(NOTE: daily mean available for SSH and OBP only.)

m. Choosing monthly mean variables in defining Objective Function.
```

```
fmd = m
  ==> Sampling MONTHLY means ...
                                        Choose variable from 1 to 5 for i=1 in Eq (1).
  Choose OBFJ variable # 1 ... (1-5)?
  (Enter 0 to end variable selection)
          Choosing SSH as variable.
  OBJF variable 1 is SSH
  Choose either VARIABLE at a point (1) or VARIABLE weighted in space (2) ...
(1/2)?
          Choosing 1 causes samp.x to form a sampling operator as weight T in Eq (1),
          i.e., T=1 at the chosen point but zero otherwise. See Section 3.3 for an example
          choosing 2.
  ... OBJF will be a scaled VARIABLE at a point
  i.e., MULT * VARIABLE
Choose horizontal location ...
 Enter 1 to select native grid location (i,j),
   or 9 to select by longitude/latitude ... (1 or 9)?
9
  Enter location's lon/lat (x,y) ...
   longitude ... (E)?
-148
   latitude ... (N)?
73.1
..... Chosen point is (i,j) = 85 604. Lists information of chosen model grid point.
     C-grid is (long E, lat N) = -148.1 73.2
     Depth (m)= 3675.7
 Enter scaling factor MULT ... ?
                                      This is alpha in Eq (1).
1.
  amult = 1.0000E+00
  Choose OBFJ variable # 2 ... (1-5)? Choosing variable for i=2 in Eq (1).
 (Enter 0 to end variable selection)
          Selecting 0 ends definition of Objective Function.
Sampling Tool output will be in : emu_samp_m_1_85_604_1. Output directory.
Sampling MONTHLY means ... Code is computing Eq (1) according to user definition.
```

```
nobjf = 1. Number of terms (i) chosen for Eq (1).

Mask file: objf_1_mask_C. Filename for T in Eq (1) for i=1.

Masks maximum absolute value = 1.0000E+00

at (i,j) = 85 604 Maximum element of T in Eq (1) for i=1.

... Done.
```

c) The Sampling Tool creates output in a directory bearing specification of the extracted variable (Objective Function) in its name, which is emu_samp_m_1_85_604_1 for the case above. Here "emu_samp" indicates output from the Sampling Tool, "m" for monthly mean variable, "1" for SSH, "85_604" for location (i,j)=(85, 604), and the last "1" for number of variables defining the Objective Function (nobjf=1).

The files in this directory for the example above are.

```
pfe24>ls-lemu_samp_m_85_604_1
total 5
-rw-r--r-- 1 ifukumor g26113 335 Nov 3 10:21 data.ecco
-rw-r--r-- 1 ifukumor g26113 465 Nov 3 10:21 samp.info
-rw-r--r-- 1 ifukumor g26113 1252 Nov 3 10:21 samp.out 312
```

The sampled variable is in file **samp.out_312** as an **anomaly time-series from its time-mean in binary format**; The last number after "_" indicates the number of records in the time-series, which in this case is 312 monthly mean values from 1992 to 2017 of V4r4's analysis period. An example FORTRAN code to read this output file is given below.

File **samp.info** is a text file summarizing the user-defined Objective Function and file **data.ecco** is an ECCO MITgcm input file defining the objective function.

FORTRAN

```
integer nrec
parameter (nrec=312)
real*4 anom(nrec), ref
character*256 f_in

f_in = 'samp.out _312'
open(60, file=trim(f_in), action='read', access='stream')
read(60) anom
read(60) ref
close(60)

Anomaly time-series of the Objective Function.
Time-mean reference of the anomaly.
close(60)
```

3.2. Perturbation Tool

a) Set up user interface (files used in steps b & c below).

As in Section 3.1, replace **FORUSERDIR** below to where the Tool is installed (what was specified in step 15 of "Section 4 Installing the Tools"); On NAS Pleiades the Tool can be found in /nobackup/ifukumor/ECCO_tools/emu.

pfe25>source FORUSERDIR/setup_pert.csh

b) Specify the control perturbation by following the prompt to pert.x.

The example below perturbs "tauu" (Table 1) at model grid (87,605) at week 518 with magnitude -0.1 (N/m²). (This is similar to the perturbation used in Figure A3 of Fukumori et al., 2021.) The program pert.x will create a namelist file pert_xx.nml and a text file pert_xx.str used by the PBS job in step c). The namelist file pert_xx.nml is used by the tool to perturb the control and the text file pert_xx.str contains a shorthand text describing the perturbation used to name the directory where the Perturbation Tool computation will take place ("7_87_605_518_-1.00E-01" for the example noting, in the order of, control, grid point, week, and amplitude).

```
pfe25>pert.x
Available control variables to perturb ...
                                              List of controls. cf Table 3
  1) empmr
  2) pload
  3) gnet
  4) gsw
  5) saltflux
  6) spflx
  7) tauu
  8) tauv
 Enter control ... (1-8)?
                                Choosing tauu as perturbed control.
 .... perturbing tauu
Choose location for perturbation ...
  Enter 1 to choose native grid location (i,j).
      9 to select by longitude/latitude ... (1 or 9)?
1
  Enter native (i,j) grid to perturb ...
 i ... (1-90)?
87
 j... (1-1170)?
605
 ..... perturbation at (i,j) =
                                  87
                                           605. Lists the chosen model grid point.
```

```
C-grid is (long E, lat N) = -147.8 72.3
     Depth (m) = 3539.5
Enter week to perturb ... (1-1358)?
                                       Contol perturbation is defined weekly.
518
 ..... perturbing week =
                              518
Default perturbation = -0.1000E+00
     in unit N/m2 (westward wind stress)
Enter 1 to keep, 9 to change ...?'
Perturbation amplitude = -0.1000E+00
     in unit N/m2 (westward wind stress)
V4r4 integrates 312-months from 1/1/1992 12Z to 12/31/2017 12Z
which requires 10-hours wallclock time.
                                          Rough measure of required wallclock time.
Enter how many months to integrate here ... (1-312)?
                  Enter number of months to integrate starting from 1/1/1992.
Will integrate model over 312 months.
```

... Program has set computation periods in files data and pbs_pert.csh accordingly. *The Tool dynamically sets the period of integration.*

Wrote pert_xx.nml
Wrote pert_xx.str

c) Submit a batch job to compute the model's response to b).

```
pfe25>qsub pbs pert.csh
```

The batch job will create a **job directory** ("emu_pert_7_87_605_518_-1.00E-01", for the example above, named using the string in pert_xx.str) in which the computation will take place under **USRDIR** (cf Section 3). Two subdirectories will be created under this **job directory**; Subdirectory temp will have output of the model (first term in the numerator on the left-hand-side of Eq 1) and subdirectory pert_result will have the gradients of the Perturbation Tool (Eq 1).

Progress of this computation can be monitored by the number of daily mean standard model state output files (one file per day) written in **temp/diags**; e.g.,

```
pfe27>ls emu pert 7 87 605 518 -1.00E-01/temp/diags/*2d*day*data | wc -l
```

d) Analyze the results.

The final results of the Perturbation Tool can be found in subdirectory

pert_result under the Tool's job directory (cf step c) and will have the following files;

pert xx.nml:

Namelist file with specifics of the perturbation saved for reference. Created by **pert.x** and used by **pert_xx.x** to perturb the model's control.

```
state_2d_set1_day.***TIMESTEP***.data state_2d_set1_day.***TIMESTEP***.meta state_2d_set1_mon.***TIMESTEP***.data state_2d_set1_mon.***TIMESTEP***.meta state_3d_set1_mon.***TIMESTEP***.data state_3d_set1_mon.***TIMESTEP***.data
```

Forward gradient in MITgcm diagnostic output format; "data" are binary, "meta" are text files with "data" file information. The ***TIMESTEP*** in the filenames are model timesteps (center step of average); each file corresponds to a particular instant. The fields are on the model's native grid.

Files "state_2d_set1_day" have gradients of daily mean dynamic sea level (ssh) and ocean bottom pressure (obp) on the model's 2-dimensional horizontal grid. Files "state_2d_set1_mon" have monthly means of these same variables. Units are meters for both variables (equivalent sea level for obp) per unit perturbation of the chosen control.

Files "state_3d_set1_mon" have gradients of monthly mean temperature (theta; deg C), salinity (salt; PSU), i-direction velocity (uvel; m/s), and j-direction velocity (vvel; m/s) on the model's 3-dimensional grid per unit perturbation of the chosen control. (NOTE: Although controls tauu and tauv are westward and southward on the native grid, uvel and vvel are in the model's i- and j-directions.)

```
Units and direction of the different controls are (as noted by pert.x prompts), control (1) = 'empmr' 'kg/m2/s (upward freshwater flux)'
```

```
control (1) = 'chiphin' kg/hi2/s (upward ficshward flux)'
control (2) = 'pload' 'N/m2 (downward surface pressure loading)'
control (3) = 'qnet' 'W/m2 (net upward heat flux)'
control (4) = 'qsw' 'W/m2 (net upward shortwave radiation)'
control (5) = 'saltflux' 'g/m2/s (net upward salt flux)'
control (6) = 'spflx' 'g/m2/s (net downward salt plume flux)'
control (7) = 'tauu' 'N/m2 (westward wind stress)'
control (8) = 'tauv' 'N/m2 (southward wind stress)'
```

Example code to read temperature, theta (the first record; irec), from file **state 3d set1 mon.0000012396.data** as variable "fvar".

FORTRAN

```
integer nx, ny, nr
   parameter (nx=90, ny=1170, nr=50)
   integer irec
   real*4 fvar(nx,ny,nr)
   character*256 f in
   f in = 'state 3d set1 mon.0000012396.data'
   open(60, file=f in, access='direct',
       recl=nx*ny*nr*4, form='unformatted')
   irec = 1
   read(60,rec=irec) fvar
IDL
  nx = 90
  ny = 1170
   nr = 50
   f in = 'state 3d set1 mon.0000012396.data'
   close,1 & openr,1,f in,/swap if little endian
   d file = assoc(1,fltarr(nx,ny,nr))
   irec = 0
   fvar = d file(irec)
MATLAB
   nx = 90;
   ny = 1170;
   nr = 50;
   f in = 'state 3d set1 mon.0000012396.data';
   fid=fopen(f in,'r','ieee-be');
   irec = 1;
   status=fseek(fid,(irec-1)*(nx*ny*nr*4),'bof');
   fvar=fread(fid, [nx*ny*nr], 'single');
   fvar=reshape(fvar, [nx,ny,nr]);
   fclose(fid);
PYTHON
   import numpy as np
   nx = 90
   ny = 1170
```

```
nr = 50

f_in = 'state_3d_set1_mon.0000012396.data'
dt = np.dtype([ ('fld', '>f4', (nr,ny,nx))])
d_file = np.fromfile(f_in,dtype=dt)

irec = 0
fvar = d_file['fld'][irec]
```

3.3. Adjoint Tool

a) Set up user interface (files used in steps b-d below).

As in Section 3.1, replace **FORUSERDIR** below to where the Tool is installed (what was specified in step 15 of "Section 4 Installing the Tools"); On NAS Pleiades the Tools can be found in /nobackup/ifukumor/ECCO_tools/emu.

pfe25>source FORUSERDIR/setup_adj.csh

b) Specify Objective Function (OBJF) by following the prompt to adj.x.

The example below sets OBJF to be monthly-mean sea level of December 1993 averaged over the Beaufort Sea. (This is similar to that used in Figure A3 of Fukumori et al., 2021.)

```
pfe25>adj.x
```

Define objective function (OBJF) ...

First define OBJF time-period ... *The Tool uses monthly means to define OBJF*.

V4r4 can integrate from 1/1/1992 12Z to 12/31/2017 12Z which is 26-years (312-months).

Select FIRST and LAST month of OBJF averaging period.

Here, mean of month 24 is chosen as OBJF.

Enter FIRST month of OBJF period ... (1-312)?

24

Enter LAST month of OBJF period ... (1-312)?

24

PERIOD start & end months = 24 24.

... Program has set computation periods in files data and pbs adj.csh accordingly.

```
... Estimated wallclock hours is
                                    The Tool dynamically sets the period of integration
                                   from 01 January 1992 to the end of OBJF and
                                   adjusts the wallclock resource request accordingly.
                                    Gradients are computed for controls during this
                                   period.
Next define OBJF variable(s) ...
                                  This is similar to the Sampling Tool (Section 3.1).
 Available VARIABLES are ...
  1) SSH (m)
  2) OBP (equivalent sea level m)
  3) THETA (deg C)
  4) SALT (PSU)
  5) UV (m/s)
 Choose OBFJ variable # 1 ... (1-5)?
 (Enter 0 to end variable selection)
1
 OBJF variable 1 is SSH
 Choose either VARIABLE at a point (1) or VARIABLE weighted in space (2) ...
(1/2)?
          Choosing 2 causes T in Eq (1) to be read from a user-specified file.
  ... OBJF will be a linear function of selected variable
  i.e., MULT * SUM( MASK * VARIABLE )
  !!!!! MASK must be uploaded (binary native format) before proceeding ...
  Enter MASK filename ... ?
f21 a 1 a.beaufort
                       Example name of a mask file (T n Eq 1)
 fmask = f21 a 1 a.beaufort
 Mask file: f21 a 1 a.beaufort.
 Masks maximum absolute value = 2.2296E-03
     at (i,j) = 86 597
                                     Lists maximum value of mask for reference.
 Enter scaling factor MULT ... ?
                                     This is alpha in Eq (1).
1.
 amult = 1.0000E+00
 Choose OBFJ variable # 2 ... (1-5)?
                                            Choosing variable for i=2 in Eq (1).
 (Enter 0 to end variable selection)
```

O Selecting 0 ends definition of Objective Function.

Adjoint Tool output will be in : emu_adj_24_24_1_f21_a_1_a.beaufort_1 *Output directory.*

Wrote adj.str

c) Submit a batch job to compute the adjoint gradients for OBJF specified in b). (NOTE: This computation can be lengthy; see wallclock in job script.)

pfe25>qsub pbs_adj.csh

The batch job will create a *job directory* in which the computation will take place under **USRDIR** (cf Section 3). The *job directory* bears the description of the computation in its name (the character string in adj in step b), which is "emu_adj_24_24_1_f21_a_1_a.beaufort_1" for the example above. Here "emu_adj" indicates output from the Adjoint Tool, "24_24" for the first and last months of the Objective Function's averaging period, "f21_a_1_a.beaufort" for the file name of the spatial mask used, and "1" for the number of variables defining the Objective Function (nobjf=1).

Two subdirectories will be created under the *job directory*; Subdirectory temp will have output of the model and its adjoint and subdirectory adj_result will have the main output of the Adjoint Tool including the adjoint gradients (Eq 5).

Progress of this computation can be monitored by variable "ad_time_tsnumber" printed in PBS job output file **STDOUT.0000**. This variable is the time-step counter of the adjoint. The time-step size is 1-hour and *counts down backward* from the ending of OBJF's definition to zero at the beginning of 01 January 1992, V4r4's initial condition. The variable is printed out every 10-days; e.g.,

```
pfe27>cd emu_adj_24_24_1_f21_a_1_a.beaufort_1
pfe27>grep ad_time_tsnumber temp/STDOUT.0000 | tail -n 3

(PID.TID 0000.0001) %MON ad_time_tsnumber = 720

(PID.TID 0000.0001) %MON ad_time_tsnumber = 480

(PID.TID 0000.0001) %MON ad_time_tsnumber = 240
```

d) Analyze the results.

The final results of the Adjoint Tool can be found in subdirectory adj_result under the Tool's *job directory* (cf step c) and will have the following files;

adj.info:

A text file summarizing the objective function created by adj.x.

```
adxx CTRL 000000129.data
```

```
adxx_***CTRL***_000000129.meta
```

Adjoint gradient in MITgcm output format; "data" are binary, "meta" are text files with "data" file information. ***CTRL*** is the name of the model's different forcing (Table 3). (0000000129 is the "iteration" number of the particular ECCO estimate.)

Example code to read the adjoint gradient with respect to tauu at 10-weeks lag from the end of OBJF averaging period.

FORTRAN

```
integer nx, ny
parameter (nx=90, ny=1170)
integer irec, f_size, nrec, nlag
real*4 fvar(nx,ny)
character*256 f_in

f_in = 'adxx_tauu.0000000129.data'
inquire(file=f_in, size=f_size)
nrec = f_size / (nx*ny*4)

Number of records in file.

open(60, file=f_in, access='direct',
$ recl=nx*ny*4, form='unformatted')

nlag = 10
irec = nrec - nlag

Record number for 10 week lag.

read(60,rec=irec) fvar
```

4. Installing the Tools

This section describes steps to install the tool on NAS Pleiades, which should be similar for other computing systems.

User commands/input are given in RED. (Steps 1-4 in italic are the same as those for setting up the bulk-formula version of the model described in Wang et al. [2020].) System prompts, file names, and variables are in CYAN. (File names and directories are in **bold**.) pfe25> denotes Unix prompt.

1) Create and cd to a work directory

```
pfe25>mkdir WORKDIR
pfe25>cd WORKDIR
```

2) Download MITgcm "checkpoint 66g" pfe25>git clone https://github.com/MITgcm/MITgcm.git -b checkpoint66g

3) Create and cd to subdirectory

```
pfe25>cd MITgcm

pfe25>mkdir -p ECCOV4/release4

pfe25>cd ECCOV4/release4
```

4) Download V4 configurations

pfe25>git clone https://github.com/ECCO-GROUP/ECCO-v4-Configurations

5) Extract flux-forced configuration of the model

```
pfe25>mv ECCO-v4-Configurations/ECCOv4\ Release\ 4/flux-forced .

pfe25>rm -rf ECCO-v4-Configurations

pfe25>cd flux-forced

pfe25>set basedir=`pwd`

pfe25>mkdir forcing
```

6) Download forcing from ECCO Drive. (Substitute username "fukumori" below with your own username and use your WebDAV password, <u>NOT</u> your Earthdata account password.) The second wget will take a while to complete.

```
pfe25>wget -P forcing -r --no-parent --user fukumori --ask-password -nH --cut-dirs=4 https://ecco.jpl.nasa.gov/drive/files/Version4/Release4/input_init
```

pfe25>wget -P forcing -r --no-parent --user *fukumori* --ask-password -nH --cut-dirs=4 https://ecco.jpl.nasa.gov/drive/files/Version4/Release4/other/flux-forced

7) Load module for compilation.

```
pfe25>module purge
pfe25>module load comp-intel/2020.4.304
pfe25>module load mpi-hpe/mpt.2.25
```

```
pfe25>module load hdf4/4.2.12
   pfe25>module load hdf5/1.8.18 mpt
   pfe25>module load netcdf/4.4.1.1 mpt
   pfe25>module list
8) Compile MITgcm program (generates executable "mitgcmuv")
   pfe25>mkdir build
   pfe25>cd build
   pfe25>../../../tools/genmake2 -mods=../code
   -optfile=../../../tools/build options/linux amd64 ifort+mpi ice nas -mpi
   pfe25>make depend
   pfe25>make all
   pfe25>cd ..
9) Derive adjoint of MITgcm by TAF and compile (generates executable "mitgcmuv_ad"). This
   step requires a license for TAF. Skip if Adjoint Tool will not be used.
   pfe25>mkdir build ad
   pfe25>cd build ad
   pfe25> ../../../tools/genmake2 -mods=../code -
   optfile=../code/linux amd64 ifort+mpi ice nas -mpi
   pfe25>make depend
   pfe25>make adtaf
   pfe25>make adall
   pfe25>cd ..
```

10) Download scripts and programs for the Tools and compile.

```
pfe25>git clone https://github.com/ECCO-GROUP/ECCO-EIS.git
   pfe25>mv ECCO-EIS/emu.
   pfe25>rm -rf ECCO-EIS
   pfe25>cd emu
   pfe25>make all
11) Download data files needed by the Tool (pert xx.scale). Substitute username "fukumori"
   below with your own username and use your WebDAV password, NOT your Earthdata
   account password.
   pfe25>wget -r --no-parent --user fukumori --ask-password -nH --cut-dirs=7
   https://ecco.jpl.nasa.gov/drive/files/Version4/Release4/other/flux-
   forced/tool pert data
12) Copy files that will be modified, just in case. (optional)
   pfe25>cp -p setup_samp.csh setup_samp.csh_orig
   pfe25>cp -p README samp README samp orig
   pfe25>cp -p pbs pert ref.csh pbs pert ref.csh orig
   pfe25>cp -p pbs pert.csh pbs pert.csh orig
   pfe25>cp -p setup_pert.csh setup_pert.csh_orig
   pfe25>cp -p README_pert README_pert_orig
   pfe25>cp -p setup adj.csh setup adj.csh orig
   pfe25>cp -p README adj README adj orig
   pfe25>cp -p pbs adj.csh pbs adj.csh orig
   pfe25>mkdir orig
   pfe25>mv *_orig orig
```

13) *Modify* scripts. (Specify directory where the tool files are set up. cf step 5)

```
pfe25>sed -i -e "s|SETUPDIR|${basedir}|g" *.csh
```

14) Run Perturbation Tool without perturbation to obtain reference results.

This job will produce results under a new directory named **emu_pert_ref** in **basedir** (step 5).

```
pfe25>qsub pbs_pert_ref.csh
```

15) Copy tools (**setup_*.csh**, **README_***) for user access. Replace **FORUSERDIR** below to a full directory path name where you want to install (copy) the tools at.

```
pfe25>set useraccessdir=FORUSERDIR

pfe25>if (! -d ${useraccessdir}) mkdir ${useraccessdir}

pfe25>sed -i -e "s|PUBLICDIR|${useraccessdir}|g" setup_*.csh

pfe25>sed -i -e "s|PUBLICDIR|${useraccessdir}|g" README_*

pfe25>cp -p ${basedir}/tool_pert/setup_*.csh ${useraccessdir}}

pfe25>cp -p ${basedir}/tool_pert/README * ${useraccessdir}}
```

References