
Problem 1. Expression

Go to Piazza Resources to download the attached files.

Background

In this problem, we deal with trees that represent arithmetic expressions. We first consider only the expressions consisting of numbers (constants), the unary + and - operators, and the binary +, -, * and / operators. Such expressions can be represented by a tree structure, which is named **expression trees** or **abstract syntax trees (AST)**. For example, the tree representing (2 + 5) * 3 / (-6) is


$$(2 + 5) * 3 / (-6)$$



Such a tree is quite useful, as it contains the structure of all subexpressions. We may perform some operations on the tree recursively, such as printing, evaluation, conversion to some special forms, etc. Now your task is to build a class hierarchy representing these different kinds of nodes. Parsing an expression into an AST is beyond the scope of CS100.

The basic structure

We start from the following basic structure.



Note: some functions should be declared virtual or pure virtual (your task).

```
class ExprNode {
public:
 // FIXME: Some of the functions below should be virtual or pure virtual.
  ExprNode() = default;
 double evaluate() const;
  std::string toString() const;
  ~ExprNode() = default;
};
class Constant : public ExprNode {
  double mValue;
public:
  explicit Constant(double value) : mValue{value} {}
  // TODO: evaluate() and toString() ...
};
enum class UnaryOpKind {
 UOK_Plus, UOK_Minus
};
class UnaryOperator : public ExprNode {
  UnaryOpKind mOpKind;
  std::shared_ptr<ExprNode> mOperand;
public:
  UnaryOperator(UnaryOpKind op, std::shared_ptr<ExprNode> operand)
      : mOpKind{op}, mOperand{std::move(operand)} {}
  // TODO: evaluate() and toString() ...
};
enum class BinaryOpKind {
  BOK_Plus, BOK_Minus, BOK_Mul, BOK_Div
};
```

It seems to be a nice hierarchy, but how does the user create a node? The user has to write

which involves creating the shared_ptr s manually. This is too ugly and inconvenient.

A level of indirection

Here goes the so-called "Fundamental Theorem of Software Engineering":

We can solve any problem by introducing an extra level of indirection.

Our problem is that the user still has to do memory management (even though smart pointers are used). Ideally, memory management should be part of our implementation details. The user should only care about the structure of the tree. For example, we expect the user to be able to create a node in the following way

```
Expr bo('+', Expr(3), Expr(4));
```

or even more conveniently like

```
auto bo = Expr(3) + Expr(4);
```

Clearly, the latter one can be supported with a simple overloaded operator as long as the former one is supported.

Let's consider defining the <code>Expr</code> class, which works as the level of indirection between the user and the specific node classes. The class <code>Expr</code> should encapsulate a <code>std::shared_ptr<ExprNode></code> and hide everything related to memory management from the user. Moreover, <code>Expr</code> should also provide the interfaces like <code>evaluate()</code> and <code>toString()</code>.

```
class Expr {
  std::shared_ptr<ExprNode> mNode;
```

```
Expr(std::shared_ptr<ExprNode> ptr) : mNode{std::move(ptr)} {}

public:
    // To enable the usage like `Expr(3)`.
    // This constructor is not marked `explicit`.

Expr(double value) : mNode{std::make_shared<Constant>(value)} {}

auto toString() const { return mNode->toString(); }

auto evaluate() const { return mNode->evaluate(); }

// TODO: Some friend declarations might be necessary ...
};
```

Since Expr is a wrapper of a std::shared_ptr<ExprNode>, it should have a constructor that initializes that shared_ptr member. We make this constructor private because we don't want the user to call it directly.

Now let's think about what Expr actually does. It contains a smart pointer to some node class, and behaves very much like a node class because it has the interfaces tostring() and evaluate(). Such a class that represents an object of any node type perfectly and does memory management internally is called a *surrogate* (代理) or a *handle* (句柄).

With this handle class defined, wherever a std::shared_ptr<ExprNode> is needed, a Expr can always work. The other node classes can simply replace every std::shared_ptr<ExprNode> with Expr and completely forget about how memory is managed:

```
class UnaryOperator : public ExprNode {
   UnaryOpKind mOpKind;
   Expr mOperand;

public:
   UnaryOperator(UnaryOpKind op, Expr operand)
      : mOpKind{op}, mOperand{std::move(operand)} {}

// TODO: evaluate and toString ...
};
```

The user may create a UnaryOperator node through the following overloaded operators:

```
Expr operator-(const Expr &arg) {
  return {std::make_shared<UnaryOperator>(UnaryOpKind::UOK_Minus, arg)};
}
Expr operator+(const Expr &arg) {
  return {std::make_shared<UnaryOperator>(UnaryOpKind::UOK_Plus, arg)};
}
```

(What is return {...}? See <u>Appendix: Returning a braced-init-list.</u>)

For example,

```
auto neg3 = -Expr(3);
```

More functionalities

With basic knowledge on our class hierarchy obtained, you are going to add support for more functionalities:

- A new kind of node called Variable, which represents the varaible x. With this supported, our AST can be used to represent unary functions, instead of only arithmetic expressions with constants.
- Evaluation of the function at a certain point $x = x_0$.
- Evaluation of the derivative of the function at a certain point $x=x_0$.

The operations that need to be supported are declared in this base class:

In the previous sections, we used only one class <code>BinaryOperator</code> to represent four different kinds of binary operators. Such design may not be convenient now, because the ways of evaluating the function and its derivative differ to a greater extent between different operators. Therefore, we separate them into four classes:

```
class BinaryOperator : public ExprNode {
protected:
  Expr mLeft;
  Expr mRight;
public:
  BinaryOperator(Expr left, Expr right)
      : mLeft{std::move(left)}, mRight{std::move(right)} {}
};
class PlusOperator : public BinaryOperator {
public:
 using BinaryOperator::BinaryOperator;
  // TODO: evaluate(), derivative() and toString() ...
};
class MinusOperator : public BinaryOperator {
public:
  using BinaryOperator::BinaryOperator;
  // TODO: evaluate(), derivative() and toString() ...
};
class MultiplyOperator : public BinaryOperator {
public:
  using BinaryOperator::BinaryOperator;
```

```
// TODO: evaluate(), derivative() and toString() ...
};

class DivideOperator : public BinaryOperator {
  public:
    using BinaryOperator::BinaryOperator;
    // TODO: evaluate(), derivative() and toString() ...
};
```

(What is using BinaryOperator::BinaryOperator; ? See Appendix: Inheriting constructors.)

To support the variable x, we define a new class Variable:

```
class Variable : public ExprNode {
   // TODO: evaluate(), derivative() and toString() ...
};
```

Then we define a static data member of Expr as follows.

```
class Expr {
   std::shared_ptr<ExprNode> mNode;

   Expr(std::shared_ptr<ExprNode> ptr) : mNode{std::move(ptr)} {}

public:
   // This constructor should be defined after the class `Constant` is defined,
   // because creating an object of type `std::shared_ptr<T>` when `T` is incomplete
   // is not allowed.
   Expr(double value);

   static const Expr x;

   // Other members ...
};


// After the definition of the class `Variable`:
   const Expr Expr::x{std::make_shared<Variable>()};
```

Note that Expr also has a non-explicit constructor that receives a double and creates a Constant node:

```
// After the definition of the class `Constant`:
Expr::Expr(double value) : mNode{std::make_shared<Constant>(value)} {}
```

Appendix: Unused parameters may be of help when defining Constant and Variable.

The final structure is as follows.



With all of these and the overloaded arithmetic operators defined **(your task)**, we can create functions in a very convenient manner:

```
auto &x = Expr::x;
auto f = x * x + 2 * x + 1; // x^2 + 2x + 1
std::cout << f.toString() << std::endl;
std::cout << f.evaluate(3) << std::endl;
std::cout << f.derivative(3) << std::endl;
auto g = f / (-x * x + x - 1); // (x^2 + 2x + 1)/(-x^2 + x - 1)
std::cout << g.evaluate(3) << std::endl;
std::cout << g.evaluate(3) << std::endl;</pre>
```

The output should be

```
(((x) * (x)) + ((2.000000) * (x))) + (1.000000)

16

8

-2.28571

0.489796
```

Requirements for toString()

Note: This is a very simple and naive way to convert an expression to a string, because we don't want to set barriers on this part. You can search for some algorithms to make the expression as simplified as possible, but it may not pass the OJ tests.

Any operand of the unary operators (+, -) or the binary operators (+, -, *, /) should be surrounded by a pair of parentheses. Correct examples:

```
• 2+3: (2.000000) + (3.000000)
```

```
• 2x + 3: ((2.000000) * (x)) + (3.000000)
```

```
• 2 \cdot (-x) + 3: ((2.000000) * (-(x))) + (3.000000)
```

Note: If the floating-point value of a Constant node is negative, it is **not** treated as a unary minus sign applied to its absolute value. For example,

```
Expr e(-2);
std::cout << e.toString() << std::endl;</pre>
```

The output should be -2.000000 instead of -(2.000000).

There should be a space before and after each binary operator, e.g. (expr1) + (expr2) instead of (expr1)+(expr2).

To convert a floating-point number to std::string, just use std::to_string and you will be free of troubles caused by precisions and floating-point errors.

example.cpp contains these simple tests.

Requirements for Expr

From the user's perspective, only <code>Expr</code> and its arithmetic operators are **interfaces**. Anything else in your code is **implementation details**, which user code will not rely on. In other words, you are free to implement these things in any way, as long as the interfaces of <code>Expr</code> meet our requirements.

- Expr is copy-constructible, copy-assignable, move-constructible, move-assignable and destructible. These operations should just perform the corresponding operations on the member <code>mNode</code>, and let the corresponding function of <code>std::shared_ptr</code> handle everything. The move operations should be <code>noexcept</code>.
- Expr is constructible from a double value, and this constructor is non-explicit.
- Let e be of type const Expr and x0 be of type double, then the subtree rooted at e represents a function.
 - \circ e.evaluate(x0) returns the value of this function at $x=x_0$.
 - \circ [e.derivative(x0)] returns the value of the derivative of this function at $x=x_0$.
 - e.toString() returns a std::string representing this function.
- Let e1 and e2 be two objects of type const Expr. The following expressions return an object of type Expr, which creates a new node corresponding to the operators.
 - o -e1
 - 0 +e1
 - 0 e1 + e2
 - 0 e1 e2
 - o e1 * e2
 - o e1 / e2
- Expr::x is an object of type const Expr, which represents the variable x.

Use compile_test.cpp to check whether your code compiles. See <u>Appendix</u>: <u>Note on static assertion</u> <u>failure</u> for how to understand the error messages.

Submission

Submit expr.hpp or its contents to OJ.

Thinking

Why do we use std::shared_ptr instead of std::unique_ptr?

Can you add support for more functionalities, e.g. the elementary functions $\sin(e)$, $\cos(e)$, exponential expressions $e_1^{e_2}$, ...? More variables? Print expressions to ET_EX ?

Appendix

Returning a braced-init-list

In the following code

```
class Expr {
   Expr(std::shared_ptr<ExprNode>);
   friend Expr operator-(const Expr &);
};
Expr operator-(const Expr &arg) {
   return {std::make_shared<UnaryOperator>(UnaryOpKind::UOK_Minus, arg)};
}
```

The return statement is equivalent to

```
return Expr{std::make_shared<UnaryOperator>(UnaryOpKind::UOK_Minus, arg)};
```

but we don't want to repeat the return type in the return statement.

Here we use a braced initializer list {...} to initialize the returned object (of type Expr). Since Expr

- is a non-aggregate class type, and
- does not have a constructor accepting std::initializer_list, and
- has a non-explicit constructor accepting std::shared_ptr<ExprNode>,

whatever written inside the pair of braces are passed to that constructor.

Detailed rules about **list-initialization** can be found <u>here</u>.

Inheriting constructors

Given the following definition for BinaryOperator

```
class BinaryOperator : public ExprNode {
protected:
    Expr mLeft;
    Expr mRight;

public:
    BinaryOperator(Expr left, Expr right)
        : mLeft{std::move(left)}, mRight{std::move(right)} {}
};
```

which has a constructor that accepts two Expr s and initializes mLeft and mRight with them respectively, the derived class PlusOperator can easily obtain a constructor that does the same thing by **inheriting** the constructor using a using declaration.

```
class PlusOperator : public BinaryOperator {
  using BinaryOperator::BinaryOperator;
};
```

Now the user can create a PlusOperator object in the following way (suppose e1 and e2 are of type Expr):

```
PlusOperator po(e1, e2);
```

Note that the access level of the inheriting constructor is always the same as that of the inherited constructor in the base class, no matter where the using declaration is placed.

Same things apply to MinusOperator, MultiplyOperator and DivideOperator.

Note on static assertion failure

compile_test.cpp will test whether the requirements for Expr are satisfied, and will report errors using static_assert. This is also used on OJ.

If any requirement is not satisfied, an error will be reported like this:

The key message in this error is what goes after static assertion failed:

```
Expect { e.evaluate(d) } -> double, with the setting (const Expr e, double d).
```

It says that given e of type const Expr and d of type double, the expression e.evaluate(d) is expected to return double. This error message indicates that either e.evaluate(d) is not supported, or its return type is not double.

Unused parameters

If a named parameter is not used in a function definition

```
void foo(int x) {}
```

the compiler will generate a warning, which becomes an error with -Werror.

If you do want to declare an unused parameter (particularly in a virtual function), the most common way is to simply **omit the name of the parameter**:

```
void foo(int /* unused */) {}
```

Note that we have seen this before: The overloaded postfix increment operator ++ has an unused parameter.

```
class Iterator {
public:
   Iterator & operator++();
   Iterator operator++(int); // the postfix version
};
```

Another noticeable way to suppress warning on unused parameters/variables is to use the
<a href="maybe_unused]] <a href="maybe_unused]

When the program is compiled with -DNDEBUG (i.e. with the macro NDEBUG defined), the assert will be removed, and str and expect will be unused.