Part 1 - Initial setup

Lab File Link: Here

- **1.** Configure the appropriate hostname on each router/switch.
- **2.** Configure the enable secret **jeremysitlab** on each router/switch. Use type 9 hashing if available; otherwise, use type 5.
- **3.** Configure the user account **cisco** with secret **ccna** on each router/switch. Use type 9 hashing if available; otherwise, use type 5.
- **4.** Configure the console line to require login with a local user account. Set a 30-minute inactivity timeout. Enable synchronous logging.

Part 2 - VLANs, Layer-2 Ether Channel

- **1.** In Office A, configure a Layer-2 EtherChannel named **PortChannel1** between DSW-A1 and DSW-A2 using a Cisco-proprietary protocol. Both switches should actively try to form an EtherChannel.
- **2.** In Office B, configure a Layer-2 EtherChannel named **PortChannel1** between DSW-B1 and DSW-B2 using an open standard protocol. Both switches should actively try to form an EtherChannel.
- 3. Configure all links between Access and Distribution switches, including the EtherChannels, as trunk links.
 - **a.** Explicitly disable DTP on all ports.
 - **b.** Set each trunk's native VLAN to VLAN 1000 (unused).
 - c. In Office A, allow VLANs 10, 20, 40, and 99 on all trunks.
 - d. In Office B, allow VLANs 10, 20, 30, and 99 on all trunks.
- **4.** Configure one of each office's Distribution switches as a VTPv2 server. Use domain name **JeremysITLab**.
 - a. Verify that other switches join the domain.
 - b. Configure all Access switches as VTP clients.
- **5.** In Office A, create and name the following VLANs on one of the Distribution switches. Ensure that VTP propagates the changes.
 - a. VLAN 10: PCs
 - **b.** VLAN 20: Phones
 - c. VLAN 40: Wi-Fi
 - d. VLAN 99: Management
- **6.** In Office B, create and name the following VLANs on one of the Distribution switches. Ensure that VTP propagates the changes.
 - a. VLAN 10: PCs
 - **b.** VLAN 20: Phones
 - c. VLAN 30: Servers
 - d. VLAN 99: Management
- 7. Configure each Access switch's access port.
 - a. LWAPs will not use FlexConnect
 - **b.** PCs in VLAN 10. Phones in VLAN 20
 - c. SRV1 in VLAN 30
 - d. Manually configure access mode and explicitly disable DTP

- **8.** Configure ASW-A1's connection to WLC1:
 - a. It must support the Wi-Fi and Management VLANs.
 - b. The Management VLAN should be untagged.
 - c. Disable DTP.
- 9. Administratively disable all unused ports on Access and Distribution switches.

Part 3 - IP Addresses, Layer-3 EtherChannel, HSRP

- 1. Configure the following IP addresses on R1's interfaces and enable them:
 - a. G0/0/0: DHCP client
 - **b.** G0/1/0: DHCP client
 - **c.** G0/0: 10.0.0.33/30
 - **d.** G0/1: 10.0.0.37/30
 - e. Loopback0: 10.0.0.76/32
- 2. Enable IPv4 routing on all Core and Distribution switches.
- **3.** Create a Layer-3 EtherChannel between CSW1 and CSW2 using a Cisco-proprietary protocol. Both switches should actively try to form an EtherChannel. Configure the following IP addresses:
 - a. CSW1 PortChannel1: 10.0.0.41/30
 - **b.** CSW2 PortChannel1: 10.0.0.42/30
- **4.** Configure the following IP addresses on CSW1. Disable all unused interfaces.
 - **a.** G1/0/1: 10.0.0.34/30
 - **b.** G1/1/1: 10.0.0.45/30
 - **c.** G1/1/2: 10.0.0.49/30
 - **d.** G1/1/3: 10.0.0.53/30
 - **e.** G1/1/4: 10.0.0.57/30
 - **f.** Loopback0: 10.0.0.77/32
- **5.** Configure the following IP addresses on CSW2. Disable all unused interfaces.
 - **a.** G1/0/1: 10.0.0.38/30
 - **b.** G1/1/1: 10.0.0.61/30
 - **c.** G1/1/2: 10.0.0.65/30
 - **d.** G1/1/3: 10.0.0.69/30
 - **e.** G1/1/4: 10.0.0.73/30
 - **f.** Loopback0: 10.0.0.78/32
- **6.** Configure the following IP addresses on DSW-A1:
 - **a.** G1/1/1: 10.0.0.46/30
 - **b.** G1/1/2: 10.0.0.62/30
 - c. Loopback0: 10.0.0.79/32

- 7. Configure the following IP addresses on DSW-A2:
 - **a.** G1/1/1: 10.0.0.50/30
 - **b.** G1/1/2: 10.0.0.66/30
 - **c.** Loopback0: 10.0.0.80/32
- **8.** Configure the following IP addresses on DSW-B1:
 - **a.** G1/1/1: 10.0.0.54/30
 - **b.** G1/1/2: 10.0.0.70/30
 - **c.** Loopback0: 10.0.0.81/32
- **9.** Configure the following IP addresses on DSW-B2:
 - **a.** G1/1/1: 10.0.0.58/30
 - **b.** G1/1/2: 10.0.0.74/30
 - **c.** Loopback0: 10.0.0.82/32
- **10.** Manually configure SRV1's IP settings:
 - a. Default Gateway: 10.5.0.1
 - **b.** IPv4 Address: 10.5.0.4
 - c. Subnet Mask: 255.255.255.0
- 11. Configure the following management IP addresses on the Access switches (interface VLAN 99), and configure the appropriate subnet's first usable address as the default gateway.
 - **a.** ASW-A1: 10.0.0.4/28
 - **b.** ASW-A2: 10.0.0.5/28
 - **c.** ASW-A3: 10.0.0.6/28
 - **d.** ASW-B1: 10.0.0.20/28
 - e. ASW-B2: 10.0.0.21/28
 - **f.** ASW-B3: 10.0.0.22/28
- **12.** Configure HSRPv2 group 1 for Office A's Management subnet (VLAN 99). Make DSW-A1 the Active router by increasing its priority to 5 above the default, and enable preemption on DSW-A1.
 - **a.** Subnet: 10.0.0.0/28
 - **b.** VIP: 10.0.0.1
 - **c.** DSW-A1: 10.0.0.2
 - **d.** DSW-A2: 10.0.0.3
- 13. Configure HSRPv2 group 2 for Office A's PCs subnet (VLAN 10). Make DSW-A1 the Active router by increasing its priority to 5 above the default, and enable preemption on DSW-A1.
 - **a.** Subnet: 10.1.0.0/24
 - **b.** VIP: 10.1.0.1
 - **c.** DSW-A1: 10.1.0.2
 - **d.** DSW-A2: 10.1.0.3

14. Configure HSRPv2 group 3 for Office A's Phones subnet (VLAN 20). Make DSW-A2 the Active router by increasing its priority to 5 above the default, and enable preemption on DSW-A2.

a. Subnet: 10.2.0.0/24

b. VIP: 10.2.0.1

c. DSW-A1: 10.2.0.2

d. DSW-A2: 10.2.0.3

15. Configure HSRPv2 group 4 for Office A's Wi-Fi subnet (VLAN 40). Make DSW-A2 the Active router by increasing its priority to 5 above the default, and enable preemption on DSW-A2.

a. Subnet: 10.6.0.0/24

b. VIP: 10.6.0.1

c. DSW-A1: 10.6.0.2

d. DSW-A2: 10.6.0.3

16. Configure HSRPv2 group 1 for Office B's Management subnet (VLAN 99). Make DSW-B1 the Active router by increasing its priority to 5 above the default, and enable preemption on DSW-B1.

a. Subnet: 10.0.0.16/28

b. VIP: 10.0.0.17

c. DSW-B1: 10.0.0.18

d. DSW-B2: 10.0.0.19

17. Configure HSRPv2 group 2 for Office B's PCs subnet (VLAN 10). Make DSW-B1 the Active router by increasing its priority to 5 above the default, and enable preemption on DSW-B1.

a. Subnet: 10.3.0.0/24

b. VIP: 10.3.0.1

c. DSW-B1: 10.3.0.2

d. DSW-B2: 10.3.0.3

18. Configure HSRPv2 group 3 for Office B's Phones subnet (VLAN 20). Make DSW-B2 the Active router by increasing its priority to 5 above the default, and enable preemption on DSW-B2.

a. Subnet: 10.4.0.0/24

b. VIP: 10.4.0.1

c. DSW-B1: 10.4.0.2

d. DSW-B2: 10.4.0.3

19. Configure HSRPv2 group 4 for Office B's Servers subnet (VLAN 30). Make DSW-B2 the Active router by increasing its priority to 5 above the default, and enable preemption on DSW-B2.

a. Subnet: 10.5.0.0/24

b. VIP: 10.5.0.1

c. DSW-B1: 10.5.0.2

d. DSW-B2: 10.5.0.3

Part 4 – Rapid Spanning Tree Protocol

- 1. Configure Rapid PVST+ on all Access and Distribution switches.
 - **a.** Ensure that the Root Bridge for each VLAN aligns with the HSRP Active router by configuring the lowest possible STP priority.
 - **b.** Configure the HSRP Standby Router for each VLAN with an STP priority one increment above the lowest priority.
- **2.** Enable PortFast and BPDU Guard on all ports connected to end hosts (including WLC1). Perform the configurations in interface config mode.

Part 5 – Static and Dynamic Routing

- 1. Configure OSPF on R1 (LAN-facing interfaces) and all Core and Distribution switches (all Layer-3 interfaces).
 - a. Use process ID 1 and Area 0.
 - **b.** Manually configure each device's RID to match the loopback interface IP.
 - c. On switches, use the network command to match the exact IP address of each interface.
 - **d.** On R1, enable OSPF in interface config mode.
 - e. Make sure OSPF is enabled on all loopback interfaces, too. Loopback interfaces should be passive.
 - f. Each Distribution switch's SVIs (except the Management VLAN SVI) should be passive, too.
 - **g.** Configure all physical connections between OSPF neighbors to use a network type that doesn't elect a DR/BDR. NOTE: This doesn't work on the Layer-3 PortChannel interfaces between CSW1/CSW2. Leave them as the default network type.
- 2. Configure one static default route for each of R1's Internet connections. They should be recursive routes.
 - **a.** Make the route via G0/1/0 a floating static route by configuring an AD value 1 greater than the default.
 - **b.** R1 should function as an OSPF ASBR, advertising its default route to other routers in the OSPF domain.

Part 6 – Network Services: DHCP, DNS, NTP, SNMP, Syslog, FTP, SSH, NAT

- **1.** Configure the following DHCP pools on R1 to make it serve as the DHCP server for hosts in Offices A and B. Exclude the first ten usable host addresses of each pool; they must not be leased to DHCP clients.
 - a. Pool: A-Mgmt
 - **i.** Subnet: 10.0.0.0/28
 - ii. Default gateway: 10.0.0.1
 - iii. Domain name: jeremysitlab.com
 - iv. DNS server: 10.5.0.4 (SRV1)
 - v. WLC: 10.0.0.7
 - b. Pool: A-PC
 - **i.** Subnet: 10.1.0.0/24
 - ii. Default gateway: 10.1.0.1
 - iii. Domain name: jeremysitlab.com
 - iv. DNS server: 10.5.0.4 (SRV1)
 - c. Pool: A-Phone
 - **i.** Subnet: 10.2.0.0/24
 - ii. Default gateway: 10.2.0.1
 - iii. Domain name: jeremysitlab.com
 - iv. DNS server: 10.5.0.4 (SRV1)
 - d. Pool: B-Mgmt
 - i. Subnet: 10.0.0.16/28
 - ii. Default gateway: 10.0.0.17
 - iii. Domain name: jeremysitlab.com
 - iv. DNS server: 10.5.0.4 (SRV1)
 - **v.** WLC: 10.0.0.7
 - e. Pool: B-PC
 - **i.** Subnet: 10.3.0.0/24
 - ii. Default gateway: 10.3.0.1
 - iii. Domain name: jeremysitlab.com
 - iv. DNS server: 10.5.0.4 (SRV1)
 - **f.** Pool: B-Phone
 - **i.** Subnet: 10.4.0.0/24
 - ii. Default gateway: 10.4.0.1
 - iii. Domain name: jeremysitlab.com
 - iv. DNS server: 10.5.0.4 (SRV1)

- g. Pool: Wi-Fi
 - i. Subnet: 10.6.0.0/24
 - ii. Default gateway: 10.6.0.1
 - iii. Domain name: jeremysitlab.com iv. DNS server: 10.5.0.4 (SRV1)
- **2.** Configure the Distribution switches to relay wired DHCP clients' broadcast messages to R1's Loopback0 IP address.
- **3.** Configure the following DNS entries on SRV1:
 - **a.** google.com = 172.253.62.100
 - **b.** youtube.com = 152.250.31.93
 - **c.** jeremysitlab.com = 66.235.200.145
 - **d.** www.jeremysitlab.com = jeremysitlab.com
- **4.** Configure all routers and switches to use domain name **jeremysitlab.com** and use SRV1 as their DNS server.
- **5.** Configure NTP on R1:
 - **a.** Make R1 a stratum 5 NTP server.
 - **b.** R1 should learn the time from NTP server 216.239.35.0.
 - **c.** NOTE: NTP takes a LONG time to sync, especially in Packet Tracer. After making the configurations, you can move on don't wait for the devices to sync.
- **6.** All Core, Distribution, and Access switches should use R1's loopback interface as their NTP server.
 - **a.** Clients should authenticate R1 using key number **1** and the password **ccna**.
- **7.** Configure the SNMP community string **SNMPSTRING** on all routers and switches. The string should allow GET messages, but not SET messages.
- **8.** Configure Syslog on all routers and switches:
 - a. Send Syslog messages to SRV1. Messages of all severity levels should be logged.
 - **b.** Enable logging to the buffer. Reserve 8192 bytes of memory for the buffer.
- **9.** Use FTP on R1 to download a new IOS version from SRV1:
 - a. Configure R1's default FTP credentials: username cisco, password cisco.
 - b. Use FTP to copy the file c2900-universalk9-mz.SPA.155-3.M4a.bin from SRV1 to R1's flash drive.
 - c. Reboot R1 using the new IOS file, and then delete the old one from flash.
- 10. Configure SSH for secure remote access on all routers and switches.
 - **a.** Use the largest modulus size for the RSA keys.
 - **b.** Allow SSHv2 connections only.
 - **c.** Create standard ACL 1, only allowing packets sourced from Office A's PCs subnet. Apply the ACL to all VTY lines to restrict SSH access.
 - **d.** Allow only SSH connections to the VTY lines.
 - e. Require users to log in with a local user account when connecting via SSH.
 - **f.** Configure synchronous logging on the VTY lines.
- 11. Configure static NAT on R1 to enable hosts on the Internet to access SRV1 via the IP address 203.0.113.113.
- **12.** Configure pool-based dynamic PAT on R1 to enable hosts in the Office A PCs, Office A Phones, Office B PCs, Office B Phones, and Wi-Fi subnets to access the Internet.
 - **a.** Use standard ACL 2 to define the appropriate inside local address ranges in the following order:
 - i. Office A PCs: 10.1.0.0/24
 ii. Office A Phones: 10.2.0.0/24
 iii. Office B PCs: 10.3.0.0/24
 iv. Office B Phones: 10.4.0.0/24
 - v. Wi-Fi: 10.6.0.0/24
 - **b.** Define a range of inside global addresses called **POOL1**, specifying the range 203.0.113.200 to 203.0.113.207 with a /29 netmask.
 - **c.** Map ACL 2 to POOL1 and enable PAT. Confirm that hosts can access the Internet by pinging jeremysitlab.com.
 - **d.** Verify that Internet link failover works by disabling R1's G0/0/0 interface and pinging again.
 - **i.** You will need to remove and re-configure the OSPF default-information originate command for this to work. In real Cisco routers, you can configure the default-information originate always command that supports failover like this, but the command isn't available in Packet Tracer.
 - ii. Re-enable G0/0/0 (and remove and re-configure default-information originate once again).
- 13. Disable CDP on all devices and enable LLDP instead.
 - **a.** Disable LLDP Tx on each Access switch's access port (F0/1).

Part 7 – Security: ACLs and Layer-2 Security Features

- 1. Configure extended ACL OfficeA_to_OfficeB where appropriate:
 - a. Allow ICMP messages from the Office A PCs subnet to the Office B PCs subnet.
 - **b.** Block all other traffic from the **Office A PCs** subnet to the **Office B PCs** subnet.
 - **c.** Allow all other traffic.
 - **d.** Apply the ACL according to general best practice for extended ACLs.
- 2. Configure Port Security on each Access switch's F0/1 port:
 - a. Allow the minimum necessary number of MAC addresses on each port.
 - i. SRV1 does not use virtualization, so it uses a single MAC address.
 - **b.** Configure a violation mode that blocks invalid traffic without affecting valid traffic. The switches should send notifications when invalid traffic is detected.
 - c. Switches should automatically save the secure MAC addresses they learn to the running-config.
- **3.** Configure DHCP Snooping on all Access switches.
 - a. Enable it for all active VLANs in each LAN.
 - **b.** Trust the appropriate ports.
 - c. Disable insertion of DHCP Option 82.
 - **d.** Set a DHCP rate limit of 15 pps on active untrusted ports.
 - e. Set a higher limit (100 pps) on ASW-A1's connection to WLC1.
- 4. Configure DAI on all Access switches.
 - a. Enable it for all active VLANs in each LAN.
 - **b.** Trust the appropriate ports.
 - c. Enable all optional validation checks.

Part 8 - IPv6

- 1. To prepare for a migration to IPv6, enable IPv6 routing and configure IPv6 addresses on R1, CSW1, and CSW2:
 - **a.** R1 G0/0/0: 2001:db8:a::2/64
 - **b.** R1 G0/1/0: 2001:db8:b::2/64
 - **c.** R1 G0/0 and CSW1 G1/0/1: Use prefix 2001:db8:a1::/64 and EUI-64 to generate an interface ID for each interface.
 - **d.** R1 G0/1 and CSW2 G1/0/1: Use prefix 2001:db8:a2::/64 and EUI-64 to generate an interface ID for each interface.
 - e. CSW1 Po1 and CSW2 Po1: Enable IPv6 without using the 'ipv6 address' command.
- 2. Configure two default static routes on R1:
 - **a.** A recursive route via next hop 2001:db8:a::1.
 - **b.** A fully-specified route via next hop 2001:db8:b::1. Make it a floating route by configuring the AD 1 higher than default.

Part 9 – Wireless

- **1.** Access the GUI of WLC1 (https://10.0.0.7) from one of the PCs.
 - **a.** Username: admin
 - **b.** Password: adminPW12
- 2. Configure a dynamic interface for the Wi-Fi WLAN (10.6.0.0/24)
 - **a.** Name: Wi-Fi **b.** VLAN: 40
 - c. Port number: 1
 - **d.** IP address: .2 of its subnet
 - **e.** Gateway: .1 of its subnet
 - **f.** DHCP server: 10.0.0.76
- **3.** Configure and enable the following WLAN:
 - a. Profile name: Wi-Fi
 - **b.** SSID: Wi-Fi
 - **c.** ID: 1
 - d. Status: Enabled
 - e. Security: WPA2 Policy with AES encryption, PSK of cisco123
- **4.** Verify that both LWAPs have associated with WLC1.
 - **a.** Due to Packet Tracer's limitations, wireless clients won't be able to lease an IP address from the Wi-Fi DHCP pool.

Part 1 - Initial setup Solution

1. Configure the appropriate hostname on each router/switch.

hostname R1

2. Configure the enable secret **jeremysitlab** on each router/switch. Use type 9 hashing if available; otherwise, use type 5

Router and Access Switches

enable secret jeremysitlab

Core and Distribution Switches

enable algorithm-type scrypt secret jeremysitlab

3. Configure the user account **cisco** with secret **ccna** on each router/switch. Use type 9 hashing if available; otherwise, use type 5.

To check if a router or switch supports an algorithm type, run the following command:

username cisco ?

R1 and all Access Switches

username cisco secret ccna

All Core and Distributed Switches

username cisco algorithm-type scrypt secret ccna

4. Configure the console line to require login with a local user account. Set a 30-minute inactivity timeout. Enable synchronous logging.

Type the following command in Router and all Access, Distribution and Core switches

line console 0
 login local
 exec-timeout 30
 logging synchronous

sh run | i enable

Part 2 - VLANs, Layer-2 EtherChannel

1. In Office A, configure a Layer-2 EtherChannel named **PortChannel1** between DSW-A1 and DSW-A2 using a Cisco-proprietary protocol. Both switches should actively try to form an EtherChannel.

```
DSW-A1 and DSW-A2
int range g1/0/4-5
channel-group 1 mode desirable
```

2. In Office B, configure a Layer-2 EtherChannel named **PortChannel1** between DSW-B1 and DSW-B2 using an open standard protocol. Both switches should actively try to form an EtherChannel.

```
DSW-B1 and DSW-B2
int range g1/0/4-5
channel-group 1 mode active
```

- **3.** Configure all links between Access and Distribution switches, including the EtherChannels, as trunk links.
 - **a.** Explicitly disable DTP on all ports.
 - **b.** Set each trunk's native VLAN to VLAN 1000 (unused).
 - c. In Office A, allow VLANs 10, 20, 40, and 99 on all trunks.
 - d. In Office B, allow VLANs 10, 20, 30, and 99 on all trunks.

```
DSW-A1, DSW-A2
int range g1/0/1-3
  switchport mode trunk
  switchport nonegotiate
  switchport trunk native vlan 1000
  switchport trunk allowed vlan 10,20,40,99
int po1
  switchport mode trunk
  switchport nonegotiate
  switchport trunk native vlan 1000
  switchport trunk allowed vlan 10,20,40,99
ASW-A1, ASW-A2, ASW-A3
int range g0/1-2
  switchport mode trunk
  switchport nonegotiate
  switchport trunk native vlan 1000
  switchport trunk allowed vlan 10,20,40,99
DSW-B1, DSW-B2
int range g1/0/1-3
  switchport mode trunk
  switchport nonegotiate
  switchport trunk native vlan 1000
  switchport trunk allowed vlan 10,20,30,99
int po1
  switchport mode trunk
  switchport nonegotiate
  switchport trunk native vlan 1000
  switchport trunk allowed vlan 10,20,30,99
ASW-B1, ASW-B2, ASW-B3
int range g0/1-2
  switchport mode trunk
  switchport nonegotiate
  switchport trunk native vlan 1000
  switchport trunk allowed vlan 10,20,30,99
```

- **4.** Configure one of each office's Distribution switches as a VTPv2 server. Use domain name **JeremysITLab**.
 - a. Verify that other switches join the domain.
 - b. Configure all Access switches as VTP clients.

```
DSW-A1, DSW-B1
vtp version 2
vtp domain JeremysITLab
ASW-A1-B1, ASW-A2-B2, ASW-A3-B3
vtp mode client
sh vtp status
```

- **5.** In Office A, create and name the following VLANs on one of the Distribution switches. Ensure that VTP propagates the changes.
 - a. VLAN 10: PCs
 - b. VLAN 20: Phones
 - c. VLAN 40: Wi-Fi
 - d. VLAN 99: Management

```
DSW-A1(config)#vlan 10
DSW-A1(config-vlan)#name PCs
DSW-A1(config-vlan)#vlan 20
DSW-A1(config-vlan)#name Phones
DSW-A1(config-vlan)#vlan 40
DSW-A1(config-vlan)#name Wi-Fi
DSW-A1(config-vlan)#vlan 99
DSW-A1(config-vlan)#name Management
```

- **6.** In Office B, create and name the following VLANs on one of the Distribution switches. Ensure that VTP propagates the changes.
 - a. VLAN 10: PCs
 - b. VLAN 20: Phones
 - c. VLAN 30: Servers
 - d. VLAN 99: Management

```
DSW-B1(config)#vlan 10
DSW-B1(config-vlan)#name PCs
DSW-B1(config-vlan)#vlan 20
DSW-B1(config-vlan)#name Phones
DSW-B1(config-vlan)#vlan 30
DSW-B1(config-vlan)#name Servers
DSW-B1(config-vlan)#vlan 99
DSW-B1(config-vlan)#name Management
```

- 7. Configure each Access switch's access port.
 - a. LWAPs will not use FlexConnect
 - **b.** PCs in VLAN 10, Phones in VLAN 20
 - c. SRV1 in VLAN 30
 - d. Manually configure access mode and explicitly disable DTP

```
ASW-A1(config)#int f0/1
ASW-A1(config-if)#sw mode access
ASW-A1(config-if)#sw nonegotiate
ASW-A1(config-if)#sw access vlan 99
ASW-B1(config)#int f0/1
ASW-B1(config-if)#sw mode access
ASW-B1(config-if)#sw nonegotiate
ASW-B1(config-if)#sw access vlan 99
ASW-A2, ASW-A3, ASW-B2
int f0/1
  sw mode access
  sw nonegotiate
  sw access vlan 10
  sw voice vlan 20
ASW-B3(config)#int f0/1
ASW-B3(config-if)#sw mode access
ASW-B3(config-if)#sw nonegotiate
ASW-B3(config-if)#sw access vlan 30
```

- **8.** Configure ASW-A1's connection to WLC1:
 - a. It must support the Wi-Fi and Management VLANs.
 - **b.** The Management VLAN should be untagged.
 - c. Disable DTP.

```
int f0/2
  sw mode trunk
  sw nonegotiate
  sw trunk allowed vlan 40,99
  sw trunk native vlan 99
```

9. Administratively disable all unused ports on Access and Distribution switches.

```
ASW-A1(config-if)#int range f0/3-24
ASW-A1(config-if-range)#shut
```

Part 3 - IP Addresses, Layer-3 EtherChannel, HSRP

1. Configure the following IP addresses on R1's interfaces and enable them:

a. G0/0/0: DHCP client
b. G0/1/0: DHCP client
c. G0/0: 10.0.0.33/30
d. G0/1: 10.0.0.37/30

e. Loopback0: 10.0.0.76/32

```
int range g0/0/0,g0/1/0
  ip address dhcp
  no shut
int g0/0
  ip address 10.0.0.33 255.255.252
  no shut
int g0/1
  ip address 10.0.0.37 255.255.252
  no shut
int loopback0
  ip address 10.0.0.76 255.255.255
  no shut
```

2. Enable IPv4 routing on all Core and Distribution switches.

ip routing

3. Create a Layer-3 EtherChannel between CSW1 and CSW2 using a Cisco-proprietary protocol. Both switches should actively try to form an EtherChannel. Configure the following IP addresses:

a. CSW1 PortChannel1: 10.0.0.41/30b. CSW2 PortChannel1: 10.0.0.42/30

```
int range g1/0/2-3
no switchport
channel-group 1 mode desirable
int po1
ip address 10.0.0.41 255.255.252
no shut
CSW2
int range g1/0/2-3
no switchport
channel-group 1 mode desirable
int po1
ip address 10.0.0.42 255.255.252
no shut
```

4. Configure the following IP addresses on CSW1. Disable all unused interfaces.

```
a. G1/0/1: 10.0.0.34/30
b. G1/1/1: 10.0.0.45/30
c. G1/1/2: 10.0.0.49/30
d. G1/1/3: 10.0.0.53/30
e. G1/1/4: 10.0.0.57/30
f. Loopback0: 10.0.0.77/32
```

```
int g1/0/1
  no switchport
  ip address 10.0.0.34 255.255.255.252
  no shut
int g1/1/1
  no switchport
  ip address 10.0.0.45 255.255.255.252
  no shut
int g1/1/2
  no switchport
  ip address 10.0.0.49 255.255.255.252
  no shut
int g1/1/3
  no switchport
  ip address 10.0.0.53 255.255.255.252
  no shut
int g1/1/4
  no switchport
  ip address 10.0.0.57 255.255.255.252
  no shut
int loopback0
  ip address 10.0.0.77 255.255.255.255
  no shut
int range g1/0/4-24
  shut
```

5. Configure the following IP addresses on CSW2. Disable all unused interfaces.

```
a. G1/0/1: 10.0.0.38/30
b. G1/1/1: 10.0.0.61/30
c. G1/1/2: 10.0.0.65/30
d. G1/1/3: 10.0.0.69/30
e. G1/1/4: 10.0.0.73/30
f. Loopback0: 10.0.0.78/32
```

```
int g1/0/1
  no switchport
  ip address 10.0.0.38 255.255.252
  no shut
int g1/1/1
  no switchport
  ip address 10.0.0.61 255.255.252
  no shut
int g1/1/2
```

```
no switchport
  ip address 10.0.0.65 255.255.252
  no shut
int g1/1/3
  no switchport
  ip address 10.0.0.69 255.255.255.252
  no shut
int g1/1/4
  no switchport
  ip address 10.0.0.73 255.255.255.252
  no shut
int loopback0
 ip address 10.0.0.78 255.255.255.255
  no shut
int range g1/0/4-24
  shut
```

6. Configure the following IP addresses on DSW-A1:

a. G1/1/1: 10.0.0.46/30

b. G1/1/2: 10.0.0.62/30

c. Loopback0: 10.0.0.79/32

```
int g1/1/1
  no switchport
  ip address 10.0.0.46 255.255.252
  no shut
int g1/1/2
  no switchport
  ip address 10.0.0.62 255.255.252
  no shut
int loopback0
  ip address 10.0.0.79 255.255.255
  no shut
```

7. Configure the following IP addresses on DSW-A2:

a. G1/1/1: 10.0.0.50/30 **b.** G1/1/2: 10.0.0.66/30

c. Loopback0: 10.0.0.80/32

```
int g1/1/1
  no switchport
  ip address 10.0.0.50 255.255.252
  no shut
int g1/1/2
  no switchport
  ip address 10.0.0.66 255.255.252
  no shut
int loopback0
  ip address 10.0.0.80 255.255.255
  no shut
```

8. Configure the following IP addresses on DSW-B1:

a. G1/1/1: 10.0.0.54/30 **b.** G1/1/2: 10.0.0.70/30

c. Loopback0: 10.0.0.81/32

```
int g1/1/1
  no switchport
  ip address 10.0.0.54 255.255.252
  no shut
int g1/1/2
  no switchport
  ip address 10.0.0.70 255.255.252
  no shut
int loopback0
  ip address 10.0.0.81 255.255.255
  no shut
```

9. Configure the following IP addresses on DSW-B2:

a. G1/1/1: 10.0.0.58/30

b. G1/1/2: 10.0.0.74/30

c. Loopback0: 10.0.0.82/32

```
int g1/1/1
  no switchport
  ip address 10.0.0.58 255.255.252
  no shut
int g1/1/2
  no switchport
  ip address 10.0.0.74 255.255.252
  no shut
int loopback0
  ip address 10.0.0.82 255.255.255
  no shut
```

10. Manually configure SRV1's IP settings:

a. Default Gateway: 10.5.0.1

b. IPv4 Address: 10.5.0.4

c. Subnet Mask: 255.255.255.0

Click SRV1 > Config > FastEthernet0

11. Configure the following management IP addresses on the Access switches (interface VLAN 99), and configure the appropriate subnet's first usable address as the default gateway.

a. ASW-A1: 10.0.0.4/28

b. ASW-A2: 10.0.0.5/28

c. ASW-A3: 10.0.0.6/28

d. ASW-B1: 10.0.0.20/28

e. ASW-B2: 10.0.0.21/28

f. ASW-B3: 10.0.0.22/28

```
int vlan 99
  ip address 10.0.0.4 255.255.255.240
  no shut
ip default-gateway 10.0.0.1
int vlan 99
  ip address 10.0.0.5 255.255.255.240
  no shut
ip default-gateway 10.0.0.1
int vlan 99
  ip address 10.0.0.6 255.255.255.240
  no shut
ip default-gateway 10.0.0.1
int vlan 99
  ip address 10.0.0.20 255.255.255.240
  no shut
ip default-gateway 10.0.0.17
int vlan 99
  ip address 10.0.0.21 255.255.255.240
  no shut
ip default-gateway 10.0.0.17
int vlan 99
  ip address 10.0.0.22 255.255.255.240
  no shut
ip default-gateway 10.0.0.17
```

12. Configure HSRPv2 group 1 for Office A's Management subnet (VLAN 99). Make DSW-A1 the Active router by increasing its priority to 5 above the default, and enable preemption on DSW-A1.

a. Subnet: 10.0.0.0/28

b. VIP: 10.0.0.1

c. DSW-A1: 10.0.0.2

d. DSW-A2: 10.0.0.3

```
int vlan 99
  ip address 10.0.0.2 255.255.255.240
  standby version 2
  standby 1 ip 10.0.0.1
  standby 1 priority 105
  standby 1 preempt
int vlan 99
  ip address 10.0.0.3 255.255.255.240
  standby version 2
  standby 1 ip 10.0.0.1
```

13. Configure HSRPv2 group 2 for Office A's PCs subnet (VLAN 10). Make DSW-A1 the Active router by increasing its priority to 5 above the default, and enable preemption on DSW-A1.

a. Subnet: 10.1.0.0/24

b. VIP: 10.1.0.1

c. DSW-A1: 10.1.0.2

d. DSW-A2: 10.1.0.3

```
int vlan 10
  ip address 10.1.0.2 255.255.255.0
  standby version 2
  standby 2 ip 10.1.0.1
  standby 2 priority 105
  standby 2 preempt
int vlan 10
  ip address 10.1.0.3 255.255.255.0
  standby version 2
  standby 2 ip 10.1.0.1
```

14. Configure HSRPv2 group 3 for Office A's Phones subnet (VLAN 20). Make DSW-A2 the Active router by increasing its priority to 5 above the default, and enable preemption on DSW-A2.

a. Subnet: 10.2.0.0/24

b. VIP: 10.2.0.1

c. DSW-A1: 10.2.0.2

d. DSW-A2: 10.2.0.3

```
int vlan 20
  ip address 10.2.0.2 255.255.255.0
  standby version 2
  standby 3 ip 10.2.0.1
int vlan 20
  ip address 10.2.0.3 255.255.255.0
  standby version 2
  standby 3 ip 10.2.0.1
  standby 3 priority 105
  standby 3 preempt
```

15. Configure HSRPv2 group 4 for Office A's Wi-Fi subnet (VLAN 40). Make DSW-A2 the Active router by increasing its priority to 5 above the default, and enable preemption on DSW-A2.

a. Subnet: 10.6.0.0/24

b. VIP: 10.6.0.1

c. DSW-A1: 10.6.0.2

d. DSW-A2: 10.6.0.3

```
int vlan 40
  ip address 10.6.0.2 255.255.255.0
  standby version 2
  standby 4 ip 10.6.0.1
int vlan 40
  ip address 10.6.0.3 255.255.255.0
  standby version 2
  standby 4 ip 10.6.0.1
  standby 4 priority 105
  standby 4 preempt
```

16. Configure HSRPv2 group 1 for Office B's Management subnet (VLAN 99). Make DSW-B1 the Active router by increasing its priority to 5 above the default, and enable preemption on DSW-B1.

a. Subnet: 10.0.0.16/28

b. VIP: 10.0.0.17

c. DSW-B1: 10.0.0.18d. DSW-B2: 10.0.0.19

```
int vlan 99
  ip address 10.0.0.18 255.255.255.240
  standby version 2
  standby 1 ip 10.0.0.17
  standby 1 priority 105
  standby 1 preempt
int vlan 99
  ip address 10.0.0.19 255.255.255.240
  standby version 2
  standby 1 ip 10.0.0.17
```

17. Configure HSRPv2 group 2 for Office B's PCs subnet (VLAN 10). Make DSW-B1 the Active router by increasing its priority to 5 above the default, and enable preemption on DSW-B1.

a. Subnet: 10.3.0.0/24

b. VIP: 10.3.0.1

c. DSW-B1: 10.3.0.2

d. DSW-B2: 10.3.0.3

```
int vlan 10
  ip address 10.3.0.2 255.255.255.0
  standby version 2
  standby 2 ip 10.3.0.1
  standby 2 priority 105
  standby 2 preempt
int vlan 10
  ip address 10.3.0.3 255.255.255.0
  standby version 2
  standby 2 ip 10.3.0.1
```

18. Configure HSRPv2 group 3 for Office B's Phones subnet (VLAN 20). Make DSW-B2 the Active router by increasing its priority to 5 above the default, and enable preemption on DSW-B2.

a. Subnet: 10.4.0.0/24

b. VIP: 10.4.0.1

c. DSW-B1: 10.4.0.2

d. DSW-B2: 10.4.0.3

```
int vlan 20
  ip address 10.4.0.2 255.255.255.0
  standby version 2
  standby 3 ip 10.4.0.1
int vlan 20
  ip address 10.4.0.3 255.255.255.0
  standby version 2
  standby 3 ip 10.4.0.1
  standby 3 priority 105
  standby 3 preempt
```

19. Configure HSRPv2 group 4 for Office B's Servers subnet (VLAN 30). Make DSW-B2 the Active router by increasing its priority to 5 above the default, and enable preemption on DSW-B2.

a. Subnet: 10.5.0.0/24

b. VIP: 10.5.0.1

c. DSW-B1: 10.5.0.2

d. DSW-B2: 10.5.0.3

```
int vlan 30
  ip address 10.5.0.2 255.255.255.0
  standby version 2
  standby 4 ip 10.5.0.1
int vlan 30
  ip address 10.5.0.3 255.255.255.0
  standby version 2
  standby 4 ip 10.5.0.1
  standby 4 priority 105
  standby 4 preempt
```

Part 4 - Rapid Spanning Tree Protocol

- 1. Configure Rapid PVST+ on all Access and Distribution switches.
 - **a.** Ensure that the Root Bridge for each VLAN aligns with the HSRP Active router by configuring the lowest possible STP priority.
 - **b.** Configure the HSRP Standby Router for each VLAN with an STP priority one increment above the lowest priority.

```
spanning-tree mode rapid-pvst
DA1
spanning-tree vlan 10,99 priority 0
spanning-tree vlan 20,40 priority 4096
DA2
spanning-tree vlan 20,40 priority 0
spanning-tree vlan 10,99 priority 4096
DB1
spanning-tree vlan 10,99 priority 0
spanning-tree vlan 20,30 priority 4096
DB2
spanning-tree vlan 20,30 priority 0
spanning-tree vlan 10,99 priority 4096
```

2. Enable PortFast and BPDU Guard on all ports connected to end hosts (including WLC1). Perform the configurations in interface config mode.

```
int f0/1
spanning-tree portfast
spanning-tree bpduguard enable
int f0/2
spanning-tree portfast trunk
spanning-tree bpduguard enable
AA2,AA3,AB1,AB2,AB3
int f0/1
spanning-tree portfast
spanning-tree bpduguard enable
```

Part 5 - Static and Dynamic Routing

- 1. Configure OSPF on R1 (LAN-facing interfaces) and all Core and Distribution switches (all Layer-3 interfaces).
 - a. Use process ID 1 and Area 0.
 - **b.** Manually configure each device's RID to match the loopback interface IP.
 - c. On switches, use the network command to match the exact IP address of each interface.
 - **d.** On R1, enable OSPF in interface config mode.
 - e. Make sure OSPF is enabled on all loopback interfaces, too. Loopback interfaces should be passive.
 - f. Each Distribution switch's SVIs (except the Management VLAN SVI) should be passive, too.
 - **g.** Configure all physical connections between OSPF neighbors to use a network type that doesn't elect a DR/BDR. NOTE: This doesn't work on the Layer-3 PortChannel interfaces between CSW1/CSW2. Leave them as the default network type.

```
R1
router ospf 1
  router-id 10.0.0.76
  passive-interface loopback0
int 10
  ip ospf 1 area 0
int range g0/0-1
  ip ospf 1 area 0
  ip ospf network point-to-point
router ospf 1
  router-id 10.0.0.77
  passive-interface loopback0
sh ip int br | exclude un
network 10.0.0.41 0.0.0.0 area 0
network 10.0.0.34 0.0.0.0 area 0
network 10.0.0.45 0.0.0.0 area 0
network 10.0.0.49 0.0.0.0 area 0
network 10.0.0.53 0.0.0.0 area 0
network 10.0.0.57 0.0.0.0 area 0
network 10.0.0.77 0.0.0.0 area 0
int range g1/0/1,g1/1/1-4
  ip ospf network point-to-point
router ospf 1
  router-id 10.0.0.78
  passive-interface loopback0
network 10.0.0.42 0.0.0.0 area 0
network 10.0.0.38 0.0.0.0 area 0
network 10.0.0.61 0.0.0.0 area 0
network 10.0.0.65 0.0.0.0 area 0
network 10.0.0.69 0.0.0.0 area 0
network 10.0.0.73 0.0.0.0 area 0
network 10.0.0.78 0.0.0.0 area 0
int range g1/0/1,g1/1/1-4
  ip ospf network point-to-point
DSW-A1
router ospf 1
  router-id 10.0.0.79
  passive-interface loopback0
  passive-interface vlan 10
  passive-interface vlan 20
  passive-interface vlan 40
network 10.0.0.46 0.0.0.0 area 0
network 10.0.0.62 0.0.0.0 area 0
network 10.0.0.79 0.0.0.0 area 0
```

```
network 10.1.0.2 0.0.0.0 area 0
network 10.2.0.2 0.0.0.0 area 0
network 10.0.0.2 0.0.0.0 area 0
network 10.6.0.2 0.0.0.0 area 0
int range g1/1/1-2
  ip ospf network point-to-point
DSW-A2
router ospf 1
  router-id 10.0.0.80
  passive-interface loopback0
  passive-interface vlan 10
  passive-interface vlan 20
  passive-interface vlan 40
network 10.0.0.50 0.0.0.0 area 0
network 10.0.0.66 0.0.0.0 area 0
network 10.0.0.80 0.0.0.0 area 0
network 10.1.0.3 0.0.0.0 area 0
network 10.2.0.3 0.0.0.0 area 0
network 10.0.0.3 0.0.0.0 area 0
network 10.6.0.3 0.0.0.0 area 0
int range g1/1/1-2
  ip ospf network point-to-point
DSW-B1
router ospf 1
  router-id 10.0.0.81
  passive-interface loopback0
  passive-interface vlan 10
  passive-interface vlan 20
  passive-interface vlan 30
network 10.0.0.54 0.0.0.0 area 0
network 10.0.0.70 0.0.0.0 area 0
network 10.0.0.81 0.0.0.0 area 0
network 10.3.0.2 0.0.0.0 area 0
network 10.4.0.2 0.0.0.0 area 0
network 10.5.0.2 0.0.0.0 area 0
network 10.0.0.18 0.0.0.0 area 0
int range g1/1/1-2
  ip ospf network point-to-point
DSW-B2
router ospf 1
  router-id 10.0.0.82
  passive-interface loopback0
  passive-interface vlan 10
  passive-interface vlan 20
  passive-interface vlan 30
network 10.0.0.58 0.0.0.0 area 0
network 10.0.0.74 0.0.0.0 area 0
network 10.0.0.82 0.0.0.0 area 0
network 10.3.0.3 0.0.0.0 area 0
network 10.4.0.3 0.0.0.0 area 0
network 10.5.0.3 0.0.0.0 area 0
network 10.0.0.19 0.0.0.0 area 0
int range g1/1/1-2
  ip ospf network point-to-point
```

- 2. Configure one static default route for each of R1's Internet connections. They should be recursive routes.
 - **a.** Make the route via G0/1/0 a floating static route by configuring an AD value 1 greater than the default.
 - **b.** R1 should function as an OSPF ASBR, advertising its default route to other routers in the OSPF domain.

```
R1
ip route 0.0.0.0 0.0.0.0 203.0.113.1
ip route 0.0.0.0 0.0.0.0 203.0.113.5 2
router ospf 1
default-information originate
```

Part 6 - Network Services: DHCP, DNS, NTP, SNMP, Syslog, FTP, SSH, NAT

1. Configure the following DHCP pools on R1 to make it serve as the DHCP server for hosts in Offices A and B. Exclude the first ten usable host addresses of each pool; they must not be leased to DHCP clients. a. Pool: A-Mgmt i. Subnet: 10.0.0.0/28 ii. Default gateway: 10.0.0.1 iii. Domain name: jeremysitlab.com iv. DNS server: 10.5.0.4 (SRV1) v. WLC: 10.0.0.7 b. Pool: A-PC **i.** Subnet: 10.1.0.0/24 ii. Default gateway: 10.1.0.1 iii. Domain name: jeremysitlab.com iv. DNS server: 10.5.0.4 (SRV1) c. Pool: A-Phone **i.** Subnet: 10.2.0.0/24 ii. Default gateway: 10.2.0.1 iii. Domain name: jeremysitlab.com iv. DNS server: 10.5.0.4 (SRV1) d. Pool: B-Mgmt i. Subnet: 10.0.0.16/28 ii. Default gateway: 10.0.0.17 iii. Domain name: jeremysitlab.com iv. DNS server: 10.5.0.4 (SRV1) v. WLC: 10.0.0.7 e. Pool: B-PC **i.** Subnet: 10.3.0.0/24 ii. Default gateway: 10.3.0.1 iii. Domain name: jeremysitlab.com iv. DNS server: 10.5.0.4 (SRV1) **f.** Pool: B-Phone **i.** Subnet: 10.4.0.0/24 ii. Default gateway: 10.4.0.1 iii. Domain name: jeremysitlab.com iv. DNS server: 10.5.0.4 (SRV1) g. Pool: Wi-Fi **i.** Subnet: 10.6.0.0/24 ii. Default gateway: 10.6.0.1 iii. Domain name: jeremysitlab.com iv. DNS server: 10.5.0.4 (SRV1) ip dhcp excluded-address 10.0.0.1 10.0.0.10 ip dhcp excluded-address 10.1.0.1 10.1.0.10 ip dhcp excluded-address 10.2.0.1 10.2.0.10 ip dhcp excluded-address 10.0.0.17 10.0.0.26 ip dhcp excluded-address 10.3.0.1 10.3.0.10 ip dhcp excluded-address 10.4.0.1 10.4.0.10 ip dhcp excluded-address 10.6.0.1 10.6.0.10 ip dhcp pool A-Mgmt network 10.0.0.0 255.255.255.240 deafult-router 10.0.0.1 dns-server 10.5.0.4 domain-name jeremysitlab.com option 43 ip 10.0.0.7 ip dhcp pool A-PC network 10.1.0.0 255.255.255.0

default-router 10.1.0.1 dns-server 10.5.0.4

domain-name jeremysitlab.com

```
ip dhcp pool A-Phone
  network 10.2.0.0 255.255.255.0
  default-router 10.2.0.1
  dns-server 10.5.0.4
  domain-name jeremysitlab.com
ip dhcp pool B-Mgmt
  network 10.0.0.16 255.255.255.240
  default-router 10.0.0.17
  dns-server 10.5.0.4
  domain-name jeremysitlab.com
  option 43 ip 10.0.0.7
ip dhcp pool B-PC
  network 10.3.0.0 255.255.255.0
  default-router 10.3.0.1
  dns-server 10.5.0.4
  domain-name jeremysitlab.com
ip dhcp pool B-Phone
  network 10.4.0.0 255.255.255.0
  default-router 10.4.0.1
  dns-server 10.5.0.4
  domain-name jeremysitlab.com
ip dhcp pool Wi-Fi
  network 10.6.0.0 255.255.255.0
  default-router 10.6.0.1
  dns-server 10.5.0.4
  domain-name jeremysitlab.com
```

2. Configure the Distribution switches to relay wired DHCP clients' broadcast messages to R1's Loopback0 IP address.

```
DA1,DA2
int vlan 10
  ip helper-address 10.0.0.76
int vlan 20
  ip helper-address 10.0.0.76
int vlan 40
  ip helper-address 10.0.0.76
int vlan 99
  ip helper-address 10.0.0.76
DB1,DB2
int vlan 10
  ip helper-address 10.0.0.76
int vlan 20
  ip helper-address 10.0.0.76
int vlan 30
  ip helper-address 10.0.0.76
int vlan 99
  ip helper-address 10.0.0.76
```

3. Configure the following DNS entries on SRV1:

```
a. google.com = 172.253.62.100
```

- **b.** youtube.com = 152.250.31.93
- **c.** jeremysitlab.com = 66.235.200.145
- **d.** www.jeremysitlab.com = jeremysitlab.com

go to srv1 then configure. (option d is canonical name)

4. Configure all routers and switches to use domain name **jeremysitlab.com** and use SRV1 as their DNS server.

```
all devices routers and switches ip domain name jeremysitlab.com
```

ip name-server 10.5.0.4

- **5.** Configure NTP on R1:
 - a. Make R1 a stratum 5 NTP server.
 - **b.** R1 should learn the time from NTP server 216.239.35.0.
 - **c.** NOTE: NTP takes a LONG time to sync, especially in Packet Tracer. After making the configurations, you can move on don't wait for the devices to sync.

```
ntp master 5
ntp server 216.239.35.0
```

- **6.** All Core, Distribution, and Access switches should use R1's loopback interface as their NTP server.
 - **a.** Clients should authenticate R1 using key number **1** and the password **ccna**.

```
ntp authentication-key 1 md5 ccna
ntp trusted-key 1
c,a,d switches
ntp authentication-key 1 md5 ccna
ntp trusted-key 1
ntp server 10.0.0.76 key 1
```

7. Configure the SNMP community string **SNMPSTRING** on all routers and switches. The string should allow GET messages, but not SET messages.

```
all r and switches
snmp-server community SNMPSTRING ro
```

- **8.** Configure Syslog on all routers and switches:
 - a. Send Syslog messages to SRV1. Messages of all severity levels should be logged.
 - **b.** Enable logging to the buffer. Reserve 8192 bytes of memory for the buffer.

```
all router and switches
logging 10.5.0.4
logging trap debugging
logging buffered 8192
```

- **9.** Use FTP on R1 to download a new IOS version from SRV1:
 - a. Configure R1's default FTP credentials: username cisco, password cisco.
 - b. Use FTP to copy the file c2900-universalk9-mz.SPA.155-3.M4a.bin from SRV1 to R1's flash drive.
 - c. Reboot R1 using the new IOS file, and then delete the old one from flash.

```
ip ftp username cisco
ip ftp password cisco
copy ftp flash
10.5.0.4
pastefilename
enter, it should take 4/5 minutes, take some time get a drink
sh flash
boot system flash:newfilename
do wr
sh version
reload
delete flash:old file name
```

- 10. Configure SSH for secure remote access on all routers and switches.
 - a. Use the largest modulus size for the RSA keys.
 - **b.** Allow SSHv2 connections only.
 - **c.** Create standard ACL 1, only allowing packets sourced from Office A's PCs subnet. Apply the ACL to all VTY lines to restrict SSH access.
 - **d.** Allow only SSH connections to the VTY lines.
 - e. Require users to log in with a local user account when connecting via SSH.
 - **f.** Configure synchronous logging on the VTY lines.

```
R1 and all switches
crypto key generate rsa
4096
```

```
ip ssh version 2
access-list 1 permit 10.1.0.0 0.0.0.255
line vty 0 15
   access-class 1 in
   transport input ssh
   login local
   logging synchronous
sh ip ssh
go to pc1
ping 10.0.0.76
ssh -1 cisco 10.0.0.76
ccna
go to pc3
ping 10.0.0.76
ssh -1 cisco 10.0.0.76
```

11. Configure static NAT on R1 to enable hosts on the Internet to access SRV1 via the IP address 203.0.113.113.

```
ip nat inside source static 10.5.0.4 203.0.113.113
int range g0/0/0,g0/1/0
ip nat outside
int range g0/0-1
ip nat inside
go srv1 > config tab > dns server 10.5.0.4
ping google.com
```

- **12.** Configure pool-based dynamic PAT on R1 to enable hosts in the Office A PCs, Office A Phones, Office B PCs, Office B Phones, and Wi-Fi subnets to access the Internet.
 - **a.** Use standard ACL 2 to define the appropriate inside local address ranges in the following order:

i. Office A PCs: 10.1.0.0/24
ii. Office A Phones: 10.2.0.0/24
iii. Office B PCs: 10.3.0.0/24
iv. Office B Phones: 10.4.0.0/24
v. Wi-Fi: 10.6.0.0/24

- **b.** Define a range of inside global addresses called **POOL1**, specifying the range 203.0.113.200 to 203.0.113.207 with a /29 netmask.
- **c.** Map ACL 2 to POOL1 and enable PAT. Confirm that hosts can access the Internet by pinging jeremysitlab.com.
- **d.** Verify that Internet link failover works by disabling R1's G0/0/0 interface and pinging again.
 - **i.** You will need to remove and re-configure the OSPF default-information originate command for this to work. In real Cisco routers, you can configure the default-information originate always command that supports failover like this, but the command isn't available in Packet Tracer.
 - ii. Re-enable G0/0/0 (and remove and re-configure default-information originate once again).

```
R1
access-list 2 permit 10.1.0.0 0.0.0.255
access-list 2 permit 10.2.0.0 0.0.0.255
access-list 2 permit 10.3.0.0 0.0.0.255
access-list 2 permit 10.4.0.0 0.0.0.255
access-list 2 permit 10.6.0.0 0.0.0.255
ip nat pool POOL1 203.0.113.200 203.0.113.207 netmask 255.255.255.248
ip nat inside source list 2 pool POOL1 overload
go pc1
ping jeremysitlab.com
go r1
int g0/0/0
  shut
router ospf 1
  no default-information originate
  default-information originate
```

```
sh ip route (see bottom S*)
go pc1
ping jeremysitlab.com
go r1
int g0/0/0
no shut
router ospf 1
no default-information originate
default-information originate
```

13. Disable CDP on all devices and enable LLDP instead.

a. Disable LLDP Tx on each Access switch's access port (F0/1).

```
r1,core and dsw
no cdp run
lldp run
access sw
no cdp run
lldp run
int f0/1
no lldp transmit
```

Part 7 – Security: ACLs and Layer-2 Security Features

- 1. Configure extended ACL OfficeA to OfficeB where appropriate:
 - a. Allow ICMP messages from the Office A PCs subnet to the Office B PCs subnet.
 - **b.** Block all other traffic from the **Office A PCs** subnet to the **Office B PCs** subnet.
 - **c.** Allow all other traffic.
 - **d.** Apply the ACL according to general best practice for extended ACLs.

```
ip access-list extended OfficeA_to_OfficeB
  permit icmp 10.1.0.0 0.0.0.255 10.3.0.0 0.0.0.255
  deny ip 10.1.0.0 0.0.0.255 10.3.0.0 0.0.0.255
  permit ip any any
int vlan 10
  ip access-group OfficeA_to_OfficeB in
dswa2
ip access-list extended OfficeA_to_OfficeB
  permit icmp 10.1.0.0 0.0.0.255 10.3.0.0 0.0.0.255
  deny ip 10.1.0.0 0.0.0.255 10.3.0.0 0.0.0.255
  permit ip any any
int vlan 10
  ip access-group OfficeA_to_OfficeB in
```

- **2.** Configure Port Security on each Access switch's F0/1 port:
 - **a.** Allow the minimum necessary number of MAC addresses on each port.
 - **i.** SRV1 does not use virtualization, so it uses a single MAC address.
 - **b.** Configure a violation mode that blocks invalid traffic without affecting valid traffic. The switches should send notifications when invalid traffic is detected.
 - c. Switches should automatically save the secure MAC addresses they learn to the running-config.

```
aswa1,aswb1,aswb3
int f0/1
  sw port-security
  sw port-security violation restrict
  sw port-security mac-address sticky
aswa2,aswa3,aswb2
int f0/1
  sw port-security
  sw port-security
  sw port-security maximum 2
  sw port-security mac-address sticky
  sw port-security violation restrict
```

- **3.** Configure DHCP Snooping on all Access switches.
 - **a.** Enable it for all active VLANs in each LAN.
 - **b.** Trust the appropriate ports.
 - c. Disable insertion of DHCP Option 82.
 - **d.** Set a DHCP rate limit of 15 pps on active untrusted ports.
 - e. Set a higher limit (100 pps) on ASW-A1's connection to WLC1.

```
aswa1
ip dhcp snooping
ip dhcp snooping vlan 10,20,40,99
no ip dhcp snooping information option
int range g0/1-2
  ip dhcp snooping trust
int f0/1
  ip dhcp snooping limit rate 15
int f0/2
  ip dhcp snooping limit rate 100
aswa2,a3
ip dhcp snooping vlan 10,20,40,99
```

```
no ip dhcp snooping information option
int range g0/1-2
  ip dhcp snooping trust
int f0/1
  ip dhcp snooping limit rate 15
aswb1,b2,b3
ip dhcp snooping
ip dhcp snooping vlan 10,20,30,99
no ip dhcp snooping information option
int range g0/1-2
  ip dhcp snooping trust
int f0/1
  ip dhcp snooping limit rate 15
```

- **4.** Configure DAI on all Access switches.
 - a. Enable it for all active VLANs in each LAN.
 - **b.** Trust the appropriate ports.
 - c. Enable all optional validation checks.

```
aswa1,a2,a3
ip arp inspection vlan 10,20,40,99
ip arp inspection validate dst-mac src-mac ip
int range g0/1-2
   ip arp inspection trust
aswb1,b2,b3
ip arp inspection vlan 10,20,30,99
ip arp inspection validate dst-mac src-mac ip
int range g0/1-2
   ip arp inspection trust
```

Part 8 - IPv6

- 1. To prepare for a migration to IPv6, enable IPv6 routing and configure IPv6 addresses on R1, CSW1, and CSW2:
 - a. R1 G0/0/0: 2001:db8:a::2/64
 - **b.** R1 G0/1/0: 2001:db8:b::2/64
 - **c.** R1 G0/0 and CSW1 G1/0/1: Use prefix 2001:db8:a1::/64 and EUI-64 to generate an interface ID for each interface.
 - **d.** R1 G0/1 and CSW2 G1/0/1: Use prefix 2001:db8:a2::/64 and EUI-64 to generate an interface ID for each interface.
 - e. CSW1 Po1 and CSW2 Po1: Enable IPv6 without using the 'ipv6 address' command.

```
r1
ipv6 unicast-routing
int g0/0/0
  ipv6 address 2001:db8:a::2/64
  no shut
int g0/1/0
  ipv6 address 2001:db8:b::2/64
  no shut
int g0/0
  ipv6 address 2001:db8:a1::/64 eui-64
int g0/1
  ipv6 address 2001:db8:a2::/64 eui-64
ipv6 unicast-routing
int g1/0/1
  ipv6 address 2001:db8:a1::/64 eui-64
int po1
  ipv6 enable
csw2
int g1/0/1
  ipv6 address 2001:db8:a2::/64 eui-64
int po1
  ipv6 enable
```

- **2.** Configure two default static routes on R1:
 - **a.** A recursive route via next hop 2001:db8:a::1.
 - **b.** A fully-specified route via next hop 2001:db8:b::1. Make it a floating route by configuring the AD 1 higher than default.

```
r1
ipv6 route ::/0 2001:db8:a::1
ipv6 route ::/0 g0/1/0 2001:db8:b::1 2
```

Part 9 - Wireless

- 1. Access the GUI of WLC1 (https://10.0.0.7) from one of the PCs.
 - **a.** Username: admin**b.** Password: adminPW12
- 2. Configure a dynamic interface for the Wi-Fi WLAN (10.6.0.0/24)
 - a. Name: Wi-Fib. VLAN: 40c. Port number: 1
 - **d.** IP address: .2 of its subnet **e.** Gateway: .1 of its subnet **f.** DHCP server: 10.0.0.76
- **3.** Configure and enable the following WLAN:
 - a. Profile name: Wi-Fi
 - **b.** SSID: Wi-Fi
 - **c.** ID: 1
 - d. Status: Enabled
 - e. Security: WPA2 Policy with AES encryption, PSK of cisco123
- 4. Verify that both LWAPs have associated with WLC1.
 - **a.** Due to Packet Tracer's limitations, wireless clients won't be able to lease an IP address from the Wi-Fi DHCP pool.

If you are confused, watch the last part of the video again.