D1.1a - VISHNU General specifications



COLLABORATORS

	TITLE : D1.1a - VISHNU Gene	ral specifications	
ACTION	NAME	DATE	SIGNATURE
WRITTEN BY	Benjamin Isnard, Daouda Traoré, Eugène Pamba Capo-Chichi, Kevin Coulomb, and Ibrahima Cissé	January 14, 2011	

REVISION HISTORY

NUMBER	DATE	DESCRIPTION	NAME
01	07/12/2010	Formatting example	SysFera
02	13/12/2010	Pre-deli <mark>verable</mark>	SysFera
03	13/01/2011	First Release	SysFera

Contents

1	Docu	ument p	resentation	1
	1.1	Docum	ent objectives	1
	1.2	Docum	ent structure	1
	1.3		nces	1
	1.4	Glossa	ry	1
2	Use	cases for	r User Management System (UMS)	2
	2.1	Use cas	se diagrams	2
		2.1.1	UC UMS User Manual	2
		2.1.2	UC UMS User Auto	2
		2.1.3	UC UMS User account	3
		2.1.4	UC UMS Admin	4
		2.1.5	UC UMS Admin Machines	4
	2.2	Use cas	se descriptions	5
		2.2.1	U1 - Session with manual closure	5
		2.2.2	U1.1 - Open session	5
		2.2.3	U1.2 - Close session	6
		2.2.4	U1.3 - Execute synchronous user request	7
		2.2.5	U1.3.1 - Configure Option	7
		2.2.6	U1.3.2 - Display options	8
		2.2.7	U1.3.3 - Change password	8
		2.2.8	U1.3.4 - Display session command history	8
		2.2.9	U1.3.5 - Display sessions log	9
		2.2.10	U1.4 - Execute asynchronous user request	9
		2.2.11	U1.5 - Reconnect to session	10
		2.2.12	U2 - Session with automatic closure on timeout	10
		2.2.13	U2.1 - Close session auto	11
		2.2.14	U3 - Session with automatic closure on disconnect	11
		2.2.15	U4 - Create new local user config	12
		2.2.16	U4.1 - Update local user config	12

		2.2.17	U4.2 - Delete local user config	13
		2.2.18	U4.3 - Display local user configs	13
		2.2.19	UA1 - Create new user account	13
		2.2.20	UA1.1 - Update user account	14
		2.2.21	UA1.2 - Delete user account	14
		2.2.22	UA2 - Reset user password	15
		2.2.23	UA3 - Save configuration	15
		2.2.24	UA4 - Restore configuration	15
		2.2.25	UA5.1 - Display sessions	16
		2.2.26	UA5.2 - Display users	16
		2.2.27	UA5.3 - Display local users configs	17
		2.2.28	UA6.1 Add a machine	17
		2.2.29	UA6.2 Remove a machine	17
			UA6.3 Display machines	
		2.2.31	UA6.4 Update machines	18
		2.2.32	UA7 - Configure default option value	18
	2.3	Data di	ctionary	19
2	Ugo	aagag f a	r Tasks Management System (TMS)	20
,	3.1		se diagrams	
	3.1	USE Cas	se diagrams	20
		3 1 1	LIC TMS Overview	20
	3.2	3.1.1	UC TMS Overview	
	3.2	Use cas	se descriptions	21
	3.2	Use cas 3.2.1	se descriptions	2121
	3.2	Use cas 3.2.1 3.2.2	T1 - Asynchronous command on a machine	212121
	3.2	Use case 3.2.1 3.2.2 3.2.3	T1 - Asynchronous command on a machine	21212122
	3.2	Use cas 3.2.1 3.2.2 3.2.3 3.2.4	T1 - Asynchronous command on a machine	2121212222
	3.2	Use cas 3.2.1 3.2.2 3.2.3 3.2.4 3.2.5	T1 - Asynchronous command on a machine T1.1 - Submit a job T1.2 - Get job outputs (asynchronous) T2 - Synchronous command on a machine T2.1 - Get job information	212121222223
	3.2	Use cas 3.2.1 3.2.2 3.2.3 3.2.4 3.2.5 3.2.6	T1 - Asynchronous command on a machine T1.1 - Submit a job T1.2 - Get job outputs (asynchronous) T2 - Synchronous command on a machine T2.1 - Get job information T2.2 - Cancel a job	21212122222323
	3.2	Use cas 3.2.1 3.2.2 3.2.3 3.2.4 3.2.5 3.2.6 3.2.7	se descriptions T1 - Asynchronous command on a machine T1.1 - Submit a job T1.2 - Get job outputs (asynchronous) T2 - Synchronous command on a machine T2.1 - Get job information T2.2 - Cancel a job T2.3 - List job queues	21 21 22 22 23 23 24
	3.2	Use cas 3.2.1 3.2.2 3.2.3 3.2.4 3.2.5 3.2.6 3.2.7 3.2.8	T1 - Asynchronous command on a machine T1.1 - Submit a job T1.2 - Get job outputs (asynchronous) T2 - Synchronous command on a machine T2.1 - Get job information T2.2 - Cancel a job T2.3 - List job queues T2.4 - List jobs	21 21 22 22 23 23 24 24
	3.2	Use cas 3.2.1 3.2.2 3.2.3 3.2.4 3.2.5 3.2.6 3.2.7 3.2.8 3.2.9	re descriptions T1 - Asynchronous command on a machine T1.1 - Submit a job T1.2 - Get job outputs (asynchronous) T2 - Synchronous command on a machine T2.1 - Get job information T2.2 - Cancel a job T2.3 - List job queues T2.4 - List jobs T2.5 - Get jobs progression	21 21 22 22 23 23 24 24 25
	3.2	Use cas 3.2.1 3.2.2 3.2.3 3.2.4 3.2.5 3.2.6 3.2.7 3.2.8 3.2.9 3.2.10	T1 - Asynchronous command on a machine T1.1 - Submit a job T1.2 - Get job outputs (asynchronous) T2 - Synchronous command on a machine T2.1 - Get job information T2.2 - Cancel a job T2.3 - List job queues T2.4 - List jobs T2.5 - Get jobs progression T2.6 - Get job outputs (synchronous)	21 21 22 22 23 23 24 24 25 25
	3.2	Use cas 3.2.1 3.2.2 3.2.3 3.2.4 3.2.5 3.2.6 3.2.7 3.2.8 3.2.9 3.2.10 3.2.11	T1 - Asynchronous command on a machine T1.1 - Submit a job T1.2 - Get job outputs (asynchronous) T2 - Synchronous command on a machine T2.1 - Get job information T2.2 - Cancel a job T2.3 - List job queues T2.4 - List jobs T2.5 - Get jobs progression T2.6 - Get job outputs (synchronous) TA1 - Set machine refresh period	21 21 22 22 23 23 24 24 25 25 26
	3.2	Use cas 3.2.1 3.2.2 3.2.3 3.2.4 3.2.5 3.2.6 3.2.7 3.2.8 3.2.9 3.2.10 3.2.11 3.2.12	T1 - Asynchronous command on a machine T1.1 - Submit a job T1.2 - Get job outputs (asynchronous) T2 - Synchronous command on a machine T2.1 - Get job information T2.2 - Cancel a job T2.3 - List job queues T2.4 - List jobs T2.5 - Get jobs progression T2.6 - Get job outputs (synchronous) TA1 - Set machine refresh period TA2 - Set machine environment	21 21 22 22 23 23 24 24 25 25 26 26
	3.2	Use cas 3.2.1 3.2.2 3.2.3 3.2.4 3.2.5 3.2.6 3.2.7 3.2.8 3.2.9 3.2.10 3.2.11 3.2.12 3.2.13	T1 - Asynchronous command on a machine T1.1 - Submit a job T1.2 - Get job outputs (asynchronous) T2 - Synchronous command on a machine T2.1 - Get job information T2.2 - Cancel a job T2.3 - List job queues T2.4 - List jobs T2.5 - Get jobs progression T2.6 - Get job outputs (synchronous) TA1 - Set machine refresh period TA2 - Set machine environment TA3 - Launch TMS Server	21 21 22 22 23 23 24 24 25 25 26 26 26
	3.2	Use cas 3.2.1 3.2.2 3.2.3 3.2.4 3.2.5 3.2.6 3.2.7 3.2.8 3.2.9 3.2.10 3.2.11 3.2.12 3.2.13 3.2.14	T1 - Asynchronous command on a machine T1.1 - Submit a job T1.2 - Get job outputs (asynchronous) T2 - Synchronous command on a machine T2.1 - Get job information T2.2 - Cancel a job T2.3 - List job queues T2.4 - List jobs T2.5 - Get jobs progression T2.6 - Get job outputs (synchronous) TA1 - Set machine refresh period TA2 - Set machine environment	21 21 22 22 23 23 24 25 25 26 26 27

4	Use		r Information Management System (IMS)	28
	4.1	Use ca	se diagrams	
		4.1.1	UC IMS Global functionalities	28
		4.1.2	UC IMS Consult	29
		4.1.3	UC IMS Replay	30
		4.1.4	UC IMS Platform management	30
		4.1.5	UC IMS Stop_Restart	31
	4.2	Use ca	se descriptions	32
		4.2.1	I1. Get the update frequency	32
		4.2.2	I2 Get metric data	32
		4.2.3	I3. Export and replay commands	32
		4.2.4	I4. Get data on the infrastructure	33
		4.2.5	IA1. Get the running processes	33
		4.2.6	IA2. Define a system load threshold	33
		4.2.7	IA2.1 Get a system load thr <mark>eshold</mark>	34
		4.2.8	IA3. Define the identifiers	34
		4.2.9	IA4.1 Hard load shedding	35
		4.2.10	IA4.2 Soft load shedding	35
		4.2.11	IA5. Set system info	36
		4.2.12	IA6. Set the update frequency	36
		4.2.13	IA7. Notification of limit ove <mark>rflow</mark>	36
		4.2.14	IA8. Restart the System	37
		4.2.15	IA9. Restart	37
		4.2.16	U1.3 Execute synchronous request	37
	4.3	Data d	ictionary	38
5			r File Management System (FMS)	39
	5.1		se diagrams	
		5.1.1	UC FMS simple command use cases	
		5.1.2	UC FMS transfer command use cases	
	5.2	Use ca	se descriptions	
		5.2.1	F1- Execute simple command on a remote host	
		5.2.2	F1.CH1- Change access rights of files	
		5.2.3	F1.CH2- Change group owner of files	42
		5.2.4	F1.CR1- Create new files	43
		5.2.5	F1.CR2- Create new directories	
		5.2.6	F1.DE1- Delete files	44
		5.2.7	F1.DE2- Delete directories	44
		5.2.8	F1.DI1- Display Head of files	45

	5.2.9	F1.DI2- Display tail of files	45
	5.2.10	F1.DI3- Display contents of files	46
	5.2.11	F1.DI4- Display contents of directories	46
	5.2.12	F1.DI5- Get information about remote files	47
	5.2.13	F2.CA1- Cancel files tranfers	47
		F2.CA2- Cancel all users file transfers	
	5.2.15	F2.CP1- Execute a synchronous copy of files	49
		F2.CP2- Execute an asynchronous copy of files	
	5.2.17	F2.LS1- List files transfer status	51
	5.2.18	F2.LS2- List all users file transfer status	52
	5.2.19	F2.LT1- List all file transfer	53
	5.2.20	F2.LT2- List all users file tran <mark>sfer</mark>	53
	5.2.21	F2.MV1- Execute a synchronous move of files	54
	5.2.22	F2.MV2- Execute an asynch <mark>ronous</mark> move <mark>of files</mark>	55
	5.2.23	F3. Launch FMS server	56
	5.2.24	F4. Stop FMS server	57
2	Doto di	tionary	57

List of Figures

2.1	UC UMS User Manual	2
2.2	UC UMS User Auto	3
2.3	UC UMS User account	4
2.4	UC UMS Admin	4
2.5	UC UMS Admin Machines	5
3.1	UC TMS Overview	20
	UC IMS Global functionalities	
4.2	UC IMS Consult	30
4.3	UC IMS Replay	30
4.4	UC IMS Platform management	31
4.5	UC IMS Stop_Restart	31
5.1	UC FMS simple command use cases	40
5.2	LIC FMS transfer command use cases	41

Chapter 1

Document presentation

1.1 Document objectives

This document presents the external specifications of the Vishnu system at a general level. At this level, we describe the interaction of a user with the system without providing implementation details. The different steps that constitute the scenario are detailed as well as the content of the messages exchanged. The main objective is to describe the system from the user point of view.

These general specifications are a prerequisite for the detailed specifications step in the software development process.

1.2 Document structure

The document is divided into 4 parts corresponding to the 4 modules that compose the Vishnu system:

- UMS: Users Management System
- TMS: Tasks Management System
- FMS: Files Management System
- IMS: Information Management System

Each module corresponds to a chapter in the document, and each chapter contains two sections:

- A first section containing "Use case descriptions" that follow the standard UML description of a use case
- A second section containing the "Use case diagrams" that describe the organization of the different use cases. These diagrams follow the UML2.0 standard.

1.3 References

None

1.4 Glossary

• Sysfera-DS: open-source middleware software used by Vishnu (former name "DIET")

•

Chapter 2

Use cases for User Management System (UMS)

2.1 Use case diagrams

2.1.1 UC UMS User Manual

This UseCase Diagram describes all cases attached when the user opens a session with manual closure




Figure 2.1: UC UMS User Manual

2.1.2 UC UMS User Auto

This UseCase Diagram describes all cases associated when a user opens a session with automatic closure (on disconnect and on timeout)




Figure 2.2: UC UMS User Auto

2.1.3 UC UMS User account

This UseCase Diagram describes all cases associated when a user executes synchronous request




Figure 2.3: UC UMS User account

2.1.4 UC UMS Admin

This UseCase Diagram describes all administrator's functions




Figure 2.4: UC UMS Admin

2.1.5 UC UMS Admin Machines

This UseCase Diagram describes all cases associated to machine using by an admin




Figure 2.5: UC UMS Admin Machines

2.2 Use case descriptions

2.2.1 U1 - Session with manual closure

Title	U1 - Session with manual closure
Cummorty	The user opens a new session and closes it manually by
Summary	using the API command for closure
Actors	User
Precondition	- The user is authenticated
recondition	- VISHNU is installed and running on the client System
	- The session is closed
Postcondition	- A session log has been created
1 ostcondition	- All user requests submitted within the session are
	completed
	1. Include::U1.1 Open session
	2. System is ready to process user commands
Base sequence	3. Include::U1.2 Close session (before the maximum
	inactivity delay if option CLOSE_POLICY is equal to
	CLOSE_ON_TIMEOUT)
	2a. U1.3 Execute synchronous user request
Branch sequence	2b. U1.4 Execute asynchronous user request
	2c. U1.5 Reconnect to session
	1a. Include::U1.1 exceptions
Exception sequence	3a. If session cannot be closed due to running commands,
Exception sequence	user must wait until all commands are completed before
	trying step 3 again
	U1.3 - Execute synchronous user request
Extensions	U1.5 - Reconnect to session
	U1.4 - Execute asynchronous user request

2.2.2 **U1.1 - Open session**

Title	U1.1 - Open session
Summary	The user opens a session
Actors	User
Precondition	- The user is connected on a client System in which VISHNU is installed and which can be connected to the VISHNU infrastructure
Postcondition	- A session is active - The user's environment contains a session key
Base sequence	1. User provides login, password and optionally the way for closing the session automatically on disconnect or on timeout to the "connect" command (when the default option is not set the SESSION_CLOSE_POLICY is CLOSE_ON_TIMEOUT). If the user is an administrator, he/she can be connected as he/she was another specific user by providing his/her login. 2. System validates login, password (user is authenticated) and optionally, the name of the closing mode (CLOSE_ON_DISCONNECT or CLOSE ON TIMEOUT) if the SESSION_CLOSE_POLICY is set or optionally a login provides by the administrator who wants to be connected as he/she was another user. 3. System creates the session and activates it 4. System provides the session key to the user
Branch sequence	2a. If the password is a temporary password (after reset by the administrator) the System asks the user to enter a new password, then asks for a confirmation, and registers the new password if both steps are ok. If the User request is done through the API (non-interactive) then this is an exception (a change password request is required).
Exception sequence	2a. The user login is unknown 2b. The user password is invalid 2c. The SESSION_CLOSE_POLICY option is unknown 2d. VISHNU infrastructure is unreachable or unavailable 2e. The user password is temporary and the request is non-interactive 2f. The substitute login provides by the administrator is unknown
Notes	This use case defines behaviour(s) that is/are not defined in the project initial requirements.

2.2.3 U1.2 - Close session

Title	U1.2 - Close session
Summary	The user closes the session manually
Actors	User
Precondition	- The user is connected on the client System
recondition	- The user has an open session on the client System
	- The session is closed
stcondition	- A session log has been created
rostcondition	- All user requests submitted during the session are
	completed

Base sequence	 The user sends a request to close a session (the session key registered in the user's environment is sent to the System) The System checks that the session key is valid and the corresponding session is open The System checks that there are no running commands within the session The System closes the session The System informs the user that the session has been closed
Branch sequence	
Exception sequence	1a. VISHNU infrastructure is unreachable or unavailable 2a. The session key is invalid 2b. The session is already closed 2c. The session key is incompatible with the authenticated user (that means that the session identifier is not for the user who sends the requests). 3a. If there are running commands within the session, the System informs the user that the session cannot be closed
Notes	This use case defines behaviour(s) that is/are not defined in the project initial requirements.

2.2.4 U1.3 - Execute synchronous user request

Title	U1.3 - Execute synchronous user request
Summary	The user submits a synchronous request to the System
Actors	User
Precondition	- The user is connected on the client System
Frecondition	- The user has an open session on the client System
Postcondition	- The request is completed
rostcondition	- A request log is created
Pasa saguanga	1. The user sends the request to the System
Base sequence	2. The System returns the results to the user
Branch sequence	
	1.a Invalid session (bad session key or unavailable session)
	1.b Invalid request
Exception sequence	1.c Permission denied (admin request issued by normal
Exception sequence	user)
	1.d Ressource not available
	1.e VISHNU System crashed
	U1 - Session with manual closure
Extension of	U3 - Session with automatic closure on disconnect
	U2 - Session with automatic closure on timeout

2.2.5 U1.3.1 - Configure Option

Title	U1.3.1 - Configure Option
Summary	The user wants to modify the value of an option attached to
	his/her VISHNU account
Actors	User
Precondition	
Postcondition	The option's value is modified

Base sequence	 The user sends a request for modifying the value of an option to the System The System checks the option name and registers the new value for the option The System returns an acknowledgment to the user
Branch sequence	
Exception sequence	2a. Invalid option name 2b. Invalid option value

2.2.6 **U1.3.2 - Display options**

Title		U1.3.2	- Display options
Summary	The use	er displays options concerning his/her VISHNU	
Summary		accoun	t
Actors		User	
Precondition			
Postcondition			
Rosa saguanca	Base sequence	1. The	user sends a request to list all his/her options
Base sequence		2. The	System returns all options of the user
		1a. The	e users sends a request to list a specific option
Branch sequence	identifi	ed by its name	
	2a. The	e System checks the name of the option specified	
		2b. The	e System returns the value of the option specified
Exception sequence		2a1. Tl	ne option name is unknown

2.2.7 U1.3.3 - Change password

Title	U1.3.3 - Change password
Summary	The user wants to change his/her password
Actors	User
Precondition	
Postcondition	- The password is changed
Base sequence	1. The user sends a request containing his/her old password and the new password 2. The System checks the login and the old password of the user (the user si authenticated) and it registers the new user's password 3. The System returns an acknowledgment to the user
Branch sequence	
Exception sequence	1a. Unknwon user

2.2.8 U1.3.4 - Display session command history

Title	U1.3.4 - Display session command history
Summary	The user displays all the commands sent during one session
Actors	User
Precondition	
Postcondition	

	1. The user sends a request to list all commands sent during the session identified by the session key registered in the user's environment
	2. The System returns the list of all commands issued by
Base sequence	the user during the session which key corresponds to the
	session key registered in the user's environment. Each
	command has exactly the same format and parameters as
	the original submission and can be resubmitted as-is to the
	System.
	1a. The user sends a request containing a session identifier
	to list all commands sent during the session identified by
Branch sequence	the session id
Branch sequence	2a. The System returns the list of all commands issued by
	the user during the session which id correspons to the
	provided id
Exception sequence	1a1. Invalid session key (unknown / belonging to another
	user, if the current user is not an administrator)
Exception sequence	1a2. Invalid session id (unknown / belonging to another
	user, if the current user is not an administrator)

2.2.9 U1.3.5 - Display sessions log

Title		U1.3.5 - Display sessions log
Summary		The user displays his/her sessions (active or closed)
Actors		User
Precondition		
Postcondition		
Base sequence		1. The user sends a request to list all his/her sessions (active and/or closed) that have an open timestamp within an interval provided by the user (start and finish date) 2. The System returns all (or only active, or only closed) sessions of the user matching the search criteria with the following information for each session: id, opening date, client host name, closure policy (timeout or disconnect), time before automatic closure (if applicable) and period using start and finish date
Branch sequence		
Exception sequence		

2.2.10 U1.4 - Execute asynchronous user request

Title	U1.4 - Execute asynchronous user request
Summary	The user submits an asynchronous request to the system
Actors	User
Precondition	- The user is connected on the client System
	- The user has an open session on the client System
Postcondition	- The request is completed
	- A request log is created
	1. The user sends the request to the system
	2. The System returns an acknowledgment to the user
Base sequence	3. The System runs the request in background
	4. When the request is completed, the system updates the
	status of the request
Branch sequence	

Exception sequence	1.a Invalid session (bad session certificate or session
	unavailable)
	1.b Invalid request
	1.c Permission denied
	1.d Ressource not available
	1.e VISHNU System crashed
Extension of	U1 - Session with manual closure
	U2 - Session with automatic closure on timeout
	U3 - Session with automatic closure on disconnect

2.2.11 U1.5 - Reconnect to session

Title		U1.5 - Reconnect to session
Summary		The user wants to use a session in which he/she was
		disconnected previously without closing it
Actors		User
		- The user is connected on a client host in which VISHNU
Precondition		is installed and that can be connected to the VISHNU
		infrastructure
Postcondition		- A session is active
1 osteonation		- The user's environment contains a session key
		1. User provides its login, password and the identifier of
		the session (in fact, for each session, an identifier is
Base sequence		assigned) to the System
Base sequence		2. The System validates the user's login, password and the
		identifier of the session
		3. The System provides the chosen session key to the user
		1a. If the user is already within an active session then go to
Branch sequence		step 3 directly. The current session will be automatically
Branch sequence		closed according to the UC U2 or U3 depending on the
		close policy for that session.
		cf U1.1 (Open session)
		2a. The identifier of the session does not exist
Exception sequence		2b. The identifier relates to a session belonging to another
		user
		2c. The identifier is for a session closed
Extension of		U1 - Session with manual closure
		U2 - Session with automatic closure on timeout
		U3 - Session with automatic closure on disconnect

2.2.12 U2 - Session with automatic closure on timeout

Title	U2 - Session with automatic closure on timeout
Cummony	The user opens a new session that will be closed by the
Summary	System after the expiration of the inactivity delay
Actors	User
	- VISHNU is installed and running on the client system
	- The client system can be connected to VISHNU
Precondition	- The option SESSION_CLOSE_POLICY is
	CLOSE_ON_TIMEOUT (either user option is defined or
	this is the default policy)
	- A session log has been created
Postcondition	- The session is closed
	- All user requests submitted during the session are
	completed

	1. U1.1 Open session
Base sequence	2. The System is ready to process user commands
	3. After inactivity delay has expired: U2.1 Close session
	auto
	2a. U1.3 Execute synchronous user request
	2b. U1.4 Execute asynchronous user request
	2c. U1.5 Reconnect to session
Branch sequence	2d. If the user disconnects from the client terminal or the
	client system crashes or is shutdown, the session remains
	open and all asynchronous commands that were not
	completed are kept running
Exception sequence	see U1
	U1.5 - Reconnect to session
Extensions	U1.4 - Execute asynchronous user request
	U1.3 - Execute synchronous user request

2.2.13 U2.1 - Close session auto

Title	U2.1 - Close session auto
Summary	The session is closed by the system
Actors	
	- The user is connected on the client system
Precondition	- The user has an open session on the client system
Frecondition	either the inactivity timeout for the session has expired or
	the user disconnected from its shell session
Postcondition	- The session is closed
Postcolidition	- The session close event is stored in the system's log
	1. The system checks if the user has got no running
Base sequence	commands (file transfers or tasks)
	2. The system registers session closure
	1a. If the user has got some running commands, the system
Branch sequence	does not close the session and reset the inactivity timeout.
	After this delay is expired, back to step 1.
Exception sequence	
Notes	This use case defines behaviour(s) that is/are not defined in
110105	the project initial requirements.

2.2.14 U3 - Session with automatic closure on disconnect

Title	U3 - Session with automatic closure on disconnect
S	The user opens a new session that will be closed by the
Summary	system after the user disconnects from the client terminal
Actors	User
	- VISHNU is installed and running on the client system
	- The client system can be connected to VISHNU
Precondition	- The option SESSION_CLOSE_POLICY is
	CLOSE_ON_DISCONNECT (either user option is defined
	or this is the default policy)
	- A session log has been created
Postcondition	- The session state is closed
	- All user requests submitted during the session are
	complete

	1. U1.1 Open session
D	2. System is ready to process user commands
	3. The user disconnects from the terminal (either by typing
Base sequence	an exit command, by closing the window, or by remote
	disconnection)
	4. U2.1 Close session auto
	2a. U1.4 Execute synchronous user request
Branch sequence	2b. U1.5 Execute asynchronous user request
	3a. if the client system crashes or is shutdown, go to step 4
Exception sequence	see U1
	U1.3 - Execute synchronous user request
Extensions	U1.5 - Reconnect to session
	U1.4 - Execute asynchronous user request

2.2.15 U4 - Create new local user config

Title		U4 - Create new local user config
1100		The user creates a new local user configuration for a given
Summary		user on a given machine
A . 4		
Actors		User
		- The user has an account on VISHNU
Precondition		- The user has no local user configuration defined for the
		machine
		- Local user config is registered
Postcondition		- An email is sent to the user with a message containing an
		SSH public key
		1. The user provides local user configuration information
		for a given machine
		2. The System checks the user login and the machine Id
		3. The System generates an ssh private/public key pair
Base sequence		4. The System sends an email to the user containing the
1		public key and asking the user to add this key to the
		authorized_keys on the machine
		5. The user updates his/her authorized_keys file on the
		machine by adding the public key
Branch sequence		machine by adding the public key
Branen sequence		2a. Unknown login
Exception sequence		2b. Unknown machine
		4a. Invalid email address
Notes		This use case defines behaviour(s) that is/are not defined in
		the project initial requirements.

2.2.16 U4.1 - Update local user config

Title	U4.1 - Update local user config
Summary	The user updates his/her local user configuration for a
	given machine
Actors	User
	- The user has an account on VISHNU
Precondition	- The user has a local user configuration defined for the
	machine
Postcondition	- local user configuration is updated

Base sequence	 The user provides the login and the identifier of the machine used by his/her local configuration and information to be updated The System checks the the local user configuration (login defined for the given machine) The System updates the local user configuration information The System returns an acknowledgment to the user
Branch sequence	1. The dystein retains an acknowledgment to the ager
Exception sequence	2a. Unknown login for the given machine 2b. Unknown machine for the given login

2.2.17 U4.2 - Delete local user config

Title	U4.2 - Delete local user config
Summary	The user deletes his/her local user configuration on a given
	machine
Actors	User
	- The local user configuration exists for the given machine
Precondition	- There is no job or file transfer running on the given
	machine
Destar d'élèce	 - The local user configuration for the given machine is
Postcondition	deleted
	1. The user provides the identifier machine of the local user
	configuration and his/her login
	2. The System checks the identifier of the machine for the
Base sequence	given user
	3. The System deletes the local user configuration
	identified
	4. The System returns an acknowledgment to the user
Branch sequence	
Exception sequence	2a. Unknown login for the given machine
	2b. Unknown machine for the given login

2.2.18 U4.3 - Display local user configs

Title	U4.3 - Display local user configs
Summary	The user displays all of his/her local configurations
Actors	User
Precondition	
Postcondition	
	1. The user sends a request to list all his/her local
Base sequence	configurations
	2. The System returns all local configurations
	1a. The user sends a request containing the identifier of a
Branch sequence	machine for listing a specific local user configurations on a
	specific machine
Exception sequence	1a1. Unknown machine

2.2.19 UA1 - Create new user account

Title	UA1 - Create new user account
Summary	The administrator creates a new user account in the System (database)

Actors	Admin
Precondition	- The user does not have an account on VISHNU
	- The user account is created in an active state
Postcondition	- The account's password must be changed at the first
	connection
	1. The administrator provides the new user's last name,
	first name, email address and specifies whether the user has
	standard or admin rights
	2. The System creates the new user account and initializes
Paga gaguanga	the password with a randomly-generated string (temporary
Base sequence	password)
	3. The System sends an email to the user containing the
	temporary password
	4. The System returns an acknowledgment to the
	administrator
Branch sequence	
Exception sequence	2a. Login already used by another active user
Exception sequence	3a. Invalid email address
Notes	This use case defines behaviour(s) that is/are not defined in
INOLES	the project initial requirements.

2.2.20 UA1.1 - Update user account

Title	UA1.1 - Update user account
Summary	The administrator updates the user account (database)
Actors	Admin
Precondition	- The user has an account on VISHNU
Postcondition	- The user account is updated
	1. The administrator provides the user's information
	changes
Base sequence	2. The System updates user account (database)
	3. The System returns an acknowledgment to the
	administrator
Branch sequence	
	1.a Invalid login or login unknown
Exception sequence	1.b The user information set are invalid
	1.c The user information set are not consistent with the
	System

2.2.21 UA1.2 - Delete user account

Title	UA1.2 - Delete user account
Summary	The administrator deletes a user account
Actors	Admin
Precondition	- The user has an account on VISHNU
	- There is no job or file transfer running for the user
	- The user account is no longer in the System
Postcondition	- System does not contain any information related to the
	user
	1. The administrator provides a user's login
	2. The System deletes the user account along with all the
Base sequence	information (configuration, history) related to it.
	3. The System returns an acknowledgment to the
	administrator

Branch sequence	
Exception sequence	1a. Invalid login (unknown or inactive)

2.2.22 UA2 - Reset user password

Title	UA2 - Reset user password
Summary	The administrator resets a user password
Actors	Admin
Precondition	
Postcondition	- The password of the user is temporary and must be changed at the first connection by the user
Base sequence	The administrator provides a user's login The System resets the user's password using a randomly-generated string The System sends an email to the user containing the new temporary password The System returns an acknowledgment to the administrator
Branch sequence	
Exception sequence	1a. Invalid login (unknown or inactive) 3a. Invalid email address
Notes	If the user has one or several active sessions when Admin requests the password reset then the sessions are not affected. Only new sessions will require the new password for authentification.

2.2.23 UA3 - Save configuration

Title	UA3 - Save configuration
Summary	The administrator saves the configuration of the system
Actors	Admin
Precondition	
Postcondition	- The configuration is saved on a file
Postcolidition	- A log information is created
	1. The administrator requests to save the configuration in a
	file
Base sequence	2. The System creates a configuration file containing: the
	list of users, the list of local users configs and the list of
	machines according to the local users configs
Branch sequence	
Everation sequence	2a. File creation problems
Exception sequence	2b. VISHNU System crashed

2.2.24 UA4 - Restore configuration

Title	UA4 - Restore configuration
Summary	The administrator restores a saved configuration
Actors	Admin
	- All users are disconnected from VISHNU
Precondition	- The configuration file was saved using the "save
	configuration" feature.

	- The System is operational on all the machines that are
Postcondition	both properly configured in the saved configuration and
	where the VISHNU processes are running.
	1. The administrator opens a session as the Root user
	2. The administrator checks that there is no other
Daga saguana	user/admin connected to VISHNU
Base sequence	3. The administrator loads the configuration file
	4. The System replaces the current configuration with the
	loaded configuration.
Branch sequence	
	1a. If the Root user already has an open session, the
	System cannot open a second session with the Root user
Exception sequence	3a. If the configuration file cannot be loaded, the System
Exception sequence	provides an error message. The System configuration is
	reset to a basic configuration with only the Root user
	configured.
	To avoid failure during this critical operation, the reasons
	to go for exception 3a should be reduced as much as
Notes	possible. Therefore inconsistencies between the saved
	configuration and the real infrastructure will not be
	considered as blocking for this operation.

2.2.25 UA5.1 - Display sessions

Title	UA5.1 - Display sessions
Summary	The administrator displays all past and present sessions stored in the database.
Actors	Admin
Precondition	
Postcondition	
Base sequence	 The administrator sends a request to list all sessions (active and/or closed) that have an open timestamp within an interval provided by the user (start and finish date) The System returns the list of sessions that match the search criteria and provides detailed information about these sessions (user id, open and close timestamp, client machine id)
Branch sequence	
Exception sequence	

2.2.26 **UA5.2 - Display users**

Title	UA5.2 - Display users
Summary	The administrator displays the description of all users
	registered in the database
Actors	Admin
Precondition	
Postcondition	
	The administrator sends a request to list all users
Pasa saguanga	2. The System returns all users with the following
Base sequence	information for each user: id, firstname, lasname, login,
	status, email and password state.
Branch sequence	1a. The administrator sends a request containing the login
	of a specific user to list information about him/her.
Exception sequence	1a1. The login is unknonwn

2.2.27 UA5.3 - Display local users configs

Title		UA5.3 - Display local users configs
Summary		The administrator displays the local user configurations for
Summary		all users registered in the database
Actors		Admin
Precondition		
Postcondition		
		1. The administrator sends a request to list all local users
Base sequence		configurations
Base sequence		2. The System returns all the local users configs for all
		users
		1a. The administrator sends a request containing the
		identifier of a machine for listing all local users
Propoh soguence		configurations on a specific machine
Branch sequence		1b. The administrator sends a request containing the login
		of one user for listing all local users configurations of a
		specific user
Exception sequence		1a1. unknonwn machine
		1b1. unknonwn login

2.2.28 UA6.1 Add a machine

Title		UA6.1 Add a machine
Summary		The administrator registers a new machine in VISHNU
Actors		Admin
Precondition		
Postcondition		A new machine is added in VISHNU System
		1. The administrator adds a new machine on VISHNU by
		giving:
		- The machine name
		- The machine state (private or accessible to users)
Base sequence		- The public IP adress
-		- A structure describing the machine state
		- A structure describing the network
		2. The machine is added on VISHNU and the System
		returns the machine ID.
Branch sequence		
Expansion aggrees	1a. The machine name already exists	
Exception sequence		1b. A machine with the same public adress already exists

2.2.29 UA6.2 Remove a machine

Title	UA6.2 Remove a machine
Summary	The administrator unsubscribed a machine
Actors	Admin
Precondition	- The machine is registered in the System
Postcondition	The Machine is unsubscribed
Base sequence	The administrator removes a machine from VISHNU by giving the machine ID The System returns an acknowledgment to the administrator
Branch sequence	
Exception sequence	1a. machine unknown

2.2.30 UA6.3 Display machines

Title	UA6.3 Display machines
Cummony	The administrator displays the machines registered in the
Summary	database
Actors	Admin
Precondition	
Postcondition	
	1. The administrator sends a request to list all machines in
Base sequence	the database
	2. The System returns all machines in the database
	1a. The administrator sends a request containing the
Pronch coguence	identifier of a machine to list a specific machine
Branch sequence	1b. The administrator sends a request containing the login
	of a user to list the machine used by this user
Evacation caguance	1a1. The machine is unknown
Exception sequence	1b1. The login is unknown

2.2.31 UA6.4 Update machines

UA6.4 Update machines
The administrator updates a machine description in the
database
Admin
The database has one more description for the machine or
the existing one has been replaced
1. The administrator sends a request to add a machine
description of a machine, giving the id of the machine, its
description and the language the description is in.
2. The System updates the database adding the machine
description
2.a The machine already has a description in this language,
the description is replaced by the new one
1a1. The machine is unknown

2.2.32 UA7 - Configure default option value

Title	UA7 - Configure default option value
Summary	The administrator configures the default value of an option
Actors	Admin
Precondition	
Postcondition	The default value of the option is configured
	1. The administrator sends a request for modifying the
	value of an option to the System
Base sequence	2. The System checks the option name and registers the
	new default value for the option
	3. System returns an acknowledgment to the administrator
Branch sequence	
	1a. VISHNU infrastructure is unreachable or unavailable
Exception sequence	2a. Invalid option name
	2b. Invalid option value

2.3 Data dictionary

- CLOSE ON DISCONNECT: CLOSE ON DISCONNECT is a value which means that the only one way for closing the session is when the user closes her/his terminal
- CLOSE ON TIMEOUT: CLOSE ON TIMEOUT is a value which means that the way for closing a session is after a session inactivity delay. This value is given by the client or registered by default by the administrator
- Client System: Client System or Client Host is a program which uses VISHNU API commands and that can be connected to VISHNU Infrastructure
- Configuration: The configuration contains all information about the users and machines registered in the database. It does not contain chronological information about the users or the infrastructure (logs, metrics values)
- Local user config: The local user configuration is the description in the database of a user account on a specific machine (login, ssh key path, home directory) for a given VISHNU user
- Manual closure: The Manual closure means that the user uses the API command for closing the session
- Option: The option is a parameter of the user account that is not mandatory. Default value for each option is defined by the administrator. This features can be used by all VISHNU modules (not only UMS).
- Password state: Records the current state of the password of a user: either 'temporary' if the password must be changed next time the user connects to the System, or 'valid' if the password is in a normal state.
- Root user: Special user that is pre-configured in the VISHNU system and that has administrator privileges. This user cannot be deleted from the system.
- SESSION_CLOSE_POLICY: SESSION_CLOSE_POLICY is an option which represents the way to close the session (on timeout or on disconnect)
- **Session**: A session is the context in which VISHNU commands are executed (ex: job submission, file transfers). It is created following authentification of a user and lasts until it is closed either manually or automatically.
- Session Key: The session key is a crypted string generated by the System for a session. It is registered in an environment variable in order to avoid systematic authentification
- Session identifier: The session identifier (or session id) is an identifier of a session easy to manipulate by a user compare to the session key
- The inactivity delay: The inactivity delay is the delay in which no api commands are lauched within a session
- User account: The user account is the description in the database of a VISHNU user

Chapter 3

Use cases for Tasks Management System (TMS)

3.1 Use case diagrams

3.1.1 UC TMS Overview




Figure 3.1: UC TMS Overview

3.2 Use case descriptions

3.2.1 T1 - Asynchronous command on a machine

Title	T1 - Asynchronous command on a machine
Summary	User starts an asynchronous command on a given machine
Actors	User
Precondition	- User has an active open session
	- The command is in active state until completed
Postcondition	- The system log has been updated and contains the request
	parameters
	1. User sends the request
	2. The System checks that the session key is valid
	3. The System checks that the machine id is valid and
	machine is available
Base sequence	4. If command parameters contain a file the System verifies
Buse sequence	that the file is available and readable
	5. The System processes the request
	6. The System returns information to the user
	6. The System records request information (time, user,
	machine, request parameters) in the system log
Branch sequence	5a. T1.1
Branch sequence	5b. T1.2
	1a. The TMS server is unavailable
	- The system returns an error message that informs the user.
	2a. The session key is invalid
Exception sequence	- The system returns an error message that informs the user.
	3a. The name of the given machine is unknown
	-The system returns an error message that informs the user.
	4a. The path to a file parameter is invalid
	- The system returns an error message that informs user.
Extensions	T1.1 - Submit a job
LACHSIONS	T1.2 - Get job outputs (asynchronous)

3.2.2 T1.1 - Submit a job

Title	T1.1 - Submit a job
Summary	User submits a job on a given machine
Actors	User
Precondition	
Postcondition	- The job is submitted on the specified machine - The job state and id are recorded on the system's log - The job id is sent to the user
Base sequence	The System checks that request parameters contain: job script path job options The TMS server on the given machine is contacted The job is submitted by the TMS server to the batch scheduler The id of the submitted job is returned to the user
Branch sequence	
Exception sequence	1a. Invalid options or script4a. The batch scheduler server is unavailable4b. The batch scheduler server rejects the request

Extension of	T1 - Asynchronous command on a machine	
--------------	--	--

3.2.3 T1.2 - Get job outputs (asynchronous)

Title		T1.2 - Get job outputs (asynchronous)
Summary		Output files of a user's jobs on a given machine are
		downloaded when any job is completed
Actors		User
Precondition		
		- All the jobs submitted by the User on the machine are
Postcondition		completed
rostcondition		- All the jobs submitted by the User on the machine are
		removed from the Batch Scheduler's internal database.
		1. The User sends the request containing the machine id
		2. The System registers the request
		3. The System checks the running jobs submitted by the
		User on the machine
		4. The System sends the job outputs for all completed jobs
Daga gaguanaa		to the client host
Base sequence		5. If the number of jobs submitted by the User on the
		machine with a waiting, queued or running status is
		positive, the System waits during a period defined by the
		administrator. If not, go to step 7
		6. Go back to step 3
		7. The User request is completed
Branch sequence		
Exception sequence		2a The TMS server is unavailable
		2b The underlying batch scheduler is unavailable
Extension of		T1 - Asynchronous command on a machine
Notes		This use case defines behaviour(s) that is/are not defined in
		the
		project initial requirements.

3.2.4 T2 - Synchronous command on a machine

Title	T2 - Synchronous command on a machine
Summary	User executes a synchronous command on a given machine
Actors	User
Precondition	- User has an active open session
	- Request is in completed state
Postcondition	- The system log has been updated and contains the request
	parameters
	1. The User sends the request with parameters including
	session key and machine id
	2. The System checks that the session key is valid
	3. The System checks that the machine id is valid and
	machine is available
Base sequence	4. If command parameters contain a file the System verifies
Dase sequence	that the file is available and readable
	5. The System processes the request
	6. The System returns information containing the results of
	the request
	7. The System records request information (time, user,
	machine, request parameters) in the system log

Branch sequence		5a. T2.1
		5b. T2.2
		5c. T2.3
		5d. T2.4
1		5e. T2.5
		5f. TA1
		5g. TA2
		1a. The TMS server is unavailable
		- The system returns an error message that informs the user.
		2a. The session key is not valid
		- The system returns an error message that informs the user.
Expension sequence		3a. The name of the given machine is unknown
Exception sequence		
		-The system returns an error message that informs the user.
		4a. The path to a file parameter is invalid
		- The system returns an error message that informs user.
		- The user revises the path
		T2.1 - Get job information
		T2.2 - Cancel a job
		T2.3 - List job queues
Extensions		T2.4 - List jobs
		T2.5 - Get jobs progression
		T2.6 - Get job outputs (synchronous)
		TA1 - Set machine refresh period
		TA2 - Set machine environment
		1712 Set machine chynolinellt

3.2.5 T2.1 - Get job information

Title	T2.1 - Get job information
Summary	User gets information about a job on a given machine
Actors	User
Precondition	
Postcondition	
	1. The Systems checks the job id
	2. The TMS server on the given machine is contacted
Base sequence	3. The TMS server asks job information to the batch
	scheduler server
	4. The User receives job information
Branch sequence	
	1a. The job id is invalid
Exception sequence	3a. The batch scheduler server is unavailable
	3b. The batch scheduler server rejects the request
Extension of	T2 - Synchronous command on a machine

3.2.6 T2.2 - Cancel a job

Title	T2.2 - Cancel a job
Summary	The user cancels a job on a given machine
Actors	User
Precondition	
Postcondition	- The job is canceled on the specified machine - The job state and id are removed to the system's log

Base sequence	 The System checks the job id If the User has no admin privilege, the System checks that the User is the submitter of the job The System cancels the job The System returns a confirmation to the User
Branch sequence	
Exception sequence	1a. The job id is invalid - The System returns an error message 2a. The User is not the submitter of the job - The System returns an error message 3a. The batch scheduler server is unavailable - The System returns an error message 3b. The batch scheduler server rejects the request - The System returns an error message
Extension of	T2 - Synchronous command on a machine

3.2.7 T2.3 - List job queues

Title		T2.3 - List job queues
Summary		User lists all queues or classes of a specific batch scheduler
Actors		User
Precondition	-	
Postcondition		
		1. The User sends the request with parameters that include
		the machine id
Paga gaguanga		2. The System obtains queues or classes information from
Base sequence		the batch scheduler server running on the machine
		identified by the machine id
		3. The System returns the list of all queues to the user
Branch sequence		
Exception sequence		2a. The batch scheduler server is unavailable
		2b. The batch scheduler server rejects the request
Extension of		T2 - Synchronous command on a machine

3.2.8 T2.4 - List jobs

Title	T2.4 - List jobs
Summary	User lists all jobs submitted on a given machine matching
	some search criteria
Actors	User
Precondition	
Postcondition	
	1. The User sends the request containing the machine id
	and the following optional search criteria: job id, number
	of CPUs required for the job, date of submission (from/to),
	job submitter, status, priority, queue, outputPath and
Base sequence	errorPath.
Base sequence	2. The System obtains jobs information from the batch
	scheduler server (depends on the underlying batch
	scheduler software)
	3. The System returns jobs information that match the
	search criteria to the User
Branch sequence	

Exception sequence	2a. The batch scheduler server is unavailable2b. The batch scheduler server rejects the request
Extension of	T2 - Synchronous command on a machine

3.2.9 T2.5 - Get jobs progression

Title	T2.5 - Get jobs progression
Summary	User gets jobs progression (execution percent) status on a machine
Actors	User
Precondition	
Postcondition	
Base sequence	1. The User sends the request containing the machine id 2. The System computes the job progression for all jobs submitted by the User running on the machine (job progression = 100 * (current_time - run_time) / job_walltime) 3. The System sends the results to the User
Branch sequence	1a. The User provides a job id in the request (optional parameter) 2a. The System computes the job progression for the job corresponding to the job id
Exception sequence	2b. The TMS server is unavailable - The system returns an error message that informs the user. 2c. The provided job id is unknown on the machine - The system returns an error message that informs the user.
Extension of	T2 - Synchronous command on a machine
Notes	This use case defines behaviour(s) that is/are not defined in the project initial requirements.

3.2.10 T2.6 - Get job outputs (synchronous)

Title	T2.6 - Get job outputs (synchronous)
Summary	Output files of a given job are downloaded on the client
	host
Actors	User
Precondition	
Postcondition	- The job is removed from the Batch Scheduler's internal
	database.
	1. The User sends the request containing the job id
	2. The System checks the job status
Base sequence	3. The System downloads the job results if the job is
	completed
	4. The System returns the path for each downloaded file
Branch sequence	
	2a. The TMS server is unavailable
Exception sequence	2b. The batch scheduler is unavailable
Exception sequence	2c. The job status is not 'completed'
	- The System returns a message that informs the user
Extension of	T2 - Synchronous command on a machine
	This use case defines behaviour(s) that is/are not defined in
Notes	the
	project initial requirements.

3.2.11 TA1 - Set machine refresh period

Title	TA1 - Set machine refresh period
C	The admin sets the refresh period of output and error file
Summary	content
Actors	Admin
Precondition	
Postcondition	- The refresh period value is stored by the system
	1. System saves the refresh period for the given machine.
Base sequence	2. System applies the refresh period to all current jobs and
	f <mark>uture re</mark> quests
Branch sequence	
	1a. Refresh period value is too short (minimum value : see
Exception sequence	technical requirements)
	- System returns an error message
Extension of	T2 - Synchronous command on a machine
	This use case defines behaviour(s) that is/are not defined in
Notes	the
	project initial requirements.

3.2.12 TA2 - Set machine environment

Title	TA2 - Set machine environment
Summary	The admin sets an environment variable on a given machine
Actors	Admin
Precondition	
Postcondition	- Environment variable is set on the machine
Base sequence	1. The User sends the request containing the machine id
	and a string containing the environment variable
	assignments (semi-column separated list of assignments
	<var_name>=<var_value>)</var_value></var_name>
	2. The System saves the environment variable for the given
	machine.
	3. The System applies the environment variable to all
	current jobs and future requests
Branch sequence	
Exception sequence	
Extension of	T2 - Synchronous command on a machine

3.2.13 TA3 - Launch TMS Server

Title	TA3 - Launch TMS Server
Summary	The administrator launches the VISHNU TMS server on a
	given machine
Actors	Admin
Precondition	- The Vishnu server software (TMS Module and
	dependencies) is installed on the machine
	- The machine is configured in the Vishnu system database
	- The batch scheduler processes are up and running on the
	same machine
	- The network connection between the machine and the
	Vishnu database server is up and running
Postcondition	- The TMS server is up and running
	- A server log has been created

	1. The Admin connects to the machine as vishnu user
	2. The Admin updates the Vishnu configuration if
	necessary (database server hostname and credentials,
	SysferaDS configuration, Batch scheduler configuration)
	3. The Admin launches the Vishnu TMS Server executable
	4. The System checks the connections to its peers within
P	the Vishnu platform
Base sequence	5. The System retrieves the list of active jobs (not
	completed jobs) that were launched on the same machine
	6. The System checks that all the active jobs (from
	previous step) are still running on the batch scheduler, and
	eventually updates the job status (for ex. from waiting to
	running, or from running to finished)
	7. The System returns a status message to the administrator
Branch sequence	
-	4a. A connection to a Vishnu peer is down. System returns
Expansion cognones	an error message and stops
Exception sequence	6a. The batch scheduler does not recognize some job ids.
	In this case the System updates the job status to completed.

3.2.14 TA4 - Stop TMS Server

Title	TA4 - Stop TMS Server
Summary	The administrator stops the VISHNU TMS server on a
	given machine
Actors	Admin
Precondition	- The TMS Server is up and running on the given machine
Postcondition	- The TMS Server is down
Base sequence	1. The Admin sends a request to stop the TMS Server and
	provides the machine id
	2. The System updates the status of all active user requests
	(non-completed jobs)
	3. The System stops all internal processes on the machine
	4. The System returns an information message to the
	Admin
Branch sequence	
Exception sequence	

3.3 Data dictionary

- Batch Scheduler: A batch scheduler is a distributed resource manager that enables to allocate at best the resources to the jobs on a machine according to user needs (the needs are specified by the user by batch directives (batch options) in file or command line).
- Job: A job is a sequence of instructions (included batch scheduler directives) written to be launched by a specified batch scheduler.
- Job id: A job id allows to identifie the job in the batch scheduler system.
- **JobPath**: A jobPath is the path to the file (script) containing the instructions (batch directives or job characteristics, job execution command) of the job.
- Queue ou Class: A queue or class associates the resource limits (CPU wallclock time, CPU memory) and execution priorities of the jobs.
- TMS: Task Management System.

Chapter 4

Use cases for Information Management System (IMS)

4.1 Use case diagrams

4.1.1 UC IMS Global functionalities

Global use case presenting all the IMS use case




Figure 4.1: UC IMS Global functionalities

4.1.2 UC IMS Consult

User consult use case




Figure 4.2: UC IMS Consult

4.1.3 UC IMS Replay

A user can replay its old commands of a session




Figure 4.3: UC IMS Replay

4.1.4 UC IMS Platform management

All the use case of the administrator concerning the platform management




Figure 4.4: UC IMS Platform management

4.1.5 UC IMS Stop_Restart

The administrator use cases concerning the stop and restart of the platform




Figure 4.5: UC IMS Stop_Restart

4.2 Use case descriptions

4.2.1 I1. Get the update frequency

Title	I1. Get the update frequency
Summary	The user gets how often the IMS database tables are
Summary	updated
Actors	User
Precondition	
Postcondition	
	1) The user calls the function to know how often the IMS
Base sequence	database tables are automatically updated
	2) The System returns the value in second
Branch sequence	
Exception sequence	2 -> There is a problem with the database, the system
Exception sequence	returns a DATABASE_ERROR

4.2.2 I2 Get metric data

Title	7	I2 Get metric data	
Summary		The user gets data concerning the evolution of a metrics on	
Summary		a machine	
Actors		User	
Precondition			
Postcondition			
		1) The user calls to get the metrics data on a machine	
		identified by a machine id, for a metric type, from start	
		time up to end time. The metrics are within {number of	
Base sequence		cpu, percentage of cpu used, total diskSpace, free	
_		diskSpace, total RAM, free RAM}	
		2) The System returns the results by groups (metric, value,	
		time).	
Branch sequence			
Exception sequence		1 -> The machine id is invalid, an	
		INVALID_PARAMETER error is returned	
		2 -> There is a problem with the database, the system	
		returns a DATABASE_ERROR	

4.2.3 I3. Export and replay commands

Title	I3. Export and replay commands
Summary	The user exports and replays a sequence of commands made during a session.
Actors	User
Precondition	
	All the System commands submitted during a session have
Postcondition	been re-executed keeping the same order they had when
	they were originally launched.

Base sequence	1a) The user calls to export the history, in shell format, of a session identified by an id.2a) The System provides a shell script containing all the commands of the session with the same parameters as provided initially by the user (including file paths,
	numbers, strings, options)
	3a) The user executes the shell script in a shell
Branch sequence	
	1 -> The session id is invalid, an INVALID_PARAMETER
Fti	exception is raised.
Exception sequence	3 -> A command in the execution fails, the error of the
	command is returned

4.2.4 I4. Get data on the infrastructure

Title	I4. Get data on the infrastructure
Summary	The user gets current System information about the machines
Actors	User
Precondition	
Postcondition	
Base sequence	 The user calls to get a current data about a machine identified by an ID. The data is within {use of cpu, number of cpu, total diskSpace, free diskSpace, total RAM, free RAM}. The System returns the value of the data. In the use of cpu case, the value is in percentage.
Branch sequence	
Exception sequence	The machine id is invalid, an INVALID_PARAMETER exception is raised

4.2.5 IA1. Get the running processes

Title	IA1. Get the running processes
Commence	The admin gets the list of the running Vishnu processes on
Summary	a machine
Actors	Admin
Precondition	
Postcondition	
	1) The admin calls to get the list of the processes on a
Base sequence	machine referenced by a machine id
	2) The System returns a list of Vishnu processes
Branch sequence	
Exception sequence	1 -> machineId is invalid, an INVALID_PARAMETER is
Exception sequence	return.

4.2.6 IA2. Define a system load threshold

Title	IA2. Define a system load threshold
Summary	The administrator defines a system load threshold for a
	machine
Actors	Admin
Precondition	

Postcondition	The system load threshold is added to the System database
	1a) The administrator calls to define the limit size of the
Base sequence	diskSpace to use with a machine id, a threshold value and
base sequence	an admin id (admin responsible for the threshold)
	2a) The System updates the database
	1b) The administrator calls to define the limit of RAM
	available to he user with a machine id, a threshold value
	and an admin id (admin responsible for the threshold)
	2b) The System updates the database
Branch sequence	
Branch sequence	1c) The administrator calls to define the number of
	processes threshold on a machine with a machine id, a
	treshold value and an admin id (admin responsible for the
	threshold)
	2c) The System updates the database
	1* -> The admin ID is invalid, the database is not updated
Exception sequence	and an INVALID_PARAMETER error is returned
Exception sequence	2* -> The modification of the database fails, a
	DATABASE_ERROR is returned.

4.2.7 IA2.1 Get a system load threshold

Title	IA2.1 Get a system load threshold
Summary	The admin wants to get the thresholds on a machine
Actors	Admin
Precondition	
Postcondition	
Base sequence	1) The admin calls to get the defined limit on a machine identified by an id. These thresholds are within {free diskSpace, free RAM, percentage of CPU used} 2) The System returns the value.
Branch sequence	
Exception sequence	1 -> The machine id is invalid, the user gets an INVALID_PARAMETER error returned 2 -> There is a problem with the database request, a DATABASE_ERROR is returned

4.2.8 IA3. Define the identifiers

Title	IA3. Define the identifiers
Summary	The administrator defines the format of the automatic
	identifiers for the System objects.
Actors	Admin
Precondition	
Postcondition	A new format will be used to create the new identifiers

		1) The administrator has a list of variables to define the identifiers shape. He has a method by kind of object (an object is either a user or a machine or a task or a file transfer). Available variables are: YEAR: the last two digits, (e.g. 10 for 2010) MONTH: Numerical value of the month (from 1 to 12)
		DAY: Day number, from 1 to 31 TYPE: The object kind
		SITE: The place for machine/users
Base sequence		NAME: Username or machine name
-		CPT: A counter automatically increased (each kind of
		object has its counter).
		2) He calls the function to redefine the format with some of
		the previous parameters in a string. A variable must be
		preceded by a '\$' symbol. For example,
		"\$TYPE\$DAY\$MONTH\$YEAR\$CPT"
		3) The System database is updated, the System does not
		check if the given format creates unique identifiers. If the
		same identifier is created, it will corrupt the database (the
		key will not be unique)
		2 -> An invalid variable is given, an
Branch sequence		INVALID_PARAMETER is returned and the old format is
1		still used
		3 -> The update fails, a DATABASE_ERROR is returned
Exception sequence		

4.2.9 IA4.1 Hard load shedding

TP'41 .	TAA I TI JI JI JI JI JI JI
Title	IA4.1 Hard load shedding
	Abruptly stops the processes running on a machine (the
Summary	waiting actions are cancelled and the running ones are
	stopped). The processes cannot be automatically restarted.
Actors	Admin
Precondition	Processes are running on the System
Postcondition	The whole machine is flushed and no job is running on it
	1) The admin launches the hard load shedding command
	on a machine identified by an id.
Base sequence	2) The System flushes all the waiting action.
	3) The System stops all the running processes on this
	machine. These processes cannot be restarted.
Branch sequence	
Exception sequence	1 -> The id of the machine is invalid, an
	INVALID_PARAMETER is returned

4.2.10 IA4.2 Soft load shedding

Title	IA4.2 Soft load shedding
Summary	The admin purges all the waiting actions and stops the
Summary	running ones. The stopped actions can be restarted later.
Actors	Admin
Precondition	Processes are running on the VISHNU system
Postcondition	No jobs are waiting to run or are running

	1) The admin calls the soft load shedding command on a					
Base sequence	machine identified by an id.					
	2) The System flushes the waiting jobs and stops the					
	running ones. They are stored and can be restarted later					
Branch sequence						
Exception sequence	1 -> The machine id is invalid, an					
	INVALID_PARAMETER error is returned					

4.2.11 IA5. Set system info

Title		IA5. Set system info				
		Updates the data in the system concerning a machine (e.g.,				
Summary		if the machine has some added memory diskSpace, some				
		added memory)				
Actors		Admin				
Precondition						
Postcondition		The description of the machine in the database is updated				
		1) An admin calls to update the data concerning a machine				
Base sequence		identified by an id giving a new diskSpace size or a new				
Base sequence		memory size.				
		2) The System updates the database				
Branch sequence						
		1 -> The machine id is invalid, an				
Exception sequence		INVALID_PARAMETER error is returned				
		2 -> There is an error with the database, a				
		DATABASE_ERROR error is returned				

4.2.12 IA6. Set the update frequency

Title	IA6. Set the update frequency		
Summary	The administrator sets the update frequency		
Actors	Admin		
Precondition			
Postcondition	The System updates the IMS database at the new frequency		
	1) The administrator calls to set the update frequency in		
Base sequence	seconds		
	2) The System updates its database update frequency value		
Branch sequence			
Exception sequence	The database is is not reachable. A DATABASE_ERROR		
Exception sequence	is returned.		

4.2.13 IA7. Notification of limit overflow

Title	IA7. Notification of limit overflow
Summary	The admin is notified a limit overflow
Actors	Admin
Precondition	A machine on the System has a limit overflow
Postcondition	
	1) The System gets the email adress of the admin to contact, using a config file to send the e-mail
Base sequence	2) The System sends a mail to the admin concerning the overflow. The mail contains the name of the machine and the concerned threshold.

Branch sequence	
Exception sequence	1 -> The system fails getting the admin e-mail, a
	DATABASE_ERROR error is returned
	2 -> Sending the mail fails, a MAIL_ERROR error is
	returned.

4.2.14 IA8. Restart the System

Title	7		IA8. Restart the System		
Summary		Restart all the servers, agents, and daemons of the System.			
		The running actions are restarted.			
Actors	Actors		Admin		
Precondition			The System platform needs to be restarted		
			The System is running with the same servers, agents and		
Postcondition			daemons as defined in the deployement file. The		
Postcolidition			interrupted actions that can be restarted are restarted from		
			the beginning.		
			1) An admin detects a problem		
			2) An admin calls to restart the System with a deployement		
			file		
Base sequence			3) The System saves the current actions		
			4) The System restarts components following the		
			deployement file guidance and restarts the stopped actions		
			from the beginning		
Branch sequence					
Execution sequence		4-> Fail to relaunch a component (server, daemon, agent),			
Exception sequence			an UNREACHABLE_COMPONENT error is returned.		

4.2.15 IA9. Restart

Title	IA9. Restart			
Summary	A component is restarted			
Actors	Admin			
Precondition	A component of the platform is down			
Postcondition	The component is up and running again			
Base sequence	1) An admin detects that a component has stopped for unknown reasons (a component = server, daemon, agent) 2) The admin calls the System to relaunch the component with its name, the machine to relaunch it and the configuration file to use 3) The System relauches the component			
Branch sequence				
Exception sequence	3-> Fail to restart the component, an UNREACHABLE_COMPONENT error is returned.			

4.2.16 U1.3 Execute synchronous request

Title	U1.3 Execute synchronous request
Summary The user submits a synchronous request to the Systhe UMS use case description (U1.3)	
Actors	User, Admin
Precondition	
Postcondition	

Base sequence					
Branch sequence					
Exception sequence					

4.3 Data dictionary

- Actions: A generic naming to design both jobs and file transfers.
- Agent: A component of the VISHNU hierarchy.
- CPU: Central Processing Unit.
- Daemon: Daemon running on the machines.
- **DiskSpace**: File system memory (not volatile).
- IMS: Information Management System.
- Infrastructure: Contains all the machines directly under the System supervision.
- Live measure: Measure regularly updated.
- Memory: RAM (Random Access Memory, volatile).
- **Objects**: An object is an abstraction of what can be manipulated by the System (user, machine, task, file transfer).
- **Process**: Process of the system.
- SeD: A component of the VISHNU hierarchy executing jobs for the clients.
- Task: Job submited via the TMS module.

Chapter 5

Use cases for File Management System (FMS)

5.1 Use case diagrams

5.1.1 UC FMS simple command use cases




Figure 5.1: UC FMS simple command use cases

5.1.2 UC FMS transfer command use cases




Figure 5.2: UC FMS transfer command use cases

5.2 Use case descriptions

5.2.1 F1- Execute simple command on a remote host

F1- Execute simple command on a remote host
This use case allows User to execute a command on a
remote host.
User
- User has an active open session.
- The command is performed succesfully and the potential
results are sent back to User.
- The log System has been updated and contains request
parameters.

Base sequence		 User enters the command by specifying the parameters, the session key and the involved host id. The System checks that the session key is valid. The System checks that the host id is valid and the machine is available. The System performs the command and send back the results to User. The System records request information (time, User, machine, request parameters). 			
Branch sequence					
Exception sequence		 1a. The given parameters are invalid for this command. 2a. The specified session key is invalid. 3a. The specified host is unknown. 3b. The specified host is unavailable. 4a. The command fails and an error message is displayed on the standard output of the client System. 			
Extensions		F1.CH2- Change group owner of files F1.CH1- Change access rights of files F1.CR2- Create new directories F1.DE2- Delete directories F1.DE1- Delete files F1.DI3- Display contents of files F1.DI4- Display Head of files F1.DI4- Display contents of directories F1.DI5- Get information about remote files F1.CR1- Create new files F1.DE1- Delete files			

5.2.2 F1.CH1- Change access rights of files

Title	F1.CH1- Change access rights of files
	This use case allows User to change access rights of a
Summary	given remote file. It is the equivalent of the "chmod" bash
	command.
Actors	User
Precondition	
Postcondition	The new access permissions of the specified file is set.
	1. User submits the change access rights command with the
Base sequence	file, the new access rights to set, the involved host.
	2. The System sets the new access rights to the file.
Branch sequence	
	1a. If there are missing parameters, a message that contains
	the way to use the command, an error message is returned.
	1b. If a file is unknown, an error message is displayed on
Exception sequence	the standard output of the client System.
Exception sequence	1c. If User does not have execute permission in a parent
	directory or if User is not the file owner or Admin, a
	permission denied message is displayed on the standard
	output of the client System
Extension of	F1- Execute simple command on a remote host

5.2.3 F1.CH2- Change group owner of files

Title	F1.CH2- Change group owner of files
	This use case allows User to change the group owner of a
Summary	named remote file. It is the equivalent of the "chgrp" bash
	command.
Actors	User
Precondition	
Postcondition	The new group owner of the specified file is set.
	1. User submits the change group owner command with the
Base sequence	file, the new group to set, the involved host.
	2. The System sets the new group owner to the file.
Branch sequence	
	1a. If there are missing parameters, a message that contains
	the way to use the command, is displayed on the standard
	output of the client System.
	1b. If a file is unknown, a message is printed out on the
Exception sequence	standard output of the client System.
	1c. If User does not have execute permission in a parent
	directory or if User is not the file owner or Admin, a
	permission denied message is displayed on the standard
	output of the client System.
Extension of	F1- Execute simple command on a remote host

5.2.4 F1.CR1- Create new files

Title		F1.CR1- Create new files
Summour:		This use case allows User to create new file in a given host.
Summary		It is the equivalent of the "touch" bash command.
Actors		User
Precondition		
Postcondition		The new file is created in the specified host and is owned
rostcondition		by User and his group.
		1. User submits the create file command with the path of
Base sequence		file to create, the involved host.
		2. The System creates the new file with the specified path.
Branch sequence		
		1a. If there are missing parameters, a message that contains
		the way to use the command, is displayed on the standard
		output of the client System.
Expontion acquence		1b. If a specified file already exists, a message is printed
Exception sequence		out on the standard output of the client System.
		1c. If User does not have execute or write permission in a
		parent directory, a message is also printed out on the
		standard output of the client System.
Extension of		F1- Execute simple command on a remote host

5.2.5 F1.CR2- Create new directories

Title	F1.CR2- Create new directories
Summary	This use case allows User to create a new directory in a named host. It is the equivalent of the "mkdir" bash command.
Actors	User
Precondition	

Postcondition	The new directory is created in the specified host and is owned by User and his group.
Base sequence	User submits the create directory command with the path of directory to create, the involved host. The System creates the new directory with the specified path.
Branch sequence	
Exception sequence	 1a. If there are missing parameters, a message that contains the way to use the command, is displayed on the standard output of the client System. 1b. If the a specified directory already exists, a message is printed out on the standard output of the client System. 1c. If User does not have read or write permission in a parent directory, a message is also printed on the standard output of the client System.
Extension of	F1- Execute simple command on a remote host

5.2.6 F1.DE1- Delete files

Title		F1.DE1- Delete files
Cummour		This use case allows User to remove a given remote file. It
Summary		is the equivalent of the "rm" bash command.
Actors		User
Precondition		_
Postcondition		The specified file is removed from the host.
	7 /	1. User submits the delete file command with the path of
Base sequence		the file to delete, the involved host.
		2. The System deletes the specified file from the host.
Branch sequence		
		1a. If there are missing parameters, a message that contains
		the way to use the command, is displayed on the standard
		output of the client System.
		1b. If the specified path is not a file or if the file is
Exception sequence		unknown, a message is printed out on the standard output
		of the client System.
		1c. If User does not have execute or write permission in the
		parent directory, a message is also printed out on the
		standard output of the client System.
Extension of		F1- Execute simple command on a remote host
		F1- Execute simple command on a remote host

5.2.7 F1.DE2- Delete directories

Title	F1.DE2- Delete directories
	This use case allows User to remove a given directory (and
Summary	its content) located on a remote host. It is the equivalent of
	the "rm -r" bash command.
Actors	User
Precondition	
Postcondition	The specified directory is removed from the given host.
	1. User submits the delete directory command with the
Base sequence	path of directory to delete, the involved host.
	2. The System deletes the specified directory from the host.
Branch sequence	

	1a. If there are missing parameters, a message that contains
	the way to use the command, is displayed on the standard
	output of the client System.
Enception	1b. If the specified path is not a directory or a directory is
	unknown, a message is printed on the standard output of
Exception sequence	the client System.
	1c. If User does not have execute or write permission in the
	parent directory, or if the specified directory contains a file
	which can not be removed, a permission denied message is
	also printed out on the standard output of the client System.
Extension of	F1- Execute simple command on a remote host

5.2.8 F1.DI1- Display Head of files

Title	F1.DI1- Display Head of files
	This command allows User to print the first few lines of a
Summary	given remote file. It is the equivalent of the "head" bash
	command.
Actors	User
Precondition	
Postcondition	The first lines of the specified file are printed out on the
rostcondition	standard output of the client System.
	1. User submits the display command with the path of the
	file
Base sequence	to display, the involved host.
	2. The System displays the first lines of the specified file on
	the standard output of the client System.
Branch sequence	
	1a. If there are missing parameters, a message that contains
	the way to use the command, is displayed on the standard
	output of the client System.
Exception sequence	1b. If the file is unknown, a message is printed out on the
	standard output of the client System.
	1c. If User does not have execute permission write in the
	parent directory or read permission on the file, a message is
	also printed out on the standard output of the client System.
Extension of	F1- Execute simple command on a remote host

5.2.9 F1.DI2- Display tail of files

Title	F1.DI2- Display tail of files
	This command allows User to print the last few lines of a
Summary	named remote file. It is the equivalent of the "tail" bash
	command.
Actors	User
Precondition	
Postcondition	The last lines of the specified file are printed out on the
	standard output of the client System.
Base sequence	1. User submits the display command with the path of the
	file to display, the involved host.
	2. The System displays the last lines of the specified file on
	the standard output of the client System.
Branch sequence	

	1a. If there are missing parameters, a message that contains
	the way to use the command, is displayed on the standard
	output of the client System.
	1b. If the file is unknown, a message is printed on the
Exception sequence	standard output of the client System.
	1.c If User does not have execute permission in the parent
	directory or read permission on the file, a permission
	denied message is also printed on the standard output of the
	client System.
Extension of	F1- Execute simple command on a remote host

5.2.10 F1.DI3- Display contents of files

Title		F1.DI3- Display contents of files
		This use case allows User to print the content of a given file
Summary		located on a remote host. It is the equivalent of the "cat"
		<mark>ba</mark> sh co <mark>mman</mark> d.
Actors		User
Precondition		
Destagndition		The named file is printed on the standard output of the
Postcondition		client System.
		1. User submits the display command with the path of the
Daga gaguanga		file to display, the involved host.
Base sequence		2. The System prints the specified file on the standard
		output of the client System.
Branch sequence		
		1a. If there are missing parameters, a message that contains
		the way to use the command, is displayed on the standard
		output of the client System.
Exception sequence		1b. If the file is unknown, a message is printed on the
		standard output of the client System.
		1c. If User does not have execute permission in the parent
		directory or read permission on the file, a message is also
		printed on the standard output of the client System.
Extension of		F1- Execute simple command on a remote host

5.2.11 F1.DI4- Display contents of directories

Title	F1.DI4- Display contents of directories
	This use case allows User to list the files contained in a
Summary	given directory located on a remote host. It is the
	equivalent of the "ls" bash command.
Actors	User
Precondition	
Postcondition	The content of the specified directory is printed out on the
1 OSCORDITION	standard output of the client System.
	1. User submits the display command with the path of the
Base sequence	directory to list, the involved host.
Base sequence	2. The System displays the content of the specified
	directory on the standard output of the client System.
	1a. If no directory is given, the content of current directory
	is displayed on the standard output of the client System.
Branch sequence	1b.If a file is given, some information about the file (like
	the access permissions, the owner, the size, etc) is printed
	out on the standard output of the client System.

	1a. If the directory is unknown, a message is printed out on
	the standard output of the client System.
Exception sequence	1b. If User does not have execute or read permission in the
	parent directory, a message is also printed out on the
	standard output of the client System.
Extension of	F1- Execute simple command on a remote host

5.2.12 F1.DI5- Get information about remote files

Title	F1.DI5- Get information about remote files
Title	This use case allows User to get information about a named
	remote file (the path, the owner, the group, the access
	permissions, the owner numeric identifier, the group
Summary	numeric identifier, the size, the last access time, the last
	modification time, the last inode change time). It is
	equivalent to "stat" bash command.
Actors	User
Precondition	
Postcondition	Some informations about the given file are printed out on
Tostcondition	the standard output of the client System.
	1. User submits the get information command with the file,
Base sequence	the involved host.
Buse sequence	2. The System prints out the information about the
	specified file on the standard output of the client System.
Branch sequence	
	1a. If there are missing parameters, a message that contains
	the way to use the command, is displayed on the standard
	output of the client System.
Exception sequence	1b. If the file is unknown, a message is printed out on the
Exception sequence	standard output of the client System.
	1.c If User does not have execute permission in the parent
	directory, a permission denied message is also printed out
	on the standard output of the client.
Extension of	F1- Execute simple command on a remote host

5.2.13 F2.CA1- Cancel files tranfers

Title	F2.CA1- Cancel files tranfers
	This use case allows User to cancel all asynchronous file
	transfers he submitted. He can optionally specify either
Summary	- a file transfer identifier to cancel that file transfer.
	- or a machine identifier to cancel all file transfer he
	submitted from that machine.
Actors	User
Precondition	User has at least an open active session.
	- All file transfer submitted by User are cancelled. If a
	search criteria is provided, only file transfer matching that
Postcondition	criteria are cancelled.
	- The log System has been updated and contains request
	parameters.

Base sequence	1. User submits a cancel file transfer command by specifying the session key. with optionally a search criteria (either a file transfer id, or a machine id). 2. The System cancels all file transfers he submitted. If a search criteria is provided, the System cancels only the file
2	transfer matching that criteria.
Branch sequence	
Exception sequence	1a. If there are missing parameters, a message that contains the way to use the command, is displayed on the standard output of the client System. 1b. If the given session key is invalid, a message is printed out on the standard output of the client System. 1c. If a tranfer id is invalid or if User did not submit a named file tranfer, a message is printed out on the standard output of the client System. 1d. If the specified host id is invalid or if no file tranfer was submitted by User from that host, a message is printed out on the standard output of the client System. 1e. If the command fails, a message is printed on the standard output of the client System.

5.2.14 F2.CA2- Cancel all users file transfers

Title	F2.CA2- Cancel all users file transfers
	This use case allows Admin to cancel all current
	asynchronous file transfer submitted. He can an optional
	search criteria among:
Summary	- a host identifier to cancel all file transfer submitted from
	that host
	- or an user identifier to cancel all file transfer submitted by
	that user.
Actors	Admin, Admin
Precondition	Admin has at least an open active session.
	- All file transfer submitted are cancelled. If a search
	criteria is provided, only the file transfer matching that
Postcondition	cr <mark>iteria</mark> are cancelled.
	- The log System has been updated and contains request
	parameters.
	1. Admin submits the cancel file transfer command by
	specifying a session key, with optionally a search criteria
Base sequence	(either a host id, or a user id).
	2. The System cancels all file transfers submitted. If a
	search criteria is provided, The System cancels only the file
	transfer matching that criteria.
Branch sequence	

	1a. If there are missing parameters, a message that contains
	the way to use the command, is displayed on the standard
	output of the client System.
	1b. If the specified session key is invalid, a message is
	printed out on the standard output of the client System.
	1c. If the specified host id is invalid or there is no file
Exception sequence	tranfer submitted from that host, a message is printed out
	on the standard output of the client System.
	1d. If the specified user id is invalid or there is no file
	tranfer submitted by that user, a message is printed out on
	the standard output of the client System.
	1e. If the command fails, a message is printed on the
	standard output of the client System.

5.2.15 F2.CP1- Execute a synchronous copy of files

Title	F2.CP1- Execute a synchronous copy of files
	This use case allows User to copy a file (or directory)
	between two hosts.
	It is the equivalent of the "cp" bash command. The four
Cummony	cases of transfer are covered by this use case:
Summary	- inside the same host which can be local or remote,
	- from local host to remote host,
	- from remote host to local host,
	- from remote host to another remote host.
Actors	User
Precondition	User has an open active VISHNU session on the client.
	- The file transfer is fully accomplished and a copy of the
Postcondition	source file (or directory) is now on the destination host.
1 ostcondition	- The log System has been updated and contains request
	parameters.
	1. User submits the file transer command with the path of
	the source file (or directory) to copy (including the host),
Base sequence	the path of destination (including the host) and the session
Dase sequence	key.
	2. The System copies the given source file (or directory) to
	the specified destination.
Branch sequence	

Exception sequence	1a. If there are missing parameters, a message that contains the way to use the command, is displayed on the standard output of the client System. 1b. If the given session key is invalid, a message is printed on the standard output of the client System. 1c. If the source file (or directory) or a host is unknown, a message is printed on the standard output of the client System. 1d. If the destination path is invalid, a message is printed on standard output of the client System. 1e. If the source path is a directory and a destination path is a file, a message is printed out on the standard output of the client System. 1f. If the source path is the same than the destination path, a message is returned. 1g. If - User does not have execute permission in the source or destination file parent, - or he does not have read permission on the source file, - or he does not have write permission in the destination parent directory, a message is printed out on the standard output of the client System. 2a. If a host is unreachable during a file transfer, the file transfer is cancelled and will restart when the connexion will be restored.
	transfer is cancelled and will restart when the connexion
	2b. If the transfer file fails, a message is also printed on the
	standard output of the client System.
Extensions	F2.MV1- Execute a synchronous move of files

5.2.16 F2.CP2- Execute an asynchronous copy of files

Title	F2.CP2- Execute an asynchronous copy of files
	This use case allows User to copy files (or directory)
	between two hosts and submit another command without
	waiting the end of file transfer.
Cummour	The four cases of transfer are covered this use case:
Summary	- inside the same host which can be local or remote
	- from local host to remote host
	- from remote host to local host
	- from remote host to another remote host.
Actors	User
Precondition	User has an active open session on the client
	- The file transfer is fully accomplished and a copy of the
Postcondition	source file (or directory) is now on the destination host.
1 oscondition	- The log System has been updated and contains request
	parameters.
	1. User submits the file tranfer command with the path of
	the source file (or directory) to copy (including the host),
	the path of destination (including the host) and the session
Base sequence	key.
Buse sequence	2. The System starts the transfer of the given source file to
	the specified destination and sends back to User a transfer
	id.
	3. When the transfer file ends, the log System is updated.
Branch sequence	

	1a. If there are missing parameters, a message that contains
	the way to use the command, is displayed on the standard
	output of the client System.
	1b. If the given session key is invalid, a message is printed
	on the standard output of the client System.
	1c. If the source file (or directory) or a host is unknown, a
	message is printed on the standard output of the client
	System.
	1d. If the destination path is invalid, a message is printed
	on standard output of the client System.
	1e. If the source path is a directory and the destination path
	is a file, a message is printed out on the standard output of
	the client System.
	1f. If the source path is the same than the destination path,
Exception sequence	a message is print out on the standard output of the client
Exception sequence	System.
	1g. If
	- User does not have execute permission in the source or
	destination file parent,
	- or he does not have read permission on the source file,
	- or he does not have write permission in the destination
	parent directory,
	a message is printed out on the standard output of the client
	System.
	2a. If a host is unreachable during a file transfer, the file
	transfer is cancelled and will restart when the connexion
	will be restored.
	2b. If the transfer file fails, a message is also printed on the
Entencione	standard output of the client System.
Extensions	F2.MV2- Execute an asynchronous move of files

5.2.17 F2.LS1- List files transfer status

Title	F2.LS1- List files transfer status
	This use case allows User to list all file transfer status he
	submitted. He can optionally specify either
Cummom	- a file transfer identifier to get the status of that file
Summary	transfer.
	- or a machine identifier to get the status of all file transfer
	he submitted from that machine.
Actors	User, User
Precondition	User has at least an open active session.
	- The status of all file transfer User submitted are displayed
Postcondition	on the standard output of client System. If a search criteria
1 oscondition	is provided, only the status of the file transfer matching that
	criteria are listed.
	1. User submits a list file transfer status command by
	specifying a session key, with optionally a search criteria
	(either a file transfer id, or a machine id).
Base sequence	2. The System displays the status of all file transfer User
	submitted. If a search criteria is provided, the System
	displays only the status of the file transfer matching that
	criteria.
Branch sequence	

	1a. If there are missing parameters, a message that contains
	the way to use the command, is displayed on the standard
	output of the client System.
	1b. If the specified session key is invalid, a message is
	printed out on the standard output of the client System.
Evantian saguance	1c. If the specified machine id is invalid, a message is
Exception sequence	printed out on the standard output of the client System.
	1d. If the specified file transfer id is invalid, a message is
	printed out on the standard output of the client System.
	1d. If no transfer was submitted by User from the specified
	machine or if the command fails, a message is printed out
	on the standard output of the client System.
Extensions	F2.LS2- List all users file transfer status

5.2.18 F2.LS2- List all users file transfer status

Title	F2.LS2- List all users file transfer status
Summary	This use case allows Admin to list file transfer status. He can specify an optional search criteria among: - a host identifier to list the status of all file transfer submitted from that host - or an user identifier to list the status of all file transfer submitted by that user.
Actors	Admin, Admin
Precondition	Admin has at least an open active session.
Postcondition	 The status of all file transfer submitted host are displayed on the standard output. If a search criteria is provided, only the file transfer matching that criteria are listed. The log System has been updated and contains request parameters.
Base sequence	 Admin submits a list file transfer status command a session key, with optionally a search criteria (either a host id, or a user id). The System displays the status of all file transfer on the standard output of client System. If a search criteria is provided, The System displays only the status of the file transfer matching that criteria.
Branch sequence	
Exception sequence	1a. If there are missing parameters, a message that contains the way to use the command, is displayed on the standard output of the client System. 1b. If the specified session key is invalid, a message is printed out on the standard output of the client System. 1c. If the specified machine id is invalid, a message is printed out on the standard output of the client System. 1c. If the specified user id is invalid, a message is printed out on the standard output of the client System. 1d. If no transfer was submitted from the specified machine, a message is printed out on the standard output of the client System. 1e. If no transfer was submitted by the specified user or if the command fails, a message is printed out on the standard output of the client System.
Extension of	F2.LS1- List files transfer status
LAWISION OF	1 2.201 Pist files transfer status

5.2.19 F2.LT1- List all file transfer

Title	F2.LT1- List all file transfer
	This use case allows User to list all file transfer he
	submitted. User can optionally specify either
Summary	- a machine id to list all file transfer he submitted from that
,	machine
	- or a status to list all file transfer matching that status.
Actors	User
Precondition	User has at least an open active session.
	- All file transfer User submitted are listed on the standard
	output of client System. If a search criteria is provided,
Postcondition	only the file transfer matching that criteria are listed.
	- The log System has been updated and contains request
	parameters.
	1. User submits a list file transfer command by specifying a
	session key with optionally a search criteria (either a host
	id, or a specific status).
Base sequence	2. The System displays all file transfer User submitted on
	the standard output of client System. If a search criteria is
	provided, the System displays only the file transfer
	matching that criteria.
Branch sequence	
	1a. If there are missing parameters, a message that contains
No. of the control of	the way to use the command, is displayed on the standard
	output of the client System.
	1b. If the specified session key is invalid, a message is
	printed out on the standard output of the client System.
	1c. If the specified machine id is invalid, a message is
Exception sequence	printed out on the standard output of the client System.
	1d. If the specified status is invalid, a message is printed
	out on the standard output of the client System.
	1e. If no transfer was submitted from the specified
	machine, a message is printed out on the standard output of
	the client System.
	1f. If the command fails, a message is printed out on the
	standard output of the client System. t System.

5.2.20 F2.LT2- List all users file transfer

Title	F2.LT2- List all users file transfer
	This use case allows Admin to list all file transfer. Admin
	can specify an optional search criteria among:
	- host identifier: to list all file transfer submitted from that
Summary	host
	- user identifier: to list all file transfer submitted by that
	user
	- status: to list all file transfer matching that status.
Actors	Admin, Admin
Precondition	User has at least an open active session.
	- All file transfer are listed on the standard output of client
	System. If a search criteria is provided, only the file
Postcondition	transfer matching that criteria are listed.
	- The log System has been updated and contains request
	parameters.

	1. Admin submits a list file transfer command by
D. D	specifying a session key with optionally a search criteria
	(either a host id, or a user id, or a specific status).
Base sequence	2. The System displays all file transfer on the standard
	output of client System. If a search criteria is provided, The
	System displays only the file transfer matching that criteria.
Branch sequence	
	1a. If there are missing parameters, a message that contains
	the way to use the command, is displayed on the standard
	output of the client System.
	1b. If the specified session key is invalid, a message is
	printed out on the standard output of the client System.
	1c. If the specified machine id is invalid, a message is
	printed out on the standard output of the client System.
Exaction sequence	1d. If the specified user id is invalid, a message is printed
Exception sequence	out on the standard output of the client System.
	1d. If the specified status is invalid, a message is printed
	out on the standard output of the client System.
	1e. If no transfer was submitted from the specified
	machine, or by the specified user, a message is printed out
	on the standard output of the client System.
	1e. If the command fails, a message is printed out on the
	standard output of the client System. t System.

5.2.21 F2.MV1- Execute a synchronous move of files

Title	F2.MV1- Execute a synchronous move of files
	This use case allows User to copy a file (directory) from a host to another host. Furthermore, the source file
	(directory) is removed from the source host. The four cases of transfer are covered this use case:
Summary	
	- inside the same host which can be local or remote
	- from local host to remote host
	- from remote host to local host
	- and from remote host to another remote host.
Actors	User
Precondition	
	- The file transfer is fully accomplished.
	- A copy of the source file (directory) is now on the
	destination host,
Postcondition	- and the source file (directory) is removed from the source
	host.
	- The log System has been updated and contains request
	parameters.
	1. User submits the tranfer file command with the path of
	the source files (or directory) to copy (including the host),
	the path of destination (including the host) and the session
Base sequence	key.
•	2. The System makes a copy of the given source file
	(directory) to the specified destination and removes the
	source file (directory) from the source host.
Branch sequence	

	1a. If there are missing parameters, a message that contains the way to use the command, is displayed on the standard output of the client System.
	1b. If the given session key is invalid, a message is printed on the standard output of the client System.
	1c. If the source file (or directory) or the host is unknown, a message is printed on the standard output of the client System.
	1d. If the destination path is invalid, a message is printed
	on standard output of the client System.
	1e. If the source path is a directory and the destination path
	is a file, a message is printed out on the standard output of
Exception sequence	the client System.
Exception sequence	1f. If
	- User does not have execute permission in the source or
	destination file parent,
	- or he does not have read permission on the source file,
	or he does not have write permission in the destination
	parent directory,
	a message is printed out on the standard output of the client
	System.
	2a. If a host is unreachable during a file transfer, the file
	transfer is cancelled and will restart when the connexion will be restored.
	2b. If the transfer file fails, a message is also printed on the
	standard output of the client System.
Extension of	
EXICIISIOII OI	F2.CP1- Execute a synchronous copy of files

5.2.22 F2.MV2- Execute an asynchronous move of files

T'.1.	EQ MOVO E (CC)
Title	F2.MV2- Execute an asynchronous move of files
	This use case allows User to move file (or directory) from
	host to another host and submit another command without
	waiting the end of file transfer. Furthermore, the source file
	(or directory) is removed from the source host.
Summary	The four cases of transfer are covered this use case:
	- inside the same host which can be local or remote
	- from local host to remote host
	- from remote host to local host
	- and from remote host to another remote host.
Actors	User
Precondition	User has at least an open active session.
	- The file transfer is in completed status.
	- The source file (or directory) is removed from the source
Postcondition	hosts.
	- The System log has been updated and contains request
	parameters.
	1. User submits the file transer command with the path of
	the source file (or directory) to copy (including the host),
Base sequence	the path of destination (including the host) and the session
	key.
	2. The System starts the transfer of the given source file (or
	directory) to the specified destination and sends back to
	User a transfer id.
	3. At the end of a transfer, the log System is updated.
Branch sequence	

standard output of the client System.			1a. If there are missing parameters, a message that contains the way to use the command, is displayed on the standard
on the standard output of the client System. 1c. If the source file (or directory) or the host is unknown a message is printed on the standard output of the client System. 1d. If the destination path is invalid, a message is printed on standard output of the client System. 1e. If the source path is a directory and a destination path a file, a message is printed out on the standard output of the client System. 1f. If - User does not have execute permission in the source or destination file parent, - or he does not have read permission on the source file, - or he does not have write permission in the destination parent directory, a message is printed out on the standard output of the client System. 2a. If a host is unreachable during a file transfer, the file transfer is cancelled and will restart when the connexion will be restored. 2b. If the transfer file fails, a message is also printed on the standard output of the client System.			1
lc. If the source file (or directory) or the host is unknown a message is printed on the standard output of the client System. 1d. If the destination path is invalid, a message is printed on standard output of the client System. 1e. If the source path is a directory and a destination path a file, a message is printed out on the standard output of to client System. 1f. If User does not have execute permission in the source or destination file parent, or he does not have read permission on the source file, or he does not have write permission in the destination parent directory, a message is printed out on the standard output of the client System. 2a. If a host is unreachable during a file transfer, the file transfer is cancelled and will restart when the connexion will be restored. 2b. If the transfer file fails, a message is also printed on the standard output of the client System.			
a message is printed on the standard output of the client System. 1d. If the destination path is invalid, a message is printed on standard output of the client System. 1e. If the source path is a directory and a destination path a file, a message is printed out on the standard output of to client System. 1f. If 1f. User does not have execute permission in the source or destination file parent, or he does not have read permission on the source file, or he does not have write permission in the destination parent directory, a message is printed out on the standard output of the client System. 2a. If a host is unreachable during a file transfer, the file transfer is cancelled and will restart when the connexion will be restored. 2b. If the transfer file fails, a message is also printed on the standard output of the client System.			•
System. 1d. If the destination path is invalid, a message is printed on standard output of the client System. 1e. If the source path is a directory and a destination path a file, a message is printed out on the standard output of the client System. 1f. If - User does not have execute permission in the source or destination file parent, - or he does not have read permission on the source file, - or he does not have write permission in the destination parent directory, a message is printed out on the standard output of the client System. 2a. If a host is unreachable during a file transfer, the file transfer is cancelled and will restart when the connexion will be restored. 2b. If the transfer file fails, a message is also printed on the standard output of the client System.			•
Id. If the destination path is invalid, a message is printed on standard output of the client System. 1e. If the source path is a directory and a destination path a file, a message is printed out on the standard output of the client System. 1f. If - User does not have execute permission in the source or destination file parent, - or he does not have read permission on the source file, - or he does not have write permission in the destination parent directory, a message is printed out on the standard output of the client System. 2a. If a host is unreachable during a file transfer, the file transfer is cancelled and will restart when the connexion will be restored. 2b. If the transfer file fails, a message is also printed on the standard output of the client System.			-
on standard output of the client System. le. If the source path is a directory and a destination path a file, a message is printed out on the standard output of t client System. If. If - User does not have execute permission in the source or destination file parent, - or he does not have read permission on the source file, - or he does not have write permission in the destination parent directory, a message is printed out on the standard output of the client System. 2a. If a host is unreachable during a file transfer, the file transfer is cancelled and will restart when the connexion will be restored. 2b. If the transfer file fails, a message is also printed on the standard output of the client System.			
Exception sequence 1e. If the source path is a directory and a destination path a file, a message is printed out on the standard output of the client System. 1f. If 1g. User does not have execute permission in the source or destination file parent, or he does not have read permission on the source file, or he does not have write permission in the destination parent directory, a message is printed out on the standard output of the client System. 2a. If a host is unreachable during a file transfer, the file transfer is cancelled and will restart when the connexion will be restored. 2b. If the transfer file fails, a message is also printed on the standard output of the client System.			
a file, a message is printed out on the standard output of to client System. If. If - User does not have execute permission in the source or destination file parent, - or he does not have read permission on the source file, - or he does not have write permission in the destination parent directory, a message is printed out on the standard output of the client System. 2a. If a host is unreachable during a file transfer, the file transfer is cancelled and will restart when the connexion will be restored. 2b. If the transfer file fails, a message is also printed on the standard output of the client System.			*
Exception sequence client System. 1f. If - User does not have execute permission in the source or destination file parent, - or he does not have read permission on the source file, - or he does not have write permission in the destination parent directory, a message is printed out on the standard output of the client System. 2a. If a host is unreachable during a file transfer, the file transfer is cancelled and will restart when the connexion will be restored. 2b. If the transfer file fails, a message is also printed on the standard output of the client System.			
1f. If - User does not have execute permission in the source or destination file parent, - or he does not have read permission on the source file, - or he does not have write permission in the destination parent directory, a message is printed out on the standard output of the clie System. 2a. If a host is unreachable during a file transfer, the file transfer is cancelled and will restart when the connexion will be restored. 2b. If the transfer file fails, a message is also printed on the standard output of the client System.		/	
- User does not have execute permission in the source or destination file parent, - or he does not have read permission on the source file, - or he does not have write permission in the destination parent directory, a message is printed out on the standard output of the clie System. 2a. If a host is unreachable during a file transfer, the file transfer is cancelled and will restart when the connexion will be restored. 2b. If the transfer file fails, a message is also printed on the standard output of the client System.	Exception sequence		·
destination file parent, - or he does not have read permission on the source file, - or he does not have write permission in the destination parent directory, a message is printed out on the standard output of the clie System. 2a. If a host is unreachable during a file transfer, the file transfer is cancelled and will restart when the connexion will be restored. 2b. If the transfer file fails, a message is also printed on the standard output of the client System.	1.1		
 or he does not have read permission on the source file, or he does not have write permission in the destination parent directory, a message is printed out on the standard output of the client System. 2a. If a host is unreachable during a file transfer, the file transfer is cancelled and will restart when the connexion will be restored. 2b. If the transfer file fails, a message is also printed on the standard output of the client System. 			-
- or he does not have write permission in the destination parent directory, a message is printed out on the standard output of the clie System. 2a. If a host is unreachable during a file transfer, the file transfer is cancelled and will restart when the connexion will be restored. 2b. If the transfer file fails, a message is also printed on the standard output of the client System.			
parent directory, a message is printed out on the standard output of the clie System. 2a. If a host is unreachable during a file transfer, the file transfer is cancelled and will restart when the connexion will be restored. 2b. If the transfer file fails, a message is also printed on the standard output of the client System.			
a message is printed out on the standard output of the clie System. 2a. If a host is unreachable during a file transfer, the file transfer is cancelled and will restart when the connexion will be restored. 2b. If the transfer file fails, a message is also printed on the standard output of the client System.			-
System. 2a. If a host is unreachable during a file transfer, the file transfer is cancelled and will restart when the connexion will be restored. 2b. If the transfer file fails, a message is also printed on the standard output of the client System.			•
2a. If a host is unreachable during a file transfer, the file transfer is cancelled and will restart when the connexion will be restored. 2b. If the transfer file fails, a message is also printed on the standard output of the client System.			
transfer is cancelled and will restart when the connexion will be restored. 2b. If the transfer file fails, a message is also printed on the standard output of the client System.			· ·
will be restored. 2b. If the transfer file fails, a message is also printed on the standard output of the client System.			
2b. If the transfer file fails, a message is also printed on the standard output of the client System.			
standard output of the client System.			
•			2b. If the transfer file fails, a message is also printed on the
TO CIDA T			
Extension of F2.CP2- Execute an asynchronous copy of files	Extension of		F2.CP2- Execute an asynchronous copy of files

5.2.23 F3. Launch FMS server

Title	F3. Launch FMS server
Cummory	This use case allows Admin to launch the VISHNU FMS
Summary	server on a given host.
Actors	Admin
	- The VISHNU server software (FMS Module and
	dependencies) is installed on the host
Precondition	- The host is configured in the VISHNU System database
	- The network connection between the host and the
	VISHNU database server is up and running.
Postcondition	- The FMS server is up and running.
1 Ostcondition	- A server log has been created.
	1. Admin logs in the host as VISHNU user
	2. Admin updates the VISHNU configuration if necessary
	(database server hostname and credentials, SysferaDS configuration)
	3. Admin launches the VISHNU FMS Server executable
	4. The System checks the connections to its peers within
Dana samura	the VISHNU platform.
Base sequence	5. The System retrieves the list of active file transfer (not
	completed file transfer) that were launched from or to the
	same host.
	6. The System checks that all the active file transfer (from
	previous step) are still running, and eventually updates the
	file transfer status (for ex. from failed to in progress).
	7. The System returns a status message to Admin.

Branch sequence	
	4a. A connection to a VISHNU peer is down. System
Evantian saguana	returns an error message and stops.
Exception sequence	6a. If a source file or destination is unreachable. In this
	case the System updates the file transfer status to failed.

5.2.24 F4. Stop FMS server

Title	F4. Stop FMS server
Summary	This use case allows Admin to stop the VISHNU FMS server on a given host.
Actors	Admin
Precondition	- The FMS Server is up and running on the given host.
Postcondition	- The FMS Server is down.
Base sequence	 Admin sends a request to stop the FMS Server and provides the host identifier. The System updates the status of all on-going file transfer requests. The System stops all internal processes on the host. The System returns an information message to Admin.
Branch sequence	
Exception sequence	

5.3 Data dictionary

- FMS: File Management System
- Host:: Computer connected to other computers or terminals to which it provides data or computing services via a network.
- Inode:
 - An inode is a data structure on a filesystem on Linux and other Unix-like operating systems that stores all the information about a file except its name and its actual data.
 - When a file is created, it is assigned both a name and an inode number, which is an integer that is unique within the filesystem.
 - An inode contains all information describing a file.
 - This includes (1) the size of the file (in bytes) and its physical location (i.e., the addresses of the blocks of storage containing the file's data on a HDD),
 - (2) the file's owner and group, (3) the file's access permissions,
 - (4) timestamps telling when the inode was created, last modified and last accessed and (5) a reference count telling how many hard links point to the inode.
- Path:: String of characters denoting the complete location of a file or folder (directory) in the host's data filing system.