D1.1d - VISHNU Command-line
interface specifications

**D1.1d - VISHNU Command-line interface specifications** 



## COLLABORATORS

	TITLE:  D1.1d - VISHNU Co	ommand-line interface		
ACTION	NAME	DATE	SIGNATURE	
WRITTEN BY	Benjamin Isnard, Daouda Traoré, Eugène Pamba Capo-Chichi, Kevin Coulomb, and Ibrahima Cissé	February 24, 2011		

## REVISION HISTORY

NUMBER	DATE	DESCRIPTION	NAME
0	05/01/2011	Formatting example	SysFera
1	13/01/2011	First release	SysFera
2	10/02/2011	Removed UMS::SessionStateType. Added UMS::StatusType, UMS::PrivilegeType. Modified UMS::addVishnuUser, UMS::updateUser, UMS::addLocalAccount, UMS::addMachine, UMS::updateMachine, UMS::listSessions, UMS::restoreConfiguration.	SysFera
3	18/02/2011	Renamed all commands to follow C-style command names with vishnu prefix.  Added the help option to all commands.  Modified update_machine and export_commands.  Removed the VISHNU_SESSION_KEY environment variable on all commands.	SysFera

# **Contents**

1	Docu	ument presentation		1
	1.1	Document objectives		1
	1.2	Document structure		1
	1.3	References		1
	1.4	Glossary		1
	1.5	Generic command definition format		2
	1.6	Environment variables and options		2
2	Com	mands specification for User Man <mark>ageme</mark> nt Service (UMS)		4
	2.1	Command definitions		
		2.1.1 vishnu_connect		4
		2.1.2 vishnu_reconnect		5
		2.1.3 vishnu_add_user		5
		2.1.4 vishnu_update_user		5
		2.1.5 vishnu_delete_user		6
		2.1.6 vishnu_close		6
		2.1.7 vishnu_change_password		7
		2.1.8 vishnu_reset_password		7
		2.1.9 vishnu_add_local_account		7
		2.1.10 vishnu_update_local_account		9
		2.1.11 vishnu_delete_local_account		9
		2.1.12 vishnu_save_configuration		10
		2.1.13 vishnu_restore_configuration	<u>.</u> .	10
		2.1.14 vishnu_add_machine		11
		2.1.15 vishnu_update_machine		11
		2.1.16 vishnu_delete_machine		12
		2.1.17 vishnu_list_local_account		12
		2.1.18 vishnu_list_machine		12
		2.1.19 vishnu_list_history_cmd		13
		2.1.20 vishnu_list_options		13

		2.1.21	vishnu_list_users	14
		2.1.22	vishnu_list_sessions	14
		2.1.23	vishnu_configure_default_option	15
		2.1.24	vishnu_configure_option	15
	2.2	Parame	eters definitions	16
3	Com	nmands	specification for Tasks Management Service (TMS)	17
	3.1	Comm	and definitions	17
		3.1.1	vishnu_submit_job	17
		3.1.2	vishnu_get_job_info	18
		3.1.3	vishnu_get_job_progress	18
		3.1.4	vishnu_list_queues	18
		3.1.5	vishnu_list_jobs	19
		3.1.6	vishnu_get_job_out_put	19
		3.1.7	vishnu_get_all_jobs_out_put	21
		3.1.8	vishnu_cancel_job	21
		3.1.9	vishnu_set_machine_env	21
			vishnu_set_machine_refresh_period	
	3.2	Parame	eters definitions	22
4	Com		specification for Information Management Service (IMS)	24
4	<b>Com</b> 4.1	ımands	specification for Information Management Service (IMS)	
4		ımands		24
4		nmands Comm	and definitions	24 24
4		Commands	and definitions	24 24 24
4		Comm. 4.1.1 4.1.2	and definitions	<ul><li>24</li><li>24</li><li>24</li><li>25</li></ul>
4		Comm. 4.1.1 4.1.2 4.1.3	and definitions	<ul><li>24</li><li>24</li><li>24</li><li>25</li><li>25</li></ul>
4		Comm. 4.1.1 4.1.2 4.1.3 4.1.4	and definitions	<ul><li>24</li><li>24</li><li>24</li><li>25</li><li>25</li><li>25</li></ul>
4		Annands Comm. 4.1.1 4.1.2 4.1.3 4.1.4 4.1.5	and definitions  vishnu_export_commands  vishnu_get_metric_current_value  vishnu_get_metric_history  vishnu_get_processes  vishnu_set_system_info	24 24 25 25 25 26
4		Amands Comm. 4.1.1 4.1.2 4.1.3 4.1.4 4.1.5 4.1.6	and definitions  vishnu_export_commands  vishnu_get_metric_current_value  vishnu_get_metric_history  vishnu_get_processes  vishnu_set_system_info  vishnu_set_system_threshold	24 24 24 25 25 25 26 26
4		Amands Comm. 4.1.1 4.1.2 4.1.3 4.1.4 4.1.5 4.1.6 4.1.7	and definitions  vishnu_export_commands  vishnu_get_metric_current_value  vishnu_get_metric_history  vishnu_get_processes  vishnu_set_system_info  vishnu_set_system_threshold  vishnu_get_system_threshold  vishnu_get_system_threshold	24 24 25 25 25 26 26 27
4		4.1.1 4.1.2 4.1.3 4.1.4 4.1.5 4.1.6 4.1.7 4.1.8 4.1.9 4.1.10	and definitions  vishnu_export_commands  vishnu_get_metric_current_value  vishnu_get_metric_history  vishnu_get_processes  vishnu_set_system_info  vishnu_set_system_threshold  vishnu_get_system_threshold  vishnu_define_user_identifier  vishnu_define_machine_identifier  vishnu_define_job_identifier	24 24 25 25 25 26 26 27 27 27
4		4.1.1 4.1.2 4.1.3 4.1.4 4.1.5 4.1.6 4.1.7 4.1.8 4.1.9 4.1.10	and definitions  vishnu_export_commands  vishnu_get_metric_current_value  vishnu_get_metric_history  vishnu_get_processes  vishnu_set_system_info  vishnu_set_system_threshold  vishnu_get_system_threshold  vishnu_define_user_identifier  vishnu_define_machine_identifier	24 24 25 25 25 26 26 27 27 27
4		4.1.1 4.1.2 4.1.3 4.1.4 4.1.5 4.1.6 4.1.7 4.1.8 4.1.9 4.1.10 4.1.11	and definitions  vishnu_export_commands  vishnu_get_metric_current_value  vishnu_get_metric_history  vishnu_get_processes  vishnu_set_system_info  vishnu_set_system_threshold  vishnu_get_system_threshold  vishnu_define_user_identifier  vishnu_define_machine_identifier  vishnu_define_job_identifier	24 24 25 25 25 26 26 27 27 27 28
4		4.1.1 4.1.2 4.1.3 4.1.4 4.1.5 4.1.6 4.1.7 4.1.8 4.1.9 4.1.10 4.1.11	and definitions  vishnu_export_commands  vishnu_get_metric_current_value  vishnu_get_metric_history  vishnu_get_processes  vishnu_set_system_info  vishnu_set_system_threshold  vishnu_get_system_threshold  vishnu_define_user_identifier  vishnu_define_machine_identifier  vishnu_define_job_identifier  vishnu_define_job_identifier	24 24 25 25 25 26 26 27 27 27 28 28
4		4.1.1 4.1.2 4.1.3 4.1.4 4.1.5 4.1.6 4.1.7 4.1.8 4.1.9 4.1.10 4.1.11 4.1.12 4.1.13	vishnu_export_commands vishnu_get_metric_current_value vishnu_get_metric_history vishnu_get_processes vishnu_set_system_info vishnu_set_system_threshold vishnu_get_system_threshold vishnu_get_system_threshold vishnu_define_user_identifier vishnu_define_machine_identifier vishnu_define_job_identifier vishnu_define_transfer_identifier vishnu_define_transfer_identifier vishnu_load_shed	24 24 25 25 25 26 26 27 27 27 28 28 29
4		4.1.1 4.1.2 4.1.3 4.1.4 4.1.5 4.1.6 4.1.7 4.1.8 4.1.9 4.1.10 4.1.11 4.1.12 4.1.13 4.1.14	vishnu_get_metric_current_value vishnu_get_metric_history vishnu_get_processes vishnu_set_system_info vishnu_set_system_threshold vishnu_get_system_threshold vishnu_define_user_identifier vishnu_define_machine_identifier vishnu_define_job_identifier vishnu_define_transfer_identifier vishnu_define_transfer_identifier vishnu_load_shed vishnu_load_shed vishnu_set_update_frequency	24 24 25 25 26 26 27 27 27 28 28 29

5	Com	nmands	specification for File Management Service (FMS)	31
	5.1	Comm	nand definitions	. 31
		5.1.1	vishnu_create_file	. 31
		5.1.2	vishnu_create_dir	. 31
		5.1.3	vishnu_remove_file	. 32
		5.1.4	vishnu_remove_dir	. 32
		5.1.5	vishnu_ch_grp	. 32
		5.1.6	vishnu_ch_mod	. 33
		5.1.7	vishnu_head_of_file	. 33
		5.1.8	vishnu_tail_of_file	. 34
		5.1.9	vishnu_content_of_file	. 34
		5.1.10	vishnu_list_dir	. 34
		5.1.11	vishnu_copy_file	. 35
		5.1.12	vishnu_copy_async_file	. 35
		5.1.13	vishnu_move_file	. 36
		5.1.14	vishnu_move_async_file	. 36
		5.1.15	vishnu_stop_file_transfer	. 37
		5.1.16	vishnu_list_file_transfer_status	. 37
			vishnu_list_file_transfers	
	5.2	Parame	eters definitions	38

# **Chapter 1**

# Document presentation

## 1.1 Document objectives

This document presents the detailed specifications of the VISHNU command line user interface.

These specifications include the definition of all commands including administration commands.

## 1.2 Document structure

The document is divided into 4 parts corresponding to the 4 modules that compose the Vishnu system:

- UMS: Users Management Service
- TMS: Tasks Management Service
- FMS: Files Management Service
- IMS: Information Management Service

Each module corresponds to a chapter in the document, and each chapter contains the following sections:

- A first section describing the definition of all commands provided by the package.
- A second section describing the definition of all enumerated values used as command parameters.

## 1.3 References

• D1.1a: VISHNU General specifications

## 1.4 Glossary

• VISHNU admin: any user having the administrator privilege

## 1.5 Generic command definition format

This section presents the generic format used in the following chapters to describe the commands. It also details the environment variables required and the user options.

A commands is defined as follows:

#### Access

Here is detailed the access level of the command line (i.e. the privilege required to use this command)

#### **Description**

Here is detailed the purpose of the command line.

#### Example of use

Here is detailed an example of the use of the command line which starts by optional arguments preceded by a short letter and the required arguments at the end.

myCommand -l acLogin -s sshKeyPath userId

#### **Parameters**

The following table contains all the input arguments of the command with their type and description, their short letter for options and a required flag.

Parameter	Type	Option	Description	Required
userId	string		This is an example of a required argument	YES
acLogin	string	1	This is an example of an optional argument	NO
sshKeyPath	string	S	This is an example of an optional argument	NO

The following table contains the list of environment variables information. These environment variables can be mandatory or optional and the value will be overriden by the corresponding command-line option if applicable. When the user option flag is true, the value for this variable can be defined persistently as a user option stored in the database (see the "vishnu\_configure\_option" command.

## **Environment variables**

Name	Parameter	Туре	Description	Required	User option
VISHNU_CONFIG_FILE	N/A	string	This is an example of an environment variable	YES	NO

#### Note:

For each command line the -h option can be used for help.

## 1.6 Environment variables and options

Here is detailed the way to use the user options which are stored in the database and environment variables in VISHNU.

## Example 1.1 Pseudo code

```
if (the option is provided in the command line) {
    optionValue = option

} else {
    if (an environment variable exists) {
        optionValue = EnVariable_Value

} else {
    if (a value has been defined in the user configuration) {
        optionValue = user_Option
    }
    else {
        //The default value of the option defined by VISHNU admin is used optionValue = defaultValueOption
    }
}
```

# **Chapter 2**

# Commands specification for User Management Service (UMS)

## 2.1 Command definitions

## 2.1.1 vishnu connect

#### Access

This command line can be used by any VISHNU user

#### **Description**

The vishnu\_connect command opens a session

## Example of use

vishnu\_connect[-h][-p closePolicy][-d sessionInactivityDelay][-s substituteUserId]userId

#### **Parameters**

Parameter	Type	Option	<b>Description</b>	Required
userId	string		userId represents the VISHNU user identifier	YES
password	string	password represents the password of the user, it is an interactive parameter		YES
closePolicy SessionCloseType		p	is an option for closing session automatically	NO
sessionInactivityDelay int d user reques		is the maximum delay in seconds between two user requests when the CLOSE_ON_TIMEOUT policy is set	NO	
substituteUserId string		s	is an admin option which allows an admin to open a session as if she was another user identified by her userId	NO

#### **Environment variables**

Name	Parameter	Туре	Description	Required	User option
VISHNU_CLOSE_POLICY	closePolicy	SessionCloseType	is an option for closing session automatically	NO	YES

## 2.1.2 vishnu\_reconnect

#### Access

This command line can be used by any VISHNU user

#### **Description**

The vishnu\_reconnect command reconnects to a session that is still active

#### Example of use

vishnu\_reconnect[-h] userId sessionId

#### **Parameters**

Parameter	Type	<b>Option</b>	Description	Req <mark>uire</mark> d
userId	string		userId represents the VISHNU user identifier	YES
password	string		password represents the password of the user, it is an interactive parameter	YES
sessionId	string		sessionId is the identifier of the session defined in the database	YES

#### **Environment variables**

This command defines no environment variables.

## 2.1.3 vishnu\_add\_user

#### Access

This command line can be used by ADMIN users only

#### **Description**

The vishnu\_add\_user command adds a new VISHNU user

#### Example of use

vishnu\_add\_user [-h] firstname lastname privilege email

#### **Parameters**

Parameter	Type	<b>Option</b>	Description	Required
firstname	string		is the firstname of the user	YES
lastname	string		is the lastname of the user	YES
privilege	PrivilegeType		is the privilege of the user (admin or simple user)	YES
email	string		is the email of the user	YES

#### **Environment variables**

This command defines no environment variables.

## 2.1.4 vishnu\_update\_user

#### Access

This command line can be used by ADMIN users only

## Description

The vishnu\_update\_user command updates the user information except the userId and the password

#### Example of use

vishnu\_update\_user[-h][-f firstname][-l lastname][-p privilege][-m email][-s status]userId

#### **Parameters**

Parameter	Type	Option	Description	Required
userId	string		represents the VISHNU user identifier	YES
firstname	string	f	represents the updated firstname of the user	NO
lastname	string	1	represents the updated lastname of the user	NO
privilege	PrivilegeType	p	represents the updated privilege of the user	NO
email	string	m	represents the updated email adress of the user	NO
status	StatusType	S	represents the status of the user (LOCKED or ACTIVE)	NO

#### **Environment variables**

This command defines no environment variables.

## 2.1.5 vishnu\_delete\_user

#### Access

This command line can be used by ADMIN users only

## Description

The vishnu\_delete\_user command removes a user from VISHNU

#### Example of use

vishnu\_delete\_user[-h] userId

#### **Parameters**

Parameter	Type	Option	Description	Required
userId	string		userId represents the VISHNU user identifier of the user who will be deleted from VISHNU	YES

#### **Environment variables**

This command defines no environment variables.

## 2.1.6 vishnu\_close

#### Access

This command line can be used by any VISHNU user

## Description

The vishnu\_close command closes the session

## Example of use

vishnu\_close[-h]

#### **Parameters**

This command defines no arguments.

#### **Environment variables**

This command defines no environment variables.

## 2.1.7 vishnu\_change\_password

#### Access

This command line can be used by any VISHNU user

#### **Description**

The vishnu\_change\_password command changes the password

#### Example of use

vishnu\_change\_password[-h] userId

#### **Parameters**

Parameter	Type	<b>Option</b>	<b>Descri</b> ption	Required
userId	string		userId represents the VISHNU user identifier	YES
password	string		password represents the password of the user, it is an interactive parameter	YES
passwordNew	string		passwordNew represents the new password of the user, it is an interactive parameter	YES

#### **Environment variables**

This command defines no environment variables.

## 2.1.8 vishnu\_reset\_password

#### Access

This command line can be used by ADMIN users only

#### **Description**

The vishnu\_reset\_password command resets the password of a user

#### Example of use

vishnu\_reset\_password[-h] userId

#### **Parameters**

Parameter	Type	<b>Option</b>	Description	Required
userId	etrina		userId represents the VISHNU user identifier of	YES
useriu	string		the user whose password will be reset	ILS

#### **Environment variables**

This command defines no environment variables.

#### 2.1.9 vishnu\_add\_local\_account

#### Access

This command line can be used by any VISHNU user

#### **Description**

The vishnu\_add\_local\_account command adds a new local user configuration

## Example of use

vishnu\_add\_local\_account [-h] userId machineId acLogin sshKeyPath homeDirectory

Parameter	Type	Option	Description	Required
userId	string		The userId represents the VISHNU user identifier	YES
uscriu	sumg		of the user of the local user configuration	1123
machineId	string		The MachineId represents the identifier of the	YES
macimieid	sumg		machine associated to the local user configuration	1123
acLogin	string		accLogin represents the login of the user on the	YES
acLogin	sumg	string	associated machine	I LS
sshKeyPath	string		sshKeyPath is the path of the ssh key of the user	YES
SSHIKCYI atti	sumg		on the associated machine	1123
homeDirectory	string		HomeDirectory is the path of the home directory	YES
	Sumg		of the user on the associated machine	1 ES

This command defines no environment variables.

## 2.1.10 vishnu\_update\_local\_account

#### Access

This command line can be used by any VISHNU user

#### Description

The vishnu\_update\_local\_account command updates a local user configuration

#### Example of use

#### **Parameters**

Parameter	Type	Option	Description	Required	
userId	string		The userId represents the VISHNU user identifier	YES	
usciiu	Sumg		of the user of the local user configuration	ILS	
machineId	string		The MachineId represents the identifier of the	YES	
macmilletu	Sumg		machine associated to the local user configuration	ILS	
acLogin	string	1	accLogin represents the login of the user on the	NO	
acLogiii	String	1	associated machine	110	
sshKeyPath	string	s	sshKeyPath is the path of the ssh key of the user	NO	
ssincyi am	String	3	on the associated machine	110	
homeDirectory	string	d	HomeDirectory is the path of the home directory	NO	
nomeDirectory	Stillig	u u	of the user on the associated machine	110	

#### **Environment variables**

This command defines no environment variables.

## 2.1.11 vishnu\_delete\_local\_account

#### Access

This command line can be used by any VISHNU user

## **Description**

The vishnu\_delete\_local\_account command removes a local user configuration (for a given user on a given machine) from VISHNU

#### Example of use

vishnu\_delete\_local\_account [-h] userId machineId

#### **Parameters**

Parameter	Type	Option	Description	Required
			userId represents the VISHNU user identifier of	
userId	string		the user whose local configuration will be deleted	YES
			for the given machine	
			machineId represents the identifier of the	
machineId	string		machine whose local configuration will be	YES
			deleted for the given user	

#### **Environment variables**

This command defines no environment variables.

## 2.1.12 vishnu\_save\_configuration

#### Access

This command line can be used by ADMIN users only

#### **Description**

The vishnu\_save\_configuration command saves the configuration of VISHNU

## Example of use

vishnu\_save\_configuration[-h]

#### **Parameters**

This command defines no arguments.

#### **Environment variables**

This command defines no environment variables.

## 2.1.13 vishnu\_restore\_configuration

#### Access

This command line can be used by ADMIN users only

#### **Description**

The vishnu\_restore\_configuration command restores the configuration of VISHNU

#### Example of use

vishnu\_restore\_configuration [-h] filePath

#### **Parameters**

Parameter	Type	Option	Description	Required
filePath	string		The filePath is the path of the file used to restore VISHNU configuration	YES

## **Environment variables**

This command defines no environment variables.

## 2.1.14 vishnu\_add\_machine

#### Access

This command line can be used by ADMIN users only

#### **Description**

The vishnu\_add\_machine command adds a new machine in VISHNU

#### Example of use

vishnu\_add\_machine [-h] name site language sshPublicKeyFile

#### **Parameters**

Parameter	Type	Option	<b>Description</b>	Required
name	string		represents the name of the machine	YES
site	string		represents the location of the machine	YES
machineDescription	string		represents the description of the machine, it is an interactive parameter	YES
language	string		represents the language used for the description of the machine	YES
sshPublicKeyFile	string		contains the path to the SSH public key used by VISHNU to access local user accounts	YES

#### **Environment variables**

This command defines no environment variables.

## 2.1.15 vishnu\_update\_machine

#### Access

This command line can be used by ADMIN users only

#### **Description**

The vishnu\_update\_machine command updates machine description

#### Example of use

vishnu\_update\_machine[-h][-n name][-s site][-d][-l language][-t status][-k sshPublicKeyFile]
machineId

#### **Parameters**

Parameter	Type	Option	Description	Required
machineId	string		represents the identifier of the machine	YES
name	string	n	represents the name of the machine	NO
site	string	S	represents the location of the machine	NO
machineDescription	string	d	represents the description of the machine, it is an interactive parameter	NO
language	string	1	represents the language used for the description of the machine	NO
status	StatusType	t	represents the status of the machine	NO
sshPublicKeyFile	string	k	contains the path to the SSH public key used by VISHNU to access local user accounts	NO

## **Environment variables**

This command defines no environment variables.

## 2.1.16 vishnu\_delete\_machine

#### Access

This command line can be used by ADMIN users only

#### **Description**

The vishnu\_delete\_machine command removes a machine from VISHNU

#### Example of use

vishnu\_delete\_machine[-h] machineId

#### **Parameters**

Parameter	Type	<b>Option</b>	<b>Descri</b> ption	Required
machineId	string		machine machine machine machine	YES

#### **Environment variables**

This command defines no environment variables.

## 2.1.17 vishnu\_list\_local\_account

#### Access

This command line can be used by any VISHNU user

## Description

The vishnu\_list\_local\_account command lists the local user configurations

#### Example of use

vishnu\_list\_local\_account[-h][-a][-u userId][-i machineId]

#### **Parameters**

Parameter	Type	Option	<b>Description</b>	Required
adminListOption	boolean	a	is an admin option for listing all local configurations of all users	NO
userId	string	u	is an admin option for listing the local configurations of a specific user	NO
machineId	string	i	is an option for listing local user configurations on a specific machine	NO

#### **Environment variables**

This command defines no environment variables.

## 2.1.18 vishnu\_list\_machine

#### Access

This command line can be used by any VISHNU user

## Description

The vishnu\_list\_machine command lists the machines in which the local user configurations are defined for the given user

#### Example of use

vishnu\_list\_machine[-h][-u userId][-a][-m machineId]

#### **Parameters**

Parameter	Type	Option	Description	Required
userId str	string	u is an admin option for listing machines in value a specific user has a local configuration	is an admin option for listing machines in which	NO
	sumg		a specific user has a local configuration	
listAllmachine	boolean	a	is an option for listing all VISHNU machines	NO
machinald	string	m	is an option for listing information about a	NO
machineId	sumg	m	specific machine	NO

#### **Environment variables**

This command defines no environment variables.

## 2.1.19 vishnu\_list\_history\_cmd

#### Access

This command line can be used by any VISHNU user

## Description

The vishnu\_list\_history\_cmd command lists the commands

#### Example of use

vishnu\_list\_history\_cmd[-h][-a][-u userId][-i sessionId][-s startDateOption][-e endDateOption]

#### **Parameters**

Parameter	Type	Option	Description	Required
adminListOption	boolean	a	is an admin option for listing all commands of all users	NO
userId	string	u	is an admin option for listing commands launched by a specific user identified by his/her userId	NO
sessionId	string	i	lists all commands launched within a specific session	NO
startDateOption	long	S	allows the user to organize the commands listed by providing the start date (the UNIX timestamp of the start date is used)	NO
endDateOption	long	e	allows the user to organize the commands listed by providing the end date (the timestamp of the end date is used). By default, the end date is the current day	NO

#### **Environment variables**

This command defines no environment variables.

## 2.1.20 vishnu\_list\_options

#### Access

This command line can be used by any VISHNU user

## Description

The vishnu\_list\_options command lists the options of the user

#### Example of use

vishnu\_list\_options[-h][-a][-u userId][-n optionName]

#### **Parameters**

Parameter	Type	Option	Description	Required
listAllDeftValue	boolean	a	is an option for listing all default option values defined by VISHNU administrator	NO
userId	string	u	is an admin option for listing the options of a specific user	NO
optionName	string	n	allows the user to get the value of a specific option identified by its name	NO

#### **Environment variables**

This command defines no environment variables.

## 2.1.21 vishnu\_list\_users

#### Access

This command line can be used by ADMIN users only

#### **Description**

The vishnu\_list\_users command lists VISHNU users

#### Example of use

vishnu\_list\_users[-h][-i userIdOption]

#### **Parameters**

Parameter	Type	Option	Description	Required
userIdOption	string	i	allows an admin to get information about a specific user identified by his/her userId	NO

#### **Environment variables**

This command defines no environment variables.

## 2.1.22 vishnu list sessions

#### Access

This command line can be used by any VISHNU user

## Description

The vishnu\_list\_sessions command lists all sessions of the user

#### Example of use

vishnu\_list\_sessions[-h][-t status][-p sessionClosePolicy][-d sessionInactivityDelay][-m machineId][-a][-u userId][-i sessionId][-s startDateOption][-e endDateOption]

Parameter	Type	Option	Description	Required
status	StatusType	t	specifies the status of the sessions which will be listed	NO

Parameter	Type	Option	Description	Required
sessionClosePolicy	SessionCloseType	p	specifies the closure mode of the sessions which will be listed (CLOSE_ON_TIMEOUT or CLOSE_ON_DISCONNECT)	NO
sessionInactivityDelay	int	d	specifies the inactivity delay in seconds of the sessions which will be listed	NO
machineId	string	m	allows the user to list sessions opened on a specific machine	NO
adminListOption	boolean	a	is an admin option for listing all sessions of all users	NO
userId	string	u	is an admin option for listing sessions opened by a specific user	NO
sessionId	string	i	allows the user to list all commands launched within a specific session	NO
startDateOption	long	S	allows the user to organize the commands listed by providing the start date (the UNIX timestamp of the start date is used)	NO
endDateOption	long	e	allows the user to organize the commands listed by providing the end date (the timestamp of the end date is used). By default, the end date is the current day	NO

This command defines no environment variables.

## 2.1.23 vishnu\_configure\_default\_option

## Access

This command line can be used by ADMIN users only

## Description

The vishnu\_configure\_default\_option command configures a default option value

## Example of use

vishnu\_configure\_default\_option[-h] optionName value

#### **Parameters**

Parameter	Type	Option	Description	Required
optionName	string		represents the name of an option	YES
value	string	1	represents the value of an option	YES

## **Environment variables**

This command defines no environment variables.

## 2.1.24 vishnu\_configure\_option

#### Access

This command line can be used by any VISHNU user

## Description

The vishnu\_configure\_option command configures an option of the user

## Example of use

vishnu\_configure\_option[-h] optionName value

## **Parameters**

Parameter	Type	Option	Description	Required
optionName	string		represents the name of an option	YES
value	string		represents the value of an option	YES

#### **Environment variables**

This command defines no environment variables.

## 2.2 Parameters definitions

**Enumeration UMS::PrivilegeType Type** 

Name	Value
USER	0
ADMIN	1

**Enumeration UMS::SessionCloseType Type** 

Name	Value
UNDEFINED	0
CLOSE_ON_TIMEOUT	1
CLOSE_ON_DISCONNECT	2

**Enumeration UMS::StatusType Type** 

Name	<b>Val</b> ue
INACTIVE	0
ACTIVE	1

# **Chapter 3**

# Commands specification for Tasks Management Service (TMS)

## 3.1 Command definitions

## 3.1.1 vishnu submit job

#### Access

This command line can be used by any VISHNU user

#### **Description**

The vishnu\_submit\_job command submits job on a machine through the use of a script (scriptFilePath). The script is a shell script which will be executed by a command shell such as sh or csh

#### Example of use

vishnu\_submit\_job[-h][-n name][-p priority][-q queue][-t wallTime][-m memory][-P nbCpu][-N n-bNodesAndCpuPerNode][-0 outPutPath][-e errorPath] machineId scriptFilePath

#### **Parameters**

Parameter	Туре	Option	Description	Required
machineId	string		Is the id of the machine where the job must be submitted	YES
scriptFilePath	string		The path to the file containing the characteristics (job command, and batch scheduler directive required or optional) of the job to submit.	YES
name	string	n	Assigns a job name. The default is the path of job.	NO
priority	JobPriority	p	Assigns priority of the job.	NO
queue	string	q	Assigns the queue or class of the job.	NO
wallTime	int	t	The maximum wall-clock time during which the job can run.	NO
memory	int	m	Is the memory size that the job requires.	NO
nbCpu	int	P	The number of cpu that the job requires.	NO
nbNodesAndCpuPerNode	string	N	The number of nodes and processors per node.	NO
outPutPath	string	0	Assigns the path and file for job output.	NO
errorPath	string	e	Assigns the path and file for job error.	NO

#### **Environment variables**

This command defines no environment variables.

## 3.1.2 vishnu\_get\_job\_info

#### Access

This command line can be used by any VISHNU user

#### Description

The vishnu\_get\_job\_info command gets information on a job from its id

#### Example of use

vishnu\_get\_job\_info[-h] machineId jobId

#### **Parameters**

Parameter	Type	Option	Description	Required
machineId	string		Machine hash key	YES
jobId	string		The id of the job	YES

#### **Environment variables**

This command defines no environment variables.

## 3.1.3 vishnu\_get\_job\_progress

#### Access

This command line can be used by any VISHNU user

## Description

The vishnu\_get\_job\_progress command gets the progression status of jobs

## Example of use

vishnu\_get\_job\_progress[-h][-i jobId][-u jobOwner] machineId

#### **Parameters**

Parameter	Type	Option	Description	Required
machineId	string		Is the id of the machine to get the jobs	YES
macminera	Sumg		progression.	TLS
jobId	string	i	Represents the id of the job that the user wants to	NO
Jobiu	Sumg	1	see the progression of.	110
jobOwner	string	u	Represents the owner of the job.	NO

#### **Environment variables**

This command defines no environment variables.

## 3.1.4 vishnu\_list\_queues

#### Access

This command line can be used by any VISHNU user

## Description

The vishnu\_list\_queues command gets queues information

#### Example of use

vishnu\_list\_queues[-h] machineId

#### **Parameters**

Parameter	Type	Option	Description	Required
machineId	string		Machine hash key	YES

#### **Environment variables**

This command defines no environment variables.

## 3.1.5 vishnu\_list\_jobs

#### Access

This command line can be used by any VISHNU user

## Description

The vishnu\_list\_jobs command gets a list of all submitted jobs

#### Example of use

vishnu\_list\_jobs[-h][-i jobId][-P nbCpu][-d fromSubmitDate][-D toSubmitDate][-u owner][-s status][-p priority][-o outPutPath][-e errorPath][-q queue] machineId

#### **Parameters**

Parameter	Type	Option	Description	Required
machineId	string		Machine hash key	YES
jobId	string	i	To list job which has this id.	NO
nbCpu	int	P	To list jobs which have this number of cpu.	NO
fromSubmitDate	long	d	List jobs submitted after this date (unix timestamp).	NO
toSubmitDate	long	D	List jobs submitted before this date (unix timestamp)	NO
owner	string	u	To list all jobs submitted by this owner.	NO
status	JobStatus	S	To list jobs which have this status.	NO
priority	JobPriority	p	To list jobs which have this priority	NO
outPutPath	string	0	Gets the path and file for each job output.	NO
errorPath	string	e	Gets the path and file for each job error.	NO
queue	string	q	To list jobs which have this queue name.	NO

#### **Environment variables**

This command defines no environment variables.

## 3.1.6 vishnu\_get\_job\_out\_put

#### Access

This command line can be used by any VISHNU user

## Description

The vishnu\_get\_job\_out\_put command gets outputPath and errorPath of a job from its id

## Example of use

vishnu\_get\_job\_out\_put [-h] machineId jobId

Parameter	Type	Option	Description	Required
machineId	string		Machine hash key	YES
jobId	string		The Id of the job	YES

This command defines no environment variables.

## 3.1.7 vishnu\_get\_all\_jobs\_out\_put

#### Access

This command line can be used by any VISHNU user

#### **Description**

The vishnu\_get\_all\_jobs\_out\_put command dynamically gets outputPath and errorPath of completed jobs

#### Example of use

vishnu\_get\_all\_jobs\_out\_put[-h] machineId

#### **Parameters**

Parameter	Type	Option	Description	Required
machineId	string		Machine hash key	YES

#### **Environment variables**

This command defines no environment variables.

## 3.1.8 vishnu\_cancel\_job

#### Access

This command line can be used by any VISHNU user

## Description

The vishnu\_cancel\_job command cancels a job from its id

## Example of use

vishnu\_cancel\_job[-h] machineId jobId

#### **Parameters**

Parameter	Type	Option	<b>Description</b>	Required
machineId	string		Machine hash key	YES
jobId	string		The Id of the job	YES

#### **Environment variables**

This command defines no environment variables.

## 3.1.9 vishnu\_set\_machine\_env

#### Access

This command line can be used by ADMIN users only

#### **Description**

The vishnu\_set\_machine\_env command sets environment variables on a remote machine

#### Example of use

vishnu\_set\_machine\_env[-h] machineId listEnv

#### **Parameters**

Parameter	Type	Option	Description	Required
machineId	string		Represents the machine id	YES
listEnv	string		Represents the list environement variables	YES

#### **Environment variables**

This command defines no environment variables.

## 3.1.10 vishnu\_set\_machine\_refresh\_period

#### Access

This command line can be used by ADMIN users only

#### **Description**

The vishnu\_set\_machine\_refresh\_period command sets the refresh period of output and error files contents

## Example of use

vishnu\_set\_machine\_refresh\_period[-h] machineId value

#### **Parameters**

Parameter	Type	Option	Description	Required
machineId	string		The id of the machine	YES
value	int		Is the refresh interval value (in seconds)	YES

#### **Environment variables**

This command defines no environment variables.

## 3.2 Parameters definitions

**Enumeration TMS::JobPriority Type** 

Name	<b>V</b> alue
VERY_LOW	100
LOW	200
NORMAL	300
HIGH	400
VERY_HIGH	500

## **Enumeration TMS::JobStatus Type**

Name	Value
RUNNING	0
WAITING	1

Name	Value
COMPLETED	2
CANCELED	3
HELD	4
QUEUED	5
FAILED	6
NOT_SUBMITTED	7

## **Enumeration TMS::QueuePriority Type**

Name	Value
VERY_LOW	0
LOW	1
NORMAL	2
HIGH	3
VERY_HIGH	4

## **Enumeration TMS::QueueStatus Type**

Name	Value
STARTED	0
RUNNING	1
NOT_STARTED	2
NOT_AVA <mark>ILABL</mark> E	3

# **Chapter 4**

# Commands specification for Information Management Service (IMS)

## 4.1 Command definitions

#### 4.1.1 vishnu export commands

#### Access

This command line can be used by any VISHNU user

#### **Description**

The vishnu\_export\_commands command exports all the commands made by a user during a session

#### Example of use

vishnu\_export\_commands [-h] oldSessionId

#### **Parameters**

Parameter	Type	Option	<b>Description</b>	Required
oldSessionId string	string		The id of the session to export (session has	YES
	string		ended)	1123

#### **Environment variables**

This command defines no environment variables.

## 4.1.2 vishnu\_get\_metric\_current\_value

#### Access

This command line can be used by any VISHNU user

#### **Description**

The vishnu\_get\_metric\_current\_value command retrieve the current value of a metric on a machine

#### Example of use

vishnu\_get\_metric\_current\_value [-h] machineId metricType

Parameter	Type	Option	Description	Required
machineId	string		The id of the machine	YES
metricType	MetricType		Type of metric	YES

This command defines no environment variables.

## 4.1.3 vishnu\_get\_metric\_history

#### Access

This command line can be used by any VISHNU user

#### **Description**

The vishnu\_get\_metric\_history command retrieve the history of values of a metric on a machine

#### Example of use

vishnu\_get\_metric\_history[-h] machineId startTime endTime metricType

#### **Parameters**

Parameter	Type	Option	Description	Required
machineId	string		The id of the machine	YES
startTime	long		Start time of metric history	YES
endTime	long		End time of metric history	YES
metricType	MetricType		Type of metric	YES

#### **Environment variables**

This command defines no environment variables.

## 4.1.4 vishnu\_get\_processes

#### Access

This command line can be used by ADMIN users only

## Description

The vishnu\_get\_processes command gets the list of the processes running over a front machine

## Example of use

vishnu\_get\_processes[-h] machineId

## **Parameters**

Parameter	Type	Option	Description	Required
machineId	string		The id of the machine the user wants the running processes	YES

#### **Environment variables**

This command defines no environment variables.

## 4.1.5 vishnu\_set\_system\_info

#### Access

This command line can be used by ADMIN users only

#### **Description**

The vishnu\_set\_system\_info command updates the system information of a machine

#### Example of use

vishnu\_set\_system\_info[-h][-m memory][-d diskSpace] machineId

#### **Parameters**

Parameter	Type	Option	Description	Required
machineId	string		The id of the machine	YES
memory	long	m	Amount of RAM memory available on the machine (in Bytes)	NO
diskSpace	long	d	Amount of disk space available on the machine (in Bytes)	NO

#### **Environment variables**

This command defines no environment variables.

## 4.1.6 vishnu\_set\_system\_threshold

#### Access

This command line can be used by ADMIN users only

#### **Description**

The vishnu\_set\_system\_threshold command sets a threshold on a machine of a system

#### Example of use

vishnu\_set\_system\_threshold[-h] machineId thresholdType value

#### **Parameters**

Parameter	Type	Option	<b>Description</b>	Required
machineId	string		The id of the machine	YES
thresholdType	MetricType		The type of the metric to set	YES
value	double		The threshold value	YES

#### **Environment variables**

This command defines no environment variables.

## 4.1.7 vishnu\_get\_system\_threshold

#### Access

This command line can be used by ADMIN users only

#### **Description**

The vishnu\_get\_system\_threshold command gets a System threshold on a machine

#### Example of use

vishnu\_get\_system\_threshold[-h] machineId type

Parameter	Type	Option	Description	Required
machineId	string		The id of the machine	YES
type	MetricType		The threshold type desired	YES

This command defines no environment variables.

## 4.1.8 vishnu\_define\_user\_identifier

#### Access

This command line can be used by ADMIN users only

#### **Description**

The vishnu\_define\_user\_identifier command defines the shape of the identifiers automatically generated for the users

#### Example of use

vishnu\_define\_user\_identifier[-h] format

#### **Parameters**

Parameter	Type	Option	Description	Required
format	string		The new format to use	YES

#### **Environment variables**

This command defines no environment variables.

### 4.1.9 vishnu\_define\_machine\_identifier

#### Access

This command line can be used by ADMIN users only

#### **Description**

The vishnu\_define\_machine\_identifier command defines the shape of the identifiers automatically generated for the machines

## Example of use

vishnu\_define\_machine\_identifier[-h] format

#### **Parameters**

Parameter	Type	Option	Description	Required
format	string		The new format to use	YES

#### **Environment variables**

This command defines no environment variables.

## 4.1.10 vishnu\_define\_job\_identifier

#### Access

This command line can be used by ADMIN users only

#### **Description**

The vishnu\_define\_job\_identifier command defines the shape of the identifiers automatically generated for the jobs

#### Example of use

vishnu\_define\_job\_identifier[-h] format

#### **Parameters**

Parameter	Type	Option	Description	Required
format	string	/	The new format to use	YES

#### **Environment variables**

This command defines no environment variables.

## 4.1.11 vishnu\_define\_transfer\_identifier

#### Access

This command line can be used by ADMIN users only

#### Description

The vishnu\_define\_transfer\_identifier command defines the shape of the identifiers automatically generated for the file transfers

#### Example of use

vishnu\_define\_transfer\_identifier[-h] format

#### **Parameters**

Parameter	Type	Option	Description	Required
format	string		The new format to use	YES

#### **Environment variables**

This command defines no environment variables.

## 4.1.12 vishnu\_load\_shed

#### Access

This command line can be used by ADMIN users only

#### **Description**

The vishnu\_load\_shed command load sheds a machine

#### Example of use

vishnu\_load\_shed[-h] machineId loadShedType

#### **Parameters**

Parameter	Type	Option	Description	Required
machineId	string		The id of the machine to stop	YES
loadShedType	LoadShedType		Selects a load shedding mode (SOFT: stops all services and they can be restarted, HARD: stops all services, they cannot be restarted)	YES

#### **Environment variables**

This command defines no environment variables.

## 4.1.13 vishnu\_set\_update\_frequency

#### Access

This command line can be used by ADMIN users only

#### **Description**

The vishnu\_set\_update\_frequency command sets the update frequency of the IMS tables

#### Example of use

vishnu\_set\_update\_frequency[-h] freq

#### **Parameters**

Parameter	Type	<b>Option</b>	Description	Req <mark>uire</mark> d
freq	int		Frequency the data are updated, in second	YES

#### **Environment variables**

This command defines no environment variables.

## 4.1.14 vishnu\_get\_update\_frequency

#### Access

This command line can be used by any VISHNU user

## Description

The vishnu\_get\_update\_frequency command gets the update frequency of the IMS database

## Example of use

vishnu\_get\_update\_frequency[-h]

#### **Parameters**

This command defines no arguments.

#### **Environment variables**

This command defines no environment variables.

#### 4.1.15 vishnu\_restart

## Access

This command line can be used by ADMIN users only

## Description

The vishnu\_restart command restarts the whole VISHNU infrastructure. Actions are saved and restarted from the beginning once the infrastructure has been restarted

#### Example of use

vishnu\_restart[-h][-n componentName][-m machineId][-f file] type

Parameter	Type	Option	Description	Required
type	RestartType		The type of restart	YES
componentName	string	n	If not restarting all, the name of the component to restart	NO
machineId	string	m	The id of the machine where the component is to be relaunched	NO
file	string	f	The config file to use to restart	NO

This command defines no environment variables.

## 4.2 Parameters definitions

## **Enumeration IMS::LoadShedType Type**

Name	Value
SOFT	0
HARD	1

## **Enumeration IMS::MetricType Type**

Name	Value
CPUNBR	0
CPUUSE	1
DISKSPACE	2
FREEDISKSPACE	3
MEMORY	4
FREEMEMORY	5

## **Enumeration IMS::RestartType Type**

Name		Value
ALL		0
SED		1
AGENT		2
DAEMON		3

# **Chapter 5**

# Commands specification for File Management Service (FMS)

## 5.1 Command definitions

## 5.1.1 vishnu create file

#### Access

This command line can be used by any VISHNU user

#### **Description**

The vishnu\_create\_file command creates files on remote machines.

## Example of use

vishnu\_create\_file[-h][-m mode] path

#### **Parameters**

Parameter	Type	Option	<b>Description</b>	Required
path	string		The file to create following the pattern [host:]file path	YES
mode	int	m	The file access permissions in octal numeral system	NO

#### **Environment variables**

This command defines no environment variables.

## 5.1.2 vishnu\_create\_dir

#### Access

This command line can be used by any VISHNU user

#### Description

The vishnu\_create\_dir command creates directories on remote machines.

## Example of use

vishnu\_create\_dir[-h][-m mode] path

Parameter	Type	Option	Description	Required
path	string		The directory to create following the pattern [host:]directory path	YES
mode	int	m	the new directories permission access in octal numeral system	NO

This command defines no environment variables.

## 5.1.3 vishnu\_remove\_file

#### Access

This command line can be used by any VISHNU user

#### **Description**

The vishnu\_remove\_file command removes files from remote hosts.

#### Example of use

vishnu\_remove\_file [-h] path

#### **Parameters**

Parameter	Type	Option	Description	Required
path	string		The file to remove following the pattern [host:]file path	YES

#### **Environment variables**

This command defines no environment variables.

## 5.1.4 vishnu\_remove\_dir

## Access

This command line can be used by any VISHNU user

## Description

The vishnu\_remove\_dir command removes directories (and subdirectories) from remote machines.

## Example of use

 ${\tt vishnu\_remove\_dir} \, [-h] \, {\tt path} \,$ 

#### **Parameters**

Parameter	Type	Option	Description	Required
path	string		The directory to remove following the pattern [host:]directory path	YES

## **Environment variables**

This command defines no environment variables.

## 5.1.5 vishnu\_ch\_grp

#### Access

This command line can be used by any VISHNU user

#### **Description**

The vishnu\_ch\_grp command changes group owner of remote files/directories.

#### Example of use

vishnu\_ch\_grp [-h] path group

#### **Parameters**

Parameter	Type	Option	Description	Required
path	string		The file/directory following the pattern [host:]file path	YES
group	string		the new group owner of file/directory	YES

#### **Environment variables**

This command defines no environment variables.

## 5.1.6 vishnu\_ch\_mod

#### Access

This command line can be used by any VISHNU user

#### **Description**

The vishnu\_ch\_mod command changes access rights of remote files/directories.

#### Example of use

vishnu\_ch\_mod[-h] path mode

#### **Parameters**

Parameter	Type	Option	Description	Required
path	string		The file/directory following the pattern [host:]file path	YES
mode	int		the access rigths of file/directory in octal system.	YES

#### **Environment variables**

This command defines no environment variables.

## 5.1.7 vishnu\_head\_of\_file

#### Access

This command line can be used by any VISHNU user

## Description

The vishnu\_head\_of\_file command displays a few first lines of files located on remote machines.

## Example of use

vishnu\_head\_of\_file[-h][-n nLine] path

Parameter	Type	Option	Description	Required
path	string		The file following the pattern [host:]file path	YES
nLine	int	n	Number of lines to display	NO

This command defines no environment variables.

## 5.1.8 vishnu\_tail\_of\_file

#### Access

This command line can be used by any VISHNU user

#### Description

The vishnu\_tail\_of\_file command displays a few last lines of files located on remote machines

#### Example of use

vishnu\_tail\_of\_file[-h][-n nLine] path

#### **Parameters**

Parameter	Type	Option	<b>Description</b>	Required
path	string		The file following the pattern [host:]file path	YES
nLine	int	n	number of lines to display	NO

#### **Environment variables**

This command defines no environment variables.

## 5.1.9 vishnu\_content\_of\_file

#### Access

This command line can be used by any VISHNU user

#### **Description**

The vishnu\_content\_of\_file command displays content of files located on remote machines

#### Example of use

vishnu\_content\_of\_file [-h] path

#### **Parameters**

Parameter	Type	Option	Description	Required
path	string		The file to display following the pattern [host:]file path	YES

#### **Environment variables**

This command defines no environment variables.

#### 5.1.10 vishnu list dir

#### Access

This command line can be used by any VISHNU user

#### Description

The vishnu\_list\_dir command displays the content of a remote directory.

#### Example of use

vishnu\_list\_dir[-h][-l][-a] path

#### **Parameters**

Parameter	Type	Option	Description	Required
path	string		The directory to list following the pattern	YES
	String		[host:]directory path	T ES
longFormat	boolean	1	It specifies the long display format (all available	NO
	boolean	1	file informations)	110
allFiles	boolean	a	Allows to display all files including hidden files	NO

#### **Environment variables**

This command defines no environment variables.

## 5.1.11 vishnu\_copy\_file

#### Access

This command line can be used by any VISHNU user

#### **Description**

The vishnu\_copy\_file command executes a synchronous copy of file.

#### Example of use

vishnu\_copy\_file[-h][-r][-c trCommand] src dest

#### **Parameters**

Parameter	Type	Option	Description	Required
src s	string		The source file to copy following the pattern	YES
			[host:]file path	
dest	string		The path of the destination file	YES
isRecursive boole	hooloon		It specifies when the copy is recursive (case of	NO
	boolean	1	directory) or not.	NO
trCommand	TransferCommand	С	the command to use to perform file transfer.	NO

#### **Environment variables**

Name	Parameter	Туре	Description	Req <mark>uire</mark> d	User option
VISHNU_TRANSFER_CMD	trCommand	TransferCommand	the command to use to perform file transfer.	NO	YES

## 5.1.12 vishnu\_copy\_async\_file

#### Access

This command line can be used by any VISHNU user

## Description

The vishnu\_copy\_async\_file command executes an asynchronous copy of file.

#### Example of use

 $\verb|vishnu_copy_async_file[-h][-r][-c trCommand]| src dest|\\$ 

Parameter	Type	Option	Option Description	
src	string		The source file to copy following the pattern [host:]file path	YES
dest	string		The path of the destination file	YES
isRecursive	boolean	r	It specifies when the copy is recursive (case of directory) or not.	NO
trCommand	TransferCommand	c	the command to use to perform file transfer.	NO

Name	Parameter	Type	Description	Required	User option
VISHNU_TRANSFER_CMD	trCommand	TransferCommand	the command to use to perform file transfer.	NO	YES

## 5.1.13 vishnu\_move\_file

#### Access

This command line can be used by any VISHNU user

#### **Description**

The vishnu\_move\_file command executes a synchronous move of file.

## Example of use

vishnu\_move\_file[-h][-c trCommand] src dest

#### **Parameters**

Parameter	Type	Option	<b>D</b> escription	Required
src	string	\	The source file to move following the pattern	YES
			[host:]file path	1123
dest	string		The path of the destination file	YES
trCommand	TransferCommand	С	the command to use to perform file transfer.	NO

#### **Environment variables**

Name	Parameter	Туре	Description	Required	User option
VISHNU_TRANSFER_CMD	trCommand	TransferCommand	the command to use to perform file transfer.	NO	YES

## 5.1.14 vishnu\_move\_async\_file

#### Access

This command line can be used by any VISHNU user

## **Description**

The vishnu\_move\_async\_file command executes an asynchronous move of file.

#### Example of use

vishnu\_move\_async\_file[-h][-c trCommand] src dest

Parameter	Type	Option	Description	Required
src	string		The source file to move following the pattern [host:]file path	YES
dest	string		The path of the destination file	YES
trCommand	TransferCommand	С	the command to use to perform file transfer.	NO

Name	Parameter	Туре	Description	Required	User option
VISHNU_TRANSFER_CMD	trCommand	TransferCommand	the command to use to perform file transfer.	NO	YES

## 5.1.15 vishnu\_stop\_file\_transfer

#### Access

This command line can be used by any VISHNU user

## Description

The vishnu\_stop\_file\_transfer command stops an execution of a set of file transfers.

#### Example of use

vishnu\_stop\_file\_transfer[-h][-i transferId][-m fromMachineId][-u userId]

#### **Parameters**

Parameter	Type	Option	Description	Required
transferId	string	i	a given transfer id	NO
fromMachineId	string	m	the machine that is the source of the file transfer	NO
userId	string	u	allows an admin to stop file transfers of a specific user	NO

#### **Environment variables**

This command defines no environment variables.

## 5.1.16 vishnu\_list\_file\_transfer\_status

#### Access

This command line can be used by any VISHNU user

## Description

The vishnu\_list\_file\_transfer\_status command displays the status of all file transfers submitted by User.

#### Example of use

vishnu\_list\_file\_transfer\_status[-h][-i transferId][-m fromMachineId][-u userId]

Parameter	Type	Option	Description	Required
transferId	string	i	a given transfer id	NO
fromMachineId	string	m	the machine that is the source of the file transfer	NO
userId	string	u	allows the admin to list file transfers initiated by a specific user	NO

This command defines no environment variables.

## 5.1.17 vishnu\_list\_file\_transfers

#### Access

This command line can be used by any VISHNU user

## Description

The vishnu\_list\_file\_transfers command displays the history of all file transfers submitted by User.

#### Example of use

vishnu\_list\_file\_transfers[-h][-m fromMachineId][-u userId][-s status]

#### **Parameters**

Parameter	Type	Option	Description	Required
fromMachineId	string	m	the machine that is the source of the file transfer	NO
userId	string	u	allows the admin to list file transfers initiated by a specific user	NO
status	Status	S	the file transfer status	NO

#### **Environment variables**

This command defines no environment variables.

## 5.2 Parameters definitions

**Enumeration FMS::FileType Type** 

Name	Value
BLOCK	0
CHARACTER	1
DIRECTORY	2
SYMBOLICLINK	3
SCKT	4
FIFO	5
REGULAR	6

## **Enumeration FMS::Status Type**

Name	Value
INPROGRESS	0
COMPLETED	1
CANCELLED	2
FAILED	3

## **Enumeration FMS::TransferCommand Type**

Name	Value
SCP	0
RSYNC	1