D1.1d - VISHNU Command-line
interface specifications

D1.1d - VISHNU Command-line interface specifications



CO	 ΛО	$\boldsymbol{\cap}$	ΛТ	n	3C
	 40	חנו	A I	.	٦.7

	TITLE: D1.1d - VISHNU Co	ommand-line interface		
ACTION	NAME	DATE	SIGNATURE	
WRITTEN BY	Benjamin Isnard, Daouda Traoré, Eugène Pamba Capo-Chichi, Kevin Coulomb, and Ibrahima Cissé	January 27, 2011		

REVISION HISTORY

NUMBER	DATE	DESCRIPTION	NAME
0	05/01/2011	Formatting example	SysFera
1	13/01/2011	First release	SysFera

Contents

1	Docu	_	presentation	1
	1.1	Docum	nent objectives	1
	1.2		nent structure	
	1.3		nces	
	1.4	Glossa	ry	1
	1.5	Generic	c command definition format	2
	1.6	Enviro	onment variables and options	2
2	Com	mands	specification for User Management System (UMS)	4
	2.1	Comma	and definitions	
		2.1.1	UMS connect	4
		2.1.2	UMS reconnect	4
		2.1.3	UMS addVishnuUser	5
		2.1.4	UMS updateUser	5
		2.1.5	UMS deleteUser	6
		2.1.6	UMS close	6
		2.1.7	UMS changePassword	7
		2.1.8	UMS resetPassword	7
		2.1.9	UMS addLocalAccount	
		2.1.10	UMS updateLocalAccount	8
		2.1.11	UMS deleteLocalAccount	9
		2.1.12	UMS saveConfiguration	10
			UMS restoreConfiguration	
		2.1.14	UMS addMachine	11
		2.1.15	UMS updateMachine	11
		2.1.16	UMS deleteMachine	12
		2.1.17	UMS listLocalAccount	12
		2.1.18	UMS listMachine	13
		2.1.19	UMS listHistoryCmd	13
		2.1.20	UMS listOptions	14

		2.1.21	UMS listUsers	14
			UMS listSessions	
		2.1.23	UMS configureDefaultOption	16
		2.1.24	UMS configureOption	16
	2.2	Parame	eters definitions	17
3	Con	ımands	specification for Tasks Management System (TMS)	18
	3.1	Comm	and definitions	18
		3.1.1	TMS submitJob	
		3.1.2	TMS getJobInfo	
		3.1.3	TMS getJobProgress	19
		3.1.4	TMS listQueues	20
		3.1.5	TMS listJobs	20
		3.1.6	TMS getJobOutPut	21
		3.1.7	TMS getAllJobsOutPut	
		3.1.8	TMS cancelJob	22
		3.1.9	TMS setMachineEnv	22
			TMS setMachineRefreshPeriod	
	3.2	Parame	eters definitions	23
4	Corr	nmands	specification for Information Management System (IMS)	25
4			specification for Information Management System (IMS)	25
4	Con 4.1	Comm	and definitions	25
4		Comm 4.1.1	and definitions	25 25
4		Comm	IMS getMetricCurrentValue	252525
4		Comm 4.1.1 4.1.2	IMS getMetricHistory	25252526
4		Comm 4.1.1 4.1.2 4.1.3	IMS getMetricCurrentValue	25 25 25 26 26
4		Comm 4.1.1 4.1.2 4.1.3 4.1.4	IMS getMetricCurrentValue IMS getMetricHistory IMS getProcesses	25 25 25 26 26 27
4		Comm 4.1.1 4.1.2 4.1.3 4.1.4 4.1.5	IMS exportCommands IMS getMetricCurrentValue IMS getMetricHistory IMS getProcesses IMS setSystemInfo IMS setSystemThreshold	25 25 26 26 27 27
4		Comm 4.1.1 4.1.2 4.1.3 4.1.4 4.1.5 4.1.6	IMS exportCommands IMS getMetricCurrentValue IMS getMetricHistory IMS getProcesses IMS setSystemInfo	25 25 25 26 26 27 27 28
4		Comm 4.1.1 4.1.2 4.1.3 4.1.4 4.1.5 4.1.6 4.1.7	and definitions IMS exportCommands IMS getMetricCurrentValue IMS getMetricHistory IMS getProcesses IMS setSystemInfo IMS setSystemThreshold IMS getSystemThreshold	25 25 25 26 26 27 27 28 28
4		Comm 4.1.1 4.1.2 4.1.3 4.1.4 4.1.5 4.1.6 4.1.7 4.1.8 4.1.9	IMS exportCommands IMS getMetricCurrentValue IMS getMetricHistory IMS getProcesses IMS setSystemInfo IMS setSystemThreshold IMS getSystemThreshold IMS defineUserIdentifier IMS defineMachineIdentifier	25 25 26 26 27 27 28 28 29
4		Comm 4.1.1 4.1.2 4.1.3 4.1.4 4.1.5 4.1.6 4.1.7 4.1.8 4.1.9 4.1.10	IMS exportCommands IMS getMetricCurrentValue IMS getMetricHistory IMS getProcesses IMS setSystemInfo IMS setSystemThreshold IMS getSystemThreshold IMS defineUserIdentifier	25 25 26 26 27 27 28 28 29
4		Comm 4.1.1 4.1.2 4.1.3 4.1.4 4.1.5 4.1.6 4.1.7 4.1.8 4.1.9 4.1.10 4.1.11	IMS exportCommands IMS getMetricCurrentValue IMS getMetricHistory IMS getProcesses IMS setSystemInfo IMS setSystemThreshold IMS getSystemThreshold IMS defineUserIdentifier IMS defineMachineIdentifier IMS defineJobIdentifier	25 25 26 26 27 27 28 28 29 29
4		Comm 4.1.1 4.1.2 4.1.3 4.1.4 4.1.5 4.1.6 4.1.7 4.1.8 4.1.9 4.1.10 4.1.11 4.1.12	IMS exportCommands IMS getMetricCurrentValue IMS getMetricHistory IMS getProcesses IMS setSystemInfo IMS setSystemThreshold IMS getSystemThreshold IMS defineUserIdentifier IMS defineMachineIdentifier IMS defineJobIdentifier	25 25 26 26 27 27 28 28 29 29 30 30
4		Comm 4.1.1 4.1.2 4.1.3 4.1.4 4.1.5 4.1.6 4.1.7 4.1.8 4.1.9 4.1.10 4.1.11 4.1.12 4.1.13	IMS exportCommands IMS getMetricCurrentValue IMS getMetricHistory IMS getProcesses IMS setSystemInfo IMS setSystemThreshold IMS getSystemThreshold IMS defineUserIdentifier IMS defineMachineIdentifier IMS defineJobIdentifier IMS defineTransferIdentifier IMS loadShed	25 25 26 26 27 27 28 28 29 29 30 30 31
4		Comm 4.1.1 4.1.2 4.1.3 4.1.4 4.1.5 4.1.6 4.1.7 4.1.8 4.1.9 4.1.10 4.1.11 4.1.12 4.1.13 4.1.14	IMS exportCommands IMS getMetricCurrentValue IMS getMetricHistory IMS getProcesses IMS setSystemInfo IMS setSystemThreshold IMS getSystemThreshold IMS defineUserIdentifier IMS defineMachineIdentifier IMS defineJobIdentifier IMS defineTransferIdentifier IMS defineTransferIdentifier IMS defineTransferIdentifier	25 25 26 26 27 27 28 29 29 30 31 31

5	Com	mands	specification for File Management System (FMS)	34
	5.1	Comma	and definitions	. 34
		5.1.1	FMS createFile	. 34
		5.1.2	FMS createDir	. 34
		5.1.3	FMS removeFile	. 35
		5.1.4	FMS removeDir	. 35
		5.1.5	FMS chGrp	. 36
		5.1.6	FMS chMod	. 36
		5.1.7	FMS headOfFile	. 37
		5.1.8	FMS tailOfFile	. 37
		5.1.9	FMS contentOfFile	. 37
		5.1.10	FMS listDir	. 38
		5.1.11	FMS copyFile	. 38
		5.1.12	FMS copyAsyncFile	. 39
		5.1.13	FMS moveFile	. 39
			FMS moveAsyncFile	
		5.1.15	FMS stopFileTransfer	. 40
		5.1.16	FMS listFileTransferStatus	4
		5.1.17	FMS listFileTransfers	4!
	5.2	Doromo	otars definitions	10

Chapter 1

Document presentation

1.1 Document objectives

This document presents the detailed specifications of the VISHNU command line user interface.

These specifications include the definition of all commands including administration commands.

1.2 Document structure

The document is divided into 4 parts corresponding to the 4 modules that compose the Vishnu system:

- UMS: Users Management System
- TMS: Tasks Management System
- FMS: Files Management System
- IMS: Information Management System

Each module corresponds to a chapter in the document, and each chapter contains the following sections:

- A first section describing the definition of all commands provided by the package.
- A second section describing the definition of all enumerated values used as command parameters.

1.3 References

• D1.1a: VISHNU General specifications

1.4 Glossary

• VISHNU admin: any user having the administrator privilege

1.5 Generic command definition format

This section presents the generic format used in the following chapters to describe the commands. It also details the environment variables required and the user options.

A commands is defined as follows:

Access

Here is detailed the access level of the command line (i.e. the privilege required to use this command)

Description

Here is detailed the purpose of the command line.

Example of use

Here is detailed an example of the use of the command line which starts by optional arguments preceded by a short letter and the required arguments at the end.

myCommand -l acLogin -s sshKeyPath userId

Parameters

The following table contains all the input arguments of the command with their type and description, their short letter for options and a required flag.

Parameter	Type	Option	Description	Required
userId	string		This is an example of a required argument	YES
acLogin	string	1	This is an example of an optional argument	NO
sshKeyPath	string	S	This is an example of an optional argument	NO

The following table contains the list of environment variables information, a required flag and a user option flag. When the user option flag is true, the environment variable can be defined as a user option stored in the database.

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	This is an example of an environment variable	YES	NO

Note:

For each command line the -h option can be used for help.

1.6 Environment variables and options

Here is detailed the way to use the user options which are stored in the database and environment variables in VISHNU.

Example 1.1 Pseudo code

```
if (the option is provided in the command line) {
    optionValue = option
} else {
    if (an environment variable exists) {
        optionValue = EnVariable_Value

    } else {

        if (a value has been defined in the user configuration) {
            optionValue = user_Option
        }
        else {
            //The default value of the option defined by VISHNU admin is used optionValue = defaultValueOption
        }
    }
}
```

Chapter 2

Commands specification for User Management System (UMS)

2.1 Command definitions

2.1.1 UMS connect

Access

This command line can be used by any VISHNU user

Description

The connect command line opens a session

Example of use

connect [-p closePolicy][-d sessionInactivityDelay][-s substituteUserId] userId

Parameters

Parameter	Type	Option	Description	Required
userId	string		userId represents the VISHNU user identifier	YES
password	string		password represents the password of the user, it is an interactive parameter	YES
closePolicy	SessionCloseType	p	is an option for closing session automatically	NO
sessionInactivityDelay	int	d	The sessionInactivityDelay is the maximum delay in seconds between two API commands when the CLOSE_ON_TIMEOUT option is set	NO
substituteUserId	string	s	is an option which allows an admin to open a session as if he/she was a specific user identified by his/her userId	NO

Environment variables

This command defines no environment variables.

2.1.2 UMS reconnect

Access

This command line can be used by any VISHNU user

Description

The reconnect command line returns the sessionKey of a session in which the user was disconnected previously without closing it

Example of use

reconnect userId sessionId

Parameters

Parameter	Type	Option	Description	Required
userId	string	/	userId represents the VISHNU user identifier	YES
password	string		password represents the password of the user, it is an interactive parameter	YES
sessionId	string		sessionId is the identifier of the session defined in the database	YES

Environment variables

This command defines no environment variables.

2.1.3 UMS addVishnuUser

Access

This command line can be used by ADMIN users only

Description

The addVishnuUser command line adds a new VISHNU user

Example of use

addVishnuUser privilege userId firstname lastname email

Parameters

Parameter	Type	Option	Description	Required
userId	string		represents the VISHNU user identifier	YES
firstname	string		is the firstname of the user	YES
lastname	string		is the lastname of the user	YES
privilege	PrivilegeType		is the privilege of the user (admin or simple user)	YES
email	string		is the email of the user	YES

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The sessionKey is the encrypted identifier of the session generated by VISHNU	YES	NO

2.1.4 UMS updateUser

Access

This command line can be used by ADMIN users only

Description

The updateUser command line updates the user information except the userId and the password

Example of use

updateUser[-f firstname][-l lastname][-p privilege][-m email]userId

Parameters

Parameter	Type	Option	Description	Required
userId	string		represents the VISHNU user identifier	YES
firstname	string	f	represents the updated firstname of the user	NO
lastname	string	1	represents the updated lastname of the user	NO
privilege	PrivilegeType	p	represents the updated privilege of the user	NO
email	string	m	represents the updated email adress of the user	NO

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The sessionKey is the encrypted identifier of the session generated by VISHNU	YES	NO

2.1.5 UMS deleteUser

Access

This command line can be used by ADMIN users only

Description

The deleteUser command line removes a user from VISHNU

Example of use

deleteUser userId

Parameters

Parameter	Type	Option	Description	Required
userId	string		userId represents the VISHNU user identifier of the user who will be deleted from VISHNU	YES

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The sessionKey is the encrypted identifier of the session generated by VISHNU	YES	NO

2.1.6 UMS close

Access

This command line can be used by any VISHNU user

Description

The close command line closes the session identified by the session key

Example of use

close

Parameters

This command defines no arguments.

Environment variables

Name	Parameter	Type	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The sessionKey is the encrypted identifier of the session generated by VISHNU	YES	NO

2.1.7 UMS changePassword

Access

This command line can be used by any VISHNU user

Description

The changePassword command line changes the password

Example of use

changePassword userId

Parameters

Parameter	Type	Option	Description	Required
userId	string		userId represents the VISHNU user identifier	YES
password	string		password represents the password of the user, it is an interactive parameter	YES
passwordNew	string		passwordNew represents the new password of the user, it is an interactive parameter	YES

Environment variables

This command defines no environment variables.

2.1.8 UMS resetPassword

Access

This command line can be used by ADMIN users only

Description

The resetPassword command line resets the password of a user

Example of use

resetPassword userId

Parameter	Type	Option	Description	Required
userId	string		userId represents the VISHNU user identifier of the user whose password will be reset	YES

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The sessionKey is the encrypted identifier of the session generated by VISHNU	YES	NO

2.1.9 UMS addLocalAccount

Access

This command line can be used by any VISHNU user

Description

The addLocalAccount command line adds a new local user configuration

Example of use

addLocalAccount userId machineId acLogin sshKeyPath homeDirectory

Parameters

Parameter	Type	Option	Description	Required
userId	string		The userId represents the VISHNU user identifier	YES
uscriu	sumg		of the user of the local user configuration	1123
machineId string		The MachineId represents the identifier of the	YES	
		machine associated to the local user configuration	1 LS	
acLogin	acLogin string		accLogin represents the login of the user on the	YES
acLogiii	sumg		associated machine	1L5
sshKeyPath	string		sshKeyPath is the path of the ssh key of the user	YES
sameyr aur	sumg		on the associated machine	1123
homeDirectory	string		HomeDirectory is the path of the home directory	YES
	Sumg		of the user on the associated machine	ILS

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The sessionKey is the encrypted identifier of the session generated by VISHNU	YES	NO

2.1.10 UMS updateLocalAccount

Access

This command line can be used by any VISHNU user

Description

The updateLocalAccount command line updates a local user configuration $\,$

Example of use

updateLocalAccount [-l acLogin] [-s sshKeyPath] [-d homeDirectory] userId machineId

Parameters

Parameter	Type	Option	Description	Required
userId	string		The userId represents the VISHNU user identifier	YES
machineId	string		of the user of the local user configuration The MachineId represents the identifier of the	YES
machinerd string			machine associated to the local user configuration	TES
acLogin	string	1	accLogin represents the login of the user on the associated machine	NO
sshKeyPath	string	S	sshKeyPath is the path of the ssh key of the user on the associated machine	NO
homeDirectory	string	d	HomeDirectory is the path of the home directory of the user on the associated machine	NO

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The sessionKey is the encrypted identifier of the session generated by VISHNU	YES	NO

2.1.11 UMS deleteLocalAccount

Access

This command line can be used by any VISHNU user

Description

The deleteLocalAccount command line removes a local user configuration (for a given user on a given machine) from VISHNU

Example of use

deleteLocalAccount userId machineId

Parameters

Parameter	Type	Option	Description	Required
			userId represents the VISHNU user identifier of	
userId	string		the user whose local configuration will be deleted	YES
			for the given machine	
			machineId represents the identifier of the	
machineId	string		machine whose local configuration will be	YES
			deleted for the given user	

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The sessionKey is the encrypted identifier of the session generated by VISHNU	YES	NO

2.1.12 UMS saveConfiguration

Access

This command line can be used by ADMIN users only

Description

The saveConfiguration command line saves the configuration of VISHNU

Example of use

saveConfiguration filePath

Parameters

Parameter	Type	Option	Descri ption	Required
filePath	string		The filePath is the path of the file in which the VISHNU configuration will be saved	YES

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The sessionKey is the encrypted identifier of the session generated by VISHNU	YES	NO

2.1.13 UMS restoreConfiguration

Access

This command line can be used by ADMIN users only

Description

The restoreConfiguration command line restores the configuration of VISHNU

Example of use

restoreConfiguration filePath

Parameters

Parameter	Туре	Option	Description	Required
filePath	string		The filePath is the path of the VISHNU configuration file	YES

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The sessionKey is the encrypted identifier of the session generated by VISHNU	YES	NO

2.1.14 UMS addMachine

Access

This command line can be used by ADMIN users only

Description

The addMachine command line adds a new machine in VISHNU

Example of use

addMachine name site language

Parameters

Parameter	Type	Option	Description	Req <mark>uired</mark>
name	string		represents the name of the machine	YES
site	string		represents the location of the machine	YES
machineDescription	string		represents the description of the machine, it is an	YES
•	0		interactive parameter	
language	string		represents the language in which the description	YES
			of the machine has been done	1123

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The sessionKey is the encrypted identifier of the session generated by VISHNU	YES	NO

2.1.15 UMS updateMachine

Access

This command line can be used by ADMIN users only

Description

The updateMachine command line updates machine description

Example of use

updateMachine [-n name] [-s site] [-d] [-l language] machineId

Parameters

Parameter	Type	Option	Description	Required
machineId	string		represents the identifier of the machine	YES
name	string	n	represents the name of the machine	NO
site	string	S	represents the location of the machine	NO
machineDescription	string	d	represents the description of the machine, it is an interactive parameter	NO
language	string	1	represents the language in which the description of the machine has been done	NO

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The sessionKey is the encrypted identifier of the session generated by VISHNU	YES	NO

2.1.16 UMS deleteMachine

Access

This command line can be used by ADMIN users only

Description

The deleteMachine command line removes a machine from VISHNU

Example of use

deleteMachine machineId

Parameters

Parameter	Type	Option	Description	Required
machineId	string		machineId represents the identifier of the machine	YES

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The sessionKey is the encrypted identifier of the session generated by VISHNU	YES	NO

2.1.17 UMS listLocalAccount

Access

This command line can be used by any VISHNU user

Description

The listLocalAccount command line lists the local user configurations

Example of use

listLocalAccount [-a][-u userId][-i machineId]

Parameter	Type	Option	Description	Required
adminListOption boolean	hooloon	a	is an admin option for listing all local	NO
	boolean		configurations of all users	110
userId	string	u	is an admin option for listing the local	NO
useria	sumg	l u	configurations of a specific user	110
machineId	string	i	is an option for listing local user configurations	NO
macminera	Sumg	1	on a specific machine	110

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The sessionKey is the encrypted identifier of the session generated by VISHNU	YES	NO

2.1.18 UMS listMachine

Access

This command line can be used by any VISHNU user

Description

The listMachine command line lists the machines in which the local user configurations are defined for the given user

Example of use

listMachine [-u userId][-a][-m machineId]

Parameters

Parameter	Type	Option	Description	Required
userId	string	u	is an admin option for listing machines in which a specific user has a local configuration	NO
listAllmachine	boolean	a	is an option for listing all VISHNU machines	NO
machineId	string	m	is an option for listing information about a specific machine	NO

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The sessionKey is the encrypted identifier of the session generated by VISHNU	YES	NO

2.1.19 UMS listHistoryCmd

Access

This command line can be used by any VISHNU user

Description

The listHistoryCmd command line lists the commands

Example of use

 $\label{listHistoryCmd} $$ [-a] [-u \ \textit{userId} \] [-i \ \textit{sessionId} \] [-s \ \textit{startDateOption} \] [-e \ \textit{endDateOption} \] $$$

Parameter	Type	Option	Description	Required
adminListOption	boolean	a	is an admin option for listing all commands of all users	NO

Parameter	Type	Option	Description	Required
userId	string	u	is an admin option for listing commands launched	NO
uscriu	Sumg	u	by a specific user identified by his/her userId	110
sessionId	string	i	lists all commands launched within a specific	NO
sessionia	sumg	1	session	NO
		S	allows the user to organize the commands listed	
startDateOption	long		by providing the start date (the UNIX timestamp	NO
			of the start date is used)	_
		/	allows the user to organize the commands listed	
endDateOption	long	e	by providing the end date (the timestamp of the	NO
			end date is used). By default, the end date is the	NO
			current day	

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The sessionKey is the encrypted identifier of the session generated by VISHNU	YES	NO

2.1.20 UMS listOptions

Access

This command line can be used by any VISHNU user

Description

The listOptions command line lists the options of the user

Example of use

listOptions [-a][-u userId][-n optionName]

Parameters

Parameter	Type	Option	Description	Required
listAllDeftValue	boolean	a	is an option for listing all default option values defined by VISHNU administrator	NO
userId	string	u	is an admin option for listing the options of a specific user	NO
optionName	string	n	allows the user to get the value of a specific option identified by its name	NO

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	. 17	.4.*	The sessionKey is the	YES	NO
	sessionKey	string	identifier of the session generated by VISHNU		NO

2.1.21 UMS listUsers

Access

This command line can be used by ADMIN users only

Description

The listUsers command line lists VISHNU users

Example of use

listUsers [-i userIdOption]

Parameters

Parameter	Type	Option	Description	Required
userIdOption	string	i	allows an admin to get information about a specific user identified by his/her userId	NO

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The sessionKey is the identifier of the session generated by VISHNU	YES	NO

2.1.22 UMS listSessions

Access

This command line can be used by any VISHNU user

Description

The listSessions command line lists all sessions of the user

Example of use

listSessions [-t sessionListOption] [-p sessionClosePolicy] [-d sessionInactivityDelay] [-m machineId] [-a] [-u userId] [-i sessionId] [-s startDateOption] [-e endDateOption]

Parameter	Type	Option	Description	Required
sessionListOption	SessionStateType	t	specifies the type of the sessions which will be listed (INACTIVE or ACTIVE)	NO
sessionClosePolicy	SessionCloseType	p	specifies the closure mode of the sessions which will be listed (CLOSE_ON_TIMEOUT or CLOSE_ON_DISCONNECT)	NO
sessionInactivityDelay	int	d	specifies the inactivity delay in seconds of the sessions which will be listed	NO
machineId	string	m	allows the user to list sessions opened on a specific machine	NO
adminListOption	boolean	a	is an admin option for listing all sessions of all users	NO
userId	string	u	is an admin option for listing sessions opened by a specific user	NO
sessionId	string	i	allows the user to list all commands launched within a specific session	NO
startDateOption	long	S	allows the user to organize the commands listed by providing the start date (the UNIX timestamp of the start date is used)	NO

Parameter	Туре	Option	Description	Required
endDateOption	long	e	allows the user to organize the commands listed by providing the end date (the timestamp of the end date is used). By default, the end date is the current day	NO

Name	Parameter	Type	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The sessionKey is the encrypted identifier of the session generated by VISHNU	YES	NO

2.1.23 UMS configureDefaultOption

Access

This command line can be used by ADMIN users only

Description

The configureDefaultOption command line configures a default option value

Example of use

configureDefaultOption optionName value

Parameters

Parameter	Type	Option	Description	Required
optionName	string		represents the name of an option	YES
value	string		represents the value of an option	YES

Environment variables

Name	Parameter	Type	Description	R <mark>equi</mark> red	User option
VISHNU_SESSION_KEY	sessionKey	string	The sessionKey is the encrypted identifier of the session generated by VISHNU	YES	NO

2.1.24 UMS configureOption

Access

This command line can be used by any VISHNU user

Description

The configureOption command line configures an option of the user

Example of use

configureOption optionName value

Parameter	Type	Option	Description	Required
optionName	string		represents the name of an option	YES
value	string		represents the value of an option	YES

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The sessionKey is the encrypted identifier of the session generated by VISHNU	YES	NO

2.2 Parameters definitions

Enumeration UMS::PrivilegeType Type

Name	Value
USER	0
ADMIN	1

Enumeration UMS::SessionCloseType Type

Name	Value
CLOSE_ON_TIMEOUT	0
CLOSE_ON_DISCONNECT	1

Enumeration UMS::SessionStateType Type

Name	Value
INACTIVE	0
ACTIVE	1

Chapter 3

Commands specification for Tasks Management System (TMS)

3.1 Command definitions

3.1.1 TMS submitJob

Access

This command line can be used by any VISHNU user

Description

The submitJob command line submits job on a machine through the use of a script (scriptFilePath). The script is a shell script which will be executed by a command shell such as sh or csh

Example of use

submitJob [-n name][-p priority][-q queue][-t wallTime][-m memory][-P nbCpu][-N nbNodesAndC-puPerNode][-o outPutPath][-e errorPath] machineId scriptFilePath

Parameters

Parameter	Туре	Option	Description	Required
machineId	string		Is the id of the machine where the job must be submitted	YES
scriptFilePath	string		The path to the file containing the characteristics (job command, and batch scheduler directive required or optional) of the job to submit.	YES
name	string	n	Assigns a job name. The default is the path of job.	NO
priority	JobPriority	p	Assigns priority of the job.	NO
queue	string	q	Assigns the queue or class of the job.	NO
wallTime	int	t	The maximum wall-clock time during which the job can run.	NO
memory	int	m	Is the memory size that the job requires.	NO
nbCpu	int	P	The number of cpu that the job requires.	NO
nbNodesAndCpuPerNode	string	N	The number of nodes and processors per node.	NO
outPutPath	string	0	Assigns the path and file for job output.	NO
errorPath	string	e	Assigns the path and file for job error.	NO

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The sessionKey is the identifier of the session generated by VISHNU	YES	NO

3.1.2 TMS getJobInfo

Access

This command line can be used by any VISHNU user

Description

The getJobInfo command line gets information on a job from its id

Example of use

getJobInfo machineId jobId

Parameters

Parameter	Type	Option	Description	Required
machineId	string		Machine hash key	YES
jobId	string	/	The id of the job	YES

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The sessionKey is the identifier of the session generated by VISHNU	YES	NO

3.1.3 TMS getJobProgress

Access

This command line can be used by any VISHNU user

Description

The getJobProgress command line gets the progression status of jobs

Example of use

getJobProgress [-i jobId][-u jobOwner] machineId

Parameters

Parameter	Type	Option	Description	Required
machineId	string		Is the id of the machine to get the jobs	YES
	String		progression.	TLS
jobId s	string	i	Represents the id of the job that the user wants to	NO
	Sumg	1	see the progression of.	110
jobOwner	string	u	Represents the owner of the job.	NO

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The sessionKey is the identifier of the session generated by VISHNU	YES	NO

3.1.4 TMS listQueues

Access

This command line can be used by any VISHNU user

Description

The listQueues command line gets queues information

Example of use

listQueues machineId

Parameters

Parameter	Type	Option	Description	Required
machineId	string		Machine hash key	YES

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The sessionKey is the identifier of the session generated by VISHNU	YES	NO

3.1.5 TMS listJobs

Access

This command line can be used by any VISHNU user

Description

The listJobs command line gets a list of all submitted jobs

Example of use

listJobs [-i jobId][-P nbCpu][-d fromSubmitDate][-D toSubmitDate][-u owner][-s status][-p priority][-o outPutPath][-e errorPath][-q queue] machineId

Parameter	Type	Option	Description	Required
machineId	string		Machine hash key	YES
jobId	string	i	To list job which has this id.	NO
nbCpu	int	P	To list jobs which have this number of cpu.	NO
fromSubmitDate	long	d	List jobs submitted after this date (unix timestamp).	NO
toSubmitDate	long	D	List jobs submitted before this date (unix timestamp)	NO
owner	string	u	To list all jobs submitted by this owner.	NO
status	JobStatus	S	To list jobs which have this status.	NO

Parameter	Type	Option	Description	Required
priority	JobPriority	p	To list jobs which have this priority	NO
outPutPath	string	О	Gets the path and file for each job output.	NO
errorPath	string	e	Gets the path and file for each job error.	NO
queue	string	q	To list jobs which have this queue name.	NO

Name	Parameter	Type	Description	Required	User option
VISHNU_SESSION_KEY	iW	string	The sessionKey is the identifier of the session	YES	NO
	sessionKey	string	generated by VISHNU	I ES	NO

3.1.6 TMS getJobOutPut

Access

This command line can be used by any VISHNU user

Description

The getJobOutPut command line gets outputPath and errorPath of a job from its id

Example of use

getJobOutPut machineId jobId

Parameters

Parameter	Type	Option	Description	Required
machineId	string		Machine hash key	YES
jobId	string		The Id of the job	YES

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The sessionKey is the identifier of the session generated by VISHNU	YES	NO

3.1.7 TMS getAllJobsOutPut

Access

This command line can be used by any VISHNU user

Description

The getAllJobsOutPut command line dynamically gets outputPath and errorPath of completed jobs

Example of use

getAllJobsOutPut machineId

Parameter	Type	Option	Description	Required
machineId	string		Machine hash key	YES

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The sessionKey is the identifier of the session generated by VISHNU	YES	NO

3.1.8 TMS cancelJob

Access

This command line can be used by any VISHNU user

Description

The cancelJob command line cancels a job from its id

Example of use

cancelJob machineId jobId

Parameters

Parameter	Type	Option	Description	Required
machineId	string		Machine hash key	YES
jobId	string		The Id of the job	YES

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The sessionKey is the identifier of the session generated by VISHNU	YES	NO

3.1.9 TMS setMachineEnv

Access

This command line can be used by ADMIN users only

Description

The setMachineEnv command line sets environment variables on a remote machine

Example of use

setMachineEnv machineId listEnv

Parameters

Parameter	Type	Option	Description	Required
machineId	string		Represents the machine id	YES
listEnv	string		Represents the list environement variables	YES

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The sessionKey is the identifier of the session generated by VISHNU	YES	NO

3.1.10 TMS setMachineRefreshPeriod

Access

This command line can be used by ADMIN users only

Description

The setMachineRefreshPeriod command line sets the refresh period of output and error files contents

Example of use

setMachineRefreshPeriod machineId value

Parameters

Parameter	Type	Option	Description	Required
machineId	string		The id of the machine	YES
value	int	/	Is the refresh interval value (in seconds)	YES

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The sessionKey is the identifier of the session generated by VISHNU	YES	NO

3.2 Parameters definitions

Enumeration TMS::JobPriority Type

Name	Value
VERY_LOW	100
LOW	200
NORMAL	300
HIGH	400
VERY_HIGH	500

Enumeration TMS::JobStatus Type

Name	Value
RUNNING	0
WAITING	1
COMPLETED	2
CANCELED	3
HELD	4
QUEUED	5
FAILED	6
NOT_SUBMITTED	7

Enumeration TMS::QueuePriority Type

Name	Value
VERY_LOW	0
LOW	1
NORMAL	2
HIGH	3
VERY_HIGH	4

Enumeration TMS::QueueStatus Type

Name	Value
STARTED	0
RUNNING	1
NOT_STARTED	2
NOT_AVAILABLE	3

Chapter 4

Commands specification for Information Management System (IMS)

4.1 Command definitions

4.1.1 IMS exportCommands

Access

This command line can be used by any VISHNU user

Description

The exportCommands command line exports all the commands made by a user during a session

Example of use

exportCommands oldSessionKey

Parameters

Parameter	Type	Option	Description	Required
oldSessionKey	string		The key of the session to export (session has ended)	YES

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The key of the session of the user that submits the command (current session key)	YES	NO

4.1.2 IMS getMetricCurrentValue

Access

This command line can be used by any VISHNU user

Description

The getMetricCurrentValue command line retrieve the current value of a metric on a machine

Example of use

getMetricCurrentValue machineId metricType

Parameters

Parameter	Type	Option	Description	Required
machineId	string	/	The id of the machine	YES
metricType	MetricType		Type of metric	YES

Environment variables

Name	Parameter	Type	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The key of the session of the user that submits the	YES	NO
			command		

4.1.3 IMS getMetricHistory

Access

This command line can be used by any VISHNU user

Description

The getMetricHistory command line retrieve the history of values of a metric on a machine

Example of use

getMetricHistory machineId startTime endTime metricType

Parameters

Parameter	Type	Option	Description	Required
machineId	string		The id of the machine	YES
startTime	long		Start time of metric history	YES
endTime	long		End time of metric history	YES
metricType	MetricType		Type of metric	YES

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The key of the session of the user that submits the command	YES	NO

4.1.4 IMS getProcesses

Access

This command line can be used by ADMIN users only

Description

The getProcesses command line gets the list of the processes running over a front machine

Example of use

getProcesses machineId

Parameters

Parameter	Type	Option	Description	Required
machineId	string		The id of the machine the user wants the running	YES
			processes	TES

Environment variables

Name	Parameter	Туре	Description	Required	User option
			The key of the session of the		
VISHNU_SESSION_KEY	sessionKey	string	user that submits the	YES	NO
			command		

4.1.5 IMS setSystemInfo

Access

This command line can be used by ADMIN users only

Description

The setSystemInfo command line updates the system information of a machine

Example of use

setSystemInfo[-m memory][-d diskSpace]

Parameters

Parameter	Type	Option	Description	Required
machineId	string		The id of the machine	YES
memory	long	m	Amount of RAM memory available on the machine (in Bytes)	NO
diskSpace	long	d	Amount of disk space available on the machine (in Bytes)	NO

Environment variables

Name	Parameter	Туре	Description	Re <mark>quir</mark> ed	User option
VISHNU_SESSION_KEY	sessionKey	string	The key of the session of the user that submits the command	YES	NO

4.1.6 IMS setSystemThreshold

Access

This command line can be used by ADMIN users only

Description

The setSystemThreshold command line sets a threshold on a machine of a system

Example of use

 $\verb|setSystemThreshold| \textit{ machineId thresholdType value}$

Parameter	Type	Option	Description	Required
machineId	string		The id of the machine	YES
thresholdType	MetricType		The type of the metric to set	YES
value	double		The threshold value	YES

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey		The key of the session of the		
		string	user that submits the	YES	NO
			command		

4.1.7 IMS getSystemThreshold

Access

This command line can be used by ADMIN users only

Description

The getSystemThreshold command line gets a System threshold on a machine

Example of use

getSystemThreshold machineId type

Parameters

Parameter	Type	Option	Description	Required
machineId	string		The id of the machine	YES
type	MetricType		The threshold type desired	YES

Environment variables

Parameter	Туре	Description	Required	User option
sessionKey	string	The key of the session of the user that submits the	YES	NO
			The key of the session of the	The key of the session of the user that submits the YES

4.1.8 IMS defineUserIdentifier

Access

This command line can be used by ADMIN users only

Description

The defineUserIdentifier command line defines the shape of the identifiers automatically generated for the users

Example of use

defineUserIdentifier format

Parameter	Type	Option	Description	Required
format	string		The new format to use	YES

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The key of the session of the user that submits the command	YES	NO

4.1.9 IMS defineMachineIdentifier

Access

This command line can be used by ADMIN users only

Description

The defineMachineIdentifier command line defines the shape of the identifiers automatically generated for the machines

Example of use

defineMachineIdentifier format

Parameters

Parameter	Type	Option	Description	Required
format	string		The new format to use	YES

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The key of the session of the user that submits the command	YES	NO

4.1.10 IMS defineJobIdentifier

Access

This command line can be used by ADMIN users only

Description

The defineJobIdentifier command line defines the shape of the identifiers automatically generated for the jobs

Example of use

defineJobIdentifier format

Parameters

Parameter	Type	Option	Description	Required
format	string		The new format to use	YES

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The key of the session of the user that submits the command	YES	NO

4.1.11 IMS defineTransferIdentifier

Access

This command line can be used by ADMIN users only

Description

The defineTransferIdentifier command line defines the shape of the identifiers automatically generated for the file transfers

Example of use

defineTransferIdentifier format

Parameters

Parameter	Type	Option	Description	Required
format	string		The new format to use	YES

Environment variables

Name	Parameter	Type	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The key of the session of the user that submits the command	YES	NO

4.1.12 IMS loadShed

Access

This command line can be used by ADMIN users only

Description

The loadShed command line load sheds a machine

Example of use

loadShed machineId loadShedType

Parameters

Parameter	Type	Option	Description	Required
machineId	string		The id of the machine to stop	YES
			Selects a load shedding mode (SOFT: stops all	
loadShedType	LoadShedType		services and they can be restarted, HARD: stops	YES
			all services, they cannot be restarted)	

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The key of the session of the user that submits the command	YES	NO

4.1.13 IMS setUpdateFrequency

Access

This command line can be used by ADMIN users only

Description

The setUpdateFrequency command line sets the update frequency of the IMS tables

Example of use

setUpdateFrequency freq

Parameters

Parameter	Type	Option	Description	Required
freq	int		Frequency the data are updated, in second	YES

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The key of the session of the user that submits the command	YES	NO

4.1.14 IMS getUpdateFrequency

Access

This command line can be used by any VISHNU user

Description

The getUpdateFrequency command line gets the update frequency of the IMS database

Example of use

getUpdateFrequency

Parameters

This command defines no arguments.

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The key of the session of the user that submits the command	YES	NO

4.1.15 IMS restart

Access

This command line can be used by ADMIN users only

Description

The restart command line restarts the whole VISHNU infrastructure. Actions are saved and restarted from the beginning once the infrastructure has been restarted

Example of use

restart [-n componentName][-m machineId][-f file] type

Parameters

Parameter	Type	Option	Description	Required
type	RestartType		The type of restart	YES
componentName	string	n	If not restarting all, the name of the component to restart	NO
machineId	string	m	The id of the machine where the component is to be relaunched	NO
file	string	f	The config file to use to restart	NO

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The key of the session of the user that submits the command	YES	NO

4.2 Parameters definitions

Enumeration IMS::LoadShedType Type

Name	Va <mark>lue</mark>
SOFT	0
HARD	1

Enumeration IMS::MetricType Type

Name	Value
CPUNBR	0
CPUUSE	1
DISKSPACE	2
FREEDISKSPACE	3
MEMORY	4
FREEMEMORY	5

Enumeration IMS::RestartType Type

Name	Value
ALL	0
SED	1

Name	Value
AGENT	2
DAEMON	3

Chapter 5

Commands specification for File Management System (FMS)

5.1 Command definitions

5.1.1 FMS createFile

Access

This command line can be used by any VISHNU user

Description

The createFile command line creates files on remote machines.

Example of use

createFile [-m mode] path

Parameters

Parameter	Type	Option	Description	Required
path string		The file to create following the pattern [host:]file	YES	
		path	ILS	
mode	int	m	The file access permissions in octal numeral	NO
mode int	111	system	110	

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The session key	YES	NO

5.1.2 FMS createDir

Access

This command line can be used by any VISHNU user

Description

The createDir command line creates directories on remote machines.

Example of use

createDir [-m mode] path

Parameters

Parameter	Type	Option	Description	Required
path	string		The directory to create following the pattern [host:]directory path	YES
mode	int	m	the new directories permission access in octal numeral system	NO

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The session key	YES	NO

5.1.3 FMS removeFile

Access

This command line can be used by any VISHNU user

Description

The removeFile command line removes files from remote hosts.

Example of use

removeFile path

Parameters

Parameter	Type	Option	Description	Required
path	string		The file to remove following the pattern	YES
•			[host:]file path	

Environment variables

Name	Parameter	Туре	Description	Re <mark>quir</mark> ed	User option
VISHNU_SESSION_KEY	sessionKey	string	The session key	YES	NO

5.1.4 FMS removeDir

Access

This command line can be used by any VISHNU user

Description

The removeDir command line removes directories (and subdirectories) from remote machines.

Example of use

removeDir path

Parameter	Type	Option	Description	Required
path	string		The directory to remove following the pattern [host:]directory path	YES

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The session key	YES	NO

5.1.5 FMS chGrp

Access

This command line can be used by any VISHNU user

Description

The chGrp command line changes group owner of remote files/directories.

Example of use

chGrp path group

Parameters

Parameter	Type	Option	Description	Required
path	string		The file/directory following the pattern [host:]file path	YES
group	string		the new group owner of file/directory	YES

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The session key	YES	NO

5.1.6 FMS chMod

Access

This command line can be used by any VISHNU user

Description

The chMod command line changes access rights of remote files/directories.

Example of use

chMod path mode

Parameters

Parameter	Type	Option	Description	Required
path	string		The file/directory following the pattern [host:]file path	YES
mode	int		the access rigths of file/directory in octal system.	YES

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The session key	YES	NO

5.1.7 FMS headOfFile

Access

This command line can be used by any VISHNU user

Description

The headOfFile command line displays a few first lines of files located on remote machines.

Example of use

headOfFile [-n nLine] path

Parameters

Parameter	Type	Option	Description	Required
path	string		The file following the pattern [host:]file path	YES
nLine	int	n	Number of lines to display	NO

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The session key	YES	NO

5.1.8 FMS tailOfFile

Access

This command line can be used by any VISHNU user

Description

The tailOfFile command line displays a few last lines of files located on remote machines

Example of use

tailOfFile $[-n \ \textit{nLine}]$ path

Parameters

Parameter	Type	Option	Description	Required
path	string		The file following the pattern [host:]file path	YES
nLine	int	n	number of lines to display	NO

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The session key	YES	NO

5.1.9 FMS contentOfFile

Access

This command line can be used by any VISHNU user

Description

The contentOfFile command line displays content of files located on remote machines

Example of use

contentOfFile path

Parameters

Parameter	Type	Option	Description	Required
path	string		The file to display following the pattern [host:]file path	YES

Environment variables

Name	Parameter	Type	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The session key	YES	NO

5.1.10 FMS listDir

Access

This command line can be used by any VISHNU user

Description

The listDir command line displays the content of a remote directory.

Example of use

listDir [-l][-a] path

Parameters

Parameter	Type	Option	Description	Required	
path str	string		The directory to list following the pattern	YES	
	sumg		[host:]directory path	1123	
longFormat boo	boolean	1	It specifies the long display format (all available	NO	
	Doolean	1	file informations)		
allFiles	boolean	a	Allows to display all files including hidden files	NO	

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The session key	YES	NO

5.1.11 FMS copyFile

Access

This command line can be used by any VISHNU user

Description

The copyFile command line executes a synchronous copy of file.

Example of use

copyFile [-r][-c trCommand] src dest

Parameters

Parameter	Type	Option	Description	Required
src string	string		The source file to copy following the pattern	YES
	string		[host:]file path	1123
dest	string		The path of the destination file	YES
isRecursive	boolean	. /	It specifies when the copy is recursive (case of	NO
	boolean	1	directory) or not.	NO
trCommand	TransferCommand	c	the command to use to perform file transfer.	NO

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The session key	YES	NO
VISHNU_TRANSFER_CMD	trCommand	TransferCommand	the command to use to perform file transfer.	NO	YES

5.1.12 FMS copyAsyncFile

Access

This command line can be used by any VISHNU user

Description

The copyAsyncFile command line executes an asynchronous copy of file.

Example of use

copyAsyncFile [-r][-c trCommand] src dest

Parameters

Parameter	Type	Option	Description	Required
src	string		The source file to copy following the pattern	YES
	sumg		[host:]file path	TLS
dest	string		The path of the destination file	YES
isRecursive	boolean	r	It specifies when the copy is recursive (case of	NO
	boolean		directory) or not.	NO
trCommand	TransferCommand	c	the command to use to perform file transfer.	NO

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The session key	YES	NO
VISHNU_TRANSFER_CMD	trCommand	TransferCommand	the command to use to perform file transfer.	NO	YES

5.1.13 FMS moveFile

Access

This command line can be used by any VISHNU user

Description

The moveFile command line executes a synchronous move of file.

Example of use

 $\verb|moveFile| [-c | \textit{trCommand}] | \textit{src dest}|$

Parameters

Parameter	Type	Option	Description	Required
src	string		The source file to move following the pattern [host:]file path	YES
dest	string	/	The path of the destination file	YES
trCommand	TransferCommand	С	the command to use to perform file transfer.	NO

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The session key	YES	NO
VISHNU_TRANSFER_CMD	trCommand	TransferCommand	the command to use to perform file transfer.	NO	YES

5.1.14 FMS moveAsyncFile

Access

This command line can be used by any VISHNU user

Description

The moveAsyncFile command line executes an asynchronous move of file.

Example of use

moveAsyncFile [-c trCommand] src dest

Parameters

Parameter	Type	Option	Description	Required
src string		The source file to move following the pattern	YES	
	string		[host:]file path	1123
dest	string		The path of the destination file	YES
trCommand	TransferCommand	c	the command to use to perform file transfer.	NO

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The session key	YES	NO
VISHNU_TRANSFER_CMD	trCommand	TransferCommand	the command to use to perform file transfer.	NO	YES

5.1.15 FMS stopFileTransfer

Access

This command line can be used by any VISHNU user

Description

The stopFileTransfer command line stops an execution of a set of file transfers.

Example of use

stopFileTransfer [-i transferId][-m fromMachineId][-u userId]

Parameters

Parameter	Type	Option	Description	Required
transferId	string	i	a given transfer id	NO
fromMachineId	string	m	the machine that is the source of the file transfer	NO
userId	string	u	allows an admin to stop file transfers of a specific user	NO

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The session key	YES	NO

5.1.16 FMS listFileTransferStatus

Access

This command line can be used by any VISHNU user

Description

The listFileTransferStatus command line displays the status of all file transfers submitted by User.

Example of use

listFileTransferStatus [-i transferId][-m fromMachineId][-u userId]

Parameters

Parameter	Туре	Option	Description	Required
transferId	string	i	a given transfer id	NO
fromMachineId	string	m	the machine that is the source of the file transfer	NO
userId	string	u	allows the admin to list file transfers initiated by a specific user	NO

Environment variables

Name	Parameter	Туре	Description	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The session key	YES	NO

5.1.17 FMS listFileTransfers

Access

This command line can be used by any VISHNU user

Description

The listFileTransfers command line displays the history of all file transfers submitted by User.

Example of use

listFileTransfers [-m fromMachineId][-u userId][-s status]

Parameters

Parameter	Type	Option	Description	Required
fromMachineId	string	m	the machine that is the source of the file transfer	NO
userId	string	u	allows the admin to list file transfers initiated by a specific user	NO
status	Status	S	the file transfer status	NO

Environment variables

Name	Parameter	Type	Description	Desc	Required	User option
VISHNU_SESSION_KEY	sessionKey	string	The session key	The s	YES	NO

5.2 Parameters definitions

Enumeration FMS::FileType Type

Name	Value
BLOCK	0
CHARACTER	1
DIRECTORY	2
SYMBOLICLINK	3
SCKT	4
FIFO	5
REGULAR	6

Enumeration FMS::Status Type

Name	V alue
INPROGRESS	0
COMPLETED	1
CANCELLED	2
FAILED	3

Enumeration FMS::TransferCommand Type

Name	Value
SCP	0
RSYNC	1