

## Commands

To update the policies and enforce them

rudder agent run -u
To see detailed output

Other commands and options

rudder agent run -i

man rudder

To trigger an inventory

rudder agent inventory

# Units

In all relevant fields (group, search, etc.), available units are B, KB, MB, GB, TB, PB, ...

When unit is omitted, is is considered as a value in bytes.

Use spaces or underscores to format the number  $(1_024 \text{ or } 2.048)$ .

# Advanced search syntax

You can use a query language to specify your search in the search bar:

is:node in:ips 192.168.1.2

is:node|group|parameter|directive|node

for the item your are searching for

in:property\_name

for the property you are searching in

is:\* in:name|id|description|long\_description|enabled

is:node in:

hostname|os\_type|os\_name|os\_version|os|
os\_kernel\_version|os\_service\_pack|architecture|
ram|ips|policy\_server\_id|properties|rudder\_roles

is:group in:dynamic

is:directives in:

dir\_param\_name|dir\_param\_value|technique\_id|
technique\_name|technique\_version

is:parameters in:parameter\_name|parameter\_value

is:rules in:directives|groups

## Conditions

Conditions are context entities represented by a string, that can be either set or not set, depending on context. They allow using conditions to generic method usage. Variable name must match:

[a-zA-Z0-9][a-zA-Z0-9\_]\*

## Available conditions

Group conditions: defined only if the node is in the given group (available in the group details)

group\_group\_uuid
group\_group\_name

System conditions: various system information defined by default

centos\_7, ubuntu\_18\_04

Result conditions: defined by the execution of another generic method (available at the bottom of the generic method call configuration)

generic\_method\_name\_parameter\_value\_kept
generic\_method\_name\_parameter\_value\_repaired
generic\_method\_name\_parameter\_value\_error

Conditions manually defined in the agent call:

rudder agent run -D my\_condition

## Condition expressions

Group	Or
<pre>(condition_expression)</pre>	condition other
And	Not
condition.other	!condition

## **Paths**

#### On the nodes

Policy server configuration file

/opt/rudder/etc/policy\_server.dat

#### On the server

Directory containing all the configuration policies in a git repository

/var/rudder/configuration-repository

Directory shared to nodes from the server

/var/rudder/configuration\_directory/shared-files

Directory containing the configuration events (change and errors)

/var/log/rudder/compliance/non-compliant-reports
Webapp log file

/var/log/rudder/webapp/YYYY\_MM\_DD.stderrout.log

# Variables

Variables in directives parameters are evaluated at generation on the server, exceptions are tagged with execution.

Variables in technique editor are evaluated at execution on the nodes.

Node properties can be overriden at execution on the nodes using files containing a "properties" object placed in :

/var/rudder/local/properties.d/\*.json

#### Only in Directives

System variables about a node

```
${rudder.node.id}
${rudder.node.hostname}
${rudder.node.admin}
```

System variables about a node's policy server

```
${rudder.node.policyserver.id}
${rudder.node.policyserver.hostname}
${rudder.node.policyserver.admin}
```

#### Node properties

```
${rudder.properties[key]}
${rudder.properties[subtree]}
${rudder.properties[key] | node} execution
```

Default values (only with node properties)

```
${variable | default="value"}
${variable | default=""" value with "quotes" """}
${variable | default= ${any_other_variable} }
${variable | default= ${var} | default="fallback"}
```

Javascript engine (with any variable)

```
"${variable}".substring(0,3)
```

RUDDER javascript library

```
rudder.hash.md5/sha256/sha512(string)
rudder.password.auto/unix/aix/("MD5/SHA256/
SHA512", password [, salt])
```

# In Directives and in the Technique Editor Global parameters

```
${rudder_parameter.string_name}
```

From the "Variable (string)" technique

\${generic\_variable\_definition.string\_name}

From the "Variable from command output" technique \${generic\_cmd\_var\_def.string\_name}

From the "Variable from JSON file (dict)" technique \${variable\_prefix.dict\_name[key]}

#### Node properties

```
${node.properties[key]}
${node.local_custom_properties[key]}
```

## Only in the technique editor

User variables defined using generic methods

```
${variable_prefix.string_name}
${variable_prefix.iterator_name}
${variable_prefix.dict_name[key]}
```

# **Mustache Templating**

#### Conditions

```
{{*classes.conditions}}
condition is defined
{{/classes.conditions}}
{{/classes.conditions}}
```

#### Variables

```
{{{vars.node.properties.variable_name}}}
{{{vars.generic_variable_definition.variable_name}}}
{{{vars.variable_prefix.string_name}}}
{{{vars.variable_prefix.dict_name.key}}}
```

#### Iteration

```
{{\{\text{"wars.variable_prefix.iterator_name}}\}
{{\{.}}\} is the current iterator_name value
{{\{vars.variable_prefix.iterator_name}}\}
{{\{\text{"wars.variable_prefix.dict_name}}\}
{{\{\text{@}}\}\} is the current dict_name key
{{\{.}}\}\} is the current dict_name[name]
{{\{\text{"yars.variable_prefix.dict_name}}}\}
```

# Jinja2 Templating

#### Conditions

```
{% if classes.condition is defined %}
condition is defined
{% endif %}
{% if not classes.condition is defined %}
condition is not defined
{% endif %}
```

#### Variables

```
{{vars.variable_prefix.my_variable}}
```

## Iteration

```
{% for item in vars.variable_prefix.dict %}
{{ item }} is the current item value
{{ item.key }} is the current item[key] value
{% endfor %}

{% for key,value in vars.prefix.dict.items() %}
{{ key }} as value {{ value }}
{% endfor %}
```

# Useful links



chat.rudder.io

docs.rudder.io

issues.rudder.io