# **NIST SPECIAL PUBLICATION 1800-5C**

# **IT Asset Management**

Volume C: How-To Guides

Michael Stone
Leah Kauffman, Editor-in-Chief
National Cybersecurity Center of Excellence
Information Technology Laboratory

Chinedum Irrechukwu Harry Perper Devin Wynne The MITRE Corporation McLean, VA

September 2018

This publication is available free of charge from: <a href="http://doi.org/10.6028/NIST.SP.1800-5">http://doi.org/10.6028/NIST.SP.1800-5</a>

The first draft of this publication is available free of charge from: https://www.nccoe.nist.gov/sites/default/files/library/sp1800/fs-itam-nist-sp1800-5-draft.pdf





#### **DISCLAIMER**

Certain commercial entities, equipment, products, or materials may be identified in this document in order to describe an experimental procedure or concept adequately. Such identification is not intended to imply recommendation or endorsement by NIST or NCCoE, nor is it intended to imply that the entities, equipment, products, or materials are necessarily the best available for the purpose.

National Institute of Standards and Technology Special Publication 1800-5C, Natl. Inst. Stand. Technol. Spec. Publ. 1800-5C, 166 pages, (September 2018), CODEN: NSPUE2

# **FEEDBACK**

As a private-public partnership, we are always seeking feedback on our Practice Guides. We are particularly interested in seeing how businesses apply NCCoE reference designs in the real world. If you have implemented the reference design, or have questions about applying it in your environment, please email us at <a href="mailto:financial\_nccoe@nist.gov">financial\_nccoe@nist.gov</a>.

All comments are subject to release under the Freedom of Information Act (FOIA).

National Cybersecurity Center of Excellence
National Institute of Standards and Technology
100 Bureau Drive
Mailstop 2002
Gaithersburg, MD 20899

Email: nccoe@nist.gov

#### NATIONAL CYBERSECURITY CENTER OF EXCELLENCE

The National Cybersecurity Center of Excellence (NCCoE), a part of the National Institute of Standards and Technology (NIST), is a collaborative hub where industry organizations, government agencies, and academic institutions work together to address businesses' most pressing cybersecurity issues. This public-private partnership enables the creation of practical cybersecurity solutions for specific industries, as well as for broad, cross-sector technology challenges. Through consortia under Cooperative Research and Development Agreements (CRADAs), including technology partners—from Fortune 50 market leaders to smaller companies specializing in IT security—the NCCoE applies standards and best practices to develop modular, easily adaptable example cybersecurity solutions using commercially available technology. The NCCoE documents these example solutions in the NIST Special Publication 1800 series, which maps capabilities to the NIST Cyber Security Framework and details the steps needed for another entity to recreate the example solution. The NCCoE was established in 2012 by NIST in partnership with the State of Maryland and Montgomery County, Md.

To learn more about the NCCoE, visit <a href="https://www.nccoe.nist.gov/">https://www.nccoe.nist.gov/</a>. To learn more about NIST, visit <a href="https://www.nist.gov">https://www.nist.gov</a>.

#### **NIST CYBERSECURITY PRACTICE GUIDES**

NIST Cybersecurity Practice Guides (Special Publication Series 1800) target specific cybersecurity challenges in the public and private sectors. They are practical, user-friendly guides that facilitate the adoption of standards-based approaches to cybersecurity. They show members of the information security community how to implement example solutions that help them align more easily with relevant standards and best practices, and provide users with the materials lists, configuration files, and other information they need to implement a similar approach.

The documents in this series describe example implementations of cybersecurity practices that businesses and other organizations may voluntarily adopt. These documents do not describe regulations or mandatory practices, nor do they carry statutory authority.

#### **ABSTRACT**

While a physical asset management system can tell you the location of a computer, it cannot answer questions like, "What operating systems are our laptops running?" and "Which devices are vulnerable to the latest threat?" An effective IT asset management (ITAM) solution can tie together physical and virtual assets and provide management with a complete picture of what, where, and how assets are being used. ITAM enhances visibility for security analysts, which leads to better asset utilization and security.

#### **KEYWORDS**

asset management; financial sector; information technology asset management; ITAM; personnel security; physical security; operational security

# **ACKNOWLEDGMENTS**

We are grateful to the following individuals for their generous contributions of expertise and time.

Name	Organization	
FS-ISAC	Financial Services Information Sharing and Analysis Center	
Gorrell Cheek	Western Union	
Joe Buselmeier	American Express	
Sean Franklin	American Express	
Ron Ritchey	Bank of America	
Sounil Yu	Bank of America	
Joel Van Dyk	Depository Trust & Clearing Corporation	
Dan Schutzer	Financial Services Roundtable	
George Mattingly	Navy Federal Credit Union	
Jimmie Owens	Navy Federal Credit Union	
Mike Curry	State Street	
Timothy Shea	RSA	
Mark McGovern	MobileSystem7	
Atul Shah	Microsoft	
Leah Kauffman	NIST	
Benham (Ben) Shariati	University of Maryland Baltimore County	
Valerie Herrington	Herrington Technologies	
Susan Symington	MITRE Corporation	
Sallie Edwards	MITRE Corporation	

Name	Organization
Sarah Weeks	MITRE Corporation
Lina Scorza	MITRE Corporation
Karen Scarfone	Scarfone Cybersecurity

The Technology Partners/Collaborators who participated in this build submitted their capabilities in response to a notice in the Federal Register. Respondents with relevant capabilities or product components were invited to sign a Cooperative Research and Development Agreement (CRADA) with NIST, allowing them to participate in a consortium to build this example solution. We worked with:

Technology Partner/Collaborator	Build Involvement
AlphaPoint Technology	AssetCentral
Belarc	BelManage, BelManage Analytics
Computer Associates	ITAM
Microsoft	WSUS, Server 2012R2 Certificate Authority
Peniel Solutions	Technology/Industry Expertise
<u>PI Achievers</u>	Penetration Testing Services
<u>PuppetLabs</u>	Puppet
RedJack	Fathom
<u>Splunk</u>	Splunk Enterprise
<u>Tyco</u>	iStar Edge
Vanguard Integrity Professionals	Security Manager

# **Contents**

1	Intr	oduct	ion	1
	1.1	Practio	ce Guide Structure	1
	1.2	Build (	Overview	2
		1.2.1	Build Architecture Components Overview	5
		1.2.2	Build Network Components	
		1.2.3	Operating Systems	7
	1.3	Typog	raphic Conventions	8
2	Tier	· 1		8
	2.1		are Configurations	
		2.1.1	Splunk Enterprise	
		2.1.2	How It's Used	
		2.1.3	Installing Splunk Enterprise	9
		2.1.4	Configurations	
		2.1.5	Lookup Table Files	
3	Tier	· 2	••••••	. 28
	3.1	AssetC	Central	28
		3.1.1	How It's Used	28
		3.1.2	Virtual Machine Configuration	29
		3.1.3	Network Configuration	29
		3.1.4	Installing AssetCentral	29
		3.1.5	Installing MySQL (MariaDB)	29
		3.1.6	Installing Apache	30
		3.1.7	Installing PHP5	30
		3.1.8	Post Installation Tasks	30
		3.1.9	Database Update – Add a View	31
		3.1.10	Add Assets into AssetCentral	32
	3.2	BelMa	nage	32
		3.2.1	How It's Used	32

	3.2.2	Virtual Machine Configuration	33
	3.2.3	Network Configuration	33
	3.2.4	Installing BelManage	33
	3.2.5	Integration and Final Steps	35
3.3	Bro		36
	3.3.1	How It's Used	36
	3.3.2	Virtual Machine Configuration	36
	3.3.3	Network Configuration	37
	3.3.4	Installing Bro	37
	3.3.5	Installing Intelligence Gathering Software	39
	3.3.6	Configuring Bro	39
	3.3.7	Installing Splunk Universal Forwarder	40
	3.3.8	Configuring Splunk Universal Forwarder	41
	3.3.9	Configurations and Scripts	42
3.4	CA Te	chnologies IT Asset Manager	50
	3.4.1	How It's Used	50
	3.4.2	Virtual Machine Configuration	51
	3.4.3	Network Configuration	51
	3.4.4	Installing CA ITAM	51
	3.4.5	Configurations	52
3.5	Fatho	m Sensor from RedJack	54
	3.5.1	How It's Used	55
	3.5.2	Virtual Machine Configuration	55
	3.5.3	Network Configuration	55
	3.5.4	Installing Fathom Sensor	55
	3.5.5	Installing Splunk Universal Forwarder	61
	3.5.6	Configuring Splunk Universal Forwarder	62
	3.5.7	Helpful Commands and Information	62
	3.5.8	Configurations and Scripts	63
3.6	Open\	VAS	64
	3.6.1	How It's Used	64

	3.6.2	Virtual Machine Configuration	64
	3.6.3	Network Configuration	64
	3.6.4	Installation Prerequisites	65
	3.6.5	Installing OpenVAS	65
	3.6.6	Configuring OpenVAS	67
	3.6.7	Installing Splunk Universal Forwarder	69
	3.6.8	Configuring Splunk Universal Forwarder	69
	3.6.9	Configurations and Scripts	70
3.7	Puppe	t Enterprise	. 74
	3.7.1	How It's Used	74
	3.7.2	Prerequisites	74
	3.7.3	Installing Puppet Enterprise Server	75
	3.7.4	Puppet Enterprise Linux Agent Installation	75
	3.7.5	Puppet Enterprise Windows Agent Installation	76
	3.7.6	Puppet Enterprise Agent Configuration	76
	3.7.7	Puppet Enterprise Manifest Files and Modules	77
	3.7.8	Reporting	79
	3.7.9	Report Directory Cleanup	80
	3.7.10	Puppet Code and Scripts	80
3.8	Snort.		. 93
	3.8.1	How It's Used	93
	3.8.2	Virtual Machine Configuration	93
	3.8.3	Network Configuration	93
	3.8.4	Installing Snort	94
	3.8.5	Installing Snort	94
	3.8.6	Get Updated Community Rules	94
	3.8.7	Installing Barnyard2	95
	3.8.8	Testing	96
	3.8.9	Installing Splunk Universal Forwarder	97
	3.8.10	Configuring Splunk Universal Forwarder	97
	2 2 11	Configurations and Scripts	۵g

	3.9	Tyco S	ecurity Products	. 134
		3.9.1	Installing Tyco Security Products	134
		3.9.2	Configurations	134
	3.10	Windo	ws Server Update Services (WSUS)	. 136
		3.10.1	How It's Used	136
		3.10.2	Virtual Machine Configuration	136
		3.10.3	Network Configuration	136
		3.10.4	Installing WSUS	137
		3.10.5	Configurations	137
		3.10.6	Configure Active Directory Server to Require WSUS	137
		3.10.7	Create WSUS Statistics for Splunk Enterprise	138
		3.10.8	Installing Splunk Universal Forwarder	140
		3.10.9	Configuring Splunk Universal Forwarder	140
		3.10.10	Configurations and Scripts	141
4	Tier	3		142
	4.1	Active	Directory Server	. 142
		4.1.1	Software Configurations	143
		4.1.2	How It's Used	143
		4.1.3	Installation	143
	4.2	AssetC	entral	. 146
		4.2.1	How It's Used	146
		4.2.2	Virtual Machine Configuration	146
		4.2.3	Network Configuration	146
		4.2.4	Installing AssetCentral	146
		4.2.5	Installing MySQL (MariaDB)	147
		4.2.6	Installing Apache	147
		4.2.7	Installing PHP5	148
		4.2.8	Post Installation Tasks	148
	4.3	Email.		. 148
		4.3.1	How It's Used	148

	4.3.2	Virtual Machine Configuration	149
	4.3.3	Network Configuration	149
	4.3.4	Installing Email	149
	4.3.5	Configure Email	149
	4.3.6	User Accounts	150
	4.3.7	DNS Settings	150
	4.3.8	Configuration Files	151
4.4	Opens	wan (VPN)	. 152
	4.4.1	How It's Used	152
	4.4.2	Virtual Machine Configuration	152
	4.4.3	Network Configuration	152
	4.4.4	Installing Openswan	153
	4.4.5	Installing Openswan	153
	4.4.6	Configurations and Scripts	154
4.5	Ubunt	u Apt-Cacher	. 157
	4.5.1	How It's Used	157
	4.5.2	Virtual Machine Configuration	157
	4.5.3	Network Configuration	157
	4.5.4	Installing Ubuntu Apt-Cacher	157
	4.5.5	Client Configuration	158
4.6	Windo	ws 2012 Certificate Authority	. 158
	4.6.1	Software Configurations	158
	4.6.2	How It's Used	158
	4.6.3	Certificate Generation and Issuance	162
4.7	Comm	on PKI Activities	. 163
	4.7.1	Generating a Certificate Signing Request from OpenSSL	163
	4.7.2	Submitting the CSR to the CA Service	163
	4.7.3	Exporting a Root Certificate from a Microsoft CA	164
	4.7.4	Converting from DER Encoding to PEM Encoding	164
4 8	Proces	ss Improvement Achievers (PIA) Security Evaluation	164

Appendix A	List of Acronyms
List of Figu	ıres
Figure 1-1 ITAM	Build5
Figure 2-1 Splunk	k Enterprise Syslog TCP Input11
Figure 2-2 Splunk	k Enterprise Syslog UDP Input
Figure 2-3 Splunk	k Enterprise Receive from Splunk Universal Forwarder 12
Figure 3-1 CCURE	9000 Overview
Figure 3-2 CCURE	9000 Messages
List of Tab	les
Table 1-1 Build A	architecture Component List3
Table 2-1 Splunk	Enterprise Data Collection Methods9
Table 2-2 Splunk	Enterprise Indexes 12
Table 2-3 Splunk	Enterprise Apps
Table 2-4 Require	ed Database Drivers
Table 2-5 DB Con	nnect v2 Identities
Table 3-1 Recom	mended Versions for AssetCentral – Tier 2
Table 4-1 Recom	mended Versions for AssetCentral – Tier 3 147

# 1 Introduction

The following volumes of this guide show information technology (IT) professionals and security engineers how we implemented this example solution. We cover all the products employed in this reference design. We do not recreate the product manufacturers' documentation, which is presumed to be widely available. Rather, these volumes show how we incorporated the products together in our environment.

Note: These are not comprehensive tutorials. There are many possible service and security configurations for these products that are out of scope for this reference design.

## 1.1 Practice Guide Structure

This National Institute of Standards and Technology (NIST) Cybersecurity Practice Guide demonstrates a standards-based reference design and provides users with the information they need to replicate all, or parts of the build created in the NCCoE ITAM Lab. This reference design is modular and can be deployed in whole or in part.

This guide contains three volumes:

- NIST SP 1800-5A: Executive Summary
- NIST SP 1800-5B: Approach, Architecture, and Security Characteristics what we built and why
- NIST SP 1800-5C: How-To Guides instructions for building the example solution (you are here)

Depending on your role in your organization, you might use this guide in different ways:

**Business decision makers, including chief security and technology officers,** will be interested in the *Executive Summary, NIST SP 1800-5A*, which describes the following topics:

- challenges enterprises face in implementing and using ITAM systems
- example solution built at the NCCoE
- benefits of adopting the example solution

**Technology or security program managers** who are concerned with how to identify, understand, assess, and mitigate risk will be interested in *NIST SP 1800-5B*, which describes what we did and why. The following sections will be of particular interest:

- Section 4.5, Risk Assessment and Mitigation, where we identify the steps we took to protect and monitor the ITAM system
- Section 4.5.1, Assessing Risk Posture, where we identify the security measures used in this implementation

- Section 4.5.2, Security Characteristics and Controls Mapping, where we map the security characteristics of this example solution to cybersecurity standards and best practices
- Section 4.6, Technologies, where we identify the products and technologies we used and map them to the relevant security controls

You might share the *Executive Summary, NIST SP 1800-5A*, with your leadership team members to help them understand the importance of adopting standards-based IT Asset Management.

**IT professionals** who want to implement an approach like this will find this whole practice guide useful. You can use this How-To portion of the guide, *NIST SP 1800-5C*, to replicate all or parts of the build created in our lab. This How-To portion of the guide provides specific product installation, configuration, and integration instructions for implementing the example solution. We do not recreate the product manufacturers' documentation, which is generally widely available. Rather, we show how we incorporated the products together in our environment to create an example solution.

This guide assumes that IT professionals have experience implementing security products within the enterprise. While we have used a suite of commercial products to address this challenge, this guide does not endorse these particular products. Your organization can adopt this solution or one that adheres to these guidelines in whole, or you can use this guide as a starting point for tailoring and implementing parts of IT Asset Management. Your organization's security experts should identify the products that will best integrate with your existing tools and IT system infrastructure. We hope that you will seek products that are congruent with applicable standards and best practices. Section 4.6, Technologies, lists the products that we used and maps them to the cybersecurity controls provided by this reference solution.

A NIST Cybersecurity Practice Guide does not describe "the" solution, but a possible solution. Comments, suggestions, and success stories will improve subsequent versions of this guide. Please contribute your thoughts to <a href="mailto:financial">financial</a> nccoe@nist.gov.

# 1.2 Build Overview

The NCCoE constructed the Information Technology Access Management (ITAM) build infrastructure using commercial off-the-shelf (COTS) hardware and software along with open source tools.

The lab network is connected to the public Internet through a virtual private network (VPN) appliance and firewall to enable secure Internet and remote access. The lab network is not connected to the NIST enterprise network. <u>Table 1-1</u> lists the software and hardware components used in the build, as well the specific function each component contributes.

**Table 1-1 Build Architecture Component List** 


Host	Product	Function	Internet Protocol Address	Operating System
		Demilitarized Zone		
Bro	Bro	Network security monitor	172.16.0.20	Ubuntu 14.04
FathomSensor	RedJack Fathom	Network analysis	172.16.0.50	CentOS 7
OpenSwan	OpenSwan	Virtual Private Network (VPN)	172.16.0.67	Ubuntu 14.04
Router0	pfSense	Router/firewall	172.16.0.11 10.33.5.9	BSD pfSense appliance
Snort	Cisco/Sourcefire Snort	Intrusion Detection System	172.16.0.40	Ubuntu 14.04
Apt-cacher0	Ubuntu apt-cacher	Patch management	172.16.0.77	Ubuntu 14.04
WSUS	Microsoft WSUS	Patch management	172.16.0.45	Server 2012R2
		IT Systems		
AD1	Microsoft Active Directory	Directory manager, AAA, DNS	172.16.1.20	Server 2012R2
AD2	Microsoft Active Directory	Directory manager, AAA, DNS	172.16.1.21	Server 2012R2
CA server	Microsoft Certifi- cate Authority	PKI certificate authority	172.16.1.41	Server 2012R2
Email Server	Postfix	Email server for the lab	172.16.1.50	Ubuntu 14.04
PE Master	Puppet Labs Puppet Enterprise	Configuration manage- ment	172.16.1.40	Ubuntu 14.04
Router1	pfSense	Router/firewall	172.16.0.12 172.16.1.1	BSD pfSense appliance
Ubuntu Client1	Ubuntu Desktop	Representative Linux client	DHCP	Ubuntu 14.04
Win7-Client1	Microsoft Windows7	Representative Windows client	DHCP	Windows 7 Enterprise
Win7-Client2	Microsoft Windows7	Representative Windows client	DHCP	Windows 7 Enterprise
		Network Security		
Router2	pfSense	Router/firewall	172.16.0.13 172.16.2.11	BSD pfSense appliance
BelManage	Belarc BelManage	Software, hardware, configuration information	172.16.2.71	Windows Server 2012R2

Host	Product	Function	Internet Protocol Address	Operating System	
BDA	Belarc BelManage Data Analytics	Analytic information for BelManage	172.16.2.72	Windows 7	
OpenVAS	OpenVAS	Vulnerability analysis system	172.16.2.33	Ubuntu 14.04	
	P	hysical Asset Managemer	nt		
Router3	pfSense	Router/firewall	172.16.0.14 172.16.3.11	BSD pfSense appliance	
AssetCentral	AlphaPoint AssetCentral	IT and datacenter asset management system	172.16.3.103	CentOS7	
CA ITAM	CA Technologies IT Asset Manager	Lifecycle asset manage- ment	172.16.3.92	Windows Server 2012R2	
		Physical Security			
Router4	pfSense	Router/firewall	172.16.0.15 192.168.1.11	BSD pfSense appliance	
iStar Edge	Tyco iStar Edge	Security system with badge reader for door access	192.168.1.169	Embedded	
NVR	Tyco/American Dynamics VideoEdge	Digital video recorder for IP security cameras	192.168.1.178	Suse Linux (JeOS)	
Camera1	Illustra 600 IP camera	IP security camera	192.168.1.176	Embedded	
Camera2	Illustra 600 IP camera	IP security camera	192.168.1.177	Embedded	
CCure9000	CCure9000	Controller for iStar Edge and NVR	192.168.1.167	Windows 7	
	ITAM				
Router5	pfSense	Router/firewall	172.16.0.16 172.16.5.11	BSD pfSense appliance	
Splunk	Splunk Enterprise	Data aggregation, storage, analysis and visualization	172.16.5.55	RHEL 7	

# 1.2.1 Build Architecture Components Overview

The build architecture consists of multiple networks implemented to mirror the infrastructure of a typical financial industry corporation. The networks include a Demilitarized Zone (DMZ) network along with several subnets as shown in <a href="Figure 1-1">Figure 1-1</a>. The DMZ network provides technologies that monitor and detect cybersecurity events, conduct patch management, and provide secure access to the mainframe computer. The Physical Asset Management Network provides management of identities and credentials for authorized devices and users. Network Security provides vulnerability scanning, along with a database for collection and analysis of data from hardware and software components. The IT Systems Network conducts configuration management and validation of client machines. Physical Security consists of management consoles for devices that operate and manage physical security. Such devices consist of badge readers and cameras. Firewalls are configured to limit access to and from the networks, blocking all traffic except required internetwork communications.

Figure 1-1 ITAM Build



# 1.2.2 Build Network Components

**Internet** – The public Internet is accessible by the lab environment to facilitate access for vendor software and NCCoE administrators. Internet access is not required to implement the build.

**VPN Firewall** – The VPN firewall is the access control point for vendors to support the installation and configuration of their components of the architecture. The NCCoE also used this access to facilitate product training. This firewall also blocks unauthorized traffic from the public Internet to the production networks. Additional firewalls are used to secure the multiple domain networks (ITAM, DMZ, Network Security, IT Systems, Physical Security, Physical Asset Management). Each network uses pfSense routers for all of its routing and firewall needs. The router is also performing duties as an NTP server and DHCP server on all subnets except the DMZ, which does not allow DHCP.

**Demilitarized Zone** – The DMZ provides a protected neutral network space that the other networks of the production network can use to route traffic to/from the Internet or each other. There is an external and internal facing subnet. The DMZ also provides technologies that monitor and detect cybersecurity events, conduct patch management, and issue secure access to the mainframe computer. DMZ devices consist of RouterO, Ubuntu Apt-Cacher, Bro, Fathom Sensor, Snort and WSUS.

**ITAM** – The ITAM network contains the Splunk Enterprise server that serves as the IT asset management database. The Splunk Enterprise server gathers logging and status information from all machines in the environment. The ITAM network also contains Router5.

**Network Security** – The network security architecture is represented in <u>Figure 1-1</u>. Network security is where all devices pertaining to network security reside. These devices include Intrusion Detection System/Intrusion Prevention System (IDS/IPS), Security Event and Incident Management (SEIM), logging systems and vulnerability scanners. Devices within this network consist of Router2, OpenVAS, Belarc and Splunk Enterprise servers.

IT Systems – The IT systems network is dedicated to traditional IT systems. Examples of such systems are Domain Name System (DNS), Active Directory, email, certificate authority, internal Web servers and client machines. Devices included in this subnet are Router1, two Windows 7 clients, a Wiki and two Windows 2012 Active Directory servers. One serves as primary while the other serves as a backup. Puppet Enterprise Master enforces security and configuration baselines across all endpoints.

**Physical Security** – The physical security network houses the devices that operate and manage physical security, such as badge readers and cameras, along with their management consoles. The devices include Router4, iStar Edge, CCure controller, two badge readers and two Internet Protocol (IP) cameras.

**Physical Asset Management** – The physical asset management network contains devices that provide and collect information regarding physical assets. The devices include Router3, AssetCentral and CA Technologies IT Asset Manager. AssetCentral is a physical asset inventory and analysis system from AlphaPoint Technology. It allows users to view assets from multiple viewpoints, including building,

room, floor, rack, project, collection, or owner. AssetCentral is running on CentOS Linux. CA IT Asset Manager allows users to holistically manage IT hardware assets, from planning and requisition to retirement and disposal.

# 1.2.3 Operating Systems

All machines used in the build had either Windows 7 enterprise, Windows server 2012 R2, Ubuntu 14.04, RedHat Enterprise Linux 7.1 or CentOS 7 operating systems (OSs) installed.

# 1.2.3.1 Base Windows Installation and Hardening Details

The NCCoE base Windows OS images are Server 2012 R2 x86\_64 and Windows 7 Enterprise x86\_64 Department of Defense (DoD) Security Technical Implementation Guide (STIG) images. The installation of both Windows systems was performed using installation media provided by the Defense Information Systems Agency (DISA). These images were chosen because they are standardized, hardened and fully documented.

# 1.2.3.2 Base Linux Installation and Hardening Details

The NCCoE base Linux OS is CentOS 7. This OS is available as an open source image. The OS was configured to meet the DoD CentOS 6, STIG. No CentOS 7 STIG was available at the time the build was implemented.

# 1.3 Typographic Conventions

The following table presents typographic conventions used in this volume.

Typeface/Symbol	Meaning	Example
Italics	file names and path names;	For detailed definitions of terms, see
	references to documents that	the NCCoE Glossary.
	are not hyperlinks; new	
	terms; and placeholders	
Bold	names of menus, options,	Choose <b>File</b> > <b>Edit</b> .
	command buttons, and fields	
Monospace command-line input,		mkdir
	on-screen computer output,	
	sample code examples, and	
	status codes	
Monospace Bold command-line user input		service sshd start
contrasted with computer		
	output	
blue text	link to other parts of the	All publications from NIST's NCCoE
	document, a web URL, or an	are available at
	email address	https://www.nccoe.nist.gov.

# 2 Tier 1

# 2.1 Software Configurations

# 2.1.1 Splunk Enterprise

Splunk Enterprise is a software platform to search, analyze, and visualize the machine-generated data gathered from the websites, applications, sensors, and devices that comprise your IT infrastructure or business. Splunk Enterprise is comprised of a database, analytic engine, front-end and various ways of gathering data.

# 2.1.2 How It's Used

In the FS ITAM build Splunk Enterprise receives data from all of the sensors and IT asset management systems. Splunk Enterprise then indexes the data, analyzes it, and displays the results as both reports and graphical desktops.

Analysts can quickly view reports and dashboards to view commonly requested information. Analysts can also form ad-hoc queries on any of the data gathered and analyzed. Splunk Enterprise also provides the ability to alert on any security or performance event.

On the high-level architecture diagram Splunk Enterprise is the Tier 1 ITAM server. Splunk Enterprise is running its own syslog server and collecting syslog information from all hosts on the network (port 514 TCP/UDP). Splunk Enterprise utilizes several methods to acquire data from the ITAM systems which are shown in <u>Table 2-1</u>. The Splunk Enterprise server listens on TCP port 9997 for connections from Universal Forwarders.

**Table 2-1 Splunk Enterprise Data Collection Methods** 

Product	Method
AssetCentral	Database Connection
Bro	Splunk Universal Forwarder
CA Technologies ITAM	Database Connection
Snort	Splunk Universal Forwarder
Fathom	Splunk Universal Forwarder
BelManage	Database Connection
Puppet	Splunk Universal Forwarder
Тусо	Files & Directories
WSUS	Splunk Universal Forwarder
OpenVAS	Splunk Universal Forwarder
Vanguard	Splunk Universal Forwarder

# 2.1.3 Installing Splunk Enterprise

- Splunk Enterprise is installed on a hardened RedHat Enterprise Linux system. Please download
  the latest RPM file from Splunk and follow the instructions for installing from an RPM file. Installation was performed following the instruction from Splunk at <a href="http://docs.splunk.com/Documentation/Splunk/6.2.3/Installation/InstallonLinux#RedHat\_RP% 20M\_install.">http://docs.splunk.com/Documentation/Splunk/6.2.3/Installation/InstallonLinux#RedHat\_RP% 20M\_install.</a>
- After installing the RPM file (explained in the Splunk Enterprise installation instructions), the following steps are recommended to start Splunk Enterprise automatically at boot time:

```
cd <splunk install_directory>/bin
Commonly: cd /opt/splunk/bin
./splunk start --accept-license
```

```
./splunk enable boot-start
./splunk enable boot-start -user splunkuser
./splunk start
```

3. Splunk Enterprise also requires several ports to be opened through the firewall(s). To allow these ports through the built-in firewall on RHEL, enter the following commands:

```
sudo firewall-cmd -permanent --add-port =8000/tcp
sudo firewall-cmd -permanent --add-port =9997/tcp
sudo firewall-cmd -permanent --add-port =514/tcp
sudo firewall-cmd -permanent --add-port =514/udp
sudo firewall-cmd -reload
sudo firewall-cmd -list-ports
```

4. It is also recommended to increase the number of files that can be open simultaneously. This is done by editing the /etc/security/limits.conf file. Please add the following lines to the end of /etc/security/limits.conf:

```
soft nproc 8192
hard nproc 8192
soft nofile 8192
soft nofile 8192
```

Note: These will not take effect until you log off and on again. You can issue the ulimit—a command to verify that it worked.

5. Splunk Enterprise can now be accessed by opening a web browser and going to

```
http://localhost:8000
Initial login = admin
Initial password = changeme
```

# 2.1.3.1 Disable Transparent Huge Pages

Using Transparent Huge Pages causes performance degradation of up to 30% when using Splunk Enterprise. Splunk recommends disabling Huge Transparent Pages and details the issue at <a href="http://docs.splunk.com/Documentation/Splunk/6.2.3/ReleaseNotes/SplunkandTHP">http://docs.splunk.com/Documentation/Splunk/6.2.3/ReleaseNotes/SplunkandTHP</a>.

1. To disable Transparent Huge Pages, we added the following lines to the end of /etc/rc.d/rc.local:

```
#disable THP at boot time
```

if test -f /sys/kernel/mm/transparent\_hugepage/enabled; then echo never >
/sys/kernel/mm/transparent\_hugepage/enabled

fi

if test -f /sys/kernel/mm/transparent\_hugepapge/defrag; then echo never >
sys/kernel/mm/transparent\_hugepapge/defrag

fi

2. Ensure that rc.local is executable:

chmod +x /etc/rc.d/rc.local

3. Run the rc.local script to make the changes:

/etc/rc.d/rc.local


# 2.1.4 Configurations

# 2.1.4.1 Splunk Enterprise Data Inputs

## 2.1.4.1.1 Syslog TCP

1. Go to Settings > Data Inputs > TCP.

Figure 2-1 Splunk Enterprise Syslog TCP Input



#### 2.1.4.1.2 Syslog UDP

1. Go to Settings > Data Inputs > UDP.

Figure 2-2 Splunk Enterprise Syslog UDP Input



#### 2.1.4.1.3 Receive Data from Splunk Universal Forwarders

- 1. Go to Settings > Forwarding and Receiving > Configure Receiving.
- 2. Click the New button, and enter port 9997.

Figure 2-3 Splunk Enterprise Receive from Splunk Universal Forwarder



# 2.1.4.2 Splunk Enterprise Indexes

Splunk Enterprise stores events in indexes. By default, the main index holds all events. However, using multiple indexes has several benefits including controlling user access to events, different retention policies for different events, and faster searches in certain situations. A separate index was created for each input type and stored in the data directory (/data/splunk). Table 2-2 contains the list of indexes that were created.

To create a new index, follow these steps.

- 1. On the web page for Splunk Enterprise (https://172.16.5.55:8000).
- 2. Navigate to **Settings > Indexes**. Then, click **New**.
- 3. Enter a **Name** for the index (see <u>Table 1-1</u> for the list of names).
- 4. Ensure that the **Home Path** is set to /data/splunk.

Follow the above steps for each index that you need to create. For additional information on indexes, go to: <a href="http://docs.splunk.com/Documentation/Splunk/6.2.3/Indexer/Setupmultipleindexes">http://docs.splunk.com/Documentation/Splunk/6.2.3/Indexer/Setupmultipleindexes</a>.

**Table 2-2 Splunk Enterprise Indexes** 

Index Name	
alerts	
assetcentral	
belmanage_computers	
belmanage_hotfixesmissing	
belmanage_hw_changes	

Index Name
belmanage_sw_changes
belmanage_software
bro
ca_itam
fathom
firewall
mainframe
openvas
puppet
router_configs
snort
syslog
tyco
wsus

# 2.1.4.3 Splunk Enterprise Apps

Several Splunk Enterprise Apps were used in this project. The list of Splunk Enterprise Apps needed for the ITAM project can be found in <u>Table 2-3</u>. Splunk Enterprise Apps assist in processing, analyzing and displaying different types of data. To download Splunk Enterprise Apps you must have a valid Splunk account. You can install Splunk Enterprise Apps from <a href="https://splunkbase.splunk.com/">https://splunkbase.splunk.com/</a>.

To install Splunk Enterpise Apps, follow these steps:

- 1. Download App from <a href="https://splunkbase.splunk.com/">https://splunkbase.splunk.com/</a>.
- 2. On Splunk Enterprise web (https://172.16.5.55:8000).
  - a. Apps (top left of web page) > Manage Apps
  - b. Click Install app from file.

**Table 2-3 Splunk Enterprise Apps** 

Splunk Add-On for Bro	Extracts information from Bro logs.
Splunk WebLog Add-On	Extracts information from web logs, such as those from an Apache server.
Splunk for Snort	Extracts information from Snort logs.

Splunk DB Connect v2	Run queries on external databases and stores the info in Splunk Enterprise indexes.
Splunk App for CEF	Extracts Common Event Format data
Technology Add-On for pfSense	Extracts information from pfSense router logs.
IP Reputation	Provides IP reputation information for Splunk Enterprise queries.
Google Maps	Provides geographic information and display for IP addresses.

The Splunk DB Connect v2 app requires the downloading and installation of specific database drivers. Database-specific drivers should be placed in the directory

\$SPLUNK\_HOME/etc/apps/splunk\_app\_db\_connect/bin/lib. This project required the installation of database drivers for Microsoft SQL and MySQL. The drivers must be obtained from the database manufacturers; in this case Microsoft and MySQL/Oracle. For more detailed information, please refer to Install database drivers at

http://docs.splunk.com/Documentation/DBX/latest/DeployDBX/Installdatabasedrivers. The required drivers are listed in Table 2-4.

**Table 2-4 Required Database Drivers** 

Database	Driver
Microsoft SQL	sqljdbc4.jar
MySQL	mysql-connector-java-5.1.36-bin.jar

# 2.1.4.4 Splunk Enterprise Connections

This section provides information about setting up connections that use the Splunk Enterprise DB Connect v2 app. The Splunk Enterprise DB Connect v2 app is used to connect to the following external databases: AssetCentral, BelManage and CA-ITAM.

To get data from an external database Splunk Enterprise DB Connect v2 requires 3 main steps:

- 1. Setup an identity. The identity is the username used to log into the database.
- 2. Setup a connection. The connection is the network and database information.
- 3. Setup an operation. The operation is what you want to do with the database (run an SQL query).

Table 2-5 provides the information needed to perform these steps.

Table 2-5 DB Connect v2 Identities

Identity	Used with
asset_query	AssetCentral
mike	BelManage
splunk	CA ITAM

## 2.1.4.4.1 Splunk Enterprise DB Connect v2 Connections

There should only be one database connection to each individual database. The database connections use the identities listed in <u>Table 2-5</u>. Please remember to select the **Enable** button when you configure each connection.

#### **DB Connect V2 AssetCentral Connection:**

AssetCentral

Status: Enabled

Connection Name: assetcentral

App: Splunk DB Connect v2

Host: assetcentral

Database Types: MySQL

Default Database: assetcentral

Identity: asset\_query

Port: 3306

Enable SSL: NOT CHECKEDReadonly: NOT CHECKED

# **DB Connect V2 BelManage Connection:**

BelManage

Status: Enabled

Connection Name: BelManage

App: Splunk DB Connect v2

Host: belmanage

Database Types: MS-SQL Server Using MS Generic Driver

Default Database: BelMonitor82\_1

Identity: mike

Port: 1433

Enable SSL: NOT CHECKEDReadonly: NOT CHECKED

#### **DB Connect V2 CA-ITAM Connection:**

CA-ITAM

Status: Enabled

Connection Name: ca-itam

App: Splunk DB Connect v2

Host: ca-itam

Database Types: MS-SQL Server Using MS Generic Driver

Default Database: mdb

Identity: splunk

Port: 1433

Enable SSL: NOT CHECKEDReadonly: NOT CHECKED

#### 2.1.4.4.2 Splunk Enterprise DB Connect v2 Operations

Operations are the SQL operations performed on the database connections and the results are saved into Splunk Enterprise indexes. The operations can be run automatically, on a recurring basis, or when new data is detected.

Each operation has four components:

- Name Input
- Choose and Preview Table
- Set Parameters
- Metadata

The following subsections show the configurations for each operation.

#### AssetCentral:

DB Input: assetcentral

- 1. Name Input
  - a. Status: Enabled
  - b. Name: assetcentral
  - c. Description: Assets from AssetCentral
  - d. App: Splunk DB Connect v2
  - e. Connection: assetcentral
  - f. Click the **Continue** button.
- 2. Choose and Preview Table
  - a. Make sure that **Simple Query Mode** is selected.
  - b. Catalog: assetcentral
  - c. Schema: NULL
  - d. Table: assetview
  - e. Max rows: 100
  - f. Click the Magnifying Glass button and up to 100 rows should be returned and displayed.
  - g. Click the **Continue** button.
- 3. Set Parameters
  - a. Type: Batch Input
  - b. Max Rows to Retrieve: 100000
  - c. Timestamp: Current Index Time
  - d. Output Timestamp Format: YYYY-MM-dd HH:mm:ss
  - e. Execution Frequency: 0 0 \* \* \*
  - f. Click the **Continue** button.

#### 4. Metadata

a. Source: assetcentral

b. Sourcetype: assetcentral

c. Index: assetcentral

d. Select Resource Pool: local

e. Click the **Save** button.

## BelManage\_Computers:

DB Input: BelManage\_Computers

## 1. Name Input

a. Status: Enabled

b. Name: BelManage\_Computers

c. Description: Computer info from BelManage

d. App: Splunk DB Connect v2

e. Connection: BelManage

f. Click the **Continue** button.

#### 2. Choose and Preview Table

a. Make sure that **Simple Query Mode** is selected.

b. Catalog: BelMonitor82\_1

c. Schema: dbo

d. Table: Computers

e. Max rows: 100

f. Click the Magnifying Glass button and up to 100 rows should be returned and displayed.

g. Click the **Continue** button.

#### 3. Set Parameters

a. Type: Rising Column

b. Max Rows to Retrieve: 100000

- c. Specify Rising Column: ProfileDate
- d. Timestamp: Current Index Time
- e. Output Timestamp Format: YYYY-MM-dd HH:mm:ss
- f. Execution Frequency: \* \* \* \* \*
- g. Click the Continue button.

#### 4. Metadata

a. Source: belmanage

b. Souretype: belmanage\_computers

c. Index: belmanage\_computers

d. Select Resource Pool: local

e. Click the **Save** button.

# Belmanage\_hotfixesmissing:

DB Input: belmanage\_hotfixesmissing

# 1. Name Input

a. Status: Enabled

b. Name: belmanage\_hotfixesmissing

c. Description: List of hotfixes/patches missing from each computer

d. App: Splunk DB Connect v2

e. Connection: BelManage

f. Click the **Continue** button.

#### 2. Choose and Preview Table

- a. Make sure that **Advanced Query Mode** is selected.
- b. In the entry box type in the following SQL statement:

```
SELECT HotfixesMissing.*, Computers.ProfileName,
Comput-ers.NetworkIPAddress FROM HotfixesMissing INNER JOIN Computers on
HotfixesMissing.Id = Computers.Id
```

- c. Click the Magnifying Glass button and up to 100 rows should be returned and displayed.
- d. Click the Continue button.

#### 3. Set Parameters

a. Type: Batch Input

b. Max Rows to Retrieve: 100000

c. Timestamp: Current Index Time

d. Output Timestamp Format: YYYY-MM-dd HH:mm:ss

e. Execution Frequency: 30 4 \* \* \*

f. Click the **Continue** button.

#### 4. Metadata

a. Source: belmanage

b. Sourcetype: belmanage\_hotfixesmissing

c. Index: belmanage\_hotfixesmissing

d. Select Resource Pool: local

e. Click the **Save** button.

# Belmanage\_hw\_changes:

DB Input: belmanage\_hw\_changes

#### 1. Name Input

a. Status: Enabled

b. Name: belmanage\_hw\_changes

c. Description: BelManage hardware changes

d. App: Splunk DB Connect v2

e. Connection: BelManage

f. Click the **Continue** button.

# 2. Choose and Preview Table

a. Make sure that **Simple Query Mode** is selected.

b. Catalog: BelMonitor82\_1

c. Schema: dbo

d. Table: HistoryReportAllHardware

e. Max rows: 100

f. Click the Magnifying Glass button and up to 100 rows should be returned and displayed.

g. Click the **Continue** button.

#### 3. Set Parameters

a. Type: Rising Column

b. Max Rows to Retrieve: 10000

c. Specify Rising Column: ActionDate

d. Timestamp: Current Index Time

e. Output Timestamp Format: YYYY-MM-dd HH:mm:ss

f. Execution Frequency: \*/15 \* \* \* \*

g. Click the **Continue** button.

#### 4. Metadata

a. Source: belmanage

b. Sourcetype: belmanage\_hw\_changes

c. Index: belmanage\_hw\_changes

d. Select Resource Pool: local

e. Click the **Save** button.

# Belmanage\_software:

DB Input: belmanage\_software

# 1. Name Input

a. Status: Enabled

b. Name: belmanage\_software

c. Description: Software from BelManage

d. App: Splunk DB Connect v2

e. Connection: BelManage

f. Click the Continue button.

#### 2. Choose and Preview Table

- a. Make sure that **Advanced Query Mode** is selected.
- b. In the entry box type in the following SQL statement:

```
SELECT
ProfileName,
Directory,
C.ProfileDate AS ProfileDate soft, CAST(C.ProfileDate AS DATE) AS
ProfileDateDate soft,
DATEDIFF (dd, ProfileDate, GETDATE() ) AS ProfileDateDaysAgo soft,
DATEDIFF (mm, ProfileDate, GETDATE() ) AS ProfileDate-MonthsAgo soft,
CASE WHEN CAST ( (CAST(GETDATE() AS FLOAT) - CAST(ProfileDate AS FLOAT))
AS INT) < 31 THEN 'yes' ELSE 'no' END AS
ProfileDateWithin-Last30Days soft,
CASE WHEN CAST ( (CAST(GETDATE() AS FLOAT) - CAST(ProfileDate AS FLOAT))
AS INT) < 61 THEN 'yes' ELSE 'no' END AS
ProfileDateWithin-Last60Days soft,
CASE WHEN CAST ( (CAST(GETDATE() AS FLOAT) - CAST(ProfileDate AS FLOAT))
AS INT) < 91 THEN 'yes' ELSE 'no' END AS
ProfileDateWithin-Last90Days soft,
CASE WHEN LastUsedTime > CAST('1971-01-01' AS smalldatetime) THEN
LastUsedTime ELSE NULL END AS LastUsedTime soft,
CASE WHEN LastUsedTime > CAST('1971-01-01' AS smalldatetime) THEN
CAST(LastUsedTime AS DATE) ELSE NULL END AS LastUsedDate soft,
-- SS2005 compatible: CASE WHEN LastUsedTime > CAST('1971-01-01' AS
smalldatetime) THEN CAST(FLOOR(CAST(LastUsedTime AS FLOAT)) AS
smalldatetime) ELSE NULL END AS LastUsedDate soft,
CASE WHEN LastUsedTime > CAST('1971-01-01' AS smalldatetime) THEN
DATEDIFF (dd, LastUsedTime, C. ProfileDate) ELSE NULL END AS
LastUsed-DaysAgo soft,
CASE WHEN LastUsedTime > CAST('1971-01-01' AS smalldatetime) THEN
DATEDIFF (mm, LastUsedTime, C. ProfileDate) ELSE NULL END AS
```

```
LastUsed-MonthsAgo soft,
CASE WHEN LastUsedTime > CAST('1971-01-01' AS smalldatetime) THEN CASE
WHEN CAST ( (CAST(C.ProfileDate AS FLOAT) - CAST(LastUsedTime AS FLOAT))
AS INT) < 31 THEN 'yes' ELSE 'no' END ELSE NULL END AS
LastUsedTimeWithinLast30Days soft,
CASE WHEN LastUsedTime > CAST('1971-01-01' AS smalldatetime) THEN CASE
WHEN CAST ( (CAST(C.ProfileDate AS FLOAT) - CAST(LastUsedTime AS FLOAT))
AS INT) < 61 THEN 'yes' ELSE 'no' END ELSE NULL END AS
LastUsedTimeWithinLast60Days soft,
CASE WHEN LastUsedTime > CAST('1971-01-01' AS smalldatetime) THEN CASE
WHEN CAST ( (CAST(C.ProfileDate AS FLOAT) - CAST(LastUsedTime AS FLOAT))
AS INT) < 91 THEN 'yes' ELSE 'no' END ELSE NULL END AS
LastUsedTimeWithinLast90Days soft,
Company AS Company_soft, Product AS Product_soft, Version6Part AS
Version6Part soft, Version AS Version soft,
CAST(dbo.VersionMajor(Version6Part) AS varchar(6)) AS Ver-sionMajor soft,
CAST(dbo.VersionMajor(Version6Part) AS varchar(6)) + '.' +
CAST(dbo.VersionMinor(Version6Part) AS varchar(6)) AS VersionMa-
jorMinor soft,
CAST(dbo.VersionMajor(Version6Part) AS varchar(6)) + '.' +
CAST(dbo.VersionMinor(Version6Part) AS varchar(6)) + '.' +
CAST(dbo.VersionRev(Version6Part) AS varchar(6)) AS VersionMajorMi-
norRev soft,
FileDescription, Filename, FileSize,
dbo.VersionFormat(dbo.VersionCompose (ProductVersionNoMS,
ProductVersionNoLS)) AS ProductVersionNo,
dbo.VersionFormat(dbo.VersionCompose (FileVersionNoMS, FileVer-sionNoLS))
AS FileVersionNo,
CASE StartUp WHEN 1 THEN 'auto' ELSE 'user' END AS StartUp,
CASE Inuse WHEN 1 THEN 'yes' WHEN 0 THEN 'no' ELSE NULL END AS Inuse,
CASE ServiceStatus WHEN 1 THEN 'running' WHEN 0 THEN 'stopped' ELSE NULL
END AS ServiceStatus,
CASE ServiceStartType WHEN 2 THEN 'auto' WHEN 3 THEN 'manual' WHEN 4 THEN
'disabled' ELSE NULL END AS ServiceStartType,
LastUserDomain, LastUser, LastUserFullName,
```

CASE WHEN Is64Bit = 1 THEN 'yes' ELSE 'no' END AS Is64Bit,

```
CASE WHEN IsNativeToOs = 1 THEN 'yes' ELSE 'no' END AS IsNativeToOs, MachineType,

ExeHeaderTypeLong AS ExeHeaderType, LoginUser,

S.Language AS Language_soft, S.LanguageName AS LanguageName_soft FROM

Software S INNER JOIN Computers C ON S.Id = C.Id;
```

- c. Click the Magnifying Glass button and up to 100 rows should be returned and displayed.
- d. Click the Continue button.

#### 3. Set Parameters

a. Type: Rising Column

b. Max Rows to Retrieve: 10000

c. Specify Rising Column: ProfileDate\_soft

d. Timestamp: Current Index Time

e. Output Timestamp Format: YYYY-MM-dd HH:mm:ss

f. Execution Frequency: \* \* \* \*

g. Click the **Continue** button.

#### 4. Metadata

a. Source: belmanage

b. Sourcetype: belmanage\_software

c. Index: belmanage\_software

d. Select Resource Pool: local

e. Click the **Save** button.

# Belmanage\_sw\_changes:

DB Input: belmanage\_sw\_changes

# 1. Name Input

a. Status: Enabled

b. Name: belmanage\_sw\_changes

c. Description: Software changes from BelManage

d. App: Splunk DB Connect v2

e. Connection: BelManage

f. Click the **Continue** button.

#### 2. Choose and Preview Table

a. Make sure that **Simple Query Mode** is selected.

b. Catalog: BelMonitor82\_1

c. Schema: dbo

d. Table: SoftwareHistoryReport

e. Max rows: 100

f. Click the Magnifying Glass button and up to 100 rows should be returned and displayed.

g. Click the **Continue** button.

#### 3. Set Parameters

a. Type: Rising Column

b. Max Rows to Retrieve: 100000

c. Specify Rising Column: ActionDate

d. Timestamp: Current Index Time

e. Output Timestamp Format: YYYY-MM-dd HH:mm:ss

f. Execution Frequency: \*/30 \* \* \* \*

g. Click the **Continue** button.

#### 4. Metadata

a. Source: belmanage

b. Sourcetype: belmanage\_sw\_changes

c. Index: belmanage\_sw\_changes

d. Select Resource Pool: local

e. Click the **Save** button.

#### CA ITAM:

DB Input: ca-itam

- 1. Name Input
  - a. Status: Enabled
  - b. Name: ca-itam
  - c. Description: Asset from CA ITAM software
  - d. App: Splunk DB Connect v2
  - e. Connection: ca-itam
  - f. Click the **Continue** button.
- 2. Choose and Preview Table
  - a. Make sure that **Advanced Query Mode** is selected.
  - b. In the entry box type in the following SQL statement:

```
SELECT DISTINCT

aud_ca_owned_resource.resource_name,audit_model_uuid,audit_resource_cl
ass, audit_resource_subclass,
ca_owned_resource.own_resource_id,ca_owned_resource.mac_address,ca_own
ed_resource.ip_address,ca_owned_resource.host_name,ca_owned_resource.s
erial_number,ca_owned_resource.asset_source_uuid,ca_owned_resource.cre
ation_user,ca_owned_resource.creation_date,
al_aud_contact_view.first_name, al_aud_contact_view.middle_name,
al_aud_contact_view.last_name, al_aud_contact_view.pri_phone_number,
ca_owned_resource.last_update_date

FROM aud_ca_owned_resource INNER JOIN ca_owned_resource

ON aud_ca_owned_resource.resource_name=ca_owned_resource.resource_name

INNER JOIN al_aud_contact_view

ON ca_owned_resource.resource_contact_uuid =
al aud contact_view.contact_uuid
```

- c. Click the Magnifying Glass button and up to 100 rows should be returned and displayed.
- d. Click the Continue button.
- 3. Set Parameters
  - a. Type: Rising Column

b. Max Rows to Retrieve: 1000

c. Specify Rising Column: last\_update\_date

d. Timestamp: Current Index Time

e. Output Timestamp Format: YYYY-MM-dd HH:mm:ss

f. Execution Frequency: \*/5 \* \* \* \*

g. Click the Continue button.

#### 4. Metadata

a. Source: ca-itam

b. Sourcetype: ca-itam

c. Index: ca\_itam

Note: the index name is **ca\_itam** with an underscore. Splunk Enterprise does not accept dashes in index names.

d. Select Resource Pool: local

e. Click the Save button.

# 2.1.5 Lookup Table Files

Several lookup table files are necessary for this project. The lookup table files are in comma separated value format and contain data generated by reports that are used in other reports and dash-boards.

To create a lookup table file:

- 1. Open the Splunk Enterprise web page (https://172.16.5.55:8000) and go to the **Lookup table files** page.
- Select Settings > Lookups.
- 3. Click Lookup table files.
- 4. Click the **New** button.

Create the following lookup table files:

- /opt/splunk/etc/apps/search/lookups/AssetRisk\_Alltime.csv
- /opt/splunk/etc/apps/search/lookups/AssetRisk\_Last7days.csv
- /opt/splunk/etc/apps/search/lookups/AssetRisk\_Last24hours.csv

- /opt/splunk/etc/apps/search/lookups/asset\_value\_table.csv
- /opt/splunk/etc/apps/search/lookups/license\_table.csv
- /opt/splunk/etc/apps/search/lookups/updown
- /opt/splunk/etc/apps/search/lookups/vun\_rating\_table.csv

## 2.1.5.1 Splunk Enterprise Configuration Files

Splunk Enterprise configuration files can be found in the external file titled Splunk Configuration Files.tar.gz.

Configuration files are stored on Splunk Enterprise in the \$SPLUNK HOME/etc/system/local directory.

# 2.1.5.2 Splunk Enterprise Dashboards

Splunk Enterprise stores dashboards in XML format. All of the dashboards can be found in the external file titled Splunk Dashboards.tar.gz.

Splunk Enterprise dashboard files are stored on Splunk Enterprise in the \$SPLUNK\_HOME/etc/apps/search/local/data/ui/views directory.

## 2.1.5.3 Restarting Splunk Enterprise After Configuration File Changes

When you make changes to Splunk Enterprise using configuration files, you might need to restart Splunk Enterprise for the changes to take effect. See the following link for details:

http://docs.splunk.com/Documentation/Splunk/6.2.3/Admin/Configurationfilechangesthatreq uirerestart.

## 3 Tier 2

## 3.1 AssetCentral

AssetCentral is an IT infrastructure management system that stores and displays information related to physical assets including location, make, model, and serial number. AssetCentral can help run an entire data center by monitoring weight, utilization, available space, heat and power distribution. AssetCentral is installed on a CentOS7 system.

#### 3.1.1 How It's Used

In the FS ITAM build AssetCentral is used to provide physical asset location. AssetCentral provides the building, room and rack of an asset.

# 3.1.2 Virtual Machine Configuration

The virtual machine is configured with 1 network interface cards, 4 GB of RAM and 1 CPU cores.

# 3.1.3 Network Configuration

The management network interface card is configured as such:

IPv4 Manual

IPv6 Ignore/Disabled

IP Address: 172.16.1.50Netmask: 255.255.255.0

Gateway: 172.16.1.11

DNS Servers: 172.16.1.20, 172.16.1.21

Search Domains: lab5.nccoe.gov

# 3.1.4 Installing AssetCentral

AssetCentral is installed on a hardened CentOS7 Linux system. AssetCentral requires PHP, Web Server (Apache) and MySQL database to be installed.

Table 3-1 Recommended Versions for AssetCentral – Tier 2

Vendor	Product	Version
RedHat	Enterprise Linux Server	6.4 (Santiago) (x86_64)
Apache	Web Server	httpd-2.2.15-26.el6.x86_64
mysql	Server	5.1.66
php		5.33 or higher

# 3.1.5 Installing MySQL (MariaDB)

```
# yum -y install mariadb-server mariadb
```

#systemctl start mariadb.service

#systemctl enable mariadb.service

- # mysql\_secure\_installation
  - 1. Answer the questions with the default answers while performing the mysql\_secure\_installation.
  - 2. Create a database assetcentral.

- 3. Create a user assetcentral.
- 4. Grant all privileges to assetcentral user.

# 3.1.6 Installing Apache

```
# yum -y install httpd
#systemctl start httpd.service
#systemctl enable httpd.service
#firewall-cmd --permanent --zone=public --add-service=http
#firewall-cmd --permanent --zone=public --add-service=https
#firewall-cmd --reload
```

# 3.1.6.1 HTTP Configuration

- 1. Go to HTTPD root; normally (/etc/httpd).
- 2. Under the modules directory, make sure *libphp5.so* exists.
- 3. Change document root (webroot) as per environment in *httpd.conf*.

# 3.1.7 Installing PHP5

```
#yum -y install php
```

```
#systemctl restart httpd.service
#yum search php
#yum -y install php-mysql
#yum -y install php-gd php-ldap php-odbc php-pear php-xml php-xmlrpc php-mbstring php-snmp php-soap curl curl-devel
```

1. Restart Apache:

```
#systemctl restart httpd.service
```

## 3.1.8 Post Installation Tasks

- 1. Copy AssetCentral files and folders from previous install to the new webroot.
- 2. Under the location (../assetcentral/application/config), make necessary changes as per environment.

## 3.1.8.1 Sample

```
<?php defined('ASSET_CENTRAL') or die(''); define('AC_URL_SUBDIR', '/acprod');
define('AC_URL_SCRIPT','/index.php'); define('AC_URL_PARAM','go');
define('AC_URL_PREFIX',AC_URL_SUBDIR . AC_URL_SCRIPT.'?'

. AC_URL_PARAM . '='); define('AC_ERROR_REPORTING',E_ERROR);
//no slash at the end of this url define('URL_SITE','http://10.1.xx.xxx');
define('OS','NIX'); // *NIX WIN BSD MAC
//default database (read) define('DB_TYPE_READ','MYSQL');
define('DB_HOST_READ','127.0.0.1');
//usually leave this blank for MYSQL define('DB_PORT_READ','');
define('DB_USER_READ','assetcentral'); define('DB_PASS_READ','xxxxxx');
define('DB_DATA_READ','asset_prod'); define('DB_PREFIX_READ','');</pre>
```

# 3.1.9 Database Update – Add a View

A database view was created on AssetCentral to gather all of the information required by the ITAM project in one place. This database view is accessed directly from Splunk Enterprise.

 On the AssetCentral machine, open a terminal window and type the following command to enter the MySQL client application (you will be asked for the root password of the MySQL database):

```
mysql assetcentral -u root -p
```

2. The following command will create the assetview view (from inside of the MySQL client application):

```
create view assetview as
select a.asset_id, a.rack_id, a.system_id, a.contact_id, a.serial_number,
a.asset_tag, a.asset_name, a.ip_addr, a.description, a.title,
a.internal_number, rack.rack_name, rack.room_id, rack.rack_type,
rack.rack_notes, s.system_name, s.system_description,
c.contact_name, c.phone_number, c.email_address, room.room_name, room.floor_id,
floor.floor_name

from assets a

left join racks rack on a.rack_id = rack.rack_id left join systems s on
a.system_id = s.system_id left join contacts c on a.contact_id = c.contact_id
left join rooms room on rack.room_id = room.room_id

left join floors floor on room.floor_id = floor.floor_id where a.asset_deleted
!= 1;
```

3. Create a new database user and assign that user privilges on the assetview view (from inside of the MySQL client application):

```
create new users and privileges inside mysql/mariadb create user
'asset_query'@'localhost';
set password for 'asset_query'@'localhost' = password('password'); grant select
on assetcentral.assetview to 'asset_query'@'localhost'; grant file on *.* to
'asset query'@'localhost';
```

- 4. Ensure that the MySQL network port is listening and is allowed through the firewall. You must be root to run these commands.
- 5. To verify that MySQL is listening:

```
netstat -l |grep mysql
```

6. To allow MySQL through the firewalld firewall:

```
firewall-cmd -permanent -add-service=mysql firewall-cmd -reload
```

7. To make sure the firewall rule was added correctly:

```
firewall-cmd -list-services
```

#### 3.1.10 Add Assets into AssetCentral

For AssetCentral to be of use, the end user must populate the system with all of the IT hardware to be tracked.

AssetCentral provides a manual method of adding one or two assets as well as an automated method of adding numerous assets that have been saved in a spreadsheet.

# 3.2 BelManage

BelManage is installed on a Windows Server 2012R2 system. BelManage gathers hardware and software information from computers on the network. BelManage gathers, stores, analyzes and displays the hardware and software information in a Web application. The BelMonitor client is installed on all computers in the network and automatically sends the BelManage server information on hardware and software changes.

#### 3.2.1 How It's Used

The ITAM system is using BelManage for its data gathering, analysis and reporting features. BelManage reports on all software installed and all hardware configurations for every machine on the network that is running the BelMonitor client.

Splunk Enterprise connects to the BelManage database to pull data and provide further analysis and correlation.

# 3.2.2 Virtual Machine Configuration

The BelManage virtual machine is configured with 1 network interface card, 8 gigabytes (GB) of random access memory (RAM) and one central processing unit (CPU) core.

# 3.2.3 Network Configuration

The management network interface card is configured as follows:

IPv4 Manual

IPv6 Disabled

IP Address: 172.16.2.71
Netmask: 255.255.255.0
Gateway: 172.16.2.11

DNS Servers: 172.16.1.20, 172.16.1.21

Search Domains: lab5.nccoe.gov

# 3.2.4 Installing BelManage

Before installing BelManage, verify that your Windows Server 2012R2 system is installed correctly, updated and that the network is correctly configured and working. Additionally, you may have to disable or modify some security services, such as AppLocker, during the installation process.

BelManage is installed by running the BelManage server installation program (BelManageServer8.1.31.exe). Documentation is provided by Belarc at https://www.belarc.com/en/products\_belmanage.

# 3.2.4.1 Prerequisites

**Internet Information Server (IIS)** 4.0 or later must be installed. The website below has detailed instructions on installing IIS: <a href="http://www.iis.net/learn/install/installing-iis-85/installing-iis-85-on-windows-server-2012-r2">http://www.iis.net/learn/install/installing-iis-85/installing-iis-85-on-windows-server-2012-r2</a>.

BelManage requires the following options: Static Content, Default Document, ASP Application Development, IIS Management Scripts and Tools, IIS 6 Metabase Compatibility, IIS 6 WMI Compatibility, and IIS 6 Scripting Tools.

MS SQL Express will be installed as part of the normal BelManage installation process.

**Microsoft (MS) Structured Query Language (SQL) Server Management Studio** is not required but is highly recommended. MS SQL Server Management Studio will make it easy to work on the BelManage database. Make sure you run MS SQL Server Management Studio as administrator or you will get

permission errors. Additional information can be found at: <a href="https://msdn.microsoft.com/en-us/library/ms174173.aspx">https://msdn.microsoft.com/en-us/library/ms174173.aspx</a>.

#### 3.2.4.2 Installation Procedure

#### 3.2.4.2.1 Installing the BelManage Server

- 1. Open Windows File Explorer and navigate to where your BelManage installer is located.
- 2. Right-click on the BelManage installer file and select **Run as Administrator**.
- 3. Choose the default selections.

Note: You will need to enter your BelManage license number during the installation process.

#### 3.2.4.2.2 Installing the BelManage Client

The BelMonitor client must be installed on all devices that you wish to monitor.

The BelMonitor client should also be installed on the BelManage server if you wish to monitor.

1. The BelMonitor client can be downloaded directly from the BelManage server that was just installed: Point your web browser to your BelManage server (172.16.2.71):

http://172.16.2.71/BelManage

- 2. Enter your login and password.
- 3. Select the **Getting Started** option on the left side of the page.
- 4. Select **Download your installable BelMonitor client** from the middle of the page.
- 5. Select the appropriate download Windows, Linux, Mac OSX or Solaris.
- 6. Follow the steps in the relevant section.
  - a. For Windows machines:
    - i. Right-click the BelMonitor client and select **Run as Administrator**.
    - ii. Then accept the default settings. The BelMonitor client will be installed and set to autorun when the system boots. There should be an icon in your system tray (right-side) that looks like a little green eye with eyelashes.
  - b. For Linux machines:

The BelMonitor client must be installed as the root user.

i. To install the BelMonitorLinux client on Linux machines you must first install the 32-bit compatibility libraries. On Ubuntu the process is as follows:

```
apt-get install lib32stdc++6
```

ii. The BelMonitor client uses RPM (RedHat Package Manager) which can be installed as follows:

```
apt-get install rpm
```

iii. Make the BelMonitorLinux executable.

```
chmod a+x BelMonitorLinux
```

iv. Start the installation.

./BelMonitorLinux

The BelMonitor client should now be running and reporting to the BelManage server every 15 minutes (default setting).

# 3.2.5 Integration and Final Steps

- Use MS SQL Server Studio Manager to create a database user for the Splunk Enterprise database connection. A new user must be created and be added to the correct database for the Splunk Enterprise integration to work.
- 2. Right-click MS SQL Server Studio Manager and select **Run as Administrator**.
- 3. Click **Connect** as the default settings should be correct:

Server type: Database Engine

Server name: BELARC\BELMANAGE

Authentication: Windows Authentication

- 4. Once MS SQL Server Management Studio has logged in and started, create a new database user.
  - a. Select **Security** > **Logins**.
  - b. Right-click Logins and select New User.
  - c. Enter a Login name.
  - d. Select SQL Server authentication.
  - e. Enter a password.
  - f. Enter the password again in the **Confirm password** box.
  - g. The Enforce password policy, **Enforce password expiration** and **User must change password at next login** should all reflect your organization's security rules.

Default database = **BelMonitor82\_1** 

Default language = English

- 5. Add the new user that you created in the preceding steps to the **BelMonitor82\_1** database.
  - a. Select Databases > BelMonitor82\_1 > Security > Users.
  - b. Right-click **Users** and select **New User**.
  - c. Enter a user name for the new user in the **User Name** and **Login Name** fields. They should be identical.

Default schema = db\_datareader

Schemas owned by this user = none selected

- d. Database role membership: BelMonitorReader and db\_datareader should be checked.
- 6. Turn on or re-enable any security settings that you might have changed, such as AppLocker.

#### 3.3 Bro

Bro is an open-source network security monitor. Bro efficiently analyzes all network traffic and provides insight into clear text password use, cryptographic certificate errors, traffic to known bad sites, network flow, and file transfers.

#### 3.3.1 How It's Used

In the FS ITAM build, Bro monitors all traffic traversing the DMZ. Bro has a dedicated network interface in promiscuous mode for sniffing/capturing traffic. This interface does not have an IP address assigned. Bro has a second network interface for management that is assigned IP address 172.16.0.20. When configuring Bro, make sure that Bro is sniffing/capturing on the correct network interface.

On the high-level architecture diagram, Bro is in Tier 2. Bro uses the Splunk Universal Forwarder to send logs to Splunk Enterprise. Some of the logs include files, Hypertext Transfer Protocol (HTTP) traffic, Kerberos authentications, Secure Socket Layer (SSL) traffic, x509 certificates seen, known hosts, DNS traffic, all connections, notices, and intelligence alerts.

# 3.3.2 Virtual Machine Configuration

The Bro virtual machine is configured with two network interface cards, 16 GB of RAM and four CPU cores.

# 3.3.3 Network Configuration

The management network interface card is configured as follows:

IPv4 Manual

IPv6 Ignore/Disabled

IP Address: 172.16.0.20

Netmask: 255.255.255.0

Gateway: 172.16.0.11

DNS Servers: 172.16.1.20, 172.16.1.21

Search Domains: lab5.nccoe.gov

# 3.3.4 Installing Bro

Bro is installed on a hardened Ubuntu 14.04 Linux system. Please download the latest source package from Bro and follow the instructions for installing from source. Installation was performed following the instruction from Bro at: https://www.bro.org/sphinx/install/index.html.

# 3.3.4.1 Installation Prerequisites

Bro requires the following libraries and tools to be installed before you begin:

- Libpcap (<a href="http://www.tcpdump.org">http://www.tcpdump.org</a>)
- OpenSSL libraries (http://www.openssl.org)
- BIND8 library
- Libz
- Bash (for BroControl)
- Python (for BroControl)

To build Bro from source, the following additional dependencies are required:

- CMake 2.8 or greater (<a href="http://www.cmake.org">http://www.cmake.org</a>)
- Make
- C/C++ compiler
- SWIG (<a href="http://www.swig.org">http://www.swig.org</a>)
- Bison (GNU Parser Generator)
- Flex (Fast Lexical Analyzer)

- Libpcap headers (<a href="http://www.tcpdump.org">http://www.tcpdump.org</a>)
- OpenSSL headers (<a href="http://www.openssl.org">http://www.openssl.org</a>)
- zlib headers
- Perl

#### 3.3.4.1.1 For Debian/Ubuntu Linux systems:

1. It is always best to make sure your system is up-to-date by performing:

```
sudo apt-get update sudo apt-get upgrade
```

2. Then install the prerequisites:

```
sudo apt-get install cmake make gcc g++ flex bison libpcap-dev libssl-dev
python-dev swig zliblg-dev
sudo apt-get install libgeoip-dev
sudo apt-get install libgoogle-perftools-dev sudo apt-get install curl
sudo apt-get install git
```

3. Download and install Bro (this will install in /usr/local/bro):

Note: You need to be root to install Bro.

```
cd /usr/local
git clone https://github.com/actor-framework/actor-framework.git cd
/usr/local/actor-framework
./configure make
make test
make install
```

#### 3.3.4.2 Installation Procedure

```
cd /usr/local
git clone --recursive git://git.bro.org/bro cd /usr/local/bro
./configure make
make install
```

1. Add Bro bin directory to your runtime path:

```
Edit .bashrc
```

2. Add the following line to the end of .bashrc:

```
EXPORT PATH=/usr/local/bro/bin:$PATH
```

3. Then:

```
source .bashrc
```

4. To start Bro the first time:

```
broctl deploy
```

5. To check the status of Bro:

```
broctl status
```

# 3.3.5 Installing Intelligence Gathering Software

1. Uses the mal-dnssearch package from Jon Schipp, which must be installed. The compiled version will be installed into /usr/local/bin/mal-dnssearch.

```
cd /opt
git clone https://github.com/jonschipp/mal-dnssearch cd /opt/mal-dnssearch
sudo make
sudo make install
mkdir /usr/local/bro_intel
cd /usr/local/bro_intel
```

2. Copy the update\_intel.sh script into /usr/local/bro\_intel.

```
cp update_intel.sh /usr/local/bro_intel
chmod 700 /usr/local/bro_intel/update_intel.sh cd /usr/local/bro_intel
./update intel.sh
```

You should now have several files usable with the Bro Intelligence Framework, including tor.intel, mandiant.intel, and alienvault.intel.

3. To have the script run automatically every day, add a link inside /etc/cron.daily.

```
ln -s /usr/local/bro_intel/update_intel.sh
/etc/cron.daily/update_intel
```

# 3.3.6 Configuring Bro

To implement all of the functionality in the FS-ITAM use case build, the default Bro configurations will need to be modified. Please follow these steps to gain the same functionality.

1. Stop Bro:

broctl stop

#### 2. Copy and edit node.cfg:

```
cp /usr/local/bro/etc/node.cfg /usr/local/bro/etc/node.cfg.orig cp
<source_dir>/node.cfg /usr/local/bro/etc
```

Edit **node.cfg**, making sure that **interface=eth0** is the correct interface on which you will be sniffing/capturing traffic (NOT your management interface).

#### 3. Edit networks.cfg:

The networks.cfg file identifies all of your internal networks, so please list them all here. Below is our example:

List of local networks in CIDR notation, optionally followed by a descriptive tag. For example:

```
10.0.0.0/8 or fe80::/64 are valid prefixes.

10.0.0.0/8 Private IP space

192.168.0.0/16 Private IP space

172.16.0.0/16 Private IP space
```

#### 4. Edit the local.bro file to reflect the settings you want:

```
cp /usr/local/bro/share/bro/site/local.bro
/usr/local/bro/share/bro/site/local.bro.orig
cp <source dir>/local.bro /usr/local/bro/share/bro/site/
```

#### 5. Check changes, install changes, and restart Bro:

```
broctl check broctl install broctl start broctl status
```

If everything goes right, you should start seeing log files in /usr/local/bro/logs/current.

# 3.3.7 Installing Splunk Universal Forwarder

Note: You will need a Splunk account to download the Splunk Universal Forwarder. The Splunk Universal Forwarder is free and can be downloaded from: https://www.splunk.com/page/sign\_up.

- 1. Download the Splunk Universal Forwarder from: <a href="http://www.splunk.com/en\_us/download/uni-versal-forwarder.html">http://www.splunk.com/en\_us/download/uni-versal-forwarder.html</a>.
- 2. You want the latest version for OS version 2.6+ kernel Linux distributions (64-bit). Since this is installing on Ubuntu, select the file that ends in .deb. An example is:

```
splunkforwader-6.2.5-272645-linux-2.6-amd64.deb
```

#### Detailed installation instructions can be found at:

http://docs.splunk.com/Documentation/Splunk/6.2.3/Installation/InstallonLinux.

3. An abridged version follows:

```
dpkg -i <splunk_package_name.deb>
Example: dpkg -i splunkforwader-6.2.5-272645-linux-2.6-amd64.deb
```

4. This will install in /opt/splunkforwarder:

```
cd /opt/splunkforwarder/bin
./splunk start --accept-license
./splunk enable boot-start
```

5. Add forwarder:

More information about adding a forwarder can be found at:

http://docs.splunk.com/Documentation/Splunk/6.2.3/Forwarding/Deployanixdfmanually.

```
cd /opt/splunkforwarder/bin
./splunk add forward-server loghost:9997 -auth admin:changme
```

# 3.3.8 Configuring Splunk Universal Forwarder

Configuring Splunk Universal Forwarder as shown in the FS-ITAM use case requires X.509 Certificates for the Splunk Enterprise server/indexer and each Splunk Universal Forwarder. You will also need a copy of your certificate authority's public certificate.

1. Create a directory to hold your certificates:

```
mkdir /opt/splunkforwarder/etc/certs
```

2. Copy your certificates in PEM format to /opt/splunkforwarder/etc/certs:

```
cp CAServerCert.pem /opt/splunkforwarder/etc/certs
cp bro worker1.pem /opt/splunkforwarder/etc/certs
```

3. Copy the Splunk Universal Forwarder configuration files:

```
cp <server.conf> /opt/splunkforwarder/etc/system/local
cp <inputs.conf> /opt/splunkforwarder/etc/system/local
cp <outputs.conf> /opt/splunkforwarder/etc/system/local
```

4. Modify **server.conf** so that:

**ServerName=Bro** is your hostname.

```
sslKeysfilePassword = <password for your private key>
```

#### 5. Modify **outputs.conf** so that:

**Server = loghost:9997** is your correct Splunk Enterprise server/indexer and port.

```
sslPassword = <password of your certificate private key>
```

Note: This will be hashed and not clear text after a restart.

Inputs.conf should work, but you are free to modify it to include the Bro logs that you are interested in.

Note: dns.log, conn.log and http.log generate a significant volume of messages for Splunk Enterprise to index. Depending on the size of your Splunk Enterprise license, this data volume might cause license warnings or violations. See

http://docs.splunk.com/Documentation/Splunk/6.2.3/Admin/Aboutlicenseviolations for more information.

# 3.3.9 Configurations and Scripts

**Update\_intel.sh** should be placed in /usr/local/bro\_intel.

```
#!/bin/sh
# This script downloads and formats reputation data from the Internet and formats it
so that Bro can use it as intel data.
# Good idea to restart bro every now and then: broctl restart
# /usr/local/bro/share/bro/site/local.bro looks for the files in this directory.
#
# Uses the mal-dnssearch package from Jon Schipp
# git clone https://github.com/jonschipp/mal-dnssearch
# cd mal-dnssearch
# sudo make install
#

cd /usr/local/bro_intel
# download and format the Mandiant APT info
mal-dnssearch -M mandiant -p | mal-dns2bro -T dns -s mandiant -n true >
/usr/local/bro intel/mandiant.intel
```

```
# download and format TOR info
mal-dnssearch -M tor -p | mal-dns2bro -T ip -s tor -n true -u
http://rules.emergingthreats.net/open/suricata/rules/tor.rules >
/usr/local/bro_intel/tor.intel
# download and format Alienvault reputation info
mal-dnssearch -M alienvault -p | mal-dns2bro -T ip -s alienvault -n true >
/usr/local/bro intel/alienvault.intel
/usr/local/bro/etc/node.cfg
# Example BroControl node configuration.
# This example has a standalone node ready to go except for possibly changing
# the sniffing interface.
# This is a complete standalone configuration. Most likely you will
# only need to change the interface. [bro]
type=standalone host=localhost interface=eth1
## Below is an example clustered configuration. If you use this,
## remove the [bro] node above.
#[manager]
#type=manager
#host=host1
#[proxy-1]
#type=proxy
#host=host1
#[worker-1]
```

#type=worker

```
#host=host2
#interface=eth0
#
#[worker-2]
#type=worker
#host=host3
#interface=eth0
#
#[worker-3]
#type=worker
#host=host4
#interface=eth0
```

# /usr/local/bro/share/bro/site/local.bro

```
##! Local site policy. Customize as appropriate.
##!
##! This file will not be overwritten when upgrading or reinstalling!

# Capture plaintext passwords
redef HTTP::default_capture_password=T; redef FTP::default_capture_password=T;
#Hash all HTTP - for APT script
#redef HTTP::generate_md5=/.*/;

# This script logs which scripts were loaded during each run.
@load misc/loaded-scripts

# Apply the default tuning scripts for common tuning settings.
@load tuning/defaults

# Load the scan detection script.
```

# @load misc/scan # Log some information about web applications being used by users # on your network. @load misc/app-stats # Detect traceroute being run on the network. @load misc/detect-traceroute # Generate notices when vulnerable versions of software are discovered. # The default is to only monitor software found in the address space defined # as "local". Refer to the software framework's documentation for more # information. @load frameworks/software/vulnerable # Detect software changing (e.g. attacker installing hacked SSHD). @load frameworks/software/version-changes # This adds signatures to detect cleartext forward and reverse windows shells. @load-sigs frameworks/signatures/detect-windows-shells # Uncomment the following line to begin receiving (by default hourly) emails # containing all of your notices. # redef Notice::policy += { [\$action = Notice::ACTION\_ALARM, \$priority = 0] }; # Load all of the scripts that detect software in various protocols. @load protocols/ftp/software @load protocols/smtp/software

@load protocols/ssh/software

```
@load protocols/http/software
# The detect-webapps script could possibly cause performance trouble when
# running on live traffic. Enable it cautiously.
#@load protocols/http/detect-webapps
# This script detects DNS results pointing toward your Site::local nets
# where the name is not part of your local DNS zone and is being hosted
# externally. Requires that the Site::local_zones variable is defined.
@load protocols/dns/detect-external-names
# Load dhcp script to log known devices
@load protocols/dhcp/known-devices-and-hostnames
# Script to detect various activity in FTP sessions.
@load protocols/ftp/detect
# Scripts that do asset tracking.
@load protocols/conn/known-hosts
@load protocols/conn/known-services
@load protocols/ssl/known-certs
# This script enables SSL/TLS certificate validation.
@load protocols/ssl/validate-certs
# Check for SSL Heartbleed attack
@load protocols/ssl/heartbleed
# Check for weak keys
@load protocols/ssl/weak-keys
```

# Check for expiring certs

```
@load protocols/ssl/expiring-certs
# Uncomment the following line to check each SSL certificate hash against the ICSI
# certificate notary service; see http://notary.icsi.berkeley.edu .
@load protocols/ssl/notary
# If you have libGeoIP support built in, do some geographic detections and
# logging for SSH traffic.
@load protocols/ssh/geo-data
# Detect hosts doing SSH bruteforce attacks.
@load protocols/ssh/detect-bruteforcing
# Detect logins using "interesting" hostnames.
@load protocols/ssh/interesting-hostnames
# Detect SQL injection attacks.
@load protocols/http/detect-sqli
const feed directory = "/usr/local/bro intel";
# Intelligence framework
#@load policy/frameworks/intel/seen
#@load policy/frameworks/intel/do notice
@load frameworks/intel/seen
@load frameworks/intel/do_notice
#@load policy/integration/collective-intel
#redef Intel::read files += {
# feed_directory + "/mandiant.intel",
# feed directory + "/tor.intel",
```

# feed\_directory + "/alienvault.intel",

```
##"/usr/local/bro/share/bro/site/bad domains.txt",
##"/somewhere/yourdata1.txt",
# };
redef Intel::read_files += { "/usr/local/bro_intel/mandiant.intel",
"/usr/local/bro_intel/tor.intel", "/usr/local/bro_intel/alienvault.intel",
};
#### Network File Handling ####
# Enable MD5 and SHA1 hashing for all files.
@load frameworks/files/hash-all-files
# Detect SHA1 sums in Team Cymru's Malware Hash Registry.
@load frameworks/files/detect-MHR
# Extract collected files
#@load extract files
# this is the original malware detect using perl and clamavd
#@load malware_detect
# can define this stuff here or in the site specific .bro scripts
#redef Communication::listen_port = 47777/tcp;
#redef Communication::nodes += {
# ["broping"] = [$host = 127.0.0.1, $class="broping", $events = /ping/,
connect = F, ssl = F],
# ["malware_detect"] = [$host = 127.0.0.1, $class="malware_detect",
$events = /malware message/, $connect= F, $ssl = F]
# } ;
#@load malware1
```

```
#@load broccoli
#@load whitelisting
#@load broping

event bro_init() { Analyzer::disable_analyzer(Analyzer::ANALYZER_SYSLOG);
}

#event bro_init()
# {
# local f = Log::get_filter(Notice::ALARM_LOG, "alarm-mail");
# f$interv = lday;
# Log::add_filter(Notice::ALARM_LOG, f);
# }
```

## /opt/splunkforwarder/etc/system/local/server.conf

```
[sslConfig]
sslKeysfilePassword = $1$20JslXSIp3Un

[lmpool:auto_generated_pool_forwarder] description = auto_generated_pool_forwarder
quota = MAX
slaves = *
stack_id = forwarder [lmpool:auto_generated_pool_free] description =
auto_generated_pool_free quota = MAX
slaves = * stack_id = free
[general]
pass4SymmKey = $1$j644iTHO7Ccn serverName = bro
```

# /opt/splunkforwarder/etc/system/local/inputs.conf

```
[default] host = bro
sourcetype=BroLogs index=bro
```

```
[monitor:///usr/local/bro/logs/current/notice.log] sourcetype=bro_notice
[monitor://usr/local/bro/logs/current/weird.log] sourcetype=bro_weird
[monitor://usr/local/bro/logs/current/ssl.log] sourcetype=bro_ssl
[monitor://usr/local/bro/logs/current/ssh.log] sourcetype=bro_ssh
[monitor://usr/local/bro/logs/current/software.log] sourcetype=bro_software
[monitor://usr/local/bro/logs/current/intel.log] sourcetype=bro_intel
[monitor://usr/local/bro/logs/current/http.log] sourcetype=bro_http
[monitor://usr/local/bro/logs/current/conn.log] sourcetype=bro_conn
[monitor://usr/local/bro/logs/current/x509.log] sourcetype=bro_x509
[monitor://usr/local/bro/logs/current/dns.log] sourcetype=bro_dns

#[monitor://usr/local/bro/logs/current/*.log]

#host=bro-worker1

#sourcetype=BroLogs

#index=bro

#[monitor:///opt/splunkforwarder/var/log/splunk/splunkd.log]
```

## /opt/splunkforwarder/etc/system/local/outputs.conf

```
[tcpout]
defaultGroup = splunkssl

[tcpout:splunkssl] server = loghost:9997 compressed = true
sslVerifyServerCert = false
sslRootCAPath = $SPLUNK_HOME/etc/certs/CAServerCert.pem sslCertPath =
$SPLUNK_HOME/etc/certs/bro-workerl.pem sslPassword = $1$23DtXas9IZD8
```

# 3.4 CA Technologies IT Asset Manager

CA Technologies IT Asset Manager (CA ITAM) allows you to holistically manage IT hardware assets, from planning and requisition to retirement and disposal. This solution helps to rein in IT costs and boost return on investment by identifying underutilized hardware assets, improving hardware usage profiles, managing contracts and usage patterns, and giving you a thorough understanding of the true costs of your IT asset base.

#### 3.4.1 How It's Used

In the FS ITAM build, CA ITAM is used to track hardware assets from requisition to disposal. Data collected during this task will be analyzed and used to notify an administrator of a change in the network

architecture. When a new hardware asset is received, an administrator will enter into the database information that includes, but is not limited to, the asset name, host name, operating system, serial number, owner, location, mac address and IP address. The data is then stored for retrieval by Splunk Enterprise. For this build, the CA ITAM database is pre-loaded with data from machines being used throughout the ITAM architecture. The Tier 1 ITAM server is connected to the CA ITAM database to query data stored in the CA ITAM resource tables.

# 3.4.2 Virtual Machine Configuration

The CA ITAM virtual machine is configured with one network interface cards, 16 GB of RAM, two CPU cores, a 40 GB hard drive, and another 100 GB hard drive. The 100 GB of hard drive space is very important for this machine.

# 3.4.3 Network Configuration

The management network interface card is configured as follows:

IPv4 Manual

IPv6 Disabled

IP Address: 172.16.3.92
Netmask: 255.255.255.0
Gateway: 172.16.3.11

DNS Servers: 172.16.1.20, 172.16.1.21

Search Domains: lab5.nccoe.gov

# 3.4.4 Installing CA ITAM


CA ITAM is installed on a clean 64-bit Windows Server 2012 R2 image with default Windows firewall configurations. Installation configurations are default for this build and are documented online by CA Technologies. CA Technologies installation guidelines can be found online at the following URL: <a href="https://support.ca.com/cadocs/0/CA%20IT%20Asset%20Manager%2012%208-ENU/Bookshelf Files/PDF/APM Impl ENU.pdf">https://support.ca.com/cadocs/0/CA%20IT%20Asset%20Manager%2012%208-ENU/Bookshelf Files/PDF/APM Impl ENU.pdf</a>.

Prerequisites for this build are as follows:

- Java 7 JRE (32-bit)
  - Set the JAVA\_HOME variable
- SQL Server 2012 with
  - Database Engine

- Backwards Compatibility
- Client Connectivity
- Management tools
- Used mixed authentication as the authentication method
- NET Framework 3.5
- NET Framework 4.5
  - Select ASP.NET
- IIS

Note: Make sure the application server supports the IIS under add roles and features



- CA Business Intelligence Server
- CA Embedded Entitlements Manager

# 3.4.5 Configurations

Once installed, the data importer engine is used to import data from a .CSV file into the MDB. The file is obtained from the Belarc Server, which exports data into a .CSV file. Then the file is copied onto the CA ITAM Server.


1. Save the .CSV file in \CA\ITAM\Storage\Common Store\Import.

The file contains data with the following field names: ProfileName, NetworkMACAddress, ComputerDomain, OperatingSystem, OSProductOptions, OSServicePack, SystemSerialNumber.

A snippet of the .CSV file is displayed in the following figure:



2. Open the CA Data Importer by logging into CA ITAM with administrator privileges and navigate to **Administration** > **Data Importer** > **New Import**.



- 3. In the **Administration** tab, specify these settings:
  - a. Name: <Name>
  - b. Data File: <filename>
  - c. Main Destination Object: Asset(Computer)
  - d. Select First Row Has Column Names
  - e. Data File Locale: English (United States)
  - f. Data Delimiter: {Comma}
- 4. In **Advanced Settings**, select all three check boxes.

- 5. Save the import.
- 6. Under Mapping, select Load Source Fields.
- 7. Map the **Source Fields** to the **Destination Fields** using the following rules:
  - a. Computer domain = Asset.Host Name
  - b. NetworkIPAddress = Asset.IP Address
  - c. NetworkMACAddress = Asset.MAC Address
  - d. OperatingSystem = Asset.Model.Model Name
  - e. OSProductOptions = Asset.Asset Type Hierarchy.Class.Value
  - f. OSServicePack = Asset.Asset Type Hierarchy.Subclass.Value
  - g. ProfileName = Asset.Asset Name
  - h. SystemSerialNumber = Asset.Serial Number
- 8. Under the **Schedule**, upload the .CSV data file again and **Submit**. Make sure that the data import service is running.
- 9. Check the status of the job under **Import Jobs**.
- 10. Use the data stored in the MDB to run a query through the Splunk DB Connection (See Section 2.1.1, Splunk Enterprise, to configure.).
- 11. Query is as follows:

```
SELECT DISTINCT

aud_ca_owned_resource.resource_name,audit_mode_uuid,audit_resource_class,au
dit_resource_subclass,ca_owned_resource.own_resource_id,ca_owned_resource.m
ac_address,ca_owned_resource.ip_address,ca_owned_resource.host_name,ca_owned
d_resource.serial_number,ca_owned_resource.asset_source_uuid,ca_owned_resou
rce.creation_user,ca_owned_resource.creation_date

FROM aud_ca_owned_resource INNER JOIN ca_owned_resource
ON aud ca owned resource.resource name = ca owned_resource.resource name
```

#### 3.5 Fathom Sensor from RedJack

Fathom Sensor passively scans network traffic analyzing and reporting on netflow and cleartext banner information crossing the network. DNS and http traffic are also analyzed. Fathom Sensor detects anomalies on the network by analyzing these data streams.

## 3.5.1 How It's Used

Fathom Sensor passively monitors, captures, and optionally forwards summarized network traffic to its service running on the Amazon AWS cloud. The data on the Amazon server is then analyzed by RedJack to detect anomalies. The data is also aggregated with data from other organizations to detect attack trends.

# 3.5.2 Virtual Machine Configuration

The FathomSensor1 virtual machine is configured with 2 network interface cards (1 card for access and 1 for sniffing traffic), 16 GB of RAM, 1 CPU cores and 16 GB of hard drive space.

# 3.5.3 Network Configuration

The management network interface card is configured as such:

IPv4 Manual

IPv6 Disabled

IP Address: 172.16.0.50

No IP address for the second network interface card Netmask: 255.255.255.0

Gateway: 172.16.0.11

DNS Servers: 172.16.1.20, 172.16.1.21

Search Domains: lab5.nccoe.gov

# 3.5.4 Installing Fathom Sensor

#### 3.5.4.1 VM Deployments

This document will track the best-practices for provisioning, installing, and deploying the fathom-sensor in a virtual machine (VM).

## 3.5.4.2 Requirements

Fathom Sensor VM requirements vary based on the size, traffic volume, and complexity of the network. The most important factor for performance is RAM. A small business network of <50 devices might be safe on a VM with **16GB RAM**, where as a large enterprise gateway may require **32-64GB RAM** and dedicated hardware.

Fathom Sensor will continue to operate in a degraded state if it becomes resource starved, but it is best to start high.

# 3.5.4.3 Configure the VM

When creating the virtual machine, create two network interfaces, one for management, and one for monitoring. The monitoring interface must be set to promiscuous mode.

Instructions vary by VM platform and host, but this is covered here:

- ESX [KB: 1004099](http://kb.vmware.com/selfservice/microsites/search.do?language=en\_US&cmd=dis playKC&externalId=1004099)
- Linux [KB: 287](http://kb.vmware.com/selfservice/microsites/search.do?language=en\_US&cmd=displayK C&externalId=287)
- Fusion Password prompt can be disabled under Preferences > Network.

#### 3.5.4.4 Install CentOS 7 Minimal

Our reference platform is CentOS 7 x64. Install (using USB or ISO or whatever) a minimal install.

## 3.5.4.5 Configure OS

Note: The following is based on the aforementioned VM with 2 NICs, one management NIC (eno1...) and one monitoring NIC (eno2...).

Before beginning the configuration, you should collect the following information: IP/Netmask/Gateway for management interface. This will need Internet access on port **80** and **443**. Optionally, you can use DHCP.

#### 172.16.0.50

DNS server. This can be a local (to the customer) DNS server, or public (8.8.8.8, 4.2.2.4), however the latter will require firewall rules. Optionally, DHCP can configure this, however it needs to be set as above.

#### 172.16.1.20, 172.16.1.21

NTP Server. This can be a local (to the customer), or a public (0.centos.pool.ntp.org) server, however the latter will require firewall rules.

#### 172.16.0.11

NICs can be obscurely named, especially in VM environments. List all interfaces with: # ip addr.

## 3.5.4.6 Configure the Management Network with a Static IP

# /etc/sysconfig/network-scripts/ifcfg-eno1

#### BOOTPROTO=static IPADDR=172.16.0.50 NETMASK=255.255.255.0 ONBOOT=yes

# 3.5.4.7 Configure the Monitoring Interface Without an IP

- 1. Configure the monitoring interface without an IP:
  - # /etc/sysconfig/network-scripts/ifcfg-eno2

BOOTPROTO=static ONBOOT=yes

2. Disable IPv6 autoconfiguration on the monitoring interface:

```
# sysctl -w net.ipv6.conf.eno2.disable ipv6=1
```

## 3.5.4.8 Configure DNS

```
# vi /etc/resolv.conf
```

search lab5.nccoe.gov

nameserver 172.16.1.20

nameserver 172.16.1.21

## 3.5.4.9 Set the Hostname

- # hostnamectl set-hostname fathomsensor1
- # vi /etc/hosts

#### 127.0.0.1 localhost

172.16.0.50 fathomsensor1

## 3.5.4.10 Adjust the Packages

- 1. Not required, but if you are planning to install VMWare Tools, you need
  - \$ yum install perl net-tools gcc kernel-devel
- 2. Install basic tools
  - \$ yum install ntp bash-completion net-tools wget curl lsof tcpdump psmisc

### 3.5.4.11 Remove Unnecessary Packages

- \$ systemctl stop postfix chronyd avahi-daemon.socket avahi-daemon.service
- \$ systemctl disable avahi-daemon.socket avahi-daemon.service
- \$ yum remove postfix chronyd avahi-autoipd avahi-libs avahi

#### 3.5.4.12 Disable SELinux

# vi /etc/selinux/config

#### SELINUX=permissive

#### 3.5.4.13 Limit SSH

# vi /etc/ssh/sshd config

ListenAddress 172.16.0.50

### 3.5.4.14 NTP

Some VM platforms or configurations will provide a synchronized system clock. If you know this is the case, you can skip this section.

```
#vi /etc/ntp.conf
```

```
driftfile /var/lib/ntp/drift
```

restrict default nomodify notrap nopeer noquery

```
server 0.centos.pool.ntp.org iburst
```

server 1.centos.pool.ntp.org iburst

server 2.centos.pool.ntp.org iburst

server 3.centos.pool.ntp.org iburst

includefile /etc/ntp/crypto/pw

keys /etc/ntp/keys

#### disable monitor

1. Limit NTP to only listening on the management interface:

```
#vi /etc/sysconfig/ntpd
OPTIONS="-g -I eno1 -I 172.16.0.50"
```

2. Before deployment, make sure the hardware clock is set to something reasonably correct:

```
$ ntpdate 172.16.0.11
```

#### 3. Set NTP to start:

\$ hwclock -w

```
$ systemctl enable ntpd
```

\$ systemctl start ntpd

#### 3.5.4.15 CollectD

We use collectd to keep track of system (and fathom metrics) and report those metrics back to customer-metrics.redjack.com every 60 seconds.

1. First, we need to install it from EPEL (version number will change):

```
#yum install
http://dl.fedoraproject.org/pub/epel/7/x86_64/e/epel-release-7-5.noarc h.rpm
#yum install collectd collectd-netlink
```

- 2. Then install the collectd config file, which will have a URL specific for this sensor, which we've been using as the sensor UUID.
- 3. Then enable collectd:

```
$ systemctl enable collectd
```

\$ systemctl start collectd

#### 3.5.4.16 Install Fathom-Sensor

1. First install all the sensor RPMs:

```
$ sudo yum install *.rpm
```

2. Assuming that you have built a sensor config with 'fathom-admin':

```
$ cp fathom-sensor1.conf /etc/fathom/fathom-sensor.conf
$ chown fathom:fathom /etc/fathom/fathom-sensor.conf
$ chmod 600 /etc/fathom/fathom-sensor.conf
```

3. Edit the sensor config to make sure that it is listening to the correct device:

```
# vi /etc/fathom/fathom-sensor.conf
```

```
FATHOM SENSOR NETWORK DEVICE=eno2
```

# 3.5.4.17 Update Dynamic Run-Time Bindings

1. Update dynamic run-time bindings because sometimes it needs it:

```
$ ldconfig
```

2. Then enable the "dedicated" version of the sensor. This has some hardcore properties in it that will reboot if there are continual problems:

```
$ systemctl enable fathom-sensor-dedicated
$ systemctl start fathom-sensor-dedicated
```

# 3.5.4.18 Install and Configure Amazon S3 Command Line Tools Using PIP

- 1. Go to http://docs.aws.amazon.com/cli/latest/userguide/installing.html.
- 2. Verify that you have at least Python 2.7:

```
$ python -version
```

3. Download the pip installation script:

```
$ curl -O https://bootstrap.pypa.io/get-pip.py
```

4. Run the pip installation script:

```
$ sudo python get-pip.py
```

5. Install the AWS CLI:

```
$ sudo pip install awscli
```

## 3.5.4.19 Configure AWS CLI

1. Configure AWS CLI:

#aws configure

2. You will get the data to configure AWS CLI from the fathom-sensor.conf file. We want the data in JSON format.

```
AWS Access Key ID = FATHOM_SENSOR_AWS_ACCESS_KEY

AWS Secret Access Key = FATHOM_SENSOR_AWS_SECRET_KEY Default region Name = None

Default output format = json
```

3. Create a directory to save the files gathered from Amazon AWS:

```
#mkdir /opt/fathom-sync
```

4. Create a script to sync data with the Amazon AWS:

```
#vi /usr/local/bin/fathom-sync.sh
```

5. Copy the following lines into fathom-sync.sh. Replace <SENSOR ID> with your individual sensor ID.

```
#!/bin/sh
```

/bin/aws s3 sync s3://fathom-pipeline/json/nccoe/<SENSOR ID>/ /opt/fathom-sync

6. Make the script executable:

```
#chmod +x /usr/local/bin/fathom-sync
```

7. Make the script run every hour by placing a link in /etc/cron.hourly:

```
#cd /etc/cron.hourly
#ln -s /usr/local/bin/fathom-sync.sh /etc/cron.hourly/fathom-sync
```

# 3.5.5 Installing Splunk Universal Forwarder

Note: You will need a Splunk account to download the Splunk Universal Forwarder. It is free and can be setup at: <a href="https://www.splunk.com/page/sign\_up">https://www.splunk.com/page/sign\_up</a>.

- 1. Download the Splunk Universal Forwarder from: <a href="http://www.splunk.com/en\_us/download/uni-versal-forwarder.html">http://www.splunk.com/en\_us/download/uni-versal-forwarder.html</a>.
- 2. Use the latest version for OS version 2.6+ kernel Linux distributions (64-bit). Since this is installing on Ubuntu select the file that ends in .deb. An example is:

```
splunkforwader-6.2.5-272645-linux-2.6-amd64.deb
```

Detailed installation instructions can be found at:

http://docs.splunk.com/Documentation/Splunk/6.2.3/Installation/InstallonLinux.

3. An abridged version follows:

```
rpm -i <splunk_package_name.deb>
Example:rpm -i splunkforwader-6.2.4-271043-linux-2.6-x86_64.rpm
```

4. This will install in /opt/splunkforwarder:

```
cd /opt/splunkforwarder/bin
./splunk start --accept-license
./splunk enable boot-start
```

5. Add forwarder:

More info about adding a forwarder can be found at:

http://docs.splunk.com/Documentation/Splunk/6.2.3/Forwarding/Deployanixdfmanually.

```
cd /opt/splunkforwarder/bin
```

./splunk add forward-server loghost:9997 -auth admin:changme

### 3.5.6 Configuring Splunk Universal Forwarder

Configuring Splunk Universal Forwarder as shown in the FS-ITAM use case requires X.509 Certificates for the Splunk Enterprise server/indexer and each Splunk Universal Forwarder. You will also need a copy of your certificate authority's public certificate.

1. Create a directory to hold your certificates:

```
mkdir /opt/splunkforwarder/etc/certs
```

2. Copy your certificates in PEM format to /opt/splunkforwarder/etc/certs:

```
cp CAServerCert.pem /opt/splunkforwarder/etc/certs
cp fathomsensor1.lab5.nccoe.pem /opt/splunkforwarder/etc/certs
```

3. Copy Splunk Universal Forwarder configuration files:

```
cp <server.conf> /opt/splunkforwarder/etc/system/local
cp <inputs.conf> /opt/splunkforwarder/etc/system/local
cp <outputs.conf> /opt/splunkforwarder/etc/system/local
```

4. Modify **server.conf** so that:

ServerName=Bro is your hostname.

```
sslKeysfilePassword = <password for your private key>
```

5. Modify **outputs.conf** so that:

Server = loghost:9997 is your correct Splunk Enterprise server/indexer and port.

```
sslPassword = <password of your certificate private key>
```

Note: this will be hashed and not clear text after a restart.

# 3.5.7 Helpful Commands and Information

The following commands could prove useful when working with Amazon Web Servers S3. Replace <SENSOR ID> with your individual sensor ID.

1. List your sensor(s):

```
aws s3 ls s3://fathom-pipeline/json/nccoe/
```

2. List data types for a sensor:

```
aws s3 ls s3://fathom-pipeline/json/nccoe/<SENSOR ID>/
```

3. List dates for the client-banner data type:

```
aws s3 ls s3://fathom-pipeline/json/nccoe/<SENSOR ID>/client-banner/
```

4. List individual JSON files on that date:

```
aws s3 ls
s3://fathom-pipeline/json/nccoe/<SENSOR ID>/client-banner/20150604/
```

5. The following command will convert from a certificate in PKCS12 format to PEM format:

```
openssl pkcs12 -in certificate.pfx -out certificate.cer -nodes
```

# 3.5.8 Configurations and Scripts

#### /opt/splunkforwarder/etc/system/local/server.conf

```
[sslConfig]
sslKeysfilePassword = $1$20JslXSIp3Un

[lmpool:auto_generated_pool_forwarder] description = auto_generated_pool_forwarder
quota = MAX
slaves = *
stack_id = forwarder

[lmpool:auto_generated_pool_free] description = auto_generated_pool_free quota = MAX
slaves = * stack_id = free
[general]
pass4SymmKey = $1$j644iTHO7Ccn serverName = fathomsensor1.lab5.nccoe.gov
```

#### /opt/splunkforwarder/etc/system/local/inputs.conf

```
[default]
host = fathomsensor1.lab5.nccoe.gov sourcetype=fathomsensor index=fathom
[monitor:///opt/fathom-sync/*/client-banner*]
/opt/splunkforwarder/etc/system/local/outputs.conf [tcpout]
defaultGroup = splunkssl
```

```
[tcpout:splunkssl] server = loghost:9997 compressed = true
sslVerifyServerCert = false
sslRootCAPath = $SPLUNK_HOME/etc/certs/CAServerCert.pem
sslCertPath = $SPLUNK_HOME/etc/certs/fathomsensor1.lab5.nccoe.gov.pem sslPassword =
$1$23DtXas9IZD8
```

# 3.6 OpenVAS

OpenVAS is an open-source network vulnerability scanner and manager. OpenVAS runs customizable scans and generates reports in multiple formats. OpenVAS is also a framework, and additional tools can be added to it.

#### 3.6.1 How It's Used

In the FS ITAM build, OpenVAS automatically runs vulnerability scans on all systems connected to the network. Every machine is scanned at least once a week. OpenVAS collects the information, stores it in a database, and creates reports. OpenVAS can also download the latest vulnerabilities along with their CVE and NVT information.

On the high-level architecture diagram, OpenVAS is in Tier 2. OpenVAS utilizes the Splunk Universal Forwarder to send reports to Splunk Enterprise. Information is extracted from the OpenVAS database every hour, and any new records are forwarded to Splunk Enterprise. Splunk Enterprise uses the information from OpenVAS to provide context to analysts regarding the security of individual systems as well as aggregating statistics to show the overall organizational security posture.

### 3.6.2 Virtual Machine Configuration

The OpenVAS virtual machine is configured with one network interface card, 16 GB of RAM and four CPU cores.

## 3.6.3 Network Configuration

The management network interface card is configured as follows:

IPv4 Manual

IPv6 Ignore/Disabled

IP Address: 172.16.2.33

Netmask: 255.255.255.0

Gateway: 172.16.2.11

- DNS Servers: 172.16.1.20, 172.16.1.21
- Search Domains: lab5.nccoe.gov

https://www.digitalocean.com/community/tutorials/how-to-use-openvas-to-audit-the-securit y-of-remote-systems-on-ubuntu-12-04

### 3.6.4 Installation Prerequisites

```
sudo apt-get update
sudo apt-get install python-software-properties
sudo apt-get install sqlite3 xsltproc texlive-latex-base
texlive-latex-extra texlive-latex-recommended htmldoc alien rpm nsis fakeroot
```

### 3.6.5 Installing OpenVAS

OpenVAS is installed on a hardened Ubuntu 14.04 Linux system. Please download the latest source package from OpenVAS and follow the instructions for installing from source.

Installation was performed following the instructions gathered from the following web sites:

- http://www.openvas.org/
- https://www.digitalocean.com/community/tutorials/how-to-use-openvas-to-audit-the-security-of-remote-systems-on-ubuntu-12-04
- https://launchpad.net/~openvas/+archive/ubuntu/openvas6
- 1. Add new file in /etc/apt/sources.list.d/openvas-openvas6-trusty.list:

```
deb http://ppa.launchpad.net/openvas/openvas6/ubuntu precise main
deb-src http://ppa.launchpad.net/openvas/openvas6/ubuntu precise main
sudo apt-get install openvas-manager openvas-scanner
openvas-administrator openvas-cli greenbone-security-assistant sudo openvas-mkcert
```

2. Answer the questions for the new certificate:

```
sudo openvas-mkcert-client -n om -i
```

3. Download and build the vulnerability database:

```
sudo openvas-nvt-sync
```

4. Stop the services:

```
sudo service openvas-manager stop
sudo service openvas-scanner stop
```

5. Start the scanner application (this will download and sync a lot of data):

```
sudo openvassd
```

6. Rebuild the database:

```
sudo openvasmd --rebuild
```

7. Download and sync SCAP data:

```
sudo openvas-scapdata-sync
```

8. Download and sync cert data:

```
sudo openvas-certdata-sync
```

Note: You will most likely get an error because the Ubuntu package is missing some files.

9. The following commands will get the files from the Fedora package and install them in the correct location:

```
cd
wget http://www6.atomicorp.com/channels/atomic/fedora/18/i386/RPMS/openvas-
manager-5.0.8-27.fc18.art.i686.rpm
sudo apt-get install rpm2cpio
rpm2cpio openvas* | cpio -div
sudo mkdir /usr/share/openvas/cert
sudo cp ./usr/share/openvas/cert/* /usr/share/openvas/cert
```

10. Now sync the certs, and everything should work:

```
sudo openvas-certdata-sync
```

11. Add user and permissions:

```
sudo openvasad -c add user -n admin -r Admin
```

12. Edit the following file and insert your OpenVAS IP address:

```
\verb+sudo+ nano /etc/default/greenbone-security-assistant+\\
```

13. Start up the services:

```
sudo killall openvassd
```

```
sudo service openvas-scanner start sudo service openvas-manager start sudo service openvas-administrator restart sudo service greenbone-security-assistant restart
```

#### 14. Enable start up at boot time:

```
sudo update-rc.d openvas-scanner enable 2 3 4 5
sudo update-rc.d openvas-manager enable 2 3 4 5
sudo update-rc.d openvas-administrator enable 2 3 4 5
sudo update-rc.d greenbone-security-assistant enable 2 3 4 5
```

#### 15. Try it out. Point your web browser to:

https://localhost:9392

https://172.16.2.33:9292

Note: It must be https.

# 3.6.6 Configuring OpenVAS

Full user documentation can be found at: http://docs.greenbone.net/index.html#user documentation.

OpenVAS supports immediate scans and scheduled scans. Scheduled scans enable full automation of scanning and reporting.

#### 1. Set up schedules:

- a. Configuration > Schedules.
- b. Click the **Star** icon to create a new schedule.
- c. Create a schedule for every day of the week. Example: Monday scans every day at 21:00.
- d. Do the same for the other 6 days of the week.

#### 2. Setup targets:

A target is an individual system to scan or a range of systems to scan. In the FS-ITAM lab a separate target was configured for each subnet.

#### a. **Configuration > Targets**.

b. Click the **Star** icon to create a new target.

Example:

Name: Network Security.

Hosts: 172.16.2.1-172.16.2.254.

Comment: Network Security systems.

c. Click Create Target button to save.

#### 3. Set up tasks:

A task is something that is done to a target. So we need to setup a scan on each target.

a. Scan Management > New Task.

Name: Scan DMZ

Comment: Scan the DMZ systems

Scan Config: Full and fast

Scan Targets: **DMZ** (this is why the target must exist before the task).

Schedule: **Tuesday scan** (this is why the schedule must exist before the task).

- b. Click the Create Task button to save.
- c. Continue adding all of the tasks that you need one for each target.

### 3.6.6.1 Openvas results.py

The *openvas\_results.py* is a Python script that accesses the OpenVAS Sqlite3 database, extracts interesting values and then writes those to files in CSV and JSON formats.

The openvas results.py is run by cron every hour to check for new results from OpenVAS scans.

The Splunk Universal Forwarder checks the CSV file written by openvas\_results.py for any changes and sends those to the Splunk Enterprise server/indexer.

1. Place openvas\_results.py in /root and make sure that it is executable:

```
cp <openvas_results.py> /root
chmod +x /root/openvas results.py
```

2. Create a symbolic link in /etc/cron.hourly so that openvas\_results.py runs every hour:

```
ln -s /root/openvas_results.py /etc/cron.daily/openvas_results
```

### 3.6.7 Installing Splunk Universal Forwarder

Note: You will need a Splunk account to download the Splunk Universal Forwarder. It is free and can be set up at: https://www.splunk.com/page/sign\_up.

- 1. Download the Splunk Universal Forwarder from: <a href="http://www.splunk.com/en\_us/download/uni-versal-forwarder.html">http://www.splunk.com/en\_us/download/uni-versal-forwarder.html</a>.
- 2. You want the latest version for OS version 2.6+ kernel Linux distributions (64-bit). Since this is installing on Ubuntu, select the file that ends in .deb. An example is:

```
splunkforwader-6.2.5-272645-linux-2.6-amd64.deb
```

Detailed installation instructions can be found at:

http://docs.splunk.com/Documentation/Splunk/6.2.3/Installation/InstallonLinux.

3. An abridged version follows:

```
dpkg -i <splunk_package_name.deb>
Example: dpkg -i splunkforwader-6.2.5-272645-linux-2.6-amd64.deb
```

4. This will install in /opt/splunkforwarder:

```
cd /opt/splunkforwarder/bin
./splunk start --accept-license
./splunk enable boot-start
```

5. Add forwarder:

More information about adding a forwarder can be found at: http://docs.splunk.com/Documentation/Splunk/6.2.3/Forwarding/Deployanixdfmanually.

```
cd /opt/splunkforwarder/bin
./splunk add forward-server loghost:9997 -auth admin:changme
```

# 3.6.8 Configuring Splunk Universal Forwarder

Configuring Splunk Universal Forwarder as shown in the FS-ITAM use case requires X.509 Certificates for the Splunk Enterprise server/indexer and each Splunk Universal Forwarder. You will also need a copy of your certificate authority's public certificate.

1. Create a directory to hold your certificates:

```
mkdir /opt/splunkforwarder/etc/certs
```

#### 2. Copy your certificates in PEM format to /opt/splunkforwarder/etc/certs:

```
cp CAServerCert.pem /opt/splunkforwarder/etc/certs
cp bro worker1.pem /opt/splunkforwarder/etc/certs
```

#### 3. Copy Splunk Universal Forwarder configuration files:

```
cp <server.conf> /opt/splunkforwarder/etc/system/local
cp <inputs.conf> /opt/splunkforwarder/etc/system/local
cp <outputs.conf> /opt/splunkforwarder/etc/system/local
```

#### 4. Modify **server.conf** so that:

**ServerName=openvascd** is your hostname.

```
sslKeysfilePassword = <password for your private key>
```

5. Modify **outputs.conf** so that:

**Server = loghost:9997** is your correct Splunk Enterprise server/indexer and port.

```
sslPassword = <password of your certificate private key>
```

Note: This will be hashed and not clear text after a restart.

**Inputs.conf** should work, but you are free to modify it to include the OpenVAS logs that you are interested in.

### 3.6.9 Configurations and Scripts

#### /root/openvas\_results.py

```
#! /usr/bin/env python
#
# Gathers info from OpenVAS database and writes it to a CSV and JSON for
SplunkForwarder
#
import os import os.path import sys
from time import sleep
from datetime import datetime import ntpath
import errno import sqlite3 import csv import json
# Global variables and configs
```

```
# SQLITE3 database file
file db = "/var/lib/openvas/mgr/tasks.db"
# JSON file to write results to
json_file = "/home/mike/openvas_results.json"
# CSV file to write results to - actually tab delimited csv file =
"/home/mike/openvas results.csv"
# last id is how we keep track of the last item added. This keeps us from re-
processing old items. This value is kept in the openvas state.txt file
last id = 0
#openvas state.txt - change this to 0 if you want to start over openvas state file =
"/home/mike/openvas state.txt"
# this is just a status of how many records have be processed. new record count = 0
print "Getting OpenVAS reports"
if os.path.isfile(openvas_state_file) and os.access(openvas_state_file, os.W_OK):
openvas_state = open(openvas_state_file, 'r+') last_id = openvas_state.read()
else:
print "File %s does not exist, creating" % openvas state file
#sys.exit()
openvas state = open(openvas state file, 'w') openvas state.write('0')
print "Last ID = ", last id
\# stripped removes non-printable characters def stripped(x):
return "".join([i for i in x if 31 < ord(i) < 127])
try:
db_conn = sqlite3.connect(file_db, check_same_thread=False) except:
print "Cannot connect to %s" % file db sys.exit()
db_cursor = db_conn.cursor()
```

```
#query = """SELECT id, task, subnet, host, port, nvt, type, description, report from
results"""
query = """SELECT results.id, results.task, results.subnet, results.host,
results.port, results.nvt, results.type, results.description, results.report,
nvts.name, nvts.description,
nvts.cve, nvts.cvss base, nvts.risk factor from results LEFT JOIN nvts ON results.nvt
= nvts.uuid ORDER BY results.id"""
#field names = ['id', 'task', 'subnet', 'host', 'port', 'nvt', 'type',
'results_description', 'report', 'nvts_name', 'nvts_description', 'cve', 'cvss_base',
'risk factor']
csvfile = open(csv_file, 'a')
csv writer = csv.writer(csvfile, delimiter='\t', quotechar='|',
quoting=csv.QUOTE MINIMAL)
jsonfile = open(json file, 'a')
for row in db_cursor.execute(query):
#print row
id = row[0] #this needs to be a number task = stripped(str(row[1]))
subnet = stripped(str(row[2])) host = stripped(str(row[3])) port =
stripped(str(row[4])) nvt = stripped(str(row[5])) type = stripped(str(row[6]))
results description = stripped(str(row[7])) report = stripped(str(row[8]))
nvts name = stripped(str(row[9])) nvts description = stripped(str(row[10])) cve =
stripped(str(row[11]))
cvss base = stripped(str(row[12])) risk factor = stripped(str(row[13]))
if int(id) > int(last_id):
#print "Greater!" last_id = id openvas_state.seek(0,0)
openvas state.write(str(last id)) new record count = new record count + 1
csv writer.writerow([id, task, subnet, host, port, nvt, type, results description,
report, nvts name, nvts description, cve, cvss base, risk factor])
```

### /opt/splunkforwarder/etc/system/local/server.conf

```
[sslConfig]
sslKeysfilePassword = $1$JnofjmZL66ZH

[lmpool:auto_generated_pool_forwarder] description = auto_generated_pool_forwarder
quota = MAX
slaves = *
stack_id = forwarder

[lmpool:auto_generated_pool_free] description = auto_generated_pool_free quota = MAX
slaves = * stack_id = free
[general]
pass4SymmKey = $1$cTZLOiMNoPRH serverName = openvas
```

#### /opt/splunkforwarder/etc/system/local/outputs.conf

```
[tcpout]
defaultGroup = splunkssl

[tcpout:splunkssl] compressed = true server = loghost:9997

sslCertPath = $SPLUNK_HOME/etc/certs/openvas.lab5.nccoe.gov.pem sslPassword = $1$JnofjmZL66ZH

sslRootCAPath = $SPLUNK_HOME/etc/certs/CAServerCert.pem sslVerifyServerCert = true
```

#### /opt/splunkforwarder/etc/system/local/inputs.conf

```
[default] host = openvas
index = openvas sourcetype = openvas
[monitor:///home/mike/openvas results.csv]
```

# 3.7 Puppet Enterprise

Puppet Enterprise enforces a configuration baseline on servers and workstations. Puppet agents installed on the hosts will run periodically, download a list of instructions referred to as a configuration catalog from the Master, and then execute it on the hosts. A successful Puppet Enterprise agent run can make configuration changes, install new software, remove unwanted software and send reports to the Master.

#### 3.7.1 How It's Used

In the Financial Services ITAM solution, Puppet Enterprise is used to enforce a base configuration for all endpoints and to enforce basic security configurations. On the endpoints, it ensures that anti-virus software is installed, firewalls are enabled, IP forwarding is disabled, and the software asset management agent is installed.

Reporting is also a feature that was extended in this solution. With the inclusion of customized scripts, Puppet Enterprise sends very valuable reports to the ITAM analysis engine. The reports include which endpoint has successfully uploaded reports to the Puppet Enterprise master.

Failure to upload a report within a certain interval would indicate an anomaly with the endpoint or an off-line endpoint. Puppet Enterprise's functionality was extended to remove blacklisted software listed in a file made available from an analyst. A script was written to parse the file on a daily basis and inject the appropriate Puppet Enterprise code to remove such listed software. After successful removal, Puppet Enterprise writes a report identifying the offending endpoint, the uninstalled software and the time of removal.

### 3.7.2 Prerequisites

Puppet Enterprise Server requires the following:

- at least a four core CPU, 6 GB of RAM and 100 GB of hard drive space
- network-wide name resolution via DNS
- network-wide time synchronization using NTP

### 3.7.3 Installing Puppet Enterprise Server

Instructions for installing Puppet Enterprise can be found at http://docs.puppetlabs.com/pe/latest/install\_pe\_mono.html.

- 1. Download the Puppet Enterprise tarball from the Puppet Labs web site. Use the instructions referenced in the preceding link to locate and download the file.
- 2. Run tar -xf <PuppetEnterpriseTarball> to unpack its contents.
- 3. List directory with ls to view current directory contents.
- 4. Change into the directory with name puppet-enterprise-<version>-<oSversion>.
- 5. Execute sudo ./puppet-enterprise-installer.
- Connect to Puppet Enterprise Server console by going to: https://YourPuppetServerFQDN:3000.
- 7. Accept the untrusted connection and make an exception to this site by storing it in your trusted list.
- 8. Confirm the security exception.
- 9. From Installation Web page, select **Let's get started**.
- 10. Select Monolithic Installation.
- 11. Choose Install on this Server.
- 12. Do not enable the Puppet 4 language parser if your existing Puppet code was developed in Puppet 3.xx.
- 13. Choose to install PostGreSQL on the same server.
- 14. Supply a console password when prompted.

### 3.7.4 Puppet Enterprise Linux Agent Installation

To install Puppet Enterprise agent on the same platform as the server:

- 1. Enter curl -k https://YourPuppetServerFQDN:8140/packages/current/install.bash | sudo bash at the agent terminal.
- 2. Request a certificate by typing puppet agent -t from the client node.
- 3. Go to the Puppet Enterprise server Web console and log in.

- 4. Accept node requests by clicking on the **Node** link.
- 5. Click **Accept** to sign the Certificate.

To install Puppet Enterprise agent on a different platform from the server:

- 1. Go to the Puppet Enterprise Web console.
- 2. Click on Classification.
- 3. Select the **PE Master Group**.
- 4. Click the **Classes** tab.
- 5. Select your platform from the new class textbox dropdown.
- 6. Click Add Class.
- 7. Click Commit 1 Change.
- 8. Run puppet agent -t to configure the newly assigned class.
- 9. To install the agent, enter curl -k https://<YourPuppetServerFQDN>:8140/packages/current/install.bash | sudo bash.

### 3.7.5 Puppet Enterprise Windows Agent Installation


To install Puppet Enterprise agent on a Windows computer:

- 1. Make sure to start the installation file or log in to the system with an administrator account.
- 2. Double-click the Puppet Enterprise executable file.
- 3. Accept the default options.

### 3.7.6 Puppet Enterprise Agent Configuration

- 1. Agents need to obtain certificates from the Puppet Enterprise Server/Master. Connect to the Puppet Enterprise Server console at https://PuppetEnterpriseServerFQDN.
- 2. Log in to the console with your configured username and password.
- 3. Click on **Nodes**.
- 4. Accept Node requests from each agent you have configured. The agent's fully qualified domain name (FQDN) will be displayed.
- 5. A certificate request can be generated if you do not see one by typing puppet agent -t from the agent terminal.

- 6. Certificate requests can be viewed from the Web console of Puppet Enterprise Server.
- 7. Windows agents offer the option of using the graphical user interface by clicking on **Start Programs** > **Puppet Enterprise** > **Run Puppet Agent**.



- 8. Puppet agents fetch and apply configurations retrieved from the Puppet Enterprise Master Server. This agent run occurs every 30 minutes. You can change this interval by adding an entry to the /etc/puppetlabs/puppet/puppet.conf file.
  - a. On Linux, add the entry runinterval = 12 to the main section of the /etc/pup-petlabs/puppet/puppet.conf file to have the agent run every 12 hours.
  - b. On Windows, add the entry runinterval = 12 to the main section of the C:\ProgramData\PuppetLabs\puppet\etc\puppet.conf file to have the agent run every 12 hours.

# 3.7.7 Puppet Enterprise Manifest Files and Modules

The main configuration file, also called a manifest file in Puppet Enterprise, is /etc/puppetlabs/puppet/environments/production/manifests/site.pp. You can place all the Puppet Enterprise code here for agents to run. In our solution, we created modules, declared classes, and called those modules from within the site.pp file.

A module consists of a parent directory that contains a file's subdirectory and a manifest's subdirectory. Within the manifests subdirectory will be another file called init.pp that contains the Puppet Enterprise

code for that module. The init.pp file must have a class declaration statement. The files subdirectory can be empty or can contain files that need to be copied over to endpoints that will execute code in that module. All modules reside in the directory /etc/puppetlabs/puppet/modules. We have the following modules:

- /etc/puppetlabs/puppet/modules/windowsnodes
- /etc/puppetlabs/puppet/modules/ubuntubase
- /etc/puppetlabs/puppet/modules/redhatbase
- /etc/puppetlabs/puppet/modules/clamav
- /etc/puppetlabs/puppet/modules/blacklist

Each has a files directory /etc/puppetlabs/puppet/modules/<modulename>/files and a manifests directory with the /etc/puppetlabs/puppet/modules/<modulename>/manifests/init.pp file.

#### 3.7.7.1 Module: windowsnodes

This module configures a baseline for Windows endpoints. Execution of this module copies a number of executable files and the baseline.bat script over to the endpoints from the Puppet Enterprise Server. Once baseline.bat is executed on the endpoint, it will look for and install the copied over executable programs, which consist of the belmonitor.exe asset management software agent and an anti-virus software. The text of the /etc/puppetlabs/puppet/modules/windowsnodes/init.pp manifest file is shown in the code and scripts section.

#### 3.7.7.2 Module: ubuntubase

This module configures a baseline for Ubuntu endpoints. It installs software, disables IP forwarding, installs clamav anti-virus, and copies over files including a script *dailyscript* that runs daily and is placed in the /etc/cron.daily directory. You can use the same technique to ensure that your scripts remain where you want them.

#### 3.7.7.3 Module: redhatbase

This module configures a baseline for RedHat or CentOS based endpoints. It disables IP forwarding on endpoints, copies over files including scripts that run periodically, ensures that the belmonitor asset management software is installed, and configures the logging to the appropriate logging server.

#### 3.7.7.4 Module: clamav

This module installs clamav anti-virus on Ubuntu endpoints and ensures that the clamav-daemon service is running.

```
class clamav{

package{'clamav-daemon': ensure=>installed,
}

service{'clamav-daemon': ensure=>running, require=>Package['clamav-daemon'],
}
}
```

#### 3.7.7.5 Module: blacklist

This module removes blacklisted software from endpoints and reports success if the software package is removed. Its *init.pp* file is constantly being updated with new software slated for removal. A python script called *blacklistenforcer.py* is used to populate the module's

/etc/puppetlabs/puppet/modules/blacklist/manifests/init.pp file. Another python script is used to read reports from the /var/opt/lib/pe-puppet/reports/<HostFQDN> subdirectories to identify successfully removed blacklisted software.

#### 3.7.7.6 Software Blacklist Removal

Puppet Enterprise Server is configured to remove blacklisted software from agent nodes. A python script placed in /etc/cron.daily directory runs daily, checking a blacklisted software. The python script will extract the software list from the file /etc/splunkreport/fakeblacklist.csv, write new Puppet code such that Puppet Enterprise catalog includes the blacklisted software, and identifies it to Puppet for removal.

### 3.7.8 Reporting

Puppet agents forward reports of their runs to the Puppet Enterprise server. To ensure reporting is enabled, go to /etc/puppetlabs/puppet/puppet.conf and verify that an entry such as reports = console, puppetdb, store exists under master section of the file.

Agents upload reports in the form of YAML files to /var/opt/lib/pe-puppet/reports/<agent\_hostname>.

In this solution, the Puppet Enterprise Server machine was set up to forward two basic reports to the ITAM server. Both were done with scripts. The first reporting function forwarded checked the fully qualified hostnames of endpoints that failed to upload reports to the server within two reporting cycles.

If a reporting interval or cycle is 30 minutes, then failure to upload a report for more than an hour would indicate that an endpoint is offline and would trigger the forwarding of a syslog message to the ITAM server declaring the endpoint absent. Other endpoints that successfully upload reports without missing two cycles are declared present and send an appropriate message to the ITAM server. The script written that accomplishes this is written in BASH and is in the code and scripts section.

The second reporting function reports on the successful removal of blacklisted software. It scans through the report files from all the nodes in Puppet Enterprise Server, identifies successfully removed software and updates the CSV file /etc/splunkreport/reporttosplunk.csv with information that identifies the endpoint, the successfully removed software and the time of removal. The Splunk Universal Forwarder agent monitors this file and forwards changes to the ITAM server, which uses Splunk Enterprise as its analysis engine.

## 3.7.9 Report Directory Cleanup

Thousands of files could be uploaded to the reports directory in a short time. Therefore, it is important to delete files that are no longer needed. We used a python script that ran hourly to delete files modification times more than 12 hours old. In this solution, that is equivalent to files that are more than 12 hours old. This script was placed in the /etc/cron.hourly.

### 3.7.10 Puppet Code and Scripts

### 3.7.10.1 Main Manifest Configuration File

#### /etc/puppetlabs/puppet/environments/production/manifests/site.pp

```
## site.pp ##

# This file (/etc/puppetlabs/puppet/manifests/site.pp) is the main
# entry point used when an agent connects to a master and asks for an # updated
configuration.
#

# Global objects like filebuckets and resource defaults should go in
# this file,as should the default node definition. (The default node
# can be omitted
# if you use the console and don't define any other nodes in site.pp. # See
http://docs.puppetlabs.com/guides/language_guide.html#nodes for # more on node
definitions.)
```

```
## Active Configurations ##
# PRIMARY FILEBUCKET
# This configures puppet agent and puppet inspect to back up file
# contents when they run. The Puppet Enterprise console needs this to # display file
contents and differences.
# Define filebucket 'main': filebucket { 'main':
server => 'puppet.lab5.nccoe.gov', path => false,
# Make filebucket 'main' the default backup location for all File resources:
File { backup => 'main' }
# DEFAULT NODE
# Node definitions in this file are merged with node data from the console. See
# http://docs.puppetlabs.com/guides/language guide.html#nodes for more
# on node definitions.
# The default node definition matches any node lacking a more specific
# node definition. If there are no other nodes in this file, classes
# declared here will be included in every node's catalog, *in
# addition* to any classes specified in the console for that node.
node default {
# This is where you can declare classes for all nodes.
# Example:
      class { 'my_class': }
```

}

```
#Changes to the site.pp file were made below this line.
#Nodes were specified with the modules that would execute
node 'centos1', 'fathomsensor1'{ include redhatbase
include blacklist
node 'ubuntu-client1', 'kibana', 'openvas', 'sensu', 'ubuntu-client2', 'wiki'{
include blacklist include ubuntubase package{'curl':
ensure => installed,
node 'ubuntu-template', 'jumpbox', 'bro', 'snort', 'apt-cache', 'warehouse'{
include blacklist include ubuntubase package{'curl':
ensure => installed,
node 'win7-client1', 'win7-client2', 'ad2', 'ad1', 'Belarc', 'eracent'{ include
blacklist
include windowsnodes
node 'asset-manager'{ include blacklist include windowsnodes
```

# 3.7.10.2 Windowsnodes Configuration File and Script

#### /etc/puppetlabs/puppet/modules/windowsnodes/manifests/init.pp

#This manifest file declares a class called windowsnodes, creates a
#C:\software directory, copies a number of files to the agent including the
baseline.bat

```
#script and executes the baseline.bat. When executed baseline.bat batch file installs
#some programs and turns on the firewall and ensures the guest account is disabled
class windowsnodes{ file{'C:\software':
ensure=>"directory",
file{'C:\software\baseline.bat':
source => "puppet:///modules/windowsnodes/baseline.bat", source permissions=>ignore,
require => File['C:\software'],
file{'C:\software\belmonitor.exe':
source => "puppet:///modules/windowsnodes/belmonitor.exe", source permissions=>ignore,
require => File['C:\software'],
}
file{'C:\software\mbamsetup.exe':
source => "puppet:///modules/windowsnodes/mbamsetup.exe", source permissions=>ignore,
require => File['C:\software'],
exec{'win baseline':
command=>'C:\windows\system32\cmd.exe /c C:\software\baseline.bat', require =>
File['C:\software\belmonitor.exe'],
}
file{'C:\Program Files (x86)\nxlog\conf\nxlog.conf': source =>
"puppet:///modules/windowsnodes/nxlog.conf", source permissions=>ignore,
```

#### /etc/puppetlabs/puppet/modules/windowsnodes/files/baseline.bat

```
REM Install new user called newuser net user newuser /add

REM Disable newuser

net user newuser /active:no

REM Disable the guest account net user guest /active:no

REM Turn on firewall

netsh advfirewall set allprofiles state on

REM Use puppet to check if Malwarebytes is installed puppet resource package |find "Malwarebytes"

REM Install Malwarebytes silently if not installed

if %errorlevel% neq 0 C:\software\mbamsetup.exe /verysilent /norestart sc query |find "BelMonitorService"

REM Install Belmonitor if the service is not running if %errorlevel% neq 0

C:\software\belmonitor.exe
```

### 3.7.10.3 Ubuntubase Configuration File and Script

#### /etc/puppetlabs/puppet/modules/ubuntubase/manifests/init.pp

```
#This module configures a baseline for Ubuntu endpoints class ubuntubase{
#Copy over the CA certificate
file{'/usr/local/share/ca-certificates/CAServerCert.crt': source =>
"puppet://modules/ubuntubase/CAServerCert.crt",
}

# Add CA certificate to Ubuntu endpoint's repository of certificates exec{'update-ca-certificates':
command=>'/usr/sbin/update-ca-certificates',
}
```

```
#Ensure the /etc/ufw directory is present or create it file{'/etc/ufw':
ensure=>"directory",
}
#Copy over the sysctl.conf file to each endpoint. IP forwarding will be
#disabled file{'/etc/ufw/sysctl.conf':
source => "puppet:///modules/ubuntubase/sysctl.conf", require => File['/etc/ufw'],
#Run the clamav module include clamav
file{'/etc/cron.daily': ensure=>"directory",
}
file{'/etc/rsyslog.d': ensure=>"directory",
}
#Copy over this script to endpoint with associated permissions
file{'/etc/cron.daily/dailyscript':
source => "puppet:///modules/ubuntubase/dailyscript", mode => 754,
require => File['/etc/cron.daily'],
#Copy over the 50-default.conf file with specified content file{'/etc/rsyslog.d/50-
default.conf':
content => "*.* @@loghost\n *.* /var/log/syslog", require => File['/etc/rsyslog.d'],
}
#Copy over Belmonitor Linux installation file file{'/opt/BelMonitorLinux':
source => "puppet:///modules/ubuntubase/BelMonitorLinux",
}
```

```
#Make the BelMonitorLinux file executable exec{'belmonitor executable':
command=>'/bin/chmod a+x /opt/BelMonitorLinux', require=>File['/opt/BelMonitorLinux'],
exec{'install_rpm':
command=>'/usr/bin/apt-get install -y rpm', require=>File['/opt/BelMonitorLinux']
##Install 32 bit library exec{'install_32bitlibrary':
command=>'/usr/bin/apt-get install -y gcc-multilib', require=>Exec['install rpm'],
}
##install 32 bit library exec{'install second 32bit library':
command=> '/usr/bin/apt-get install -y lib32stdc++6',
exec{'install belmonitor': command=>'/opt/BelMonitorLinux',
require=>Exec['install 32bitlibrary'],
service{'BelMonitor': ensure=>'running',
```

#### /etc/puppetlabs/puppet/modules/ubuntubase/files/dailyscript

```
#!/bin/bash df -kh mount
netstat -nult ifconfig -a iptables -L
/usr/bin/freshclam
cat /var/lib/apt/extended states apt-get update
```

### 3.7.10.4 Redhatbase Module Configuration File and Script

#### /etc/puppetlabs/puppet/modules/redhatbase/manifests/init.pp

```
class redhatbase{
#Copies over a customized sysctl.conf that disables IP forwarding
file{'/etc/sysctl.conf':
source => "puppet:///modules/redhatbase/sysctl.conf",
#Ensures that cron.daily directory is present or creates it file{'/etc/cron.daily':
ensure=>"directory",
file{'/etc/rsyslog.d': ensure=>"directory",
#Copies over the a script that runs daily called dailyscript
file{'/etc/cron.daily/dailyscript':
source => "puppet:///modules/redhatbase/dailyscript", mode => 754,
require => File['/etc/cron.daily'],
#Ensures that log messages are forwarded to loghost and
/var/log/messages file{'/etc/rsyslog.d/50-default.conf':
content => "*.* @@loghost:514\n *.* /var/log/messages", require =>
File['/etc/rsyslog.d'],
#Copies over the a script that installs clamav if not installed
file{'/etc/cron.daily/claminstall':
source => "puppet:///modules/redhatbase/claminstall", mode => 754,
```

```
require => File['/etc/cron.daily'],
##Ensure the opt dir is present, copy the BelMonitorLinux script file
## Copy the belmonitor install script to the /opt dir
## Check that the BelMonitor file is present before belmonitor install
## executes
file{'/opt': ensure=>"directory",
file{'/opt/BelMonitorLinux':
source => "puppet:///modules/redhatbase/BelMonitorLinux",
}
##Make BelMonitorLinux executable exec{'make_executable':
command=>'/bin/chmod a+x /opt/BelMonitorLinux', require =>
File['/opt/BelMonitorLinux'],
##Install dependencies exec{'upgrade_dep1':
command=>'/usr/bin/yum -y upgrade libstdc++',
}
exec{'install_dep2':
command=>'/usr/bin/yum -y install libstdc++.i686',
exec{'upgrade_dep3': command=>'/usr/bin/yum -y upgrade zlib',
}
```

```
exec{'install_dep4':
command=>'/usr/bin/yum -y install zlib.i686',
}

exec{'install_belmonitor': command=>'/opt/BelMonitorLinux',
}
file{'/opt/belmonitor_install':
source => "puppet:///modules/redhatbase/belmonitor_install",
}
```

### /etc/puppetlabs/puppet/modules/redhatbase/files/claminstall

```
#!/bin/bash
# /etc/puppetlabs/puppet/modules/redhatbase/files/claminstall#
# Script installs clamav if not already installed when run

if rpm -qa clamav; then
echo "Clamav is installed" else
yum install -y epel-release
yum --enablerepo=epel -y install clamav clamav-update sed -i -e "s/^Example/#Example/"
/etc/freshclam.conf
```

### 3.7.10.5 Clamav Puppet Module Configuration File

### /etc/puppetlabs/puppet/modules/clamav/manifests/init.pp class clamav{

```
package{'clamav-daemon': ensure=>installed,
}
service{'clamav-daemon': ensure=>running, require=>Package['clamav-daemon'],
}
```

### 3.7.10.6 Blacklisted Software Removal Script

# /etc/puppetlabs/puppet/modules/blacklist/manifests/init.pp #!/usr/bin/python3 #-----# #Script will search through the Puppet reports directory and subdirectories, and identify blacklisted #packages within the yaml files that have been confirmed as removed. It will retrieve the software #package, host and time of removal and write this to a file called reporttosplunk.csv import os #List directories in /var/opt/lib/pe-puppet/reports report list = os.listdir('/var/opt/lib/pe-puppet/reports') #Make the path to reports a string origdir path = '/var/opt/lib/pe-puppet/reports' action term = "file: /etc/puppetlabs/puppet/modules/blacklist/manifests/init.pp" outfile = open('/etc/splunkreport/reporttosplunk.csv', 'a') #For loop iterates through report\_list (or the reports directory) for sub\_dirs in report\_list: hostname = sub dirs print(hostname) #Concatenation creates the full path to subdirectories (it remains a string) subdir path = origdir path+'/'+sub dirs #Creates the list of files in the variable (the variable in this case would be a sub directory) #At the end of this block, infile contains a list of line elements in each file sub dirs list = os.listdir(subdir path) for files in sub dirs list: files path = subdir path+'/'+files reportfile = open(files path, "r") infile = reportfile.readlines() reportfile.close() #line counter used in keeping track of the index for the line elements in each file

```
line_counter = 0

for line in infile:
    if action_term in line:
    if "source" in infile[line_counter + 3]: bad_package = infile[line_counter + 3]
    bad_package = bad_package.replace('\n',',') if "removed" in infile[line_counter + 2]:
    message_var = infile[line_counter + 2] message_var = message_var.replace('\n',',') if
    "time" in infile[line_counter + 1]:
    time_var = infile[line_counter + 1] time_var = time_var.replace('\n',',')
    refined_bad_pkg = bad_package.split('/') bad_pkg = refined_bad_pkg[3]

bad_pkg = bad_pkg + ","
    print(hostname+","+bad_pkg+message_var+time_var+'\n')

outfile.write(hostname+','+bad_pkg+message_var+time_var+'\n') line_counter = line_counter + 1
```

## 3.7.10.7 Reports Directory Cleanup Script

#### /etc/cron.hourly/cleanreportdir.py

```
#!/usr/bin/python3
```

```
#------#
#Script removes files with mtimes older than 12 hours to keep the number of files to a manageable size
#Files removed are from the reports subdirectory within Puppet import os
import time
#List directories in /var/opt/lib/pe-puppet/reports report_list =
os.listdir('/var/opt/lib/pe-puppet/reports')
#Make the path to reports a string
origdir_path = '/var/opt/lib/pe-puppet/reports'
#For loop iterates through report_list for sub_dirs in report_list:
#Concatenation creates the full path to subdirectories (it remains a string)
subdir path = origdir path+'/'+sub dirs
```

```
print('Old files are being removed from ', subdir path)
#Creates the list of files in the variable sub dirs list sub dirs list =
os.listdir(subdir path)
for files in sub dirs list:
files path = subdir path+'/'+files mtime = os.path.getmtime(files path) current time =
time.time()
time diff = current time - mtime
#Removes files with mtimes older than 12 hours if time diff > 43200:
print(files path, " will be deleted") os.remove(files path)
3.7.10.8 Reporting Section Script
#!/bin/bash
#/etc/cron.hourly/nodereport
#Time in seconds before declaring an agent that has not checked in absent
#Change the time to suit your needs
let "desired interval=3600"
for node in $(ls /var/opt/lib/pe-puppet/yaml/node) do
#Strip out the yaml extension from the node name node=${node%.*}
#Get time of most recent agent run or check in
#This time will be reported without formatting node report time=$(date -r
/var/opt/lib/pe-puppet/yaml/facts/$node.yaml)
#Get epoch time of agent facter yaml file, assign time to variable node time=$(date
+%s -r
/var/opt/lib/pe-puppet/yaml/facts/$node.yaml)
#Assign current epoch time to variable current time=$(date +%s)
#Subtract node most recent report time from current time and
#assign to variable node interval=$((current time-node time))
#Nodes that have not reported in the given interval are
#declared absent, otherwise they are declared present if (("$node interval" >
"$desired interval"))
then
echo $node "is absent with a last run time of "
```

```
$node_report_time
logger $node "is absent. Last run is " $node_report_time
else
echo $node "is present with a last run time of "
$node_report_time
logger $node "is present. Last run is " $node_report_time
fi
done
```

#### 3.8 Snort

Snort is an open-source intrusion detection system. Snort efficiently analyzes all network traffic and matches it with signatures of know bad traffic. An alert is generated if a signature is matched.

#### 3.8.1 How It's Used

In the FS ITAM build, Snort monitors all traffic traversing the DMZ.

On the high-level architecture diagram, Snort is in Tier 2. Snort utilizes the Splunk Universal Forwarder to send alerts to Splunk Enterprise.

# 3.8.2 Virtual Machine Configuration

The Snort virtual machine is configured with one network interface card, 2 GB of RAM and one CPU core.

### 3.8.3 Network Configuration

The management network interface card is configured as follows:

- IPv4 Manual
- IPv6 Ignore/Disabled

IP Address: 172.16.0.40

Netmask: 255.255.255.0

Gateway: 172.16.0.11

DNS Servers: 172.16.1.20, 172.16.1.21

Search Domains: lab5.nccoe.gov

### 3.8.4 Installing Snort

Snort is installed on a hardened Ubuntu 14.04 Linux system. Complete installation instructions can be found at: https://www.snort.org/.

This installation utilized the Snort IDS and Barnyard2 to interpret binary Snort alerts into readable text.

### 3.8.5 Installing Snort

1. For Debian/Ubuntu Linux systems, it is always best to make sure your system is up-to-date by performing:

```
sudo apt-get update
sudo apt-get upgrade
sudo apt-get install snort
```

- 2. You will be asked to input your local networks. For the FS-ITAM lab this is 172.16.0.0/16.
- 3. Configure /etc/snort/snort.debian.conf.
- 4. Make sure that the correct HOME\_NET and INTERFACE are specified in /etc/snort/snort.debian.conf.

```
DEBIAN_SNORT_HOME_NET="172.16.0.0/16"

DEBIAN_SNORT_INTERFACE="eth0"
```

- 5. Configure /etc/snort/snort.conf.
- 6. Comment out all output configuration lines and add the following:

```
output unified2: filename /var/log/snort/snort.log, limit 128, mpls_event_types, vlan_event_types
```

The preceding line is important for Barnyard2 to work correctly.

# 3.8.6 Get Updated Community Rules

```
cd /opt
```

 $\label{lem:wget} wget\ https://snort.org/downloads/community/community-rules.tar.gz\ tar\ xzvf\ community.rules.tar.gz\ -C\ /etc/snort/rules$ 

These community rules contain the **sid-msg.map** file that Barnyard2 needs.

```
mkdir /etc/snort/etc
cp /etc/snort/rules/community-rules/sid-msg.map /etc/snort/etc
```

Note: In a production environment, it is advisable to install an automatic rule updater such as PulledPork. PulledPork requires obtaining an account at Snort.org which results in an Oinkcode.

### 3.8.7 Installing Barnyard2

1. Install the prerequisites:

```
sudo apt-get install build-essential libtool autoconf git nmap
sudo apt-get install libpcap-dev libmysqld-dev libpcre3-dev libdumbnet-dev
sudo apt-get install flex bison ldconfig
```

2. Barnyard2 requires the <dnet.h> header. Unfortunately, Ubuntu names this header <dumbnet.h> so we must create a symbolic link for Barnyard2 to compile.

```
cd /usr/include
ln -s /usr/include/dumbnet.h dnet.h
```

Note: You need to be root to install Barnyard2.

```
cd /opt
Need the Daq libraries from Snort
wget https://www.snort.org/downloads/snort/daq-2.0.6.tar.gz
tar xzvf daq-2.0.6.tar.gz
cd /opt/daq-2.0.6
./configure make
make install
git clone https://github.com/firnsy/barnyard2.git
cd /opt/barnyard2
./autogen.sh
./configure make
make install
```

3. Copy the provided **barnyard2.conf** file to /usr/local/etc:

```
cp /usr/local/etc/barnyard2.conf /usr/local/etc/barnyard2.conf.orig
cp <barnyard2.conf> /usr/local/etc
```

4. Create a link inside /etc/snort to this file:

```
ln -s /usr/local/etc/barnyard2 /etc/snort/barnyard.conf
```

5. Copy the provided **barnyard2** init script to /etc/init.d and make it executable:

```
cp <barnyard2> /etc/init.d chmod 755 /etc/init.d/barnyard2
sudo update-rc.d barnyard2 defaults sudo update-rc.d barnyard2 enable
```

6. Start up Barnyard2:

```
/etc/init.d/barnyard2 start
```

Error messages can be found in /var/log/syslog.

#### 3.8.8 Testing

Performing these steps will let you know that Snort and Barnyard2 are working.

- 1. Add a local rule.
- 2. Edit /etc/snort/rules/local.rules by adding the following line at the bottom that will generate alerts for any ICMP/Ping traffic:

alert icmp any any -> any any (msg: "ICMP Detected";classtype:unknown; sid:1000001; rev:1;)

Note: the sid must be greater than 1 million.

3. Restart Snort:

```
service snort restart
```

4. Verify that Snort is running:

```
ps -ef |grep snort
```

5. Verify that Barnyard2 is running:

```
ps -ef |grep barnyard2
```

- 6. Check the logs in /var/log/snort. The snort.log and alert files should both be growing fast.
- 7. You can view the alert file:

```
tail -f /var/log/snort/alert
```

Note: Do not leave this test running. If you do, it will fill your hard drive.

8. If everything is good, just comment out the line that you created in local rules and restart Snort.

### 3.8.9 Installing Splunk Universal Forwarder

Note: You will need a Splunk account to download the Splunk Universal Forwarder. It is free and can be set up at: https://www.splunk.com/page/sign\_up.

- 1. Download the Splunk Universal Forwarder from: <a href="http://www.splunk.com/en\_us/download/uni-versal-forwarder.html">http://www.splunk.com/en\_us/download/uni-versal-forwarder.html</a>.
- 2. You want the latest version for OS version 2.6+ kernel Linux distributions (64-bit). Since this is installing on Ubuntu, select the file that ends in .deb. An example is:

```
splunkforwader-6.2.5-272645-linux-2.6-amd64.deb
```

Detailed installation instructions can be found at:

http://docs.splunk.com/Documentation/Splunk/6.2.3/Installation/InstallonLinux.

3. An abridged version follows:

```
dpkg -i <splunk_package_name.deb>
Example: dpkg -i splunkforwader-6.2.5-272645-linux-2.6-amd64.deb
```

4. This will install in /opt/splunkforwarder:

```
cd /opt/splunkforwarder/bin
./splunk start --accept-license
./splunk enable boot-start
```

5. Add forwarder:

More information about adding a forwarder can be found at: http://docs.splunk.com/Documentation/Splunk/6.2.3/Forwarding/Deployanixdfmanually.

```
cd /opt/splunkforwarder/bin
./splunk add forward-server loghost:9997 -auth admin:changme
```

# 3.8.10 Configuring Splunk Universal Forwarder

Configuring Splunk Universal Forwarder as shown in the FS-ITAM use case requires X.509 Certificates for the Splunk Enterprise server/indexer and each Splunk Universal Forwarder. You will also need a copy of your certificate authority's public certificate.

1. Create a directory to hold your certificates:

```
mkdir /opt/splunkforwarder/etc/certs
```

### 2. Copy your certificates in PEM format to /opt/splunkforwarder/etc/certs:

```
cp CAServerCert.pem /opt/splunkforwarder/etc/certs
```

cp bro\_worker1.pem /opt/splunkforwarder/etc/certs

## 3. Copy Splunk Universal Forwarder configuration files:

```
cp <server.conf> /opt/splunkforwarder/etc/system/local
```

- cp <inputs.conf> /opt/splunkforwarder/etc/system/local
- cp <outputs.conf> /opt/splunkforwarder/etc/system/local

#### 4. Modify **server.conf** so that:

**ServerName=snort** is your hostname.

sslKeysfilePassword = <password for your private key>

#### 5. Modify **outputs.conf** so that:

**Server = loghost:9997** is your correct Splunk Enterprise server/indexer and port.

```
sslPassword = <password of your certificate private key>
```

Note: This will be hashed and not clear text after a restart.

Inputs.conf should work, but you are free to modify it to include the Bro logs that you are interested in.

# 3.8.11 Configurations and Scripts

#### /etc/default/barnyard2

```
# Config file for /etc/init.d/barnyard2
```

```
#LOG_FILE="snort_unified.log" LOG_FILE="snort.log"
```

# You probably don't want to change this, but in case you do SNORTDIR="/var/log/snort"
INTERFACES="eth0"

# Probably not this either CONF=/etc/snort/barnyard2.conf
EXTRA ARGS="

#### /etc/snort/snort.conf

#-----

```
VRT Rule Packages Snort.conf
      For more information visit us at:
     http://www.snort.org
                             Snort Website
     http://vrt-blog.snort.org/ Sourcefire VRT Blog
     Mailing list Contact:
                            snort-sigs@lists.sourceforge.net
      False Positive reports:
                             fp@sourcefire.com
      Snort bugs: bugs@snort.org
      Compatible with Snort Versions:
     VERSIONS : 2.9.6.0
      Snort build options:
     OPTIONS: --enable-gre --enable-mpls --enable-targetbased
--enable-ppm --enable-perfprofiling --enable-zlib
--enable-active-response --enable-normalizer --enable-reload
--enable-react --enable-flexresp3
     Additional information:
     This configuration file enables active response, to run snort in
      test mode -T you are required to supply an interface -i
<interface>
      or test mode will fail to fully validate the configuration and
      exit with a FATAL error
#-----
# This file contains a sample snort configuration.
# You should take the following steps to create your own custom configuration:
```

```
1) Set the network variables.
     2) Configure the decoder
     3) Configure the base detection engine
     4) Configure dynamic loaded libraries
     5) Configure preprocessors
     6) Configure output plugins
     7) Customize your rule set
     8) Customize preprocessor and decoder rule set
     9) Customize shared object rule set
# Step #1: Set the network variables. For more information, see README.variables
# Setup the network addresses you are protecting
# Note to Debian users: this value is overriden when starting
# up the Snort daemon through the init.d script by the
# value of DEBIAN SNORT HOME NET s defined in the
# /etc/snort/snort.debian.conf configuration file
ipvar HOME NET any
# Set up the external network addresses. Leave as "any" in most situations
ipvar EXTERNAL NET any
# If HOME NET is defined as something other than "any", alternative, you can
# use this definition if you do not want to detect attacks from your internal
# IP addresses:
#ipvar EXTERNAL_NET !$HOME_NET
```

# List of DNS servers on your network ipvar DNS SERVERS \$HOME NET # List of SMTP servers on your network ipvar SMTP SERVERS \$HOME NET # List of web servers on your network ipvar HTTP SERVERS \$HOME NET # List of sql servers on your network ipvar SQL SERVERS \$HOME NET # List of telnet servers on your network ipvar TELNET SERVERS \$HOME NET # List of ssh servers on your network ipvar SSH SERVERS \$HOME NET # List of ftp servers on your network ipvar FTP SERVERS \$HOME NET # List of sip servers on your network ipvar SIP SERVERS \$HOME NET # List of ports you run web servers on portvar HTTP PORTS [36,80,81,82,83,84,85,86,87,88,89,90,311,383,555,591,593,631,801,808,8 18,901,972,1158,1220,1414,1533,1741,1830,2231,2301,2381,2809,3029,3037 ,3057,3128,3443,3702,4000,4343,4848,5117,5250,6080,6173,6988,7000,7001 ,7144,7145,7510,7770,7777,7779,8000,8008,8014,8028,8080,8081,8082,8085 ,8088,8090,8118,8123,8180,8181,8222,8243,8280,8300,8500,8509,8800,8888 ,8899,9000,9060,9080,9090,9091,9111,9443,9999,10000,11371,12601,15489, 29991, 33300, 34412, 34443, 34444, 41080, 44449, 50000, 50002, 51423, 53331, 5525 2,55555,56712] # List of ports you want to look for SHELLCODE on. portvar SHELLCODE PORTS !80 # List of ports you might see oracle attacks on portvar ORACLE PORTS 1024: # List of ports you want to look for SSH connections on: portvar SSH PORTS 22 # List of ports you run ftp servers on portvar FTP PORTS [21,2100,3535] # List of ports you run SIP servers on portvar SIP PORTS [5060,5061,5600] # List of file data ports for file inspection portvar FILE DATA PORTS [\$HTTP PORTS, 110, 143] # List of GTP ports for GTP preprocessor portvar GTP PORTS [2123,2152,3386] # other variables, these should not be modified ipvar AIM SERVERS [64.12.24.0/23,64.12.28.0/23,64.12.161.0/24,64.12.163.0/24,64.12.200.0 /24,205.188.3.0/24,205.188.5.0/24,205.188.7.0/24,205.188.9.0/24,205.18 8.153.0/24,205.188.179.0/24,205.188.248.0/24]

```
# Path to your rules files (this can be a relative path)
# Note for Windows users: You are advised to make this an absolute path,
# such as: c:\snort\rules
#var RULE PATH /etc/snort/rules var RULE PATH rules
var SO RULE PATH /etc/snort/so rules
var PREPROC RULE PATH /etc/snort/preproc rules
# If you are using reputation preprocessor set these
# Currently there is a bug with relative paths, they are relative to where snort is
# not relative to snort.conf like the above variables
# This is completely inconsistent with how other vars work, BUG 89986
# Set the absolute path appropriately var WHITE LIST PATH /etc/snort/rules var
BLACK LIST PATH /etc/snort/rules
# Step #2: Configure the decoder. For more information, see README.decode
# Stop generic decode events: config disable decode alerts
# Stop Alerts on experimental TCP options config disable tcpopt experimental alerts
# Stop Alerts on obsolete TCP options config disable tcpopt obsolete alerts
# Stop Alerts on T/TCP alerts config disable tcpopt ttcp alerts
# Stop Alerts on all other TCPOption type events: config disable tcpopt alerts
# Stop Alerts on invalid ip options config disable_ipopt_alerts
# Alert if value in length field (IP, TCP, UDP) is greater th elength of the packet
# config enable decode oversized alerts
# Same as above, but drop packet if in Inline mode (requires
enable_decode_oversized_alerts)
# config enable decode oversized drops
```

# Configure IP / TCP checksum mode config checksum mode: all

```
# Configure maximum number of flowbit references. For more information, see
README.flowbits
# config flowbits size: 64
# Configure ports to ignore
# config ignore ports: tcp 21 6667:6671 1356
# config ignore ports: udp 1:17 53
# Configure active response for non inline operation. For more information, see
REAMDE.active
# config response: eth0 attempts 2
# Configure DAQ related options for inline operation. For more information, see
README.dag
# config daq: <type>
# config daq_dir: <dir>
# config dag mode: <mode>
# config daq var: <var>
# <type> ::= pcap | afpacket | dump | nfq | ipq | ipfw
# <mode> ::= read-file | passive | inline
# <var> ::= arbitrary <name>=<value passed to DAQ
# <dir> ::= path as to where to look for DAQ module so's
# Configure specific UID and GID to run snort as after dropping privs. For more
information see snort -h command line options
# config set gid:
# config set uid:
# Configure default snaplen. Snort defaults to MTU of in use interface. For more
information see README
```

```
# config snaplen:
# Configure default bpf file to use for filtering what traffic reaches snort. For more
information see snort -h command line options (-F)
# config bpf file:
# Configure default log directory for snort to log to. For more information see snort
-h command line options (-1)
# config logdir:
# Step #3: Configure the base detection engine. For more information, see README.decode
# Configure PCRE match limitations config pore match limit: 3500
config pcre match limit recursion: 1500
# Configure the detection engine See the Snort Manual, Configuring Snort - Includes -
Config
config detection: search-method ac-split search-optimize max-pattern-len 20
# Configure the event queue.
                           For more information, see README.event queue
config event queue: max queue 8 log 5 order events content length
## Configure GTP if it is to be used.
## For more information, see README.GTP
```

```
# config enable gtp
# Per packet and rule latency enforcement
# For more information see README.ppm
# Per Packet latency configuration
#config ppm: max-pkt-time 250, \
    fastpath-expensive-packets, \
    pkt-log
# Per Rule latency configuration
#config ppm: max-rule-time 200, \
    threshold 3, \setminus
    suspend-expensive-rules, \
    suspend-timeout 20, \
    rule-log alert
# Configure Perf Profiling for debugging
# For more information see README.PerfProfiling
#config profile rules: print all, sort avg ticks
#config profile preprocs: print all, sort avg ticks
# Configure protocol aware flushing
```

```
# For more information see README.stream5
config paf max: 16000
# Step #4: Configure dynamic loaded libraries.
# For more information, see Snort Manual, Configuring Snort - Dynamic Modules
# path to dynamic preprocessor libraries
dynamicpreprocessor directory /usr/lib/snort dynamicpreprocessor/
# path to base preprocessor engine
dynamicengine /usr/lib/snort_dynamicengine/libsf_engine.so
# path to dynamic rules libraries
dynamicdetection directory /usr/lib/snort dynamicrules
# Step #5: Configure preprocessors
# For more information, see the Snort Manual, Configuring Snort - Preprocessors
# GTP Control Channle Preprocessor. For more information, see README.GTP
# preprocessor gtp: ports { 2123 3386 2152 }
# Inline packet normalization. For more information, see README.normalize
# Does nothing in IDS mode preprocessor normalize ip4
preprocessor normalize_tcp: ips ecn stream preprocessor normalize_icmp4
preprocessor normalize ip6 preprocessor normalize icmp6
```

```
# Target-based IP defragmentation.
                                   For more inforation, see README.frag3
preprocessor frag3 global: max frags 65536
preprocessor frag3 engine: policy windows detect anomalies overlap limit 10
min fragment length 100 timeout 180
# Target-Based stateful inspection/stream reassembly. For more inforation, see
README.stream5
preprocessor stream5_global: track_tcp yes, \ track_udp yes, \
track icmp no, \ max tcp 262144, \
max_udp 131072, \
max active responses 2, \
min response seconds 5
preprocessor stream5 tcp: policy windows, detect anomalies, require 3whs 180, \
overlap limit 10, small segments 3 bytes 150, timeout 180, \
ports client 21 22 23 25 42 53 70 79 109 110 111 113 119 135 136 137
139 143 \
161 445 513 514 587 593 691 1433 1521 1741 2100 3306 6070 6665
6666 6667 6668 6669 \
7000 8181 32770 32771 32772 32773 32774 32775 32776 32777 32778
32779, \
ports both 36 80 81 82 83 84 85 86 87 88 89 90 110 311 383 443 465
563 555 591 593 631 636 801 808 818 901 972 989 992 993 994 995 1158
1220 1414 1533 1741 1830 2231 2301 2381 2809 3029 3037 3057 3128 3443
3702 4000 4343 4848 5117 5250 6080 6173 6988 7907 7000 7001 7144 7145
7510 7802 7770 7777 7779 \
7801 7900 7901 7902 7903 7904 7905 7906 7908 7909 7910 7911 7912
7913 7914 7915 7916 \
7917 7918 7919 7920 8000 8008 8014 8028 8080 8081 8082 8085 8088
8090 8118 8123 8180 8181 8222 8243 8280 8300 8500 8509 8800 8888 8899
9000 9060 9080 9090 9091 9111 9443 9999 10000 11371 12601 15489 29991
33300 34412 34443 34444 41080 44449 50000 50002 51423 53331 55252 55555
```

```
56712
preprocessor stream5 udp: timeout 180
# performance statistics. For more information, see the Snort Manual, Configuring
Snort - Preprocessors - Performance Monitor
# preprocessor perfmonitor: time 300 file /var/snort/snort.stats pktcnt 10000
# HTTP normalization and anomaly detection. For more information, see
README.http inspect
preprocessor http inspect: global iis unicode map unicode.map 1252 compress depth
65535 decompress depth 65535 max gzip mem 104857600
preprocessor http inspect server: server default \
http methods { GET POST PUT SEARCH MKCOL COPY MOVE LOCK UNLOCK NOTIFY POLL BCOPY
BDELETE BMOVE LINK UNLINK OPTIONS HEAD DELETE TRACE TRACK CONNECT SOURCE SUBSCRIBE
UNSUBSCRIBE PROPFIND PROPPATCH BPROPFIND BPROPPATCH RPC CONNECT PROXY SUCCESS
BITS_POST CCM_POST SMS_POST RPC_IN_DATA RPC_OUT_DATA RPC_ECHO_DATA } \
chunk length 500000 \
server flow depth 0 \
client flow depth 0 \
post_depth 65495 \
oversize dir length 500 \
max header length 750 \
max headers 100 \
max spaces 200 \
small chunk length { 10 5 } \
ports { 36 80 81 82 83 84 85 86 87 88 89 90 311 383 555 591 593 631
801 808 818 901 972 1158 1220 1414 1741 1830 2231 2301 2381 2809 3029
3037 3057 3128 3443 3702 4000 4343 4848 5117 5250 6080 6173 6988 7000
7001 7144 7145 7510 7770 7777 7779 8000 8008 8014 8028 8080 8081 8082
8085 8088 8090 8118 8123 8180 8181 8222 8243 8280 8300 8500 8509 8800
8888 8899 9000 9060 9080 9090 9091 9111 9443 9999 10000 11371 12601
15489 29991 33300 34412 34443 34444 41080 44449 50000 50002 51423 53331
55252 55555 56712 } \
```

```
non rfc char { 0x00\ 0x01\ 0x02\ 0x03\ 0x04\ 0x05\ 0x06\ 0x07\ } \ enable cookie \
extended response inspection \ inspect gzip \
normalize utf \ unlimited decompress \ normalize javascript \ apache whitespace no \
ascii no \
bare byte no \ directory no \ double decode no \ iis backslash no \ iis delimiter no \
iis unicode no \ multi slash no \ utf 8 no \ u encode yes \ webroot no
# ONC-RPC normalization and anomaly detection. For more information, see the Snort
Manual, Configuring Snort - Preprocessors - RPC Decode
preprocessor rpc decode: 111 32770 32771 32772 32773 32774 32775 32776
32777 32778 32779 no alert multiple requests no alert large fragments
no alert incomplete
# Back Orifice detection. preprocessor bo
# FTP / Telnet normalization and anomaly detection. For more information, see
README.ftptelnet
preprocessor ftp telnet: global inspection type stateful encrypted traffic no
check encrypted
preprocessor ftp telnet protocol: telnet \ ayt attack thresh 20 \
normalize ports { 23 } \ detect anomalies
preprocessor ftp telnet protocol: ftp server default \setminus def max param len 100 \setminus
ports { 21 2100 3535 } \ telnet_cmds yes \ ignore_telnet_erase_cmds yes \
ftp cmds { ABOR ACCT ADAT ALLO APPE AUTH CCC CDUP } \ ftp_cmds { CEL CLNT CMD CONF CWD
DELE ENC EPRT } \ ftp cmds { EPSV ESTA ESTP FEAT HELP LANG LIST LPRT } \ ftp cmds {
LPSV MACB MAIL MDTM MIC MKD MLSD MLST } \ ftp cmds { MODE NLST NOOP OPTS PASS PASV
PBSZ PORT } \ ftp cmds { PROT PWD QUIT REIN REST RETR RMD RNFR } \ ftp cmds { RNTO
SDUP SITE SIZE SMNT STAT STOR STOU } \ ftp cmds { STRU SYST TEST TYPE USER XCUP XCRC
XCWD } \ ftp_cmds { XMAS XMD5 XMKD XPWD XRCP XRMD XRSQ XSEM } \
ftp cmds { XSEN XSHA1 XSHA256 } \
alt max param len 0 { ABOR CCC CDUP ESTA FEAT LPSV NOOP PASV PWD QUIT REIN STOU SYST
XCUP XPWD } \
alt max param len 200 { ALLO APPE CMD HELP NLST RETR RNFR STOR STOU XMKD } \
alt max param len 256 { CWD RNTO } \ alt max param len 400 { PORT } \setminus
alt_max_param_len 512 { SIZE } \
chk str fmt { ACCT ADAT ALLO APPE AUTH CEL CLNT CMD } \ chk str fmt { CONF CWD DELE
ENC EPRT EPSV ESTP HELP } \ chk str fmt { LANG LIST LPRT MACB MAIL MDTM MIC MKD } \
chk str fmt { MLSD MLST MODE NLST OPTS PASS PBSZ PORT } \ chk str fmt { PROT REST RETR
```

```
RMD RNFR RNTO SDUP SITE } \ chk str fmt { SIZE SMNT STAT STOR STRU TEST TYPE USER } \
chk str fmt { XCRC XCWD XMAS XMD5 XMKD XRCP XRMD XRSQ } \
chk str fmt { XSEM XSEN XSHA1 XSHA256 } \ cmd validity ALLO < int [ char R int ] > \
cmd validity EPSV < [ { char 12 | char L char L } ] > \setminus cmd validity MACB <
string > \
char ASBCZ > \
cmd validity PORT < host port > \ cmd validity PROT < char CSEP > \ cmd validity STRU
< char FRPO [ string ] > \
cmd validity TYPE < { char AE [ char NTC ] | char I | char L [ number ] } >
preprocessor ftp telnet protocol: ftp client default \ max resp len 256 \
bounce yes \ ignore telnet erase cmds yes \ telnet cmds yes
# SMTP normalization and anomaly detection.
                                            For more information, see README.SMTP
preprocessor smtp: ports { 25 465 587 691 } \ inspection_type stateful \
b64 decode depth 0 \
qp_decode_depth 0 \
bitenc decode depth 0 \
uu decode depth 0 \ log mailfrom \ log rcptto \ log filename \ log email hdrs \
normalize cmds \
normalize cmds { ATRN AUTH BDAT CHUNKING DATA DEBUG EHLO EMAL ESAM ESND ESOM ETRN EVFY
normalize cmds { EXPN HELO HELP IDENT MAIL NOOP ONEX QUEU QUIT RCPT RSET SAML SEND
SOML } \
normalize cmds { STARTTLS TICK TIME TURN TURNME VERB VRFY X-ADAT X-DRCP X-ERCP X-
EXCH50 } \
normalize cmds { X-EXPS X-LINK2STATE XADR XAUTH XCIR XEXCH50 XGEN XLICENSE XQUE XSTA
XTRN XUSR } \
max command line len 512 \
max header line len 1000 \
max response line len 512 \ alt max command line len 260 { MAIL } \
alt max command line len 300 { RCPT } \
alt max command line len 500 { HELP HELO ETRN EHLO } \
alt max command line len 255 { EXPN VRFY ATRN SIZE BDAT DEBUG EMAL ESAM ESAM ESOM EVFY
IDENT NOOP RSET } \
```

```
alt_max_command_line_len 246 { SEND SAML SOML AUTH TURN ETRN DATA RSET QUIT ONEX QUEU
STARTILS TICK TIME TURNME VERB X-EXPS X-LINK2STATE XADR XAUTH XCIR XEXCH50 XGEN
XLICENSE XOUE XSTA XTRN XUSR } \
valid_cmds { ATRN AUTH BDAT CHUNKING DATA DEBUG EHLO EMAL ESAM ESND ESOM ETRN EVFY } \
valid cmds { EXPN HELO HELP IDENT MAIL NOOP ONEX QUEU QUIT RCPT RSET SAML SEND SOML }
valid cmds { STARTTLS TICK TIME TURN TURNME VERB VRFY X-ADAT X-DRCP X-ERCP X-EXCH50 }
valid cmds { X-EXPS X-LINK2STATE XADR XAUTH XCIR XEXCH50 XGEN XLICENSE XQUE XSTA XTRN
XUSR } \
xlink2state { enabled }
# Portscan detection.
                         For more information, see README.sfportscan
# preprocessor sfportscan: proto { all } memcap { 10000000 } sense level { low }
# ARP spoof detection.
                         For more information, see the Snort Manual - Configuring
Snort - Preprocessors - ARP Spoof Preprocessor
# preprocessor arpspoof
# preprocessor arpspoof detect host: 192.168.40.1 f0:0f:00:f0:0f:00
# SSH anomaly detection. For more information, see README.ssh preprocessor ssh:
server ports { 22 } \
autodetect \ max client bytes 19600 \
max encrypted packets 20 \
max server version len 100 \ enable respoverflow enable ssh1crc32 \ enable srvoverflow
enable protomismatch
# SMB / DCE-RPC normalization and anomaly detection. For more information, see
README.dcerpc2
preprocessor dcerpc2: memcap 102400, events [co ] preprocessor dcerpc2 server:
default, policy WinXP, \
detect [smb [139,445], tcp 135, udp 135, rpc-over-http-server 593],
autodetect [tcp 1025:, udp 1025:, rpc-over-http-server 1025:], \ smb_max_chain 3,
smb invalid shares ["C$", "D$", "ADMIN$"]
# DNS anomaly detection. For more information, see README.dns preprocessor dns:
ports { 53 } enable rdata overflow
```

```
# SSL anomaly detection and traffic bypass. For more information, see README.ssl
preprocessor ssl: ports { 443 465 563 636 989 992 993 994 995 7801 7802
7900 7901 7902 7903 7904 7905 7906 7907 7908 7909 7910 7911 7912 7913
7914 7915 7916 7917 7918 7919 7920 }, trustservers, noinspect encrypted
# SDF sensitive data preprocessor.
                                         For more information see README.sensitive data
preprocessor sensitive data: alert threshold 25
# SIP Session Initiation Protocol preprocessor. For more information see README.sip
preprocessor sip: max sessions 40000, \ ports { 5060 5061 5600 }, \
methods { invite \
cancel \ ack \
bye \ register \ options \ refer \
subscribe \ update \ join \
info \ message \ notify \ benotify \ do \
qauth \ sprack \ publish \ service \ unsubscribe \ prack }, \
max uri len 512, \
max call id len 80, \setminus
max_requestName_len 20, \
max from len 256, \setminus
max to len 256, \setminus
max_via_len 1024, \
max contact len 512, \setminus
max_content_len 2048
# IMAP preprocessor. For more information see README.imap preprocessor imap: \
ports { 143 } \ b64 decode depth 0 \
qp_decode_depth 0 \
bitenc decode depth 0 \
uu_decode_depth 0
```

```
# POP preprocessor. For more information see README.pop preprocessor pop: \
ports { 110 } \ b64 decode depth 0 \
qp_decode_depth 0 \
bitenc decode depth 0 \
uu decode depth 0
# Modbus preprocessor. For more information see README.modbus preprocessor modbus:
ports { 502 }
# DNP3 preprocessor. For more information see README.dnp3 preprocessor dnp3: ports {
20000 } \
memcap 262144 \
check crc
# Note to Debian users: this is disabled since it is an experimental
# preprocessor. If you want to use it you have to create the rules files
# referenced below in the /etc/snort/rules directory
# Reputation preprocessor. For more information see README.reputation
#preprocessor reputation: \
      memcap 500, \setminus
      priority whitelist, \
      nested ip inner, \
      whitelist $WHITE LIST PATH/white list.rules, \
      blacklist $BLACK_LIST_PATH/black_list.rules
# Step #6: Configure output plugins
# For more information, see Snort Manual, Configuring Snort - Output Modules
```

```
# unified2
# Recommended for most installs
# output unified2: filename merged.log, limit 128, nostamp, mpls_event_types,
vlan event types
#output unified2: filename snort.log, limit 128, nostamp, mpls event types,
vlan event types
output unified2: filename /var/log/snort/snort.log, limit 128, mpls event types,
vlan_event_types
# Additional configuration for specific types of installs
# output alert unified2: filename snort.alert, limit 128, nostamp
# output log unified2: filename snort.log, limit 128, nostamp
# syslog
# output alert_syslog: LOG_AUTH LOG_ALERT
# pcap
# output log tcpdump: tcpdump.log
# metadata reference data. do not modify these lines include classification.config
include reference.config
# Step #7: Customize your rule set
# For more information, see Snort Manual, Writing Snort Rules
# NOTE: All categories are enabled in this conf file
# Note to Debian users: The rules preinstalled in the system
# can be *very* out of date. For more information please read
```

```
# the /usr/share/doc/snort-rules-default/README.Debian file
# If you install the official VRT Sourcefire rules please review this
# configuration file and re-enable (remove the comment in the first line) those
# rules files that are available in your system (in the
/etc/snort/rules
# directory)
# site specific rules
include $RULE PATH/local.rules
#include $RULE PATH/app-detect.rules include $RULE PATH/attack-responses.rules include
$RULE PATH/backdoor.rules
include $RULE PATH/bad-traffic.rules
#include $RULE PATH/blacklist.rules
#include $RULE PATH/botnet-cnc.rules
#include $RULE PATH/browser-chrome.rules
#include $RULE PATH/browser-firefox.rules
#include $RULE PATH/browser-ie.rules
#include $RULE PATH/browser-other.rules
#include $RULE PATH/browser-plugins.rules
#include $RULE PATH/browser-webkit.rules include $RULE PATH/chat.rules
#include $RULE PATH/content-replace.rules include $RULE PATH/ddos.rules
include $RULE PATH/dns.rules include $RULE PATH/dos.rules
include $RULE PATH/experimental.rules
#include $RULE PATH/exploit-kit.rules include $RULE PATH/exploit.rules
#include $RULE PATH/file-executable.rules
#include $RULE PATH/file-flash.rules
#include $RULE PATH/file-identify.rules
#include $RULE PATH/file-image.rules
```

```
#include $RULE PATH/file-java.rules
#include $RULE PATH/file-multimedia.rules
#include $RULE PATH/file-office.rules
#include $RULE PATH/file-other.rules
#include $RULE PATH/file-pdf.rules include $RULE PATH/finger.rules include
$RULE PATH/ftp.rules include $RULE PATH/icmp-info.rules include $RULE PATH/icmp.rules
include $RULE PATH/imap.rules
#include $RULE PATH/indicator-compromise.rules
#include $RULE PATH/indicator-obfuscation.rules
#include $RULE PATH/indicator-scan.rules
#include $RULE_PATH/indicator-shellcode.rules include $RULE PATH/info.rules
#include $RULE PATH/malware-backdoor.rules
#include $RULE PATH/malware-cnc.rules
#include $RULE PATH/malware-other.rules
#include $RULE PATH/malware-tools.rules include $RULE PATH/misc.rules
include $RULE PATH/multimedia.rules include $RULE PATH/mysql.rules include
$RULE PATH/netbios.rules include $RULE PATH/nntp.rules include $RULE PATH/oracle.rules
#include $RULE PATH/os-linux.rules
#include $RULE PATH/os-mobile.rules
#include $RULE PATH/os-other.rules
#include $RULE PATH/os-solaris.rules
#include $RULE PATH/os-windows.rules include $RULE PATH/other-ids.rules include
$RULE PATH/p2p.rules
#include $RULE PATH/phishing-spam.rules
#include $RULE PATH/policy-multimedia.rules
#include $RULE_PATH/policy-other.rules include $RULE_PATH/policy.rules
#include $RULE PATH/policy-social.rules
#include $RULE PATH/policy-spam.rules include $RULE PATH/pop2.rules include
$RULE PATH/pop3.rules
#include $RULE PATH/protocol-dns.rules
#include $RULE PATH/protocol-finger.rules
```

#include \$RULE PATH/protocol-ftp.rules

```
#include $RULE PATH/protocol-icmp.rules
#include $RULE PATH/protocol-imap.rules
#include $RULE PATH/protocol-nntp.rules
#include $RULE PATH/protocol-pop.rules
#include $RULE PATH/protocol-rpc.rules
#include $RULE PATH/protocol-scada.rules
#include $RULE PATH/protocol-services.rules
#include $RULE PATH/protocol-snmp.rules
#include $RULE PATH/protocol-telnet.rules
#include $RULE PATH/protocol-tftp.rules
#include $RULE PATH/protocol-voip.rules
#include $RULE PATH/pua-adware.rules
#include $RULE PATH/pua-other.rules
#include $RULE PATH/pua-p2p.rules
#include $RULE PATH/pua-toolbars.rules include $RULE PATH/rpc.rules
include $RULE PATH/rservices.rules
#include $RULE PATH/scada.rules include $RULE PATH/scan.rules
#include $RULE PATH/server-apache.rules
#include $RULE PATH/server-iis.rules
#include $RULE PATH/server-mail.rules
#include $RULE PATH/server-mssql.rules
#include $RULE PATH/server-mysql.rules
#include $RULE PATH/server-oracle.rules
#include $RULE PATH/server-other.rules
#include $RULE PATH/server-samba.rules
#include $RULE PATH/server-webapp.rules
# Note: These rules are disable by default as they are
# too coarse grained. Enabling them causes a large
# performance impact
```

```
#include $RULE PATH/shellcode.rules include $RULE PATH/smtp.rules include
$RULE PATH/snmp.rules
#include $RULE PATH/specific-threats.rules
#include $RULE PATH/spyware-put.rules include $RULE PATH/sql.rules
include $RULE PATH/telnet.rules include $RULE PATH/tftp.rules include
$RULE PATH/virus.rules
#include $RULE PATH/voip.rules
#include $RULE PATH/web-activex.rules include $RULE PATH/web-attacks.rules
include $RULE PATH/web-cgi.rules include $RULE PATH/web-client.rules include
$RULE PATH/web-coldfusion.rules include $RULE PATH/web-frontpage.rules include
$RULE PATH/web-iis.rules include $RULE PATH/web-misc.rules include $RULE PATH/web-
php.rules include $RULE PATH/x11.rules
include $RULE PATH/community-sql-injection.rules include $RULE PATH/community-web-
client.rules include $RULE PATH/community-web-dos.rules include $RULE PATH/community-
web-iis.rules include $RULE_PATH/community-web-misc.rules include
$RULE PATH/community-web-php.rules include $RULE PATH/community-sql-injection.rules
include $RULE PATH/community-web-client.rules include $RULE PATH/community-web-
dos.rules include $RULE PATH/community-web-iis.rules include $RULE PATH/community-web-
misc.rules include $RULE PATH/community-web-php.rules
# Step #8: Customize your preprocessor and decoder alerts
# For more information, see README.decoder preproc rules
# decoder and preprocessor event rules
# include $PREPROC RULE PATH/preprocessor.rules
# include $PREPROC RULE PATH/decoder.rules
# include $PREPROC RULE PATH/sensitive-data.rules
# Step #9: Customize your Shared Object Snort Rules
# For more information, see
http://vrt-blog.snort.org/2009/01/using-vrt-certified-shared-object-ru les.html
```

```
# dynamic library rules
# include $SO RULE PATH/bad-traffic.rules
# include $SO RULE PATH/chat.rules
# include $SO_RULE_PATH/dos.rules
# include $SO RULE PATH/exploit.rules
# include $SO RULE PATH/icmp.rules
# include $SO RULE PATH/imap.rules
# include $SO RULE PATH/misc.rules
# include $SO RULE PATH/multimedia.rules
# include $SO RULE PATH/netbios.rules
# include $SO RULE PATH/nntp.rules
# include $SO RULE PATH/p2p.rules
# include $SO_RULE_PATH/smtp.rules
# include $SO RULE PATH/snmp.rules
# include $SO RULE PATH/specific-threats.rules
# include $SO RULE PATH/web-activex.rules
# include $SO RULE PATH/web-client.rules
# include $SO RULE PATH/web-iis.rules
# include $SO RULE PATH/web-misc.rules
# Event thresholding or suppression commands. See threshold.conf include
threshold.conf
```

#### /etc/snort/snort.debian.conf

```
# snort.debian.config (Debian Snort configuration file)
#
# This file was generated by the post-installation script of the snort
# package using values from the debconf database.
#
# It is used for options that are changed by Debian to leave
```

```
# the original configuration files untouched.
# This file is automatically updated on upgrades of the snort package
# *only* if it has not been modified since the last upgrade of that package.
# If you have edited this file but would like it to be automatically updated
# again, run the following command as root:
      dpkg-reconfigure snort
DEBIAN SNORT STARTUP="boot" DEBIAN SNORT HOME NET="172.16.0.0/16"
DEBIAN SNORT OPTIONS="" DEBIAN SNORT INTERFACE="eth0" DEBIAN SNORT SEND STATS="true"
DEBIAN_SNORT_STATS_RCPT="root" DEBIAN_SNORT_STATS_THRESHOLD="1"
/usr/local/etc/barnyard2.conf
Also linked from /etc/snort/barnyard.conf.
      Barnyard2 example configuration file
# This file contains a sample barnyard2 configuration.
# You can take the following steps to create your own custom configuration:
      1) Configure the variable declarations
      2) Setup the input plugins
      3) Setup the output plugins
# Step 1: configure the variable declarations
```

```
# in order to keep from having a commandline that uses every letter in the
# alphabet most configuration options are set here.
# use UTC for timestamps
#config utc
# set the appropriate paths to the file(s) your Snort process is using.
                         /etc/snort/etc/reference.config config classification file:
config reference file:
/etc/snort/etc/classification.config config gen file:/etc/snort/gen-msg.map
config sid file:
                   /etc/snort/etc/sid-msg.map
# Configure signature suppression at the spooler level see doc/README.sig_suppress
#config sig suppress: 1:10
# Set the event cache size to defined max value before recycling of event occur.
#config event cache size: 4096
# define dedicated references similar to that of snort.
#config reference: mybugs http://www.mybugs.com/?s=
# define explicit classifications similar to that of snort.
#config classification: shortname, short description, priority
# set the directory for any output logging
```

```
config logdir: /var/log/barnyard2
# to ensure that any plugins requiring some level of uniqueness in their output
# the alert with interface name, interface and hostname directives are provided.
# An example of usage would be to configure them to the values of the associated
# snort process whose unified files you are reading.
# Example:
      For a snort process as follows:
      snort -i eth0 -c /etc/snort.conf
      Typical options would be:
      config hostname:
                          thor
      config interface: eth0
      config alert with interface name
config hostname:
                  snort config interface:
# enable printing of the interface name when alerting.
#config alert with interface name
# at times snort will alert on a packet within a stream and dump that stream to
# the unified output. barnyard2 can generate output on each packet of that
# stream or the first packet only.
#config alert on each packet in stream
# enable daemon mode
```

```
config daemon
# make barnyard2 process chroot to directory after initialisation.
#config chroot: /var/spool/barnyard2
# specifiy the group or GID for barnyard2 to run as after initialisation.
#config set gid: 999
\# specifiy the user or UID for barnyard2 to run as after initialisation.
#config set_uid: 999
# specify the directory for the barnyard2 PID file.
#config pidpath: /var/run/by2.pid
# enable decoding of the data link (or second level headers).
#config decode data link
# dump the application data
#config dump_payload
# dump the application data as chars only
#config dump_chars_only
```

```
# enable verbose dumping of payload information in log style output plugins.
#config dump_payload_verbose
# enable obfuscation of logged IP addresses.
#config obfuscate
# enable the year being shown in timestamps
config show year
# set the umask for all files created by the barnyard2 process (eg. log files).
#config umask: 066
# enable verbose logging
#config verbose
# quiet down some of the output
#config quiet
# define the full waldo filepath.
config waldo file: /tmp/waldo
# specificy the maximum length of the MPLS label chain
```

```
#config max mpls labelchain len: 64
# specify the protocol (ie ipv4, ipv6, ethernet) that is encapsulated by MPLS.
#config mpls payload type: ipv4
# set the reference network or homenet which is predominantly used by the
# log ascii plugin.
#config reference_net: 192.168.0.0/24
# CONTINOUS MODE
# set the archive directory for use with continous mode
#config archivedir: /tmp
# when in operating in continous mode, only process new records and ignore any
# existing unified files
#config process_new_records_only
# Step 2: setup the input plugins
# this is not hard, only unified2 is supported ;)
input unified2
```

```
# Step 3: setup the output plugins#
# alert cef
# Purpose:
      This output module provides the abilty to output alert information to a
# remote network host as well as the local host using the open standard
# Common Event Format (CEF).
# Arguments: host=hostname[:port], severity facility
      arguments should be comma delimited.
      host - specify a remote hostname or IP with optional port number
      this is only specific to WIN32 (and is not yet fully supported)
                  - as defined in RFC 3164 (eg. LOG WARN, LOG INFO)
      severity
                  - as defined in RFC 3164 (eg. LOG_AUTH, LOG_LOCALO)
      facility
# Examples:
      output alert_cef
      output alert cef: host=192.168.10.1
      output alert_cef: host=sysserver.com:1001
      output alert_cef: LOG_AUTH LOG_INFO
# alert bro
```

```
# Purpose: Send alerts to a Bro-IDS instance.
# Arguments: hostname:port
# Examples:
     output alert bro: 127.0.0.1:47757
# alert fast
______
# Purpose: Converts data to an approximation of Snort's "fast alert" mode.
# Arguments: file <file>, stdout
     arguments should be comma delimited.
     file - specifiy alert file
     stdout - no alert file, just print to screen
# Examples:
     output alert fast
     output alert fast: stdout
#output alert_fast: stdout
output alert_fast: /var/log/snort/alert
# prelude: log to the Prelude Hybrid IDS system
______
# Purpose:
```

```
This output module provides logging to the Prelude Hybrid IDS system
# Arguments: profile=snort-profile
      snort-profile - name of the Prelude profile to use (default is snort).
# Snort priority to IDMEF severity mappings:
# high < medium < low < info</pre>
# These are the default mapped from classification.config:
# info = 4
\# low = 3
\# medium = 2
# high = anything below medium
# Examples:
      output alert prelude
      output alert prelude: profile=snort-profile-name
# alert syslog
# Purpose:
      This output module provides the abilty to output alert information to local
syslog
      severity - as defined in RFC 3164 (eg. LOG WARN, LOG INFO)
      facility - as defined in RFC 3164 (eg. LOG_AUTH, LOG_LOCALO)
# Examples:
```

```
output alert syslog
      output alert syslog: LOG AUTH LOG INFO
output alert_syslog: LOG_AUTH LOG_INFO
# syslog full
#-----
# Available as both a log and alert output plugin. Used to output data via TCP/UDP or
LOCAL ie(syslog())
# Arguments:
      sensor name $sensor name - unique sensor name
      server $server
                         - server the device will report to
      local - if defined, ignore all remote information and use syslog() to send
message.
      protocol $protocol - protocol device will report over (tcp/udp)
      port $port - destination port device will report to (default: 514)
      delimiters $delimiters
                                       - define a character that will delimit message
sections ex: "|", will use | as message section delimiters. (default: |)
    separators $separators
                                - define field separator included in each message ex:
" " , will use space as field separator. (default: [:space:])
      operation mode $operaion mode
                                       - default | complete : default mode is
compatible with default snort syslog message, complete prints more information such as
the raw packet (hexed)
      log priority $log priority - used by local option for syslog priority call. (man
syslog(3) for supported options) (default: LOG INFO)
      log facility $log facility - used by local option for syslog facility call. (man
syslog(3) for supported options) (default: LOG USER)
      payload encoding
                         - (default: hex)
                                              support hex/ascii/base64 for
log syslog full using operation mode complete only.
# Usage Examples:
# output alert syslog full: sensor name snortIds1-eth2, server xxx.xxx.xxx,
protocol udp, port 514, operation mode default
# output alert syslog full: sensor name snortIds1-eth2, server xxx.xxx.xxx,
protocol udp, port 514, operation mode complete
```

```
# output log syslog full: sensor name snortIds1-eth2, server xxx.xxx.xxx.xxx, protocol
udp, port 514, operation mode default
# output log_syslog_full: sensor_name snortIds1-eth2, server xxx.xxx.xxx.xxx, protocol
udp, port 514, operation mode complete
# output alert_syslog_full: sensor_name snortIds1-eth2, server xxx.xxx.xxx,
protocol udp, port 514
# output log syslog full: sensor name snortIds1-eth2, server xxx.xxx.xxx.xxx, protocol
udp, port 514
# output alert syslog full: sensor name snortIds1-eth2, local
# output log syslog full: sensor name snortIds1-eth2, local, log priority
LOG_CRIT, log_facility LOG_CRON
# log ascii
# Purpose: This output module provides the default packet logging funtionality
# Arguments: None.
# Examples:
      output log ascii
output log ascii
# log_tcpdump
# Purpose
      This output module logs packets in binary tcpdump format
```

```
# Arguments:
      The only argument is the output file name.
# Examples:
      output log tcpdump: tcpdump.log
output log tcpdump: /var/log/snort/tcpdump.log
# squil
# Purpose: This output module provides logging ability for the sguil interface
# See doc/README.sguil
# Arguments: agent_port <port>, sensor_name <name>
      arguments should be comma delimited.
      agent port - explicitly set the sguil agent listening port
      (default: 7736)
      sensor_name - explicitly set the sensor name
      (default: machine hostname)
# Examples:
      output sguil
      output sguil: agent_port=7000
      output sguil: sensor_name=argyle
      output sguil: agent port=7000, sensor name=argyle
# database: log to a variety of databases
```

```
# Purpose: This output module provides logging ability to a variety of databases
# See doc/README.database for additional information.
# Examples:
      output database: log, mysql, user=root password=test dbname=db host=localhost
      output database: alert, postgresql, user=snort dbname=snort
      output database: log, odbc, user=snort dbname=snort
      output database: log, mssql, dbname=snort user=snort password=test
      output database: log, oracle, dbname=snort user=snort password=test
#output database: log, mysql, user=root password=1Password! dbname=snortdb
# alert fwsam: allow blocking of IP's through remote services
# output alert fwsam: <SnortSam Station>:<port>/<key>
      <FW Mgmt Station>: IP address or host name of the host running SnortSam.
      <port>:
                    Port the remote SnortSam service listens on (default 898).
      <key>: Key used for authentication (encryption really)
      of the communication to the remote service.
# Examples:
# output alert fwsam: snortsambox/idspassword
# output alert_fwsam: fw1.domain.tld:898/mykey
# output alert fwsam: 192.168.0.1/borderfw 192.168.1.254/wanfw
```

# /opt/splunkforwarder/etc/system/local/server.conf

```
[sslConfig]
sslKeysfilePassword = $1$A0zU/599e04g

[lmpool:auto_generated_pool_forwarder] description = auto_generated_pool_forwarder
quota = MAX
slaves = *
stack_id = forwarder

[lmpool:auto_generated_pool_free] description = auto_generated_pool_free quota = MAX
slaves = * stack_id = free
[general]
pass4SymmKey = $1$VACAo9o7M7wg serverName = snort
```

#### /opt/splunkforwarder/etc/system/local/inputs.conf

Note: The **sourcetype=snort\_alert\_full** is important if you are using the Splunk TA Snort app.

```
[default] host=snort
sourcetype=snort_alert_full index=snort
[monitor:///var/log/snort/alert] sourcetype=snort alert full
```

### /opt/splunkforwarder/etc/system/local/outputs.conf

```
[tcpout]
defaultGroup = splunkssl

[tcpout:splunkssl] server = loghost:9997 compressed = true
sslVerifyServerCert = false
sslRootCAPath = $SPLUNK_HOME/etc/certs/CAServerCert.pem sslCertPath =
$SPLUNK_HOME/etc/certs/snort.lab5.nccoe.gov.pem sslPassword = $1$cw==
```

## 3.9 Tyco Security Products

Tyco Security Products are used to integrate personnel access management into the FS ITAM build. The CCURE 9000 security and event management system allows integration with a variety of intrusion devices, allowing admins to monitor and perform intrusion detection within facilities to stop incidents of malicious activity or violation of policy. For the ITAM build, the focal point of the CCURE 9000 product is personnel and visitor management. The iSTAR Edge Door Controller provides features to secure any door, including clustering, door monitoring, and anti-passback.

## 3.9.1 Installing Tyco Security Products

Tyco Security Products hardware is received with pre-installed software. Hardware components received for this build include the following:

- host laptop
- iSTAR Edge Door Controller
- two badge readers
- three badges
- American Dynamics Video Edge Network Video Recorder (NVR)
- one camera
- NETGEAR ProSAFE switch
- Ethernet cables

Directions for connecting components will be included in the packaging on the iSTAR Edge Installation Reference disc. The host laptop will have the iSTAR Configuration Utility, CCURE 9000, License Manager, KeyCodeGenerator, and Victor Management Software installed and pre-configured. The iSTAR Configuration Utility can be used to confirm IP addresses.

## 3.9.2 Configurations

All components included with Tyco Security Products will be pre-configured. Configuration manuals are documented at the Tyco Security Products website as well as on the iSTAR Edge Installation Reference disc. In addition, the security product suite will be accompanied by a list of all static IP addresses to confirm or correct any configurations. Static IP addresses for the ITAM build are as follows:

laptop (host): 192.168.1.167


NVR: 192.168.1.178camera: 192.168.1.177

iSTAR: 192.168.1.169

The three badges received are configured for the ITAM build. Two badges contain access rights, with a clearance, while one badge does not. Two door readers are configured as door controllers for one door. One reader is configured as the **IN** reader while the second is configured as the **OUT** reader. Badges must have a clearance to be admitted into the door.

Configurations for badges, doors and readers can be viewed and managed using CCURE 9000 software shown in <u>Figure 3-1</u>.

Figure 3-1 CCURE 9000 Overview



The host machine should then be connected to the ITAM network to integrate with the ITAM build. To prepare the host machine for integration with ITAM, SQL Server Management Studio must be installed. For the ITAM build, a query to the journal table is called by Splunk Enterprise to retrieve information, including the Cardholder Name, Door Name, Journal Log Message Type, Message Text and Message Date/Time. The information produced from CCURE is shown in Figure 3-2.

Figure 3-2 CCURE 9000 Messages

C-CURE #000	SWH13 - Personnel Admitted at Doors Report			
<u>Journal</u>				
Cardholder Name	Door Name	Journal Log Message Type	Message Text	Message Date/Time
good, guy	iSTAR Edge NCCoE door 1	Card Admitted	Admitted 'good, guy' (Card: 16053) at 'ISTAR Edge NCCoE door 1' (IN) ([Unused]).	8/20/2015 12:55:14 PM
good, guy	iSTAR Edge NCCoE door 1	Card Admitted	Admitted good, guy' (Card: 16053) at 'ISTAR Edge NCCoE door 1' (OUT) ([Unused]).	8/20/2015 12:55:24 PM
good, guy II	iSTAR Edge NCCoE door 1	Card Admitted	Admitted good, guy II' (Card: 608) at 'ISTAR Edge NCCoE door 1' (IN) ([Unused]).	8/20/2015 12:56:06 PM
good, guy II	iSTAR Edge NCCoE door 1	Card Admitted	Admitted 'good, guy II' (Card: 608) at 'iSTAR Edge NCCoE door 1' (OUT)	8/20/2015 12:56:15 PM

The query ran for Splunk Enterprise to retrieve the information from the journal is as follows:

```
SELECT MessageType, MessageUTC, REPLACE(PrimaryObjectName,',','') AS
PrimaryObjectName, XmlMessage
FROM JournalLog WHERE MessageType='CardAdmitted' OR MessageType='CardRejected'
```

## 3.10 Windows Server Update Services (WSUS)

WSUS is integrated into Windows Server 2012 as a server role. WSUS enables IT administrators to deploy the latest Microsoft product updates to computers that are running the Windows operating system. Using WSUS, an administrator can fully manage the distribution of updates that are released through Microsoft Update to computers in their network.

#### 3.10.1 How It's Used

The ITAM system is using WSUS for its reporting features. WSUS reports on the volume and status of software updates from Microsoft Update. ITAM uses this information to provide insight to administrators for analysis of which Windows machines in the network are not in compliance with the latest vulnerability patches and software updates.

## 3.10.2 Virtual Machine Configuration

The WSUS virtual machine is configured with one network interface card, 8 GB of RAM, one CPU core and 100 GB of hard drive space. The 100 GB of hard drive space is very important for this machine.

## 3.10.3 Network Configuration

The management network interface card is configured as follows:

IPv4 Manual

IPv6 Disabled

■ IP Address: 172.16.0.45

Netmask: 255.255.255.0

Gateway: 172.16.0.11

DNS Servers: 172.16.1.20, 172.16.1.21

Search Domains: lab5.nccoe.gov

## 3.10.4 Installing WSUS

WSUS is installed through the add roles and features wizard in Server Manager. Documentation is provided by Microsoft at: <a href="https://technet.microsoft.com/en-us/windowsserver/bb332157.aspx">https://technet.microsoft.com/en-us/windowsserver/bb332157.aspx</a>. WSUS should NOT be a member of your domain.

## 3.10.5 Configurations

You configure WSUS using the WSUS Server Configuration Wizard. When the wizard prompts you, set these options as follows:

- Update Source and Proxy Server Synchronize form Microsoft Update
- Products and Classifications Microsoft SQL Server 2012, Microsoft SQL Server 2014, SQL
   Server 2008 R2, SQL Server 2008, SQL Server 2012 Product Updates for Setup, SQL server
   Feature Pack, Windows 7, Windows Server 2012 R2 and later drivers, Windows Server 2012 R2
- Update Files and Languages Store update files locally on this server < Download update files to this server only when updates are approved, Download updates only in English
- Synchronization Schedule Automatically > 1 per day
- Automatic Approvals Default
- Computers Use the Update Services console
- Reporting Rollup N/A
- E-mail Notifications N/A
- Personalization N/A

#### 3.10.6 Configure Active Directory Server to Require WSUS

Clients are configured to get their Windows updates and patches through Group Policy on the Active Directory server.

Full documentation can be found at: <a href="https://technet.microsoft.com/en-us/library/Cc720539%28v=WS.10%29.aspx">https://technet.microsoft.com/en-us/library/Cc720539%28v=WS.10%29.aspx</a>.

1. On the Active Directory Server:

#### **Administrative Tools > Group Policy Management**

- 2. Under your domain, create a new group policy object by right-clicking and selecting **Create a GPO** in this domain, and link it here.
- 3. Then right-click the newly created GPO in the Group Policy Objects area of the Group Policy Management window and select **Edit**.

- 4. In the **Group Policy Management Editor** expand **Computer Configuration**, expand **Administrative Templates**, expand **Windows Components**, and then click **Windows Update**.
- 5. In the details pane, select Specify intranet Microsoft update service location.
- 6. Click **ENABLED** and enter the URL of the WSUS server and statistics server (they are the same for this build): http://wsus.lab5.nccoe.gov:8530.

## 3.10.7 Create WSUS Statistics for Splunk Enterprise

When WSUS is running and downloading updates (you can check this by running a report), you can work with assemblies using Windows PowerShell to connect to the WSUS server. With this connection, PowerShell script can be written to extract information from WSUS. The script creates two .CSV files with WSUS information that are forwarded to Splunk Enterprise. The script to accomplish this task is as follows:

1. Filename: WSUSReport.ps1

```
$wsus
$wsusserver = 'wsus'
```

2. Load required assemblies:

```
[reflection.assembly]::LoadWithPartialName("Microsoft.UpdateServices.A
dministration") | Out-Null
$wsus = [Microsoft.UpdateServices.Administration.AdminProxy]::getUpdateServer(
'wsus',$False,8530)
```

3. Create update scope object:

```
$updatescope = New-Object Microsoft.UpdateServices.Administration.UpdateScope
$updatescope.IncludedInstallationStates =
[Microsoft.UpdateServices.Administration.UpdateInstallationStates]::No
tInstalled
$updatescope.FromArrivalDate = [datetime]"12/13/2011"
$computerscope = New-Object
Microsoft.UpdateServices.Administration.ComputerTargetScope
$wsus.GetSummariesPerComputerTarget($updatescope,$computerscope) | Select
@{L='ComputerTarget';E={($wsus.GetComputerTarget([guid]$_.ComputerTargetId)).FullDomainName}},
@{L='NeededCount';E={($_.DownloadedCount+$_.NotInstalledCount)}},DownloadedCount,NotInstalledCount,InstalledCount,FailedCount | Export-Csv
c:\ReportCount.csv
```

```
$wsus.GetUpdateApprovals($updatescope) | Select


@{L='ComputerTargetGroup';E={$_.GetComputerTargetGroup().Name}},

@{L='UpdateTitle';E={($wsus.GetUpdate([guid]$_.UpdateId.UpdateId.Guid)}
).Title}}, GoLiveTime, AdministratorName, Deadline | Export-Csv c:\UpdateStat.csv
```

This script creates two .CSV files and places them on the C drive: ReportCount.csv and UpdateStat.csv. These two files contain the fields ComputerTarget, NeededCount, DownloadedCount, NotInstalledCount, InstalledCount, FailedCount; and ComputerTargetGroup, UpdateTitle, GoLiveTime, AdministratorName and Deadline, respectively.

When the script is running error free, a task is scheduled for the script to run daily for updates to the data. To create a scheduled task, complete the following steps:

- 1. Open Task Scheduler and select **Create Task**.
- 2. Name the task and give it a description. Select **Run whether user is logged on or not**. Select **Run with highest privileges**. Configure for: **Windows Server 2012 R2**.
- 3. Select the **Triggers** tab and select **New**. Create a trigger to run every day at the desired time.
- 4. Select the **Actions** tab and select **New**. Under **Action**, select **Start a Program**. In the Program/script box, enter **c:\Windows\System32\WindowsPowershell\v1.0\powershell.exe** or browse for the PowerShell executable.
- In the arguments box insert -ExecutionPolicy Bypass <locationofscript>. Select OK to save the task.
- 6. Use the defaults for the remaining settings. The scheduled task should look similar to the task highlighted in the following figure.



## 3.10.8 Installing Splunk Universal Forwarder

Note: You will need a Splunk account to download the Splunk Universal Forwarder. It is free and can be set up at: <a href="https://www.splunk.com/page/sign\_up">https://www.splunk.com/page/sign\_up</a>.

- 1. Download the Splunk Universal Forwarder from: <a href="http://www.splunk.com/en\_us/download/uni-versal-forwarder.html">http://www.splunk.com/en\_us/download/uni-versal-forwarder.html</a>.
- 2. You want the latest version for OS version Windows (64-bit). Since this is installing on Windows, select the file that ends in .msi. An example is:

```
splunkforwader-6.2.5-272645-x64-release.msi
```

Detailed installation instructions can be found at:

http://docs.splunk.com/Documentation/Splunk/6.2.3/Forwarding/DeployaWindowsdfmanually #Install the universal forwarder.

## 3.10.9 Configuring Splunk Universal Forwarder

Configuring Splunk Universal Forwarder as shown in the FS-ITAM use case requires X.509 Certificates for the Splunk Enterprise server/indexer and each Splunk Universal Forwarder. You will also need a copy of your certificate authority's public certificate.

If you entered your certificates during install time, they will be located at:

C:\Program Files\SplunkUniversalForwarder\etc\auth

If not, you will need to manually copy your certificates here.

1. Copy Splunk Universal Forwarder configuration files:

```
copy <server.conf> C:\Program Files\SplunkUniversalForwarder\etc\system\local
copy <inputs.conf> C:\Program Files\SplunkUniversalForwarder\etc\system\local
copy <outputs.conf> C:\Program Files\SplunkUniversalForwarder\etc\system\local
```

2. Modify **server.conf** so that:

**ServerName=WSUS** is your hostname.

```
sslKeysfilePassword = <password for your private key>
```

3. Modify **outputs.conf** so that:

**Server = loghost:9997** is your correct Splunk Enterprise server/indexer and port.

```
sslPassword = <password of your certificate private key>
```

Note: This will be hashed and not clear text after a restart.

**Inputs.conf** should work, but you are free to modify it to include the Windows logs that you are interested in.

## 3.10.10 Configurations and Scripts

#### C:\Program Files\SplunkUniversalForwarder\etc\system\local server.conf

```
[sslConfig]
sslKeysfilePassword = $1$sznWu23zCGHY

[general]
pass4SymmKey = $1$5HWC5yi1QzPY serverName = WSUS
[lmpool:auto_generated_pool_forwarder] description = auto_generated_pool_forwarder
quota = MAX
slaves = *
stack id = forwarder
```

```
[lmpool:auto_generated_pool_free] description = auto_generated_pool_free quota = MAX
slaves = * stack_id = free
```

#### C:\Program Files\SplunkUniversalForwarder\etc\system\local\inputs.conf

```
[default] host = WSUS
sourcetype = wsus
index = wsus

[script://$SPLUNK_HOME\bin\scripts\splunk-wmi.path] disabled = 0
[monitor:///C:\ReportCount.csv] sourcetype=wsus_reportcount
crcSalt is needed because this file doesn't change much and is small crcSalt = <SOURCE>
ignoreOlderThan = 2d disabled = 0
[monitor:///C:\UpdateStat.csv] sourcetype=wsus_updatestat ignoreOlderThan = 2d disabled = 0
```

#### C:\Program Files\SplunkUniversalForwarder\etc\system\local\outputs.conf

```
[tcpout]
defaultGroup = default-autolb-group

[tcpout:default-autolb-group] server = loghost:9997

[tcpout-server://loghost:9997] sslCertPath = C:\wsus.lab5.nccoe.gov.pem sslPassword = $1$sznWu23zCGHY

sslRootCAPath = C:\Users\DoD Admin\Downloads\CAServerCert.pem
```

## 4 Tier 3

## 4.1 Active Directory Server

The Active Directory server in the ITAM build uses an NCCoE base 2012 R2 x86\_64 DoD STIG image. The installation of the Windows Active Directory server was performed using installation media provided by DISA. This image was chosen because it is standardized, hardened, and fully documented.

## 4.1.1 Software Configurations

## 4.1.1.1 Windows 2012 Active Directory Server


Active Directory provides centralized management, authentication, security, and information storage for end devices and users in a networked environment.

#### 4.1.2 How It's Used


The Active Directory service is used in the ITAM build to provide authentication, user management and security within a mixed environment with Windows and Linux endpoints.

#### 4.1.3 Installation


1. Go to Server Manager and click Add Roles and Features Wizard.









- 3. Ensure that the appropriate server name is selected. Then, click **Next**.
- 4. Click the checkbox next to **Active Directory Domain Services**. Then click **Next** to advance to the next screen. Then, click **Add Features**.




- 5. Use the features selected by default. Then, click Next.
- 6. In the Active Directory Domain Services screen, click Next.





- 8. When you see the message that the installation was successful, click close.
- 9. Return to the Server Manager and click on the yellow warning message.



- 10. On the Post-deployment Configuration box, click **Promote this server to a domain controller**.
- 11. Choose Add a new forest, specify the root domain name and click Next.
- 12. Use the default settings in the Domain Controller Options page. Ensure that **DNS server** is selected. Enter the **Directory Services Restore Mode** password and click **Next**.
- 13. Choose a NetBIOS domain Name and click Next.

- 14. Accept the default locations for AD DS, DS Database, log files and SYSVOL.
- 15. In the Review Options screen, click Next.
- 16. Allow the system to complete the prerequisites check and click **Install**.
- 17. When the installation completes, reboot the system.

#### 4.2 AssetCentral

AssetCentral is an IT infrastructure management system that stores and displays information related to physical assets including location, make, model, and serial number. AssetCentral can help run an entire data center by monitoring weight, utilization, available space, heat and power distribution. AssetCentral is installed on a CentOS7 system.

#### 4.2.1 How It's Used

In the FS ITAM build AssetCentral is used to provide physical asset location. AssetCentral provides the building, room and rack of an asset.

## 4.2.2 Virtual Machine Configuration

The virtual machine is configured with 1 network interface cards, 4 GB of RAM and 1 CPU cores.

## 4.2.3 Network Configuration

The management network interface card is configured as such:

- IPv4 Manual
- IPv6 Ignore/Disabled

IP Address: 172.16.1.50

Netmask: 255.255.255.0

Gateway: 172.16.1.11

DNS Servers: 172.16.1.20, 172.16.1.21

Search Domains: lab5.nccoe.gov

## 4.2.4 Installing AssetCentral

AssetCentral is installed on a hardened CentOS7 Linux system. AssetCentral requires PHP, Web Server (Apache) and MySQL database to be installed.

Table 4-1 Recommended Versions for AssetCentral – Tier 3

Vendor	Product	Version
RedHat	Enterprise Linux Server	Release 6.4 (Santiago) (x86_64)
Apache	Web Server	httpd-2.2.15-26.el6.x86_64
mysql	Server	5.1.6.6
php		5.3.3 or higher

## 4.2.5 Installing MySQL (MariaDB)

```
# yum -y install mariadb-server mariadb
#systemctl start mariadb.service
#systemctl enable mariadb.service
# mysql secure installation
```

- 1. Answer the questions with the default answers while performing the mysql\_secure\_installation.
- 2. Create a database assetcentral.
- 3. Create a user assetcentral.
- 4. Grant all privileges to assetcentral user.

## 4.2.6 Installing Apache

```
# yum -y install httpd
#systemctl start httpd.service
#systemctl enable httpd.service
#firewall-cmd --permanent --zone=public --add-service=http
#firewall-cmd --permanent --zone=public --add-service=https
#firewall-cmd --reload
```

## 4.2.6.1 HTTP Configuration

- 1. Go to HTTPD root; normally (/etc/httpd).
- 2. Under the modules directory, make sure libphp5.so exists.
- 3. Change documentroot (webroot) as per environment in httpd.conf.

## 4.2.7 Installing PHP5

```
#yum -y install php
#systemctl restart httpd.service
#yum search php
#yum -y install php-mysql
#yum -y install php-gd php-ldap php-odbc php-pear php-xml php-xmlrpc php-mbstring php-snmp php-soap curl curl-devel
```

#### 1. Restart Apache:

```
#systemctl restart httpd.service
```

#### 4.2.8 Post Installation Tasks

- 1. Copy AssetCentral files and folders from previous install to the new webroot.
- 2. Under the location (../assetcentral/application/config) make necessary changes as per environment.

#### 4.2.8.1 Sample

```
<?php defined('ASSET_CENTRAL')ordie(''); define('AC_URL_SUBDIR','/acprod');
define('AC_URL_SCRIPT','/index.php'); define('AC_URL_PARAM','go');
define('AC_URL_PREFIX',AC_URL_SUBDIR . AC_URL_SCRIPT.'?'

. AC_URL_PARAM . '='); define('AC_ERROR_REPORTING',E_ERROR);
//no slash at the end of this url define('URL_SITE','http://10.1.xx.xxx');
define('OS','NIX'); // *NIX WIN BSD MAC
//default database (read) define('DB_TYPE_READ','MYSQL');
define('DB_HOST_READ','127.0.0.1');
//usually leave this blank for MYSQL define('DB_PORT_READ','');
define('DB_USER_READ','assetcentral'); define('DB_PASS_READ','xxxxx');
define('DB_DATA_READ','asset_prod'); define('DB_PREFIX_READ','');</pre>
```

#### 4.3 Email

Email is the email server for the FS-ITAM build.

#### 4.3.1 How It's Used

In the FS ITAM build, Email provides all users with email.

## 4.3.2 Virtual Machine Configuration

The Email virtual machine is configured with one network interface card, 4 GB of RAM and one CPU core.

## 4.3.3 Network Configuration

The management network interface card is configured as follows:

IPv4 Manual

IPv6 Ignore/Disabled

■ IP Address: 172.16.1.50

Netmask: 255.255.255.0

Gateway: 172.16.1.11

DNS Servers: 172.16.1.20, 172.16.1.21

Search Domains: lab5.nccoe.gov

## 4.3.4 Installing Email

Email is installed on a hardened Ubuntu 14.04 Linux system. This email system is using the Postfix email program. Complete installation instructions can be found at:

https://help.ubuntu.com/community/Postfix#Installation.

For Debian/Ubuntu Linux systems: It is always best to make sure your system is up-to-date by performing:

```
sudo apt-get update sudo apt-get upgrade
sudo apt-get install postfix
```

## 4.3.5 Configure Email

From a terminal prompt:

```
sudo dpkg-reconfigure postfix
```

General type of mail configuration: Internet Site

NONE doesn't appear to be requested in current config.

System mail name: mail1.lab5.nccoe.gov

Root and postmaster mail recipient: <admin user name>

Other destinations for mail: email1, email1.lab5.nccoe.gov, localhost.lab5.nccoe.gov, localhost.localdomain, localhost, lab5.nccoe.gov

Force synchronous updates on mail queue? No

Local networks: 172.16.0.0/16

Yes doesn't appear to be requested in current config.

Mailbox size limit (bytes): 0

Local address extension character: +

Internet protocols to use: all

Ensure that /etc/postfix/main.cf looks like the version below in the Configuration Files section (Section 4.3.8). Especially take note that the inet\_interfaces setting. inet\_interfaces = loopback-only will NOT allow mail from other machines.

#### 4.3.6 User Accounts

1. Create an account for each user that needs email:

```
adduser <username>
```

2. Answer the questions.

## 4.3.7 DNS Settings

For mail to work correctly, an MX record must be set up on the DNS server.

The FS-ITAM build is using a Microsoft Server 2012R2 as its DNS server.

1. First set up a DNS A-Record for the email server, which looks like:

```
Host: email1
FQDN: email1.lab5.nccoe.gov IP address: 172.16.1.50
```

- 2. Check next to Update associates pointer record.
- 3. Next create an MX record that looks like:

```
Host or child domain: (same as parent folder)
FQDN: lab5.nccoe.gov
FQDN of mail server: email1.lab5.nccoe.gov
Mail server priority: 10
```

## 4.3.8 Configuration Files

#### /etc/postfix/main.cf

```
# See /usr/share/postfix/main.cf.dist for a commented, more complete version
# Debian specific: Specifying a file name will cause the first
# line of that file to be used as the name. The Debian default
# is /etc/mailname.
#myorigin = /etc/mailname
smtpd banner = $myhostname ESMTP $mail name (Ubuntu) biff = no
# appending .domain is the MUA's job. append dot mydomain = no
# Uncomment the next line to generate "delayed mail" warnings
#delay warning time = 4h readme directory = no
# TLS parameters
smtpd tls cert file = /etc/ssl/certs/smtpd.crt smtpd tls key file =
/etc/ssl/private/smtpd.key smtpd_use_tls=yes
smtpd_tls_session_cache_database = btree:${data_directory}/smtpd_scache
smtp tls session cache database = btree:${data directory}/smtp scache
# See /usr/share/doc/postfix/TLS README.gz in the postfix-doc package for
# information on enabling SSL in the smtp client.
smtpd relay restrictions = permit mynetworks permit sasl authenticated
defer unauth destination
myhostname = mail1.lab5.nccoe.gov alias maps = hash:/etc/aliases alias database =
hash:/etc/aliases
mydestination = email1, email1.lab5.nccoe.gov, localhost.lab5.nccoe.gov,
localhost.localdomain, localhost, lab5.nccoe.gov
relayhost =
```

```
mynetworks = 172.16.0.0/16 127.0.0.0/8 [::ffff:127.0.0.0]/104 [::1]/128
mailbox_size_limit = 0 recipient_delimiter = +
#inet_interfaces = loopback-only inet_interfaces = all default_transport = smtp
relay_transport = smtp

myorigin = /etc/mailname inet_protocols = all home_mailbox = Maildir/ mailbox_command
= smtpd_sasl_local_domain = smtpd_sasl_auth_enable = yes

smtpd_sasl_security_options = noanonymous broken_sasl_auth_clients = yes

smtpd_recipient_restrictions =
permit_sasl_authenticated,permit_mynetworks,reject_unauth_destination

smtp_tls_security_level = may smtpd_tls_security_level = may smtpd_tls_auth_only = no
smtp_tls_note_starttls_offer = yes smtpd_tls_CAfile = /etc/ssl/certs/cacert.pem
smtpd_tls_loglevel = 1 smtpd_tls_received_header = yes smtpd_tls_session_cache_timeout
= 3600s tls random source = dev:/dev/urandom
```

## 4.4 Openswan (VPN)

Openswan is an open-source IPsec VPN. Openswan runs on Linux and supports IKEv1, IKEv2, X.509 Digital Certificates and NAT Traversal.

#### 4.4.1 How It's Used

In the FS ITAM build, Openswan is used to form a secure VPN to the mainframe computer owned by Vanguard Integrity Professionals.

## 4.4.2 Virtual Machine Configuration

The Openswan virtual machine is configured with two network interface cards, 8 GB of RAM and one CPU core.

## 4.4.3 Network Configuration

The management network interface card is configured as follows:

- IPv4 Manual
- IPv6 Ignore/Disabled
- IP Address: 172.16.0.67 (internal interface)
- IP Address: 10.33.5.16 (external interface for the VPN) Netmask: 255.255.255.0
- Gateway: 10.33.5.1
- DNS Servers: 8.8.8.8, 172.16.1.20, 172.16.1.21
- Search Domains: lab5.nccoe.gov

## 4.4.4 Installing Openswan

Openswan is installed on a hardened Ubuntu 14.04 Linux system. Complete installation instructions can be found at https://www.openswan.org/.

## 4.4.5 Installing Openswan

1. For Debian/Ubuntu Linux systems: It is always best to make sure your system is up-to-date by performing:

```
sudo apt-get update sudo apt-get upgrade
sudo apt-get install openswan x12tpd ppp lsof
```

2. Copy the provided configuration files into /etc:

```
cp <ipsec.conf> /etc
cp <ipsec.secrets> /etc
```

- 3. Edit /etc/ipsec.secrets and replace MYSECRET with your pre-shared key.
- 4. Restart Openswan:

```
service ipsec restart
```

5. Verify by running:

```
service ipsec status
```

6. Bring up the IPsec tunnel:

```
ipsec auto -up nccoe-vanguard
```

7. Verify by running:

```
ipsec auto -verbose -status
```

If you see (ISAKMP SA established) then that is good.

A little script was created to keep the connection up - connect\_vanguard.sh.

8. Copy connect vanguard.sh somewhere typical like /usr/local/bin:

```
cp <connect_vanguard.sh> /usr/local/bin chmod 755
/usr/local/bin/connect vanguard.sh
```

9. Have it run every hour by linking it into cron.daily:

```
ln - s /usr/local/bin/connect_vanguard.sh
/etc/cron.daily/connect vanguard
```

## 4.4.6 Configurations and Scripts

# /etc/ipsec.conf # /etc/ipsec.conf - Openswan IPsec configuration file # This file: /usr/share/doc/openswan/ipsec.conf-sample # Manual: ipsec.conf.5 # conforms to second version of ipsec.conf specification # basic configuration config setup # Do not set debug options to debug configuration issues! # plutodebug / klipsdebug = "all", "none" or a combation from below: # "raw crypt parsing emitting control klips pfkey natt x509 dpd private" # eq: # plutodebug="control parsing" # Again: only enable plutodebug or klipsdebug when asked by a developer # enable to get logs per-peer # plutoopts="--perpeerlog" # Enable core dumps (might require system changes, like ulimit -C) # This is required for abrtd to work properly # Note: incorrect SElinux policies might prevent pluto writing the core dumpdir=/var/run/pluto/ # NAT-TRAVERSAL support, see README.NAT-Traversal nat traversal=yes # exclude networks used on server side by adding %v4:!a.b.c.0/24 # It seems that T-Mobile in the US and Rogers/Fido in Canada are

```
# using 25/8 as "private" address space on their 3G network.
# This range has not been announced via BGP (at least upto 2010-12-21)
virtual private=%v4:10.0.0.0/8,%v4:192.168.0.0/16,%v4:172.16.0.0/12,%v
4:25.0.0.0/8,%v6:fd00::/8,%v6:fe80::/10
# OE is now off by default. Uncomment and change to on, to enable. oe=off
# which IPsec stack to use. auto will try netkey, then klips then mast
#protostack=auto protostack=netkey
# Use this to log to a file, or disable logging on embedded systems (like openwrt)
#plutostderrlog=/dev/null
#plutodebug=all plutostderrlog=/var/log/pluto.log nat traversal=yes
oe=off
#myid=172.16.0.66
# Add connections here conn nccoe-vanguard
type=tunnel forceencaps=yes authby=secret
ike=3des-sha1; modp1024 #don't actually need to specify this keyexchange=ike
ikelifetime=22800s phase2=esp
phase2alg=aes256-sha1; modp1024 salifetime=3600s
pfs=yes #vanguard has pfs on auto=start
keyingtries=3
#rekey=no
left=%defaultroute leftnexthop=%defaultroute
leftsubnet=172.16.0.0/24 #NCCoE ITAM lab internal subnet
# either one of these seems to work
#leftid=10.33.5.16 #behind firewall ip address leftid=136.160.255.42 #public ip
address
#leftsourceip=136.160.255.42 leftsourceip=10.33.5.16
```

```
right=174.47.13.99 #IOS outside address
rightid=174.47.13.99
                           #IKE ID send by IOS
#rightsubnet is the internal subnet on the distant end rightsubnet=172.17.212.0/24
#network behind IOS rightnexthop=%defaultroute
/etc/ipsec.secrets
# This file holds shared secrets or RSA private keys for inter-Pluto
# authentication. See ipsec pluto(8) manpage, and HTML documentation.
# RSA private key for this host, authenticating it to any other host
# which knows the public part. Suitable public keys, for ipsec.conf, DNS,
# or configuration of other implementations, can be extracted conveniently
# with "ipsec showhostkey".
# this file is managed with debconf and will contain the automatically created RSA
keys
# The %any %any line is just for testing
# Replace MYSECRET with your pre-shared key
include /var/lib/openswan/ipsec.secrets.inc 172.16.0.67 174.47.13.99 : PSK "MYSECRET"
10.33.5.16 174.47.13.99 : PSK "MYSECRET"
#%any %any : PSK "MYSECRET"
```

#### /usr/local/bin/connect vanguard.sh

#!/bin/sh

#start IPsec tunnel
ipsec auto --up nccoe-vanguard

#status

#ipsec auto --verbose --status

## 4.5 Ubuntu Apt-Cacher

Ubuntu Apt-Cacher is a central repository for update and patch management used by all Ubuntu systems on the network.

#### 4.5.1 How It's Used

In the FS ITAM build, Ubuntu Apt-Cacher provides all Ubuntu systems with patches and updates.

## 4.5.2 Virtual Machine Configuration

The Ubuntu Apt-Cacher virtual machine is configured with one network interface cards, 4 GB of RAM and one CPU core.

## 4.5.3 Network Configuration

The management network interface card is configured as follows:

- IPv4 Manual
- IPv6 Ignore/Disabled

IP Address: 172.16.0.67

Netmask: 255.255.255.0

Gateway: 172.16.0.11

DNS Servers: 172.16.1.20, 172.16.1.21

Search Domains: lab5.nccoe.gov

## 4.5.4 Installing Ubuntu Apt-Cacher

Ubuntu Apt-Cacher is installed on a hardened Ubuntu 14.04 Linux system. Complete installation instructions can be found at: <a href="https://help.ubuntu.com/community/Apt-Cacher-Server">https://help.ubuntu.com/community/Apt-Cacher-Server</a>.

1. For Debian/Ubuntu Linux systems: It is always best to make sure your system is up-to-date by performing:

```
sudo apt-get update sudo apt-get upgrade
sudo apt-get install apt-cacher apache2
```

2. Enable apt-cacher by editing /etc/default/apt-cacher and change autostart to 1.

#### 3. Restart Apache:

```
sudo /etc/init.d/apache2 restart
```

- 4. Verify that things are working by pointing your Web browser to http://<apt-cacher>:3142.
- 5. Edit /etc/apt-cacher/apt-cacher.conf and uncomment the following line: allowed hosts = \*
- 6. Configure as a proxy to APT:

```
sudo nano /etc/apt/apt.conf.d/01proxy
```

7. Inside your new file, add a line that says:

```
Acquire::http::Proxy "http://<IP address or hostname of the apt-cacher server>:3142";
```

8. Restart apt-cacher:

```
sudo /etc/init.d/apt-cacher restart
```

## 4.5.5 Client Configuration

1. Client configuration is the same as setting up the server as a proxy to APT:

```
sudo nano /etc/apt/apt.conf.d/01proxy
```

2. Inside your new file, add a line that says:

```
Acquire::http::Proxy "http://172.16.0.77:3142";
```

## 4.6 Windows 2012 Certificate Authority

The Windows 2012 Certificate Authority server in the ITAM build uses an NCCoE base 2012 R2 x86\_64 DoD STIG image. The installation of the Windows 2012 Certificate Authority server was performed using installation media provided by DISA. This image was chosen because it is standardized, hardened, and fully documented.

## 4.6.1 Software Configurations

Windows 2012 Certificate Authority (CA) server was designed to issue certificates to endpoints that need to be accessed by users such that communication to such devices are deemed secure. It is used in building a PKI system.

#### 4.6.2 How It's Used

The ITAM solution uses the Windows 2012 CA server to issue certificates to endpoints that have services that need to be accessed securely such as HTTPS enabled devices. The pfSense routers utilized these

certificates allowing for secure communication and configuration. The certificates are also utilized by Splunk Enterprise and the Splunk Universal Forwarder.

#### 4.6.2.1 INSTALL ACTIVE DIRECTORY CERTIFICATE SERVICES (AD CS)

- 1. Go to Server Manager and click Add Roles and Features Wizard.
- 2. Click Next. Select Role-based or feature-based installation. Click Next.
- 3. Select your server on the next screen and click **Next**.
- 4. Select the Active Directory Certificate Services and Add Features when prompted.
- 5. Click **Next** when you see .NET 4.5 framework and other default selections.
- Click Next on informational screens.
- 7. On the Role Services for AD CS, select all checkboxes and click Next.
- 8. When you are prompted to install the IIS web service, click **Install**.
- 9. Click **Close** when the installation completes.

#### 4.6.2.2 CONFIGURE AD CS SERVICES PART 1

- 1. Go back to **Server Manager** and click on the warning icon.
- 2. Click on Configure Active Directory Certificate Services. Click Next.
- 3. On the Role Services to configure screen, select Certification Authority, Certification Authority Web Enrollment.
- 4. Choose **Enterprise CA**. On the following screen click **Next**.
- 5. Choose Root CA and click Next.
- 6. Choose Create a new private key and click Next.
- 7. Leave the defaults on the Specify the cryptographic options screen and click Next.
- 8. Specify the CA common name and click **Next**.
- 9. Use the default selection: Specify a validity period at the default of 5 years for the certificates generated by this CA.
- 10. Leave the database locations at default and click Next.
- 11. Click **Configure** to initiate configuration of the selected roles.

- 12. Click **Close** when the configurations succeed.
- 13. Click **No** if a **Configure additional role services** pop up is presented.

#### 4.6.2.3 CONFIGURE AD CS PART 2

- 1. Go back to **Server Manager** and click on the yellow warning sign.
- 2. Click on Configure AD CS on the destination server.
- 3. Specify a user with credentials to configure role services. The user must be part of the **Enter- prise Admins** group.
- 4. Select the other checkboxes and click Next.
- 5. Select a domain account with the specified permissions.
- 6. Accept the default RA name and click Next.
- 7. Accept the default Cryptographic options cryptographic service providers and key lengths and click **Next**.
- 8. Select the default CA name as the name to be used for **Certificate Enrollment Services**.
- 9. Specify the same service account for to be used for Certificate Enrollment Web Service.
- 10. Choose the available Server Certificate and click Next. Click Configure; then, click Close.

#### 4.6.2.4 CONFIGURE A CERTIFICATE AND PUBLISH TO ACTIVE DIRECTORY

- 1. Open the Certification Authority tool from Server Manager.
- 2. Right-click Certificate Templates.
- 3. Click Manage.
- 4. Right-click Any template and click **Duplicate**.
- 5. Give it a distinct name/Template Display name.
- 6. Click the **Subject Name** tab and select **Common Name** from the subject name format dropdown list.
- 7. Click **Apply**, click **OK** and then close the dialog box.
- 8. Go back to the Certification Authority tool and right-click Certificate Templates.
- 9. Select the certificate you just created and click on **Properties**.

- 10. On the **General** tab, click on **Publish to Active Directory**.
- 11. Click on the **Security** tab, select **Domain Computers** and check the **Read**, **Enroll** and **Autoenroll** boxes.
- 12. Click Apply and then OK to close the dialog box.

#### 4.6.2.5 CONFIGURE GROUP POLICY TO AUTO-ENROLL DOMAIN COMPUTERS

- 1. Log on to the domain controller.
- 2. Go to Group Policy Management Tool via Server Manager.
- 3. Expand the forest, then expand the domain.
- 4. Right-click on **Default Domain Policy** and click **Edit**.
- 5. Click Computer Configuration, Policies, Windows Settings, Security Settings, Public Key Policies and open Certificates Services Client Auto-Enrollment policy.
- 6. Choose **Enabled** from the Configuration Model box, check Renew Expired certificates, update pending certificates, and remove revoked certificates.
- 7. Also check Update certificates that use certificate templates.
- 8. Click Apply; then, click OK.
- 9. Click Computer Configuration, Policies, Windows Settings, Security Settings, and Public Key Policies.
- 10. Right-click Certificate Services Client Certificate Enrollment Policy, click Properties.
- 11. Choose **Enabled** from the **Configuration Model** drop down list.
- 12. Ensure that Active Directory Enrollment Policy is checked.
- 13. Check Properties of Active Directory Enrollment Policy and ensure that the **Enable for automatic enrollment and renewal** and the **Require strong validation during enrollment** boxes are checked.
- 14. Click **Apply** and then **OK** to close the dialog boxes.

#### 4.6.3 Certificate Generation and Issuance

This ITAM solution had a mix of endpoints which included Windows and Linux hosts including some pfSense routers. Some of these devices pfSense routers had HTTPS enabled. The PKI implementation was extended to further secure these HTTPS services. The overall process includes the following steps:

- 1. Generate a certificate signing request (CSR).
- 2. Copy the CSR over to the Windows Certificate Authority (CA).
- 3. Submit the CSR to the CA service.
- 4. Sign the CSR and copying the issued certificate along with the CA certificate to the device.
- 5. Generate a Certificate Signing Request.
- 6. Open the terminal in a Linux computer with OpenSSL and run openssl req -new -newkey rsa:2048 -nodes -keyout server.key -out server.csr

where server.key and server.csr represent arbitrary names you have chosen. The common name field should be the FQDN of the endpoint.

This will generate two files: the private key file and a CSR file.

- 7. Copy the CSR file.
  - a. Use any of the file transfer utilities such as SCP or FTP to copy the CSR to the CA.
  - b. Alternatively, the CSR can be copied via USB or other means.
- 8. Submit the Certificate Signing Request to the CA Service.
  - a. Log on to the CA server, go to the command prompt and type Certreq.exe -attrib "CertificateTemplate:<Nameofthetemplate>" -submit <pathtoCSR>
  - b. An example of what could be typed is certreq.exe -attrib "CertificateTem-plate:WebServer" -submit D:\requestfile.txt
- 9. Sign the CSR and copy the Certificates to the device.
  - a. To sign the CSR, go to the Windows CA server and perform the following steps:
    - i. Click Start > Control Panel > Administrative Tools > Certification Authority.
    - ii. Expand the **CA name** and click **Pending Requests**.
    - iii. Right-click the CSR on the right pane showing a request **ID number** > **Click All Tasks** > **Click Issue**.

- b. Run certutil -ca.cert ca\_name.cer from the command prompt where ca\_name.cer is the arbitrary file name for the CA certificate.
- 10. Copy the client certificate and CA certificate to client system.
- 11. Make the application aware of the location of these certificates. Once logged in, the pfSense routers in the ITAM build provide links to copy and paste the contents of the private key, the certificate file and the CA server certificate.

#### 4.7 Common PKI Activities

This section provides instructions for common PKI activities using a Microsoft Certificate Authority (CA) in a heterogeneous environment.

## 4.7.1 Generating a Certificate Signing Request from OpenSSL

1. Run:

```
openss1 req -new -newkey rsa:2048 -nodes -keyout serverFQDN.key -out serverFQDN.csr
```

where serverFQDN.key is the private key file and the serverFQDN.csr is the certificate signing request file. The files can be arbitrarily named.

2. When prompted, ensure that the common name field is set to the server FQDN.

A Certificate Signing Request (CSR) can be generated for as many servers as you need in your enterprise.

3. Copy the CSR file to the Certificate Authority (CA) server for signing.

## 4.7.2 Submitting the CSR to the CA Service

- 1. Log on to the CA server.
- 2. Go to the command prompt and type:

```
Certreq.exe -attrib "CertificateTemplate:<Nameofthetemplate>" -submit
<pathtoCSR>
```

An example command could be:

certreq.exe -attrib "CertificateTemplate:WebServer" -submit D:\serverFQDN.key

## 4.7.3 Exporting a Root Certificate from a Microsoft CA

1. From the command prompt run:

```
Certutil -ca.cert new_ca_filename.cer

where new ca_filename.cer is the arbitrary file name for the exported CA certificate.
```

The exported CA certificate would need to be copied over to the other servers that would be included in Public Key Infrastructure.

The Microsoft Windows CA root certificate would be in Distinguished Encoding Rules (DER) encoded format. Some platforms, especially Linux platforms, may prefer PEM encoding and conversion to Privacy Enhanced Mail (PEM) encoding might be necessary.

## 4.7.4 Converting from DER Encoding to PEM Encoding

1. Run:

openssl x509 -in DER\_CA\_CERT.crt -inform der -outformpem -out PEM\_CA\_CERT.pem where DER\_CA\_CERT.crt is DER encoded and PEM\_CA\_CERT is the transformed PEM encoded certificate.

Additional information on converting certificates can be found at the following link http://info.ssl.com/article.aspx?id=12149.

## 4.8 Process Improvement Achievers (PIA) Security Evaluation

Process Improvement Achievers (PIA) conducted a remote security evaluation of the FS ITAM build. The evaluation consisted of running multiple tools against the machines in the lab to find any vulnerabilities due to misconfiguration.

## **Appendix A** List of Acronyms

AD Active Directory

**CA** CA Technologies

**CA** Certificate Authority

**COTS** Commercial Off-The-Shelf

**CRADA** Collaborative Research and Development Agreement

**CSR** Certificate Signing Request

.csv Comma-Separated Value

**DER** Distinguished Encoding Rules

**DMZ** Demilitarized Zone

**FS** Financial Sector

HR Human Resources

**ID** Identity

**ITAM** Information Technology Asset Management

**IDS** Intrusion Detection System

IP Internet Protocol

NAS Network Attached Storage

NCCoE National Cybersecurity Center of Excellence

NIST National Institute of Standards and Technology

**OS** Operating System

PEM Privacy Enhanced Mail

PKI Public Key Infrastructure

**SME** Subject Matter Expert

**SQL** Structured Query Language

**SSL** Secure Socket Layer

**STIG** Security Technical Implementation Guideline

**TLS** Transport Layer Security

**VLAN** Virtual Local Area Network

VM Virtual Machine

**VPN** Virtual Private Network