# The openMMF library: an open source software for multimode driven quantum systems

# User manual V0.5

# September 15, 2020.

# Contents

1	now to build the library and compile the examples	4		
2	What does the library calculate and how?	3		
3	Use of the library 3.1 Declaration of the Hamiltonian 3.2 Hamiltonian components			
4	Typical performance	6		
5	$ \begin{array}{cccccccccccccccccccccccccccccccccccc$			
6	List of examples           6.1 Python            6.2 C++.            6.3 Fortran	8 9 9		
7	C++ wrappers			
8	Python wrappers			
9	Bugs and known limitations	11		
10	Acknowledgements	11		
11	MODULES 11.1 Physical Constants 11.2 Arrays 11.3 Atomic properties 11.4 MKL	13 14		
<b>12</b>	2 DERIVED TYPES (src/modes.f90)	17		
13	COMPUTATIONAL SUBROUTINES	18		
	DRIVER SUBROUTINES  14.1 Utility subroutines	<b>2</b> 4		

# 1 How to build the library and compile the examples

The openMMF source code includes a Makefilefile for compiling and building the library. The user must ensure that make.inc sets correctly the system's path to the LAPACK and (optionally) the MKL-intel libraries and linking/compiling options.

When the paths are set correctly, compiling the library requires invoking a single make command, which will build the library. To indicate whether the MKL library can be used, the user should indicate so in make.inc. The make builing options are:

- make: Compiles the library and selected Fortran and C++ examples
- make lib: compiles the library including support for sparse matrices. This option requires the LAPACK and MKL-intel libraries.
- make lib\_lapack: compiles the library without support for sparse matrices. This option requires LAPACK.
- make Examples\_lib: compiles examples under the folder examples/FORTRAN, which uses LAPACK
- make Examples\_lib\_sp: compiles examples under the folder examples/FORTRAN, which uses the MKL library
- make Examples\_lib\_c: compiles examples under the folder examples/CPP, which uses LAPACK
- make Examples\_lib\_c\_sp: compiles examples under the folder examples/CPP, which uses the MKL library
- make : run the options lib and all\_examples.

All options of the make command produces static and dynamical libraries libopenmmf.a and libopenmmf.so in the folder ~/lib. A number of .mod files produced with the building process are moved to the folder ~/include and they are required for running the application.

The examples that only require the support of the LAPACK library are compiled with:

```
gfortran -o out SourceCode.f90 -I$(INCLUDE_OPENMMF) -L$(LIB_OPENMMF) -lopenmmf $(GFFLAGS)
g++ -o out SourceCode.cpp -I$(INCLUDE_OPENMMF) -L$(LIB_OPENMMF) -lopenmmf -lgfortran $(GFFLAGS)
while code that requires support from the MKL library is compiled by:

gfortran -o out SourceCode.f90 -I$(INCLUDE_OPENMMF) -L$(LIB_OPENMMF) -lopenmmf
-L$(MKLLIBS) -I$(MKLLINC) $(MKLFLAGS)
g++ -o out SourceCode.cpp -I$(INCLUDE_OPENMMF) -L$(LIB_OPENMMF) -lopenmmf -lgfortran
```

-L\$(MKLLIBS) -I\$(MKLINC) \$(MKLFLAGS)

The variables MKLLIBS, MKLINC, GFFLAGS, and MKLFLAGS are defined in the file Makefile. The environmental variables INCLUDE\_OPENMMF and LIB\_OPENMMF indicate the paths to the include and library directories of the openMMF library. Compilation of C++ source code follows the same formula, using the additional flag -lgfortran and the corresponding compiler g++. For an explicit example of usage in this case see the building script under examples/CPP/Makefile.

When running applications, the environmental variable LD\_LIBRARY\_PATH must indicate the path to such a library, which can be done with the shell command:

```
export LD_LIBRARY_PATH="/opt/intel/compilers_and_libraries/linux/mkl/lib/intel64:./lib" which assumes default folder location of the MKL library and that libopenmmf is located in ./lib.
```

# 2 What does the library calculate and how?

The library can be used to calculate the time-evolution operator, U(t',t), t' > t, of systems whose Hamiltonian has the form:

$$H = \sum_{i,j}^{D} E_{i,j} |i\rangle \langle j| + \sum_{i,j}^{D} \sum_{\ell=1}^{N} \sum_{n \in \mathbb{Z}} V_{i,j}^{\ell,n} e^{in\omega_{\ell}t} |i\rangle \langle j| + \text{h.c.}$$

$$\tag{1}$$

where D is the dimension of the Hilbert space,  $E_{i,j}$  defines a static component of H,  $V_{i,j}^{\ell,n}$  is the coupling between the states i and j oscillating at frequency  $n\omega_{\ell}$  (i.e. the n-th harmonic of the  $\ell$ -th fundamental frequency  $\omega_{\ell}$ ) and N is the number of incommensurate frequencies.

To calculate the time-evolution operator we generalise the Rotating (or Resonant) Wave Approximation (RWA), taking into account the complex time dependence of Eq. (1). For this, we rephrase the problem in terms of building a time-dependent unitary transformation,  $U_F(t)$  to a new basis  $\{|\bar{i}\rangle\}$ , that leads to a time-independent and diagonal Hamiltonian,  $\bar{H}$ . The operator  $U_F(t)$  is called the micromotion operator and the new basis is a generalised multimode definition of the dressed basis. After applying the standard quantum-mechanical transformation rule to the Schrödinger equation [1, 2], this condition becomes:

$$U_F^{\dagger}(t) \left[ H(t) - i\hbar \partial_t \right] U_F(t) = \sum_{\bar{i}} \bar{E}_{\bar{i}} \left| \bar{i} \right\rangle \left\langle \bar{i} \right| \tag{2}$$

where  $\bar{E}_{\bar{i}}$  is the eigen-energy of the dressed state  $|\bar{i}\rangle$ , which is an eigenstate of the static Hamiltonian  $\bar{H}$ .

Importantly, in the basis of states defined by this transformation the time evolution operator is diagonal and has the form:

$$\bar{U}(t',t) = \sum_{\bar{i}} e^{-i\bar{E}_{\bar{i}}(t'-t)} |\bar{i}\rangle \langle \bar{i}|$$
(3)

which let us to calculate the time evolution operator in the original basis  $\{|i\rangle\}$ , just by inverting the transformation  $U_F(t)$ , according to [2]:

$$U(t',t) = U_F(t')\bar{U}(t',t)U_F(t) \tag{4}$$

To formulate a fully defined computational problem, we express the unitary transformation  $U_F(t)$  as the multifrequency Fourier series [3]:

$$U_F(t) = \sum_{\vec{n}} U_{i,\vec{i}}^{\vec{n}} e^{-i\vec{\omega}\cdot\vec{n}t} |i\rangle \langle \vec{i}|$$
 (5)

where  $\vec{\omega} = (\omega_1, \omega_2, \dots, \omega_N)$  and  $\vec{n}$  is a N-dimensional vector of integers. After plugging this expansion in Eq. (2) and performing an integral over time, we obtain a fully defined eigenproblem for the eigenvalues  $\bar{E}_{\bar{i}}$  and Fourier components of the unitary transformation  $U_{i\bar{E}}^{\vec{n}}$ :

$$\sum_{j} (E_{i,j} - \hbar \vec{n} \cdot \vec{\omega}) U_{j,\bar{i}}^{\vec{n}} + \sum_{j} \sum_{\vec{m}} \left[ V_{i,j}^{\vec{m}} U_{j,\bar{i}}^{\vec{n}+\vec{m}} + V_{ji}^{\vec{m}*} U_{j,\bar{i}}^{\vec{m}-\vec{n}} \right] = \bar{E}_{\bar{i}} U_{i,\bar{i}}^{\vec{n}}$$
(6)

where  $\vec{n}_{\ell,m} = \vec{n} + mP_{\ell}$  with  $P_{\ell} = (0, \dots, 1, \dots, 0)$  the projector at the  $\ell$ -th position. To obtain a finite matrix representation of this problem we truncate the sum over the number of modes of the Fourier expansion Eq. (5).

This formulation to calculate the time-evolution operator is equivalent to the multimode Floquet representation of the Hamiltonian that introduces an extended Hilbert space  $|E_i, \vec{n}\rangle$  [3, 4]. However, the semiclassical description presented here makes emphasis in the physically accessible states.

# 3 Use of the library

Here we illustrate the use of the library's functionality considering a qubit driven by two harmonic forces. The Hamiltonian of this system has the form:

$$H = \hbar\omega_0 S_z + \hbar\Omega_1 \cos(\omega_1 t) S_x + \hbar\Omega_{2,x} \cos(\omega_2 t) S_x + \hbar\Omega_{2,y} \cos(\omega_2 t) S_z$$
 (7)

The Fortran and C++ source codes to find the time-evolution operator are in the files:

- ullet examples/FORTRAN/main\_DressedQubit.f90 .
- examples/CPP/main\_dressedqubit.cpp .

### 3.1 Declaration of the Hamiltonian

First of all, we should declare the two derived types:

```
TYPE(ATOM) ID
TYPE(MODE), DIMENSION(:), ALLOCATABLE :: FIELDS
```

The variable ID contains information about the type of system, such as the number of levels and their energy spectrum (see the declaration of TYPE(ATOM) in Section 12). The derived type FIELDS stores information required to build the components of the Hamiltonian as well as the explicit matrix representation of the couplings.

In this concrete example, the components of ID are initialised by calling the subroutine:

```
CALL FLOQUETINIT(ID, 'qubit', INFO)
```

The second argument indicates the type of system (here 'qubit'), which, is sufficient to initialise the variable TD:

```
ID%id_system = 1
ID%D_BARE = 2
```

where ID%D\_BARE indicates the dimension of the Hilbert space.

Additional options of the function FLOQUETINIT are presented in section 5, which are useful for initialising some frequently used physical systems with default parameters. When dealing with a general quantum system (i.e. with an arbitrary energy spectrum), there is no need to call this function and the values of a variable of TYPE(ATOM) must be initialised explicitly.

In the source code, the next relevant instruction is the definition of an integer vector that provides information about the number of driving frequencies. The integer array MODES\_NUM is allocated with size 3, indicating that the system will be driven by two fundamental frequencies (corresponding to  $\ell=1,2$  in Eq. 1), since the first component is reserved to the static part of the Hamiltonian. The values of the elements of this array indicate the number of driving harmonics of each frequency, which here we set to 1 (making n=1 in Eq. 1).

The total number of driving frequencies is equal to the sum of all elements of the array MODES\_NUM. The user then should allocate sufficient memory space to store each one of the matrix representations of the couplings  $V^{\ell,n}$ . This is done with the sequence of instructions:

```
TOTAL_FREQUENCIES = SUM(MODES_NUM,1)
ALLOCATE(FIELDS(TOTAL_FREQUENCIES))
DO m=1,TOTAL_FREQUENCIES
   ALLOCATE(FIELDS(m)%V(ID%D_BARE,ID%D_BARE))
END DO
```

By default the first element of the array of FIELDS is reserved for the static component of the Hamiltonian, which includes the spectrum of the static system as diagonal elements of the matrix FILEDS(1)%V. The next step then consist in defining all components of the Hamiltonian. For a quantum system with arbitrary energy spectrum, each one of the matrices FIELDS(m)%V must be declared explicitly.

When dealing with spin systems, as in the present example, each component of the Hamiltonian can be written as:

$$V^{\ell,n} = e^{\phi_x} X S_x + e^{\phi_y} Y S_y + e^{\phi_z} Z S_z \tag{8}$$

where  $S_i$  is the angular momentum operator. Therefore, we need only six parameters (three phases and three amplitudes) to define the coupling matrices.

These six parameters should be declared explicitly for each one of the the driving modes, along with the frequency ( omega ) and the corresponding number of modes to be included in the Fourier expansion of the evolution operator (N\_Floquet). The values of these parameters are initialised as follows:

Source code	Parameter in Eq. (8)
FIELDS(1)%X=0.0	X
FIELDS(1)%Y=0.0	Y
FIELDS(1)%Z=1.0	Z
FIELDS(1)%phi_x=0.0	$\phi_z$
FIELDS(1)%phi_y=0.0	$\phi_z$
FIELDS(1)%phi_z=0.0	$\phi_z$
FIELDS(1)%omega=0.0	$\omega$
$   \texttt{FIELDS(1)\%N\_Floquet} = 0 $	N

where we have a direct correspondence with Eq. (8). This set of instructions is repeated for each one of the driving fields, as can be seen in the source code.

### 3.2 Hamiltonian components

The instructions detailed before let us to build the matrix representation of the terms in Eq. (8). This is done simply by calling the subroutine:

```
CALL SETHAMILTONIANCOMPONENTS(ID, size(modes_num, 1), total_frequencies, MODES_NUM, FIELDS, INFO)
```

which results in storing the coupling  $V^{\ell,n}$  in the set of matrices FIELDS(r)%V, with r=1,total\_frequencies. We remind the user that when the system of interest is not one of the default types defined in section 3.1, the user must define explicitly and in full all the coupling matrices. For an example of this situation, see the source file example/FORTRAN/main\_lattice.f90.

### 3.3 Multimode Floquet matrix and diagonalisation

Once the components of the Hamiltonian are defined (i.e the complete set of matrices FIELDS(r)%V has been initialised), the multimode Hamiltonian can be calculated calling the function:

```
CALL MULTIMODEFLOQUETMATRIX(ID, size (modes_num, 1), total_frequencies, MODES_NUM, FIELDS, INFO)
```

As a result of this call, the system stores the full multimode Floquet matrix on the left-hand side of Eq. (6) in the matrix H\_FLOQUET. This matrix is defined in the module ARRAYS and can be accessed (and modified!) by all computational routines that include this module. The size of this matrix is calculated internally and stored in the parameter h\_floquet\_size, which is also a global variable.

The library includes a subroutine to evaluate a sparse representation of this matrix, which results after invoking:

```
CALL MULTIMODEFLOQUETMATRIX_SP(ID,SIZE(MODES_NUM,1),total_frequencies, MODES_NUM,FIELDS,VALUES,ROW_INDEX,COLUMN,INFO)
```

Setting INFO = 0, this instruction produces the representation of the Floquet matrix H\_FLOQUET in the three array variation of the Compressed Sparse Row (CSR) storage format. With INFO=6, we get the matrix stored as three arrays of equal length, corresponding to values, rows and columns positions. The non-zero values of the matrix are stored in the complex array VALUES, and the information about their location is encoded in the integer arrays COLUMN and ROW\_INDEX. The size of these three arrays are evaluated internally.

The library includes wrappers to diagonalisation subroutines from the Lapack and the MKL-intel (for the sparse CSR representation) libraries. These functions are called using:

Lapack:

```
CALL LAPACK_FULLEIGENVALUES(U_F,SIZE(H_FLOQUET,1),E_FLOQUET,INFO)
```

MKL:

```
CALL MKLSPARSE_FULLEIGENVALUES(D_MULTIFLOQUET,SIZE(VALUES,1),VALUES,ROW_INDEX,

COLUMN,E_L,E_R,E_FLOQUET,U_F,INFO)
```

In both cases, the eigenvalues are stored in the array  $E_FLOQUET$  and the eigenvectors are stored as columns of the matrix  $U_F$ . Remember that these eigenvectors correspond to the coefficients of the multimode Fourier decomposition of the micromotion operator Eq. (5). Invoking the MKL subroutine requires two additional parameter  $E_L$  and  $E_R$ : the lower and upper bounds of the interval to be searched for eigenvalues, respectively. The user is responsible to set meaningful values of both parameters.

The MKL sparse solvers requires the use of the variation of the Compressed sparse row (CSR) representation of the matrix, which is produced by sorting the array of ROW position, in such a way that all non-zero values of a given row become stored consecutively. This sorting is done using a QUICK\_SORT algorithm by Robert Renka (OAK Ridge Natl. Lab, US) accessible from the Alan Miller's Fortran Software website [5]. Alternatively, calling the function MULTIMODEFLOQUETMATRIX\_SP with the variable INFO=6, the user obtains the extended Hamiltonian represented by the three arrays of value,column,row, which can be used with a different eigenvalue solver for sparse matrices.

### 3.4 Time-evolution operator

With the full spectrum of H\_FLOQUET, the time evolution operator between T1 and T2, corresponding to Eq. (4), can be evaluated calling the function:

```
CALL MULTIMODETIMEEVOLUTINOPERATOR(SIZE(U_F,1),SIZE(MODES_NUM,1),MODES_NUM,U_F,E_FLOQUET, ID%D_BARE,FIELDS,T1,T2,U_AUX,INFO)
```

which produces the matrix representation of the operator in Eq. (4). The time evolution operator is stored in the complex matrix U\_AUX, whose size is equal to the number of bare states ID%D\_BARE.

### 3.5 Micromotion operator

The micromotion operator is the time-dependent unitary transformation between the basis and the basis of state where the Hamiltonian is time-independent. Since we know the Fourier decomposition of this transformation via the diagonalisation of H\_FLOQUET, we can evaluate the instantaneous transformation, e.g. at time T1, using the subroutine:

```
CALL MULTIMODEMICROMOTION(ID,SIZE(U_F,1),NM,MODES_NUM,U_F,E_FLOQUET,ID%D_BARE, FIELDS_,T1,U_F1,INFO)
```

which produces the matrix representation of the operator in Eq. (5). This micromotion operator is stored in the square matrix U\_F1 of size ID%D\_BARE.

# 3.6 Identifying the dressing modes

In several applications is useful to define a dressed basis of states and the openMMF library includes functions to simplify the evaluation of the evolution operator in this basis. For this, first the user should identify the subset of driving fields that define the dressed states. This is done using an integer array with as a many components as dressing fields. The elements of this array indicate the indices of the fields corresponding to the array modes\_num. For example, if there is only one dressing field and it corresponds to the second component of the array MODES\_NUM, then the array that indicates the dressing field, DRESSINFIELDS\_INDICES, must be:

```
INTEGER, DIMENSION(2) :: DRESSINGFIELDS_INDICES

DRESSINGFIELDS_INDICES(1) = 1 ! THE STATIC COMPONEN

DRESSINGFIELDS_INDICES(2) = 2 ! THE FIRST DRIVING FIELD, WHICH DRESSES THE SYSTEM
```

With this, the Fourier decomposition of the micromotion operator defining the dressed basis in Eq. (5), can be obtained simply by calling the function:

```
CALL MICROMOTIONFOURIERDRESSEDBASIS(ID, DRESSINGFIELDS_INDICES, MODES_NUM, FIELDS, U_FD, E_DRESSED, INFO)
```

The Fourier components  $U_{i,\bar{i}}^{\bar{n}}$  are stored in the matrix U\_FD and the spectrum of dressed energies,  $\bar{E}_{\bar{i}}$ , are stored in the array E\_DRESSED. With these two elements, we can calculate the micromotion operator of the dressed basis using the subroutine:

```
CALL MICROMOTIONDRESSEDBASIS(ID, MODES_NUM, DRESSINGFIELDS_INDICES, FIELDS, U_FD, E_DRESSED, T1, U_FD_1, INFO)
```

The micromotion operator at T1 is then stored as the square matrix U\_FD\_1. This set of instructions let us to evaluate the time-evolution operator in the dressed basis using the sequence:

# 4 Typical performance

The efficiency of the library is limited by the capability to solve the eigenvalue problem of the multimode Floquet Hamiltonian. Fig. ??(a) compares the execution times for a single diagonalisation of the Floquet HamiltonianBosonic and Fermionic Hubbard models, as functions of the size of the matrix (red and blue data/lines). The source codes can be found in examples/FORTRAN/MANYBODYHUBBARD/ and the model Hamiltonian are:

$$H_{Bosons}(t) = (t + \Delta t \cos(\omega t + \phi)) \sum_{\langle i,j \rangle} b_i b_j^{\dagger} + \frac{u}{2} \sum_j n_j (n_j - 1)$$

$$H_{Fermions}(t) = (t + \Delta t \cos(\omega t + \phi)) \sum_{\substack{i \text{o} \\ 6}} (f_{i,\sigma} f_{i+1,\sigma}^{\dagger} + f_{i+1,\sigma}^{\dagger} f_{i,\sigma}) + u \sum_j n_{j,\uparrow} n_{j,\downarrow}$$

and we use the parameters  $t=1, u=0.5, \phi=0.0, \omega=1.0, \Delta t=0.2$ . To vary the size of the Floquet Hamiltonian we increase the number of Floquet manifolds.

For these tests, the library performs two tasks: evaluates the Floquet Hamiltonian and use LAPACK to obtain the spectrum (only once for each matrix size). The Hamiltonian corresponds to a periodically driven Hubbard model (with near-neighbour tunnelling and on-site interaction) and the matrix dimension is given by the number of Floquet manifolds.

Figure ??(b) shows the execution time required to evaluate a single time-step of the time-evolution operator of driven qubit with a noisy background. The Hamiltonian of this system is:

$$H = \hbar\omega_0 S_z + \hbar\Omega S_x \cos(\omega t + \phi) + \sum_{\ell} \Delta_i \cos(\ell\omega/Nt + \phi_i)$$
(9)

with N the number of frequencies contributing to the noisy field,  $\Delta_i$  and  $\phi_i$  random amplitudes and phases, respectively. With this, the noise frequency is limited up to the driving frequency  $\omega$ . The matrix size reflects the number of components of the noisy driving.

In this case we use a DRIVER subroutine and build a sparse representation of the multimode Hamiltonian. In contrast to the previous test, we observe that the matrix building and diagonalisation take about the same fraction of the total time. However, a direct comparison of the total times between these two examples is not straightforward since the structure of the Floquet matrix of the two problems is significantly different.

These results give us a rough idea of the scaling of the execution time with the matrix size, as well as the possible performance bottlenecks. These tests were performed using a DELL XPS with an Intel Core i7 vPro @ 2.7 GHz and 8GB of RAM. The machine runs on Linux Mint 17.2 Rafaela, with gcc-4.9.4

#### 5 Default system types

The openMMF library defines three different system types by default. These are Qubit, Spin and the ground state of several alkali atoms. A general system with D energy leveles can be defined using the "spin" type and setting by hand all coupling matrices.

#### 5.1Qubit

This type represents a two level system, where the couplings with the oscillating field are of the form

$$V^{\ell,n} = X S_x e^{\phi_{\ell,x}} + Y S_y e^{\phi_{\ell,y}} + Y S_z e^{\phi_{\ell,z}}$$
(10)

with  $S_i$ ,  $i \in x, y, z$  the set of spin 1/2 angular momentum operators with  $\hbar := 1$ .

The corresponding derived type is initialised with the instruction:

FLOQUET\_INIT(ID, 'qubit', INFO)

# Spin of total angular momentum $S_z$

This type represents a system with  $2S_z + 1$  equally space energy levels, where the couplings with oscillating fields are of the form:

$$V^{\ell,n} = X S_x e^{\phi_{\ell,x}} + Y S_y e^{\phi_{\ell,y}} + Y S_z e^{\phi_{\ell,z}}$$

$$\tag{11}$$

with  $S_i$ ,  $i \in x, y, z$  the set of angular momentum operators with total spin  $S_z$ .

The corresponding derived type is initialised with the instruction:

FLOQUET\_INIT(ID, 'spin', 2\*Sz, INFO)

where the third argument is a DOUBLEPRECISION variable equal to the double of the projection of the total angular momentum.

The matrix representation of the angular momentum operators  $s_i$  is build using [6]:

$$\langle S, m' | S_x | S, m \rangle = \frac{1}{2} \left[ \sqrt{(S-m)(S+m+1)} \delta_{m,m'+1} + \sqrt{(S+m)(S-m+1)} \delta_{m,m'-1} \right]$$

$$\langle S, m' | S_y | S, m \rangle = \frac{i}{2} \left[ \sqrt{(S-m)(S+m+1)} \delta_{m,m'+1} - \sqrt{(S+m)(S-m+1)} \delta_{m,m'-1} \right]$$
(13)

$$\langle S, m' | S_y | S, m \rangle = \frac{i}{2} \left[ \sqrt{(S-m)(S+m+1)} \delta_{m,m'+1} - \sqrt{(S+m)(S-m+1)} \delta_{m,m'-1} \right]$$
(13)

$$\langle S, m' | S_z | S, m \rangle = m \delta_{m,m'} \tag{14}$$

#### Ground state Alkali atoms. 5.3

The effective model of an alkali atom consist of an electron with zero orbital angular momenta interacting with a static nucleus. These two particles interact via their magnetic moments, which define two manifolds of states corresponding to the total angular momenta  $F = I \pm 1/2$ . The library can be used to study inter and intra manifold dynamics.

For example, to study the dynamics with focus on the manifold with total angular momentum F = I - 1/2('L', for lower), the corresponding ID can be obtained by invoking:

### CALL FLOQUET\_INIT(ID, SPECIE\_NAME, 'L', INFO)

and the Hamiltonian components are built assuming the form:

$$V^{\ell,n} = \frac{\mu_B g_{I-1/2} B_x}{A} F_x e^{\phi_{\ell,x}} + \frac{\mu_B g_{I-1/2} B_y}{A} F_y e^{\phi_{\ell,y}} + \frac{\mu_B g_{I-1/2} B_z}{A} F_z e^{\phi_{\ell,z}}$$
(15)

Similarly, to study the dynamic of the manifold with F = I + 1/2 ('U', for upper), the system is initialised using:

#### FLOQUET\_INIT(ID,SPECIE\_NAME,'U',INFO) CALL

which assumes couplings of the form

$$V^{\ell,n} = \frac{\mu_B g_{I+1/2} B_x}{A} F_x e^{\phi_{\ell,x}} + \frac{\mu_B g_{I+1/2} B_y}{A} F_y e^{\phi_{\ell,y}} + \frac{\mu_B g_{I+1/2} B_z}{A} F_z e^{\phi_{\ell,z}}$$
(16)

The atomic gyromagnetic factor is defined by:

$$g_F = g_J * (F * (F+1) - I * (I+1) + J * (J+1)) / (2 * F * (F+1)) + g_I * (F * (F+1) + I * (I+1) - J * (J+1)) / (2 * F * (F+1))!$$

$$(17)$$

with  $F = I \pm 1/2$ . The matrix representation in each case follows the same procedure as in the case of a spin system.

Finally, when both manifolds are of interest, we should use:

### CALL FLOQUET\_INIT(ID, SPECIE\_NAME, 'B', INFO)

which prepares the system to initialise couplings of the form:

$$V^{\ell,n} = \frac{\mu_B B_x}{A} (g_J J_x + g_I I_x) e^{\phi_{\ell,x}} + \frac{\mu_B B_y}{A} (g_J J_y + g_I I_y) e^{\phi_{\ell,y}} + \frac{\mu_B B_z}{A} (g_J J_z + g_I I_z) e^{\phi_{\ell,z}}$$
(18)

In this case, the angular momentum operators are represented in the uncoupled basis  $|I, J, m_I, m_J\rangle$ , corresponding to a tensor multiplication of the matrices resulting from Eqs. (12)-(14) representing  $I_i$  and  $J_i$ .

In all these cases, after invoking the initialisation routine FLOQUET\_INIT and defining the parameters of the couplings using the derived data type TYPE(MODES)::FIELDS, the matrix representation of each component of the Hamiltonian can be obtained with a single call to the subroutine:

### CALL SETHAMILTONIANCOMPONENTS(ID, size(modes\_num, 1), total\_frequencies, MODES\_NUM, FIELDS, INFO)

where total\_frequencies is the total number of driving fields (including a static component). For a complete example see the source code at examples/FORTRAN/main\_87Rb.f90.

#### 6 List of examples

#### 6.1Python

Build the examples running make in the folder examples/PYTHON.

main\_87Rb.py Evaluates the time-evolution and spectrum of a driven atom main\_DressedQubit.py Evaluates the time evolution of a dressed qubit in the bare and dressed basis. main\_floquetinit.py Illustrates the optional systems. main\_qubit\_driver.py Evaluates the tim-evolution operator of a driven qubit using a DRIVER subroutine. Evaluates the time-evolution operator of a driven qubit. main\_qubit.py

main\_qubit\_sp.py Evaluatese the time-evolution operator of driven qubit using

the sparse representation of the Hamiltonian.

Defines the Python wrappers. openmmf.py

#### 6.2C++

Build the examples running make in the folder examples/CPP.

Evaluates the time evolution of a dressed qubit in the bare and main\_DressedQubit.cpp

dressed basis.

main\_DressedQubit\_SP.cpp Evaluates the time evolution of a dressed qubit in the bare and

dressed basis using the sparse representation of the Hamilton-

main\_qubit\_driver.cpp Evaluates the tim-evolution operator of a driven qubit using a

DRIVER subroutine.

main\_qubit.cpp Evaluates the time-evolution operator of a driven qubit. main\_qubit\_sp.cpp Evaluatese the time-evolution operator of driven qubit using

the sparse representation of the Hamiltonian.

MultimodeFloquet.h Prototype of the C++ wrapper functios.

#### 6.3Fortran

 $main\_DressedQubit.f90$ 

DoublePeakSearch.f90

Manybody/main\_MBH\_Bosons.f90

Build the examples running make in the folder examples/FORTRAN.

main\_qubit\_Shirley.f90 Evaluates the time-evolution operator of a driven qubit with

parameters as in the classical paper by Jon Shirley.

main\_qubit.f90 Evaluates the time-evolution operator of a driven qubit. main\_qubit\_SP.f90

Evaluatese the time-evolution operator of driven qubit using

the sparse representation of the Hamiltonian.

main\_qubit\_DRIVER.f90 Evaluates the tim-evolution operator of a driven qubit using a

DRIVER subroutine.

main\_QuantumInterference.f90 Evaluates the time-evolution of a bichromatically driven qubit. main\_qubit\_noise\_SP.f90 Evaluates the time-evolution operator of a driven qubit ina

noisy environment. Uses a sparse representation of the Hamil-

tonian.

main\_halfspin\_DRIVER.f90 Evaluates the time-evolution operator of a two-level system

(defined with 'spin') using a DRIVER subroutine,

 $main\_spin\_DRIVER.f90$ Evaluates the time-evolution operator of a L-level system (de-

fined with 'spin') using a DRIVER subroutine,

main\_lattice.f90 evaluates the spectrum and micromotion of a driven lattice

with two sites in the unit cell.

main\_threesiteslattice.f90 evaluates the spectrum and micromotion of a driven lattice

with three sites in the unit cell.

main\_qubitLattice.f90 Evaluates the time-evolution of a bichromatically driven qubit

as in Eq. (20), arxiv 1612.02143.

main\_qubitLattice\_SP.f90 Evaluates the time-evolution of a bichromatically driven qubit

as in Eq. (20), arxiv 1612.02143, using a sparse representation

of the Hamiltonian.

main\_qubitLattice\_DRIVER.f90 Evaluates the time-evolution of a bichromatically driven qubit

as in Eq. (20), arxiv 1612.02143, using a DRIVER subroutine. Evaluates the time evolution of a dressed qubit in the bare and

dressed basis.

 $main\_DressedQubitV2.f90$ Evaluates the time evolution of a dressed qubit in the bare and

dressed basis.

main\_DressedQubit\_SP.f90 Evaluates the time evolution of a dressed qubit in the bare and

dressed basis using the sparse representation of the Hamilton-

 $main\_DressedQubit\_DRIVER.f90$ Evaluates the time evolution of a dressed qubit in the bare and

dressed basis using a DRIVER subroutine..

main\_87Rb\_RFMW\_DRIVER.f90 Evaluates the time-evolution operator of 87Rb dressed by a

RF field and driven by a MW field, using the dressed basis. Evaluates the time-evolution operator of 87Rb dressed by a

RF field and driven by a MW field, using the dressed basis.

Evaluates the spectrum of the Bosonic Hubbard model with

time-dependent tunnelling.

Evaluates the spectrum of the Fermionic Hubbard model with Manybody/main\_MBH\_Fermions.f90

time-dependent tunnelling.

# 7 C++ wrappers

The library includes C++ interfaces for each one of the subroutines defined. These interfaces are declared in files with the same name as the ones containing the Fortran declarations, but with the particle \_C appended before the ending extension .f90. Similarly, wrapper subroutine are named using the corresponding Fortran names and appending the particle \_c at the end of the name. For example, the file MultimodeFloquetTE\_C.f90 is paired with the file MultimodeFloquet.f90 and defines the subroutine MULTIMODETIMEEVOLUTIONOPERATOR\_C, which is used in c++ using multimodetimeevolutionoperator\_c\_ followed by the declared list of arguments (see example at examples/CPP/main\_qubit.cpp.

The prototype of all function enabled for C++ are declared in the header file include/MultimodeFloquet.h. This scheme lets us to establish a line-by-line correspondence between the Fortran and C++ source codes.

# 8 Python wrappers

The library includes an interface to Python, which is implemented using CTYPES. Similarly to the C++ wrappers, for Python we define a function for each one of the functionalities of the library. This set of functions is declared in the file src/openmmf.py, which should be copied to the python working directory. The Python wrappers call the C++ wrappers which are compiled in the file library library. The user should make sure that the correct path to this file is set in src/openmmf.py.

The python wrapper requires to define the equivalent of the atomand mode derived data types, which are:

```
class atom_c_T(ctypes.Structure):
    _fields_ = [
                 ("id_system", c_int),
                 ("d_bare", c_int)
            ]
and
class mode_c_T(ctypes.Structure):
    c_dcmplx = ctypes.c_double*2
    _fields_ = [
                 ("omega",
                                c_double),
                 ("x",
                                c_dcmplx),
                 ("v",
                                c_dcmplx),
                 ("z",
                                c_dcmplx),
                 ("phi_x",
                                c_double),
                 ("phi_y",
                                c_double),
                 ("phi_z",
                                c_double),
                 ("N_Floquet", c_int)
            ٦
```

respectively.

Each python wrapper function in **src/openmmf.py** takes numpy input parameters and define the set of ctype pointers required to call the corresponding C++ wrapper function. Let's examine the instruction to build the multimode Floquet Hamiltonian:

def multimodefloquetmatrix(id,modes\_num,fields,info):

The input parameter mode\_num is an numpy array of integers that, as before, defines the number of driving mode and harmonics. Also, the input parameter info is a numpy integer. id is an instance of the class atom\_c\_T and fields is an instance of the class modes\_c\_T. This functions calls: openmmfC.multimodefloquetmatrix\_c\_python\_ passing all parameters by reference.

The ctypes wrappers rely on the equivalence between the data types in Fortran, C++ and Python, which should be observed rigourosly following the Table 1

Fortran	C++	ctypes	numpy
integer	int	$ctypes.c\_int$	numpy.int32
double precision	double	ctypes.c_double	numpy.double
complex*16	std::complex <double></double>	$c_dcmplx = ctypes.c_double*2$	np.complex

Table 1: Equivalence between the numerical data types in Fortran, C++, Ctypes and numpy.

# 9 Bugs and known limitations

If you find any bug please contact the developing team using the github hosting link https://github.com/openMMF/

# 10 Acknowledgements

This work has been supported by the EPSRC grants EP/I010394/1 and EP/M013294/1.

# References

- [1] Shih-I Chu. Recent developments in semiclassical floquet theories for intense-field multiphoton processes. 21:197–253, 1985.
- [2] Andreas Hemmerich. Effective time-independent description of optical lattices with periodic driving. *Phys. Rev. A*, 81:063626, Jun 2010.
- [3] Tak-San Ho, Shih-I Chu, and James V Tietz. Semiclassical many-mode floquet theory. *Chemical Physics Letters*, 96(4):464–471, 1983.
- [4] Albert Verdeny, Joaquim Puig, and Florian Mintert. Quasi-periodically driven quantum systems. Zeitschrift für Naturforschung A, 71(10):897–907, 2016.
- [5] Alan Miller and Jason Blevis. Alan miller's fortran software.
- [6] Jun John Sakurai and Eugene D Commins. *Modern quantum mechanics, revised edition*. American Association of Physics Teachers, 1995.

# 11 MODULES

In this section we provide the header of each one of the subroutines of the library, including the argument declaration, to help the user to identify the type of variable expected by each function.

# 11.1 Physical Constants

The module physical\_constants defines the default values of commonly used parameters defining the Hamiltonian of atomic systems. The user can modify these values accessing the file in src/Modules.f90.

```
MODULE physical_constants
 IMPLICIT NONE
 DOUBLE PRECISION, PARAMETER :: pi
                                             = 4.0*ATAN(1.0)
 DOUBLE PRECISION, PARAMETER :: e
                                             = 1.602176462D-19
 DOUBLE PRECISION, PARAMETER :: h_P
                                             = 6.62606957D-34
 DOUBLE PRECISION, PARAMETER :: hbar
                                             = h_P/(2.0*4.0*ATAN(1.0))
 DOUBLE PRECISION, PARAMETER :: mu_B
                                            = 9.27400968D-24
 DOUBLE PRECISION, PARAMETER :: k_B
                                            = 1.3806488D-23
                                          = 12.566370614D-7
 DOUBLE PRECISION, PARAMETER :: mu_cero
 DOUBLE PRECISION, PARAMETER :: epsilon_cero = 8.854187817D-12
 DOUBLE PRECISION, PARAMETER :: amu
                                        = 1.660538921D-27
 DOUBLE PRECISION, PARAMETER :: g_t
                                             = 9.8D0
 DOUBLE PRECISION, PARAMETER :: SB_ct
                                             = 5.6704D-8
 COMPLEX*16,
                 PARAMETER :: J_IMAG
                                             = DCMPLX(0.0D0,1.0D0)
 DOUBLE PRECISION, PARAMETER :: speedoflight = 299792458.0D0
 DOUBLE PRECISION
                             :: TOTAL_TIME
END MODULE physical_constants
```

# 11.2 Arrays

The module ARRAYS provides global definitions of matrices. When using the module, the user cannot define variables using any of the names declared in this module.

### MODULE ARRAYS

```
DOUBLE PRECISION, DIMENSION(:,:), ALLOCATABLE :: Identity,j_x,j_y,j_z,I_x,I_y,I_z
COMPLEX*16, DIMENSION(:,:), ALLOCATABLE :: H_IJ,HAMILTONIAN
COMPLEX*16, DIMENSION(:,:), ALLOCATABLE :: H_FLOQUET,H_FLOQUET_COPY
COMPLEX*16, DIMENSION(:,:), ALLOCATABLE :: U_ZEEMAN
END MODULE ARRAYS
```

To deallocate these arrays, the user can invoke the call:

### CALL DEALLOCATEALL(ID)

where the variable  ${\tt TYPE(ATOM)}$   ${\tt ID}$  defines the type of problem.

# 11.3 Atomic properties

The ATOMIC\_PROPERTIES module defines the default physical parameters of common alkali atomic species used in the context of ultracold atomic physics.

```
MODULE ATOMIC_PROPERTIES
 USE physical_constants
 IMPLICIT NONE
 DOUBLE PRECISION :: L=0.0D0, S = 0.5D0
 DOUBLE PRECISION :: mass_at = 87*amu
 DOUBLE PRECISION :: I,g_I,g_J
 DOUBLE PRECISION :: J,F,gf,mf
 DOUBLE PRECISION :: gF_2,gF_1,G_F
 DOUBLE PRECISION :: A,a_s,alpha_E
 INTEGER :: Fup,Fdown,Ftotal
INTEGER :: Total_states_LSI
 CHARACTER(LEN=7) :: ID_name
 187Rb
 DOUBLE PRECISION :: I_87Rb = 1.5D0
 DOUBLE PRECISION :: J_87Rb = 0.5D0
 DOUBLE PRECISION :: gJ_87Rb = 2.0D0
 DOUBLE PRECISION :: gI_87Rb = -0.000995D0
 DOUBLE PRECISION :: A_87Rb = 2*pi*hbar*3.417341D9
 DOUBLE PRECISION :: a_s_87Rb = 5.77D-9
 DOUBLE PRECISION :: alpha_E_87Rb = 2*pi*hbar*0.0794*1D-4
 INTEGER :: Fup_87Rb = 2
                 :: Fdown_87Rb = 1
 INTEGER
 CHARACTER(LEN=7) :: ID_name_87Rb = "87Rb"
 !6Li
 DOUBLE PRECISION :: I_6Li = 1.0D0
 DOUBLE PRECISION :: J_6Li = 0.5D0
 DOUBLE PRECISION :: gJ_6Li = 2.0D0
 DOUBLE PRECISION :: gI_6Li = -0.000995D0
 DOUBLE PRECISION :: A_6Li = 2*pi*hbar*152.137D6
 DOUBLE PRECISION :: a_s_6Li = 5.77D-9
 DOUBLE PRECISION :: alpha_E_6Li = 2*pi*hbar*0.0794*1D-4
 INTEGER :: Fup_6Li = 1
INTEGER :: Fdown_6Li = 1
 CHARACTER(LEN=7) :: ID_name_6Li = "6Li"
 !qubit
 DOUBLE PRECISION :: I_qubit = 0.0D0
 DOUBLE PRECISION :: J_qubit = 0.0D0
 DOUBLE PRECISION :: gJ_qubit = 1.0D0
 DOUBLE PRECISION :: gI_qubit = 0.0D0
 DOUBLE PRECISION :: A_qubit = 1.0D0
 DOUBLE PRECISION :: a_s_qubit = 0.0D0
 DOUBLE PRECISION :: alpha_E_qubit = 0.0D0
 CHARACTER(LEN=7) :: ID_name_qubit = "qubit"
 !spin
 DOUBLE PRECISION :: I_spin = 0.0D0
 DOUBLE PRECISION :: J_spin = 0.0D0
 DOUBLE PRECISION :: gJ_spin = 1.0D0
 DOUBLE PRECISION :: gI_spin = 0.0D0
 DOUBLE PRECISION :: A_spin = 1.0D0
 DOUBLE PRECISION :: a_s_spin = 0.0D0
 DOUBLE PRECISION :: alpha_E_spin = 0.0D0
```

INTEGER :: Fup\_spin = 1
INTEGER :: Fdown\_spin = 1
CHARACTER(LEN=7) :: ID\_name\_spin = "spin"

!lattice

CHARACTER :: PERIODIC

CHARACTER(LEN=7) :: ID\_name\_lattice = "lattice"

END MODULE ATOMIC\_PROPERTIES

# 11.4 MKL

# MODULE FEAST

END MODULE FEAST

# 12 DERIVED TYPES (src/modes.f90)

The derived type defined

```
MODULE TYPES
```

```
TYPE :: MODE
  DOUBLE PRECISION :: OMEGA
   COMPLEX*16 :: X,Y,Z
   DOUBLE PRECISION :: phi_x,phi_y,phi_z
   INTEGER :: N_Floquet
   COMPLEX*16, DIMENSION(:,:), ALLOCATABLE :: V
   COMPLEX*16, DIMENSION(:), ALLOCATABLE :: VALUES INTEGER, DIMENSION(:), ALLOCATABLE :: ROW, COLUMN
END TYPE MODE
TYPE :: ATOM
   INTEGER :: id_system INTEGER :: D_BARE
   DOUBLE PRECISION, DIMENSION(:), ALLOCATABLE :: E_BARE
END TYPE ATOM
TYPE :: HARMONIC_FACTORS
   COMPLEX*16,DIMENSION(:,:), ALLOCATABLE :: U,U_r,U_AVG
   INTEGER, DIMENSION(:), ALLOCATABLE :: n
END type HARMONIC_FACTORS
```

END MODULE TYPES

# 13 COMPUTATIONAL SUBROUTINES

```
MODULE FLOQUETINITINTERFACE
  INTERFACE FLOQUETINIT
    MODULE PROCEDURE FLOQUETINIT_QUBIT, FLOQUETINIT_SPIN,FLOQUETINIT_ALKALI
 END INTERFACE FLOQUETINIT
 SUBROUTINE FLOQUETINIT_QUBIT(ID, atomicspecie, INFO)
    ! ATOMICSPECIE: 87Rb,6Li,Cs,41K,qubit,lattice, SPIN
    ! MANIFOLD : "U" UPPER HYPERFINE MANIFOLD, "L" LOWER HYPERFIND MANIFOLD, "B" BOTH
    ! JTOTAL : IF ATOMICSPECIE .EQ. SPIN THEN JTOTAL IS THE TOTAL ANGULAR MOMENTUM OF THE SPIN
                 IF ATOMICSPECIE .EQ. LATTICE, THEN JTOTAL IS THE NUMBER OF SITES
    ! calculate the dimenson of the Hilbert space
    ! initialize all the matrices required for a full Floquet calcuations
    ! Calculate the nuclear, electron and total angular momentum operators
 TYPE(ATOM), INTENT(INOUT) :: ID
 CHARACTER (LEN=*), INTENT(IN) :: ATOMICSPECIE
 INTEGER,
                   INTENT(INOUT) :: INFO
. . .
SUBROUTINE FLOQUETINIT_SPIN(ID, atomicspecie, jtotal, info)
 ! ATOMICSPECIE: 87Rb,6Li,Cs,41K,qubit,lattice, SPIN
 ! MANIFOLD : "U" UPPER HYPERFINE MANIFOLD, "L" LOWER HYPERFIND MANIFOLD, "B" BOTH
  ! JTOTAL : IF ATOMICSPECIE .EQ. SPIN THEN JTOTAL IS THE TOTAL ANGULAR MOMENTUM OF THE SPIN
               IF ATOMICSPECIE .EQ. LATTICE, THEN JTOTAL IS THE NUMBER OF SITES
  ! calculate the dimenson of the Hilbert space
  ! initialize all the matrices required for a full Floquet calcuations
  ! Calculate the nuclear, electron and total angular momentum operators
 IMPLICIT NONE
 TYPE(ATOM), INTENT(INOUT) :: ID
 CHARACTER (LEN=*), INTENT(IN) :: ATOMICSPECIE
 DOUBLE PRECISION, intent(in) :: jtotal
 INTEGER, INTENT(INOUT) :: INFO
SUBROUTINE FLOQUETINIT_ALKALI(ID, atomicspecie, manifold, info)
 ! ATOMICSPECIE: 87Rb,6Li,Cs,41K,qubit,lattice, SPIN
 ! MANIFOLD : "U" UPPER HYPERFINE MANIFOLD, "L" LOWER HYPERFIND MANIFOLD, "B" BOTH
 ! JTOTAL : IF ATOMICSPECIE .EQ. SPIN THEN JTOTAL IS THE TOTAL ANGULAR MOMENTUM OF THE SPIN
               IF ATOMICSPECIE .EQ. LATTICE, THEN JTOTAL IS THE NUMBER OF SITES
  ! calculate the dimenson of the Hilbert space
  ! initialize all the matrices required for a full Floquet calcuations
  ! Calculate the nuclear, electron and total angular momentum operators
 TYPE(ATOM),
                 INTENT(INOUT) :: ID
 CHARACTER (LEN=*), INTENT(IN) :: ATOMICSPECIE CHARACTER (LEN=1), INTENT(IN) :: MANIFOLD
 INTEGER.
                   INTENT(INOUT) :: INFO
```

18

END MODULE FLOQUETINITINTERFACE

```
SUBROUTINE SETHAMILTONIANCOMPONENTS(ID,NM,NF,MODES_NUM,FIELD,INFO)
  ! ID tYPE OF ATOM
  ! MODES_NUM, VECTOR. THE SIZE OF THE VECTOR TELL US THE NUMBER OF
  Ţ
             FREQUENCIES, AND THE VALUE OF EACH COMPONENT INDICATES
             THE NUMBER OF HARMONICS OF EACH FREQUENCI
  ! FIELDS : IN AND OUTPUT THE MATRICES
  ! INFO
  USE ARRAYS
  USE ATOMIC_PROPERTIES
  USE TYPES
  USE SUBINTERFACE_LAPACK ! write_matrix interface
  IMPLICIT NONE
  INTEGER,
                             INTENT(IN)
                                        :: NM,NF
  TYPE(ATOM),
                           INTENT(IN)
                                         :: ID
  INTEGER, DIMENSION(NM), INTENT(IN)
                                          :: MODES_NUM
  TYPE(MODE), DIMENSION(NF), INTENT(INOUT) :: FIELD
  INTEGER,
                             INTENT(INOUT) :: INFO
SUBROUTINE F_representation(Fx,Fy,Fz,Ftotal)
  USE FUNCIONES
  IMPLICIT NONE
  DOUBLE PRECISION, DIMENSION(:,:), INTENT(OUT):: Fx,Fy,Fz
  DOUBLE PRECISION, INTENT(IN) :: Ftotal
  !INTEGER, INTENT(IN) :: Ftotal_
  !DOUBLE PRECISION
  INTEGER k,p,N_k
  double precision k_!,Ftotal
  Fx = 0.0
  Fy = 0.0
  Fz = 0.0
SUBROUTINE I_and_J_representations(j_x,j_y,j_z,I_x,I_y,I_z,L,S,I)
  USE FUNCIONES
  IMPLICIT NONE
  DOUBLE PRECISION, DIMENSION(:,:),INTENT(INOUT) :: j_x,j_y,j_z,I_x,I_y,I_z
  DOUBLE PRECISION, INTENT(IN) :: L,S,I
```

SUBROUTINE MULTIMODETIMEEVOLUTINOPERATOR(D,NM,MODES\_NUM,U\_F\_MODES,E\_MULTIFLOQUET, D\_BARE,FIELD,T1,T2,U,INFO)

```
! THE EVOLUTION OPERATOR IS WRITEN IN THE BASIS USED TO EXPRESS THE
  ! MULTIMODE FLOQUET HAMILTONIAN
  ! U : MATRIX OF AMPLITUED OF PROBABILITIES FOR TRANSITIONS BETWEEN T1 TO T2
!!$ D
                       (IN) : DIMENSION OF THE EXTENDED HILBERT SPACE
!!$
                                (SIZE OF THE MULTIMODE FLOQUET MATRIX)
!!$ NM (IN) : NUMBER OF MODES
!!$ MODES_NUM (IN) : VECTOR (NM) INDICATING THE NUMBER OF HARMONICS OF EACH MODE
!!$ U_F_MODES (IN) : TRANSFORMATION, DIMENSOON (D,D)
!!$ E_MULTIFLOQUET (IN) : MULTIMODE FLOQUET SPECTRUM
!!$ D_BARE (IN) : DIMENSION OF THE BARE HILBERT SPACE !!$ FIELD (IN) : STRUCTURE DESCRIBING THE COUPLINGS
                    (IN) : INITIAL TIME
(IN) : FINAL TIME
(OUT) : TRANFORMATION BETWEEN THE EXTENDED BARE BASIS AND
!!$ T1
!!$ T2
!!$ U
              THE FLOQUET STATES, DI
(INOUT): (POSSIBLE) ERROR FLAG
11$
                                 THE FLOQUET STATES, DIMENSION (D_BARE,D)
!!$ INFO
  USE TYPES
  USE SUBINTERFACE_LAPACK
  IMPLICIT NONE
                                                    INTENT(IN) :: D,D_BARE,NM
  INTEGER,
  INTEGER,
                                                    INTENT(INOUT) :: INFO
  INTEGER,
  INTEGER, DIMENSION(NM),
TYPE(MODE), DIMENSION(NM),
                                                    INTENT(IN) :: MODES_NUM
                                                    INTENT(IN) :: FIELD
  DOUBLE PRECISION.
                                                    INTENT(IN) :: T1.T2
  DOUBLE PRECISION, DIMENSION(D), INTENT(IN) :: I1,12

DOUBLE PRECISION, DIMENSION(D), INTENT(IN) :: E_MULTIFLOQUET

COMPLEX*16, DIMENSION(D,D), INTENT(IN) :: U_F_MODES

COMPLEX*16, DIMENSION(D_BARE,D_BARE), INTENT(OUT) :: U
SUBROUTINE MULTIMODEFLOQUETMATRIX(ATOM_,NM,NF,MODES_NUM,FIELD,INFO)
  !ID, size(modes_num, 1), total_frequencies, MODES_NUM, FIELDS, INFO
  ! USE FLOQUET
  !ATOM_ type atom, -> dimension of the bare Hilbert space
  !NM -> number of modes
  !NF -> Number of Fields
  !MODES_NUM -> number of harmonics of each mode
  !FIELD -> Field couplings
  !INFO
  USE ARRAYS
  USE ATOMIC_PROPERTIES
  USE TYPES
  USE SUBINTERFACE_LAPACK
  IMPLICIT NONE
  INTEGER,
                                INTENT(IN) :: NM,NF
  INTEGER,
                               INTENT(INOUT) :: INFO
  INTEGER, DIMENSION(NM), INTENT(IN) :: MODES_NUM
  TYPE(MODE), DIMENSION(NF), INTENT(IN) :: FIELD
                              INTENT(IN) :: ATOM_
  TYPE(ATOM),
```

```
! NM
            (IN) : number of modes
        (IN) : number of driving fields
!NF
!MODES_NUM (IN) : vector indicating the number of harmonics of each driving field (mode)
!FIELDS (IN) : Fields
!VALUES_ (OUT) : Hamiltonian values
!ROW_INDEX_ (OUT) : vector indicating the row position of values
!COLUMN_ (OUT) : vector indicating the column position of the values
!INFO (INOUT) : error flag. INFO=0 means there is no error
  USE TYPES
                       !(modes.f90)
  USE MERGINGARRAYS ! (utils.f90)
  IMPLICIT NONE
  INTEGER
                                               INTENT(IN) :: NM,NF
  TYPE(MODE), DIMENSION(NF),
                                              INTENT(INOUT) :: FIELDS
  TYPE(ATOM),
                                              INTENT(IN) :: ATOM__
              DIMENSION(NM),
                                              INTENT(IN) :: MODES_NUM
  INTEGER,
                                               INTENT(INOUT) :: INFO
  INTEGER,
  COMPLEX*16, DIMENSION(:), ALLOCATABLE, INTENT(OUT) :: VALUES_
  INTEGER, DIMENSION(:), ALLOCATABLE,INTENT(OUT) :: COLUMN_
INTEGER, DIMENSION(:), ALLOCATABLE,INTENT(OUT) :: ROW_INDEX_
SUBROUTINE MULTIMODEFLOQUETTRANSFORMATION(D,NM,MODES_NUM,U_F_MODES,E_MULTIFLOQUET,
                                                                            D_BARE,FIELD,T1,U,INFO)
  ! TIME-DEPENDENT TRANSFORMATION BETWEEN THE EXTENDED BARE BASIS AND THE FLOQUET STATES
  ! U(T1) = sum_ U^n exp(i n omega T1)
!!$ D
                      (IN) : DIMENSION OF THE EXTENDED HILBERT SPACE (SIZE OF THE MULTIMODE FLOQUET
!!$ NM
                      (IN) : NUMBER OF MODES
!!$ MODES_NUM (IN) : VECTOR (NM) INDICATING THE NUMBER OF HARMONICS OF EACH MODE
!!$ U_F_MODES (IN) : TRANSFORMATION, DIMENSOON (D,D)
!!$ E_MULTIFLOQUET (IN) : MULTIMODE FLOQUET SPECTRUM
!!$ D_BARE (IN) : DIMENSION OF THE BARE HILBERT SPACE
!!$ FIELD (IN) : STRUCTURE DESCRIBING THE COUPLINGS
!!$ T1 (IN) : TIME. THE BARE 2 DRESSED TRANSFORMATINO IS TIME DEPENDENT
!!$ U (OUT) : TRANFORMATION BETWEEN THE EXTENDED BARE BASIS AND THE FLOQUET STATES,
!!$
                                  DIMENSION (D_BARE,D)
!!$ INFO (INOUT): (POSSIBLE) ERROR FLAG
  USE TYPES
  IMPLICIT NONE
  INTEGER,
                                                       INTENT(IN) :: D,D_BARE,NM
  INTEGER,
                                                       INTENT(INOUT) :: INFO
                                                     INTENT(IN) :: MODES_NUM
  INTEGER,
                       DIMENSION(NM),
  TYPE(MODE),
                       DIMENSION(NM),
                                                      INTENT(IN) :: FIELD
  DOUBLE PRECISION,
                                                      INTENT(IN) :: T1
  DOUBLE PRECISION, DIMENSION(D), INTENT(IN) :: E_MULTIFLOQUET COMPLEX*16, DIMENSION(D,D), INTENT(IN) :: U_F_MODES COMPLEX*16, DIMENSION(D_BARE,D), INTENT(OUT) :: U
```

!ATOM\_ : type of quantum system

SUBROUTINE MULTIMODEMICROMOTION(ID,D,NM,MODES\_NUM,U\_F\_MODES,E\_MULTIFLOQUET,D\_BARE,FIELD,T1,U,INFO)

```
! U(T1) = sum_ U^n exp(i n omega T1)
                        (IN) : DIMENSION OF THE EXTENDED HILBERT SPACE (SIZE OF THE MULTIMODE FLOQUET
!!$ D
!!$ NM
                       (IN) : NUMBER OF MODES
!!$ MODES_NUM (IN) : VECTOR (NM) INDICATING THE NUMBER OF HARMONICS OF EACH MODE
!!$ U_F_MODES (IN) : TRANSFORMATION, DIMENSOON (D,D)
!!$ E_MULTIFLOQUET (IN) : MULTIMODE FLOQUET SPECTRUM
!!$ D_BARE (IN) : DIMENSION OF THE BARE HILBERT SPACE
!!$ FIELD
                      (IN) : STRUCTURE DESCRIBING THE COUPLINGS
                    (IN) : TIME. THE BARE 2 DRESSED TRANSFORMATINO IS TIME DEPENDENT (OUT) : TRANFORMATION BETWEEN THE EXTENDED BARE BASIS AND THE FLOQUET STATES, D (INOUT): (POSSIBLE) ERROR FLAG
!!$ T1
!!$ U
!!$ INFO
  !USE TYPES_C
  USE TYPES
  !USE MODES_4F
  USE SUBINTERFACE_LAPACK
  USE ATOMIC_PROPERTIES
  IMPLICIT NONE
  TYPE(ATOM),
                                   INTENT(IN) :: ID
                                                        INTENT(IN) :: D,D_BARE,NM
  INTEGER,
  INTEGER,
                                                       INTENT(INOUT) :: INFO
  INTEGER,
  INTEGER, DIMENSION(NM), TYPE(MODE), DIMENSION(NM),
                                                      INTENT(IN) :: MODES_NUM
                                                      INTENT(IN) :: FIELD
  DOUBLE PRECISION,
                                                      INTENT(IN) :: T1
  DOUBLE PRECISION, DIMENSION(D), INTENT(IN) :: IT

COMPLEX*16, DIMENSION(D,D), INTENT(IN) :: E_MULTIFLOQUET

COMPLEX*16, DIMENSION(D_BARE,D_BARE), INTENT(OUT) :: U
SUBROUTINE MICROMOTIONFOURIERDRESSEDBASIS(ID, DRESSINGFIELDS_INDICES, MODES_NUM, FIELDS,
                                                                                     U_FD,E_DRESSED,INFO)
             (in) :: TYPE(ATOM) system ID
! DRESSINGFIELDS_INDICES (in) :: integer array indicating the indices of the dressing modes
! MODES_NUM (in) :: integer array indicating the number of harmonics of all driving modes
! FIELDS (in) :: Array of TYPE(MODE) of dimension
! U_FD (out) :: complex*16 matrix fourier decomposition of the micromotion operator of the dr
! E_DRESSED (out) :: dressed energies
! INFO (inout) :: error flag
  USE TYPES
  TYPE(ATOM), INTENT(IN) :: ID

INTEGER, DIMENSION(:), INTENT(IN) :: DRESSINGFIELDS_INDICES

INTEGER, DIMENSION(:), INTENT(IN) :: MODES_NUM

TYPE(MODE), DIMENSION(:), INTENT(IN) :: FIELDS

COMPLEX*16, DIMENSION(:,:), ALLOCATABLE, INTENT(OUT) :: U_FD
  DOUBLE PRECISION, DIMENSION(:), ALLOCATABLE, INTENT(OUT) :: E_DRESSED
SUBROUTINE MICROMOTIONDRESSEDBASIS(ID, MODES_NUM, DRESSINGFIELDS_INDICES, FIELDS,
                                                                  U_F_MODES,E_MULTIFLOQUET,T1,U,INFO)
```

! TIME-DEPENDENT TRANSFORMATION BETWEEN THE EXTENDED BARE BASIS AND THE FLOQUET STATES

! MODES\_NUM (in) :: integer array indicating the number of harmonics of each driving mode

:: TYPE(ATOM) system ID

! ID (in)

```
! FIELDS :: Array of TYPE(MODES) with NM components (all driving fields)
! U_F_MODES :: complex*16 matrix of dimension DxD. Fourier decomposition of the micromotion ope
! E_MULTIFLOQUET :: dressed energies
       :: double precision, time
! U
                :: complex*16 matrix of dimension D_BARE x D_BARE. micromotion operator at time T1
! INFO
               :: error flag
 USE TYPES
 IMPLICIT NONE
 TYPE(ATOM),
                                   INTENT(IN) :: ID
 INTEGER,
                   INTENT(IN) :: DRESSINGFIELDS_INDICES
 INTEGER,
                 DIMENSION(:),
 COMPLEX*16, DIMENSION(:,:), INTENT(IN) :: U_F_MODES
DOUBLE PRECISION, DIMENSION(:), INTENT(IN) :: E_MULTIFLOQUET
 TYPE(MODE), DIMENSION(:), INTENT(IN) :: FIELDS
 DOUBLE PRECISION ,
                                   INTENT(IN) :: T1
 COMPLEX*16, DIMENSION(:,:), INTENT(OUT) :: U
 INTEGER,
                                   INTENT(INOUT) :: INFO
SUBROUTINE MULTIMODETRANSITIONAVG(D,NM,FIELD,MODES_NUM,U_F_MODES,
                                             E_MULTIFLOQUET,D_BARE,U,INFO)
     AVERAGE TIME EVOLUTION OPERATOR OF A MULTIMODE DRESSED SYSTEM.
!!$
!!$
     THE AVERAGE EVOLUTION OPERATOR IS WRITEN IN THE BASIS USED TO EXPRESS THE
     MULTIMODE FLOQUET HAMILTONIAN
    U : MATRIX OF AVERAGE TRANSITION PROBABILITIES
!!$
!!$
!!$ D
                   (IN) : DIMENSION OF THE EXTENDED HILBERT SPACE
                           (SIZE OF THE MULTIMODE FLOQUET MATRIX)
!!$
!!$ NM
                   (IN) : NUMBER OF MODES
!!$ MODES_NUM (IN) : VECTOR (NM) INDICATING THE NUMBER OF HARMONICS OF EACH MODE !!$ U_F_MODES (IN) : TRANSFORMATION, DIMENSOON (D,D)
!!$ E_MULTIFLOQUET (IN) : MULTIMODE FLOQUET SPECTRUM
!!$ D_BARE (IN) : DIMENSION OF THE BARE HILBERT SPACE
                  (OUT) : MATRIX OF AVERAGE TRANSITION PROBABILITIES
!!$ U
!!$ INFO
               (INOUT): (POSSIBLE) ERROR FLAG
 USE TYPES
 IMPLICIT NONE
 TYPE(MODE), DIMENSION(NM), INTENT(IN) :: FIELD
 INTEGER, DIMENSION(NM), INTENT(IN)
                                         :: MODES_NUM
 INTEGER,
                                              INTENT(IN) :: D,D_BARE,NM
                                              INTENT(INOUT) :: INFO
 INTEGER,
 COMPLEX*16, DIMENSION(D,D),
 DOUBLE PRECISION, DIMENSION(D),
                                             INTENT(IN) :: E_MULTIFLOQUET
                                             INTENT(IN)
                                                           :: U_F_MODES
 DOUBLE PRECISION, DIMENSION(D_BARE,D_BARE), INTENT(OUT) :: U
```

23

# 14 DRIVER SUBROUTINES

SUBROUTINE DRESSEDBASIS(D,ID,NM,MODES\_NUM,FIELDS,U\_FD,E\_DRESSED,INFO) !!\$ THIS SUBROUTINES CALCULATES THE FOURIER COMPONENTS OF THE !!\$ TRANSFORMATION BETWEEN THE BARE BASIS TO THE DRESSED BASIS DEFINDED !!\$ BY THE FULL SET OF DRIVING FIELDS. !!\$ D : DIMENSION OF THE MULTIMODE EXTENDED HILBERT SPACE : TYPE OF QUANTUM SYSTEM !!\$ ID (IN) : NUMBER OF MODES == NUMBER OF DRIVING FIELDS !!\$ NM (IN) !!\$ NM (IN)
!!\$ MODES\_NUM
!!\$ FIELDS (IN)
!!\$ U\_FD (OUT)
!!\$ E\_DRESSED (OUT) : VECTOR INDICATING THE NUMBER OF HARMONICS OF EACH DRESSING FIELD
: AMPLITUDE, FREQUENCY AND PHASES OF ALL DRIVING FIELDS : THIS IS THE TRANSFORMATION WE ARE LOOKING FOR : DRESSED ENERGIES : INFO = O MEANS SUCESS !!\$ INFO (INOUT) USE ATOMIC\_PROPERTIES USE TYPES USE SUBINTERFACE USE SUBINTERFACE\_LAPACK USE FLOQUETINIT\_ USE ARRAYS IMPLICIT NONE TYPE(MODE), DIMENSION(NM), INTENT(IN) :: FIELDS TYPE(ATOM), INTENT(IN) :: ID

INTEGER, DIMENSION(NM), INTENT(IN) :: MODES\_NUM

COMPLEX\*16, DIMENSION(D,D), INTENT(OUT) :: U\_FD DOUBLE PRECISION, DIMENSION(D), INTENT(OUT) :: E\_DRESSED INTENT(IN) :: NM,D INTEGER, INTENT(INOUT) :: INFO SUBROUTINE DRESSEDBASIS\_SP(D,ID,NM,MODES\_NUM,FIELDS,U\_FD,E\_DRESSED,INFO) !!\$ THIS SUBROUTINES CALCULATES THE TRANSFORMATION BETWEEN THE BARE !!\$ BASIS TO THE DRESSED BASIS DEFINDED BY THE FULL SET OF DRIVING FIELDS. : DIMENSION OF THE MULTIMODE EXTENDED HILBERT SPACE
: TYPE OF QUATUM SYSTEM
: NUMBER OF MODES == NUMBER OF DRIVING FIELDS
: VECTOR INDICATING THE NUMBER OF HARMONICS OF EACH DRESSING FIELD
: AMPLITUDE, FREQUENCY AND PHASES OF ALL DRIVING FIELDS
: THIS IS THE TRANSFORMATION WE ARE LOOKING FOR

JT)
: DRESSED ENERGIES !!\$ D !!\$ ID (IN) !!\$ NM (IN) !!\$ MODES\_NUM !!\$ FIELDS (IN) !!\$ U\_FD (OUT) !!\$ E\_DRESSED (OUT) : INFO = O MEANS SUCESS !!\$ INFO (INOUT)

```
USE ATOMIC_PROPERTIES
USE TYPES
USE SPARSE_INTERFACE
USE SUBINTERFACE
USE SUBINTERFACE_LAPACK
USE FLOQUETINIT_
USE ARRAYS

IMPLICIT NONE
TYPE(MODE), DIMENSION(NM
```

TYPE(MODE), DIMENSION(NM), INTENT(INOUT) :: FIELDS

```
TYPE (ATOM),
                                  INTENT(IN) :: ID
 INTEGER, DIMENSION(NM), INTENT(IN) :: MODES_NUM
COMPLEX*16, DIMENSION(D,D), INTENT(OUT) :: U_FD
 DOUBLE PRECISION, DIMENSION(D), INTENT(OUT) :: E_DRESSED
                                  INTENT(IN) :: NM,D
 INTEGER,
                                  INTENT(INOUT) :: INFO
  INTEGER,
SUBROUTINE TIMEEVOLUTIONOPERATOR(ID, D_BARE, NM, MODES_NUM, FIELD, T1, T2, U, INFO)
 ! TIME EVOLUTION OPERATOR OF A MULTIMODE DRESSED SYSTEM. THE EVOLUTION
 ! OPERATOR IS WRITEN IN THE BASIS USED TO EXPRESS THE
 ! MULTIMODE FLOQUET HAMILTONIAN
 ! U : MATRIX OF AMPLITUED OF PROBABILITIES FOR TRANSITIONS BETWEEN T1 TO T2
                (IN) : NUMBER OF MODES
!!$ NM
                  (IN) : VECTOR (NM) INDICATING THE NUMBER OF HARMONICS OF EACH MODE
!!$ MODES_NUM
!!$ D_BARE (IN) : DIMENSION OF THE BARE HILBERT SPACE
!!$ FIELD
                  (IN) : STRUCTURE DESCRIBING THE COUPLINGS
!!$ T1
                  (IN) : INITIAL TIME
!!$ T2
                  (IN) : FINAL TIME
              (OUT) : TRANFORMATION BETWEEN THE EXTENDED BARE BASIS AND
THE FLOQUET STATES, DIMENSION (D_BARE,D)
!!$ U
!!$
                             THE FLOQUET STATES, DIMENSION (D_BARE,D)
!!$ INFO
                  (INOUT): (POSSIBLE) ERROR FLAG
   USE ATOMIC_PROPERTIES
   USE TYPES
   USE SUBINTERFACE
   USE SUBINTERFACE_LAPACK
   USE FLOQUETINIT_
   USE ARRAYS
   IMPLICIT NONE
   TYPE(ATOM) ,
                                                INTENT(IN) :: ID
    INTEGER,
                                                INTENT(IN) :: D_BARE
    INTEGER,
                                                INTENT(IN)
                                                              :: NM
                    DIMENSION(NM),
                                                             :: MODES_NUM
    INTEGER,
                                                INTENT(IN)
   TYPE(MODE),
                    DIMENSION(NM),
                                                INTENT(IN) :: FIELD
   DOUBLE PRECISION,
                                                INTENT(IN) :: T1
   DOUBLE PRECISION,
                                                INTENT(IN)
                                                             :: T2
   COMPLEX*16, DIMENSION(D_BARE,D_BARE), INTENT(OUT) :: U
    INTEGER,
                                                INTENT(INOUT) :: INFO
SUBROUTINE MICROMOTIONFOURIERDRESSEDBASIS(ID, DRESSINGFIELDS_INDICES,
                                           MODES_NUM,FIELDS, U_FD,E_DRESSED,INFO)
! THIS SUBROUTINE CALCULATES THE FOURIER COMPONENTS (U_FD) AND PHASES (E_DRESSED)
! OF THE MICROMOTION OPERATOR OF SUBSET OF DRIVING MODES
! ID
            (in) :: TYPE(ATOM) system ID
! DRESSINGFIELDS_INDICES (in) :: integer array indicating the indices of the dressing modes
! MODES_NUM (in) :: integer array indicating the number of harmonics of all driving modes ! FIELDS (in) :: Array of TYPE(MODE) of dimension
! U_FD
            (out) :: complex*16 matrix fourier decomposition of the micromotion
                    operator of the dressed basis
! E_DRESSED (out) :: dressed energies
! INFO (inout) :: error flag
 USE TYPES
 IMPLICIT NONE
 TYPE(ATOM),
                                  INTENT(IN) :: ID
  INTEGER, DIMENSION(:),
                                  INTENT(IN) :: DRESSINGFIELDS_INDICES
                                  INTENT(IN) :: MODES_NUM
  INTEGER, DIMENSION(:),
```

```
TYPE(MODE), DIMENSION(:), INTENT(IN) :: FIELDS
COMPLEX*16, DIMENSION(:,:), ALLOCATABLE, INTENT(OUT) :: U_FD
```

DOUBLE PRECISION, DIMENSION(:), ALLOCATABLE, INTENT(OUT) :: E\_DRESSED

INTEGER, INTENT(INOUT) :: INFO

INTEGER,

### END SUBROUTINE MICROMOTIONFOURIERDRESSEDBASIS

SUBROUTINE MICROMOTIONDRESSEDBASIS(ID, MODES\_NUM, DRESSINGFIELDS\_INDICES, FIELDS, U\_F\_MODES,E\_MULTIFLOQUET,T1,U,INFO) ! THIS SUBROUTINE CALCULATES U: THE TIME-DEPENDENT MICROMOTION OPERATOR OF ! A SUBSET OF THE DRIVING MODES. U\_F\_MODES AND E\_MULTIFLOQUET ARE THE ARRAYS ! CALCULATED WITH THE SUBROUTINE MICROMOTIONFOURIERDRESSEDBASIS ! ID (in) :: TYPE(ATOM) system ID ! MODES\_NUM (in) :: integer array indicating the number of harmonics of each driving mode ! DRESSINFIELDS\_INDICES :: integer array indicating the indices of the dressing modes ! FIELDS :: Array of TYPE(MODES) with NM components (all driving fields) ! TILLE ! U\_F\_MODES :: complex\*16 matrix of dimension DxD. Fourier decomposition of the micromotion operator of the dressed basis ! E\_MULTIFLOQUET :: dressed energies ! T1 :: double precision, time ! U :: complex\*16 matrix of dimension D\_BARE x D\_BARE. micromotion operator at time T1 ! ! INFO :: error flag USE TYPES IMPLICIT NONE INTENT(IN) :: ID TYPE(ATOM), INTEGER, DIMENSION(:), INTENT(IN) :: MODES\_NUM INTEGER, DIMENSION(:), INTENT(IN) :: DRESSINGFIELDS\_INDICES
COMPLEX\*16, DIMENSION(:,:), INTENT(IN) :: U\_F\_MODES
DOUBLE PRECISION, DIMENSION(:), INTENT(IN) :: E\_MULTIFLOQUET TYPE(MODE), DIMENSION(:), INTENT(IN) :: FIELDS DOUBLE PRECISION , INTENT(IN) :: T1 COMPLEX\*16, DIMENSION(:,:), INTENT(OUT) :: U

INTENT(INOUT) :: INFO

# 14.1 Utility subroutines

SUBROUTINE PACKINGBANDMATRIX (N, A, KD, AB, INFO)

```
! brute force packing of a banded matrix
 IMPLICIT NONE
 INTEGER, INTENT(INOUT) :: INFO
 INTEGER, INTENT(IN)
                      :: N,KD
 COMPLEX*16, DIMENSION(N,N)
 COMPLEX*16, DIMENSION(KD+1,N) :: AB
SUBROUTINE LAPACK_FULLEIGENVALUES(H,N,W_SPACE,INFO)
!eigenvalues/vectors of matrix ab
!H, inout, packed banded matrix
! , out, eigenvectors
!N, in, matrix dimension
!W_space, out, eigenvalues
!INFO, inout, error flag
 !H is COMPLEX*16 array, dimension (N, N)
                   On entry, the Hermitian matrix A. If UPLO = 'U', the
  ! 70 *>
                   leading N-by-N upper triangular part of A contains the
 ! 71 *>
                   upper triangular part of the matrix A. If UPLO = 'L',
 ! 72 *>
                   the leading N-by-N lower triangular part of A contains
 ! 73 *>
                   the lower triangular part of the matrix A.
 ! 74 *>
                   On exit, if JOBZ = 'V', then if INFO = 0, A contains the
 ! 75 *>
                   orthonormal eigenvectors of the matrix A.
 ! 76 *>
                 If JOBZ = 'N', then on exit the lower triangle (if UPLO='L')
 ! 77 *>
                   or the upper triangle (if UPLO='U') of A, including the
  ! 78 *>
                   diagonal, is destroyed.
 ! The eigenvector H(:,r) corresponds to the eigenvalue W_SPACE(r)
 IMPLICIT NONE
                                   INTENT(IN)
 INTEGER,
 COMPLEX*16,
                 DIMENSION(N,N), INTENT(INOUT) :: H
 DOUBLE PRECISION, DIMENSION(N), INTENT(INOUT) :: W_SPACE
 INTEGER,
                                   INTENT(OUT)
                                                :: INFO
SUBROUTINE LAPACK_FULLEIGENVALUESBAND(AB,Z,KD,N,W,INFO)
!eigenvalues/vectors of banded matrix ab
!AB, inout, packed banded matrix
!Z, out, eigenvectors
!KD out, calcuated eigenvectors
!N, in, matrix dimension
!W, out, eigenvalues
!INFO, inout, error flag
 !H is COMPLEX*16 array, dimension (N, N)
 ! 69 *>
                 On entry, the Hermitian matrix A. If UPLO = 'U', the
 ! 70 *>
                   leading N-by-N upper triangular part of A contains the
 ! 71 *>
                   upper triangular part of the matrix A. If UPLO = 'L',
 ! 72 *>
                   the leading N-by-N lower triangular part of A contains
 ! 73 *>
                   the lower triangular part of the matrix A.
 ! 74 *>
                   On exit, if JOBZ = 'V', then if INFO = O, A contains the
 ! 75 *>
                   orthonormal eigenvectors of the matrix A.
 ! 76 *>
                   If JOBZ = 'N', then on exit the lower triangle (if UPLO='L')
 ! 77 *>
                   or the upper triangle (if UPLO='U') of A, including the
```

```
! The eigenvector H(:,r) corresponds to the eigenvalue W_SPACE(r)
 IMPLICIT NONE
  INTEGER,
                                           INTENT(IN)
                                                        :: N,KD
 COMPLEX*16, DIMENSION(KD+1,N), INTENT(INOUT) :: AB
COMPLEX*16, DIMENSION(N,N), INTENT(INOUT) :: Z
 DOUBLE PRECISION, DIMENSION(N),
                                         INTENT(INOUT) :: W
 INTEGER,
                                         INTENT(OUT) :: INFO
SUBROUTINE LAPACK_SELECTEIGENVALUES(H,N,W_SPACE,L1,L2,Z,INFO)
!selected eigenvalues/vectors of hermitian matrix
!H, inout, packed banded matrix
! , out, eigenvectors
!N, in, matrix dimension
!W_space, out, eigenvalues
!L1 ordinal lowest eigenvalue
!L2 ordinal highest eigenvlaue
!Z : eigenvectors
!INFO, inout, error flag
  !USE FLOQUET
 IMPLICIT NONE
 INTEGER,
                                  INTENT(IN) :: N,L1,L2
 COMPLEX*16, DIMENSION(:,:), INTENT(INOUT) :: H
COMPLEX*16, DIMENSION(:,:), INTENT(OUT) :: Z
 DOUBLE PRECISION, DIMENSION(:), INTENT(OUT) :: W_SPACE
 INTEGER,
                                  INTENT(OUT) :: INFO
SUBROUTINE MKLSPARSE_FULLEIGENVALUES (D, DV, VALUES, ROW_INDEX, COLUMN, E_L, E_R, E_FLOQUET, U_F, INFO)
!CALCULATES THE ENERGY SPECTRUM OF THE MATRIX REPRESENTED BY VALUES, ROW_INDEX AND COLUMN
! D (IN), MATRIX DIMENSION == NUMBER OF EIGENVALUES
! DV (IN), NUMBER OF VALUES != 0
! VALUES (IN) ARRAY OF VALUES
! ROW_INDEX (IN), ARRAY OF INDICES
! COLUMN (IN), ARRAY OF COLUMN NUMBERS
                 LEFT BOUNDARY OF THE SEARCH INTERVAL
! E_L (IN),
                RIGHT BOUNDARY OF THE SEARCH INTERVAL
! E_R (IN),
! E_FLOQUET (OUT), ARRAY OF EIGENVALUES
          (INOUT) ERROR FLAG and VERBOSITY FLAG
                  O display no information
                  1 DISPLAY INFORMAITON ABOUT THE SIZE OF THE ARRAYS
                  10 DISPLAY INFORMAITON ABOUT THE ARRAYS AND THE ARRAYS
 USE FEAST
 IMPLICIT NONE
 INTEGER,
                                    INTENT(IN) :: D,DV
 COMPLEX*16,
                  DIMENSION(DV), INTENT(INOUT) :: VALUES
 INTEGER,
                  DIMENSION(DV), INTENT(INOUT) :: COLUMN
                  DIMENSION(D+1), INTENT(INOUT) :: ROW_INDEX
 INTEGER,
 DOUBLE PRECISION,
                                    INTENT(IN) :: E_L, E_R
 DOUBLE PRECISION, DIMENSION(D), INTENT(OUT) :: E_FLOQUET
 COMPLEX*16, DIMENSION(D,D), INTENT(OUT) :: U_F
 INTEGER,
                                    INTENT(INOUT) :: INFO
```

! 78 \*>

diagonal, is destroyed.

```
SUBROUTINE QUICK_SORT_INTEGERS(v,index_t,N)
  IMPLICIT NONE
  INTEGER, INTENT(IN) :: N
  INTEGER, DIMENSION(N), INTENT(INOUT) :: v
  INTEGER, DIMENSION(N), INTENT(INOUT) :: index_t
  INTEGER, PARAMETER :: NN=10000, NSTACK=8000
SUBROUTINE WRITE_MATRIX(A)
! it writes a matrix of doubles nxm on the screen
  DOUBLE PRECISION, DIMENSION(:,:) :: A
  CHARACTER(LEN=105) STRING
  CHARACTER(LEN=105) aux_char
  integer :: aux
SUBROUTINE WRITE_MATRIX_INT(A)
!it writes a matrix of integer nxm on the screen
  INTEGER, DIMENSION(:,:) :: A
SUBROUTINE COORDINATEPACKING(D,A,V,R,C,index,INFO)
  IMPLICIT NONE
  INTEGER, INTENT(IN):: D
  COMPLEX*16,DIMENSION(D,D),INTENT(IN) :: A
  COMPLEX*16,DIMENSION(D*D),INTENT(OUT) :: V
  INTEGER, DIMENSION(D*D), INTENT(OUT) :: R,C
  INTEGER, INTENT(OUT)
                       :: index
  INTEGER, INTENT(INOUT) :: INFO
SUBROUTINE APPENDARRAYS(V,B,INFO)
  COMPLEX*16, DIMENSION(:), ALLOCATABLE, INTENT(INOUT) :: V
  COMPLEX*16, DIMENSION(:),INTENT(IN) :: B
                          INTENT(INOUT) :: INFO
  INTEGER,
SUBROUTINE APPENDARRAYSI(V,B,INFO)
  INTEGER, DIMENSION(:),ALLOCATABLE, INTENT(INOUT) :: V
  INTEGER, DIMENSION(:),INTENT(IN) :: B
  INTEGER.
                          INTENT(INOUT) :: INFO
```

# SUBROUTINE VARCRCPACKING(N,DIM,UPLO,zero,A,VALUES,COLUMNS,ROWINDEX,INFO)

INTEGER, INTENT(INOUT) :: INFO,DIM CHARACTER, INTENT(IN) :: UPLO DOUBLE PRECISION, INTENT(IN) :: ZERO COMPLEX\*16,DIMENSION(N,N), INTENT(IN) :: A

COMPLEX\*16, DIMENSION(DIM), INTENT(OUT) :: VALUES INTEGER, DIMENSION(DIM), INTENT(OUT) :: COLUMNS INTEGER, DIMENSION(N+1), INTENT(OUT) :: ROWINDEX

# 15 C++ Wrappers prototypes: src/MultimodeFloquet.h

```
struct mode_c{
 double omega;
 dcmplx x,y,z;
 double phi_x,phi_y,phi_z;
  int N_Floquet;
};
struct atom_c{
 int id_system;
 int d_bare;
};
extern "C" {
 // DIMENSION OF THE MULTIMODE FLOQUET MATRIX. CALCULATED INTERNALLY
 int h_floquet_size;
  int h_floquet_c; // Floquet matrix in the bare basis
  // GENERAL INIT SUBROUTINE
 void floquetinit_qubit_c_ (atom_c *id, int *lenght_name, char * atomicspecie,
  void floquetinit_spin_c_ (atom_c *id, int *lenght_name, char * atomicspecie, double * jtotal,
 void floquetinit_alkali_c_(atom_c *id, int *lenght_name, char * atomicspecie, int * lenght_name2,
 // SET HAMILTONIAN OF SPIN-LIKE MODELS
 void sethamiltoniancomponents_c_(atom_c *id,int * nm, int * total_frequencies,int * modes_num,mod
  // BUILDING FLOQUET MATRIX OF GENERIC MODEL
       multimodefloquetmatrix_c (atom_c *id,int * nm, int * total_frequencies,
          int * modes_num,mode_c * fields, int * info);
  void get_h_floquet_c_(int * h, dcmplx * values, int* info);
         multimodefloquetmatrix_c_python_(atom_c *id,int * nm, int * total_frequencies,
          int * modes_num,mode_c * fields,int * info);
                                         (atom_c *id,int * nm, int * total_frequencies,
  void multimodefloquetmatrix_sp_c_
          int * modes_num,mode_c * fields, int * info);
 void multimodefloquetmatrix_python_sp_c_(atom_c *id,int * nm, int * total_frequencies,
          int * modes_num,mode_c * fields, int * h_f,int * info);
 void get_h_floquet_sp_c_(int * h_f, dcmplx * values, int * row_index, int * column, int * info);
 // CALCULATE THE SPECTRUM OF THE FLOQUET HAMILTONIAN
        lapack_fulleigenvalues_c_(dcmplx * u_f,int * h_floquet_size,
           double * e_floquet,int *info);
 void mklsparse_fulleigenvalues_c_(int * h_floquet_size,
           double * e_1,double * e_r,double * e_floquet,dcmplx *U_F, int * info);
  void matmul_c_(int * op, dcmplx * a, int * ra, int * ca,
          dcmplx * b, int * rb, int * cb, dcmplx * c,int * info);
  // CONTSRUCTION OF THE TIME-EVOLUTION OPERATOR
              multimodetransitionavg_c_(int * h_floquet_size,int * nm,mode_c * fields,
      int * modes_num,dcmplx * U_F,double * e_floquet,int * d_bare,double * p_avg,int *info);
 void multimodefloquettransformation_c_(int * h_floquet_size,int * nm,int * modes_num,
      dcmplx * U_F,double * e_floquet,int * d_bare,mode_c * fields,double * t1,dcmplx * U_B2D,int *
 void multimodemicromotion_c_(atom_c *id,int * h_floquet_size,int * nm,int * modes_num,
      dcmplx * U_F,double * e_floquet,int * d_bare,mode_c * fields,double * t1,dcmplx * U_B2D,int *
  void multimodetimeevolutionoperator_c_(int * h_floquet_size,int * nm,int * modes_num,
      dcmplx * U_F,double * e_floquet,int * d_bare,mode_c * fields,double * t1,double * t2,dcmplx *
```

```
void timeevolutionoperator_c_(atom_c *id, int *d_bare, int *nm, int *nf, int * modes_num,
    mode_c *field, double *t1, double *t2, dcmplx *U, int *info);
// DEFINITION OF DRESSED BASIS
void
                dressedbasis_c_(int * h_floquet_size,atom_c *id,int * nm,
                                int * modes_num,mode_c * fields, dcmplx * U_FD,
                                double * e_dressed,int * info);
void dressedbasis_subset_c_(atom_c *id , int * dressingfloquetdimension,
                             int * dressingfields, int * nm, int * dressingfields_indices,
                             int * modes_num,mode_c * fields, dcmplx * U_FD,
                             double * e_dressed,int * info);
void dressedbasis_subset_sp_c_(atom_c * id, int * dressingfloquetdimension,
                                int * dressingfields,int * nm, int * dressingfields_indices,
                                int * modes_num,mode_c * fields, dcmplx * U_FD,
                                double * e_dressed,int * info);
void dressedbasis_sp_c_(int h_floquet_size, atom_c *id, int * nm, int * modes_num,
                         mode_c * fields, dcmplx * U_FD, double * e_dressed,
                         int * info);
void micromotionfourierdressedbasis_c_(atom_c *id , int *DF, int * dressingfields_indices,
                                       int * nm, int * modes_num, int *nf, mode_c * fields,
                                       int * nd,dcmplx * U_FD, double *e_dressed,int * info);
void micromotiondressedbasis_c_(atom_c *id , int * modes_num, int * dressingfields_indices,
                                mode_c * fields, double T1, dcmplx * U, int * info);
// UTILITY FUNCTIONS: WRITE MATRICES ON THE SCREEN
void write_matrix_c_(double *A,int * A_dim);
void rec_write_matrix_c_(double *A,int * A_dim1, int * A_dim2);
// deallocate all arrays allocated with fortran
void deallocateall_c_(int *id);
```

# 16 Python Wrappers prototypes

OPENMMF includes a set of wrappers to use the library with Python, defined in the file <code>src/openmmf.py</code>, The wrapper use CTYPES to pass on parameters to the C++ wrappers. In order for this to work, you should make sure that the openmmf dynamical library is loaded correctly, e.g. using the instruction: openmmfC=ctypes.CDLL('../lib/libmultimodefloquet.so') near the top of <code>src/openmmf.py</code>. Make sure the path is correct.

The wrappers were developed and tested using: Python 3.7.6, ctypes 1.1.0, numpy 1.16.2, scipy 1.4.1 and matplotlib 3.0.3.

```
#_____
  // GENERAL CLASSES
              ______
class atom_c_T(ctypes.Structure):
  _fields_ = [
           ("id_system", c_int),
           ("d_bare", c_int)
#-----
class mode_c_T(ctypes.Structure):
  c_dcmplx = ctypes.c_double*2
  _fields_ = [
           ("omega", c_double),
                 c_dcmplx),
           ("x",
           ("y",
                  c_dcmplx),
c_dcmplx),
           ("z",
           ("phi_x", c_double),
           ("phi_y",
                    c_double),
           ("phi_z",
                    c_double),
           ("N_Floquet", c_int)
        ]
// GENERAL INIT SUBROUTINE
openmmf.floquetinit(id,*argsv,info):
     Parameters: id: atom_c_T
               Identifies the type of system
             *argsv: array
               Depending on the system of inters
             info: int
               Error/success flag
This function supports the following calls:
openmmf.floquetinit(id,qubit,info=info)
    qubit: str
         'qubit' to define a two-level system
    info: int
        Error/success flag
openmmf.floquetinit(id,alkali,manifold,info=info)
     alkali: str
```

```
'87Rb', '23Na' atomic specie
       manifold: str
               Manifold of the hyperfine splitting
              'L' : Lower with total angular moment F = I-J
              'U' : Upper with total angular momentum F= I+J
              'B' : both manifods
      info: int
           Error/success flag
openmmf.floquetinit(id,system,L,info=info)
       system: str
              'spin' single particle with total angular momentum 2*L
              'lattice' quantum system with L sites/states
       L: np.double
              define
      info: int
           Error/success flag
   EVALUATE THE HAMILTONIAN COMPONENTS OF PRE-DEFINED SYSTEMS.
   ._____
openmmf.sethamiltoniancomponents(id,modes_num,fields,info):
       id: atom_c_T instance
       modes_num: 1D np.array([],dtype=np.int32)
             define the number of fundamental frequencies and modes
             the total number of modes is nm = np.sum(modes_num)
       fields: instance of openmmf.mode_c_T*nm
             equivalent to the FORTRAN data derived type FIELDS
       info: int
           Error/success flag
#-----
# // BUILDING FLOQUET MATRIX OF GENERIC MODEL
openmmf.multimodefloquetmatrix(id,modes_num,fields,info):
       id: atom_c_T instance
       modes_num: 1D np.array([],dtype=np.int32)
             define the number of fundamental frequencies and modes
             the total number of modes is nm = np.sum(modes_num)
       fields: instance of openmmf.mode_c_T*nm
             equivalent to the FORTRAN data derived type FIELDS
       info: int
           Error/success flag
openmmf.get_h_floquet(h_floquet_size, info):
       h_floquet_size: int
             size of the multimode Floquet matrx
       returns the multimode floquet matrix
openmmf.multimodefloquetmatrix_sp(id,modes_num,fields,info):
       id: atom_c_T instance
       modes_num: 1D np.array([],dtype=np.int32)
             define the number of fundamental frequencies and modes
             the total number of modes is nm = np.sum(modes_num)
       fields: instance of openmmf.mode_c_T*nm
             equivalent to the FORTRAN data derived type FIELDS
       info: int
           Error/success flag
```

```
openmmf.get_h_floquet_sp(h_floquet_size, info):
       h_floquet_size: int
             size of the multimode Floquet matrx
       returns VALUE, ROW, COLUMN arrays to represent a sparse multimode floquet matrix
# // CALCULATE THE SPECTRUM OF THE FLOQUET HAMILTONIAN
#-----
openmmf.lapack_fulleigenvalues(U_F,h_floquet_size,e_floquet,info):
       U_F: 1D np.array([],dtype=np.complex)
            h_floquet_size x h_floquet_size matrix of eigenvectors
       h_floquet_size: int
              size of the multimode Floquet matrx
       e_floquet: 1D np.array([],dtype=np.complex)
              array of size h_floquet_size containing the eigenvalues of
              the multimode Floquet Hamiltonian
       info: int
           Error/success flag
   EVALUATES THE TIME AVERAGE TRANSITIONS PROBABILITIES
open \verb|mmf.mu|| timo detransition avg(h\_floquet\_size, fields, modes\_num, U\_F, e\_floquet, d\_bare, p\_avg, info):
       h_floquet_size: int
             size of the multimode Floquet matrx
       fields: instance of openmmf.mode_c_T*nm
             equivalent to the FORTRAN data derived type FIELDS
       modes_num: 1D np.array([],dtype=np.int32)
             define the number of fundamental frequencies and modes
              the total number of modes is nm = np.sum(modes_num)
       U_F: 1D np.array([],dtype=np.complex)
            h_floquet_size x h_floquet_size matrix of eigenvectors
       e_floquet: 1D np.array([],dtype=np.complex)
              array containing the eigenvalues of the multimode Floquet
             Hamiltonian
       d_bare: int
            Hilbert space dimension of the static system
       p_avg: 1D np.array([],dtype=np.double)
            d_bare x d_bare Matrix of the time-average state occupationrs
       info: int
            Error/success flag
                           ______
# FOURIER COMPONENTS OF THE TRANSFORMATION BETWEEN THE DRESSED AND THE BARE BASIS
# U_B2D is of dimension [D_bare*D_floquet]
openmmf.multimodefloquettransformation(modes_num, U_F,e_floquet,d_bare,fields,t1, U_B2D,info):
       modes_num: 1D np.array([],dtype=np.int32)
              define the number of fundamental frequencies and modes
              the total number of modes is nm = np.sum(modes_num)
       U_F: 1D np.array([],dtype=np.complex)
            h_floquet_size x h_floquet_size Matrix of eigenvectors
       e_floquet: 1D np.array([],dtype=np.complex)
              array containing the eigenvalues of the multimode Floquet
             Hamiltonian
       d_bare: int
            Hilbert space dimension of the static system
       fields: instance of openmmf.mode_c_T*nm
              equivalent to the FORTRAN data derived type FIELDS
       t1: np.double
            instant of time to evaluate the micromotion operator
       U_B2D: 1D np.array([],dtype=np.complex)
```

```
#-----
# CALCULATE THE MICROMOTION OPERATOR
# U_B2D is of dimension [D_bare*D_bare]
openmmf.multimodemicromotion(id,h_floquet_size,modes_num,U_F,e_floquet,d_bare,fields,t1, U_B2D,info)
       id: atom_c_T instance
       h_floquet_size: int
             size of the multimode Floquet matrx
       modes_num: 1D np.array([],dtype=np.int32)
             define the number of fundamental frequencies and modes
             the total number of modes is nm = np.sum(modes_num)
       U_F: 1D np.array([],dtype=np.complex)
           h_floquet_size x h_floquet_size Matrix of eigenvectors
       e_floquet: 1D np.array([],dtype=np.complex)
             array containing the eigenvalues of the multimode Floquet
             Hamiltonian
       d_bare: int
            Hilbert space dimension of the static system
       fields: instance of openmmf.mode_c_T*nm
             equivalent to the FORTRAN data derived type FIELDS
       t1: np.double
           instant of time to evaluate the micromotion operator
       U_B2D: 1D np.array([],dtype=np.complex)
           d_bare x d_bare Matrix of the time-average state occupationrs
       info: int
           Error/success flag
#-----
# COMP. ROUTINE: EVALUATE THE TIME EVOULUTION OPERATOR BETWEEN T1 AND T2
# USING THE FOURIER DECOMPOSITION
# OF THE MICROMOTION OPERATOR, WHICH IS STORE IN U_F.
#-----
def multimodetimeevolutionoperator(h_floquet_size,modes_num,U_F,e_floquet,d_bare,
          fields,t1,t2,U_AUX,info):
       h_floquet_size: int
             size of the multimode Floquet matrx
       modes_num: 1D np.array([],dtype=np.int32)
             define the number of fundamental frequencies and modes
             the total number of modes is nm = np.sum(modes_num)
       U_F: 1D np.array([],dtype=np.complex)
           h_floquet_size x h_floquet_size Matrix of eigenvectors
       e_floquet: 1D np.array([],dtype=np.complex)
             array containing the eigenvalues of the multimode Floquet
             Hamiltonian
       d bare: int
            Hilbert space dimension of the static system
       fields: instance of openmmf.mode_c_T*nm
             equivalent to the FORTRAN data derived type FIELDS
       t1: np.double
           instant of time to evaluate the time-evolution operator
       t2: np.double
           instant of time to evaluate the time-evolution operator
       U_AUX: 1D np.array([],dtype=np.complex)
           d_bare x d_bare Matrix of the time-evolution operator
       info: int
```

d\_bare x d\_bare Matrix of the time-average state occupationrs

info: int

Error/success flag

Error/success flag

```
# DRIVER ROUTINE: EVALUATE THE TIME EVOULUTION OPERATOR BETWEEN T1 AND T2
#-----
def timeevolutionoperator(id,d_bare,modes_num,fields,t1,t2,U,info):
       id: atom_c_T instance
       d_bare: int
            Hilbert space dimension of the static system
       modes_num: 1D np.array([],dtype=np.int32)
             define the number of fundamental frequencies and modes
             the total number of modes is nm = np.sum(modes_num)
       fields: instance of openmmf.mode_c_T*nm
             equivalent to the FORTRAN data derived type FIELDS
       t1: np.double
            instant of time to evaluate the time evolution operator
       t2: np.double
            instant of time to evaluate the time evolution operator
       U: 1D np.array([],dtype=np.complex)
            d_bare x d_bare Matrix of the time-evolution operator
       info: int
           Error/success flag
#-----
# // DEFINITION OF DRESSED BASIS WITH ALL FIELDS
def dressedbasis(h_floquet_size,id,modes_num,fields,U_FD,e_dressed,info):
       h_floquet_size: int
             size of the multimode Floquet matrx
       id: atom_c_T instance
       modes_num: 1D np.array([],dtype=np.int32)
             define the number of fundamental frequencies and modes
             the total number of modes is nm = np.sum(modes_num)
       fields: instance of openmmf.mode_c_T*nm
             equivalent to the FORTRAN data derived type FIELDS
       U_FD: 1D np.array([],dtype=np.complex)
            d_bare x d_bare Matrix of the time-average state occupationrs
       e_dressed: 1D np.array([],dtype=np.complex)
             array containing the eigenvalues of the multimode Floquet
             Hamiltonian
       info: int
           Error/success flag
def dressedbasis_sp(h_floquet_size,id,modes_num,fields,U_FD,e_dressed,info):
       h_floquet_size: int
             size of the multimode Floquet matrx
       id: atom_c_T instance
       modes_num: 1D np.array([],dtype=np.int32)
             define the number of fundamental frequencies and modes
             the total number of modes is nm = np.sum(modes_num)
       fields: instance of openmmf.mode_c_T*nm
             equivalent to the FORTRAN data derived type FIELDS
       U_FD: 1D np.array([],dtype=np.complex)
            d_bare x d_bare Matrix of the time-average state occupationrs
       e_dressed: 1D np.array([],dtype=np.complex)
             array containing the eigenvalues of the multimode Floquet
             Hamiltonian
       info: int
           Error/success flag
```

```
# // DEFINITION OF DRESSED BASIS WITH A SUBSET OF THE FIELDS
def dressedbasis_subset(id,dressingfields_indices,modes_num,fields,U_FD,e_dressed,info):
       id: atom_c_T instance
       dressingfields_indices: 1D np.array([],dtype=np.int32)
              define the index of dressing fields
       modes_num: 1D np.array([],dtype=np.int32)
              define the number of fundamental frequencies and modes
             the total number of modes is nm = np.sum(modes_num)
       fields: instance of openmmf.mode_c_T*nm
             equivalent to the FORTRAN data derived type FIELDS
       U_FD: 1D np.array([],dtype=np.complex)
            h_floquet_size x h_floquet_size Matrix of eigenvectors
       e_dressed: 1D np.array([],dtype=np.complex)
              array containing the eigenvalues of the multimode Floquet
              Hamiltonian
       info: int
            Error/success flag
def dressedbasis_subset_sp(id,dressingfields_indices,modes_num,fields,U_FD,e_dressed,info):
       id: atom_c_T instance
       dressingfields_indices: 1D np.array([],dtype=np.int32)
              define the index of dressing fields
       modes_num: 1D np.array([],dtype=np.int32)
             define the number of fundamental frequencies and modes
             the total number of modes is nm = np.sum(modes_num)
       fields: instance of openmmf.mode_c_T*nm
             equivalent to the FORTRAN data derived type FIELDS
       U_FD: 1D np.array([],dtype=np.complex)
            h_floquet_size x h_floquet_size Matrix of eigenvectors
       e_dressed: 1D np.array([],dtype=np.complex)
             array containing the eigenvalues of the multimode Floquet
             Hamiltonian
       info: int
            Error/success flag
     _____
# EVALUATE THE FOURIER COMPONENTS OF THE MICROMOTION OPERATOR USING THE DRESSING FIELDS
#-----
def micromotionfourierdressedbasis(id,dressingfields_indices,modes_num,fields,
         U_FD,e_dressed,info):
       id: atom_c_T instance
       dressingfields_indices: 1D np.array([],dtype=np.int32)
             define the index of dressing fields
       modes_num: 1D np.array([],dtype=np.int32)
             define the number of fundamental frequencies and modes
             the total number of modes is nm = np.sum(modes_num)
       fields: instance of openmmf.mode_c_T*nm
              equivalent to the FORTRAN data derived type FIELDS
       U_FD: 1D np.array([],dtype=np.complex)
       e_dressed: 1D np.array([],dtype=np.complex)
              array containing the eigenvalues of the multimode Floquet
             Hamiltonian
       info: int
            Error/success flag
```

```
# EVALUATE THE MICROMOTION OPERATOR USING THE DRESSING FIELDS
#-----
def micromotiondressedbasis(id,modes_num,dressingfields_indices,fields,t1,U,info):
      id: atom_c_T instance
      modes_num: 1D np.array([],dtype=np.int32)
           define the number of fundamental frequencies and modes
            the total number of modes is nm = np.sum(modes_num)
      dressingfields_indices: 1D np.array([],dtype=np.int32)
           define the index of dressing fields
      fields: instance of openmmf.mode_c_T*nm
           equivalent to the FORTRAN data derived type FIELDS
      t1: np.double
          instant of time to evaluate the micromotion operator
      U : 1D np.array([],dtype=np.complex)
      info: int
          Error/success flag
#-----
# DEALLOCATE ALL MEMORY ARRAYS
#-----
def deallocateall(id):
      id: atom_c_T instance
```