


CSEC 202 Reverse Engineering Fundamentals



The Lifetime of Hello World



The Lifetime of hello.c

```
#include <stdio.h>
int main()
    printf("hello, world\n");
    return 0;
```



The Lifetime of hello.c – ASCII

#	i	n	С	1	u	d	е	SP	<	s	t	d	i	0		
35	105	110	99		117	100	101	32	60	115	116	100	105	111	46	
h	>	\n	\n	i	n	t	SP	m	a	i	n	()	\n	{	
104	62	10	10	105	110	116	32	109	97	105	110	40	41	10	123	
\n	SP	SP	SP	SP	р	r	i	n	t	f	("	h	е	1	
10	32	32	32		112										108	
1	0	,	SP	W	0	r	1	d	\	n	")	;	\n	SP	
108	111	44	32	119	111	114	108	100	92	110	34	41		10	32	
SP	SP	SP	r	е	t	u	r	n	SP	0	;	\n	}	\n		
32	32	32	114	101	116	117	114	110	32	48	59	10	125	10		

The ASCII text representation of hello.c.

ASCII stands for American Standard Code for Information Interchange. Computers can only understand numbers, so an ASCII code is the numerical representation of a character such as 'a' or '@' or an action of some sort.



The Lifetime of hello.c – ASCII - Hex

```
23 69 6E 63 6C 75 64 65 20 3C 73 74 64 69 6F 2E 68 3E 0A 0A 69 6E 74 20 6D 61 69 6E 28 29 20 0A 7B 0A 20 20 20 20 70 72 69 6E 74 66 28 22 68 65 6C 6C 6F 2C 20 77 6F 72 6C 64 5C 6E 22 29 3B 0A 20 20 20 20 72 65 74 75 72 6E 20 30 3B 0A 7D
```

https://www.rapidtables.com/convert/number/ascii-to-binary.html



The Lifetime of hello.c – ASCII - Binary

```
01101111 00101110 01101000 00111110 00001010 00001010 01101001
00101000 00101001 00100000 00001010 01111011 00001010 00100000
01101100 01100100 01011100 01101110 00100010 00101001 00111011
00001010 00100000 00100000 00100000 00100000 01110010 01100101
01110100 01110101 01110010 01101110 00100000 00110000 00111011
00001010 01111101
```

Rochester Institute	Hex I				Нех	Dec	Char	Hex	Dec	Char	Hex	Dec	Char
of Technology of Dubai	0x00	0	NULL	null	0x20	32	Space	0x40	64	@	0x60	96	
	0x01	1	No. of Street, or other Persons	Start of heading	0x21	33	1	0x41	65	A	0x61	97	a
	0x02	2		Start of text	0x22	34		0x42	66	В	0x62	98	b
	0x03	3		End of text	0x23		#	0x43		C	0x63	99	C
	0×04	4	The same of the same	End of transmission	0x24	36	\$	0x44	68	D	0x64		d
	0x05		State	Enquiry	0x25		%	0x45		E	0x65		е
The ASCII table is a character-encoding	0x06	0.070		Acknowledge	0x26		&	0x46	TO COTTO	F	0x66		f
	0x07			Bell	0x27		**	0x47	71	G	0x67		g
standard for electronic communication.	0x08	8	BS	Backspace	0x28		(0x48		H	0x68		h
ASCII stands for American Standard	0x09	9	TAB	Horizontal tab	0x29)	0x49		I	0x69		i
Code for Information Interchange. It	A0x0	10	LF	New line	0x2A		*	0x4A		J	0x6A		J
assigns a unique decimal number to	0x0B	11	VT	Vertical tab Form Feed	0x2B		+	0x4B		K	0x6B		K
	0x0C	12	FF	Carriage return	0x2C		,	0x4C		L	0x6C		1
different characters, including letters,	0x0D 0x0E	13	CR	Shift out	0x2D 0x2E		_	0x4D 0x4E		M	0x6D 0x6E		m
digits, punctuation marks, and control	0x0E	15	SI	Shift in	0x2E		,	0x4E 0x4F	700000	O	0x6E	0.0000000000000000000000000000000000000	0
characters. For instance, in ASCII, the	0x10	16	-	Data link escape	0x2F		0	0x4r		P	0x70		p
uppercase letter "A" is represented by	0x11	17		Device control 1	0x31		1	0x51	111419241	Q	0x71		q
	0x12	18	DC2	Device control 2	0x32	50	2	0x52	82	R	0x72	114	r
the number 65, while the lowercase "a"	0x13	19	DC3	Device control 3	0x33	51	3	0x53	83	S	0x73	115	S
is 97. Each entry in the ASCII table	0x14	20	DC4	Device control 4	0x34	52	4	0x54	84	T	0x74	116	t
corresponds to a byte in the computer's	0x15	21	NAK	Negative ack	0x35	53	5	0x55	85	U	0x75	117	u
memory, with the standard ASCII using	0x16	22	SYN	Synchronous idle	0x36	54	6	0x56	86	V	0x76	118	V
	0x17	23	ETB	End transmission block	0x37	55	7	0x57	87	W	0x77	119	W
7 bits of the byte, giving it the ability to	0x18	24	CAN	Cancel	0x38	56	8	0x58	88	X	0x78	120	x
represent 128 unique characters.	0x19	25	EM	End of medium	0x39		9	0x59		Y	0x79		У
ASCII is fundamental in computers and	0x1A			Substitute	0x3A		:	0x5A		Z	0x7A		Z
is used to translate human-readable text				Escape	0x3B		;	0x5B		[0x7B		{
	0x1C			File separator	0x3C		<	0x5C		\	0x7C		
into a format that machines can			GS	Group separator	0x3D		=	0x5D]	0x7D		}
process.	0x1E		RS	Record separator	0x3E		>	0x5E			0x7E		
	0x1F	31	US	Unit separator	0x3F	63	?	0x5F	95		0x7F	127	DEL


Hands On – IDA – Static Analysis 101:

Compile the hello.c file by typing the following command in the terminal:

gcc hello.c -o hello

- This command creates an executable file named hello.
- Open IDA and load the newly created binary hello.
- In IDA, search for the string "hello, world" to find where it appears in the code.
- Note down the memory address where the string "hello, world" is located.
- Observe and write down how the string is represented in memory by switching to the Hex View in IDA.
- Determine whether the compiled binary is 64-bit or 32-bit. This can be identified by examining the file's properties or analyzing the architecture-specific details within IDA.

The Compilation System: gcc hello.c -o hello



The compilation system.




The Compilation System: gcc hello.c -o hello

- The four phases of compiling a C program involve different programs:
- Preprocessor (cpp): Prepares the source code by processing directives like #include.
- Compiler (gcc / ccl): Transforms the preprocessed code into assembly language.
- Assembler (as): Converts assembly language into machine code (object files).
- Linker (Id): Combines object files and libraries into a final executable.

Hardware Organization of a System

Hardware organization of a typical system. CPU: central processing unit, ALU: arithmetic/logic unit, PC: program counter, USB: Universal Serial Bus.




The Von Neumann Architecture



The Von Neumann Architecture

Von Neumann Architecture refers to a design model for computers where the processing unit, memory, and input-output devices are interconnected through a single, central system bus.

This architecture was first proposed by John von Neumann, a Hungarian-American mathematician and physicist, in the mid-20th century.





Check your understanding:

What are the four main components of Von Neumann Architecture?

- a) Central Processing Unit (CPU), Registers, Cache, And Input-Output (I/O) Devices
- b) Central Processing Unit (CPU), Memory (RAM And Secondary Memory), Input-Output (I/O) Devices, And System Bus
- Arithmetic Logic Unit (ALU), Control Unit (CU), Memory, And System Bus
- d) Central Processing Unit (CPU), Primary Memory, External Storage Devices, And Input-Output (I/O) Devices



Hardware Organization of a System:

There are four main components within the Von Neumann Architecture. These components work together to enable processing, storage, and communication within the computer system. They are:


- **Central Processing Unit (CPU):** The part of a computer that carries out instructions and performs arithmetic, logical, and control operations.
- **Memory:** A place where the computer stores and retrieves data and instructions. Memory is divided into two types: primary memory, such as Random Access Memory (RAM), and secondary memory, like hard disk drives and solid-state drives.
- **Input-Output (I/O) devices:** Components responsible for interfacing the computer with the external world. Examples of I/O devices include keyboards, mice, printers, and monitors.
- **System Bus:** A communication pathway that connects the CPU, memory, and I/O devices, enabling data and control signals to flow between these components.

The smooth interaction of these four components contributes towards the efficient functioning of a computer system built on the principles of Von Neumann Architecture.



The components of (CPU) include:

- Arithmetic Logic Unit (ALU): Conducts mathematical and logical operations.
- Control Unit (CU): Interprets instructions from memory and manages execution.
- Registers: Fast storage areas for temporary data, including the Program Counter (PC), which holds the address of the next instruction.
- Cache: Stores commonly accessed information to expedite access.
- Bus Interface Unit: Facilitates data communication between the CPU and other components.




The components of (CPU) include:

- Clock: Synchronizes the operation of CPU components with a constant timing signal.
- Instruction Decoder: Converts instructions into signals for the CPU.
- Memory Management Unit (MMU): Oversees memory hierarchy and access.
- Floating-Point Unit (FPU): Specializes in processing floating-point operations.
- Program Counter (PC)/Instruction Pointer (IP): Contains the address of the current instruction being executed or to be executed next.



ALU (Arithmetic Logic Unit):


- A crucial component within the CPU.
- Performs computing functions involving integers.
- Arithmetic Operations:
 - Addition, subtraction, multiplication, division.
- Logic Operations:
 - Comparisons (e.g., less than, greater than, equal to).
- Numeric Processing:
 - All data reduced to numeric form.
- Constant Operation Handling:
 - Always active, handling operations rapidly.
- Result Storage:
 - Stores results in registers, memory, or outputs.



Basic CPU Operations:


- Load: Transfer data from memory to a register within the CPU.
- Store: Transfer data from a CPU register back into memory.
- Operate: Perform arithmetic or logical operations using the ALU and store results in a register.
- **Jump:** Change the flow of execution by updating the PC with a new address.

CPU-BUS-Memory:



Memory Read Transition (1/3)

CPU places address A on the memory bus







Compose an Assembly command for the x86 32-bit architecture that writes the value located at memory address A into the accumulator



MOV EAX, DWORD PTR [A]

- MOV is the mnemonic for "move."
- **EAX** is the 32-bit accumulator register.
- DWORD PTR specifies that you are working with a double-word (32 bits) of data.
- [A] represents the memory address labeled as "A" from which you want to move

Is MOV EAX, [A] correct?


Yes. In assembly language, the instruction MOV EAX, DWORD PTR [A] explicitly tells the assembler that EAX should be loaded with a 32-bit value from the memory address labeled A. The **DWORD PTR** part is a type specifier that clarifies the size of the operand being moved.

On the other hand, MOV EAX, [A] also moves data from memory into EAX, but here the size of the data (in this case, 32 bits because EAX is a 32-bit register) is implied by the destination operand EAX. The assembler assumes that you are moving a value size that matches the destination register size.



Memory Read Transition (2/3)


Main memory reads A from the memory bus, retrieves word x, and places it on the bus





Memory Read Transition (3/3)


CPU reads word x from the bus and copies it into register %rax





Memory Write Transition (1/3)


CPU puts memory address A on the bus, and main memory reads it, awaiting the corresponding data word



_

Memory Write Transition (2/3)


CPU puts data word 'y' on the bus





Memory Write Transition (3/3)

Main memory reads data word 'y' from the bus and stores it at address A







Perform data manipulation tasks in x86 assembly language:

Load Data from Memory:

- Retrieve the data stored at memory address "A"
- Place this data into the 'eax' register.

1. Perform Arithmetic Operation:

- Add the value 10 to the data stored in the "eax" register.
- Store the result back in the "eax" register.

2. Write the Result Back to Memory:

- Send the result (the updated value in 'eax') back to the same memory address "A"
- 3. Determine ALU Operation: Explain the role of the ALU in these operations.

section .data A dd 42

section .text global main

main:

mov eax, dword [A] add eax, 10 mov dword [A], eax

The **PTR** keyword is optional and often omitted when the operand size is clear from the context. Including PTR is more about making the intention explicit for clarity, which can be especially useful in more complex assembly language programs where the operand size might not be immediately apparent.


section .bss

Running the hello Program

Figure 1.5

Reading the hello command from the keyboard.

Typing the Command (Figure 1.5): When you type ./hello at the keyboard, the shell program reads each keystroke and stores the command in memory. The keystrokes are processed by the CPU after being received by the USB controller for the keyboard.





Running the hello Program

Loading the Program (Figure 1.6): The hello program is loaded from the disk into the main memory using Direct Memory Access (DMA). This process bypasses the CPU, allowing the data to move directly from the disk to the main memory.





Figure 1.6 Loading the executable from disk into main memory.



Running the hello Program

Executing the Program (Figure 1.7): With the program loaded into main memory, the CPU begins executing its instructions. It copies the "hello, world\n" string from memory into the CPU's registers and then to the display through the graphics adapter, resulting in the text appearing on your screen.



Writing the output string from memory to the display.



CPU Design & Architecture



Levels of Abstraction in Computer Systems

The software layers include applications, algorithms, programming languages, assembly language, and machine code. Below these are the hardware layers: the Instruction Set (ISA), is Architecture which implemented by the microarchitecture, followed by the gates and registers made from transistors, and ultimately grounded in physics. The division between software and hardware is also highlighted, with ISA serving as a bridge between the two.

Increasing order of Complexity

Abstraction

order of

Increasing

Application Algorithm Software **Programming Language Assembly Language** Machine Code Instruction Set Architecture Micro Architecture Hardware Gates/Registers **Devices (Transistors) Physics**

Layers of Abstraction

The Instruction Set Architecture (ISA)

Have you ever wondered how your software programs tell your computer what to do?

- The ISA acts as an interface between the hardware and the software, specifying both what the processor is capable of doing as well as how it gets done.
 - **Instructions:** The actual commands that tell the CPU what operations to perform, such as arithmetic operations, moving data, or controlling other hardware functions.
 - **Registers:** Small, fast storage locations in the CPU that instructions use to operate quickly on data.
 - Data Types: Defines the types of data the CPU can process, like integers, floating-point numbers, and others.
 - **Addressing Modes:** Methods for specifying operands for the CPU instructions.
 - I/O Model: Defines how the CPU interacts with the system's input/output mechanisms.





The Instruction Set Architecture (ISA)

Have you ever wondered how your software programs tell your computer what to do?


- The ISA acts as an interface between the hardware and the software, specifying both what the processor is capable of doing as well as how it gets done.
 - **Instructions:** The actual commands that tell the CPU what operations to perform, such as arithmetic operations, moving data, or controlling other hardware functions.
 - **Registers:** Small, fast storage locations in the CPU that instructions use to operate quickly on data.
 - Data Types: Defines the types of data the CPU can process, like integers, floating-point numbers, and others.
 - **Addressing Modes:** Methods for specifying operands for the CPU instructions.
 - I/O Model: Defines how the CPU interacts with the system's input/output mechanisms.

The Instruction Set Architecture (ISA)

Microarchitecture:

Microarchitecture, sometimes referred to as computer organization, is essentially how a particular ISA is translated into an actual silicon design, or the physical circuitry, on a processor. It's the layer that gives the ISA a physical form and function.

This includes the design of various subsystems such as the arithmetic logic unit (ALU), control unit (CU), memory hierarchies (registers, L1/L2/L3 caches), and more.



The Instruction Set Architecture (ISA)

Have you ever wondered how your software programs tell your computer what to do?

Example ISAs:


Intel x86: One of the most common ISAs for desktops and laptops, known for a complex set of variable-length instructions (**CISC**).

ARM: Used in most smartphones and tablets, known for its simple, fixed-length instructions designed for efficiency (**RISC**).

MIPS: Another RISC ISA often used in academic settings for teaching due to its simplicity and regularity.

•





https://www.intel.com/content/www/us/en/developer/articles/technical/intel-sdm.html



CISC and RISC

Different Processor Design Methodologies

CISC - Complex Instruction Set Computer

RISC - Reduced Instruction Set Computer

Complex Instruction Set (CISC)

Reduced Instruction Set (RISC)





CISC and RISC

RSIC: ARM Assembly Instructions	CISC: x86 Assembly Instruction
LDR R3, [R3] ADDS R2, R3, #1 STR R2, [R3]	INC dword ptr [eax]

- In ARM, it requires three separate instructions to load the value into a register (LDR), increment the register (ADD), and store the value back into memory (STR).
- In contrast, x86 can increment a value in memory directly with a single instruction like INC or ADD, thanks to its capability to perform certain operations directly on memory without the need for a register intermediary.

CISC and RISC

Complexity: CISC has complex instructions capable of performing multiple operations in one instruction, while RISC has simpler, more uniform instructions.

Execution Speed: RISC typically executes instructions faster due to their simplicity, whereas CISC may take more cycles per instruction due to complexity.

Instruction Length: CISC instructions vary in length, whereas RISC instructions are of a fixed size.

Number of Instructions: A task might require fewer instructions in CISC due to their complexity, but more in RISC.

Hardware Design: RISC design is generally simpler, leading to potentially more efficient use of the silicon area.

Usage: CISC is common in personal computers (e.g., Intel's x86 architecture), while RISC is widely used in mobile devices (e.g., ARM architecture).



Registers



Registers

Registers in a CPU are a key element of the Instruction Set Architecture (ISA) because they are the fastest type of memory where the CPU stores and retrieves the data that is immediately needed for execution.

The ISA defines:

- The number and size of registers available.
- The specific functions of each register (e.g., data, address, general-purpose, or special-purpose registers).
- How instructions reference these registers for performing operations.

BASIC PROGRAM EXECUTION REGISTERS

IA-32 architecture provides 16 basic program execution registers for use in general system and application programing. These registers can be grouped as follows:

- 1. General-purpose registers: These eight registers are available for storing operands and pointers.
- 2. Segment registers: These registers hold up to six segment selectors.
- 3. EFLAGS (program status and control) register: The EFLAGS register report on the status of the program being executed and allows limited (applicationprogram level) control of the processor.
- 4. EIP (instruction pointer) register: The EIP register contains a 32-bit pointer to the next instruction to be executed.

BASIC PROGRAM EXECUTION REGISTERS




Figure 3-4. General System and Application Programming Registers

general purpose


%esi

%edi

%esp

%ebp

Overview of 32-bit general-purpose registers in x86 architecture: EAX, EBX, ECX, EDX, ESI, EDI, EBP, ESP. Primary uses: storing operands for operations, address calculations, and memory pointers.



16-bit virtual registers

(backwards compatibility)

%si

%di

%sp

gd&

stack pointer base pointer

destination

index

index

The 32-bit general-purpose registers EAX, EBX, ECX, EDX, ESI, EDI, EBP, and ESP are provided for holding the following items:

- Operands for logical and arithmetic operations.
- Operands for address calculations.
- Memory pointers.

Although all of these registers are available for general storage of operands, results, and pointers, caution should be used when referencing the **ESP** register.

The ESP register holds the stack pointer and as a general rule should not be used for another purpose.

In the x86 architecture, each general-purpose register has typical uses:

- 1. EAX: Accumulator for operands and results; often used in arithmetic operations.
- 2. EBX: Base register; often used in indexed addressing.
- **3. ECX:** Counter for string and loop operations.
- 4. EDX: Data register; extends the accumulator for certain operations.
- **5. ESI:** Source index for string operations.
- **6. EDI:** Destination index for string operations.
- 7. EBP: Base pointer for stack frames.
- **8. ESP:** Stack pointer; points to the top of the stack.

The registers have been extended in the x86-64 architecture, indicated by an 'R' prefix instead of 'E'. For example, the 32-bit 'EAX' register becomes 'RAX' in 64bit, expanding from 32 bits to 64 bits. This allows for more efficient processing and handling of larger data types and values, enabling more complex computations and addressing a larger memory space.

x86-64 Integer Registers

%rax	%eax	%r8	%r8d
%rbx	%ebx	%r9	%r9d
%rcx	%ecx	%r10	%r10d
%rdx	%edx	%r11	%r11d
%rsi	%esi	%r12	%r12d
%rdi	%edi	%r13	%r13d
%rsp	%esp	%r14	%r14d
%rbp	%ebp	%r15	%r15d



Segment Register

The segment registers (CS, DS, SS, ES, FS, and GS) hold 16-bit segment selectors. A segment selector is a special pointer that identifies a segment in memory. To access a particular segment in memory, the segment selector for that segment must be present in the appropriate segment register.




Figure 3-6. Use of Segment Registers for Flat Memory Model

Segment Registers





Figure 3-7. Use of Segment Registers in Segmented Memory Model





EFLAGS Register

The EFLAGS register in x86 architecture is a special register that contains a collection of flags used by the processor to indicate the status of operations and to control certain processor functions.





EFLAGS Register

The EFLAGS register contains status flags that reflect the outcome of arithmetic operations. These flags include:

- CF (Carry Flag): Indicates if an arithmetic operation has resulted in a carry out of the most significant bit, relevant for unsigned integer arithmetic.
- **PF (Parity Flag):** Shows if the low-order byte of the result has an even number of set bits.
- AF (Auxiliary Carry Flag): Set if there's a carry out of the least significant nibble, used for BCD arithmetic.
- **ZF** (**Zero Flag**): Set if the result of an arithmetic operation is zero.
- SF (Sign Flag): Reflects the sign of the result of an operation; set if negative.
- **OF (Overflow Flag):** Indicates an overflow in signed integer arithmetic.

EFLAGS Register

1. CF (Carry Flag):

ADD AL, 0xFF; If AL contains 0x01 or greater, this will set the CF because the result wraps around.

2. ZF (Zero Flag):

XOR EAX, EAX; This will set ZF as the result is zero.

3. SF (Sign Flag):

SUB EAX, EAX; Followed by DEC EAX. EAX will be 0xFFFFFFF, setting the SF.

4. OF (Overflow Flag):

ADD EAX, 0x7FFFFFFF; If EAX also contains 0x7FFFFFFF, adding them will set the OF.



The Zero Flag (ZF) is set when the result of an operation is zero. Which instruction always sets the ZF?

- a) XOR EAX, EAX
- b) ADD EAX, 1
- c) SUB EAX, EAX
- d) CMP EAX, EAX



If the Sign Flag (SF) is set after an instruction, what can be inferred about the result?

- a) It is zero.
- b) It is a positive number.
- c) It is a negative number.
- d) An unsigned overflow occurred

Which instruction would you use to compare two values and set flags accordingly without changing the values?

- a) ADD
- b) SUB
- c) XOR

What is the result of the following instruction in terms of the Zero Flag (ZF)?

SUB EAX, EAX

- a) ZF is cleared.
- b) ZF is set.
- c) ZF is unchanged.
- d) ZF state is unpredictable.

MOV EAX, 5 CMP EAX, 5 JE Label

After executing the above instructions, what will be the state of the Zero Flag (ZF) when the comparison happens?

- a) The ZF will be set (ZF = 1) because EAX is not equal to 5.
- b) The ZF will be cleared (ZF = 0) because EAX is equal to 5.
- c) The ZF will be set (ZF = 1) because EAX is equal to 5.
- d) The ZF state is unpredictable.

Memory

...0x2BC0N10U



Course Overview

Title: "CSEC 202 - Reverse Engineering Fundamentals"

Instructor	Office	Phone	Email	Semester-Year
Emad Abu Khousa	B217		<u>eakcad@rit.edu</u>	Spring-2024
Office Hours:	M: 12:00-01:00 TR: 11:00-12:00			

600: 12:05-01:20, **Room D-114** 601: MW 01:05-02:25, **Room C-109** 01:30-02:50, **Room D-207 602**:



Thank You and Q&A