# **Composable Algebra with Dependencies**

Draft

#### **Abstract**

This paper presents composable algebra with dependencies: a new approach to compose algebras together to allow dependent interpretations with *fold*. For a given datatype represented by two-eveltypes[1], if one of its interpretations depends on a second interpretation, we compose the algebra corresponding to this interpretation with the algebra corresponding to the second one, and use the composed algebra with *fold* to evaluate the expression.

#### 1. Introduction

Algebras can often be used with *fold* to evaluate recursive expressions. However, *fold* supports only compositional interpretations, meaning that an interpretation of a whole is determined solely from the interpretations of its parts. The compositionality of an interpretaion is a significant limitation to expressivity: sometimes a 'primary' interpretation of the whole depends also on 'secondary' interpretaions of its parts.

In the context of Embedded Domain Specific Languages (DSL), Jeremy Gibbons[2] proposed two approaches on F-Algebra to tackle the problems of compositionality and dependencies. We will examine the two approaches in section 4 and show that each of them has its problems.

In section 5, We will present an approach that allows us to compose algebras corresponding to different interpretations of a datatype modularly. Next, we will show how dependent interpretations can be achieved using composable algebras in section 6. We will then show that our approach can be integrated with the Modular Rifiable Matching (MRM) [4] approach to allow dependenvies brought by new datatypes.

In this paper, F-Algebra will also be used as the primary representation of algebras. In section 6, we will show that the problem of dependent interpretation with *fold* can be handled using other representations of algebras as well.

**Contributions** In summary, the contributions of this paper are:

- An approach to compose algebras modularly: We introduce a type class for membership relations and how it allows us to compose algebras together.
- Incorporating dependencies in composable algebras: We show how dependent interpretations can be achieved on top of composable algebras.
- Extensibility in both dimensions We show how our algebras can be integrated with the MRM approach to resolve dependencies brought in by newly-added datatypes.
- Dependent interpretations with type classes We present another representation of algebras using type classes that also allows dependent interpretations.
- Dependnt interpretations with records We present another representation of algebras using records that also allows dependent interpretations



Figure 1. The Brent-Kung parallel prefix circuit of widht 4

# 2. DSL for parallel prefix circuits

In Jeremy Gibbons's paper[2], parallel prefix circuit is used as an example of a DSL. To make better comparison between his and our approaches, we will also work on top of the DSL of circuits.

Given an associative binary operator  $\circ$ , a prefix computation of width n>0 takes a sequence  $x_1,x_1,\ldots,x_n$  of inputs and produces the sequence  $x_1,x_1\circ x_2,\ldots,x_1\circ x_2\circ\ldots\circ x_n$  of outputs. A parallel prefix circuit performs this computation in parallel, in a fixed format independent of the input value xi.

Figuire 1 shows an example of a circuit. The inputs are fed in at the top, and the outputs fall out at the bottom. Each node represents a local computation, combining the values on each of its input wires using  $\circ$ , in left-to-right order, and providing copies of the result on each its output wires.

Such cirucits can be represented by the following data structure:

data Circuit =

Identity Int

| Fan Int

| Above Circuit Circuit

| Beside Circuit Circuit

| Stretch [Int] Circuit

• **Identity:** *Identity n* creates a circuit consisting of n parallel wires that copy input to output. *Identity* of width 4:



• Fan: Fan n takes takes n inputs, and adds its first input to each of the others. Fan of width 4:



• **Beside:** *Beside* x y is the parallel or horizontal composition. It places c beside d, leaving them unconnected. There are no width constraints on c and d.

A 2-Fan beside a 1-Identity:



• **Above:** Above x y is the seires or veritical composition. It takes two circuits c and d of the same width, and connects the outputs of c to the inputs of d.

Place Beside (Fan 2) (Identity 1) above Beside (Identity 1) (Fan 2). Both of the circuits are of width 3:



• **Stretch:** *Stretch ws x* takes a non-empty list of positive widths ws = [w1, ..., wn] of length n, and "stretchs" c out to width *sum ws* by interleaving some additional wires. Of the first bundle of w1 inputs, the last is routed to the first input of c and the rest pass straight through; of the next bundle of w2 inputs, the last is routed to the second input of c and the rest pass straight through; and so on.

A 3-Fan stretched out by widths [3, 2, 3]



On possible construction of the Brent-Kung parallel prefix circuit in Figure 1 is:

```
circuit =
Above (Beside (Fan 2) (Fan 2))
(Above (Stretch [2, 2] (Fan 2))
(Beside (Identity 1) (Beside (Fan 2) (Identity 1))))
```

# 3. F-Algebras

Alternatively, the circuit presented above can be represented using *two-level-types*[1] The shape of the circuit is given by functor *CircuitF* as follows:

```
data CircuitF r =
  IdentityF Int
  | FanF Int
  | AboveF r r
  | BesideF r r
  | StretchF [Int] r
  deriving Functor
```

CircuitF abstracts the recursive occurrences of the datatype away, using a type parameter r. We can then recover the datatype of Circuit:

```
data Circuit = In (CircuitF Circuit)
```

An algebra for CircuitF consists of a type a and a function taking a CircuitF of a-values to an a-value:

```
type CircuitAlg a = CircuitF a \rightarrow a
```

Suppose we want to obtain the width of a circuit, we can pick *Width* as our evaluation target (i.e. the carrier type of *widthAlg*):

```
type Width = Int
widthAlg :: CircuitAlg Width
widthAlg (IdentityF w) = w
```

```
widthAlg (FanF w) = w
widthAlg (AboveF \times y) = x
widthAlg (BesideF \times y) = x + y
widthAlg (StretchF \times s ×) = sum \timess
```

widthAlg here will give us the final evaluation result (i.e. the width) of a circuit, assuming all children of AboveF, BesideF and StretchF are already evaluated and are of type Width.

Similarly, we can define depthAlg to obtain the depth of a circuit:

```
\label{eq:type_def} \begin{split} \mathbf{type} \ \mathsf{Depth} &= \mathsf{Int} \\ \\ \mathsf{depthAlg} :: \mathsf{CircuitAlg} \ \mathsf{Depth} \\ \mathsf{depthAlg} \ (\mathsf{IdentityF} \ \mathsf{w}) &= 0 \\ \mathsf{depthAlg} \ (\mathsf{FanF} \ \mathsf{w}) &= 1 \\ \mathsf{depthAlg} \ (\mathsf{AboveF} \times \mathsf{y}) &= \mathsf{x} + \mathsf{y} \\ \mathsf{depthAlg} \ (\mathsf{AboveF} \times \mathsf{y}) &= \mathsf{x} \text{ `max' y} \\ \mathsf{depthAlg} \ (\mathsf{BesideF} \times \mathsf{y}) &= \mathsf{x} \end{split}
```

Given a nested circuit, we need a fold to traverse the recursive data structure, using algebras defined earlier for evaluation at each recursive step:

```
fold :: CircuitAlg a \to Circuit \to a fold alg (In x) = alg (fmap (fold alg) x)
```

Compositional observation functions for our circuit can be defined as:

```
width :: Circuit → Width width = fold widthAlg depth :: Circuit → Depth depth = fold depthAlg
```

In order to conveniently construct circuits with *CircuitF*, we define the following smart constructos:

```
\begin{split} & \text{identity} :: Int \to Circuit \\ & \text{identity} = In \circ IdentityF \\ \\ & \text{fan} :: Int \to Circuit \\ & \text{fan} = In \circ FanF \\ \\ & \text{above} :: Circuit \to Circuit \to Circuit \\ & \text{above} \times y = In \ (AboveF \times y) \\ \\ & \text{beside} :: Circuit \to Circuit \to Circuit \\ & \text{beside} \times y = In \ (BesideF \times y) \\ \\ & \text{stretch} :: [Int] \to Circuit \to Circuit \\ & \text{stretch} \times x \times = In \ (StretchF \times x \times) \\ \end{split}
```

Therefore, the Brent-Kung parallel prefix circuit in Figure 1 can be constructed as:

```
\begin{aligned} & \mathsf{circuit1} = \\ & & (\mathsf{fan}\ 2\ \mathsf{`beside'}\ \mathsf{fan}\ 2)\ \mathsf{`above'} \\ & & \mathsf{stretch}\ [2,2]\ (\mathsf{fan}\ 2)\ \mathsf{`above'} \\ & & & (\mathsf{identity}\ 1\ \mathsf{`beside'}\ \mathsf{fan}\ 2\ \mathsf{`beside'}\ \mathsf{identity}\ 1) \end{aligned}
```

It can be directly evaluated using observation functions defined earlier:

```
test1 = width circuit1
test2 = depth circuit1
```

# 4. Existing Approaches

 $\mathbf{type} \ \mathsf{WellSized} = \mathsf{Bool}$ 

To maintain the compositionality of an interpretation while bringing in dependencies, Jeremy Gibbons proposed two approaches based on F-Algebra. One example of a dependent interpretation is to see whether a circuit is well formed or not, as it depends on the widths of the circuit's constituent parts. Since the interpretation is non-compositional[2], there is no corresponding CircuitAlg and fold can not be used.

# 4.1 Pairs for multiple interpretations with dependencies

To allow multiple interpretations with dependencies using fold, Gibbons[2] proposed the following zygomorphism [3], making the semantic domain of the interpretaion (i.e. the carrier type of an algebra) a pair:

```
wswAlg :: CircuitAlg (WellSized, Width)
wswAlg (IdentityF w) = (True, w)
wswAlg (FanF w)
                     = (True, w)
wswAlg (AboveF x y) = (fst x && fst y && snd x == snd y, snd x)
wswAlg (BesideF x y) = (fst x && fst y, snd x + snd y)
wswAlg (StretchF ws x) = (fst x && length ws == snd x, sum ws)
```

In this way, fold wswAlg is still a fold, and individual interpretations can be recovered as follows:

```
wellSized1 :: Circuit \rightarrow WellSized
wellSized1 \times = fst (fold wswAlg \times)
\mathsf{width1} :: \mathsf{Circuit} \to \mathsf{Width}
width1 x = snd (fold wswAlg x)
```

# 4.2 Church encoding for multiple interpretations

From the previous section we can see that it is possible to provide dependent interpretaions by pairing semantics up and projecting the desired interpretation from the tuple. However, it is still clumsy and not modular: existing code needs to be revised every time a new interpretation is added. Moreover, for more than two interpretations, we have to either create a combination for each pair of interpretations, or use tuples which generally lack good language support.

Therefore, Gibbons[2] presented a single parametrized interpretation, which provides a universal generic interpretation as the Church encoding:

```
newtype Circuit1 = C1 { unC1 :: \foralla.CircuitAlg a \rightarrow a }
    identity1 w = C1 (\lambdaalg \rightarrow alg (IdentityF w))
                  = C1 (\lambda alg \rightarrow alg (FanF w))
    above1 x y = C1 (\lambdaalg \rightarrow alg (AboveF (unC1 x alg) (unC1 y alg)))
    beside1 x y = C1 (\lambdaalg \rightarrow alg (BesideF (unC1 x alg) (unC1 y alg)))
    stretch1 ws x = C1 (\lambdaalg \rightarrow alg (StretchF ws (unC1 x alg)))
It can then specialize to width and depth:
    width 2 :: Circuit 1 \rightarrow Width
    width2 x = unC1 \times widthAlg
    depth2 :: Circuit1 \rightarrow Depth
    depth2 x = unC1 x depthAlg
```

However, one big problem with the above church encoding approach is that it still does not support dependent interpretations.

#### 5. Composable Algebras

Our first goal is to compose algebras modularly. It will allow us to bring in dependent interpretions later. By composing two algebras together, we can get a new algebra with a carrier type containing the types of its components. In this section, we will use algebras for width and depth as examples and show how we can compose the two together.

Since a composed algebra has a composed carrier type, instead of using Width and Depth defined earlier to represent the semantic domain of each interpretation, we make use of the newtype wrapper to allow multiple interpretations over the same underlying type:

```
newtype Width2 = Width2 { width :: Int }
newtype Depth2 = Depth2 { depth :: Int }
```

Algebras can be defined in the same way as before:

```
widthAlg2 :: CircuitAlg Width2
widthAlg2 (IdentityF w) = Width2 w
widthAlg2 (FanF w)
                        = Width2 w
widthAlg2 (AboveF \times y) = Width2 (width x)
widthAlg2 (BesideF \times y) = Width2 (width \times + width y)
widthAlg2 (StretchF xs x) = Width2 (sum xs)
depthAlg2 :: CircuitAlg Depth2
depthAlg2 (IdentityFw) = Depth2 0
depthAlg2 (FanF w)
                        = Depth2 1
depthAlg2 (AboveF \times y) = Depth2 (depth \times + depth y)
depthAlg2 (BesideF \times y) = Depth2 (depth \times 'max' depth y)
depthAlg2 (StretchF xs x) = Depth2 (depth x)
```

Next we introduce the following type class to state a membership relationship between type i and e:

```
class i :<: e where
  inter :: e \rightarrow i
```

Here i :<: e means that type i is a component of a larger collection of types represented by e, and gives the corresponding projection functions:

```
instance i:<:i where
  inter = id
instance i :<: (Compose i i2) where
  inter = fst
instance (i :<: i2) \Rightarrow i :<: (Compose i1 i2) where
  inter = inter \circ snd
```

To actually compose two algebras together, we define the operator (<+>):

```
type Compose i1 i2 = (i1, i2)
```

```
(<+>) :: CircuitAlg a \rightarrow CircuitAlg b \rightarrow CircuitAlg (Compose a b)
(<+>) a1 a2 (IdentityF w) = (a1 (IdentityF w), a2 (IdentityF w))
(<+>) a1 a2 (FanF w)
                             = (a1 (FanF w), a2 (FanF w))
(<+>) a1 a2 (AboveF x y) =
  (a1 (AboveF (inter x) (inter y)), a2 (AboveF (inter x) (inter y)))
(<+>) a1 a2 (BesideF x y) =
  (a1 (BesideF (inter x) (inter y)), a2 (BesideF (inter x) (inter y)))
(<+>) a1 a2 (StretchF xs x) =
  (a1 (StretchF xs (inter x)), a2 (StretchF xs (inter x)))
```

(<+>) takes two algebras with carrier types a and b as inputs and gives back an algebra with a composed carrier type (Compose a b). For AboveF, BesideF and StretchF, their children x and y are of type e, where Width2 :<: e and WellSized2 :<: e. In the output tuple, (inter x) and (inter y) will have types corresponding to the carrier type of a1 and a2 respectively.

Now it is straightforward to compose algebras together:

```
\mathsf{cAlg} = \mathsf{widthAlg2} < + > \mathsf{depthAlg2}
```

cAlg is composed of widthAlg2 and depthAlg2, with a carrier type of (Compose Width2 Depth2).

We can define the evaluation function of our circuit as a *fold*:

```
eval = fold cAlg
```

To retrieve a target evaluation type from a composed type, we define *gwidth* and *gdepth*:

```
gwidth :: (Width2 :<: e) \Rightarrow e \rightarrow Int gwidth = width \circ inter gdepth :: (Depth2 :<: e) \Rightarrow e \rightarrow Int gdepth = depth \circ inter
```

Individual interpretations can be defined as:

```
width3 :: Circuit \rightarrow Int width3 = gwidth \circ eval depth3 :: Circuit \rightarrow Int depth3 = gdepth \circ eval
```

They can be used to evaluate the Brent-Kung parallel prefix circuit defined in section 3:

```
test1 = width3 circuit1
test2 = depth3 circuit1
```

# 6. Dependent Algebras

In the previous section we talked about how algebras can be composed together to allow multiple interpretations. In this section, we will introduce an approach that allows multiple interpretations with dependencies. With our approach, each property we want to evaluate has a corresponding algebra. There is no need to construct a pair of interpretations when one depends on the other. For example, unlike wswAlg in section 4.1, we have wsAlg that corresponds to wellSized, where the definition of widthAlg is no longer needed.

The first step is to change our definition of alegebra from CircuitAlg to GAlg:

```
type GAlg r a = CircuitF r \rightarrow a
```

GAlg stands for *generic algebra*. It consists of two types r and a, and a function taking CiruictF of r-vlaues to an a-value, where a:<: r. For wsAlg, the first type r represents a collection of types containing both WellSized2 and Width2 (specified by (WellSized2:<: r, Width2:<: r)). Since each child of AboveF, BesideF and StretchF is of type r, gwidth can be used to retrieve the width of a circuit. Therefore, wsAlg can be defined as follows:

```
newtype WellSized2 = WellSized2 { wellSized :: Bool }
```

```
\label{eq:wsAlg::} \begin{aligned} & \text{wsAlg::} (\text{WellSized2:} <: r, \text{Width2:} <: r) \Rightarrow \text{GAlg r WellSized2} \\ & \text{wsAlg (IdentityF w)} = \text{WellSized2 True} \\ & \text{wsAlg (FanF w)} = \text{WellSized2 True} \\ & \text{wsAlg (AboveF} \times y) = \\ & \text{WellSized2 (gwellSized} \times \&\& \text{ gwellSized y }\&\& \text{ gwidth } \times =: \text{ gwidwsAlg (BesideF} \times y) = \\ & \text{WellSized2 (gwellSized} \times \&\& \text{ gwellSized y)} \\ & \text{wsAlg (StretchF} \times x) = \end{aligned}
```

Since Width2 needs to be part of the carrier type of wsAlg such that we can retreive the width of a circuit and test if it is well-formed, we need to compose widthAlg3 and wsAlg together for evaluation. While the (<+>) operator is very similar to the one defined in

WellSized2 (gwellSized x && length xs == gwidth x)

the previous section, we need to specify the relationships between types of algebras we are compsoing. Given an algebra from type r to type a, and another from type r to type b, where r contains both a and b, it gives back a new algebra from type r to type (Compose a b).

```
(<+>) :: (a:<:r,b:<:r) \Rightarrow \mathsf{GAlg}\ r\ a \rightarrow \mathsf{GAlg}\ r\ b \rightarrow
  GAlg r (Compose a b)
(<+>) a1 a2 (IdentityF w) =
  (a1 (IdentityF w), a2 (IdentityF w))
(<+>) a1 a2 (FanF w)
  (a1 (FanF w), a2 (FanF w))
(<+>) a1 a2 (AboveF x y) =
  (a1 (AboveF (inter x) (inter y)), a2 (AboveF (inter x) (inter y)))
(<+>) a1 a2 (BesideF x y) =
  (a1 (BesideF (inter x) (inter y)), a2 (BesideF (inter x) (inter y)))
(<+>) a1 a2 (StretchF xs x) =
  (a1 (StretchF xs (inter x)), a2 (StretchF xs (inter x)))
widthAlg3 :: (Width2 :<: r) \Rightarrow GAlg r Width2
widthAlg3 (IdentityF w) = Width2 w
widthAlg3 (FanF w)
                          = Width2 w
widthAlg3 (AboveF \times y) = Width2 (gwidth \times)
widthAlg3 (BesideF \times y) = Width2 (gwidth \times + gwidth y)
widthAlg3 (StretchF xs x) = Width2 (sum xs)
```

Now we can define cAlg2 that is composed of widthAlg3 and wsAlg:

```
\mathsf{cAlg2} = \mathsf{widthAlg3} < + > \mathsf{wsAlg}
```

With observation functions width2 and wellSized2 defined as:

```
\label{eq:width2} \begin{split} & \text{width2} :: \mathsf{Circuit} \to \mathsf{Int} \\ & \text{width2} \ \mathsf{x} = \mathsf{gwidth} \ (\mathsf{fold} \ \mathsf{cAlg2} \ \mathsf{x}) \\ & \text{wellSized2} :: \mathsf{Circuit} \to \mathsf{Bool} \\ & \text{wellSized2} \ \mathsf{x} = \mathsf{gwellSized} \ (\mathsf{fold} \ \mathsf{cAlg2} \ \mathsf{x}) \end{split}
```

# 7. Extensibility in Both Dimensions

So far we have only talked about extensibility in one dimension, namely, how to add new observation functions in a modular way with algebras for our DSL. What if we want to have extensibility in a second dimension, which is to extend our grammer by adding new data constructors modularly? To make the problem more interesting, these additional constructors may also bring dependencies in their corresponding observation functions at the same time. In this section, we will show that our approach of composing algebras while incorporating dependencies works well with the Modular Refiable Matching (MRM) approach[4], which allows us to add additional constructors modularly. We will present a two-level composition of algebras: for each modular component, we compose its algebras together if an interpretation is dependent; for different components, we combine their corresponding algebras together to allow evaluation of a composed data structure.

WellSized2 (gwellSized x && gwellSized y && gwidth x = y gwidth y go example, say at first we only have three constructs in our sAlg (BesideF x y) = DSL of circuits: *IdentityF*, *FanF*, and *BesideF*. We can define a WellSized2 (gwellSized x && gwellSized y) functor *CircuitFB* to represent this datatype, where B stands for y = x

```
data CircuitFB r =
IdentityF Int
| FanF Int
| BesideF r r
deriving Functor
```

There is no dependencies involved for the algebras of this ciruict, since with only *IdentityF*, *FanF* and *BesideF*, whether a circuit is well formed or not is not dependent on the width of its parts. However, we will keep our representation for dependent algebras to be consistent with algeras we will later define for extended datatypes:

```
type GAlgB r a = CircuitFB r \rightarrow a
```

Algebras for width and wellSized are exactly the same as before:

```
\label{eq:widthAlgB} \begin{tabular}{ll} widthAlgB :: (Width2 :<: r) &\Rightarrow CircuitFB \ r \to Width2 \\ widthAlgB (IdentityF w) &= Width2 \ w \\ widthAlgB (FanF w) &= Width2 \ w \\ widthAlgB (BesideF x y) &= Width2 (gwidth x + gwidth y) \\ wsAlgB :: (Width2 :<: r, WellSized2 :<: r) &\Rightarrow \\ CircuitFB \ r \to WellSized2 \\ wsAlgB (IdentityF w) &= WellSized2 \ True \\ wsAlgB (FanF w) &= WellSized2 \ True \\ wsAlgB (BesideF x y) &= WellSized2 (gwellSized x \&\& gwellSized) \\ \end{tabular}
```

Now suppose we want to extend our circuits by adding new constructs *AboveF* and *StretchF*. We add the datatype constructors as a functor *CircuitFE*, where E stands for *Extended*:

```
data CircuitFE r =
  AboveF r r
  | StretchF [Int] r
  deriving Functor
```

Algebras correspond to this functor are similar to the ones above. The only difference is that the interpretation for checking if a circuit is well formed now depends on the widths of its part. Same as in section 6, we use *gwidth* to retrieve the width of a circuit:

```
\label{eq:type GAlgE r a = CircuitFE r on a} widthAlgE :: (Width2 :<: r) \Rightarrow CircuitFE r on widthAlgE (AboveF x y) = Width2 (gwidth x) widthAlgE (AboveF x x) = Width2 (gwidth x) They circuitFE r on WellSized2 :<: r) \Rightarrow CircuitFE r on WellSized2 wsAlgE (AboveF x y) = WellSized2 (gwellSized x && gwellSized y && gwidth x == gwidth y) wsAlgE (StretchF xs x) = WellSized2 (gwellSized x && length xs == gwidth x)
```

Unlike the <+> operator defined in previous sections, here we associate it with a type class to compose algebras correponding to different functors. With this approach, we don't have to define a different operator for algebra composition each time a new functor is added. Instead, all we have to do is to make a new instance of type class Comb and define the corresponding behavior of <+>. Since we have two functors CircuitFB and CircuitFE, we create two instances of Comb and define <+> for each of them:

```
class Comb f r a b where (<+>):: (f r \rightarrow a) \rightarrow (f r \rightarrow b) \rightarrow (f r \rightarrow (Compose a b))

instance (a:<: r, b:<: r) \Rightarrow Comb CircuitFB r a b where (<+>) a1 a2 (IdentityF w) = (a1 (IdentityF w), a2 (IdentityF w)) of that int and output (<+>) a1 a2 (FanF w) = (a1 (FanF w), a2 (FanF w)) class (<+>) a1 a2 (BesideF x y) = identity (>+>) a1 a2 (BesideF x y) = identity (>+>) a1 a2 (BesideF x y) = identity (>+>) a1 a2 (BesideF (inter x) (inter y)) fan
```

```
instance (a :<: r, b :<: r) \Rightarrow Comb CircuitFE r a b where
  (< + >) a1 a2 (AboveF x y) =
    (a1 (AboveF (inter x) (inter y)), a2 (AboveF (inter x) (inter y)))
  (< + >) a1 a2 (StretchF xs x) =
    (a1 (StretchF xs (inter x)), a2 (StretchF xs (inter x)))
```

A circuit with all five constructs can be built from the modular components. First we define the type of the circuit:

```
type Circuit2 = Fix'[CircuitFB, CircuitFE]
```

The type Circuit2 denotes circuits that have IdentityF, FanF, BesideF, AboveF and StretchF as their components.

Since *Width2* needs to be part of the carrier type of wsAlgE such that we can retreive the width of a circuit and test if it is well-formed, for *CircuitFE*, we need to compose *widthAlgE* and *wsAlgE* together and use *compAlgE* for evaluation.

```
compAlgE = widthAlgE < + > wsAlgE
```

Then we use (:::) to combine algebras correspond to different functors together [?]. Since the algebras in the list constructed by (:::) need to have the same carrier and return type, we compose widthAlgB and wsAlgB for CircuitFB and get compAlgB:

```
compAlgB = widthAlgB < + > wsAlgB
```

The *fold* operator defined in MRM library [?] takes an fs-algebra and Fix fs arguments. We define the evaluation function for our circuit as a fold using the combined algebras:

```
eval :: Circuit2 \rightarrow Compose Width2 WellSized2 eval = fold (compAlgB ::: (compAlgE ::: Void))
```

Invidual interpretations can then be retrieved by *gwidth* and *gwell-Sized*:

```
width3 :: Circuit2 \rightarrow Int width3 = gwidth \circ eval wellSized3 :: Circuit2 \rightarrow Bool wellSized3 = gwellSized \circ eval
```

They can be used with smart constructors to evaluate a concrete circuit:

# 3. Other representations of algebra

Apart from *two-level-types*, there are other ways to represent and evaluate the DSL of parallel prefix circuits. In this section, we will show two other representations, and how they can be used to allow dependent interpretations.

### 8.1 Type Class with Proxies

One way to represent the circuit is to use a type class. Each interpretation corresponds to an instance of the type class for the type of that interpretation. The two class type variables stand for input and output domains of an interpretation:

```
class Circuit inn out where identity :: Proxy inn \rightarrow Int \rightarrow out )) fan :: Proxy inn \rightarrow Int \rightarrow out
```

```
above :: inn \rightarrow inn \rightarrow out beside :: inn \rightarrow inn \rightarrow out stretch :: \lceil Int \rceil \rightarrow inn \rightarrow out
```

Due to the restriction of Haskell's type classes, all of the class type variables must be reachable from the free variables of each method type. Therefore, we need the *Proxy* here for *identity* and *fan* to allow the use of class type *inn*:

```
data Proxy a = Proxy
```

For example, the interpretation for width can be defined as:

```
\begin{array}{l} \mathbf{instance} \; (\mathsf{Circuit} \; \mathsf{inn} \; \mathsf{Width2}, \mathsf{Width2} \; :<: \mathsf{inn}) \Rightarrow \\ \mathsf{Circuit} \; \mathsf{inn} \; \mathsf{Width2} \; \mathbf{where} \\ \mathsf{identity} \; (\mathsf{Proxy} :: \mathsf{Proxy} \; \mathsf{inn}) \; \mathsf{w} = \mathsf{Width2} \; \mathsf{w} \\ \mathsf{fan} \; (\mathsf{Proxy} :: \mathsf{Proxy} \; \mathsf{inn}) \; \mathsf{w} = \mathsf{Width2} \; \mathsf{w} \\ \mathsf{above} \; \mathsf{x} \; \mathsf{y} \; = \mathsf{Width2} \; (\mathsf{gwidth} \; \mathsf{x}) \\ \mathsf{beside} \; \mathsf{x} \; \mathsf{y} \; = \mathsf{Width2} \; (\mathsf{gwidth} \; \mathsf{x} + \mathsf{gwidth} \; \mathsf{y}) \\ \mathsf{stretch} \; \mathsf{xs} \; \mathsf{x} = \mathsf{Width2} \; (\mathsf{sum} \; \mathsf{xs}) \end{array}
```

On the other hand, the interpretation for *wellSized* is dependent. For member functions *above* and *stretch*, the inputs are of type *inn* which contains both *Width2* and *WellSized2*. We can retrieve the width of x and y with the help of *gwidth*:

```
instance (Circuit inn WellSized2, Each interval width2:<: inn, WellSized2:<: inn) \Rightarrow example, in values width2:<: inn WellSized2 where identity (Proxy:: Proxy inn) w = WellSized2 True fan (Proxy:: Proxy inn) w = WellSized2 True width2 above x y = WellSized2 (gwellSized x && gwellSized y && gwidth x == gwidth x width2 beside x y = WellSized2 (gwellSized x && gwellSized y stretch x x = WellSized2 (gwellSized x && length x == gwidth x stretch x == WellSized2 (gwellSized x && length x == gwidth x stretch x == x ==
```

Instead of using a composition operator as before, we make another instance for interpretations with composed type:

```
instance (Circuit inn inn1, Circuit inn inn2) ⇒

Circuit inn (Compose inn1 inn2) where

identity (Proxy :: Proxy inn) w =

((identity (Proxy :: Proxy inn) w), (identity (Proxy :: Proxy inn) w)

fan (Proxy :: Proxy inn) w =

((fan (Proxy :: Proxy inn) w), (fan (Proxy :: Proxy inn) w))

above x y = ((above x y), (above x y))

beside x y = ((beside x y), (beside x y))

stretch x = ((above x y), (above x x))
```

Here we support interpretations for composed type by making the output of member functions a pair. The first element in the pair represents the interpretation for the first type *inn1*, while the second represents the interpretation for *inn2*.

For example, if we want to have an interpretation for type (Compose Width2 WellSized2), we annotate each member function with type ComposedType to associate it with the instance of interpretation for composed types:

```
\mathbf{type}\ \mathsf{ComposedType} = \mathsf{Compose}\ \mathsf{Width2}\ \mathsf{WellSized2}
```

```
\begin{array}{ll} {\sf gfan} \ {\sf w} &= \\ {\sf fan} \ ({\sf Proxy} :: {\sf Proxy} \ {\sf ComposedType}) \ {\sf w} :: {\sf ComposedType} \\ {\sf gidentity} \ {\sf w} &= \\ {\sf identity} \ ({\sf Proxy} :: {\sf Proxy} \ {\sf ComposedType}) \ {\sf w} :: {\sf ComposedType} \\ {\sf gbeside} \ {\sf x} \ {\sf y} = ({\sf beside} \ {\sf x} \ {\sf y}) :: {\sf ComposedType} \\ {\sf gabove} \ {\sf x} \ {\sf y} = ({\sf above} \ {\sf x} \ {\sf y}) :: {\sf ComposedType} \\ {\sf gstretch} \ {\sf xs} \ {\sf x} = ({\sf stretch} \ {\sf xs} \ {\sf x}) :: {\sf ComposedType} \\ \end{array}
```

The Brent-Kung circuit in Figure 1 can be constructed as:

```
circuit3 =
  (gfan 2 'gbeside' gfan 2) 'gabove'
  gstretch [2, 2] (gfan 2) 'gabove'
  (gidentity 1 'gbeside' gfan 2 'gbeside' gidentity 1)
```

We can project individual interpretations out using *gwidth* and *gwellSized*:

```
test1 = gwidth circuit3
test3 = gwellSized circuit3
```

#### 8.2 Records

Alternatively, circuits can be represented using records.

We define the following datatype with record syntax for circuit constructions:

```
 \begin{array}{l} \textbf{data Circuit inn out} = \textbf{Circuit } \{ \\ \textbf{identity} :: \textbf{Int} \rightarrow \textbf{out}, \\ \textbf{fan} & :: \textbf{Int} \rightarrow \textbf{out}, \\ \textbf{above} & :: \textbf{inn} \rightarrow \textbf{inn} \rightarrow \textbf{out}, \\ \textbf{beside} & :: \textbf{inn} \rightarrow \textbf{inn} \rightarrow \textbf{out}, \\ \textbf{stretch} :: [\textbf{Int}] \rightarrow \textbf{inn} \rightarrow \textbf{out} \\ \} \end{array}
```

Each interpretation corresponds to a value of the datatype. For example, for *width* and *wellSized* interpretations, we define two values *widthAlg* and *wsAlg*:

```
widthAlg :: (Width2 :<: inn) ⇒ Circuit inn Width2
widthAlg = Circuit {
   identity = \lambda w \rightarrow Width2 w,
          = \lambda w \rightarrow Width2 w,
   above = \lambda x y \rightarrow Width2 (gwidth x),
   beside = \lambda x y \rightarrow Width2 (gwidth x + gwidth y),
   stretch = \lambda xs x \rightarrow Width2 (sum xs)
wsAlg :: (Width2 : <: inn, WellSized2 : <: inn) \Rightarrow
   Circuit inn WellSized2
wsAlg = Circuit {
  identity = \lambda w \rightarrow \text{WellSized2 True},
          = \lambda w \rightarrow WellSized2 True,
   above = \lambda x y \rightarrow WellSized2 (gwellSized x && gwellSized y &&
                       gwidth x = gwidth y),
   beside = \lambda x y \rightarrow \text{WellSized2} (gwellSized x && gwellSized y),
   stretch = \lambda xs x \rightarrow WellSized2 (gwellSized x &&
                       length xs == gwidth x)
```

Circuit composition is also defined as a value of the datatype:

```
 \begin{array}{l} (<+>) :: (\mathsf{inn1} :<: \mathsf{inn}, \mathsf{inn2} :<: \mathsf{inn}) \Rightarrow \\ \mathsf{Circuit} \; \mathsf{inn} \; \mathsf{inn1} \to \mathsf{Circuit} \; \mathsf{inn} \; \mathsf{inn2} \to \\ \mathsf{Circuit} \; \mathsf{inn} \; (\mathsf{Compose} \; \mathsf{inn1} \; \mathsf{inn2}) \\ (<+>) \; \mathsf{a1} \; \mathsf{a2} = \mathsf{Circuit} \; \{ \\ \mathsf{identity} = \lambda \mathsf{w} \; \to \; (\mathsf{identity} \; \mathsf{a1} \; \mathsf{w}, \mathsf{identity} \; \mathsf{a2} \; \mathsf{w}), \\ \mathsf{fan} \; = \lambda \mathsf{w} \; \to \; (\mathsf{fan} \; \mathsf{a1} \; \mathsf{w}, \mathsf{fan} \; \mathsf{a2} \; 2), \\ \mathsf{above} \; = \lambda \mathsf{x} \; \mathsf{y} \to \; (\mathsf{above} \; \mathsf{a1} \; (\mathsf{inter} \; \mathsf{x}) \; (\mathsf{inter} \; \mathsf{y}), \\ \mathsf{above} \; \mathsf{a2} \; (\mathsf{inter} \; \mathsf{x}) \; (\mathsf{inter} \; \mathsf{y}), \\ \mathsf{beside} \; = \lambda \mathsf{x} \; \mathsf{y} \to \; (\mathsf{beside} \; \mathsf{a1} \; (\mathsf{inter} \; \mathsf{x}) \; (\mathsf{inter} \; \mathsf{y}), \\ \mathsf{beside} \; \mathsf{a2} \; (\mathsf{inter} \; \mathsf{x}) \; (\mathsf{inter} \; \mathsf{x}), \\ \mathsf{stretch} \; \mathsf{a2} \; \mathsf{xs} \; (\mathsf{inter} \; \mathsf{x}), \\ \mathsf{stretch} \; \mathsf{a2} \; \mathsf{xs} \; (\mathsf{inter} \; \mathsf{x}), \\ \} \end{array}
```

Now we can compose interpretations smoothly. For example, widthAlg and wsAlg can be composed together as follows:

```
 \begin{array}{l} {\sf cAlg::Circuit\;(Compose\;Width2\;WellSized2)}\\ ({\sf Compose\;Width2\;WellSized2})\\ {\sf cAlg=widthAlg}<+>{\sf wsAlg} \end{array}
```

Each construct is associated with the corresponding field in cAlg:

```
cidentity = identity cAlg
cfan = fan cAlg
cabove = above cAlg
cbeside = beside cAlg
cstretch = stretch cAlg
```

The Brent-Kung circuit in Figure 1 can be constructed as follows:

```
c =
    (cfan 2 'cbeside' cfan 2) 'cabove'
    cstretch [2, 2] (cfan 2) 'cabove'
    (cidentity 1 'cbeside' cfan 2 'cbeside' cidentity 1)
```

It can be evaluated directly using gwidth and gwellSized.

# 9. Related Work

Throughout this paper we have talked about the relationship with Jeremy Gibbons's work on deep and shallow embeddings for DSLs. In this section, we will discuss additional related works.

Type class for membership relations Bahr and Axelesson[5] presented a recursion scheme based on attribute grammars that can be transparently applied to trees and acyclic graphs. When discussing synthesisd attributes, they introduced a type class to express that an attribute of type c is part of a larger collection of attributes, and corresponding projection functions. However, they restricted the usage of the type class to synthesised attributes without generalizing it to algebras. Moreover, no dependencies were involved throughout their discussion of attributes.

# 10. Conclusion

We have presented composable algebra with dependencies. To support dependent interpretation with *fold*, we introduced a way to compose algebras together, and approaches to encode dependent relations in composed algebras. We showed that dependent interpretations can be achieved using composed algebras with *fold*. Apart from F-Algebra, we presented two other representations of algebra: type class and record, and showed how they can be used to support dependent interpretations.

# References

- [1] Sheard, Tim and Pasalic, Emir. Two-level types and parameterized modules. *Journal of Functional Programming*. 14(5):547-587, September 2014.
- [2] Gibbons, Jeremy and Wu, Nicolas. Folding Domain-Specific Languages: Deep and Shallow Embeddings. *International Conference on Functional Programming*. 2014.
- [3] Fokkinga, Maarten M. Tupling and mutumorphisms. 1990.
- [4] Oliveira, B.C.d.S., Mu, Shin-Cheng and You, Shu-Hung. Modular Reifiable Matching: A List-of-Functors Approach to Two-Level Types. February 2015.
- [5] Bahr, Patrick and Axelsson, Emil. Generalising Tree Traversals to DAGs. Proceedings of the 2015 Workshop on Partial Evaluation and Program Manipulation, pages 27-38. 2015