QUANTUM CIRCUITS AS CONTRACTION PROVIDERS FOR

tnreason

RESEARCH NOTES IN THE ENEXA PROJECT

July 21, 2025

By its central axioms, quantum mechanics of multiple qubits is formulated by tensors capturing states and discrete time evolutions. Quantum circuits are contractions of multiple tensors and therefore tensor networks, and measurement probabilities are given by contractions. Here we investigate how we can exploit these as contraction provider for threason.

1 Comparing tensor networks and quantum circuits

First of all, we need to extend to complex tensors, which are maps

$$\tau: \underset{k \in [d]}{\textstyle \times} [2] \to \mathbb{C}$$

with image in \mathbb{C} instead of \mathbb{R} as in the report.

A coarse comparison of the nomenclature used for quantum circuits and tensor networks:

Quantum Circuit	Tensor Network
Qubit	Boolean Variable
Quantum Gate	Unitary Tensor
Quantum Circuit	Tensor Network on a graph

Some constraints appear for a tensor network to be a quantum circuit

• Unitarity of each gate: That is the variables of each tensor are bipartite into sets A^{in} and A^{out} of same cardinality and the basis encoding with respect to this bipartition, that is

$$T_{\mathrm{in} \to \mathrm{out}}[X_{\mathrm{in}}, X_{\mathrm{out}}] : \bigotimes_{k \in A^{\mathrm{in}}} \mathbb{C}^2 \to \bigotimes_{k \in A^{\mathrm{out}}} \mathbb{C}^2 \,,$$

is a unitary map, that is

$$\left(T_{\mathrm{in}\to\mathrm{out}}\right)^{H}\circ\left(T_{\mathrm{in}\to\mathrm{out}}\right) = \left\langle T_{\mathrm{in}\to\mathrm{out}}[X_{\mathrm{in}},Y],\overline{T}_{\mathrm{in}\to\mathrm{out}}[Y,X_{\mathrm{out}}]\right\rangle\left[X_{\mathrm{out}},X_{\mathrm{in}}\right] = \delta\left[X_{\mathrm{out}},X_{\mathrm{in}}\right].$$

- Acylicity: Incoming and outgoing variables of each tensor core provide a direction of each edge tensor. With respect to this directionality the graph underlying the tensor network has to be acyclic.
- Incoming-Outgoing structure: Variable appear at most once as incoming and at most once as outgoing
 variables. Those appearing either as incoming or as outgoing are the input and the output variables of the
 whole circuit.

The unitary tensors can be aligned layerwise, if and only if the last two assumption hold, i.e. the directed graph is acylic and each variable appears at most once as an incoming and at most once as an outgoing variable.

2 Representing Computation Activation Networks as Quantum Circuits

2.1 Value Qubits

We introduce a value qubit, which stores in its coefficient to the first state the probability of the configuration. When we have a probability tensor, this can be prepared, since all values are in [0,1]. The value qubit is intialized by the zeroth one hot encoding $(|0\rangle)$ and rotated by a controlled rotation gate, which is controlled by the variable qubits.

2.2 Polynomial Sparsity

Each monomial can be prepared by a multiple-controlled NOT gate, where the control qubits are the affected variables and the target qubit is the value qubit. When we sum monomials wrt modulus 2 calculus, then the preparation is a sequence of such circuits. In such way, we can prepare any propositional formula.

2.3 Decomposition Sparsity

We can decompose any propositional formula into logical connectives and prepare to each a modulus 2 circuit implementation. This works, when the target qubit of one connective is used as a value qubit of another.

2.4 Quantum Rejection Sampling

Note, that the variable qubits are uniformly distributed when only the computation circuit is applied. When sampling the probability distribution, we need the value qubit to be in state 1 in order for the sample to be valid. Any other states will have to be rejected.

Classically, this can be simulated in the same way: Just draw the variables from uniform, calculate the value qubit by a logical circuit inference and accept with probability by the computed value.

For this procedure to be more effective (and in particular not having an efficient classical pendant), we need amplitude amplification on the value qubit. This can provide a square root speedup in the complexity compared with classical rejection sampling.

3 POVM measurements as contractions

The main difficulty of using quantum circuits as contraction providers is that we can only extract information through measurements. Therefore measurement is the only way to execute contractions of the circuit, which come with restrictions when interested in contraction with open variables.

The most general measurement formalism is through a POVM, a set $\{E_y : y \in [r]\}$ of positive operators with

$$\sum_{y \in [r]} E_y = I$$

Measuring a pure state $|\psi\rangle$ We then get outcome m with probability

$$\langle \psi | E_u | \psi \rangle$$

We define a measurement variable Y taking indices $y \in [r]$ and a measurement tensor

$$E[Y, X_{\rm in}, X_{\rm out}]$$

with slices

$$E[Y = y, X_{\text{in}}, X_{\text{out}}] = E_y.$$

Repeating the measurement asymptotically on a state $|\psi\rangle$ prepared by a quantum circuit $\tau^{\mathcal{G}}$ acting on the trivial start state \mathbb{I} , we denote the measurement outcome by y^j . In the limit $m \to \infty$ we get almost surely

$$\frac{1}{m} \sum_{j \in [m]} \epsilon_{y^j} [Y] \to \left\langle \tau^{\mathcal{G}}[X_{\rm in}], E[Y, X_{\rm in}, X_{\rm out}], \tau^{\tilde{\mathcal{G}}}[X_{\rm out}] \right\rangle [Y] .$$