

EDB Backup and Recovery Tool Version 2.5.2

1	EDB Postgres BART Installation and Upgrade Guide	3
1.1	Requirements Overview	3
1.2	Installing BART	4
1.3	Configuring BART	7
1.4	Troubleshooting	26
1.5	Performing a BART Upgrade	27
1.6	Uninstallation	29
2	EDB Postgres Backup and Recovery Tool Quickstart	29
2.1	Installation	30
2.2	Configuring BART	31
2.3	Configuring a Database Server	34
2.4	Taking a Backup	36
3	EDB Postgres Backup and Recovery Reference Guide	39
3.1	Using BART Subcommands	40
3.1.1	BACKUP	41
3.1.2	CHECK-CONFIG	47
3.1.3	DELETE	49
3.1.4	INIT	51
3.1.5	MANAGE	57
3.1.6	RESTORE	61
3.1.7	SHOW-SERVERS	67
3.1.8	SHOW-BACKUPS	68
3.1.9	VERIFY-CHKSUM	70
3.1.10	Running the BART WAL Scanner	71
3.2	Examples	75
3.3	Restoring an Incremental Backup	100
3.4	A Sample BART System with Local and Remote Database Servers	104

1 EDB Postgres BART Installation and Upgrade Guide

The EDB Postgres Backup and Recovery (BART) Installation and Upgrade Guide is a comprehensive guide that provides detailed information about how to install and upgrade BART. This guide is organized as follows:

- Requirements Overview section provides information about BART installation requirements and limitations.
- Using an RPM Package to Install BART section provides instructions for installing and upgrading BART.
- Configuring BART section provides instructions for configuring BART and the database servers.
- Troubleshooting section provides information about installation troubleshooting.
- Performing a BART Upgrade section provides information about upgrading BART.
- Uninstallation section provides information about uninstalling BART.

1.1 Requirements Overview

The following sections detail the requirement for BART installation.

Supported Platforms

BART can be installed on the following 64-bit platforms:

- CentOS 6.x or 7.x
- Red Hat Enterprise Linux (RHEL) 6.x or 7.x
- PPC-LE 8 running RHEL or CentOS 7.x
- Ubuntu 18.04 (Bionic)
- Debian 9.x (Stretch)

Supported Database Versions

BART supports the following database versions:

- Advanced Server versions 9.5, 9.6, 10, 11, 12
- PostgreSQL versions 9.5, 9.6, 10, 11, 12

Software Requirements

The following sections detail the components required for BART installation.

BART Host Components

Use EnterpriseDB packages to add BART host components; see Installing BART using an RPM Package for installation instructions.

Additional Components

In addition to the BART host components, the following components must be enabled and activated:

- The Secure Shell (SSH) server daemon must be enabled and activated on the BART host, as well as on any remote database server hosts on which BART will be managing backup and recovery.
- The SSH and Secure Copy (SCP) client programs must be available on the BART host as well as on the remote database server hosts.

See the Authorizing SSH/SCP Access <authorizing ssh/scp access> section for additional information.

BART uses the pg_basebackup utility program when taking full backups. Your pg_basebackup version must be the same or more recent than the database server to be backed up. For example, pg_basebackup version 10 can back up database server version 10, but cannot be used to back up database server version 11.

Limitations

BART can take backups from database clusters with a WAL segment file size other than the default size of 16 MB. You can use the Advanced Server initdb --wal-segsize option to modify the WAL segment file size.

For information about using the Advanced Server initdb --wal-segsize option, see the EDB Postgres Advanced Server User Guide available at:

https://www.enterprisedb.com/edb-docs/

• BART supports taking only a full backup of standby servers; it does not support taking incremental and parallel backups of standby servers.

1.2 Installing BART

This section will walk you through performing a fresh installation of BART on a host. This section is organized as follows:

- Using an RPM Package to Install BART section describes how to install BART using an RPM package.
- Installing BART on a Debian or Ubuntu Host section describes how to install BART on a Debian or Ubuntu host.

Using an RPM Package to Install BART

Perform the following steps to use an RPM package to install BART:

Step 1 Assume superuser privileges and install the *Extra Packages for Enterprise Linux (EPEL)* package by invoking the following command:

```
yum install -y epel*
```

The EPEL package contains supporting libraries required by BART; if yum cannot access a repository that contains epel-release, see the Troubleshooting section for help.

Step 2 Use either yum or rpm to create the repository configuration file.

```
yum install -y https://yum.enterprisedb.com/edbrepos/edb-repo-
latest.noarch.rpm
```

or

```
rpm -Uvh https://yum.enterprisedb.com/edbrepos/edb-repo-latest.noarch.rpm
```

Step 3 Visit the following website to request credentials to the EDB Yum Repository:

https://www.enterprisedb.com/repository-access-request/

Step 4 Use your choice of editor to open and modify the repository configuration file. The repository configuration file is named edb.rep and is located in the /etc/yum.repos.d directory.

Step 5 After creating the **edb.repo** file, use your choice of editor to:

- ensure that the value of the enabled parameter is 1.
- replace the username and password placeholders in the baseurl specification with the name and password of a registered EnterpriseDB user.

```
[edb]
name=EnterpriseDB RPMs $releasever - $basearch
baseurl=https://<username>:<password>@yum.enterprisedb.com/edb/redhat/
rhel-$releasever-$basearch
enabled=1
gpgcheck=1
gpgcheck=1
gpgkey=file:///etc/pki/rpm-gpg/ENTERPRISEDB-GPG-KEY
```

Step 6 After modifying applicable entries in the repository configuration file, save the configuration file and exit the editor.

Step 7 Optionally, install the pg_basebackup utility program using the server client package. If you do not already have the pg_basebackup program installed on the BART host, you can install a limited number of files that include the pg_basebackup program by using the following command to install the server client package:

```
yum install edb-asxx-server-client
```

In the above command, replace xx with the required Advanced Server version. For example, to install the as11 server client package, execute the command:

```
yum install edb-as11-server-client
```

Step 8 Use the following command to install the BART RPM package:

```
yum install edb-bart
```

Step 9 Repeat the installation process described in this section to install BART on each remote host on which an

incremental backup is to be restored.

You can use the following command to verify the BART installation:

```
/usr/bin/bart --version
```

The bart --version command should return the current BART version. If the bart --version command returns an error stating the PATH is not available after switching from the root user to another BART user account, adjust the setting of the PATH environment variable to include the directory location of the BART bin subdirectory in the ~/.bashrc or ~/.bash profile files of the following user accounts:

- The BART user account on the BART host. See the Configuration Section (Step 3) for details.
- The remote user account on the remote host to which incremental backups are to be restored. For details, see the *Restoring an Incremental Backup on a Remote Host* Section of the *EDB Postgres Backup and Recovery User Guide* available at:

https://www.enterprisedb.com/edb-docs/

Upon successful installation, BART is installed in the BART HOME directory:

```
/usr/edb/bart
```

The installation includes the following files:

File Name	Location	Description
bart	<pre><bart_home>/bin</bart_home></pre>	BART command line, executable program
bart-scanner	<pre><bart_home>/bin</bart_home></pre>	BART WAL scanner program
bart.cfg.sample	<pre><bart_home>/etc</bart_home></pre>	Sample BART configuration file
<pre>xlogreader_ident.so</pre>	<pre><bart_home>/lib</bart_home></pre>	Libraries supporting WAL versions
bart_license.txt	<bart_home></bart_home>	License agreement

After BART is installed successfully, you need to configure. See the Configuration Section for details.

Installing BART on a Debian or Ubuntu Host

To install BART on a Debian or Ubuntu host, you must have credentials that allow access to the EnterpriseDB repository. To request credentials for the repository, visit the EnterpriseDB Repository Access Request page.

Perform the following steps to install a Debian package using the EnterpriseDB apt repository.

1. Assume the superuser privileges.

```
sudo su -
```

2. Configure the EnterpriseDB repository.

```
sh -c 'echo "deb
https://username:password@apt.enterprisedb.com/$(lsb_release -cs)-edb/
$(lsb_release -cs) main" > /etc/apt/sources.list.d/edb-$(lsb_release -cs).list'
```

3. Add support to your system for secure APT repositories.

```
apt-get install apt-transport-https
```

4. Add the EBD signing key; When invoking the command, replace the username and password with the credentials provided by EnterpriseDB.

```
> wget -q -0 - https://username:password@apt.enterprisedb.com/edb-
deb.gpg.key | apt-key add -
```

5. Update the repository metadata.

```
apt-get update
```

6. Install the Debian package.

```
apt-get install edb-bart
```

1.3 Configuring BART

To configure BART, you must:

- 1. Establish the BART user account.
- 2. Configure the BART host.
- 3. Configure the database server.

Establishing the BART User Account

The *BART user account* is an operating system user that will run the BART command line program. The BART user account must:

- own the BART backup catalog.
- be able to run the bart program and the bart-scanner program.
- establish a SSH/SCP connection to and from each database server managed by BART.

You can optionally use the:

- enterprisedb database user as the BART user account for an Advanced Server database
- postgres database user as the BART user account for a PostgreSQL server.

If you do not wish to use an existing database user as the BART user account, you must create an operating system user to assume the role.

Configuring the BART Host

This section describes the initial BART configuration steps that must be performed on the BART host.

Step 1. Copy the bart.cfg.sample file to create the bart.cfg file. The BART configuration file (bart.cfg) is located in BART_HOME/etc/bart.cfg. For example, you can use the following command to create the bart.cfg file:

```
cp bart.cfg.sample bart.cfg
```

Step 2. Confirm if the pg_basebackup utility program is installed on the BART host. The pg_basebackup utility resides in the bin directory under your Postgres installation.

Step 3. Ensure that the LD_LIBRARY_PATH environment variable includes the location of the libpq library. If your libpq library does not reside in the default location (POSTGRES_INSTALL_HOME/lib), you must add the library path to the LD_LIBRARY_PATH environment variable. Modify the BART user account's profile (bash profle file is located in the /home/<bar>

```
# .bash_profile
# Get the aliases and functions
if [ -f ~/.bashrc ]; then
. ~/.bashrc
fi
# User specific environment and startup programs
export LD_LIBRARY_PATH=/usr/edb/as11/lib:$LD_LIBRARY_PATH
```

Step 4. Create the BART backup catalog. The BART user account must hold privileges to create subdirectories and files within the location specified in the backup_path parameter in the BART configuration file. In the following example, the BART configuration file specifies opt/backup as the parent directory for the BART backup catalog:

```
[BART]
bart_host = bartuser@192.168.2.22
backup_path = /opt/backup
pg_basebackup_path = /usr/edb/as11/bin/pg_basebackup
logfile = /tmp/bart.log
scanner_logfile = /tmp/bart_scanner.log
```

In the following example, bartuser is the BART user account. The example creates and sets the ownership and permissions on the BART backup catalog:

```
su root
mkdir /opt/backup
chown bartuser /opt/backup
chgrp bartuser /opt/backup
chmod 700 /opt/backup
```

If the subdirectory does not exist, BART creates a subdirectory for each database server listed in the configuration file when you invoke the bart command line program.

Step 5. Specify the BART configuration parameter values in the BART configuration file (located in BART_HOME/etc/bart.cfg). Some parameters must be set in the server section, while others may be set in either the server section or the global (also referred as BART) section.

In the table that follows:

• global refers to parameters set in the [BART] section and it lists the scope of each parameter. Global parameters apply to backup and recovery management on all BART managed database servers.

• server refers to parameters set in the database server section and it lists the scope of each parameter.

Parameter	Required	Default	Server	Global
<pre><bart_host></bart_host></pre>	Yes	N/A	N/A	yes
<pre><backup_path></backup_path></pre>	Yes	N/A	N/A	yes
<pg_basebackup_path></pg_basebackup_path>	Yes	N/A	N/A	yes
xlog_method	No	Fetch	N/A	yes
retention_policy	No	0	N/A	yes
wal_compression	No	Disabled	Yes	yes
copy_wals_during_restore	No	Disabled	Yes	yes
logfile	No	Disabled	Yes	yes
scanner_logfile	No	None	Yes	yes
<pre><bart_socket_directory></bart_socket_directory></pre>	No	/tmp	N/A	yes
<thread_count></thread_count>	No	1	Yes	yes
<pre><batch_size></batch_size></pre>	No	49142	Yes	yes
<scan_interval></scan_interval>	No	0	Yes	yes
<mbm_scan_timeout></mbm_scan_timeout>	No	20 seconds	Yes	yes
<workers></workers>	No	1	Yes	yes

The following is an example of BART configuration parameters in the global section [BART]:

```
bart_host = bartuser@192.168.2.22
backup_path = /opt/backup
pg_basebackup_path = /usr/edb/as11/bin/pg_basebackup
retention_policy = 3 MONTHS
logfile = /tmp/bart.log
scanner_logfile = /tmp/bart_scanner.log
bart_socket_directory = /home/edb/scanner_socket
```

- <bart_host (required) <bart_host_address> is the IP address of the BART host. Specify the parameter value in the form of <bart_user>@<bart_host_address>.
- <backup path> (required) Specify the path to the file system parent directory where all BART backups are

stored.

• <pg_basebackup_path> (required) - Specify the path to the pg_basebackup program that you installed on the BART host. For information about pg_basebackup version-specific restrictions, see the EDB Postgres Backup and Recovery User Guide available at:

https://www.enterprisedb.com/edb-docs/

- xlog_method (optional) Specify how the transaction log is collected during the execution of pg_basebackup through the BACKUP subcommand.
 - Set xlog_method to fetch to collect the transaction log files after the backup is completed. This is the default setting.
 - Set to stream to stream the transaction log in parallel with the full backup creation. If stream is used, the max_wal_senders configuration parameter in the postgresql.conf file for the affected database servers must account for an additional session for the streaming of the transaction log, (that is, the setting must be a minimum of 2).
- retention_policy (optional) Specify the retention policy for the backup. This determines when an active backup should be marked as obsolete. You can specify the retention policy either in terms of number of backup or in terms of duration (days, weeks, or months).

```
<max_number> BACKUPS

<max_number> DAYS

<max_number> WEEKS

<max_number> MONTHS

where <max_number> is a positive integer.
```

If you do not specify a keyword (BACKUPS, DAYS, WEEKS, or MONTHS), the integer is interpreted as <max number> BACKUPS by default.

If the retention_policy parameter is not specified, then no backups are marked as obsolete when the MANAGE subcommand is used. For information about managing backups using a retention policy, see the EDB Postgres Backup and Recovery User Guide available at:

https://www.enterprisedb.com/edb-docs/

• wal_compression (optional) - Set wal_compression parameter to enabled to compress the archived WAL files in gzip format in the BART backup catalog when the MANAGE subcommand is invoked. By default it is set to disabled.

Note

The gzip compression program must be in the BART user account's PATH.

For information about using the MANAGE subcommand for WAL compression, see the *EDB Postgres Backup* and Recovery User Guide available at:

https://www.enterprisedb.com/edb-docs/

• copy_wals_during_restore (optional) - Use copy_wals_during_restore parameter to specify how the archived WAL files are collected during the restore operation.

Set this parameter to:

- enabled to copy the archived WAL files from the BART backup catalog to the restore_path/archived_wals directory prior to the database server archive recovery. Enabling this option helps you save time during the restore operation.
- disabled to retrieve the archived WAL files directly from the BART backup catalog during the database server archive recovery. This is the default setting.

During the restore operation, recovery settings will be saved in the postgresql.auto.conf file. The restore_command in the postgresql.auto.conf file will be determined by the value specified in the copy wals during restore parameter.

- If the RESTORE subcommand is invoked with the -c option, the archived WAL files are copied from the BART backup catalog to the restore_path/archived_wals directory, thus overriding any setting of the copy wals during restore parameter.
- If the RESTORE subcommand is invoked without the -c option, the value specified by the copy wals during restore parameter is used.

For more information about the **RESTORE** command, see the *EDB Postgres Backup and Recovery User Guide* available at:

https://www.enterprisedb.com/edb-docs/.

• logfile (optional) - Use logfile paramter to specify the path to the BART log file. The default location is /tmp/bart.log.

The log file will be created the first time you invoke the bart command line program using the sample configuration file value. To change the default setting, you must delete the /tmp/bart.log file so that a new log file will be created and owned by the new BART user account.

- scanner_logfile (optional) Use scanner_logfile parameter to specify the path to the XLOG/WAL scanner log file. The default location is /tmp/bart_scanner.log. The scanner log file will be created the first time you invoke the bart command line program using the sample configuration file value. To change the default setting, you must delete the /tmp/bart.log file so that a new log file will be created and owned by the new BART user account.
- <bart_socket_directory> (optional) Specify the socket directory path where all BART sockets will be stored. The default directory is /tmp.

While specifying the bart_socket_directory path, you must ensure that the directory exists and the BART user has the required access permissions to the directory.

- <thread_count> (optional) Specify the number of worker threads for copying blocks (for incremental backups) or data files (for full backup) from the database server to the archive_path when the BACKUP subcommand is invoked. The default thread count value is 1.
 - \circ If parallel backup is run with N number of worker threads, then it will initiate N + 1 concurrent connections with the server.
 - <thread count> will not be effective if the backup is taken on a standby server.
 - The same set of processes are used for the compression operation when taking full backups in order to provide parallel, compressed backups when the BACKUP subcommand is specified with the -z or -c options.

Note

The compression operation does not apply to incremental backups.

If the BACKUP subcommand is invoked with the --thread-count option, then the number of worker threads specified by this option overrides any setting of the thread_count parameter in the BART configuration file.

- If the BACKUP subcommand is invoked without the --thread-count option, then the following determines the number of worker threads used:
 - The setting of the thread_count parameter in the server section of the BART configuration file overrides the setting of thread_count in the global section for that particular database server. If omitted in the server section, the setting of thread_count in the global section is used.
 - If the thread count parameter is not specified in either section, the default is 1.

Note

When taking a full backup, if the thread count in effect is only 1, then the pg_basebackup utility is used to take the full backup unless the --no-pg_basebackup option is specified with the BACKUP subcommand.

• <batch_size> (optional) - Specify the number of blocks of memory used for copying modified blocks from the database server to the archive_path when the BACKUP subcommand is invoked for incremental backups.

Each block is 8192 bytes; the default value is 49142 blocks. The maximum permitted value is 131072 (131072 * 8192 = 1 GB). The minimum permitted value is 1 (1 * 8192 = 8192 bytes). Reduce the setting if the server runs out of memory while executing pg read binary file().

- <scan_interval> (optional) Specify the number of seconds after which the WAL scanner should scan the new WAL files. The default value is 0, which means no brute-force scanning will be started.
- <mbm_scan_timeout> (optional) Specify the number of seconds to wait for MBM files before timing out; the default value is 20 seconds. The mbm scan timeout parameter value must be greater than
 - 0. If the value is 0 or negative, then an error will be displayed during an incremental backup.

Note

The mbm scan timeout parameter is applicable only for incremental backup.

• <workers> (optional) - Specify the number of parallel worker processes required to stream the modified blocks of an incremental backup to the restore host. The default value is 1.

Step 6 Invoke the CHECK-CONFIG subcommand, omitting the -s option to check the parameter settings in the BART configuration file including bart_host, backup_path, and pg_basebackup_path. The CHECK-CONFIG subcommand displays an error message if the required configuration is not properly set.

The following example shows successful checking of the global section of the BART configuration file:

- bash-4.1\$ bart CHECK-CONFIG
- INFO: Verifying that pg basebackup is executable
- INFO: success
- pg_basebackup(/usr/edb/as11/bin/pg_basebackup) returns version 11.400000

Configuring the Database Server

This section describes the procedure for enabling BART backup and recovery management for a database server. To configure the database server, you need to:

• Authorize SSH/SCP access without a password prompt.

- Create and configure a replication database user.
- Update the BART configuration file (server section).
- Enable WAL archiving of the server.
- Verify the server configuration settings.

Note

You must authorize SSH/SCP access and set up a replication database user before restarting the database server with WAL archiving enabled.

Authorizing SSH/SCP Access

BART uses the Secure Shell (ssh) and Secure Copy (scp) Linux utility programs to copy the backup and WAL files from the BART managed database servers to the BART host as well as to restore backups.

The client/server ssh and scp commands must not prompt for a password when establishing a connection with the server. A passwordless connection uses *authorized public keys* to authenticate with the server. An *authorized public key* is the public key of a client user account that is authorized to connect to the target server. You must add the public key of each client user account to the target user account's authorized public keys list on the target server.

The sections that follow describe how to:

- Enable public key authentication on the server running the SSH server daemon.
- Configure the authorized public keys file.
- The combination of hosts for BART usage on which a connection must be established without a password prompt.

Specific examples are provided in the EDB Postgres Backup and Recovery Reference Guide, available at:

https://www.enterprisedb.com/edb-docs/

Enabling Public Key Authentication Usage

The following example enables SSH/SCP access on a CentOS 6.x host; similar (platform-specific) steps will apply to other platforms/versions.

1. First, enable public key authentication; in the SSH server daemon configuration file (/etc/ssh/sshd_config) ensure that the following parameter is set to yes and is not commented:

```
PubkeyAuthentication yes
```

2. Reload the configuration file:

```
[root@localhost ssh]# service sshd reload
Reloading sshd: [ OK ]
```

The following commands can be used instead of service sshd reload:

```
service sshd start
service sshd restart
```

If you get any SSH or SCP errors, examine the following log file:

```
/var/log/secure
```

Authorized Public Key Generation

The target server (the server to which a passwordless connection is being made) must contain an authorized_keys file located under the USER_HOME is the home directory of the user account on the target server that will be used to establish the remote session.

The generated public key of each client that will connect to the target server must be copied to the target server and concatenated onto the USER_HOME/.ssh/authorized_keys file. The public key should be appended onto the end of any existing authorized_keys file. Any existing authorized_keys file should not be replaced in its entirety.

The following general instructions will walk you through generating a client's public key file and creating the target server's authorized public keys file.

Step 1. On the client system, log in as the user account that will be initiating the SSH or SCP connection.

Step 2. Navigate to the user account's home directory and check for an existing .ssh subdirectory. If the .ssh directory does not exist, use the following commands to create it:

```
mkdir .ssh chown user .ssh chgrp usergroup .ssh chmod 700 .ssh
```

Where user is the user account name and usergroup is the associated group of the user.

Step 3. Generate the public key file with the following command. Accept all prompted defaults and do not specify a passphrase when prompted for one.

```
ssh-keygen -t rsa
```

The public key file named id rsa.pub is created in the .ssh subdirectory.

Step 4. Create a copy of file id rsa.pub on the target server.

For example, while logged into the client where you just generated the public key file, use SCP to make a temporary copy of it on the target server:

```
scp ~/.ssh/id_rsa.pub target_user@host_address:tmp.pub
```

Step 5. Log into the target server as target user.

For example, while logged into the client, use SSH to log into the target server:

```
ssh target user@host address
```

Step 6. Navigate into the target user account's home directory and check for an existing .ssh subdirectory. If not, create one as shown in Step 2.

Step 7. Append the temporary, client's public key file, tmp.pub, to the authorized keys file named authorized_keys. If an existing authorized keys file does not exist, create a new file, but do not completely replace any existing authorized keys file.

```
cat tmp.pub >> ~/.ssh/authorized keys
```

Make sure the authorized_keys file is only accessible by the file owner and not by groups or other users. If the authorized_keys file does not have the required permission setting (600) or it was newly created, change the file permissions as follows:

```
chmod 600 ~/.ssh/authorized keys
```

Step 8. Delete the temporary public key file, tmp.pub:

```
rm tmp.pub
```

Now, when logged into the client system as user there should be no prompt for a password when commands such as the following are given:

```
ssh target_user@host_address
or
scp file_name target_user@host_address:directory_path
or
scp target user@host address:directory path/file file name
```

BART Connections that Require Authentication without a Password

For BART usage, there are two scenarios that require a passwordless SSH/SCP connection:

• When connecting from each BART managed database server (SSH/SCP client) to the BART host (target SSH/SCP server) to support WAL archiving as implemented by the archive_command parameter. In this case, the public key file (id_rsa.pub) is generated with the ssh-keygen —t rsa command on the host of the database server.

The public key file should be generated by the user account running the database server. The public key file name should be appended to the ~/.ssh/authorized_keys file on the BART host. The authorized_keys file is in the BART user account's home directory.

• When connecting from the BART host (SSH/SCP client) to each BART managed database server (target SSH/SCP server) for taking incremental backups and for supporting restoration of the full backup, the archived WAL files, and the modified blocks, which occurs when the BART RESTORE subcommand is given.

In this case, the public key file (id_rsa.pub) is generated with the ssh-keygen —t rsa command on the BART host. The public key file is generated by the BART user account. The public key file name should be appended to the ~/.ssh/authorized_keys file on the host of the database server. The authorized_keys file is in the home directory of the user account that owns the directory where the database backup is to be restored.

If backups are to be taken from a given database server host, but restored to a different database server host, the passwordless SSH/SCP connections must be configured from the BART host to the database server host from which the backup is to be taken as well as from the BART host to the database server host to which the backup is to be restored.

For examples of each scenario, see the EDB Postgres Backup and Recovery Reference Guide available at:

https://www.enterprisedb.com/edb-docs/

Setting up a Replication Database User

For each Postgres database server that is to be managed by BART, a database user must be chosen to serve as the *replication database user*. The replication database user:

- Sets the Postgres archive command configuration parameter when the INIT subcommand in invoked.
- Creates backups when the **BACKUP** subcommand is invoked.

The replication database user must be a superuser.

When executed with the PSQL client, the following PostgreSQL command creates a superuser to be the replication database user:

```
CREATE ROLE repuser WITH LOGIN SUPERUSER PASSWORD 'password';
```

The pg_hba.conf file must minimally permit the replication database user to have access to the template1 database as shown for repuser in the following example. The IP address from which the replication database user has access to database template1 is the location of the BART host:

```
# TYPE DATABASE USER ADDRESS METHOD
# "local" is for Unix domain socket connections only
local all all md5
# IPv4 local connections:
host template1 repuser 192.168.2.22/32 md5
host all enterprisedb 127.0.0.1/32 md5
# IPv6 local connections:
host all all ::1/128 md5
# Allow replication connections from localhost, by a user with the
# replication privilege.
host replication repuser 192.168.2.22/32 md5
```

For pg_basebackup only: The replication database user must also be included in the pg_hba.conf file as a replication database connection as shown by the last entry in the example if pg_basebackup is to be used for taking any backups such as for standby servers.

The replication database user must be specified with the user parameter of the BART configuration file for the database server as shown by the following example:

```
[ACCTG]
host = 192.168.2.24
port = 5444
user = repuser
cluster_owner = enterprisedb
remote_host = enterprisedb@192.168.2.24
description = "Accounting"
```

There must be no password prompt when connecting to the database server with the replication database user. There are several Postgres standard ways to permit this. A recommended method is to use the .pgpass file located in the BART user account's home directory.

For example, if bartuser is the BART user account, then the .pgpass file located in /home/bartuser/.pgpass must contain the following entry:

```
192.168.2.24:5444::repuser:password
```

When bartuser invokes a BART backup, the password for the replication database user, repuser, is obtained from the .pgpass file of bartuser to connect to the database server running at 192.168.2.24 on port 5444.

The .pgpass file must contain an entry for each BART managed database server and its corresponding replication database user and password.

Updating the Server Configuration Parameters

To manage the backup and recovery of a database server, you must add entries to the server section of the BART configuration file (located in BART_HOME/etc/bart.cfg). Settings in the server section will override the settings in the [BART] section for that particular database server. If omitted, default values will be used.

For each cluster serviced by BART, the following parameters are required:

```
host = 192.168.2.24
port = 5432
user = postgres
cluster_owner = postgres
description = "EPAS 11 Server"
allow_incremental_backups = enabled
```

The following table lists the server-specific parameters and their default values (where applicable):

Parameter	Required	Default
[Server Name]	Yes	N/A
<pre><backup_name></backup_name></pre>	No	N/A
host	Yes	N/A
port	No	5444
user	Yes	N/A
<archive_path></archive_path>	No	BART backup catalog
<archive_command></archive_command>	No	N/A
<pre><cluster_owner></cluster_owner></pre>	Yes	enterprisedb for Advanced Server database clusters installed in the mode compatible with Oracle databases. postgres for PostgreSQL database clusters and for Advanced Server database clusters installed in PostgreSQL mode.
<remote_host></remote_host>	Yes	N/A
<tablespace_path></tablespace_path>	No	N/A
retention_policy	No	0
xlog_method	No	Fetch
wal_compression	No	Disabled
<pre>copy_wals_during_restore</pre>	No	Disabled
allow_incremental_backup	No	Disabled
thread_count	No	1
batch_size	No	49142

Parameter	Required	Default
scan_interval	No	0
mbm_scan_timeout	No	20
description	Yes	No
workers	No	1

Set the following parameters in the server section of the BART configuration file. The parameter setting in the server section overrides the setting in the global [BART] section for that particular database server. If omitted, the default value will be used.

- [ServerName] (required) Specify the server name that you want to backup using BART. This is the name by which you refer to the database server when using BART; the name is case-insensitive when referenced with BART subcommand options. A lowercase conversion of this name is used to create a subdirectory in the BART backup catalog for storing the backups and WAL files for this database server.
- <backup_name> (optional) Specify a template for user-defined, friendly names that will be assigned to the backups of the database server. The maximum permitted length of backup names is 49 characters. The template is an alphanumeric string that may include the following variables that will be replaced with the timestamp values when the backup is taken:

```
%year - 4-digit year
%month - 2-digit month
%day - 2-digit day
%hour - 2-digit hour
%minute - 2-digit minute
%second - 2-digit second
```

To include a percent sign (%) as a character in the backup name, specify %% in the template.

Do not enclose the template string in quotes even if you want the template to include space characters, otherwise the enclosing quotes are stored as part of the backup name. However, when referenced with the -i option by BART subcommands use of space characters in the backup name requires enclosing the backup name in quotes.

This parameter can be overridden by the **--backup-name** option of the **BACKUP** subcommand. If this parameter is omitted from the BART configuration file, and the **--backup-name** option with a user-defined name is not specified with the **BACKUP** subcommand, then the backup can only be referenced in BART subcommands by the BART assigned, integer backup identifier.

- host (required) Specify the IP address of the database server to be configured for backup.
- port (optional) Specify the port number identifying the database server instance (that is, the relevant database cluster) to be backed up. The default is port 5444.
- User (required) Specify the replication database user name used by BART to:
 - establish the connection to the database server for full backups
 - set the Postgres archive_command configuration parameter when running the INIT subcommand
 - take incremental backups. This database user must be a superuser.

While running as the BART user, the connection to the database server must not prompt for a password. The

pg_hba.conf file must contain a replication connection entry for this database user name. See Setting up a Replication Database User for more information.

- <archive_path> (optional) Specify the path where archived WAL files will be stored. The default location of the archived WAL files is the BART backup catalog (<backup path>/<server name>/archived wals).
- <archive_command> (optional) When the INIT subcommand is used, the content and variables specified in the BART archive_command result in the archive command string to be generated into the Postgres archive command parameter in the postgresql.auto.conf file.

The BART archive_command parameter in the BART configuration file, and the Postgres archive_command parameter in the postgresql.conf file (or the postgresql.auto.conf file) refer to two different parameters that are to be set in different manners. You should carefully observe the distinction between the BART archive_command and the PostgreSQL archive_command when configuring these parameters.

The following information applies only to the BART archive command parameter.

- Enclose the command string within single quotes (').
- If the archive_command parameter is omitted, it still results in its usage by the INIT subcommand as if it were actually specified with a setting of scp %p %h:%a/%f. The variables represent:
 - *p The path of the file to archive used by the Postgres archiving process.
 - %h Will be replaced by the <bart host> parameter setting.
 - %a Will be replaced by the BART archived_wals directory as specified in the archive_path parameter in the server section of the bart.cfg file. If the archive_path is not specified, then the default archived_wals directory is

 backup_path>/<server_name>/archived_wals where <backup_path> is the BART backup catalog parent directory specified in the global section of the BART configuration file and <server_name> is the lowercase conversion of the database server name specified for this database server in the server section of the BART configuration file.
 - % f − The archived file name used by the Postgres archiving process.

See Archive Command Auto Configuration for additional information.

- <cluster_owner> (required) Specify the Linux operating system user account that owns the database cluster. This is typically enterprisedb for Advanced Server database clusters installed in the Oracle compatible mode, or postgres for Advanced Server database clusters installed in the PostgreSQL compatible mode and PostgreSQL database clusters.
- <remote_host> (optional). Specify the IP address of the remote server to which a backup is to be restored.
 The value for this parameter must be specified in the form of
 <remote user>@<remote host address>. Where:

<remote_user> is the user account on the target database server host that accepts a passwordless
SSH/SCP login connection and owns the directory where the backup is to be restored.

<remote_host_address> is the IP address of the remote host. For restoring a backup to a remote
host or for restoring any backup where <remote_user> and the BART user account are not the same
users, either this parameter must be set or it may be specified with the -r option with the BART
RESTORE subcommand.

<tablespace_path> (optional) - Specify path to which tablespaces are to be restored in the format OID =

<tablespace_path>; If the backup is to be restored to a remote host specified by the <remote_host> parameter, then the tablespace paths must exist on the remote host.

• allow_incremental_backups (optional) - Enables use of the WAL scanner for incremental backups. Permits taking incremental backups when the BACKUP subcommand is invoked with the --parent option.

Set this parameter to:

enabled to permit incremental backups.

disabled to disallow incremental backups and thus permit only full backups.

If the allow incremental backups parameter is not specified, the default is disabled.

For information about using the BACKUP subcommand and running the WAL scanner, please see the EDB Postgres Backup and Recovery User Guide available at:

https://www.enterprisedb.com/edb-docs/

• Description (optional) – Specify the description of the database server. This parameter is optional.

Refer to the Configuring the BART host section for information about configuring the following optional parameters.

```
retention_policy
xlog_method
wal_compression
copy_wals_during_restore.
thread_count.
batch_size.
scan_interval.
mbm_scan_timeout.
workers
```

After configuring the BART host and the database server(s), you can start using BART. For information about using BART, see the *EDB Postgres Backup and Recovery User Guide* available at:

https://www.enterprisedb.com/edb-docs/

The following example shows the configuration settings of three database servers:

```
[ACCTG]
host = 127.0.0.1
port = 5444
user = enterprisedb
cluster_owner = enterprisedb
backup_name = acctg_%year-%month-%dayT%hour:%minute:%second
archive_command = 'cp %p %a/%f'
allow_incremental_backups = enabled
retention_policy = 8 BACKUPS
description = "Accounting"

[MKTG]
host = 192.168.2.24
```

```
port = 5444
user = repuser
cluster_owner = enterprisedb
remote_host = enterprisedb@192.168.2.24
allow_incremental_backups = enabled
description = "Marketing"

[HR]
host = 127.0.0.1
port = 5432
user = postgres
cluster_owner = postgres
retention_policy = 4 DAYS
description = "Human Resources"
```

Enabling WAL Archiving

WAL archiving must be enabled for the database server for which BART is to perform backup and recovery management. For detailed information about WAL archiving, see the PostgreSQL Core Documentation. The following sections provide information about configuring WAL Archiving for BART:

- The WAL Archiving Configuration section describes the manual WAL Archiving Configuration process.
- The Archive Command Auto Configuration section describes an automated WAL Archiving process.

WAL Archiving Configuration

The following configuration parameters must be set in the postgresql.conf file to enable WAL archiving:

- Set wal level to archive for Postgres 9.5 or to replica for Postgres 9.6 or later.
- Set archive mode to on.
- Set the PostgreSQL archive_command parameter to copy the WAL files to the archive_path. The archive_command configuration parameter mentioned here is located in the postgresql.conf file; the PostgreSQL archive_command parameter is used in a different manner than the BART archive command parameter previously mentioned in this guide.
- Set max_wal_senders to a value high enough to leave at least one session available for the backup. If the xlog_method=stream parameter setting is to be used by this database server as determined in the BART configuration file, the max_wal_senders setting must account for an additional session for the transaction log streaming (the setting must be a minimum of 2). See Configuring the BART host for information about the xlog_method parameter.

The ARCHIVE PATH field displayed by the BART SHOW-SERVERS subcommand displays the full directory path where the WAL files should be copied as specified in the Postgres archive_command configuration parameter in the postgresql.conf file:

```
-bash-4.1$ bart SHOW-SERVERS -s acctg

SERVER NAME : acctg

HOST NAME : 192.168.2.24

USER NAME : repuser

PORT : 5444

REMOTE HOST :

RETENTION POLICY : none
```

```
DISK UTILIZATION: 0.00 bytes

NUMBER OF ARCHIVES: 0

ARCHIVE PATH: /opt/backup/acctg/archived_wals

ARCHIVE COMMAND: (disabled)

XLOG METHOD: fetch

WAL COMPRESSION: disabled

TABLESPACE PATH(s):
INCREMENTAL BACKUP: DISABLED

DESCRIPTION: "Accounting"
```

The parameter settings in the following example will copy the WAL files to a directory named /opt/backup/acctg/archived_wals on the BART host located at 192.168.2.22 as the bartuser user account. Using the bartuser account ensures that the operation will have sufficient permissions to copy to the BART backup catalog owned by bartuser.

```
wal level = archive
                                          # minimal, archive, or hot standby
                                          # (change requires restart)
archive mode = on
                                          # allows archiving to be done
                                          # (change requires restart)
archive command = 'scp %p
bartuser@192.168.2.22:/opt/backup/acctg/archived_wals/%f'
                                          # command to use to archive a
logfile segment
                                          # placeholders: %p = path of file
to archive
                                          # %f = file name only
max wal senders = 1
                                          # max number of walsender processes
                                          # (change requires restart)
```

The database server must be restarted in order to initiate WAL archiving, but do not do so until you have verified that the full path of the BART backup catalog has been created by some prior BART subcommand or the archive operation will fail.

Start the WAL scanner by executing the following command:

```
./bart-scanner
```

Archive Command Auto Configuration

The Postgres archive_command parameter can be automatically configured with the INIT subcommand. The INIT subcommand invokes the Postgres ALTER SYSTEM command to set the Postgres archive_command configuration parameter in the postgresql.auto.conf file located in the managed database server's POSTGRES_INSTALL_HOME data directory. For additional information about the INIT subcommand, see the EDB Postgres Backup and Recovery User Guide available at:

https://www.enterprisedb.com/edb-docs/

The archive command string that the INIT subcommand generates into the postgresql.auto.conf file is determined by the parameter setting of the BART archive_command parameter located in the BART configuration file.

The server section of the BART configuration file can contain a BART archive_command parameter to specify the desired format of the archive command string to be generated into the Postgres archive_command parameter in the postgresql.auto.conf file. If the BART archive_command parameter is not set in the server section for a given database server, the command string that is configured uses the following default format:

```
scp %p %h:%a/%f
```

where:

%p

Path of the file to archive used by the Postgres archiving process

%h

Replaced by the setting of the bart_host parameter located in the global section of the BART configuration file

%a

Replaced by the archive_path where the WAL files are to be stored. The default archive path takes the form backup_path/server_name/archived_wals where backup_path is the BART backup catalog parent directory specified in the global section of the BART configuration file and server_name is the lowercase conversion of the database server name specified for this database server in the server section of the BART configuration file.

%f

Archived file name used by the Postgres archiving process

The placeholders %h and %a are replaced by the INIT subcommand when creating the archive command string. The placeholders %p and %f are not replaced by the INIT subcommand, but are kept as given to be used by the Postgres archiving process.

For example, to use the default archive command format, the BART configuration file contains the following settings where the BART archive command parameter is omitted from the server section for ACCTG:

```
[BART]
bart_host= bartuser@192.168.2.22
backup_path = /opt/backup
pg_basebackup_path = /usr/edb/as11/bin/pg_basebackup
logfile = /tmp/bart.log
scanner_logfile = /tmp/bart_scanner.log

[ACCTG]
host = 127.0.0.1
port = 5444
user = repuser
cluster_owner = enterprisedb
description = "Accounting"
```

The INIT subcommand is invoked by BART user account bartuser as follows:

```
[bartuser@localhost ~]$ bart INIT -s acctg -o
```

```
INFO: setting archive_command for server 'acctg'
WARNING: archive_command is set. server restart is required
```

If the BART backup catalog directory is not already complete, it will be completed.

The resulting Postgres archive command string in the postgresql.auto.conf file located in the managed database server's POSTGRES_INSTALL_HOME/data directory appears as follows:

```
# Do not edit this file manually!
# It will be overwritten by ALTER SYSTEM command.
archive_command = 'scp %p
bartuser@192.168.2.22:/opt/backup/acctg/archived_wals/%f'
```

Run the INIT subcommand with the -o option to override any existing Postgres archive_command setting in the postgresql.conf or the postgresql.auto.conf file. In addition, the -o option must be used to generate the command string if the archive_mode is set to off even if there are no existing settings of the Postgres archive_command in the postgresql.conf or postgresql.auto.conf files.

In this example, the following BART configuration file is used with an explicit setting of the BART archive command parameter:

```
[BART]
bart_host= enterprisedb@192.168.2.22
backup_path = /opt/backup
pg_basebackup_path = /usr/edb/as11/bin/pg_basebackup
logfile = /tmp/bart.log
scanner_logfile = /tmp/bart_scanner.log

[ACCTG]
host = 127.0.0.1
port = 5444
user = repuser
cluster_owner = enterprisedb
archive_command = 'cp %p %a/%f'
description = "Accounting"
```

The INIT subcommand is invoked by BART user account enterprisedb as follows:

```
-bash-4.1$ bart INIT -s acctg -o
INFO: setting archive_command for server 'acctg'
WARNING: archive_command is set. server restart is required
```

The resulting Postgres archive_command parameter in the postgresql.auto.conf file appears as follows:

```
# Do not edit this file manually!
# It will be overwritten by ALTER SYSTEM command.
archive_command = 'cp %p /opt/backup/acctg/archived_wals/%f'
```

After generating the desired command string in the postgresql.auto.conf file, complete the required WAL archive settings in the postgresql.conf file:

- Set wal level to archive for Postgres 9.5 or to replica for Postgres 9.6 or later.
- Set archive mode to on.
- Set max_wal_senders to a value high enough to leave at least one session available for the backup. If the xlog_method=stream parameter setting is to be used by this database server as determined in the BART configuration file, the max_wal_senders setting must account for an additional session for the transaction log streaming (that is, the setting must be a minimum of 2). See Configuring the BART host for information on the xlog method parameter.

Restart the database server when you are ready to initiate WAL archiving.

When the database server has been restarted, the ARCHIVE COMMAND field of the SHOW-SERVERS subcommand displays the active Postgres archive command as shown by the following example:

```
-bash-4.1$ bart SHOW-SERVERS -s acctg
SERVER NAME : acctq
HOST NAME: 127.0.0.1
USER NAME : repuser
PORT : 5444
REMOTE HOST :
RETENTION POLICY: none
DISK UTILIZATION: 48.00 MB
NUMBER OF ARCHIVES: 0
ARCHIVE PATH : /opt/backup/acctg/archived wals
ARCHIVE SCOMMAND: cp %p /opt/backup/acctg/archived wals/%f
XLOG METHOD : fetch
WAL COMPRESSION: disabled
TABLESPACE PATH(s):
INCREMENTAL BACKUP : DISABLED
DESCRIPTION: "Accounting"
```

Verifying Configuration Settings

The CHECK-CONFIG subcommand with the —s option checks the parameter settings of the database server specified:

```
bart CHECK-CONFIG [ -s server name ]
```

The CHECK-CONFIG subcommand displays an error message if the required configuration is not properly set. The following example shows the results from a successful configuration.

```
bash-4.1$ bart CHECK-CONFIG -s mktg
INFO: Checking server mktg
INFO: Verifying cluster_owner and ssh/scp connectivity
INFO: success
INFO: Verifying user, host, and replication connectivity
INFO: success
INFO: Verifying that user is a database superuser
INFO: success
INFO: Verifying that cluster_owner can read cluster data files
INFO: success
INFO: Verifying that you have permission to write to vault
INFO: success
```

```
INFO: /opt/backup/mktg
INFO: Verifying database server configuration
INFO: success
INFO: Verifying that WAL archiving is working
INFO: success
INFO: Verifying that bart-scanner is configured and running
INFO: success
```

The CHECK-CONFIG subcommand confirms the following:

- The cluster owner parameter is set to the user account owning the database cluster directory.
- A passwordless SSH/SCP connection is set between the BART user and the user account specified by the cluster owner parameter.
- The BART user parameter specifies a database superuser.
- The BART user has access to the backup directory catalog.
- The pg_hba.conf file contains a replication entry for the database superuser specified by the BART user parameter.
- The archive mode parameter in the postgresql.conf file is enabled.
- The archive_command parameter in the postgresql.auto.conf or the postgresql.conf file is set.
- The allow_incremental_backups parameter in the BART configuration file is enabled for database servers for which incremental backups are to be taken.
- Archiving of WAL files to the archive path is in process.
- The WAL scanner program is running.

1.4 Troubleshooting

This section provides a workaround for the following installation issue:

```
Yum cannot access a repository that contains epel-release
```

If yum cannot access a repository that contains epel-release, you will get an error message:

```
No package epel available.

Error: Nothing to do
```

Workaround:

To fix this issue, you must download the **EPEL** rpm package and install it manually. To manually install **EPEL**:

- 1. Download the rpm package.
- 2. Assume the superuser privileges and navigate to the directory that contains the package.
- 3. Install **EPEL** with the command:

```
yum install epel-release
```

1.5 Performing a BART Upgrade

This section outlines the process of upgrading BART from an existing version to the latest version.

- Upgrading from BART 2.0 describes the upgrade process from BART 2.0 to the latest version.
- Upgrading from BART older versions describes the upgrade process from previous BART versions (except 2.0) to the latest version.

Upgrade Restrictions

The following restrictions apply with regard to previous BART versions.

- When using the latest version of BART (for example 2.5.2), the BART backup catalog (as specified by the backup_path parameter of the BART configuration file) must not be the same directory that was used by the previous BART versions (for example 2.5.1) for their backup catalogs. New full backups and incremental backups taken using the latest BART version must be stored in a new BART backup catalog.
- You can take incremental backups using the latest version (for example 2.5.2) only when the parent backup (full or incremental backup) has been taken with the latest version (for example 2.5.2).
- Using the latest version (for example 2.5.2), you can restore incremental backups taken only with the latest version of BART (for example 2.5.2). However, using the latest version (for example 2.5.2) you can restore full backups that were taken with older versions (for example 2.5.1).

Upgrading from older versions of BART (except 2.0) to the latest version

Perform the following steps to upgrade from older versions of BART (except 2.0) to the latest version:

Step 1: Assume the identity of the BART user account and invoke the following command to stop the BART 2.x WAL scanner program (bart-scanner):

```
bart-scanner STOP
```

Step 2: As the root user, upgrade to the latest BART version with the yum upgrade command.

• To upgrade the BART RPM package directly from the *EDB Yum Repository* website, specify only the package name:

```
yum upgrade edb-bart
```

You can also use a downloaded RPM package file to upgrade. To use a downloaded BART RPM package file to upgrade, use the yum command, specifying the complete RPM package file name:

```
yum upgrade edb-bart-2.5.x-x.rhel7.x86 64.rpm
```

Ensure the

| Spackup_path | parameter of the BART configuration file is set to a new directory and not to any existing BART 2.x backup catalog. New full backups and incremental backups taken using BART 2.5.x.x must be stored in a new BART backup catalog.

Note

The bart.cfg configuration file is only required on the BART 2.5.x.x host from which you will invoke BART subcommands. BART does not require the bart.cfg file on hosts on which an incremental backup will be restored.

Step 3: Repeat the process described in this section to upgrade to BART 2.5.x.x on each remote hosts where an incremental backup will be restored.

For additional information about restoration of incremental backups on remote hosts, see the *EDB Postgres Backup* and *Recovery User Guide* available at:

https://www.enterprisedb.com/edb-docs/

If the bart --version command returns an error stating the PATH is not available after switching from root user to another BART user account, adjust the setting of the PATH environment variable to include the location of the BART 2.5 executable (the bin subdirectory) in the ~/.bashrc or ~/.bash_profile files of the following user accounts:

- The BART user account on the BART host. See Configuring the BART host for more information about BART user account.
- The remote user account on the remote host to which incremental backups are to be restored. For details, see the *EDB Postgres Backup and Recovery User Guide* available at:

https://www.enterprisedb.com/edb-docs/

The PATH setting should be the same as set for BART 2.x since all versions use /usr/edb/bart/bin.

Note

After upgrading to BART 2.5.x.x, you must take a new full backup of your system before performing an incremental backup.

Upgrading from BART 2.0

Perform the following steps to upgrade BART 2.0 to the latest version of BART:

Step 1: Install the latest version of BART; for details, see Using an RPM Package to Install BART.

Step 2: Save a copy of your BART 2.0 configuration file. The default location of the BART 2.0 configuration file is /usr/edb/bart2.0/etc/bart.cfg.

Step 3: Invoke the following command to remove BART 2.0:

```
yum remove edb-bart20
```

Step 4: Place the BART 2.0 configuration file (bart.cfg) that you saved in Step 2 in the newly created /usr/edb/bart/etc directory. You can use many of the same configuration parameters for BART 2.5.x.x, but note that you must use a new directory for the BART backup catalog. A new set of full backups and incremental backups taken using BART 2.5.x.x must be stored in a new BART backup catalog.

To specify an alternative configuration file name or location, use the **-c** option with BART subcommands. For details, see the EDB Postgres Backup and Recovery User Guide available at:

https://www.enterprisedb.com/edb-docs/

Note

The bart.cfg configuration file is only required on the BART 2.5.x.x host from which you will invoke BART subcommands. BART does not require the bart.cfg file on hosts on which an incremental backup will be

restored.

Step 5: Adjust the setting of the PATH environment variable to include the location of the BART 2.5.x.x executable (the bin subdirectory) in the ~/.bashrc or ~/.bash profile files for the following user accounts:

- The BART user account on the BART host. See Configuring the BART host, Step 3 for more information.
- The user account on the remote host to which incremental backups will be restored. For details, see the *EDB Postgres Backup and Recovery User Guide* available at:

https://www.enterprisedb.com/edb-docs/

Step 6: Perform the BART 2.5.x.x installation and BART 2.0 removal process on each remote host on which an incremental backup was restored using BART 2.0.

Note

After upgrading to BART 2.5.x.x, you must take a new full backup of your system before performing an incremental backup.

1.6 Uninstallation

To uninstall BART, assume the identity of the **root** user and invoke the following command:

```
yum remove edb-bart
```

Uninstalling BART does not delete the backup files and archived WAL files that reside in the BART backup catalog. To permanently delete the backup files and archived WAL files in the BART backup catalog (/opt/backup), use one of the following commands:

- rm -rf /opt/backup
- BART DELETE subcommand

For information about the BART DELETE subcommand, refer the EDB Postgres Backup and Recovery User Guide available at:

https://www.enterprisedb.com/edb-docs/.

2 EDB Postgres Backup and Recovery Tool Quickstart

This document provides shortcuts that allow you to install and configure BART and take a full and incremental backup of a database server quickly. Please note that your system may have requirements that are not addressed in this document. For detailed information about BART installation and configuration, see the *BART Installation and Upgrade Guide* available at:

https://www.enterprisedb.com/edb-docs/

BART is supported on the following platforms (64 bit only):

- CentOS 6.x or 7.x
- RHEL 6.x or 7.x
- PPC-LE 8 running RHEL or CentOS 7.x
- Ubuntu 18.04 (Bionic)
- Debian 9.x (Stretch)

BART works with the following database versions:

- Advanced Server versions 9.5, 9.6, 10, 11, and 12.
- PostgreSQL versions 9.5, 9.6, 10, 11, and 12.

2.1 Installation

Before installing BART, ensure that your repository configuration allows access to the EDB repository. To request credentials to the EDB repository, visit:

https://www.enterprisedb.com/repository-access-request

1. Then, use yum to create the repository configuration file:

```
yum install -y https://yum.enterprisedb.com/edbrepos/edb-repo-
latest.noarch.rpm
```

- 2. Modify the repository configuration file (named edb.repo, located in /etc/yum.repos.d). Ensure that the value of the enabled parameter is 1, and replace the username and password placeholders in the baseurl specification with the name and password of a registered EnterpriseDB user.
- 3. Before installing other software, use yum to install the EPEL package:

```
yum install epel-release
```

- 4. Then, use yum to install an Advanced Server or PostgreSQL database on any server on which an incremental backup will be restored. The host of the BART server is not required to have an installation of Postgres, but must include a copy of the following:
 - Postgres libpq library
 - Postgres pg basebackup utility program
 - Boost Libraries version 1.48 and 1.53 (for RHEL/CentOS 6 and RHEL/CentOS 7 only).
- 5. Enable and activate Secure Shell (SSH) and Secure Copy (SCP) client programs on the BART host as well as on the remote database server hosts. The BART host and target database server host must accept a passwordless SSH/SCP login connection.

After meeting the prerequisites, you can install the BART RPM package directly from the EnterpriseDB yum repository with the following command:

```
yum install edb-bart
```

Repeat the installation process described in this section to install BART 2.4 on all remote hosts where incremental backups are to be restored.

BART is installed in the /usr/edb/bart directory location referred to as <BART HOME>.

2.2 Configuring BART

To configure the BART host and each database server that is to be managed by BART, you must:

- 1. Establish the BART user account and ensure it runs the bart and the bart-scanner program.
- 2. Use the bart.cfg.sample file to create the bart.cfg file. The BART configuration file is located in <BART HOME>/etc/bart.cfg:

```
cp bart.cfg.sample bart.cfg
```

3. Set the environment variable for the BART user account. If the <code>libpq</code> library does not reside in the default installation location, you must add the <code>libpq</code> library to the <code>LD_LIBRARY_PATH</code> environment variable and place the following settings in the BART user account's profile so they take effect upon login:

```
# .bash\_profile
# Get the aliases and functions
if [ -f ~/.bashrc ]; then
. ~/.bashrc
fi
# User specific environment and startup programs
export LD_LIBRARY_PATH=/usr/edb/as11/lib:$LD_LIBRARY_PATH
```

1. Set the following parameters in the [BART] section of the BART configuration file:

bart_host (required)

Use this field to specify the IP address of the host where BART is installed, in the form of bart_user>@<bart_host_address>.

backup_path (required)

Use this field to specify the path to the file system parent directory where all BART backups and archived WAL files will be stored. Ensure the BART user account owns the location specified in the backup path parameter.

pg_basebackup_path (required)

Use this field to specify the path to the pg_basebackup utility.

xlog method (optional)

Use this field to specify how the transaction log should be collected during the execution of

pg_basebackup. The default value is fetch; it specifies that the transaction log files will be collected after backup is completed. Set to stream to stream

retention_policy (optional)

Use this field to specify the retention policy for the backup. This determines when an active backup should be marked as <code>obsolete</code>, and hence, be a candidate for deletion. You can specify the retention policy in terms of number of backup or in terms of duration (days, weeks, or months). For example, <code>max_number BACKUPS</code> (default setting), <code>max_number DAYS</code>, <code>max_number WEEKS</code>, or <code>max_number MONTHS</code> where <code>max_number</code> is a positive integer.

wal compression (optional)

Use this field to specify if you want to compress the archived Xlog/WAL files in gzip format. Set to enabled to compress the archived WAL files in gzip format when the MANAGE subcommand is invoked.

To enable WAL compression, the gzip compression program must be present in the BART user account's PATH. The WAL compression setting must not be enabled for those database servers where you need to take incremental backups.

copy wals during restore (optional)

Use this field to specify how the archived WAL files are collected when invoking the RESTORE operation. Set to enabled to copy the archived WAL files from the BART backup catalog to the <restore_path>/<archived_wals> directory prior to the database server archive recovery. Set to disabled to retrieve the archived WAL files directly from the BART backup catalog during the database server archive recovery. Enabling this option helps you save time during the restore operation.

logfile (optional)

Use this field to specify the path to the BART log file.

scanner_logfile (optional)

Use this field to specify the path to the Xlog/WAL scanner log file. BART does not create a WAL scanner log file if you do not specify the path.

bart_socket_directory (optional) -

Use this field to specify the socket directory path where all BART sockets will be stored. The default directory is /tmp.

While specifying the <code>bart_socket_directory</code> path, you must ensure that the directory exists and the BART user has the required directory access permissions.

thread_count (optional)

Use this field to specify the number of worker threads to copy blocks or data files from the database server to the BART backup catalog.

Specify a thread count of 1 if you want to take the backup using the pg basebackup utility.

batch_size (optional)

Use this field to specify the number of blocks of memory used for copying modified blocks from the database server to the BART backup catalog when the BACKUP subcommand is invoked for incremental

backups. The maximum permitted value is 131072 (131072 * 8192 = 1 GB). The minimum permitted value is 1 (1 * 8192 = 8192 bytes).

scan_interval (optional)

Use this field to specify the number of seconds after which the WAL scanner should scan the new WAL files. The default value is 0, which means no brute-force scanning will be started.

mbm_scan_timeout (optional)

Use this field to specify the number of seconds to wait for MBM files before timing out; the default value is 20 seconds. The value must be greater than 0. The mbm_scan_timeout parameter is applicable only for incremental backup.

workers (optional)

Use this field to specify the number of parallel worker processes required to stream the modified blocks of an incremental backup to the restore host. The default value is 1.

- 1. Invoke the CHECK-CONFIG subcommand omitting the -s option to check the parameter settings in the BART configuration file including bart_host, backup_path, and pg_basebackup_path.
- 2. Set the following parameters for each database server in the server section of the BART configuration file. The parameter setting in the server section overrides the setting in the global [BART] section for that particular database server.

[ServerName] (required)

Specify a database server name.

backup name (optional)

Specify user-friendly name for the backups of the database server.

host (required)

Specify the IP address of the database server to be configured for backup.

port (optional)

Specify the port number identifying the database server instance to be backed up. The default is port 5444.

user (required)

Specify the replication database user name used by BART to establish the connection to the database server for full backups.

archive_path (optional) – Specify the path where archived WAL files will be stored. The default location of the archived WAL files is the BART backup catalog (backup path/server name/archived wals).

archive command (optional)

Use this field to specify the desired format of the archive command string to be used in the bart.cfg file.

cluster owner (required)

Specify the Linux operating system user account that owns the database cluster. This is typically enterprisedb for Advanced Server clusters installed in compatible mode, or postgres for PostgreSQL or Advanced Server clusters installed in the PostgreSQL compatible mode.

remote host (optional)

Use this field to specify the IP address of the remote server to which a backup is to be restored.

Specify the value in the form of remote_user>@cremote_host_address>
sis the user account on the target database server host that accepts a passwordless
SSH/SCP login connection and owns the directory where the backup is to be restored.
cremote_host_address> is the IP address of the remote host where you want to restore the backup.

tablespace_path (optional)

Use this field to specify the path to which tablespaces are to be restored. Specify this parameter value in the OID = tablespace_path; OID = tablespace_path ... format. If the backup is to be restored to a remote host (specified by the remote_host parameter), then the tablespace must exist on the remote host.

allow incremental backups (optional)

Set this parameter to **enabled** to permit incremental backups.

description (optional)

Use this field to specify the database server description.

For detailed information about configuring the following optional parameters in the server section, refer to the *BART Installation and Upgrade Guide* available at:

https://www.enterprisedb.com/edb-docs/

- Retention_policy
- xlog method
- wal compression
- copy wals during restore
- thread count
- batch size
- scan interval
- mbm scan timeout
- workers

2.3 Configuring a Database Server

To configure a database server, you must:

- 1. Authorize SSH/SCP access to the server.
- 2. Create and configure a replication database user.
- 3. Enable WAL archiving of the server.

4. Verify the server configuration settings.

Note

You must authorize SSH/SCP access and set up a replication database user before restarting the database server with WAL archiving enabled.

Authorizing SSH/SCP Access

The following example enables SSH/SCP access on a CentOS 6.x host; similar (platform-specific) steps will apply to other platforms/versions.

- 1. First, enable public key authentication:
 - 1. In the SSH server daemon configuration file /etc/ssh/sshd_config, ensure that the following parameter is set to yes and is not commented out:

PubkeyAuthentication yes

2. Reload the configuration file using the service sshd reload, service sshd stop, service sshd start, or service sshd restart command.

Note

If you get any SSH or SCP errors, examine the log file (/var/log/secure).

1. Then, execute the following command to create a passwordless connection:

```
ssh-copy-id target user@host address
```

For more information about how to generate an authorized public key, see the *Authorized Public Keys Generation* section of the *BART Installation and Upgrade Guide* available at:

https://www.enterprisedb.com/edb-docs

Setting up a Replication Database User

To set up a replication database user:

- 1. Choose a database user to serve as the *replication database user* (a superuser) for each Postgres database server to be managed by BART.
- 2. Modify the pg_hba.conf file to allow the replication database user to access the template1 database. Include the replication database user in the pg_hba.conf file as a replication connection if pg_basebackup is to be used for taking any backups.
- 3. Specify the replication database user for the database server in the BART configuration file in the user parameter.

Enabling WAL Archiving

To enable WAL archiving, set the following parameters in the postgresql.conf file for any database server for which BART is to perform a backup.

- Set wal level to archive for Postgres 9.5 or to replica for Postgres 9.6 or later.
- Set archive mode to on.
- Set the PostgreSQL archive_command parameter to copy the WAL files to the archive_path. The archive_command configuration parameter mentioned here is located in the postgresql.conf file; the PostgreSQL archive_command parameter is used in a different manner than the BART archive command parameter previously mentioned in this guide.
- Set max_wal_senders to a value high enough to leave at least one session available for the backup. If the xlog_method=stream parameter setting is to be used by this server, the max_wal_senders setting must account for an additional session for transaction log streaming.

Note

Run the INIT subcommand with the -o option to override any existing archive_command setting in the postgresql.conf or the postgresql.auto.conf file.

- 1. After verifying that the full path of the BART backup catalog has been created, restart the database server to initiate WAL archiving.
- 2. Start the WAL scanner by executing the following command:

```
./bart-scanner
```

Verifying Configuration Setting

• Use the CHECK-CONFIG subcommand with the —s option to verify the parameter settings in the database server configuration for which the —s option is specified.

```
bart CHECK-CONFIG [ -s <server name> ]
```

In addition, the following postgresql.conf parameters for the database server must be properly set and activated for certain processes:

- The cluster owner parameter must be set to the user account owning the database cluster directory.
- A passwordless SSH/SCP connection must be set between the BART user and the user account specified by the cluster owner parameter.
- The BART user parameter must specify a database superuser.
- The pg_hba.conf file must contain a replication entry for the database superuser specified by the BART user parameter.
- The archive mode parameter in the postgresql.conf file must be enabled.
- The archive_command parameter in the postgresql.auto.conf or the postgresql.conf file must be set.
- The allow_incremental_backups parameter in the BART configuration file must be enabled for database servers for which incremental backups are to be taken.
- Archiving of WAL files to the archive path must be in process.
- The WAL scanner program must be running.

2.4 Taking a Backup

This section provides information about creating a full or incremental backup of a database server. For detailed

information about taking a full backup, incremental backup, point-in-time recovery and restore process, see the *BART User Guide* available at:

https://www.enterprisedb.com/edb-docs

The syntax of the **BACKUP** subcommand is:

```
bart BACKUP -s { server_name | all }
[ -F { p | t } ]
[ -z ] [ -c compression_level ]
[ --parent { backup_id | backup_name } ]
[ --backup-name backup_name ]
[ --thread-count number_of_threads ]
[ { --with-pg_basebackup | --no-pg_basebackup } ]
[ --check ]
```

Note

While a BACKUP subcommand is in progress, no other processes may run in parallel.

Along with the BACKUP subcommand, you can:

• Specify the —s option and replace the *server_name* with the server name to be backed up (it must be configured in the BART configuration file). Specify all to take a backup of all servers. This argument is mandatory.

The backup is saved in the backup path/server_name/backup_id directory.

Specify the following options only if required. If you do not specify any of the following options, the backup is created using the default settings.

- Specify the —F p option to create a backup in the plain text format and —F t to create a backup in tar format (default). If the transaction log streaming method is used, then the —F p option must be specified.
- Specify the -z option to use gzip compression on the tar file output using the default compression level. This option is applicable only for the tar format.
- Specify the —c option to apply the gzip compression level on the tar file output, and replace compression_level with the digit 1 through 9, with 9 being the best compression (applicable only for the tar format).
- If you want to take an incremental backup, specify the option --parent and replace backup_id with the backup identifier of a parent backup or replace backup_name with the parent backup name. Incremental backup can only be taken in the plain text format (-F p). Specify the option --check before taking an incremental backup to verify if the required MBM files are present in the BART backup catalog. The --parent option must be specified when the --check option is used.
- Specify the option ——backup—name and replace backup_name with the user-friendly name assigned to the backup.
- Specify the option —thread count and replace *number_of_threads* with the number of worker threads to run in parallel to copy blocks for incremental backups
- Specify the option --with-pg_basebackup to use pg_basebackup to take a full backup. The number of thread counts in effect is ignored as given by the thread_count parameter in the BART configuration file.

Note

If the thread count in effect is greater than 1, then the pg_basebackup utility is not used to take the full backup unless the --with-pg_basebackup option is specified with the BACKUP subcommand.

• Specify the option --no pg basebackup to not use pg basebackup to take a full backup.

The following example creates a full backup in the default tar format with gzip compression. Note that checksums are generated for the full backup and user-defined tablespaces for the tar format backup.

```
[edb@localhost bin]$ ./bart BACKUP -s hr -z
      DebugTarget - getVar(checkDiskSpace.bytesAvailable)
INFO:
INFO:
      new backup identifier generated 1567591909098
INFO:
      creating 5 harvester threads
NOTICE: all required WAL segments have been archived
INFO: backup completed successfully
INFO:
BART VERSION: 2.5
BACKUP DETAILS:
BACKUP STATUS: active
BACKUP IDENTIFIER: 1567591909098
BACKUP NAME: none
BACKUP PARENT: none
BACKUP LOCATION: /home/edb/bkup new/hr/1567591909098
BACKUP SIZE: 13.91 MB
BACKUP FORMAT: tar.qz
BACKUP TIMEZONE: America/New York
XLOG METHOD: fetch
BACKUP CHECKSUM(s): 0
TABLESPACE(s): 3
Oid
       Name
               Location
16387 test1
               /home/edb/tbl1
16388
       test2 /home/edb/tbl2
16389 test3 /home/edb/tbl3
START WAL LOCATION: 0000001000000000000025
STOP WAL LOCATION: 000000010000000000000026
BACKUP METHOD: streamed
BACKUP FROM: master
START TIME: 2019-09-04 06:11:49 EDT
STOP TIME: 2019-09-04 06:11:53 EDT
TOTAL DURATION: 4 sec(s)
```

The following example shows an incremental backup taken by specifying the --parent option. The option -F p must be specified as well for plain text format.

```
[edb@localhost bin]$ ./bart BACKUP -s hr -F p --parent hr_full_1 --backup-
name
hr_incr_1
INFO: DebugTarget - getVar(checkDiskSpace.bytesAvailable)
INFO: checking /home/edb/bkup_new/hr/archived_wals for MBM files from
0/20000028 to
0/22000000
INFO: new backup identifier generated 1566899827751
INFO: creating 5 harvester threads
NOTICE: all required WAL segments have been archived
INFO: backup completed successfully
INFO:
BART VERSION: 2.5
BACKUP DETAILS:
```

```
BACKUP STATUS: active
BACKUP IDENTIFIER: 1566899827751
BACKUP NAME: hr incr 1
BACKUP PARENT: 1566899819709
BACKUP LOCATION: /home/edb/bkup new/hr/1566899827751
BACKUP SIZE: 7.19 MB
BACKUP FORMAT: plain
BACKUP TIMEZONE: America/New_York
XLOG METHOD: fetch
BACKUP CHECKSUM(s): 0
TABLESPACE(s): 0
START WAL LOCATION: 0000001000000000000022
STOP WAL LOCATION: 0000001000000000000023
BACKUP METHOD: streamed
BACKUP FROM: master
START TIME: 2019-08-27 05:57:07 EDT
STOP TIME: 2019-08-27 05:57:08 EDT
TOTAL DURATION: 1 sec(s)
```

3 EDB Postgres Backup and Recovery Reference Guide

This guide acts as a quick reference for BART subcommands and provides comprehensive examples of the following BART operations:

- Performing a full backup of database servers
- Performing point-in-time recovery (PITR) on a remote PostgreSQL database server
- Restoring an incremental backup
- Restoring a database cluster with tablespaces
- Evaluating, marking, and deleting backups and incremental backups
- Local and remote database server configuration and operation

For detailed information about BART subcommands and operations, see *EDB Postgres Backup and Recovery User Guide* available at:

https://www.enterprisedb.com/edb-docs/

The current document is organized as follows:

- The Subcommands section provides information about BART subcommands with options and examples.
- The Examples section provides examples of BART operations.
- The Sample BART System section provides a comprehensive example of both local and remote database server configuration and operation.

3.1 Using BART Subcommands

This section briefly describes the BART subcommands.

Invoking BART

BART subcommands are invoked at the Linux command line. You can invoke the bart program (located in the <BART HOME>/bin directory) with the desired options to manage your BART installation.

The following examples demonstrate ways of invoking BART. In these examples, the BART user account is named bartuser.

```
$ su bartuser
Password:
$ export
LD_LIBRARY_PATH=/opt/PostgresPlus/9.5AS/lib/:$LD_LIBRARY_PATH
$ ./bart SHOW-SERVERS
```

To run BART from any current working directory:

```
$ su bartuser
Password:
$ export
LD_LIBRARY_PATH=/opt/PostgresPlus/9.5AS/lib/:$LD_LIBRARY_PATH
$ bart SHOW-SERVERS
```

To use a BART configuration file other than <BART_HOME>/etc/bart.cfg, include the -c option and the path and name of the configuration file:

```
$ su bartuser
Password:
$ export
LD_LIBRARY_PATH=/opt/PostgresPlus/9.5AS/lib/:$LD_LIBRARY_PATH
$ bart -c /home/bartuser/bart.cfg SHOW-SERVERS
```

Syntax for invoking BART

```
bart [ <general_option> ]... [ <subcommand> ] [<subcommand_option>]...
```

Note

You can use either abbreviated (for example -h) or long (for example --help) option forms on the command line.

General Options

You can specify the following general options with bart.

- -h or (--help)
 - Displays general syntax and information about BART usage.
 - All subcommands support a help option (-h, --help). If the help option is specified, information is displayed regarding that particular subcommand. The subcommand, itself, is not executed.

The following code sample shows the result of invoking the --help option for the BACKUP subcommand:

```
-bash-4.2$ bart BACKUP --help
bart: backup and recovery tool

Usage:
bart BACKUP [OPTION]...

Options:
-h, --help Show this help message and exit
-s, --server Name of the server or 'all' (full backups only) to specify all
servers
-F, --format=p|t Backup output format (tar (default) or plain)
-z, --gzip Enables gzip compression of tar files
-c, --compress-level Specifies the compression level (1 through 9, 9 being
best compression)
--backup-name Specify a friendly name for the current backup
--parent Specify parent backup for incremental backup
--check Verify checksum of required mbm files
```

• -v (or --version)

Displays information about BART version.

• -d (or --debug)

Displays information about debugging output while executing BART subcommands.

• -c (or --config-path) <config file path>

Specifies config_file_path as the full directory path to a BART configuration file. Use this option if you do not want to use the default BART configuration file BART HOME/etc/bart.cfg.

The following section describes the BART subcommands. The option help is omitted from the syntax diagrams in the following sections for the purpose of providing clarity for the subcommand options.

3.1.1 BACKUP

Use the **BACKUP** subcommand to create a full or incremental backup.

Syntax for a Full Backup:

```
bart BACKUP -s { <server_name> | all } [ -F { p | t } ]

[ -z ] [ -c <compression_level> ]

[ --backup-name <backup_name> ]

[ --thread-count <number_of_threads> ]
```

```
[ { --with-pg_basebackup | --no-pg_basebackup } ]
```

Note

While a BACKUP is in progress, no other subcommands (INIT, DELETE, MANAGE, SHOW BACKUPS, VERIFY-CHKSUM) should be issued. Any subcommands issued while a backup is in progress will skip and ignore the backups.

Syntax for an Incremental Backup:

Before performing an incremental backup, you must take a full backup.

For more details about incremental backup, refer to the *Block-Level Incremental Backup* section of the *EDB Postgres Backup and Recovery User Guide* available at:

https://www.enterprisedb.com/edb-docs/

Options

```
--s { <server name> | all } or --server {<server name> | all}
```

• Use this option to specify the database server to be backed up. - Specify <server_name> to take a backup of the database server (as specified in the BART configuration file). - Specify all to take a backup of all servers.

```
-- F { p | t } or -- format { p | t }
```

• Use this option to specify the backup file format. - Specify p option to take backup in plain text format and specify t to take backup in tar format. If the p or t option is omitted, the default is tar format. - Use p option with the BACKUP subcommand when streaming is used as a backup method.

Note

An incremental backup can only be taken in plain text format (p).

• -z or --gzip (applicable only for full backup and tar format)

Use this option to enable gzip compression of tar files using the default compression level (typically 6).

• -c <compression_level> or --compress-level <compression_level> (applicable only for full backup and tar format)

Use this option to specify the gzip compression level on the tar file output. <compression_level> is a digit from 1 through 9, with 9 being the best compression.

```
---parent { <backup id> | <backup name> }
```

- Use this option to take an incremental backup. The parent backup is a backup taken prior to the incremental backup; it can be either a full backup or an incremental backup.

```
\-`<backup_id>` is the backup identifier of a parent backup and
`<backup name>` is the user-defined alphanumeric name of a parent backup.
```

- --backup-name <backup name>
 - <backup_name> is a user-defined, alphanumeric friendly name to be assigned to the backup. The maximum permitted length of backup name is 49 characters.
 - The backup name may include the following variables to be substituted by the timestamp values when the backup is taken:
 - 1. %year 4-digit year
 - 1. %month 2-digit month
 - 1. %day 2-digit day
 - 1. **%hour** 2-digit hour
 - 1. %minute 2-digit minute
 - 1. %second 2-digit second

The following example demonstrates invoking **BACKUP**:

```
./bart backup -s ppas12 -Ft --backup-name "YEAR = %year MONTH = %month DAY = %day"
```

• To include the percent sign (%) as a character in the backup name, specify %% in the alphanumeric string.

For example,

```
./bart backup -s ppas12 -Ft --backup-name "YEAR = %year MONTH = %month DAY = %day %%"
```

• If the backup name contains space characters or when backup name is referenced with the option -i by other subcommands (such as restore), enclose the string in single quotes (') or double quotes (").

For example,

```
./bart show-backups -s ppas12 -i "test backup"
```

- If the option --backup-name is not specified and the backup_name parameter is not set for this
 database server in the BART configuration file, then the backup can only be referenced in other BART
 subcommands by the BART assigned backup identifier.
- --thread-count <number of threads>
 - <number of threads> is the number of worker threads to run in parallel to copy blocks for a backup.
 - For detailed information about the --thread-count parameter, see the configuration section of the *EDB Postgres Backup and Recovery Installation and Upgrade Guide* available at:

https://www.enterprisedb.com/edb-docs/

--with-pg basebackup (applicable only for full backup)

- Specifies that pg_basebackup is to be used to take a full backup. The number of thread counts in effect is ignored as given by the thread count parameter in the BART configuration file.
- When taking a full backup, if the thread count in effect is greater than 1, then the pg_basebackup utility is not used to take the full backup (parallel worker threads are used) unless the --with-pg basebackup option is specified with the BACKUP subcommand.
- --no-pg basebackup (applicable only for full backup)
 - Specifies that pg basebackup is not to be used to take a full backup.
 - When taking a full backup, if the thread count in effect is only 1, then the pg_basebackup utility is used to take the full backup unless the --no-pg_basebackup option is specified with the BACKUP subcommand.
- --check (applicable only for incremental backup)
 - Use this option to verify if the required MBM files are present in the BART backup catalog before taking an incremental backup. However, an actual incremental backup is not taken when the --check option is specified.
 - The --parent option must be used along with the --check option.

Examples

The following example creates a full backup in the default tar format with gzip compression. Note that checksums are generated for the full backup and user-defined tablespaces for the tar format backup.

```
[edb@localhost bin]$ ./bart BACKUP -s hr -z
       DebugTarget - getVar(checkDiskSpace.bytesAvailable)
INFO:
       new backup identifier generated 1567591909098
INFO:
       creating 5 harvester threads
INFO:
NOTICE: all required WAL segments have been archived
INFO:
      backup completed successfully
INFO:
BART VERSION: 2.5
BACKUP DETAILS:
BACKUP STATUS: active
BACKUP IDENTIFIER: 1567591909098
BACKUP NAME: none
BACKUP PARENT: none
BACKUP LOCATION: /home/edb/bkup new/hr/1567591909098
BACKUP SIZE: 13.91 MB
BACKUP FORMAT: tar.gz
BACKUP TIMEZONE: America/New York
XLOG METHOD: fetch
BACKUP CHECKSUM(s): 0
TABLESPACE(s): 3
Oid
       Name
               Location
16387
       test1
                /home/edb/tbl1
                /home/edb/tbl2
16388
        test2
16389
        test3
                /home/edb/tbl3
START WAL LOCATION: 0000001000000000000025
STOP WAL LOCATION: 0000001000000000000026
BACKUP METHOD: streamed
BACKUP FROM: master
START TIME: 2019-09-04 06:11:49 EDT
```

```
STOP TIME: 2019-09-04 06:11:53 EDT TOTAL DURATION: 4 sec(s)
```

The following example shows the directory containing the full backup:

```
[edb@localhost bin]$number_of_threads>
[edb@localhost bin]$ ls -1 /home/edb/bkup_new/hr/
total 8
drwxrwxr-x. 3 edb edb    34 Aug 27 05:57 1566899819709
drwxrwxr-x. 3 edb edb    58 Aug 27 05:57 1566899827751
drwxrwxr-x. 3 edb edb 4096 Sep    4 06:11 1567591909098
drwxrwxr-x. 2 edb edb 4096 Sep    4 06:11 archived_wals
[edb@localhost bin]$
```

The following example shows the creation of a full backup while streaming the transaction log. Note that the **F** p option must be specified with the **BACKUP** subcommand when streaming is used as a backup method.

```
[edb@localhost bin]$ ./bart BACKUP -s ACCTG -F p
INFO: DebugTarget - getVar(checkDiskSpace.bytesAvailable)
INFO: new backup identifier generated 1566898964200
INFO: creating 5 harvester threads
NOTICE: pg stop backup complete, all required WAL segments have been archived
INFO: backup completed successfully
INFO:
BART VERSION: 2.5
BACKUP DETAILS:
BACKUP STATUS: active
BACKUP IDENTIFIER: 1566898964200
BACKUP NAME: none
BACKUP PARENT: none
BACKUP LOCATION: /home/edb/bkup new/acctg/1566898964200
BACKUP SIZE: 46.03 MB
BACKUP FORMAT: plain
BACKUP TIMEZONE: US/Eastern
XLOG METHOD: fetch
BACKUP CHECKSUM(s): 0
TABLESPACE(s): 0
START WAL LOCATION: 00000001000000000000017
BACKUP METHOD: streamed
BACKUP FROM: master
START TIME: 2019-08-27 05:42:44 EDT
STOP TIME: 2019-08-27 05:42:46 EDT
TOTAL DURATION: 2 sec(s)
```

The following example shows the assignment of a user-defined backup name with the --backup-name option:

```
[edb@localhost bin]$ ./bart BACKUP -s acctg --backup-name acctg_%year-
%month-%day
INFO: DebugTarget - getVar(checkDiskSpace.bytesAvailable)
INFO: new backup identifier generated 1566899004804
INFO: creating 5 harvester threads
NOTICE: pg_stop_backup complete, all required WAL segments have been archived
INFO: backup completed successfully
```

```
INFO:
BART VERSION: 2.5
BACKUP DETAILS:
BACKUP STATUS: active
BACKUP IDENTIFIER: 1566899004804
BACKUP NAME: acctg 2019-08-27
BACKUP PARENT: none
BACKUP LOCATION: /home/edb/bkup new/acctg/1566899004804
BACKUP SIZE: 46.86 MB
BACKUP FORMAT: tar
BACKUP TIMEZONE: US/Eastern
XLOG METHOD: fetch
BACKUP CHECKSUM(s): 0
TABLESPACE(s): 0
START WAL LOCATION: 0000000100000000000001A
BACKUP METHOD: streamed
BACKUP FROM: master
START TIME: 2019-08-27 05:43:24 EDT
STOP TIME: 2019-08-27 05:43:24 EDT
TOTAL DURATION: 0 sec(s)
```

The following example shows an incremental backup taken by specifying the --parent option. The option -F p must be specified as well for plain text format.

```
[edb@localhost bin]$ ./bart BACKUP -s hr -F p --parent hr full 1 --backup-
name
hr incr 1
INFO: DebugTarget - getVar(checkDiskSpace.bytesAvailable)
INFO: checking /home/edb/bkup new/hr/archived wals for MBM files from
0/20000028 to
0/22000000
INFO: new backup identifier generated 1566899827751
INFO: creating 5 harvester threads
NOTICE: all required WAL segments have been archived
INFO: backup completed successfully
INFO:
BART VERSION: 2.5
BACKUP DETAILS:
BACKUP STATUS: active
BACKUP IDENTIFIER: 1566899827751
BACKUP NAME: hr incr 1
BACKUP PARENT: 1566899819709
BACKUP LOCATION: /home/edb/bkup new/hr/1566899827751
BACKUP SIZE: 7.19 MB
BACKUP FORMAT: plain
BACKUP TIMEZONE: America/New York
XLOG METHOD: fetch
BACKUP CHECKSUM(s): 0
TABLESPACE(s): 0
START WAL LOCATION: 0000001000000000000022
STOP WAL LOCATION: 00000001000000000000023
BACKUP METHOD: streamed
BACKUP FROM: master
```

START TIME: 2019-08-27 05:57:07 EDT STOP TIME: 2019-08-27 05:57:08 EDT

TOTAL DURATION: 1 sec(s)

Error messages

The following table lists the error messages that may be encountered when using BART with the subcommand.

error message	Cause	
edb@localhost bin]\$./bart backup -s mktg -Ft		

WARNING: xlog method is empty, defaulting

to global policy

ERROR: backup failed for server 'mktg'

free disk space is not enough to backup the server 'mktg'

space available 13.35 GB, approximately required 14.65 GB

Insufficient free disk space.

ERROR: backup failed for server 'mktg'

command failed with exit code 1

pg_basebackup: could not get transaction log end position from server: ERROR: requested WAL segment 00000001000000D50000006B has already been removed The wal_keep_segments configuration parameter is not set to a sufficiently large value in the postgresql.conf file.

ERROR: backup failed for server 'mktg'

connection to the server failed: could not connect to server: Connection refused

Is the server running on host "172.16.114.132" and accepting

TCP/IP connections on port 5444?

A connection to a database server listed in the BART configuration file fails. As a result the backup for that database server is skipped, but the backup operation continues for other database servers

3.1.2 CHECK-CONFIG

The CHECK-CONFIG subcommand checks the parameter settings in the BART configuration file as well as the database server configuration for which the -s option is specified.

Syntax:

```
bart CHECK-CONFIG [ -s <server_name> ]
```

In the above syntax diagram, CHECK-CONFIG is the BART subcommand and —s <server_name> is the subcommand option.

Option

```
-s (or --server) <server_name>
```

<server_name> is the name of the database server whose configuration parameter settings are to be checked. If
you do not specify the <server name>, the settings of the BART configuration file global section are checked.

Example

The following example demonstrates a bart CHECK-CONFIG command without the —s option. It successfully checks the global section of the BART configuration file:

```
bash-4.1$ bart CHECK-CONFIG
INFO: Verifying that pg_basebackup is executable
INFO: success -
INFO: success - pg_basebackup(/usr/edb/as11/bin/pg_basebackup) returns
version 11.400000
```

The following example demonstrates executing a bart CHECK-CONFIG command with the —s option. It successfully checks the database server parameter settings:

```
[edb@localhost bin]$ ./bart check-config -s hr
INFO: Checking server hr
INFO: Verifying cluster owner and ssh/scp connectivity
INFO: success
INFO: Verifying user, host, and replication connectivity
INFO: success
INFO: Verifying that user is a database superuser
INFO: success
INFO: Verifying that cluster owner can read cluster data files
INFO: success
INFO: Verifying that you have permission to write to vault
INFO: success
INFO: /home/edb/bkup new/hr
INFO: Verifying database server configuration
INFO: success
INFO: Verifying that WAL archiving is working
INFO: waiting 30 seconds for
/home/edb/bkup new/hr/archived wals/000000010000000000001E
INFO: success
INFO: Verifying that bart-scanner is configured and running
INFO: success
```

3.1.3 DELETE

The **DELETE** subcommand removes the subdirectory and data files from the BART backup catalog for the specified backups along with archived WAL files.

Syntax:

```
bart DELETE -s <server_name>
-i { all | [']{ <backup_id> | <backup_name> },... }['] }
[ -n ]
```

Note

While invoking the **DELETE** subcommand, you must specify a database server.

For database servers under a retention policy, there are conditions where certain backups may not be deleted. For more information regarding this, see the Deletions Permitted Under a Retention Policy section of the *EDB Postgres Backup and Recovery User Guide* available at:

https://www.enterprisedb.com/edb-docs/

Options

```
• -s (or --server) <server name>
```

<server_name> is the name of the database server whose backups are to be deleted.

```
--i (or --backupid) { all | ['] { <backup id> | <backup name> }',... }[`] }
```

- <backup_id> is the backup identifier of the backup to be deleted. <backup_name> is the user-defined alphanumeric name for the backup. Multiple backup identifiers and backup names may be specified in a comma-separated list. The list must be enclosed within single quotes if there is any white space appearing before or after each comma (see Example section). If all is specified, all backups and their archived WAL files for the specified database server are deleted.
- -n or --dry-run

Performs the test run and displays the results prior to physically removing files, however, no files are actually deleted.

Example

The following example deletes a backup from the specified database server.

After the deletion, the BART backup catalog for the database server no longer contains the corresponding directory for the deleted backup ID. The archived wals subdirectory no longer contains the backup WAL files.

```
[edb@localhost acctg]$ ls -l
total 16
drwxrwxr-x. 3 edb edb 4096 Aug 27 06:03 1566900199604
drwxrwxr-x. 3 edb edb 4096 Aug 27 06:03 1566900204377
drwxrwxr-x. 3 edb edb 4096 Aug 27 06:03 1566900209087
drwxrwxr-x. 3 edb edb 4096 Aug 27 06:05 1566900321228
drwxrwxr-x. 2 edb edb 6 Aug 27 06:01 archived_wals
```

The following example deletes multiple backups from the database server.

```
[edb@localhost bin]$ ./bart DELETE -s acctg -i `1566988095633,1566988100760,
acctg 2019-08-28`
INFO: deleting backup `1566988095633` of server `acctg`
INFO: deleting backup `1566988095633`
INFO: WALs of deleted backup(s) will belong to prior backup(if any), or will
be marked unused
WARNING: not marking any WALs as unused WALs, the WAL file
`/home/edb/bkup new/acctg/archived wals/00000001000000000000000037` is
required,
yet not available in archived wals directory
INFO: backup(s) deleted
INFO: deleting backup `1566988100760` of server `acctq`
INFO: deleting backup `1566988100760`
INFO: WALs of deleted backup(s) will belong to prior backup(if any), or will
be marked unused
WARNING: not marking any WALs as unused WALs, the WAL file
`/home/edb/bkup new/acctg/archived wals/000000010000000000000039` is
required, yet not available in archived wals directory
INFO: backup(s) deleted
INFO: deleting backup `acctg_2019-08-28` of server `acctg`
INFO: deleting backup `1566988115512`
INFO: WALs of deleted backup(s) will belong to prior backup(if any), or will
be marked unused
WARNING: not marking any WALs as unused WALs, the WAL file
`/home/edb/bkup new/acctg/archived wals/00000001000000000000003C` is
required,
yet not available in archived wals directory
INFO: backup(s) deleted
[edb@localhost bin]$
[edb@localhost bin]$
[edb@localhost bin]$
[edb@localhost acctg]$
[edb@localhost acctg]$ ls -1
total 8
drwxrwxr-x. 3 edb edb 4096 Aug 28 06:28 1566988105086
drwxrwxr-x. 3 edb edb 4096 Aug 28 06:28 1566988109477
drwxrwxr-x. 2 edb edb 6 Aug 28 06:09 archived wals
[edb@localhost acctq]$
```

Deleting Multiple Backups with Space Characters

The following example also deletes multiple backups, but since there are space characters in the comma-separated list, the entire list must be enclosed within single quotes.

```
[edb@localhost bin]$ ./bart DELETE -s acctg -i
`1566900199604,1566900204377,1566900209087`;
INFO: deleting backup `1566900199604` of server `acctq`
INFO: deleting backup `1566900199604`
INFO: WALs of deleted backup(s) will belong to prior backup(if any), or will
be marked unused
WARNING: not marking any WALs as unused WALs, the WAL file
required,
yet not available in archived wals directory
INFO: backup(s) deleted
INFO: deleting backup `1566900204377` of server `acctq`
INFO: deleting backup `1566900204377`
INFO: WALs of deleted backup(s) will belong to prior backup(if any), or will
be marked unused
WARNING: not marking any WALs as unused WALs, the WAL file
`/home/edb/bkup new/acctg/archived wals/0000001000000000000002A` is
yet not available in archived wals directory
INFO: backup(s) deleted
INFO: deleting backup `1566900209087` of server `acctg`
INFO: deleting backup `1566900209087`
INFO: WALs of deleted backup(s) will belong to prior backup(if any), or will
be marked unused
WARNING: not marking any WALs as unused WALs, the WAL file
required,
yet not available in archived wals directory
INFO: backup(s) deleted
[edb@localhost bin]$
[edb@localhost bin]$
[edb@localhost acctg]$ ls -1
total 4
drwxrwxr-x. 3 edb edb 4096 Aug 27 06:05 1566900321228
drwxrwxr-x. 2 edb edb 6 Aug 27 06:01 archived wals
[edb@localhost acctg]$
```

3.1.4 INIT

The INIT subcommand is used to create the BART backup catalog directory, rebuild the BART backupinfo file, and set the archive_command in the server based on the archive_command setting in the bart.cfg file.

Syntax:

```
bart INIT [ -s { <server_name> | all } ] [ -o ]
[ -r [ -i { <backup_id> | <backup_name> | all } ] ]
[-- no-configure]
```

Options

```
--s or --server { <server_name> | all }
```

<server_name> is the name of the database server to which the INIT actions are to be applied. If all is
specified or if the option is omitted, actions are applied to all servers.

• -o or -override

Overrides the existing Postgres archive_command configuration parameter setting in the postgresql.conf file or the postgresql.auto.conf file using the BART archive_command parameter in the BART configuration file. The INIT generated archive command string is written to the postgresql.auto.conf file.

• -r or -rebuild

Rebuilds the backupinfo file located in each backup subdirectory.

```
--i or --backupid { <backup_id> | <backup_name> | all }
```

<backup_id> is an integer, backup identifier and <backup_name> is the user-defined alphanumeric
name for the backup. If all is specified or if the option is omitted, the backupinfo files of all backups for
the database servers specified by the -s option are recreated. The -i option can only be used with the -r
option.

• --no-configure

Prevents the archive command from being set in the PostgreSQL server.

Examples

In the following example, you can see that archive_mode = off and archive_command is not set. After invoking the BART INIT subcommand, archive_mode is set to on and archive_command is set.

```
archive_mode = off # enables archiving; off, on, or always
# (change requires restart)
archive_command = ''
# command to use to archive a logfile segment
[edb@localhost bin]$ ./bart init -s ppas11
INFO: setting archive_mode/archive_command for server 'ppas11'
WARNING: archive_mode/archive_command is set. Restart the PostgreSQL
server using 'pg_ctl restart'
[edb@localhost bin]$
# Do not edit this file manually!
# It will be overwritten by the ALTER SYSTEM command.
archive_mode = 'on'
archive_command = 'scp %p
edb@127.0.0.1:/home/edb/bkup/ppas11/archived_wals/%f'
```

In this following example, you can see that archive_mode = on, and archive_command is not set. After invoking BART INIT subcommand, archive command is set.

```
archive_mode = on # enables archiving; off, on, or always
# (change requires restart)
archive_command = '' # command to use to archive a logfile segment
[edb@localhost bin]$ ./bart init -s ppas11
INFO: setting archive_mode/archive_command for server 'ppas11'
WARNING: archive_command is set. Reload the configuration in the
PostgreSQL server using pg_reload_conf() or 'pg_ctl reload'
[edb@localhost bin]$
# Do not edit this file manually!
# It will be overwritten by the ALTER SYSTEM command.
archive_command = 'scp %p
edb@127.0.0.1:/home/edb/bkup/ppas11/archived_wals/%f'
```

In the following example, you can see that archive_mode = on and archive_command is already set. After invoking BART INIT subcommand, there is no change in the setting.

Note

To override the existing archive command, you must include the -o option.

```
archive_mode = on # enables archiving; off, on, or always
# (change requires restart)
archive_command = 'scp %p
edb@127.0.0.1:/home/edb/bkup/ppas11/archived_wals/%f' # command to use
to archive a logfile segment
# placeholders: %p = path of file to archive
[edb@localhost bin]$ ./bart init -s ppas11
INFO: setting archive_mode/archive_command for server 'ppas11'
WARNING: archive_command is not set for server 'ppas11'
[edb@localhost bin]$
# Do not edit this file manually!
# It will be overwritten by the ALTER SYSTEM command.
```

In this following example, you can see that archive_mode = off and archive_command is already set. After invoking BART INIT subcommand, archive_mode is set to on.

```
archive_mode = off # enables archiving; off, on, or always
# (change requires restart)
archive_command = 'scp %p
edb@127.0.0.1:/home/edb/bkup/ppas11/archived_wals/%f' # command to use
to archive a log file segment
[edb@localhost bin]$ ./bart init -s ppas11
INFO: setting archive_mode/archive_command for server 'ppas11'
WARNING: archive_mode/archive_command is set. Restart the PostgreSQL
server using 'pg_ctl restart'
# Do not edit this file manually!
# It will be overwritten by the ALTER SYSTEM command.
archive_mode = 'on'
archive_command = 'scp %p
edb@127.0.0.1:/home/edb/bkup/ppas11/archived_wals/%f'
```

The following example overrides an existing archive command setting by resetting the archive_command in the PostgreSQL server with the archive_command = 'cp %p %a/%f' parameter from the bart.cfg file.

The following parameters are set in the bart.cfg file:

```
[BART]
bart_host= enterprisedb@192.168.2.22
backup_path = /opt/backup_edb
pg_basebackup_path = /usr/edb/as11/bin/pg_basebackup
logfile = /tmp/bart.log
scanner_logfile = /tmp/bart_scanner.log

[ACCTG]
host = 127.0.0.1
port = 5444
user = repuser
cluster_owner = enterprisedb
archive_command = 'cp %p %a/%f'
description = "Accounting"
```

The archive mode and archive command parameters in the database server are set as follows:

Invoke the INIT subcommand with the -o option to override the current archive_command setting in the PostgreSQL server:

```
-bash-4.1$ bart INIT -s acctg -o
INFO: setting archive_mode/archive_command for server 'acctg'
WARNING: archive_command is set. Reload the configuration in the
PostgreSQL server using pg_reload_conf() or 'pg_ctl reload'
```

Reload the database server configuration; a restart of the database server is not necessary to reset only the archive_command parameter.

```
[root@localhost tmp]# service ppas11 reload
```

The archive command in the PostgreSQL server is now set as follows:

```
edb=# SHOW archive_command;
```

The new command string is written to the postgresql.auto.conf file:

```
# Do not edit this file manually!
# It will be overwritten by ALTER SYSTEM command.
archive_command = 'cp %p /opt/backup_edb/acctg/archived_wals/%f'
```

The following example shows invoking BART INIT with the -r option

When you invoke the BART INIT command with the -r option, BART rebuilds the backupinfo file using the content of the backup directory for the server specified or for all servers. The BART backupinfo file is initially created by the BACKUP subcommand and contains the backup information used by BART.

Note

If the backup was initially created with a user-defined backup name, and then the INIT -r option is invoked to rebuild that backupinfo file, the user-defined backup name is no longer available. Thus, future references to the backup must use the backup identifier.

The following example shows the backupinfo file location in a backup subdirectory:

```
[root@localhost acctg]# pwd
/opt/backup/acctg
[root@localhost acctg]# ls -1
total 4
drwx----- 2 enterprisedb enterprisedb 38 Oct 26 10:21 1477491569966
drwxrwxr-x 2 enterprisedb enterprisedb 4096 Oct 26 10:19 archived_wals
[root@localhost acctg]# ls -1 1477491569966
total 61144
-rw-rw-r-- 1 enterprisedb enterprisedb 703 Oct 26 10:19 backupinfo
-rw-rw-r-- 1 enterprisedb enterprisedb 62603776 Oct 26 10:19 base.tar
```

The backupinfo file content is as follows:

```
BACKUP DETAILS:
BACKUP STATUS: active
BACKUP IDENTIFIER: 1477491569966
BACKUP NAME: none
BACKUP PARENT: none
BACKUP LOCATION: /opt/backup/acctg/1477491569966
BACKUP SIZE: 59.70 MB
BACKUP FORMAT: tar
BACKUP TIMEZONE:
XLOG METHOD: fetch
BACKUP CHECKSUM(s): 1
ChkSum File
84b3eeb1e3f7b3e75c2f689570d04f10 base.tar
TABLESPACE(s): 0
START WAL LOCATION: 2/A5000028 (file 0000000100000002000000A5)
STOP WAL LOCATION: 2/A50000C0 (file 0000000100000002000000A5)
```

CHECKPOINT LOCATION: 2/A5000028

BACKUP METHOD: streamed

BACKUP FROM: master

START TIME: 2016-10-26 10:19:30 EDT LABEL: pg_basebackup base backup STOP TIME: 2016-10-26 10:19:30 EDT

TOTAL DURATION: 0 sec(s)

If the backupinfo file is missing, you will get an error message when invoking a BART subcommand:

```
-bash-4.2$ bart SHOW-BACKUPS
ERROR: 'backupinfo' file does not exist for backup '1477491569966'
please use 'INIT -r' to generate the file
```

The backupinfo file may be missing if the BACKUP subcommand did not complete successfully.

The following example rebuilds the backupinfo file of the specified backup for database server acctg.

```
-bash-4.1$ bart INIT -s acctg -r -i 1428346620427
INFO: rebuilding BACKUPINFO for backup '1428346620427' of server 'acctg'
INFO: backup checksum: ced59b72a7846ff8fb8afb6922c70649 of base.tar
```

The following example shows how the backupinfo files of all backups are rebuilt for all database servers.

```
-bash-4.1$ bart INIT -r

INFO: rebuilding BACKUPINFO for backup '1428347191544' of server 'acctg' INFO: backup checksum: lac5c61f055c910db314783212f2544f of base.tar INFO: rebuilding BACKUPINFO for backup '1428346620427' of server 'acctg' INFO: backup checksum: ced59b72a7846ff8fb8afb6922c70649 of base.tar INFO: rebuilding BACKUPINFO for backup '1428347198335' of server 'dev' INFO: backup checksum: a8890dd8ab7e6be5d5bc0f38028a237b of base.tar INFO: rebuilding BACKUPINFO for backup '1428346957515' of server 'dev' INFO: backup checksum: ea62549cf090573625d4adeb7d919700 of base.tar
```

The following example shows invoking BART INIT with the -r - i option

```
edb@localhost bin]$ ./bart init -s ppas11 -i 1551778898392 -r
INFO: rebuilding BACKUPINFO for backup '1551778898392' of server
'ppas11'
[edb@localhost bin]$ ls /home/edb/bkup/ppas11/1551778898392/
backupinfo backup_label base base-1.tar base-2.tar base-3.tar
base-4.tar base-5.tar base.tar
```

The following example shows invoking BART INIT with the --no-configure option

You can use the --no-configure option with the INIT subcommand to prevent the archive_command option from being set in the PostgreSQL server.

```
[edb@localhost bin]$ ./bart init -s ppas11 -o --no-configure
[edb@localhost bin]$
# Do not edit this file manually!
# It will be overwritten by the ALTER SYSTEM command.
```

3.1.5 MANAGE

The MANAGE subcommand can be invoked to:

- Evaluate backups, mark their status, and delete obsolete backups based on the retention_policy parameter in the BART configuration file.
- Compress the archived WAL files based on the wal_compression parameter in the BART configuration file

Syntax:

```
> bart MANAGE [ -s { <server_name> | all} ]
```

```
[ -l ] [ -d ]
[ -c { keep | nokeep }
-i { <backup_id> | <backup_name> | all } ]
[ -n ]
```

To view detailed information about the MANAGE subcommand and retention policy management, see *the EDB*Postgres Backup and Recovery User Guide. For information about setting the wal_compression parameter, see the EDB Postgres Backup and Recovery Installation and Upgrade Guide. These guides are available at:

https://www.enterprisedb.com/edb-docs/

Options

```
--s [ <server_name> | all ] or --server [ <server_name> | all ]

> - `<server_name>` is the name of the database server to which the

`MANAGE` actions are to be applied.

> - If `all` is specified or if the `-s` option is omitted, actions are applied to all database servers.
```

• -1 or --list-obsolete

Lists the backups marked as obsolete.

• -d or --delete-obsolete

Deletes the backups marked as obsolete. This action physically deletes the backup along with its archived WAL files and any MBM files for incremental backups.

```
--c { keep | nokeep } or --change-status { keep | nokeep }
```

- Specify `keep` to change the backup status to `keep` to retain the backup indefinitely.
- Specify `nokeep` to change the backup status back to `active`. You can then re-evaluate and possibly mark the backup as `obsolete` (according to the retention policy) using the `MANAGE` subcommand.

Note

The -c option can only be used with the -i option.

```
--i { <backup_id> | <backup_name> | all } or --backupid { <backup_id> |
<backup_name> | all }

- `<backup_id>` is a backup identifier and `<backup_name>` is the user-
defined alphanumeric name for the backup.
- If `all` is specified, actions are applied to all backups.
- The `-i` option can only be used with the `-c` option.
```

• -n, --dry-run

Performs the test run and displays the results prior to actually implementing the actions as if the operation was performed, however, no changes are actually made.

- If you specify -n with the -d option, it displays which backups would be deleted, but does not actually delete the backups.
- If you specify -n with the -c option, it displays the keep or nokeep action, but does not actually change the backup status.
- o If you specify -n alone with no other options or if you specify -n with only the -s option, it displays which active backups would be marked as obsolete, but does not actually change the backup status. In addition, no compression is performed on uncompressed, archived WAL files even if WAL compression is enabled for the database server.

Example

The following example performs a dry run for the specified database server displaying which active backups are evaluated as obsolete according to the retention policy, but does not actually change the backup status:

```
-bash-4.2$ bart MANAGE -s acctg -n
INFO: processing server 'acctg', backup '1482770807519'
INFO: processing server 'acctg', backup '1482770803000'
INFO: marking backup '1482770803000' as obsolete
INFO: 1 WAL file(s) marked obsolete
INFO: processing server 'acctg', backup '1482770735155'
INFO: marking backup '1482770735155' as obsolete
INFO: 2 incremental(s) of backup '1482770735155' will be marked obsolete
INFO: marking incremental backup '1482770780423' as obsolete
INFO: marking incremental backup '1482770763227' as obsolete
INFO: 3 WAL file(s) marked obsolete
INFO: 1 Unused WAL file(s) present
INFO: 2 Unused file(s) (WALs included) present, use 'MANAGE -1' for the list
```

The following example marks active backups as obsolete according to the retention policy for the specified database server:

```
-bash-4.2$ bart MANAGE -s acctg
INFO: processing server 'acctg', backup '1482770807519'
INFO: processing server 'acctg', backup '1482770803000'
INFO: marking backup '1482770803000' as obsolete
INFO: 1 WAL file(s) marked obsolete
INFO: processing server 'acctg', backup '1482770735155'
INFO: marking backup '1482770735155' as obsolete
```

```
INFO: 2 incremental(s) of backup '1482770735155' will be marked obsolete
INFO: marking incremental backup '1482770780423' as obsolete
INFO: marking incremental backup '1482770763227' as obsolete
INFO: 3 WAL file(s) marked obsolete
INFO: 1 Unused WAL file(s) present
INFO: 2 Unused file(s) (WALs included) present, use 'MANAGE -1' for the
list
```

The following example lists backups marked as obsolete for the specified database server:

```
-bash-4.2$ bart MANAGE -s acctg -1
SERVER NAME: acctq
BACKUP ID: 1482770803000
BACKUP STATUS: obsolete
BACKUP TIME: 2016-12-26 11:46:43 EST
BACKUP SIZE: 59.52 MB
WAL FILE(s): 1
WAL FILE: 00000001000000100000055
SERVER NAME: acctq
BACKUP ID: 1482770735155
BACKUP STATUS: obsolete
BACKUP TIME: 2016-12-26 11:45:35 EST
BACKUP SIZE: 59.52 MB
INCREMENTAL BACKUP(s): 2
BACKUP ID: 1482770780423
BACKUP PARENT: 1482770735155
BACKUP STATUS: obsolete
BACKUP TIME: 2016-12-26 11:45:35 EST
BACKUP SIZE: 59.52 MB
BACKUP ID: 1482770763227
BACKUP PARENT: 1482770735155
BACKUP STATUS: obsolete
BACKUP TIME: 2016-12-26 11:45:35 EST
BACKUP SIZE: 59.52 MB
WAL FILE(s): 3
WAL FILE: 0000000100000010000054
WAL FILE: 00000001000000100000053
WAL FILE: 0000000100000010000052
UNUSED FILE(s): 2
UNUSED FILE: 000000100000010000051
UNUSED FILE: 0000000100000001510000280000000152000000.mbm
```

The following example deletes the obsolete backups for the specified database server:

```
-bash-4.2$ bart MANAGE -s acctg -d
INFO: removing all obsolete backups of server 'acctg'
INFO: removing obsolete backup '1482770803000'
INFO: 1 WAL file(s) will be removed
INFO: removing WAL file '000000010000000055'
INFO: removing obsolete backup '1482770735155'
INFO: 3 WAL file(s) will be removed
INFO: 2 incremental(s) of backup '1482770735155' will be removed
INFO: removing obsolete incremental backup '1482770780423'
```

The following example changes the specified backup to keep status to retain it indefinitely:

```
-bash-4.2$ bart MANAGE -s acctg -c keep -i 1482770807519
INFO: changing status of backup '1482770807519' of server 'acctg' from
'active' to 'keep'
INFO: 1 WAL file(s) changed
-bash-4.2$ bart SHOW-BACKUPS -s acctg -i 1482770807519 -t
SERVER NAME : acctq
BACKUP ID : 1482770807519
BACKUP NAME : none
BACKUP PARENT : none
BACKUP STATUS : keep
BACKUP TIME : 2016-12-26 11:46:47 EST
BACKUP SIZE: 59.52 MB
WAL(S) SIZE: 16.00 MB
NO. OF WALS: 1
FIRST WAL FILE : 0000000100000010000057
CREATION TIME : 2016-12-26 11:52:47 EST
LAST WAL FILE : 0000000100000010000057
CREATION TIME : 2016-12-26 11:52:47 EST
```

The following example resets the specified backup to active status:

```
-bash-4.2$ bart MANAGE -s acctg -c nokeep -i 1482770807519
INFO: changing status of backup '1482770807519' of server 'acctg' from 'keep' to 'active'
INFO: 1 WAL file(s) changed
-bash-4.2$ bart SHOW-BACKUPS -s acctg -i 1482770807519 -t
SERVER NAME: acctg
BACKUP ID: 1482770807519
BACKUP NAME: none
BACKUP PARENT: none
BACKUP STATUS: active
BACKUP STATUS: active
BACKUP SIZE: 59.52 MB
WAL(S) SIZE: 16.00 MB
NO. OF WALS: 1
FIRST WAL FILE: 000000010000000100000057
```

```
CREATION TIME : 2016-12-26 11:52:47 EST

LAST WAL FILE : 000000010000000057

CREATION TIME : 2016-12-26 11:52:47 EST
```

The following example uses the enabled wal_compression parameter in the BART configuration file as shown by the following:

```
host = 127.0.0.1
port = 5445
user = enterprisedb
cluster_owner = enterprisedb
allow_incremental_backups = disabled
wal_compression = enabled
description = "Accounting"
```

When the MANAGE subcommand is invoked, the following message is displayed indicating that WAL file compression is performed:

```
-bash-4.2$ bart MANAGE -s acctg
INFO: 4 WAL file(s) compressed
WARNING: 'retention_policy' is not set for server 'acctg'
```

The following example shows the archived WAL files in compressed format:

```
-bash-4.2$ pwd
/opt/backup/acctg
-bash-4.2$ ls -l archived wals
total 160
-rw----- 1 enterprisedb enterprisedb 27089 Dec 26 12:16
00000001000000010000005B.qz
-rw----- 1 enterprisedb enterprisedb 305 Dec 26 12:17
000000100000010000005C.00000028.backup
-rw----- 1 enterprisedb enterprisedb 27112 Dec 26 12:17
00000001000000010000005C.gz
-rw----- 1 enterprisedb enterprisedb 65995 Dec 26 12:18
0000001000000010000005D.gz
-rw----- 1 enterprisedb enterprisedb 305 Dec 26 12:18
000000100000010000005E.00000028.backup
-rw----- 1 enterprisedb enterprisedb 27117 Dec 26 12:18
00000001000000010000005E.qz
```

3.1.6 RESTORE

The **RESTORE** subcommand restores a backup and its archived WAL files for the designated database server to the specified directory location.

Syntax for Restore:

To view detailed information about the **RESTORE** subcommand, see the *EDB Postgres Backup and Recovery User Guide* available at:

https://www.enterprisedb.com/edb-docs/

If the backup is restored to a different database cluster directory than where the original database cluster resided, then certain operations dependent upon the database cluster location may fail. This happens if their supporting service scripts are not updated to reflect the new directory location of restored backup.

For information about the use and modification of service scripts, see the *EDB Postgres Advanced Server Installation Guide* available at:

https://www.enterprisedb.com/edb-docs/

The following table lists the service scripts with Database Cluster Location for RHEL 6/CentOS 6.

File Name	Location	Description
postgres-reg.ini	/etc	Product information for upgrades
ppas-9.5	/etc/init.d	Service script for Advanced Server 9.5 from interactive installer
edb-as-9.6	/etc/init.d	Service script for Advanced Server 9.6 from interactive installer
edb-as-10	/etc/init.d	Service script for Advanced Server 10 from interactive installer
edb-as-11	/etc/init.d	Service script for Advanced Server 11 from interactive installer
edb-as-12	/etc/init.d	Service script for Advanced Server 12 from interactive installer
ppas-9.5	/etc/sysconfig/ppas	Configuration script for Advanced Server 9.5 from RPM package
edb-as- 9.6.sysconfig	/etc/sysconfig/edb/as9.6	Configuration script for Advanced Server 9.6 from RPM package
edb-as-10.sysconfig	/etc/sysconfig/edb/as10	Configuration script for Advanced Server 10 from RPM package
edb-as-11.sysconfig	/etc/sysconfig/edb/as11	Configuration script for Advanced Server 11 from RPM package
postgresql-9.5	/etc/init.d	Service script for PostgreSQL 9.5 from interactive installer
postgresql-9.6	/etc/init.d	Service script for PostgreSQL 9.6 from interactive installer
postgresql-10	/etc/init.d	Service script for PostgreSQL 10 from interactive installer
postgresql-11	/etc/init.d	Service script for PostgreSQL 11 from interactive installer
postgresql-12	/etc/init.d	Service script for PostgreSQL 12 from interactive installer

Before modifying the service unit files for Advanced Server in RHEL 7/CentOS 7, review the instructions in the *Modifying the Data Directory Location on CentOS or RedHat 7.x* section in the *EDB Postgres Advanced Server Installation Guide* for your release available at:

https://www.enterprisedb.com/edb-docs/

The following table lists the service unit files and scripts with Database Cluster Location for RHEL 7/CentOS 7.

File Name	Location	Description
postgres-reg.ini	/etc	Product information for upgrades
ppas-9.5.service ppas-9.5.sh	/usr/lib/systemd/system	Service unit file and script for Advanced Server 9.5 from interactive installer
edb-as-9.6.service edb-as-9.6.sh	/usr/lib/systemd/system	Service unit file and script for Advanced Server 9.6 from interactive installer
edb-as-10.service edb-as-10.sh	/usr/lib/systemd/system	Service unit file and script for Advanced Server 10 from interactive installer
edb-as-11	/usr/lib/systemd/system	Service unit file and script for Advanced Server 11 from interactive installer
ppas-9.5.service ppas-9.5.sh	/usr/lib/systemd/system	Service unit file and script for Advanced Server 9.5 from RPM package
edb-as-9.6.service	/usr/lib/systemd/system	Service unit file for Advanced Server 9.6 from RPM package
edb-as-10.service	/usr/lib/systemd/system	Service unit file for Advanced Server 10 from RPM package
edb-as-11	/usr/lib/systemd/system	Service unit file for Advanced Server 11 from RPM package
postgresql- 9.5.service	/usr/lib/systemd/system	Service unit file for PostgreSQL 9.5 from interactive installer
postgresql- 9.6.service	/usr/lib/systemd/system	Service unit file for PostgreSQL 9.6 from interactive installer
postgresql- 10.service	/usr/lib/systemd/system	Service unit file for PostgreSQL 10 from interactive installer
postgresql-11	/usr/lib/systemd/system	Service unit file for PostgreSQL 11 from interactive installer

Options

-s <server_name> or --server <server_name>

<server name> is the name of the database server to be restored.

• -p <restore_path> or --restore-path <restore_path>

<restore_path> is the directory path where the backup of the database server is to be restored. The
directory must be empty and have the proper ownership and privileges assigned to it.

```
--i { <backup_id> | <backup_name> } or --backupid { <backup_id> |
<backup_name>}
```

- `backup_id` is the backup identifier of the backup to be used for the restoration and `<backup_name>` is the user-defined alphanumeric name for the

backup.

- If the option is omitted, the default is to use the latest backup.
- r <remote_user>@<remote_host_address> or --remote-host
 <remote user@remote host address>
 - remote_user is the user account on the remote database server host that accepts a passwordless SSH/SCP login connection and is the owner of the directory where the backup is to be restored.
 - <remote_host_address> is the IP address of the remote host to which the backup is to be restored. This option must be specified if the remote_host parameter for this database server is not set in the BART configuration file.

For information about the **remote_host** parameter, see the configuration section of the *EDB Postgres Backup and Recovery Installation and Upgrade Guide* available at:

https://www.enterprisedb.com/edb-docs/

-w <number of workers> or --workers <number of workers>

<number_of_workers> is the number of worker processes to run in parallel to stream the modified
blocks of an incremental backup to the restore location. If the _w option is omitted, the default is 1 worker
process.

For example, if four worker processes are specified, four receiver processes on the restore host and four streamer processes on the BART host are used. The output of each streamer process is connected to the input of a receiver process. When the receiver gets to the point where it needs a modified block file, it obtains those modified blocks from its input. With this method, the modified block files are never written to the restore host disk.

• -t <timeline id> or --target-tli <timeline id>

<timeline_id> is the integer identifier of the timeline to be used for replaying the archived WAL files for point-in-time recovery.

-x <target xid> or --target-xid <target xid>

<target_xid> is the integer identifier of the transaction ID that determines the transaction up to and including, which point-in-time recovery encompasses.

-g <target_timestamp> or --target-timestamp <target_timestamp>

<target_timestamp> is the timestamp that determines the point in time up to and including, which
point-in-time recovery encompasses.

• -c or --copy-wals

Specify this option to copy archived WAL files from the BART backup catalog to <restore path>/archived wals

The restore_command retrieves the WAL files from <restore_path>/archived_wals for the database server archive recovery. If the -c option is omitted and the copy_wals_during_restore parameter in the BART configuration file is not enabled in a manner applicable to this database server, then the restore_command in the postgresql.conf retrieves the archived WAL files directly from the BART backup catalog. For information about the copy_wals_during_restore parameter, see the EDB Postgres Backup and Recovery Installation and Upgrade Guide available at:

https://www.enterprisedb.com/edb-docs/

Example

The following example restores a database server(named mktg) to the /opt/restore directory up to timestamp 2015-12-15 10:47:00:

```
-bash-4.1$ bart RESTORE -s mktg -i 1450194208824 -p /opt/restore -t 1 -g '2015-12-15 10:47:00'
INFO: restoring backup '1450194208824' of server 'mktg'
INFO: restoring backup to enterprisedb@192.168.2.24:/opt/restore
INFO: base backup restored
INFO: WAL file(s) will be streamed from the BART host
INFO: writing recovery settings to postgresql.auto.conf file
INFO: archiving is disabled
INFO: tablespace(s) restored
```

The following parameters are set in the postgresql.auto.conf file:

```
restore_command = 'scp -o BatchMode=yes -o PasswordAuthentication=no enterprisedb@192.168.2.22:/opt/backup/mktg/archived_wals/%f %p' recovery_target_time = '2015-12-15 10:47:00' recovery_target_timeline = 1
```

The following is a list of the restored files and subdirectories:

```
[root@localhost restore]# pwd
/opt/restore
[root@localhost restore]# ls -1
total 108
-rw----- 1 enterprisedb enterprisedb 208 Dec 15 10:43 backup_label
drwx----- 6 enterprisedb enterprisedb 4096 Dec 2 10:38 base
drwx----- 2 enterprisedb enterprisedb 4096 Dec 15 10:42 dbms pipe
drwx----- 2 enterprisedb enterprisedb 4096 Dec 15 11:00 global
drwx----- 2 enterprisedb enterprisedb 4096 Nov 10 15:38 pg clog\
-rw----- 1 enterprisedb enterprisedb 4438 Dec 2 10:38 pg hba.conf
-rw----- 1 enterprisedb enterprisedb 1636 Nov 10 15:38 pg ident.conf
drwxr-xr-x 2 enterprisedb enterprisedb 4096 Dec 15 10:42 pg log
drwx----- 4 enterprisedb enterprisedb 4096 Nov 10 15:38 pg multixact
drwx----- 2 enterprisedb enterprisedb 4096 Dec 15 10:42 pg notify
drwx----- 2 enterprisedb enterprisedb 4096 Nov 10 15:38 pg serial
drwx----- 2 enterprisedb enterprisedb 4096 Nov 10 15:38 pg snapshots
drwx----- 2 enterprisedb enterprisedb 4096 Dec 15 10:42 pg stat
drwx----- 2 enterprisedb enterprisedb 4096 Dec 15 10:43 pg stat tmp
drwx----- 2 enterprisedb enterprisedb 4096 Nov 10 15:38 pg subtrans
drwx----- 2 enterprisedb enterprisedb 4096 Dec 15 11:00 pg tblspc
drwx----- 2 enterprisedb enterprisedb 4096 Nov 10 15:38 pg twophase
-rw---- 1 enterprisedb enterprisedb 4 Nov 10 15:38 PG VERSION
drwx----- 2 enterprisedb enterprisedb 4096 Dec 15 11:00 pg xlog
-rw----- 1 enterprisedb enterprisedb 23906 Dec 15 11:00
postgresql.conf
-rw-r--r- 1 enterprisedb enterprisedb 217 Dec 15 11:00
postgresql.auto.conf
```

Example

The following example performs a RESTORE operation with the copy_wals_during_restore parameter enabled to copy the archived WAL files to the local <restore path>/archived wals directory:

```
-bash-4.1$ bart RESTORE -s hr -i hr_2017-03-29T13:50 -p
/opt/restore_pg95 -t 1 -g '2017-03-29 14:01:00'
INFO: restoring backup 'hr_2017-03-29T13:50' of server 'hr'
INFO: base backup restored
INFO: copying WAL file(s) to
postgres@192.168.2.24:/opt/restore_pg95/archived_wals
INFO: writing recovery settings to postgresql.auto.conf file
INFO: archiving is disabled
INFO: permissions set on $PGDATA
INFO: restore completed successfully
```

The following parameters are set in the postgresql.auto.conf file:

```
restore_command = 'cp archived_wals/%f %p'
recovery_target_time = '2017-03-29 14:01:00'
recovery_target_timeline = 1
```

The following is a list of the restored files and subdirectories:

```
-bash-4.1$ pwd
/opt/restore pg95
-bash-4.1$ ls -l
total 128
drwxr-xr-x 2 postgres postgres 4096 Mar 29 14:27 archived wals
-rw----- 1 postgres postgres 206 Mar 29 13:50 backup_label
drwx----- 5 postgres postgres 4096 Mar 29 12:25 base
drwx----- 2 postgres postgres 4096 Mar 29 14:27 global
drwx----- 2 postgres postgres 4096 Mar 29 12:25 pg_clog
drwx----- 2 postgres postgres 4096 Mar 29 12:25 pg commit ts
drwx----- 2 postgres postgres 4096 Mar 29 12:25 pg dynshmem
-rw----- 1 postgres postgres 4212 Mar 29 13:18 pg hba.conf
-rw----- 1 postgres postgres 1636 Mar 29 12:25 pg ident.conf
drwxr-xr-x 2 postgres postgres 4096 Mar 29 13:45 pg log
drwx----- 4 postgres postgres 4096 Mar 29 12:25 pg logical
drwx----- 4 postgres postgres 4096 Mar 29 12:25 pg multixact
drwx----- 2 postgres postgres 4096 Mar 29 13:43 pg_notify
drwx----- 2 postgres postgres 4096 Mar 29 12:25 pg replslot
drwx----- 2 postgres postgres 4096 Mar 29 12:25 pg serial
drwx----- 2 postgres postgres 4096 Mar 29 12:25 pg snapshots
drwx----- 2 postgres postgres 4096 Mar 29 13:43 pg stat
drwx----- 2 postgres postgres 4096 Mar 29 13:50 pg_stat_tmp
drwx----- 2 postgres postgres 4096 Mar 29 12:25 pg subtrans
drwx----- 2 postgres postgres 4096 Mar 29 12:25 pg tblspc
drwx----- 2 postgres postgres 4096 Mar 29 12:25 pg twophase
-rw---- 1 postgres postgres 4 Mar 29 12:25 PG VERSION
drwx----- 3 postgres postgres 4096 Mar 29 14:27 pg xlog
-rw----- 1 postgres postgres 169 Mar 29 13:24 postgresql.auto.conf
-rw-r--r-- 1 postgres postgres 21458 Mar 29 14:27 postgresql.conf
-rw-r--r- 1 postgres postgres 118 Mar 29 14:27 postgresql.auto.conf
```

3.1.7 SHOW-SERVERS

The SHOW-SERVERS subcommand displays information for the managed database servers listed in the BART configuration file.

Syntax:

```
> bart SHOW-SERVERS [ -s { < server name > | all } ]
```

In the above syntax diagram, SHOW-SERVERS is the BART subcommand and -s <server_name> and all are subcommand options.

Option

```
-s { <server_name> | all } or --server { <server_name> | all }
```

- <server name> is the name of the database server to which the SHOW-SERVERS actions are to be applied.
- If all is specified or if the -s option is omitted, the actions are applied to all database servers.

Example

The following example shows all database servers managed by BART when you execute the SHOW-SERVERS subcommand:

```
-bash-4.2$ bart SHOW-SERVERS
SERVER NAME : acctg
BACKUP FRIENDLY NAME: acctg_%year-%month-%dayT%hour:%minute
HOST NAME: 127.0.0.1
USER NAME : enterprisedb
PORT : 5444
REMOTE HOST :
RETENTION POLICY: 6 Backups
DISK UTILIZATION: 0.00 bytes
NUMBER OF ARCHIVES: 0
ARCHIVE PATH : /opt/backup/acctg/archived wals
ARCHIVE COMMAND: (disabled)
XLOG METHOD : fetch
WAL COMPRESSION: disabled
TABLESPACE PATH(s):
INCREMENTAL BACKUP : DISABLED
DESCRIPTION: "Accounting"
SERVER NAME : hr
BACKUP FRIENDLY NAME: hr %year-%month-%dayT%hour:%minute
HOST NAME: 192.168.2.24
USER NAME : postgres
PORT : 5432
REMOTE HOST: postgres@192.168.2.24
RETENTION POLICY: 6 Backups
DISK UTILIZATION: 0.00 bytes
NUMBER OF ARCHIVES: 0
ARCHIVE PATH : /opt/backup/hr/archived wals
```

```
ARCHIVE COMMAND: (disabled)
XLOG METHOD : fetch
WAL COMPRESSION : disabled
TABLESPACE PATH(s):
INCREMENTAL BACKUP : DISABLED
DESCRIPTION: "Human Resources"
SERVER NAME : mktg
BACKUP FRIENDLY NAME: mktg %year-%month-%dayT%hour:%minute
HOST NAME: 192.168.2.24
USER NAME : repuser
PORT : 5444
REMOTE HOST: enterprisedb@192.168.2.24
RETENTION POLICY: 6 Backups
DISK UTILIZATION: 0.00 bytes
NUMBER OF ARCHIVES: 0
ARCHIVE PATH : /opt/backup/mktg/archived wals
ARCHIVE COMMAND: (disabled)
XLOG METHOD : fetch
WAL COMPRESSION : disabled
TABLESPACE PATH(s):
INCREMENTAL BACKUP : DISABLED\
DESCRIPTION: "Marketing"
```

3.1.8 SHOW-BACKUPS

The SHOW-BACKUPS subcommand displays the backup information for the managed database servers.

Syntax:

```
> bart SHOW-BACKUPS [ -s { <server_name> | all } ]

[ -i { <backup_id> | <backup_name> | all } ]

[ -t ]
```

Options

```
--s { <server_name> | all } or --server { <server_name> | all }

> - `<server_name>` is the name of the database server whose backup information is to be displayed.

> - If `all` is specified or if the option is omitted, the backup information for all database servers is displayed with the exception as described by the following note:

> > If you invoke the `SHOW-BACKUPS` subcommand while the BART `BACKUP` subcommand is in progress, backups affected by the backup process are shown in progress status in the displayed backup information.
```

```
--i { <backup_id> | <backup_name> | all } or --backupid { <backup_id> | <backup_name> | all }
```

- > `<backup_id>` is a backup identifier and `<backup_name>` is the user-defined alphanumeric name for the backup.
- > If `all` is specified or if the option is omitted, all backup information for the relevant database server is displayed.
- -t or --toggle

Displays detailed backup information in list format. If the option is omitted, the default is a tabular format.

Example

The following example shows the backup from database server dev:

-bash-4.2\$ bart SHOW-BACKUPS -s dev							
SERVER NAME	BACKUP ID	BACKUP NAME	BACKUP				
PARENT							
BACKUP TIME	BACKUP SIZE	WAL(s) SIZE	WAL FILES				
STATUS							
dev	1477579596637	dev_2016-10-27T10:46:36	none				
2016-10-27 10:46:37 EDT	54.50 MB	96.00 MB	6				
active							

The following example shows detailed information using the -t option.

The following example shows a listing of an incremental backup along with its parent backup.

```
-bash-4.2$ bart SHOW-BACKUPS
SERVER NAME
                         BACKUP ID
                                           BACKUP NAME
                                                              BACKUP PARENT
BACKUP TIME
                         BACKUP SIZE
                                           WAL(s) SIZE
                                                              WAL FILES
STATUS
acctg
                         1477580293193
                                           acctg 2016-10-27
                                                              none
2016-10-27 10:58:13 EDT 16.45 MB
                                            16.00 MB
                                                              1
acctg 1477580111358 acctg 2016-10-27 none 2016-10-27 10:55:11 EDT 59.71
MB 16.00 MB 1 active
```

The following example shows the complete, detailed information of the incremental backup and the parent backup.

```
-bash-4.2$ bart SHOW-BACKUPS -t
SERVER NAME : acctg
BACKUP ID: 1477580293193
BACKUP NAME: none
BACKUP PARENT : acctg_2016-10-27
BACKUP STATUS: active
BACKUP TIME: 2016-10-27 10:58:13 EDT
BACKUP SIZE: 16.45 MB
WAL(S) SIZE: 16.00 MB
NO. OF WALS: 1
FIRST WAL FILE : 00000001000000200000009
CREATION TIME: 2016-10-27 10:58:13 EDT
LAST WAL FILE : 0000001000000200000009
CREATION TIME : 2016-10-27 10:58:13 EDT
SERVER NAME : acctq
BACKUP ID : 1477580111358
BACKUP NAME: acctg 2016-10-27
BACKUP PARENT : none
BACKUP STATUS : active
BACKUP TIME : 2016-10-27 10:55:11 EDT
BACKUP SIZE: 59.71 MB
WAL(S) SIZE: 16.00 MB
NO. OF WALS: 1
FIRST WAL FILE : 00000001000000200000008
CREATION TIME: 2016-10-27 10:55:12 EDT
LAST WAL FILE : 00000001000000200000008
CREATION TIME : 2016-10-27 10:55:12 EDT
```

3.1.9 VERIFY-CHKSUM

The VERIFY-CHKSUM subcommand verifies the MD5 checksums of the full backups and any user-defined tablespaces for the specified database server or for all database servers. The checksum is verified by comparing the current checksum of the backup against the checksum when the backup was taken.

Note

The VERIFY-CHKSUM subcommand is only used for tar format backups.

Syntax:

```
bart VERIFY-CHKSUM
[ -s { <server_name> | all } ]
[ -i { <backup_id> | <backup_name> | all } ]
```

Options

```
--s { <server name> | all } or --server { <server name> | all }
```

• <server_name> is the name of the database server whose tar backup checksums are to be verified. - If all is specified or if the -s option is omitted, the checksums of all tar backups are verified for all database servers.

```
--i { <backup_id> | <backup_name> | all } or --backupid {<backup_id> |
<backup_name> | all }
```

<backup_id> is the backup identifier of a tar format full backup whose checksum is to be verified along with any user-defined tablespaces.
 <backup_name> is the user-defined alphanumeric name for the full backup. - If all is specified or if the -i option is omitted, the checksums of all tar backups for the relevant database server are verified.

Example

The following example verifies the checksum of all tar format backups of the specified database server:

```
-bash-4.1$ bart VERIFY-CHKSUM -s acctg -i all
SERVER NAME BACKUP ID VERIFY
acctg 1430239348243 OK
acctg 1430232284202 OK
acctg 1430232016284 OK
acctg 1430231949065 OK
acctg 1429821844271 OK
```

3.1.10 Running the BART WAL Scanner

The BART WAL scanner is used to process each WAL file to find and record modified blocks in a corresponding MBM file. As a BART account user, use the BART WAL scanner to invoke the bart-scanner program located in the <BART_HOME>/bin directory.

For detailed information about WAL scanner and its usage, see the *Running the BART WAL Scanner* section of *EDB Postgres Backup and Recovery User Guide* available at:

https://www.enterprisedb.com/edb-docs/

Syntax:

```
bart-scanner
[ -d ]
[ -c <config_file_path> ]
{ -h |
-v |
--daemon |
-p <mbm_file> |
<wal_file> |
RELOAD |
STOP }
```

When the bart-scanner program is invoked, it forks a separate process for each database server enabled with the allow_incremental_backups parameter.

The WAL scanner processes can run in either the foreground or background depending upon usage of the —— daemon option:

- If the --daemon option is specified, the WAL scanner process runs in the background. All output messages can be viewed in the BART log file.
- If the --daemon option is omitted, the WAL scanner process runs in the foreground. All output messages can be viewed from the terminal running the program as well as in the BART log file.

Options

• -h or --help

Displays general syntax and information on WAL scanner usage.

• -v or --version

Displays the WAL scanner version information.

-d or --debug

Displays debugging output while executing the WAL scanner with any of its options.

• -c <config file path> or --config-path <config file path>

Specifies <config_file_path> as the full directory path to a BART configuration file. Use this option if you do not want to use the default BART configuration file <BART HOME>/etc/bart.cfg

--daemon

Runs the WAL scanner as a background process.

• -p <mbm_file> or --print <mbm_file>

Specifies the full directory path to an MBM file whose content is to be printed. The archived_wals directory as specified in the the archive path parameter in the bart.cfg file contains the MBM files.

• wal file

Specifies the full directory path to a WAL file to be scanned. The archive path directory contains the WAL files. Use it if a WAL file in the archive path is missing its MBM file.

This option is to be used for assisting the EnterpriseDB support team for debugging problems that may have been encountered.

• RELOAD

Reloads the BART configuration file. The keyword RELOAD is case-insensitive. The RELOAD option is useful if you make changes to the configuration file after the WAL scanner has been started. It will reload the configuration file and adjust the WAL scanners accordingly.

For example, if a server section allowing incremental backups is removed from the BART configuration file, then the process attached to that server will stop. Similarly, if a server allowing incremental backups is added, a new WAL scanner process will be launched to scan the WAL files of that server.

STOP

Stops the WAL scanner. The keyword **STOP** is not case-sensitive.

Example

The following example shows the startup of the WAL scanner to run interactively. The WAL scanner begins scanning existing WAL files in the archive path that have not yet been scanned (that is, there is no corresponding MBM file for the WAL file):

The following code snippet is the content of the archive path showing the MBM files created for the WAL files. (The user name and group name of the files have been removed from the example to list the WAL files and MBM files in a more readable manner):

```
[root@localhost archived wals]# pwd
/opt/backup/acctg/archived wals
[root@localhost archived wals]# ls -l
total 81944
-rw----- 1 ... ... 16777216 Dec 20 09:10 0000001000000000000000
-rw----- 1 ... 16777216 Dec 20 09:06 00000010000000000000EE
-rw----- 1 ... ... 16777216 Dec 20 09:11 0000001000000000000000EF
-rw----- 1 ... ... 16777216 Dec 20 09:16 000000100000000000000001
-rw----- 1 ... 305
                          Dec 20 09:16
00000010000000000000F1.00000028.backup
-rw-rw-r-- 1 ... 161
                          Dec 20 09:18
000000100000000ED0000280000000EE000000.mbm
-rw-rw-r-- 1 ... 161
                          Dec 20 09:18
000000100000000EE0000280000000EF000000.mbm
-rw-rw-r-- 1 ... 161
                          Dec 20 09:18
00000010000000EF000028000000F0000000.mbm
-rw-rw-r-- 1 ... 161
                          Dec 20 09:18
00000010000000F0000028000000F1000000.mbm
-rw-rw-r-- 1 ... 161
                          Dec 20 09:18
00000010000000F1000028000000F2000000.mbm
```

To stop the interactively running WAL scanner, either enter ctrl-C at the terminal running the WAL scanner or invoke the bart-scanner program from another terminal with the STOP option:

```
-bash-4.2$ bart-scanner STOP
-bash-4.2$
```

The terminal on which the WAL scanner was running interactively now appears as follows after it has been stopped:

```
-bash-4.2$ bart-scanner
INFO: process created for server 'acctg', pid = 5287
```

The following example shows how to invoke the WAL scanner to run as a background process with the **——daemon** option:

```
-bash-4.2$ bart-scanner --daemon
-bash-4.2$
```

The WAL scanner runs as a background process. There is also a separate background process for each database server that has been enabled for WAL scanning with the allow_incremental_backups parameter in the BART configuration file:

```
-bash-4.2$ ps -ef | grep bart
enterpr+ 4340 1 0 09:48 ? 00:00:00 bart-scanner --daemon
enterpr+ 4341 4340 0 09:48 ? 00:00:00 bart-scanner --daemon
enterpr+ 4415 3673 0 09:50 pts/0 00:00:00 grep --color=auto bart
```

To stop the WAL scanner processes, invoke the WAL scanner with the stop option:

```
-bash-4.2$ bart-scanner STOP
-bash-4.2$
```

If it is necessary to individually scan a WAL file, this can be done as follows:

```
-bash-4.2$ bart-scanner /opt/backup/acctg/archived_wals/0000001000000000000000FF -bash-4.2$
```

Should it be necessary to print the content of an MBM file for assisting the EnterpriseDB support team for debugging problems that may have been encountered, use the -p option to specify the file as in the following example:

```
First modified block: 0
Total modified blocks: 1

Path: base/14845/16391
NodeTag: BLOCK_CHANGE
Relation: relPath base/14845/16391, isTSNode 0, Blocks
*...

First modified block: 0
Total modified blocks: 1
```

3.2 Examples

This section lists examples of the following BART operations.

- Restoring a database cluster with tablespaces.
- Evaluating, marking, and deleting backups and incremental backups using redundancy and recovery window retention policy.
- Restoring an incremental backup.

Restoring a Database Cluster with Tablespaces

The following example illustrates taking a backup and restoring a database cluster on a remote host containing tablespaces. For detailed information regarding using tablespaces, see the *EDB Postgres Backup and Recovery User Guide* available at:

https://www.enterprisedb.com/edb-docs/

On an Advanced Server database running on a remote host, the following tablespaces are created and used by two tables:

```
edb=# CREATE TABLESPACE tblspc_1 LOCATION '/mnt/tablespace_1';
CREATE TABLESPACE
edb=# CREATE TABLESPACE tblspc_2 LOCATION '/mnt/tablespace_2';
CREATE TABLESPACE
edb=# \db
            List of tablespaces
Name
            Owner
                             Location
pg default | enterprisedb
           enterprisedb
pg_global
tblspc 1
            enterprisedb
                             /mnt/tablespace 1
tblspc 2
           enterprisedb
                             /mnt/tablespace 2
(4 rows)
```

```
edb=# CREATE TABLE tbl tblspc 1 (c1 TEXT) TABLESPACE tblspc 1;
CREATE TABLE
edb=# CREATE TABLE tbl_tblspc_2 (c1 TEXT) TABLESPACE tblspc_2;
CREATE TABLE
edb=# \d tbl tblspc 1
Table "enterprisedb.tbl tblspc 1"
Column | Type | Modifiers
-----
c1
     text
Tablespace: "tblspc_1"
edb=# \d tbl_tblspc_2
Table "enterprisedb.tbl tblspc 2"
Column | Type | Modifiers
-----
      text
c1
Tablespace: "tblspc_2"
```

The following example shows the OIDs assigned to the tablespaces and the symbolic links to the tablespace directories:

```
-bash-4.1$ pwd
/opt/PostgresPlus/9.5AS/data/pg_tblspc
-bash-4.1$ ls -l
total 0
lrwxrwxrwx 1 enterprisedb enterprisedb 17 Nov 16 16:17 16587 -
>/mnt/tablespace_1
lrwxrwxrwx 1 enterprisedb enterprisedb 17 Nov 16 16:17 16588 -
>/mnt/tablespace_2
```

The BART configuration file contains the following settings. Note that the tablespace_path parameter does not have to be set at this point.

```
[BART]
bart_host= enterprisedb@192.168.2.22
backup_path = /opt/backup
pg_basebackup_path = /usr/edb/as11/bin/pg_basebackup
logfile = /tmp/bart.log
scanner_logfile = /tmp/bart_scanner.log

[ACCTG]
host = 192.168.2.24
port = 5444
user = repuser
cluster_owner = enterprisedb
remote_host = enterprisedb@192.168.2.24
tablespace_path =
description = "Accounting"
```

After the necessary configuration steps are performed to ensure BART manages the remote database server, a full backup is taken.

```
-bash-4.1$ bart BACKUP -s acctg
```

```
INFO: creating backup for server 'acctg'
INFO: backup identifier: '1447709811516'
54521/54521 kB (100%), 3/3 tablespaces
INFO: backup completed successfully
INFO: backup checksum: 594f69fe7d26af991d4173d3823e174f of 16587.tar
INFO: backup checksum: 7a5507567729a21c98a15c948ff6c015 of base.tar
INFO: backup checksum: ae8c62604c409635c9d9e82b29cc0399 of 16588.tar
INFO:
BACKUP DETAILS:
BACKUP STATUS: active
BACKUP IDENTIFIER: 1447709811516
BACKUP NAME: none
BACKUP LOCATION: /opt/backup/acctg/1447709811516
BACKUP SIZE: 53.25 MB
BACKUP FORMAT: tar
XLOG METHOD: fetch
BACKUP CHECKSUM(s): 3
ChkSum File
594f69fe7d26af991d4173d3823e174f 16587.tar
7a5507567729a21c98a15c948ff6c015 base.tar
ae8c62604c409635c9d9e82b29cc0399 16588.tar
TABLESPACE(s): 2
Oid Name Location
16587 tblspc 1 /mnt/tablespace 1
16588 tblspc 2 /mnt/tablespace 2
START WAL LOCATION: 0000001000000000000000
BACKUP METHOD: streamed
BACKUP FROM: master
START TIME: 2015-11-16 16:36:51 EST
STOP TIME: 2015-11-16 16:36:52 EST
TOTAL DURATION: 1 sec(s)
```

Note in the output from the preceding example that checksums are generated for the tablespaces as well as the full backup.

Within the backup subdirectory 1447709811516 of the BART backup catalog, the tablespace data is stored with file names 16587.tar.gz and 16588.tar.gz as shown by the following example:

```
-bash-4.1$ pwd
/opt/backup/acctg
-bash-4.1$ ls -1
total 8
drwx----- 2 enterprisedb enterprisedb 4096 Nov 16 16:36 1447709811516
drwx----- 2 enterprisedb enterprisedb 4096 Nov 16 16:43 archived_wals
-bash-4.1$ ls -1 1447709811516
total 54536
-rw-rw-r-- 1 enterprisedb enterprisedb 19968 Nov 16 16:36 16587.tar
-rw-rw-r-- 1 enterprisedb enterprisedb 19968 Nov 16 16:36 16588.tar
-rw-rw-r-- 1 enterprisedb enterprisedb 949 Nov 16 17:05 backupinfo
-rw-rw-r-- 1 enterprisedb enterprisedb 55792640 Nov 16 16:36 base.tar
```

When you are ready to restore the backup, in addition to creating the directory to which the main database cluster is to be restored, prepare the directories to which the tablespaces are to be restored.

On the remote host, directories /opt/restore_tblspc_1 and /opt/restore_tblspc_2 are created and assigned the proper ownership and permissions as shown by the following example. The main database cluster is to be restored to /opt/restore.

```
[root@localhost opt]# mkdir restore_tblspc_1
[root@localhost opt]# chown enterprisedb restore_tblspc_1
[root@localhost opt]# chgrp enterprisedb restore tblspc 1
[root@localhost opt]# chmod 700 restore tblspc 1
[root@localhost opt]# mkdir restore tblspc 2
[root@localhost opt]# chown enterprisedb restore tblspc 2
[root@localhost opt]# chgrp enterprisedb restore tblspc 2
[root@localhost opt]# chmod 700 restore tblspc 2
[root@localhost opt]# ls -1
total 20
drwxr-xr-x 3 root daemon 4096 Nov 10 15:38 PostgresPlus
drwx----- 2 enterprisedb enterprisedb 4096 Nov 16 17:40 restore
drwx----- 2 enterprisedb enterprisedb 4096 Nov 16 17:40
restore tblspc 1
drwx----- 2 enterprisedb enterprisedb 4096 Nov 16 17:41
restore tblspc 2
drwxr-xr-x. 2 root root 4096 Nov 22 2013 rh
```

Set the tablespace path parameter in the BART configuration file to specify the tablespace directories.

Also note that the remote host user and IP address are specified by the **remote** host configuration parameter.

```
host = 192.168.2.24
port = 5444
user = repuser
cluster_owner = enterprisedb
remote_host = enterprisedb@192.168.2.24
tablespace_path =
16587=/opt/restore_tblspc_1;16588=/opt/restore_tblspc_2
description = "Accounting"
```

The following example shows invocation of the RESTORE subcommand:

```
-bash-4.1$ bart RESTORE -s acctg -i 1447709811516 -p /opt/restore
INFO: restoring backup '1447709811516' of server 'acctg'
INFO: restoring backup to enterprisedb@192.168.2.24:/opt/restore
INFO: base backup restored
INFO: archiving is disabled
INFO: tablespace(s) restored
```

The following example shows the restored full backup including the restored tablespaces:

```
bash-4.1$ pwd
```

```
/opt
-bash-4.1$ ls -l restore
total 104
-rw----- 1 enterprisedb enterprisedb 206 Nov 16 16:36 backup label.old
drwx----- 6 enterprisedb enterprisedb 4096 Nov 10 15:38 base
drwx----- 2 enterprisedb enterprisedb 4096 Nov 16 17:46 global
drwx----- 2 enterprisedb enterprisedb 4096 Nov 10 15:38 pg clog
-rw----- 1 enterprisedb enterprisedb 4438 Nov 10 16:23 pg hba.conf
-rw----- 1 enterprisedb enterprisedb 1636 Nov 10 15:38 pg ident.conf
drwxr-xr-x 2 enterprisedb enterprisedb 4096 Nov 16 17:45 pg log
drwx----- 4 enterprisedb enterprisedb 4096 Nov 10 15:38 pg multixact
drwx----- 2 enterprisedb enterprisedb 4096 Nov 16 17:45 pg notify
drwx----- 2 enterprisedb enterprisedb 4096 Nov 10 15:38 pg serial
drwx----- 2 enterprisedb enterprisedb 4096 Nov 10 15:38 pg snapshots
drwx----- 2 enterprisedb enterprisedb 4096 Nov 16 17:47 pg stat
drwx----- 2 enterprisedb enterprisedb 4096 Nov 16 17:47 pg_stat_tmp
drwx----- 2 enterprisedb enterprisedb 4096 Nov 10 15:38 pg_subtrans
drwx----- 2 enterprisedb enterprisedb 4096 Nov 16 17:42 pg tblspc
drwx----- 2 enterprisedb enterprisedb 4096 Nov 10 15:38 pg twophase
-rw----- 1 enterprisedb enterprisedb 4 Nov 10 15:38 PG VERSION
drwx----- 3 enterprisedb enterprisedb 4096 Nov 16 17:47 pg xlog
-rw----- 1 enterprisedb enterprisedb 23906 Nov 16 17:42 postgresql.conf
-rw----- 1 enterprisedb enterprisedb 61 Nov 16 17:45 postmaster.opts
-bash-4.1$
-bash-4.1$ ls -l restore_tblspc_1
drwx----- 3 enterprisedb enterprisedb 4096 Nov 16 16:18
PG 9.5 201306121
-bash-4.1$ ls -l restore_tblspc_2
drwx----- 3 enterprisedb enterprisedb 4096 Nov 16 16:18
PG 9.5 201306121
```

The symbolic links in the pg tblspc subdirectory point to the restored directory location:

```
bash-4.1$ pwd
/opt/restore/pg_tblspc
-bash-4.1$ ls -1
total 0
lrwxrwxrwx 1 enterprisedb enterprisedb 21 Nov 16 17:42 16587 ->
/opt/restore_tblspc_1
lrwxrwxrwx 1 enterprisedb enterprisedb 21 Nov 16 17:42 16588 ->
/opt/restore_tblspc_2
```

Queries within psql also show the restored tablespaces:

tblspc_1	enterprisedb	<pre>/opt/restore_tblspc_1</pre>
tblspc_2	enterprisedb	<pre>/opt/restore_tblspc_2</pre>

Managing Backups

This section illustrates evaluating, marking, and deleting backups using the MANAGE subcommand with two examples – the first for a redundancy retention policy and the second for a recovery window retention policy. For detailed information about the MANAGE subcommand, see the EDB Postgres Backup and Recovery User Guide available at:

https://www.enterprisedb.com/edb-docs/

Using a Redundancy Retention Policy

The following example uses a redundancy retention policy to evaluate, mark, and delete backups as shown by the following server configuration:

```
[ACCTG]
host = 127.0.0.1
port = 5444
user = enterprisedb
archive_command = 'cp %p %a/%f'
retention_policy = 3 BACKUPS
description = "Accounting"
```

The following list is the set of backups. Note that the last backup in the list has been marked as keep.

-bash-4.1\$ b	-bash-4.1\$ bart SHOW-BACKUPS -s acctg					
SERVER NAME	BACKUP ID	BACKUP TIME	BACKUP SIZE	WAL(s)		
SIZE						
WAL FILES	STATUS					
acctg	1428768344061	2015-04-11 12:05:46 EDT	5.72 MB	48.00 MB		
3	active					
acctg	1428684537299	2015-04-10 12:49:00 EDT	5.72 MB	272.00		
MB						
17	active					
acctg	1428589759899	2015-04-09 10:29:27 EDT	5.65 MB	96.00 MB		
6	active					
acctg	1428502049836	2015-04-08 10:07:30 EDT	55.25 MB	96.00 MB		
6	active					
acctg	1428422324880	2015-04-07 11:58:45 EDT	54.53 MB	32.00 MB		
2	active					
acctq	1428355371389	2015-04-06 17:22:53 EDT	5.71 MB	16.00 MB		
1	keep					
	-					

Invoke the MANAGE subcommand with the -n option to perform a dry run to observe which active backups would be changed to obsolete according to the retention policy:

```
-bash-4.1$ bart MANAGE -s acctg -n
INFO: processing server 'acctg', backup '1428768344061'
```

```
INFO: processing server 'acctg', backup '1428684537299'
INFO: processing server 'acctg', backup '1428589759899'
INFO: processing server 'acctg', backup '1428502049836'
INFO: marking backup '1428502049836' as obsolete
INFO: 6 WAL file(s) marked obsolete
INFO: processing server 'acctg', backup '1428422324880'
INFO: marking backup '1428422324880' as obsolete
INFO: 2 WAL file(s) marked obsolete
INFO: processing server 'acctg', backup '1428355371389'
```

The dry run shows that backups 1428502049836 and 1428422324880 would be marked as obsolete.

Note

A dry run does not change the backup status. The two backups that would be considered obsolete are still marked as active:

-bash-4.1\$ b	art SHOW-BACKUPS BACKUP ID	S -s acctg BACKUP TIME	BACKUP SIZE	WAL(s)
SIZE				
WAL FILES	STATUS			
acctg	1428768344061	2015-04-11 12:05:46 EDT	5.72 MB	48.00 MB
3	active			
acctg	1428684537299	2015-04-10 12:49:00 EDT	5.72 MB	272.00
MB				
17	active			
acctg	1428589759899	2015-04-09 10:29:27 EDT	5.65 MB	96.00 MB
6	active			
acctg	1428502049836	2015-04-08 10:07:30 EDT	55.25 MB	96.00 MB
6	active			
acctg	1428422324880	2015-04-07 11:58:45 EDT	54.53 MB	32.00 MB
2	active			
acctg	1428355371389	2015-04-06 17:22:53 EDT	5.71 MB	16.00 MB
1	keep			
1	keep			

Invoke the MANAGE subcommand omitting the -n option to change and mark the status of the backups as obsolete:

```
-bash-4.1$ bart MANAGE -s acctg
INFO: processing server 'acctg', backup '1428768344061'
INFO: processing server 'acctg', backup '1428684537299'
INFO: processing server 'acctg', backup '1428589759899'
INFO: processing server 'acctg', backup '1428502049836'
INFO: marking backup '1428502049836' as obsolete
INFO: 6 WAL file(s) marked obsolete
INFO: processing server 'acctg', backup '1428422324880'
INFO: marking backup '1428422324880' as obsolete
INFO: 2 WAL file(s) marked obsolete
INFO: processing server 'acctg', backup '1428355371389'
```

The obsolete backups can be observed in a number of ways. Use the MANAGE subcommand with the -1 option to list the obsolete backups:

```
-bash-4.1$ bart MANAGE -s acctg -1
INFO: 6 WAL file(s) will be removed
SERVER NAME: acctq
BACKUP ID: 1428502049836
BACKUP STATUS: obsolete
BACKUP TIME: 2015-04-08 10:07:30 EDT
BACKUP SIZE: 55.25 MB
WAL FILE(s): 6
WAL FILE: 00000001000000100000003
WAL FILE: 00000001000000100000002
WAL FILE: 00000001000000100000001
WAL FILE: 00000001000000100000000
INFO: 2 WAL file(s) will be removed
SERVER NAME: acctg
BACKUP ID: 1428422324880
BACKUP STATUS: obsolete
BACKUP TIME: 2015-04-07 11:58:45 EDT
BACKUP SIZE: 54.53 MB
WAL FILE(s): 2
WAL FILE: 000000010000000000000001
WAL FILE: 000000010000000000000000
```

The STATUS field of the SHOW-BACKUPS subcommand displays the current status:

-bash-4.1\$ bart SHOW-BACKUPS -s acctg						
SERVER NAME	BACKUP ID	BACKUP TIME		BACKUP SIZE	WAL(s)	
SIZE						
WAL FILES	STATUS					
acctg	1428768344061	2015-04-11 12	2:05:46 EDT	5.72 MB	48.00 MB	
3	active					
acctg	1428684537299	2015-04-10 12	2:49:00 EDT	5.72 MB	272.00 MB	
17	active					
acctg	1428589759899	2015-04-09 10	0:29:27 EDT	5.65 MB	96.00 MB	
6	active					
acctg	1428502049836	2015-04-08 10	0:07:30 EDT	55.25 MB	96.00 MB	
6	obsolete					
acctg	1428422324880	2015-04-07 13	1:58:45 EDT	54.53 MB	32.00 MB	
2	obsolete					
acctg	1428355371389	2015-04-06 1	7:22:53 EDT	5.71 MB	16.00 MB	
1	keep					

The details of an individual backup can be displayed using the SHOW-BACKUPS subcommand with the -t option. Note the status in the BACKUP STATUS field.

```
-bash-4.1$ bart SHOW-BACKUPS -s acctg -i 1428502049836 -t
SERVER NAME : acctg
BACKUP ID : 1428502049836
BACKUP NAME : none
BACKUP STATUS : obsolete
BACKUP TIME : 2015-04-08 10:07:30 EDT
BACKUP SIZE : 55.25 MB
```

Use the MANAGE subcommand with the -d option to physically delete the obsolete backups including the unneeded WAL files.

The SHOW-BACKUPS subcommand now displays the remaining backups marked as active or keep:

-bash-4.1\$ bar	rt SHOW-BACKUPS -s	acctg	
SERVER NAME	BACKUP ID	BACKUP TIME	BACKUP SIZE
WAL(s) SIZE			
WAL FILES	STATUS		
acctg	1428768344061	2015-04-11 12:05:46 EDT	5.72 MB
48.00 MB			
3	active		
acctg	1428684537299	2015-04-10 12:49:00 EDT	5.72 MB
272.00 MB			
17	active		
acctg	1428589759899	2015-04-09 10:29:27 EDT	5.65 MB
96.00 MB			
6	active		
acctg	1428355371389	2015-04-06 17:22:53 EDT	5.71 MB
16.00 MB			
1	keep		

Using a Recovery Window Retention Policy

This section illustrates the evaluation, marking, and deletion of backup using a recovery window retention policy. To use the recovery window retention policy, set the **retention_policy** parameter to the desired length of time for the recovery window.

This section provides examples of the following:

- How to view the calculated recovery window.
- How to evaluate, mark, and delete backup using a recovery window retention policy.

Viewing the Recovery Window

You can view the actual, calculated recovery window by invoking any of the following subcommands:

- MANAGE subcommand in debug mode (along with the -n option).
- SHOW-SERVERS subcommand.

Viewing the Recovery Window Using the Manage Subcommand

By invoking BART in debug mode and the MANAGE subcommand with the -n option, time length of the recovery window is calculated based on the retention policy setting and the current date/time.

For example, using the following retention policy settings:

```
[ACCTG]
host = 127.0.0.1
port = 5444
user = enterprisedb
archive_command = 'cp %p %a/%f'
retention policy = 3 DAYS
backup-name = acctg %year-%month-%dayT%hour:%minute:%second
description = "Accounting"
[DEV]
host = 127.0.0.1
port = 5445
user = enterprisedb
archive command = 'cp %p %a/%f'
retention policy = 3 WEEKS
description = "Development"
[HR]
host = 127.0.0.1
port = 5432
user = postgres
retention policy = 3 MONTHS
description = "Human Resources"
```

If the MANAGE subcommand is invoked in debug mode along with the -n option on 2015-04-17, the following results are displayed:

```
-bash-4.1$ bart -d MANAGE -n

DEBUG: Server: acctg, Now: 2015-04-17 16:34:03 EDT, RetentionWindow:

259200 (secs) ==> 72 hour(s)

DEBUG: Server: dev, Now: 2015-04-17 16:34:03 EDT, RetentionWindow:

1814400 (secs) ==> 504 hour(s)
```

```
DEBUG: Server: hr, Now: 2015-04-17 16:34:03 EDT, RetentionWindow: 7776000 (secs) ==> 2160 hour(s)
```

For server acctg, 72 hours translates to a recovery window of 3 days.

For server dev, 504 hours translates to a recovery window of 21 days (3 weeks).

For server hr, 2160 hours translates to a recovery window of 90 days (3 months).

For a setting of <max_number> MONTHS, the calculated total number of days for the recovery window is dependent upon the actual number of days in the preceding months from the current date/time. Thus, <max_number> MONTHS is not always exactly equivalent to <max_number> x 30 DAYS. (For example, if the current date/time is in the month of March, a 1-month recovery window would be equivalent to only 28 days because the preceding month is February. Thus, for a current date of March 31, a 1-month recovery window would start on March 3.) However, the typical result is that the day of the month of the starting recovery window boundary will be the same day of the month of when the MANAGE subcommand is invoked.

Viewing the Recovery Window Using the Show-Servers Subcommand

This section provides example of viewing the recovery window using the SHOW-SERVERS subcommand, the RETENTION POLICY field displays the start of the recovery window.

In the following example, the recovery window retention policy setting considers the backups taken within a 3-day recovery window as the active backups.

```
[ACCTG]
host = 127.0.0.1
port = 5444
user = enterprisedb
archive_command = 'cp %p %a/%f'
retention_policy = 3 DAYS
description = "Accounting"
```

The start of the 3-day recovery window displayed in the RETENTION POLICY field is 2015-04-07 14:57:36 EDT when the SHOW-SERVERS subcommand is invoked on 2015-04-10.

At this current point in time, backups taken on or after 2015-04-07 14:57:36 EDT would be considered active. Backups taken prior to 2015-04-07 14:57:36 EDT would be considered obsolete except for backups marked as keep.

```
-bash-4.1$ date
Fri Apr 10 14:57:33 EDT 2015
-bash-4.1$
-bash-4.1$ bart SHOW-SERVERS -s acctg
SERVER NAME
                 : acctg
HOST NAME
                   : 127.0.0.1
USER NAME
                   : enterprisedb
                   : 5444
PORT
REMOTE HOST
RETENTION POLICY : 2015-04-07 14:57:36 EDT
DISK UTILIZATION
                  : 824.77 MB
NUMBER OF ARCHIVES: 37
ARCHIVE PATH
                   : /opt/backup/acctg/archived wals
                   : cp %p /opt/backup/acctg/archived wals/%f
ARCHIVE COMMAND
```

```
XLOG METHOD : fetch
WAL COMPRESSION : disabled
TABLESPACE PATH(s) :
DESCRIPTION : "Accounting"
```

In the following example, the recovery window retention policy setting considers the backups taken within a 3-week recovery window as the active backups.

```
[DEV]
host = 127.0.0.1
port = 5445
user = enterprisedb
archive_command = 'cp %p %a/%f'
retention_policy = 3 WEEKS
description = "Development"
```

The start of the 3-week recovery window displayed in the RETENTION POLICY field is 2015-03-20 14:59:42 EDT when the SHOW-SERVERS subcommand is invoked on 2015-04-10.

At this current point in time, backups taken on or after 2015-03-20 14:59:42 EDT would be considered active. Backups taken prior to 2015-03-20 14:59:42 EDT would be considered obsolete except for backups marked as keep.

```
-bash-4.1$ date
Fri Apr 10 14:59:39 EDT 2015
-bash-4.1$
-bash-4.1$ bart SHOW-SERVERS -s dev
SERVER NAME : dev
HOST NAME : 127.0.0.1
USER NAME : enterprisedb
PORT : 5445
REMOTE HOST :
RETENTION POLICY: 2015-03-20 14:59:42 EDT
DISK UTILIZATION: 434.53 MB
NUMBER OF ARCHIVES: 22
ARCHIVE PATH : /opt/backup/dev/archived wals
ARCHIVE COMMAND: cp %p /opt/backup/dev/archived wals/%f
XLOG METHOD : fetch
WAL COMPRESSION : disabled
TABLESPACE PATH(s):
DESCRIPTION : "Development"
```

In the following example, the recovery window retention policy setting considers the backups taken within a 3-month recovery window as the active backups.

```
[HR]
host = 127.0.0.1
port = 5432
user = postgres
retention_policy = 3 MONTHS
description = "Human Resources"
```

The start of the 3-month recovery window displayed in the RETENTION POLICY field is 2015-01-10

14:04:23 EST when the SHOW-SERVERS subcommand is invoked on 2015-04-10.

At this current point in time, backups taken on or after 2015-01-10 14:04:23 EST would be considered active. Backups taken prior to 2015-01-10 14:04:23 EST would be considered obsolete, except for backups marked as keep.

```
-bash-4.1$ date
Fri Apr 10 15:04:19 EDT 2015
-bash-4.1$
-bash-4.1$ bart SHOW-SERVERS -s hr
SERVER NAME : hr
HOST NAME: 127.0.0.1
USER NAME : postgres
PORT : 5432
REMOTE HOST :
RETENTION POLICY: 2015-01-10 14:04:23 EST
DISK UTILIZATION: 480.76 MB
NUMBER OF ARCHIVES: 26
ARCHIVE PATH : /opt/backup/hr/archived wals
ARCHIVE COMMAND : scp %p
enterprisedb@192.168.2.22:/opt/backup/hr/archived wals/%f
XLOG METHOD : fetch
WAL COMPRESSION : disabled
TABLESPACE PATH(s):
DESCRIPTION: "Human Resources"
```

Evaluating, Marking, and Deleting Backup Using a Recovery Window Retention Policy

The following example uses a recovery window retention policy to evaluate, mark, and delete backups as shown by the following server configuration:

```
[DEV]
host = 127.0.0.1
port = 5445
user = enterprisedb
archive_command = 'cp %p %a/%f'
retention_policy = 3 DAYS
description = "Development"
```

The following is the current set of backups. Note that the last backup in the list has been marked as keep.

-bash-4.1\$ bart SHOW-BACKUPS -s dev					
SERVER NAME	BACKUP ID	BACKUP TIME	BACKUP SIZE		
WAL(s) SIZE					
WAL FILES	STATUS				
dev	1428933278236	2015-04-13 09:54:40 EDT	5.65 MB 16.00		
MB					
1	active				
dev	1428862187757	2015-04-12 14:09:50 EDT	5.65 MB 32.00		
MB					
2	active				
dev	1428768351638	2015-04-11 12:05:54 EDT	5.65 MB 32.00		

MB						
2	active					
dev	1428684544008	2015-04-10	12:49:06	EDT	5.65 MB	224.00
MB						
14	active					
dev	1428590536488	2015-04-09	10:42:18	EDT	5.65 MB	48.00
MB						
3	active					
dev	1428502171990	2015-04-08	10:09:34	EDT	5.65 MB	80.00
MB						
5	keep					

The current date and time is 2015-04-13 16:46:35 EDT as shown by the following:

```
-bash-4.1$ date
Mon Apr 13 16:46:35 EDT 2015
```

Thus, a 3-day recovery window would evaluate backups prior to 2015-04-10 16:46:35 EDT as obsolete except for those marked as keep.

Invoke the MANAGE subcommand with the -n option to perform a dry run to observe which active backups would be changed to obsolete according to the retention policy.

```
-bash-4.1$ bart MANAGE -s dev -n

INFO: processing server 'dev', backup '1428933278236'

INFO: processing server 'dev', backup '1428768351638'

INFO: processing server 'dev', backup '1428684544008'

INFO: processing server 'dev', backup '1428684544008'

INFO: marking backup '1428684544008' as obsolete

INFO: 14 WAL file(s) marked obsolete

INFO: 1 Unused WAL file(s) present

INFO: processing server 'dev', backup '1428590536488'

INFO: marking backup '1428590536488' as obsolete

INFO: 3 WAL file(s) marked obsolete

INFO: 1 Unused WAL file(s) present

INFO: processing server 'dev', backup '1428502171990'
```

The dry run shows that backups 1428684544008 and 1428590536488 would be marked as obsolete.

Also note that a dry run does not change the backup status. The two backups that would be considered obsolete are still marked as active:

-bash-4.1\$ bar	t SHOW-BACKUPS	-s dev\	
SERVER NAME	BACKUP ID	BACKUP TIME	BACKUP SIZE
WAL(s) SIZE			
WAL FILES	STATUS		
dev	1428933278236	2015-04-13 09:54:40 EDT	5.65 MB 16.00
MB			
1	active		
dev	1428862187757	2015-04-12 14:09:50 EDT	5.65 MB 32.00
MB			
2	active		
dev	1428768351638	2015-04-11 12:05:54 EDT	5.65 MB 32.00

MB						
2	active					
dev	1428684544008	2015-04-10	12:49:06	EDT	5.65 MB	224.00
MB						
14	active					
dev	1428590536488	2015-04-09	10:42:18	EDT	5.65 MB	48.00
MB						
3	active					
dev	1428502171990	2015-04-08	10:09:34	EDT	5.65 MB	80.00
MB						
5	keep					

Invoke the MANAGE subcommand omitting the -n option to change and mark the status of the backups as obsolete:

```
-bash-4.1$ bart MANAGE -s dev

INFO: processing server 'dev', backup '1428933278236'
INFO: processing server 'dev', backup '1428862187757'
INFO: processing server 'dev', backup '1428768351638'
INFO: processing server 'dev', backup '1428684544008'
INFO: marking backup '1428684544008' as obsolete
INFO: 14 WAL file(s) marked obsolete
INFO: 1 Unused WAL file(s) present
INFO: processing server 'dev', backup '1428590536488'
INFO: marking backup '1428590536488' as obsolete
INFO: 3 WAL file(s) marked obsolete
INFO: 1 Unused WAL file(s) present
INFO: processing server 'dev', backup '1428502171990'
```

The obsolete backups can be observed in a number of ways. Use the MANAGE subcommand with the -1 option to list the obsolete backups:

```
-bash-4.1$ bart MANAGE -s dev -l
INFO: 14 WAL file(s) will be removed
INFO: 1 Unused WAL file(s) will be removed
SERVER NAME: dev
BACKUP ID: 1428684544008
BACKUP STATUS: obsolete
BACKUP TIME: 2015-04-10 12:49:06 EDT
BACKUP SIZE: 5.65 MB
WAL FILE(s): 14
UNUSED WAL FILE(s): 1
WAL FILE: 0000000100000000000002E
WAL FILE: 0000001000000000000002B
WAL FILE: 00000001000000000000002A
WAL FILE: 00000010000000000000028
WAL FILE: 00000001000000000000027
WAL FILE: 000000010000000000000026
WAL FILE: 000000100000000000000025
WAL FILE: 0000001000000000000024
```

INFO: 1 Unused WAL file(s) will be removed

SERVER NAME: dev

BACKUP ID: 1428590536488
BACKUP STATUS: obsolete

BACKUP TIME: 2015-04-09 10:42:18 EDT\

BACKUP SIZE: 5.65 MB

WAL FILE(s): 3

UNUSED WAL FILE(s): 1

UNUSED WAL FILE: 000000010000000000000.00000028

The STATUS field of the SHOW-BACKUPS subcommand displays the current status:

-bash-4.1\$ bart SHOW-BACKUPS -s dev						
SERVER NAME	BACKUP ID	BACKUP TIME	BACKUP SIZE WAL(s)			
SIZE						
WAL FILES	STATUS					
dev	1428933278236	2015-04-13 09:54:40 EDT	5.65 MB 16.00 MB			
1	active					
dev	1428862187757	2015-04-12 14:09:50 EDT	5.65 MB 32.00 MB			
2	active					
dev	1428768351638	2015-04-11 12:05:54 EDT	5.65 MB 32.00 MB			
2	active					
dev	1428684544008	2015-04-10 12:49:06 EDT	5.65 MB 224.00 MB			
14	obsolete					
dev	1428590536488	2015-04-09 10:42:18 EDT	5.65 MB 48.00 MB			
3	obsolete					
dev	1428502171990	2015-04-08 10:09:34 EDT	5.65 MB 80.00 MB			
5	keep					

The details of an individual backup can be displayed using the SHOW-BACKUPS subcommand with the -t option. Note the status in the BACKUP STATUS field.

```
-bash-4.1$ bart SHOW-BACKUPS -s dev -i 1428684544008 -t
SERVER NAME : dev
BACKUP ID
             : 1428684544008
BACKUP NAME
             : none
BACKUP STATUS : obsolete
BACKUP TIME : 2015-04-10 12:49:06 EDT
BACKUP SIZE
             : 5.65 MB
             : 224.00 MB
WAL(S) SIZE
NO. OF WALS
            : 14
FIRST WAL FILE : 00000001000000000000021
CREATION TIME : 2015-04-10 12:49:06 EDT
LAST WAL FILE : 0000000100000000000002E
CREATION TIME : 2015-04-11 12:02:15 EDT
```

Use the MANAGE subcommand with the -d option to physically delete the obsolete backups including the unneeded WAL files.

```
-bash-4.1$ bart MANAGE -s dev -d
INFO: removing all obsolete backups of server 'dev'
INFO: removing obsolete backup '1428684544008'
INFO: 14 WAL file(s) will be removed
INFO: 1 Unused WAL file(s) will be removed
INFO: removing WAL file '00000001000000000000002E'
INFO: removing WAL file '00000001000000000000002B'
INFO: removing WAL file '0000000100000000000002A'
INFO: removing WAL file '000000010000000000000000005'
INFO: removing WAL file '000000010000000000000024'
INFO: removing WAL file '000000010000000000000003'
INFO: removing WAL file '000000010000000000000022'
INFO: removing WAL file '00000001000000000000001'
INFO: removing (unused) WAL file '00000001000000000000000F.00000028'
INFO: removing obsolete backup '1428590536488'
INFO: 3 WAL file(s) will be removed
INFO: removing WAL file '0000000100000000000001F'
INFO: removing WAL file '0000000100000000000001E'
```

The SHOW-BACKUPS subcommand now displays the remaining backups marked as active or keep:

-bash-4.1\$ b	art SHOW-BACKUP	S -s dev				
SERVER NAME	BACKUP ID	BACKUP TIME			BACKUP SIZE	WAL(s)
SIZE						
WAL FILES	STATUS					
dev	1428933278236	2015-04-13	09:54:40	EDT	5.65 MB	16.00
MB						
1	active					
dev	1428862187757	2015-04-12	14:09:50	EDT	5.65 MB	32.00
MB						
2	active					
dev	1428768351638	2015-04-11	12:05:54	EDT	5.65 MB	32.00
MB						
2	active					
dev	1428502171990	2015-04-08	10:09:34	EDT	5.65 MB	80.00
MB						
5	keep					

Managing Incremental Backups

This section illustrates evaluating, marking, and deleting incremental backups using the MANAGE and

DELETE subcommands with two examples – the first for a redundancy retention policy and the second for a recovery window retention policy. For detailed information about the **MANAGE** and **DELETE** subcommands, as well as the redundancy retention and recovery window retention policy, see the *EDB Postgres Backup and Recovery User Guide* available at:

https://www.enterprisedb.com/edb-docs/

- Using a Redundancy Retention Policy provides an example of using the MANAGE and DELETE subcommands when a 3 backup redundancy retention policy is in effect.
- Using a Recovery Window Retention Policy provides an example of using the MANAGE and DELETE subcommands when a 1-day recovery window retention policy is in effect.

Using a Redundancy Retention Policy

The following examples show using the MANAGE and DELETE subcommands to evaluate, mark, and delete incremental backups when a 3 backup redundancy retention policy is in effect. This is shown by the following server configuration:

```
host = 192.168.2.24
port = 5445
user = enterprisedb
cluster_owner = enterprisedb
remote_host = enterprisedb@192.168.2.24
allow_incremental_backups = enabled
retention_policy = 3 BACKUPS
description = "Accounting"
```

The following is the current set of backups. (In these examples, some columns have been omitted from the SHOW-BACKUPS output in order to display the relevant information in a more observable manner).

-bash-4.2\$ b	oart SHOW-BACKUPS	-s acctg		
SERVER NAME	BACKUP ID	BACKUP PARENT	BACKUP TIME	
STATUS				
acctg	1481749696905	1481749673603	2016-12-14 16:08:17 EST	• • •
active				
acctg	1481749673603	1481749651927	2016-12-14 16:07:53 EST	• • •
active				
acctg	1481749651927	1481749619582	2016-12-14 16:07:32 EST	• • •
active				
acctg	1481749619582	none	2016-12-14 16:07:00 EST	• • •
active				

There is one backup chain. The first backup is the initial full backup.

Backup chain: 1481749619582 => 1481749651927 => 1481749673603 => 1481749696905

The MANAGE subcommand is invoked as shown by the following:

```
-bash-4.2$ bart MANAGE -s acctg
INFO: processing server 'acctg', backup '1481749619582'
```

```
INFO: 2 Unused WAL file(s) present
INFO: 4 Unused file(s) (WALs included) present, use 'MANAGE -1' for the
list
```

The following example shows the resulting status of the backups:

-bash-4.2\$ bar	t SHOW-BACKUPS	-s acctg		
SERVER NAME	BACKUP ID	BACKUP PARENT	BACKUP TIME	
STATUS				
acctg	1481749696905	1481749673603	2016-12-14 16:08:17 EST	• • •
active				
acctg	1481749673603	1481749651927	2016-12-14 16:07:53 EST	• • •
active				
acctg	1481749651927	1481749619582	2016-12-14 16:07:32 EST	• • •
active				
acctg	1481749619582	none	2016-12-14 16:07:00 EST	• • •
active				

The status remains active for all backups. Even though the total number of backups exceeds the 3 backup redundancy retention policy, it is only the total number of full backups that is used to determine if the redundancy retention policy has been exceeded.

Additional full backups are added including a second backup chain. The following example shows the resulting list of backups:

-bash-4.2\$ b	oart SHOW-BACKU	IPS -s acctq		
		BACKUP PARENT	BACKUP TIME	• • •
acctg active	1481750365397	none	2016-12-14 16:19:26 EST	• • •
acctg	1481750098924	1481749997807	2016-12-14 16:14:59 EST	• • •
acctg	1481749997807	none	2016-12-14 16:13:18 EST	• • •
acctg active	1481749992003	none	2016-12-14 16:13:12 EST	• • •
acctg	1481749696905	1481749673603	2016-12-14 16:08:17 EST	• • •
active acctg	1481749673603	1481749651927	2016-12-14 16:07:53 EST	• • •
active	1481749651927	1481749619582	2016-12-14 16:07:32 EST	• • •
active acctg	1481749619582	none	2016-12-14 16:07:00 EST	
active				

Second backup chain: 1481749997807 => 1481750098924

The MANAGE subcommand is invoked, but now with a total of four active full backups.

```
-bash-4.2$ bart MANAGE -s acctg
INFO: processing server 'acctg', backup '1481750365397'
INFO: processing server 'acctg', backup '1481749997807'
INFO: processing server 'acctg', backup '1481749992003'
```

```
INFO: processing server 'acctg', backup '1481749619582'
INFO: marking backup '1481749619582' as obsolete
INFO: 3 incremental(s) of backup '1481749619582' will be marked obsolete
INFO: marking incremental backup '1481749696905' as obsolete
INFO: marking incremental backup '1481749673603' as obsolete
INFO: marking incremental backup '1481749651927' as obsolete
INFO: 4 WAL file(s) marked obsolete
INFO: 2 Unused WAL file(s) present
INFO: 4 Unused file(s) (WALs included) present, use 'MANAGE -1' for the
list
```

The oldest full backup and its chain of incremental backups are now marked as obsolete.

```
-bash-4.2$ bart SHOW-BACKUPS -s acctq
SERVER NAME BACKUP ID
                              ... BACKUP PARENT
                                                  BACKUP TIME
... STATUS
            1481750365397
                                                  2016-12-14 16:19:26 EST ...
acctg
                              ... none
active
acctg
             1481750098924
                              ... 1481749997807
                                                  2016-12-14 16:14:59 EST ...
active
                                                  2016-12-14 16:13:18 EST ...
             1481749997807
                              ... none
acctg
active
                                                  2016-12-14 16:13:12 EST ...
acctg
             1481749992003
                              ... none
active
             1481749696905
                              ... 1481749673603
                                                  2016-12-14 16:08:17 EST ...
acctq
obsolete
acctg
             1481749673603
                              ... 1481749651927
                                                  2016-12-14 16:07:53 EST ...
obsolete
acctq
             1481749651927
                              ... 1481749619582
                                                  2016-12-14 16:07:32 EST ...
obsolete
                              ... none
                                                  2016-12-14 16:07:00 EST ...
acctq
             1481749619582
obsolete
```

Invoking the MANAGE subcommand with the -d option deletes the entire obsolete backup chain.

```
'000000010000000FB0000280000000FC000000.mbm'
```

The following example shows the remaining full backups and the second backup chain.

```
-bash-4.2$ bart SHOW-BACKUPS -s acctq
SERVER NAME
             BACKUP ID
                               ... BACKUP PARENT
                                                    BACKUP TIME
STATUS
             1481750365397
                               ... none
                                                    2016-12-14 16:19:26 EST ...
acctq
active
                                                    2016-12-14 16:14:59 EST ...
acctg
             1481750098924
                               ... 1481749997807
active
             1481749997807
                                                    2016-12-14 16:13:18 EST ...
acctg
                               ... none
active
                                                    2016-12-14 16:13:12 EST ...
acctg
             1481749992003
                               ... none
active
```

Using a Recovery Window Retention Policy

The following examples show using the MANAGE and DELETE subcommands to evaluate, mark, and delete incremental backups when a 1-day recovery window retention policy is in effect. This is shown by the following server configuration:

```
host = 192.168.2.24
port = 5445
user = enterprisedb
cluster_owner = enterprisedb
remote_host = enterprisedb@192.168.2.24
allow_incremental_backups = enabled
retention_policy = 1 DAYS
description = "Accounting"
```

The following is the current set of backups. In these examples, some columns have been omitted from the SHOW-BACKUPS output in order to display the relevant information in a more observable manner.

```
-bash-4.2$ bart SHOW-BACKUPS -s acctg

SERVER NAME BACKUP ID ... BACKUP PARENT BACKUP TIME ... STATUS

acctg 1481559303348 ... 1481554203288 2016-12-12 11:15:03 EST ... active

acctg 1481559014359 ... 1481554802918 2016-12-12 11:10:14 EST ... active

acctg 1481554802918 ... 1481553914533 2016-12-12 10:00:03 EST ... active

acctg 1481554203288 ... 1481553651165 2016-12-12 09:50:03 EST ... active

acctg 1481553914533 ... 1481553088053 2016-12-12 09:45:14 EST ... active

acctg 1481553651165 ... none 2016-12-12 09:40:51 EST ... active

acctg 1481553088053 ... 1481552078404 2016-12-12 09:31:28 EST ... active

acctg 1481552078404 ... none 2016-12-12 09:14:39 EST ... active
```

There are two backup chains. In each of the following chains, the first backup is the initial full backup.

```
First backup chain: 1481552078404 => 1481553088053 => 1481553914533 => 1481554802918 => 1481559014359
```

Second backup chain: 1481553651165 => 1481554203288 => 1481559303348

The MANAGE subcommand is invoked when the first full backup 1481552078404 falls out of the recovery window. When the MANAGE subcommand is invoked, it is 2016-12-13 09:20:03 EST, thus making the start of the 1-day recovery window at 2016-12-12 09:20:03 EST exactly one day earlier. This backup was taken at 2016-12-12 09:14:39 EST, which is about 5 ½ minutes before the start of the recovery window, thus making the backup obsolete.

```
-bash-4.2$ date

Tue Dec 13 09:20:03 EST 2016
-bash-4.2$ bart MANAGE -s acctg

INFO: processing server 'acctg', backup '1481553651165'

INFO: processing server 'acctg', backup '1481552078404'

INFO: marking backup '1481552078404' as obsolete

INFO: 4 incremental(s) of backup '1481552078404' will be marked obsolete

INFO: marking incremental backup '1481559014359' as obsolete

INFO: marking incremental backup '1481554802918' as obsolete

INFO: marking incremental backup '1481553914533' as obsolete

INFO: marking incremental backup '1481553088053' as obsolete

INFO: 7 WAL file(s) marked obsolete

INFO: 1 Unused WAL file(s) present

INFO: 2 Unused file(s) (WALs included) present, use 'MANAGE -1' for the list
```

The entire first backup chain is now marked obsolete.

The incremental backup date and time are within the recovery window since they were taken after the start of the recovery window of 2016-12-12 09:20:03 EST, but all backups in the chain are marked as obsolete.

-bash-4.2\$ bart			•	
	BACKUP ID	• • •	BACKUP PARENT	BACKUP TIME
STATUS	1/1015503032/0		1481554203288	2016-12-12 11:15:03
EST	1401333303340	• • •	1401334203200	2010-12-12 11:15:05
active				
acctg	1481559014359		1481554802918	2016-12-12 11:10:14
EST				
obsolete acctg	1481554802918		1481553914533	2016-12-12 10:00:03
EST	1401334002310	• • •	1401333714333	2010 12-12 10:00:03
obsolete				
_	1481554203288	• • •	1481553651165	2016-12-12 09:50:03
EST				
active acctq	1/0155201/522		1481553088053	2016-12-12 09:45:14
EST	1461555914555	• • •	1401555000055	2016-12-12 09:45:14
obsolete				
acctg	1481553651165		none	2016-12-12 09:40:51
EST				
active	140155200055		1401552070404	2016 12 12 00 21 22
acctg EST	1481553088053	• • •	1481552078404	2016-12-12 09:31:28
obsolete				
acctg	1481552078404		none	2016-12-12 09:14:39

EST

... obsolete

The following example shows how the entire backup chain is changed back to active status by invoking the MANAGE subcommand with the -c nokeep option on the full backup of the chain.

```
-bash-4.2$ bart MANAGE -s acctg -c nokeep -i 1481552078404

INFO: changing status of backup '1481552078404' of server 'acctg' from 'obsolete' to 'active'

INFO: status of 4 incremental(s) of backup '1481552078404' will be changed

INFO: changing status of incremental backup '1481559014359' of server 'acctg' from 'obsolete' to 'active'

INFO: changing status of incremental backup '1481554802918' of server 'acctg' from 'obsolete' to 'active'

INFO: changing status of incremental backup '1481553914533' of server 'acctg' from 'obsolete' to 'active'

INFO: changing status of incremental backup '1481553088053' of server 'acctg' from 'obsolete' to 'active'

INFO: 7 WAL file(s) changed
```

The backup chain has now been reset to active status.

-bash-4.2\$ bar	t SHOW-BACKUPS -s	acctq	
SERVER NAME STATUS	BACKUP ID	BACKUP PARENT	BACKUP TIME
acctg active	1481559303348	1481554203288	2016-12-12 11:15:03 EST
acctg active	1481559014359	1481554802918	2016-12-12 11:10:14 EST
acctg active	1481554802918	1481553914533	2016-12-12 10:00:03 EST
acctg active	1481554203288	1481553651165	2016-12-12 09:50:03 EST
acctg active	1481553914533	1481553088053	2016-12-12 09:45:14 EST
acctg active	1481553651165	none	2016-12-12 09:40:51 EST
acctg active	1481553088053	1481552078404	2016-12-12 09:31:28 EST
acctg active	1481552078404	none	2016-12-12 09:14:39 EST

The following example shows usage of the DELETE subcommand on an incremental backup. The specified incremental backup 1481554802918 in the first backup chain as well as its successive incremental backup 1481559014359 are deleted.

```
-bash-4.2$ bart DELETE -s acctg -i 1481554802918
INFO: deleting backup '1481554802918' of server 'acctg'
INFO: deleting backup '1481554802918'
INFO: 1 incremental backup(s) will be deleted
INFO: deleting incremental backup '1481559014359'
INFO: WALs of deleted backup(s) will belong to prior backup(if any), or
```

```
will be marked unused
INFO: 2 Unused file(s) will be removed
INFO: removing (unused) file '00000001000000000000BA'
INFO: removing (unused) file
'000000010000000BA0000280000000BB000000.mbm'
INFO: backup(s) deleted
```

The results show that incremental backup 1481554802918 as well as its successive backup 1481559014359 are no longer listed by the SHOW-BACKUPS subcommand.

```
-bash-4.2$ bart SHOW-BACKUPS -s acctg
                            ... BACKUP PARENT
SERVER NAME BACKUP ID
                                                 BACKUP TIME
... STATUS
             1481559303348
                             ... 1481554203288
                                                 2016-12-12 11:15:03 EST
acctg
... active
                             ... 1481553651165
                                                 2016-12-12 09:50:03 EST
             1481554203288
acctq
... active
                             ... 1481553088053
                                                 2016-12-12 09:45:14 EST
acctq
             1481553914533
... active
             1481553651165
                                                 2016-12-12 09:40:51 EST
acctq
                             ... none
... active
             1481553088053
                             ... 1481552078404
                                                 2016-12-12 09:31:28 EST
acctq
... active
                                                  2016-12-12 09:14:39 EST
             1481552078404
                             ... none
acctg
... active
```

The MANAGE subcommand is invoked again. This time both backup chains are marked obsolete since the full backups of both chains fall out of the start of the recovery window, which is now 2016-12-12 09:55:03 EST.

```
-bash-4.2$ date

Tue Dec 13 09:55:03 EST 2016

-bash-4.2$ bart MANAGE -s acctg

INFO: processing server 'acctg', backup '1481553651165'

INFO: marking backup '1481553651165' as obsolete

INFO: 2 incremental(s) of backup '1481553651165' will be marked obsolete

INFO: marking incremental backup '1481559303348' as obsolete

INFO: marking incremental backup '1481554203288' as obsolete

INFO: 38 WAL file(s) marked obsolete

INFO: processing server 'acctg', backup '1481552078404'

INFO: marking backup '1481552078404' as obsolete

INFO: 2 incremental(s) of backup '1481552078404' will be marked obsolete

INFO: marking incremental backup '1481553914533' as obsolete

INFO: marking incremental backup '1481553088053' as obsolete

INFO: 7 WAL file(s) marked obsolete
```

The following example shows both backup chains marked as obsolete.

```
-bash-4.2$ bart SHOW-BACKUPS -s acctg

SERVER NAME BACKUP ID ... BACKUP PARENT BACKUP TIME
... STATUS

acctg 1481559303348 ... 1481554203288 2016-12-12 11:15:03 EST
... obsolete
```

acctg obsolete	1481554203288	1481553651165	2016-12-12 09:50:03 EST
acctg obsolete	1481553914533	1481553088053	2016-12-12 09:45:14 EST
<pre>acctg obsolete</pre>	1481553651165	none	2016-12-12 09:40:51 EST
acctg obsolete	1481553088053	1481552078404	2016-12-12 09:31:28 EST
acctg obsolete	1481552078404	none	2016-12-12 09:14:39 EST

The following example shows usage of the MANAGE subcommand with the -c keep option to keep a backup chain indefinitely. The MANAGE subcommand with the -c keep option must specify the backup identifier or backup name of the full backup of the chain, and not any incremental backup.

```
-bash-4.2$ bart MANAGE -s acctg -c keep -i 1481553651165
INFO: changing status of backup '1481553651165' of server 'acctg' from 'obsolete' to 'keep'
INFO: status of 2 incremental(s) of backup '1481553651165' will be changed
INFO: changing status of incremental backup '1481559303348' of server 'acctg' from 'obsolete' to 'keep'
INFO: changing status of incremental backup '1481554203288' of server 'acctg' from 'obsolete' to 'keep'
INFO: 38 WAL file(s) changed
```

The following now displays the full backup 1481553651165 of the backup chain and its successive incremental backups 1481554203288 and 1481559303348, changed to keep status.

```
-bash-4.2$ bart SHOW-BACKUPS -s acctq
SERVER NAME BACKUP ID
                             ... BACKUP PARENT
                                                  BACKUP TIME
... STATUS
acctq
             1481559303348
                             ... 1481554203288
                                                  2016-12-12 11:15:03 EST
... keep
             1481554203288
                             ... 1481553651165
                                                  2016-12-12 09:50:03 EST
acctg
... keep
             1481553914533
                             ... 1481553088053
                                                  2016-12-12 09:45:14 EST
acctg
... obsolete
                             ... none
                                                  2016-12-12 09:40:51 EST
             1481553651165
acctq
... keep
                              ... 1481552078404
                                                  2016-12-12 09:31:28 EST
acctg
             1481553088053
... obsolete
                                                  2016-12-12 09:14:39 EST
acctq
             1481552078404
                              ... none
... obsolete
```

Finally, the MANAGE subcommand with the -d option is used to delete the obsolete backup chain.

```
-bash-4.2$ bart MANAGE -s acctg -d
INFO: removing all obsolete backups of server 'acctg'
INFO: removing obsolete backup '1481552078404'
INFO: 7 WAL file(s) will be removed
INFO: 2 incremental(s) of backup '1481552078404' will be removed
INFO: removing obsolete incremental backup '1481553914533'
```

Only the backup chain with the keep status remains as shown by the following.

```
-bash-4.2$ bart SHOW-BACKUPS -s acctq
                              ... BACKUP PARENT
SERVER NAME
               BACKUP ID
                                                   BACKUP TIME
... STATUS
               1481559303348 ... 1481554203288
                                                   2016-12-12 11:15:03 EST
acctg
... keep
               1481554203288 ... 1481553651165
                                                   2016-12-12 09:50:03 EST
acctg
... keep
                                                   2016-12-12 09:40:51 EST
               1481553651165 ... none
acctg
... keep
```

3.3 Restoring an Incremental Backup

Restoring an incremental backup may require additional setup steps depending upon the host on which the incremental backup is to be restored. For more information, see the *Restoring an Incremental Backup* section of the *EDB Postgres Backup and Recovery User Guide* available at:

https://www.enterprisedb.com/edb-docs/

This section provides an example of creating backup chains and then restoring an incremental backup.

Creating a Backup Chain

A *backup chain* is the set of backups consisting of a full backup and all of its successive incremental backups. Tracing back on the parent backups of all incremental backups in the chain eventually leads back to that single, full backup.

In the following example, the allow_incremental_backups parameter is set to enabled in the BART configuration file to permit incremental backups on the listed database server:

```
[BART]
```

```
bart_host= enterprisedb@192.168.2.27
backup_path = /opt/backup
pg_basebackup_path = /usr/edb/as11/bin/pg_basebackup
logfile = /tmp/bart.log
scanner_logfile = /tmp/bart_scanner.log

[ACCTG]

host = 127.0.0.1
port = 5445
user = enterprisedb
cluster_owner = enterprisedb
allow_incremental_backups = enabled
description = "Accounting"
```

After the database server has been started with WAL archiving enabled to the BART backup catalog, the WAL scanner is started:

```
-bash-4.2$ bart-scanner --daemon
```

First, a full backup is taken.

```
-bash-4.2$ bart BACKUP -s acctg --backup-name full 1
INFO: creating backup for server 'acctg'
INFO: backup identifier: '1490649204327'\
63364/63364 kB (100%), 1/1 tablespace
INFO: backup completed successfully
INFO: backup checksum: aae27d4a7c09dffc82f423221154db7e of base.tar
INFO:
BACKUP DETAILS:
BACKUP STATUS: active
BACKUP IDENTIFIER: 1490649204327
BACKUP NAME: full 1
BACKUP PARENT: none
BACKUP LOCATION: /opt/backup/acctg/1490649204327
BACKUP SIZE: 61.88 MB
BACKUP FORMAT: tar
BACKUP TIMEZONE: US/Eastern
XLOG METHOD: fetch
BACKUP CHECKSUM(s): 1
ChkSum File
aae27d4a7c09dffc82f423221154db7e base.tar
TABLESPACE(s): 0
START WAL LOCATION: 0000001000000000000000
BACKUP METHOD: streamed
BACKUP FROM: master
START TIME: 2017-03-27 17:13:24 EDT
STOP TIME: 2017-03-27 17:13:25 EDT
TOTAL DURATION: 1 sec(s)
```

A series of incremental backup are taken. The first incremental backup specifies the full backup as the parent. Each successive incremental backup then uses the preceding incremental backup as its parent.

```
-bash-4.2$ bart BACKUP -s acctq -F p --parent full 1 --backup-name
incr 1-a
INFO: creating incremental backup for server 'acctg'
INFO: checking mbm files /opt/backup/acctg/archived wals
INFO: new backup identifier generated 1490649255649
INFO: reading directory /opt/backup/acctg/archived wals
INFO: all files processed
NOTICE: pg stop backup complete, all required WAL segments have been
archived
INFO: incremental backup completed successfully
INFO:
BACKUP DETAILS:
BACKUP STATUS: active
BACKUP IDENTIFIER: 1490649255649
BACKUP NAME: incr 1-a
BACKUP PARENT: 1490649204327
BACKUP LOCATION: /opt/backup/acctg/1490649255649
BACKUP SIZE: 16.56 MB
BACKUP FORMAT: plain
BACKUP TIMEZONE: US/Eastern
XLOG METHOD: fetch
BACKUP CHECKSUM(s): 0
TABLESPACE(s): 0
START WAL LOCATION: 00000010000000000000010
STOP WAL LOCATION: 0000001000000000000010
BACKUP METHOD: pg start backup
BACKUP FROM: master
START TIME: 2017-03-27 17:14:15 EDT
STOP TIME: 2017-03-27 17:14:16 EDT
TOTAL DURATION: 1 sec(s)
-bash-4.2$ bart BACKUP -s acctg -F p --parent incr_1-a --backup-name
incr 1-b
INFO: creating incremental backup for server 'acctg'
INFO: checking mbm files /opt/backup/acctg/archived wals
INFO: new backup identifier generated 1490649336845
INFO: reading directory /opt/backup/acctg/archived wals
INFO: all files processed
NOTICE: pg stop backup complete, all required WAL segments have been
archived
INFO: incremental backup completed successfully
-bash-4.2$ bart BACKUP -s acctg -F p --parent incr 1-b --backup-name
incr 1-c
INFO: creating incremental backup for server 'acctg'
INFO: checking mbm files /opt/backup/acctg/archived wals
INFO: new backup identifier generated 1490649414316
INFO: reading directory /opt/backup/acctg/archived wals
INFO: all files processed
NOTICE: pg stop backup complete, all required WAL segments have been
archived
```

```
INFO: incremental backup completed successfully
.
.
.
```

The following output of the SHOW-BACKUPS subcommand lists the backup chain, which are backups full_1, incr 1-a, incr 1-b, and incr 1-c.

```
-bash-4.2$ bart SHOW-BACKUPS -s acctg

SERVER NAME BACKUP ID BACKUP NAME BACKUP PARENT BACKUP TIME ...

acctg 1490649414316 incr_1-c incr_1-b 2017-03-27 17:16:55 ...

acctg 1490649336845 incr_1-b incr_1-a 2017-03-27 17:15:37 ...

acctg 1490649255649 incr_1-a full_1 2017-03-27 17:14:16 ...

acctg 1490649204327 full_1 none 2017-03-27 17:13:25 ...
```

Note

For the full backup full_1, the BACKUP PARENT field contains none. For each incremental backup, the BACKUP PARENT field contains the backup identifier or name of its parent backup.

A second backup chain is created in the same manner with the BACKUP subcommand. The following example shows the addition of the resulting, second backup chain consisting of full backup full_2 and incremental backups incr_2-a and incr_2-b.

-bash-4.2\$ bart SHOW-BACKUPS -s acctg							
SERVER NAME	BACKUP ID	BACKUP NAME	BACKUP PARENT	BACKUP TIME			
acctg	1490649605607	incr_2-b	incr_2-a	2017-03-27 17:20:06			
acctg	1490649587702	incr_2-a	full_2	2017-03-27 17:19:48			
acctg	1490649528633	full_2	none	2017-03-27 17:18:49			
acctg	1490649414316	incr_1-c	incr_1-b	2017-03-27 17:16:55			
acctg	1490649336845	incr_1-b	incr_1-a	2017-03-27 17:15:37			
acctg	1490649255649	incr_1-a	full_1	2017-03-27 17:14:16			
acctg	1490649204327	full_1	none	2017-03-27 17:13:25			
• • •							

The following additional incremental backups starting with incr_1-b-1, which designates incr_1-b as the parent, results in the forking from that backup into a second line of backups in the chain consisting of full_1, incr_1-a, incr_1-b, incr_1-b-1, incr_1-b-2, and incr_1-b-3 as shown in the following list:

-bash-4.2\$ bart SHOW-BACKUPS -s acctg							
SERVER NAME	BACKUP ID	BACKUP NAME	BACKUP PARENT	BACKUP TIME			
acctq	1490649791430	incr 1-b-3	incr 1-b-2	2017-03-27 17:23:12			
•••	1150015,51100		1.101_1 2 2	2017 00 27 17 20 12			
acctg	1490649763929	incr_1-b-2	incr_1-b-1	2017-03-27 17:22:44			
•••	1490649731672	inam 1 h 1	inam 1 h	2017-03-27 17:22:12			
acctg	1490649/316/2	Incr_1-b-1	incr_1-b	2017-03-27 17:22:12			
acctg	1490649605607	incr_2-b	incr_2-a	2017-03-27 17:20:06			
•••	140064050550		6 11 0	0015 00 05 15 10 40			
acctg	1490649587702	incr_2-a	full_2	2017-03-27 17:19:48			
acctg	1490649528633	full_2	none	2017-03-27 17:18:49			
		_					

acctg	1490649414316 inc	cr_1-c	incr_1-b	2017-03-27 17:3	16:55
acctg	1490649336845 inc	cr_1-b	incr_1-a	2017-03-27 17:	L5 : 37
acctg	1490649255649 inc	cr_1-a :	full_1	2017-03-27 17:	14:16
acctg	1490649204327 ful	11_1	none	2017-03-27 17:3	13:25

Restoring an Incremental Backup

Restoring an incremental backup is done with the **RESTORE** subcommand in the same manner as for restoring a full backup. Specify the backup identifier or backup name of the incremental backup to be restored as shown in the following example.

```
-bash-4.2$ bart RESTORE -s acctg -p /opt/restore -i incr_1-b
INFO: restoring incremental backup 'incr_1-b' of server 'acctg'
INFO: base backup restored
INFO: archiving is disabled
INFO: permissions set on $PGDATA
INFO: incremental restore completed successfully
```

Restoring incremental backup incr_1-b as shown by the preceding example results in the restoration of full backup full 1, then incremental backups incr 1-a and finally, incr 1-b.

3.4 A Sample BART System with Local and Remote Database Servers

This section describes a sample BART managed backup and recovery system consisting of both local and remote database servers. The complete steps to configure and operate the system are provided.

For detailed information about configuring a BART system, see the *EDB Postgres Backup and Recovery Installation and Upgrade Guide* and for information about the operational procedures and BART subcommands, see the *EDB Postgres Backup and Recovery User Guide* available at:

https://www.enterprisedb.com/edb-docs/

The environment for this sample system is as follows:

- BART on host 192.168.2.22 running with BART user account enterprisedb
- Local Advanced Server on host 192.168.2.22 running with user account enterprisedb
- Remote Advanced Server on host 192.168.2.24 running with user account enterprisedb
- Remote PostgreSQL server on host 192.168.2.24 running with user account postgres

passwordless SSH/SCP connections are required between the following:

- BART on host 192.168.2.22 and the local Advanced Server on the same host 192.168.2.22
- BART on host 192.168.2.22 and the remote Advanced Server on host 192.168.2.24
- BART on host 192.168.2.22 and the remote PostgreSQL server on host 192.168.2.24

The following sections demonstrate configuring and taking full backups only. To support incremental backups as well, enable the allow_incremental_backups parameter for the desired database servers and use the wall scanner program.

- The BART Configuration File shows the settings used in the BART configuration file.
- Establishing SSH/SCP Passwordless Connections <establishing_ssh/scp_passwordless_connections> provides an example of how to establish an SSH/SCP passwordless connection.
- Configuring a Replication Database User provides an example of how to configure the replication database user.
- WAL Archiving Configuration Parameters provides an example of how to configure WAL archiving.
- Creating the BART Backup Catalog provides information about creating a BART Backup Catalog.
- Starting the Database Servers with WAL Archiving provides example of starting the database servers with WAL archiving.
- Taking a Full Backup illustrates taking the first full backup of the database servers.
- Using Point-In-Time Recovery demonstrates the point-in-time recovery operation on the remote PostgreSQL database server.

The BART Configuration File

The following code snippet shows the settings used in the BART configuration file for the examples that follow:

```
[BART]
bart host= enterprisedb@192.168.2.22
backup path = /opt/backup
pg basebackup path = /usr/edb/as11/bin/pg basebackup
retention policy = 6 BACKUPS
logfile = /tmp/bart.log
scanner logfile = /tmp/bart scanner.log
[ACCTG]
host = 127.0.0.1
port = 5444
user = enterprisedb
cluster owner = enterprisedb
backup name = acctg %year-%month-%dayT%hour:%minute
archive command = 'cp %p %a/%f'
description = "Accounting"
[MKTG]
host = 192.168.2.24
port = 5444
user = repuser
cluster owner = enterprisedb
backup name = mktg %year-%month-%dayT%hour:%minute
remote host = enterprisedb@192.168.2.24
description = "Marketing"
[HR]
host = 192.168.2.24
port = 5432
user = postgres
```

```
cluster_owner = postgres
backup_name = hr_%year-%month-%dayT%hour:%minute
remote_host = postgres@192.168.2.24
copy_wals_during_restore = enabled
description = "Human Resources"
```

Establishing SSH/SCP Passwordless Connections

This section shows how the passwordless SSH/SCP connections are established with the authorized public keys files.

Generating a Public Key File for the BART User Account

The BART user account is enterprised with the home directory of /opt/PostgresPlus/9.5AS.

To generate the public key file, first create the .ssh subdirectory in the BART user's home directory:

```
[root@localhost 9.5AS]# pwd
/opt/PostgresPlus/9.5AS
[root@localhost 9.5AS]# mkdir .ssh
[root@localhost 9.5AS]# chown enterprisedb .ssh
[root@localhost 9.5AS]# chgrp enterprisedb .ssh
[root@localhost 9.5AS]# chmod 700 .ssh
[root@localhost 9.5AS]# ls -la | grep ssh
drwx----- 2 enterprisedb enterprisedb 4096 Apr 23 13:02 .ssh
```

Make sure there are no groups or other users that can access the .ssh directory.

Now, generate the public key file:

```
[user@localhost ~]$ su - enterprisedb
Password:
-bash-4.1$ pwd
/opt/PostgresPlus/9.5AS
-bash-4.1$ ssh-keygen -t rsa
Generating public/private rsa key pair.
Enter file in which to save the key
(/opt/PostgresPlus/9.5AS/.ssh/id rsa):
Enter passphrase (empty for no passphrase):
Enter same passphrase again:
Your identification has been saved in
/opt/PostgresPlus/9.5AS/.ssh/id rsa.
Your public key has been saved in
/opt/PostgresPlus/9.5AS/.ssh/id rsa.pub.
The key fingerprint is:
de:65:34:d6:b1:d2:32:3c:b0:43:c6:a3:c0:9f:f4:64
enterprisedb@localhost.localdomain
The key's randomart image is:
+----[ RSA 2048]----+
```

```
. .+ . |
O .OE+ O O |
+ * O.X + |
+ .+ * |
S O |
. . O |
. . . |
```

The following are the resulting files. id_rsa.pub is the public key file of BART user account enterprisedb.

```
-bash-4.1$ ls -l .ssh
total 8
-rw----- 1 enterprisedb enterprisedb 1675 Apr 23 13:04 id_rsa
-rw-r--r- 1 enterprisedb enterprisedb 416 Apr 23 13:04 id_rsa.pub
```

Configuring Access between Local Advanced Server and the BART Host

Even when the Advanced Server database is on the same host as the BART user account, and the Advanced Server database cluster owner is also the BART user account (enterprised) is this case), a passwordless SSH/SCP connection must be established from the same user account to itself.

On the BART host where the public key file was just generated as shown in Generating a Public Key File for the BART User Account, create the authorized keys file by appending the public key file to any existing authorized keys file.

Log into the BART host as the BART user account and append the public key file, id_rsa.pub onto the authorized_keys file in the same .ssh directory.

```
[user@localhost ~]$ su - enterprisedb
Password:
Last login: Thu Mar 23 10:27:35 EDT 2017 on pts/0
-bash-4.2$ pwd
/opt/PostgresPlus/9.5AS
-bash-4.2$ ls -l.ssh
-rw----- 1 enterprisedb enterprisedb 1675 Mar 23 09:54 id rsa
-rw-r--r- 1 enterprisedb enterprisedb 416 Mar 23 09:54 id rsa.pub
-rw-r--r-- 1 enterprisedb enterprisedb 345 Mar 23 10:05 known hosts
-bash-4.2$ cat ~/.ssh/id rsa.pub >> ~/.ssh/authorized keys
-bash-4.2$ ls -l.ssh
total 16
-rw-rw-r-- 1 enterprisedb enterprisedb 416 Mar 23 10:33 authorized keys
-rw----- 1 enterprisedb enterprisedb 1675 Mar 23 09:54 id_rsa
-rw-r--r-- 1 enterprisedb enterprisedb 416 Mar 23 09:54 id rsa.pub
-rw-r--r-- 1 enterprisedb enterprisedb 345 Mar 23 10:05 known hosts
```

The authorized keys file must have file permission 600 as set by the following chmod 600 command,

otherwise the passwordless connection fails:

```
-bash-4.2$ chmod 600 ~/.ssh/authorized_keys
-bash-4.2$ ls -l .ssh
total 16
-rw----- 1 enterprisedb enterprisedb 416 Mar 23 10:33 authorized_keys
-rw----- 1 enterprisedb enterprisedb 1675 Mar 23 09:54 id_rsa
-rw-r--r-- 1 enterprisedb enterprisedb 416 Mar 23 09:54 id_rsa.pub
-rw-r--r-- 1 enterprisedb enterprisedb 345 Mar 23 10:05 known_hosts
```

Test the passwordless connection. Use the ssh command to verify that you can access the same user account as you are currently logged in as (enterprisedb) without being prompted for a password:

```
-bash-4.2$ ssh enterprisedb@127.0.0.1
Last login: Thu Mar 23 10:27:50 2017
-bash-4.2$ exit
logout
Connection to 127.0.0.1 closed.
```

Configuring Access from Remote Advanced Server to BART Host

On the remote host 192.168.2.24, create the public key file for the remote database server user account, enterprisedb, for access to the BART user account, enterprisedb, on the BART host 192.168.2.22.

Create the .ssh directory for user account enterprisedb on the remote host:

```
[root@localhost 9.5AS]# pwd
/opt/PostgresPlus/9.5AS
[root@localhost 9.5AS]# mkdir .ssh
[root@localhost 9.5AS]# chown enterprisedb .ssh
[root@localhost 9.5AS]# chgrp enterprisedb .ssh
[root@localhost 9.5AS]# chmod 700 .ssh
[root@localhost 9.5AS]# ls -la | grep ssh
drwx----- 2 enterprisedb enterprisedb 4096 Apr 23 13:08 .ssh
```

Generate the public key file on the remote host for user account enterprisedb:

```
[user@localhost ~]$ su - enterprisedb
Password:
-bash-4.1$ ssh-keygen -t rsa
Generating public/private rsa key pair.
Enter file in which to save the key
(/opt/PostgresPlus/9.5AS/.ssh/id_rsa):
Enter passphrase (empty for no passphrase):
Enter same passphrase again:
Your identification has been saved in
/opt/PostgresPlus/9.5AS/.ssh/id_rsa.
Your public key has been saved in
/opt/PostgresPlus/9.5AS/.ssh/id_rsa.pub.
The key fingerprint is:
15:27:1e:1e:61:4b:48:66:67:0b:b2:be:fc:ea:ea:e6
```

Copy the generated public key file, id_rsa.pub, to the BART user account, enterprisedb, on the BART host, 192.168.2.22:

```
-bash-4.1$ scp ~/.ssh/id_rsa.pub enterprisedb@192.168.2.22:/tmp/tmp.pub
The authenticity of host '192.168.2.22 (192.168.2.22)' can't be
established.
RSA key fingerprint is b8:a9:97:31:79:16:b8:2b:b0:60:5a:91:38:d7:68:22.
Are you sure you want to continue connecting (yes/no)? yes
Warning: Permanently added '192.168.2.22' (RSA) to the list of known hosts.
enterprisedb@192.168.2.22's password:
id_rsa.pub
```

Log into the BART host as the BART user account and append the temporary public key file, /tmp/tmp.pub onto the authorized keys file owned by the BART user account.

```
-bash-4.1$ ssh enterprisedb@192.168.2.22
enterprisedb@192.168.2.22's password:
Last login: Tue Apr 21 17:03:24 2015 from 192.168.2.22
-bash-4.1$ pwd
/opt/PostgresPlus/9.5AS
-bash-4.1$ cat /tmp/tmp.pub >> ~/.ssh/authorized_keys
-bash-4.1$ ls -l .ssh
total 12
-rw-rw-r-- 1 enterprisedb enterprisedb 416 Apr 23 13:15 authorized_keys
-rw----- 1 enterprisedb enterprisedb 1675 Apr 23 13:04 id_rsa
-rw-r---- 1 enterprisedb enterprisedb 416 Apr 23 13:04 id_rsa.pub
```

The authorized_keys file must have file permission 600 as set by the following chmod 600 command, otherwise the passwordless connection fails:

```
-bash-4.1$ chmod 600 ~/.ssh/authorized_keys
-bash-4.1$ ls -l .ssh
total 12
-rw----- 1 enterprisedb enterprisedb 416 Apr 23 13:15 authorized_keys
-rw----- 1 enterprisedb enterprisedb 1675 Apr 23 13:04 id_rsa
-rw-r--r- 1 enterprisedb enterprisedb 416 Apr 23 13:04 id_rsa.pub
-bash-4.1$ rm /tmp/tmp.pub
-bash-4.1$ exit
logout
```

```
Connection to 192.168.2.22 closed.
```

Test the passwordless connection. From the remote host, verify that you can log into the BART host with the BART user account without being prompted for a password:

```
-bash-4.1$ ssh enterprisedb@192.168.2.22
Last login: Thu Apr 23 13:14:48 2015 from 192.168.2.24
-bash-4.1$ exit
logout
Connection to 192.168.2.22 closed.
```

Configuring Access from BART Host to Remote Advanced Server

On the BART host 192.168.2.22, copy the public key file for the BART user account, enterprisedb, for access to the remote database server user account, enterprisedb, on the remote host 192.168.2.24.

The following lists the current SSH keys files in the BART user's .ssh directory on the BART host:

```
[user@localhost ~]$ su - enterprisedb
Password:
-bash-4.1$ pwd
/opt/PostgresPlus/9.5AS
-bash-4.1$ ls -l .ssh
total 12
-rw----- 1 enterprisedb enterprisedb 416 Apr 23 13:15 authorized_keys
-rw----- 1 enterprisedb enterprisedb 1675 Apr 23 13:04 id_rsa
-rw-r--r-- 1 enterprisedb enterprisedb 416 Apr 23 13:04 id_rsa.pub
```

The public key file, id_rsa.pub, for BART user account enterprisedb on the BART host was generated in Generating a Public Key File for the BART User Account Section, and is now copied to the remote Advanced Server host on 192.168.2.24:

```
-bash-4.1$ scp ~/.ssh/id_rsa.pub enterprisedb@192.168.2.24:/tmp/tmp.pub
The authenticity of host '192.168.2.24 (192.168.2.24)' can't be
established.
RSA key fingerprint is 59:41:fb:0c:ae:64:3d:3f:a2:d9:90:95:cf:2c:99:f2.
Are you sure you want to continue connecting (yes/no)? yes
Warning: Permanently added '192.168.2.24' (RSA) to the list of known
hosts.
enterprisedb@192.168.2.24's password:
id_rsa.pub
```

Log into the enterprisedb user account on the remote host and copy the public key file onto the authorized keys file of the remote enterprisedb user account under its .ssh directory:

```
-bash-4.1$ ssh enterprisedb@192.168.2.24
enterprisedb@192.168.2.24's password:
Last login: Tue Apr 21 09:53:18 2015 from 192.168.2.22
-bash-4.1$ pwd
/opt/PostgresPlus/9.5AS
-bash-4.1$ ls -l .ssh
```

```
total 12
-rw----- 1 enterprisedb enterprisedb 1675 Apr 23 13:11 id_rsa
-rw-r--r- 1 enterprisedb enterprisedb 416 Apr 23 13:11 id_rsa.pub
-rw-r--r- 1 enterprisedb enterprisedb 394 Apr 23 13:12 known_hosts
-bash-4.1$ cat /tmp/tmp.pub >> ~/.ssh/authorized_keys
```

Adjust the file permission on authorized keys.

```
-bash-4.1$ chmod 600 ~/.ssh/authorized_keys
-bash-4.1$ ls -l .ssh

total 16
-rw----- 1 enterprisedb enterprisedb 416 Apr 23 13:26 authorized_keys
-rw----- 1 enterprisedb enterprisedb 1675 Apr 23 13:11 id_rsa
-rw-r--r-- 1 enterprisedb enterprisedb 416 Apr 23 13:11 id_rsa.pub
-rw-r--r-- 1 enterprisedb enterprisedb 394 Apr 23 13:12 known_hosts
-bash-4.1$ rm /tmp/tmp.pub
-bash-4.1$ exit
logout
Connection to 192.168.2.24 closed.
```

While logged into the BART host, test the passwordless connection from the BART host to the remote Advanced Server host.

```
-bash-4.1$ ssh enterprisedb@192.168.2.24

Last login: Thu Apr 23 13:25:53 2015 from 192.168.2.22

-bash-4.1$ exit

logout

Connection to 192.168.2.24 closed.
```

Configuring Access from Remote PostgreSQL to BART Host

On the remote host 192.168.2.24, create the public key file for the remote database server user account, postgres, for access to the BART user account, enterprisedb, on the BART host 192.168.2.22.

Create the .ssh directory for user account postgres on the remote host:

```
[root@localhost 9.5]# cd /opt/PostgreSQL/9.5
[root@localhost 9.5]# mkdir .ssh
[root@localhost 9.5]# chown postgres .ssh
[root@localhost 9.5]# chgrp postgres .ssh
[root@localhost 9.5]# chmod 700 .ssh
[root@localhost 9.5]# ls -la | grep ssh
drwx----- 2 postgres postgres 4096 Apr 23 13:32 .ssh
```

Create and copy the generated public key file, id_rsa.pub, to the BART user account, enterprisedb, on the BART host, 192.168.2.22:

```
[user@localhost ~]$ su - postgres
Password:
-bash-4.1$ pwd
/opt/PostgreSQL/9.5
```

```
-bash-4.1$ ssh-keygen -t rsa
Generating public/private rsa key pair.
Enter file in which to save the key (/opt/PostgreSQL/9.5/.ssh/id_rsa):
Enter passphrase (empty for no passphrase):
Enter same passphrase again:
Your identification has been saved in /opt/PostgreSQL/9.5/.ssh/id rsa.
Your public key has been saved in /opt/PostgreSQL/9.5/.ssh/id_rsa.pub.
The key fingerprint is:
1f:f8:76:d6:fc:a5:la:c5:5a:66:66:01:d0:a0:ca:ba
postgres@localhost.localdomain
The key's randomart image is:
+--[ RSA 2048]----+
          0+.
            . .
      . . .
      os.
             0
        0.0
        + = 0 .
         . 0 . 0.
     Ε
-bash-4.1$ ls -l.ssh
total 8
-rw----- 1 postgres postgres 1671 Apr 23 13:36 id rsa
-rw-r--r- 1 postgres postgres 412 Apr 23 13:36 id rsa.pub
-bash-4.1$ scp ~/.ssh/id rsa.pub enterprisedb@192.168.2.22:/tmp/tmp.pub
The authenticity of host '192.168.2.22 (192.168.2.22)' can't be
established.
RSA key fingerprint is b8:a9:97:31:79:16:b8:2b:b0:60:5a:91:38:d7:68:22.
Are you sure you want to continue connecting (yes/no)? yes
Warning: Permanently added '192.168.2.22' (RSA) to the list of known
hosts.
enterprisedb@192.168.2.22's password:
id rsa.pub
```

Log into the BART host as the BART user account and append the temporary public key file, /tmp/tmp.pub, onto the authorized keys file owned by the BART user account.

```
-bash-4.1$ ssh enterprisedb@192.168.2.22
enterprisedb@192.168.2.22's password:

Last login: Thu Apr 23 13:19:25 2015 from 192.168.2.24
-bash-4.1$ pwd
/opt/PostgresPlus/9.5AS
-bash-4.1$ cat /tmp/tmp.pub >> ~/.ssh/authorized_keys
-bash-4.1$ ls -l .ssh
total 16
-rw------ l enterprisedb enterprisedb 828 Apr 23 13:40 authorized_keys
-rw------ l enterprisedb enterprisedb 1675 Apr 23 13:04 id_rsa
-rw-r--r- l enterprisedb enterprisedb 416 Apr 23 13:04 id_rsa.pub
-rw-r--r-- l enterprisedb enterprisedb 394 Apr 23 13:24 known_hosts
-bash-4.1$ rm /tmp/tmp.pub
-bash-4.1$ exit
```

```
logout
Connection to 192.168.2.22 closed.
```

Make sure the authorized_keys file has file permission 600 as shown, otherwise the passwordless connection fails. Test the passwordless connection. From the remote host, while logged in as user account postgres, verify that you can log into the BART host with the BART user account without being prompted for a password:

```
-bash-4.1$ pwd
/opt/PostgreSQL/9.5
-bash-4.1$ ssh enterprisedb@192.168.2.22
Last login: Thu Apr 23 13:40:10 2015 from 192.168.2.24
-bash-4.1$ exit
logout
Connection to 192.168.2.22 closed.
```

Configuring Access from the BART Host to Remote PostgreSQL

On the BART host 192.168.2.22, copy the public key file for the BART user account, enterprisedb, for access to the remote database server user account, postgres, on the remote host 192.168.2.24.

The following lists the current SSH keys files in the BART user's .ssh directory on the BART host:

```
[user@localhost ~]$ su - enterprisedb
Password:
-bash-4.1$ ls -l .ssh
total 16
-rw----- 1 enterprisedb enterprisedb 828 Apr 23 13:40 authorized_keys
-rw----- 1 enterprisedb enterprisedb 1675 Apr 23 13:04 id_rsa
-rw-r--r- 1 enterprisedb enterprisedb 416 Apr 23 13:04 id_rsa.pub
-rw-r--r- 1 enterprisedb enterprisedb 394 Apr 23 13:24 known_hosts
```

The public key file, id_rsa.pub, for BART user account enterprisedb on the BART host was generated in Generating a Public Key File for the BART User Account Section, and is now copied to the remote PostgreSQL host on 192.168.2.24:

```
-bash-4.1$ scp ~/.ssh/id_rsa.pub postgres@192.168.2.24:/tmp/tmp.pub postgres@192.168.2.24's password: id_rsa.pub
```

Log into the **postgres** user account on the remote host and copy the public key file onto the **authorized** keys file of **postgres** under its **.ssh** directory:

```
-bash-4.1$ ssh postgres@192.168.2.24
postgres@192.168.2.24's password:
Last login: Mon Jan 26 18:08:36 2015 from 192.168.2.19
-bash-4.1$ pwd
/opt/PostgreSQL/9.5
-bash-4.1$ cat /tmp/tmp.pub >> ~/.ssh/authorized_keys
```

Adjust the file permissions on authorized keys.

```
-bash-4.1$ ls -l.ssh
total 16
-rw-rw-r-- 1 postgres postgres 416 Apr 23 13:52 authorized keys
-rw----- 1 postgres postgres 1671 Apr 23 13:36 id rsa
-rw-r--r-- 1 postgres postgres 412 Apr 23 13:36 id rsa.pub
-rw-r--r-- 1 postgres postgres 394 Apr 23 13:36 known hosts
-bash-4.1$ chmod 600 ~/.ssh/authorized keys
-bash-4.1$ ls -l.ssh
total 16
-rw----- 1 postgres postgres 416 Apr 23 13:52 authorized keys
-rw----- 1 postgres postgres 1671 Apr 23 13:36 id rsa
-rw-r--r-- 1 postgres postgres 412 Apr 23 13:36 id rsa.pub
-rw-r--r-- 1 postgres postgres 394 Apr 23 13:36 known_hosts
-bash-4.1$ rm /tmp/tmp.pub
-bash-4.1$ exit
logout
Connection to 192.168.2.24 closed.
```

Test the passwordless connection from the BART host to the remote PostgreSQL host.

```
[user@localhost ~]$ su - enterprisedb
Password:
-bash-4.1$ ssh postgres@192.168.2.24
Last login: Thu Apr 23 13:52:25 2015 from 192.168.2.22
-bash-4.1$ exit
logout
Connection to 192.168.2.24 closed.
```

Configuring a Replication Database User

This section shows how the replication database user is established.

All database servers must use a superuser as the replication database user.

The replication database user for each database server is specified by the user parameter in the BART configuration file as shown by the following:

```
[ACCTG]
host = 127.0.0.1
port = 5444
user = enterprisedb <=== Replication Database User
cluster_owner = enterprisedb
backup_name = acctg_%year-%month-%dayT%hour:%minute
archive_command = 'cp %p %a/%f'
description = "Accounting"

[MKTG]
host = 192.168.2.24
port = 5444
user = repuser <=== Replication Database User</pre>
```

```
cluster_owner = enterprisedb
backup_name = mktg_%year-%month-%dayT%hour:%minute
remote_host = enterprisedb@192.168.2.24
description = "Marketing"

[HR]

host = 192.168.2.24
port = 5432
user = postgres <=== Replication Database User
cluster_owner = enterprisedb
backup_name = hr_%year-%month-%dayT%hour:%minute
remote_host = postgres@192.168.2.24
copy_wals_during_restore = enabled
description = "Human Resources"</pre>
```

Add entries to the .pgpass file on each server to allow the BART user account to initiate a backup without being prompted for credentials. The .pgpass file is located in /opt/PostgresPlus/9.5AS/.pgpass.

```
127.0.0.1:5444:*:enterprisedb:password
192.168.2.24:5444:*:repuser:password
192.168.2.24:5432:*:postgres:password
```

For more information about using a .pgpass file, please see the PostgreSQL documentation available at:

https://www.postgresql.org/docs/current/libpq-pgpass.html

While connected to MKTG on 192.168.2.24, the following CREATE ROLE command is given to create the replication database superuser:

```
CREATE ROLE repuser WITH LOGIN SUPERUSER PASSWORD 'password';
```

The pg hba.conf file for the local Advanced Server, ACCTG is set as follows:

```
# TYPE
           DATABASE
                                USER
                                             ADDRESS
                                                              METHOD
# "local" is for Unix domain socket connections only
local
             all
                                 all
                                                               md5
           local connections:
# IPv4
host
           template1
                              enterprisedb 127.0.0.1/32
                                                               md5
                              enterprisedb 127.0.0.1/32
host
           edb
                                                               md5
#host
           all
                              all
                                             127.0.0.1/32
                                                               md5
# IPv6 local connections:
                              all
                                             ::1/128
host
# Allow replication connections from localhost, by a user with the
# replication privilege.
#local
           replication
                              enterprisedb
                                                               md5
host
           replication
                              enterprisedb 127.0.0.1/32
                                                               md5
```

The pg hba.conf file for the remote Advanced Server, MKTG is set as follows:

```
# TYPE DATABASE USER ADDRESS METHOD
# "local" is for Unix domain socket connections only
local all md5
```

```
# IPv4 local connections:
           template1
                                             192.168.2.22/32
                                                                   md5
host
                               repuser
host
           all
                               enterprisedb 127.0.0.1/32
                                                                   md5
                                             127.0.0.1/32
#host
           all
                               all
                                                                   md5
# IPv6 local connections:
host
           all
                               all
                                              ::1/128
                                                                   md5
# Allow replication connections from localhost, by a user with the
# replication privilege.
         replication
#local
                               enterprisedb
                                                                   md5
         replication
host
                               repuser
                                              192.168.2.22/32
                                                                   md5
```

The pg hba.conf file for the remote PostgreSQL server, HR is set as follows:

```
# TYPE
           DATABASE
                                            ADDRESS
                               USER
                                                                   METHOD
# "local" is for Unix domain socket connections only
local
           all
                               all
                                                                     md5
# IPv4 local connections:
                                            192.168.2.22/32
host
           template1
                               postgres
                                                                     md5
                                            127.0.0.1/32
host
           all
                               all
                                                                     md5
# IPv6 local connections:
host
           all
                               all
                                            ::1/128
                                                                     md5
# Allow replication connections from localhost, by a user with the
q# replication privilege.
#local
           replication
                               postgres
                                                                     md5
                                            192.168.2.22/32
host
           replication
                                                                     md5
                               postgres
```

WAL Archiving Configuration Parameters

Use the following parameters in the postgresql.conf file to enable WAL archiving. The postgresql.conf file for the local Advanced Server, ACCTG is set as follows:

When the INIT subcommand is invoked, the Postgres archive_command configuration parameter in the postgresql.auto.conf file will be set based on the BART archive_command parameter located in the BART configuration file.

Note

If the Postgres archive_command is already set, to prevent the archive_command from re-setting invoke the INIT subcommand with the -- no-configure option. For details, see INIT section.

```
[BART]
bart_host= enterprisedb@192.168.2.22
backup_path = /opt/backup
pg_basebackup_path = /usr/edb/as11/bin/pg_basebackup
retention_policy = 6 BACKUPS
logfile = /tmp/bart.log
scanner_logfile = /tmp/bart_scanner.log

[ACCTG]
host = 127.0.0.1
port = 5444
user = enterprisedb
cluster_owner = enterprisedb
backup_name = acctg_%year-%month-%dayT%hour:%minute
archive_command = 'cp %p %a/%f'
description = "Accounting"
```

When the INIT subcommand is invoked, the postgresql.auto.conf file contains the following:

```
# Do not edit this file manually!
# It will be overwritten by ALTER SYSTEM command.
archive_command = 'cp %p /opt/backup/acctg/archived_wals/%f'
```

The archive_command uses the cp command instead of scp since the BART backup catalog is local to this database cluster and the BART user account (owning the backup catalog, enterprisedb), is the same user account running Advanced Server. The result is that there is no directory permission conflict during the archive operation.

The postgresql.conf file for the remote Advanced Server, MKTG is set as follows:

When the INIT subcommand is invoked, the Postgres archive_command configuration parameter in the postgresql.auto.conf file will be set by the default BART format of the BART archive_command parameter (since it is not explicitly set for this database server in the BART configuration file).

```
[BART]
bart_host= enterprisedb@192.168.2.22
backup_path = /opt/backup
pg_basebackup_path = /usr/edb/as11/bin/pg_basebackup
retention_policy = 6 BACKUPS
logfile = /tmp/bart.log
scanner_logfile = /tmp/bart_scanner.log
.
```

```
[MKTG]

host = 192.168.2.24

port = 5444

user = repuser

cluster_owner = enterprisedb

backup_name = mktg_%year-%month-%dayT%hour:%minute

remote_host = enterprisedb@192.168.2.24

description = "Marketing"
```

The default, BART archive command format is the following:

```
archive_command = 'scp %p %h:%a/%f'
```

The postgresql.auto.conf file contains the following after the INIT subcommand is invoked:

```
# Do not edit this file manually!
# It will be overwritten by ALTER SYSTEM command.
archive_command = 'scp %p
enterprisedb@192.168.2.22:/opt/backup/hr/archived_wals/%f'
```

The archive_command uses the scp command since the BART backup catalog is remote relative to this database cluster. The BART user account, enterprisedb, is specified on the scp command since this is the user account owning the BART backup catalog where the archived WAL files are to be copied. The result is that there is no directory permission conflict during the archive operation.

The postgresql.conf file for the remote PostgreSQL server, HR is set as follows:

When the INIT subcommand is invoked, the Postgres archive_command configuration parameter in the postgresql.auto.conf file will be set by the default BART format of the BART archive_command parameter (since it is not explicitly set for this database server in the BART configuration file).

```
bart_host= enterprisedb@192.168.2.22
backup_path = /opt/backup
pg_basebackup_path = /usr/edb/as11/bin/pg_basebackup
retention_policy = 6 BACKUPS
logfile = /tmp/bart.log
scanner_logfile = /tmp/bart_scanner.log
.
```

```
[HR]
host = 192.168.2.24
port = 5432
user = postgres
cluster_owner = postgres
backup_name = hr_%year-%month-%dayT%hour:%minute
remote_host = postgres@192.168.2.24
copy_wals_during_restore = enabled
description = "Human Resources"
```

The default, BART archive command format is the following:

```
archive_command = 'scp %p %h:%a/%f'
```

The postgresql.auto.conf file contains the following after the INIT subcommand is invoked:

```
# Do not edit this file manually!
# It will be overwritten by ALTER SYSTEM command.
archive_command = 'scp %p
enterprisedb@192.168.2.22:/opt/backup/hr/archived_wals/%f'
```

The archive_command uses the scp command since the BART backup catalog is remote relative to this database cluster. The BART user account, enterprisedb, is specified on the scp command since this is the user account owning the BART backup catalog where the archived WAL files are to be copied. The result is that there is no directory permission conflict during the archive operation.

Creating the BART Backup Catalog (backup_path)

Create the directory specified by the backup path configuration parameter.

```
[BART]
bart_host= enterprisedb@192.168.2.22
backup_path = /opt/backup
pg_basebackup_path = /usr/edb/as11/bin/pg_basebackup
retention_policy = 6 BACKUPS
logfile = /tmp/bart.log
scanner_logfile = /tmp/bart_scanner.log
```

Make sure it is owned by the BART user account:

```
[root@localhost opt]# pwd
/opt
[root@localhost opt]# mkdir backup
[root@localhost opt]# chown enterprisedb backup
[root@localhost opt]# chgrp enterprisedb backup
[root@localhost opt]# chmod 700 backup
[root@localhost opt]# ls -l | grep backup
drwx----- 2 enterprisedb enterprisedb 4096 Apr 23 15:36 backup
```

Use the BART INIT subcommand to complete the directory structure and set the Postgres archive_command configuration parameter.

Note

Before invoking any BART subcommands, set up a profile under the BART user account's home directory to set the LD LIBRARY PATH and PATH environment variables.

For more information regarding setting this variable, see the Configuring the BART host section of *EDB Postgres Backup and Recovery Installation and Upgrade Guide* available at:

https://www.enterprisedb.com/edb-docs/

The -o option is specified with the INIT subcommand to force the setting of the Postgres archive_command configuration parameter when archive_mode is off or if the Postgres archive_command parameter is already set and needs to be overridden.

```
[user@localhost ~]$ su - enterprisedb
Password:
-bash-4.1$ bart INIT -o
INFO: setting archive_command for server 'acctg'
WARNING: archive_command is set. server restart is required
INFO: setting archive_command for server 'hr'
WARNING: archive_command is set. server restart is required
INFO: setting archive_command for server 'mktg'
WARNING: archive_command is set. server restart is required
```

The BART SHOW-SERVERS subcommand displays the following:

```
-bash-4.1$ bart SHOW-SERVERS
SERVER NAME :
                            acctq
BACKUP FRIENDLY NAME:
                            acctg %year-%month-%dayT%hour:%minute
HOST NAME:
                            127.0.0.1
USER NAME:
                            enterprisedb
                            5444
PORT:
REMOTE HOST :
RETENTION POLICY:
                            6 Backups
DISK UTILIZATION:
                            0.00 bytes
NUMBER OF ARCHIVES:
ARCHIVE PATH:
                            /opt/backup/acctg/archived wals
                           (disabled)
ARCHIVE COMMAND:
XLOG METHOD:
                           fetch
                           disabled
WAL COMPRESSION:
TABLESPACE PATH(s):
INCREMENTAL BACKUP:
                           DISABLED
DESCRIPTION:
                           "Accounting"
SERVER NAME :
BACKUP FRIENDLY NAME:
                           hr %year-%month-%dayT%hour:%minute
HOST NAME:
                           192.168.2.24
USER NAME:
                           postgres
                           5432
PORT:
REMOTE HOST:
                           postgres@192.168.2.24
RETENTION POLICY:
                           6 Backups
DISK UTILIZATION:
                           0.00 bytes
```

```
NUMBER OF ARCHIVES:
ARCHIVE PATH :
                           /opt/backup/hr/archived wals
ARCHIVE COMMAND:
                           (disabled)
XLOG METHOD :
                           fetch
WAL COMPRESSION:
                           disabled
TABLESPACE PATH(s):
INCREMENTAL BACKUP :
                           DISABLED
DESCRIPTION:
                           "Human Resources"
SERVER NAME:
                           mktq
                           mktg %year-%month-%dayT%hour:%minute
BACKUP FRIENDLY NAME:
HOST NAME :
                           192.168.2.24
USER NAME :
                           repuser
                           5444
PORT:
REMOTE HOST :
                           enterprisedb@192.168.2.24
RETENTION POLICY:
                           6 Backups
DISK UTILIZATION:
                           0.00 bytes
NUMBER OF ARCHIVES:
ARCHIVE PATH :
                           /opt/backup/mktg/archived wals
ARCHIVE COMMAND:
                           (disabled)
XLOG METHOD:
                           fetch
                           disabled
WAL COMPRESSION:
TABLESPACE PATH(s):
INCREMENTAL BACKUP :
                           DISABLED
DESCRIPTION:
                           "Marketing"
-bash-4.1$ cd /opt/backup
-bash-4.1$ pwd
/opt/backup
-bash-4.1$ ls -1
total 12
drwxrwxr-x 3 enterprisedb enterprisedb 4096 Mar 29 13:16 acctg
drwxrwxr-x 3 enterprisedb enterprisedb 4096 Mar 29 13:16 hr
drwxrwxr-x 3 enterprisedb enterprisedb 4096 Mar 29 13:16 mktg
-bash-4.1$ ls -l acctg
total 4
drwxrwxr-x 2 enterprisedb enterprisedb 4096 Mar 29 13:16 archived wals
-bash-4.1$ ls -l hr
total 4
drwxrwxr-x 2 enterprisedb enterprisedb 4096 Mar 29 13:16 archived wals
-bash-4.1$ ls -l mktq
total 4
drwxrwxr-x 2 enterprisedb enterprisedb 4096 Mar 29 13:16 archived_wals
```

The ARCHIVE PATH field displays the full directory path to where the WAL files are copied. This directory path must match the directory path specified in the Postgres archive_command parameter of the postgresql.conf file or the postgresql.auto.conf file of each database server.

Starting the Database Servers with WAL Archiving

After the BART backup catalog directory structure has been completed, begin the archiving of WAL files from the database servers by restarting each database server. On BART host 192.168.2.22:

```
[root@localhost data]# service ppas-9.5 restart
```

On remote host 192.168.2.24:

```
[root@localhost data]# service ppas-9.5 restart
[root@localhost data]# service postgresql-9.5 restart
```

In the BART backup catalog, verify that the WAL files are archiving.

Archived WAL files may not appear very frequently depending upon how often WAL archiving is set to switch to a new segment file with the **archive timeout** parameter in your database server configuration settings.

Verify that there are no archiving-related errors in the database server log files.

Taking a Full Backup

The following code snippet shows the first full backup of the database servers.

```
-bash-4.1$ bart BACKUP -s acctg -z
INFO: creating backup for server 'acctg'
INFO: backup identifier: '1490809695281'
60776/60776 kB (100%), 1/1 tablespace
INFO: backup completed successfully
INFO: backup checksum: 37f3defb98ca88dcf05079815555dfc2 of base.tar.gz
INFO:
BACKUP DETAILS:
BACKUP STATUS: active
BACKUP IDENTIFIER: 1490809695281
BACKUP NAME: acctg 2017-03-29T13:48
BACKUP PARENT: none
BACKUP LOCATION: /opt/backup/acctg/1490809695281
BACKUP SIZE: 6.10 MB
BACKUP FORMAT: tar.qz
BACKUP TIMEZONE: US/Eastern
XLOG METHOD: fetch
BACKUP CHECKSUM(s): 1
ChkSum File
37f3defb98ca88dcf05079815555dfc2 base.tar.gz
TABLESPACE(s): 0
START WAL LOCATION: 0000001000000000000004
STOP WAL LOCATION: 000000010000000000000004
BACKUP METHOD: streamed
BACKUP FROM: master
START TIME: 2017-03-29 13:48:15 EDT
STOP TIME: 2017-03-29 13:48:17 EDT
TOTAL DURATION: 2 sec(s)
-bash-4.1$ bart BACKUP -s mktg -z
```

```
INFO: creating backup for server 'mktg'
INFO: backup identifier: '1490809751193'
61016/61016 kB (100%), 1/1 tablespace
INFO: backup completed successfully
INFO: backup checksum: 8b010e130a105e76d01346bb56dfcf14 of base.tar.gz
INFO:
BACKUP DETAILS:
BACKUP STATUS: active
BACKUP IDENTIFIER: 1490809751193
BACKUP NAME: mktg 2017-03-29T13:49
BACKUP PARENT: none
BACKUP LOCATION: /opt/backup/mktg/1490809751193
BACKUP SIZE: 6.13 MB
BACKUP FORMAT: tar.qz
BACKUP TIMEZONE: US/Eastern
XLOG METHOD: fetch
BACKUP CHECKSUM(s): 1
ChkSum File
8b010e130a105e76d01346bb56dfcf14 base.tar.gz
TABLESPACE(s): 0
START WAL LOCATION: 00000001000000100000085
BACKUP METHOD: streamed
BACKUP FROM: master
START TIME: 2017-03-29 13:49:11 EDT
STOP TIME: 2017-03-29 13:49:14 EDT
TOTAL DURATION: 3 sec(s)
-bash-4.1$ bart BACKUP -s hr -z
INFO: creating backup for server 'hr'
INFO: backup identifier: '1490809824946'
38991/38991 kB (100%), 1/1 tablespace
INFO: backup completed successfully
INFO: backup checksum: 277e8a1a80ba3474f541eb316a417c9a of base.tar.gz
INFO:
BACKUP DETAILS:
BACKUP STATUS: active
BACKUP IDENTIFIER: 1490809824946
BACKUP NAME: hr 2017-03-29T13:50
BACKUP PARENT: none
BACKUP LOCATION: /opt/backup/hr/1490809824946
BACKUP SIZE: 2.59 MB
BACKUP FORMAT: tar.qz
BACKUP TIMEZONE: US/Eastern
XLOG METHOD: fetch
BACKUP CHECKSUM(s): 1
ChkSum File
277e8a1a80ba3474f541eb316a417c9a base.tar.gz
TABLESPACE(s): 0
START WAL LOCATION: 0000001000000000000000
BACKUP METHOD: streamed
```

```
BACKUP FROM: master

START TIME: 2017-03-29 13:50:25 EDT

STOP TIME: 2017-03-29 13:50:26 EDT

TOTAL DURATION: 1 sec(s)
```

The following code snippet shows the backup directories created for each backup of each database server. The backup ID is used as the backup directory name.

```
-bash-4.1$ cd /opt/backup
-bash-4.1$ ls -1
total 12
drwxrwxr-x 4 enterprisedb enterprisedb 4096 Mar 29 13:48 acctg
drwxrwxr-x 4 enterprisedb enterprisedb 4096 Mar 29 13:50 hr
drwxrwxr-x 4 enterprisedb enterprisedb 4096 Mar 29 13:49 mktg
-bash-4.1$ ls -l acctg
total 8
drwx----- 2 enterprisedb enterprisedb 4096 Mar 29 13:48 1490809695281
drwxrwxr-x 2 enterprisedb enterprisedb 4096 Mar 29 13:48 archived_wals
-bash-4.1$ ls -l hr
total 8
drwx----- 2 enterprisedb enterprisedb 4096 Mar 29 13:50 1490809824946
drwxrwxr-x 2 enterprisedb enterprisedb 4096 Mar 29 13:50 archived wals
-bash-4.1$ ls -l mktg
total 8
drwx----- 2 enterprisedb enterprisedb 4096 Mar 29 13:49 1490809751193
drwxrwxr-x 2 enterprisedb enterprisedb 4096 Mar 29 13:49 archived wals
```

Using Point-In-Time Recovery

The following section demonstrates the point-in-time recovery operation on the remote PostgreSQL database server.

The following tables were created about two minutes apart while WAL archiving is enabled:

```
postgres=# \dt
           List of relations
Schema
             Name
                         Type
                               Owner
public | hr rmt t1 1356 | table
                               postgres
public | hr rmt t1 1358 | table
                               postgres
public
       | hr_rmt_t1_1400 | table
                               postgres
public
       postgres
public
       hr rmt t1 1404 | table
                               postgres
       hr rmt t1 1406 | table
                               postgres
public
(6 rows)
```

In the table name hr_rmt_t<n>_<hhmi>, n represents the active timeline. <hhmi> is the approximate time the table was created. For example, hr_rmt_t1_1356 was created at approximately 1:56 PM while timeline #1 is active.

The PostgreSQL database server was then stopped.

WAL files that have been created, but not yet archived must be identified, and then saved.

The following are the archived WAL files in the BART backup catalog:

The following lists the current PostgreSQL server WAL files. The unarchived WAL files are marked with two stars (**).

```
-bash-4.1$ cd /opt/PostgreSQL/9.5/data/pg_xlog
-bash-4.1$ pwd
/opt/PostgreSQL/9.5/data/pg_xlog
-bash-4.1$ ls -1
total 49160
-rw----- 1 postgres postgres 302 Mar 29 13:50
0000000100000000000000002.00000028.backup
-rw----- 1 postgres postgres 16777216 Mar 29 14:07
00000010000000000000000003
-rw----- 1 postgres postgres 16777216 Mar 29 14:07
**000000100000000000000004**
-rw----- 1 postgres postgres 16777216 Mar 29 13:50
**00000010000000000000000005**
drwx----- 2 postgres postgres 4096 Mar 29 14:07 archive_status
```

Copies of the unarchived WAL files are saved to a temporary location:

On the remote host, the directory is created to which the PostgreSQL database cluster is to be restored. This restore path is /opt/restore pg95 owned by user account postgres.

```
[user@localhost ~]$ su root
Password:
[root@localhost user]# cd /opt
```

```
[root@localhost opt]# mkdir restore_pg95
[root@localhost opt]# chown postgres restore_pg95
[root@localhost opt]# chgrp postgres restore_pg95
[root@localhost opt]# chmod 700 restore_pg95
[root@localhost opt]# ls -l
total 16
drwxr-xr-x 4 root daemon 4096 Mar 29 12:10 PostgresPlus
drwxr-xr-x 3 root daemon 4096 Mar 29 12:25 PostgreSQL
drwx----- 2 postgres postgres 4096 Mar 29 14:15 restore_pg95
drwxr-xr-x. 2 root root 4096 Nov 22 2013 rh
```

Note

In the BART configuration file, the remote user and remote host IP address, postgres@192.168.2.24, have been set with the remote_host parameter. If not given in the BART configuration file, this information must then be specified by the --remote-host option when giving the RESTORE subcommand (for example, bart RESTORE --remote-host postgres@192.168.2.24 ...).

```
[HR]
host = 192.168.2.24
port = 5432
user = postgres
cluster_owner = postgres
backup_name = hr_%year-%month-%dayT%hour:%minute
remote_host = postgres@192.168.2.24
copy_wals_during_restore = enabled
description = "Human Resources"
```

Use the SHOW-BACKUPS subcommand to identify the backup to use with the RESTORE subcommand.

SERVER NAME	BACKUP ID	BACKUP NAME	BACKUP PARENT
BACKUP TIME			
BACKUP SIZE	WAL(s) SIZE	WAL FILES	STATUS
acctg	1490809695281	acctg_2017-03-29T13:48	none
2017-03-29 13:48:17	EDT		
6.10 MB	32.00 MB	2	active
hr	1490809824946	hr_2017-03-29T13:50	none
2017-03-29 13:50:26	EDT		
2.59 MB	32.00 MB	2	active
mktg	1490809751193	mktg_2017-03-29T13:49	none
2017-03-29 13:49:14	EDT		
6.13 MB	64.00 MB	4	active

The -t option with the SHOW-BACKUPS subcommand displays additional backup information:

```
-bash-4.1$ bart SHOW-BACKUPS -s hr -i 1490809824946 -t
SERVER NAME : hr
BACKUP ID : 1490809824946
BACKUP NAME : hr_2017-03-29T13:50
BACKUP PARENT : none
BACKUP STATUS : active
BACKUP TIME : 2017-03-29 13:50:26 EDT
```

A recovery is made using timeline 1 to 2017-03-29 14:01:00.

```
-bash-4.1$ bart RESTORE -s hr -i hr_2017-03-29T13:50 -p
/opt/restore_pg95 -t 1 -g '2017-03-29 14:01:00'
INFO: restoring backup 'hr_2017-03-29T13:50' of server 'hr'
INFO: base backup restored
INFO: copying WAL file(s) to
postgres@192.168.2.24:/opt/restore_pg95/archived_wals
INFO: writing recovery settings to postgresql.auto.conf file
INFO: archiving is disabled
INFO: permissions set on $PGDATA
INFO: restore completed successfully
```

The following example shows the restored backup files in the restore path directory, /opt/restore pg95:

```
-bash-4.1$ pwd
/opt/restore pg95
-bash-4.1$ ls -1
total 128
drwxr-xr-x 2 postgres postgres 4096 Mar 29 14:27 archived wals
-rw----- 1 postgres postgres 206 Mar 29 13:50 backup label
drwx---- 5 postgres postgres 4096 Mar 29 12:25 base
drwx----- 2 postgres postgres 4096 Mar 29 14:27 global
drwx----- 2 postgres postgres 4096 Mar 29 12:25 pg clog
drwx----- 2 postgres postgres 4096 Mar 29 12:25 pg_commit_ts
drwx----- 2 postgres postgres 4096 Mar 29 12:25 pg dynshmem
-rw---- 1 postgres postgres 4212 Mar 29 13:18 pg hba.conf
-rw----- 1 postgres postgres 1636 Mar 29 12:25 pg ident.conf
drwxr-xr-x 2 postgres postgres 4096 Mar 29 13:45 pg log
drwx----- 4 postgres postgres 4096 Mar 29 12:25 pg logical
drwx----- 4 postgres postgres 4096 Mar 29 12:25 pg multixact
drwx----- 2 postgres postgres 4096 Mar 29 13:43 pg notify
drwx----- 2 postgres postgres 4096 Mar 29 12:25 pg replslot
drwx----- 2 postgres postgres 4096 Mar 29 12:25 pg serial
drwx----- 2 postgres postgres 4096 Mar 29 12:25 pg snapshots
drwx----- 2 postgres postgres 4096 Mar 29 13:43 pg stat
drwx----- 2 postgres postgres 4096 Mar 29 13:50 pg stat tmp
drwx----- 2 postgres postgres 4096 Mar 29 12:25 pg subtrans
drwx----- 2 postgres postgres 4096 Mar 29 12:25 pg tblspc
drwx----- 2 postgres postgres 4096 Mar 29 12:25 pg twophase
-rw----- 1 postgres postgres 4 Mar 29 12:25 PG VERSION
drwx----- 3 postgres postgres 4096 Mar 29 14:27 pg xlog
-rw----- 1 postgres postgres 169 Mar 29 13:24 postgresql.auto.conf
-rw-r--r- 1 postgres postgres 21458 Mar 29 14:27 postgresgl.conf
-rw-r--r-- 1 postgres postgres 118 Mar 29 14:27 postgresql.auto.conf
```

Copy the saved, unarchived WAL files to the restore path pg_xlog subdirectory (/opt/restore_pg95/pg_xlog):

```
-bash-4.1$ pwd
/opt/restore_pg95/pg_xlog
-bash-4.1$ ls -1
total 16388
-rw----- 1 postgres postgres 16777216 Mar 29 13:50
00000010000000000000002
drwx----- 2 postgres postgres 4096 Mar 29 14:27 archive status
-bash-4.1$ ls -l /tmp/unarchived pg95 wals
total 32768
-rw----- 1 postgres postgres 16777216 Mar 29 14:07
0000001000000000000004
-rw----- 1 postgres postgres 16777216 Mar 29 13:50
0000001000000000000005
-bash-4.1$ cp -p /tmp/unarchived pg95 wals/* .
-bash-4.1$ ls -1
total 49156
-rw----- 1 postgres postgres 16777216 Mar 29 13:50
00000010000000000000002
-rw----- 1 postgres postgres 16777216 Mar 29 14:07
00000010000000000000004
-rw----- 1 postgres postgres 16777216 Mar 29 13:50
00000010000000000000005
drwx----- 2 postgres postgres 4096 Mar 29 14:27 archive status
```

Inspect the /opt/restore_pg95/postgresql.auto.conf file to verify that it contains the correct recovery settings:

```
restore_command = 'cp archived_wals/%f %p'
recovery_target_time = '2017-03-29 14:01:00'
recovery_target_timeline = 1
```

Note that it restores from the archived_wals subdirectory of /opt/restore_pg95 since the copy_wals_during_restore parameter in the BART configuration file is set to enabled for database server hr.

Start the database server to initiate the point-in-time recovery operation.

```
[user@localhost ~]$ su postgres
Password:
bash-4.1$ cd /opt/restore_pg95
bash-4.1$ /opt/PostgreSQL/9.5/bin/pg_ctl start -D /opt/restore_pg95 -l
/opt/restore_pg95/pg_log/logfile
server starting
```

Inspect the database server log file to ensure the operation did not result in any errors.

```
2017-03-29 14:33:23 EDT LOG: database system was interrupted; last known up at 2017-03-29 13:50:25 EDT 2017-03-29 14:33:23 EDT LOG: starting point-in-time recovery to 2017-03-29 14:01:00-04
```

```
2017-03-29 14:33:23 EDT LOG: restored log file
2017-03-29 14:33:23 EDT LOG: redo starts at 0/2000098
2017-03-29 14:33:23 EDT LOG: consistent recovery state reached at
0/2000C0
2017-03-29 14:33:23 EDT LOG: restored log file
"00000010000000000000003" from archive
2017-03-29 14:33:23 EDT LOG: recovery stopping before commit of
transaction 1762, time 2017-03-29 14:02:28.100072-04
2017-03-29 14:33:23 EDT LOG: redo done at 0/303F390
2017-03-29 14:33:23 EDT LOG: last completed transaction was at log time
2017-03-29 14:00:43.351333-04
cp: cannot stat `archived wals/0000002.history': No such file or
directory
2017-03-29 14:33:23 EDT LOG: selected new timeline ID: 2
cp: cannot stat `archived wals/0000001.history': No such file or
directory
2017-03-29 14:33:23 EDT LOG: archive recovery complete
2017-03-29 14:33:23 EDT LOG: MultiXact member wraparound protections are
now enabled
2017-03-29 14:33:23 EDT LOG: database system is ready to accept
connections
2017-03-29 14:33:23 EDT LOG: autovacuum launcher started
```

The tables that exist in the recovered database cluster are the following:

Since recovery was up to and including 2017-03-29 14:01:00, the following tables created after 14:01 are not present:

```
public | hr_rmt_t1_1402 | table | postgres
public | hr_rmt_t1_1404 | table | postgres
public | hr_rmt_t1_1406 | table | postgres
```

Note

The BART RESTORE operation stops WAL archiving by adding an archive_mode = off parameter at the very end of the postgresql.conf file. This last parameter in the file overrides any other previous setting of the same parameter in the file. Delete the last setting and restart the database server to start WAL archiving.

```
# Add settings for extensions here
archive_mode = off
4.
```