Embedded Software

Parallel programs, processes and threads




Agenda

- The problem A Case
- A Solution Parallelism
- Processes and Threads in Linux
- Advantages & Disadvantages with multitasking




- Consider a system that allows a user to enter a PIN.
 - How would you implement this?





- Consider a system that allows a user to enter a PIN.
 - How would you implement this?



```
void main()
{
   print "ENTER PIN:"
   get key -> ch
   while(ch != "OK")
   input += ch
   compare(input, pin)
}
```



- Now consider the same system, but now with a clock.
 - How would you implement this?



- How would you update the clock while waiting for input?
- How would you capture key presses while updating the clock?



- Now consider the same system, but now with a clock.
 - How would you implement this?



```
void main()
{
    ???
}
```

- How would you update the clock while waiting for input?
- How would you capture key presses while updating the clock?



Case - Solution

• With multiple threads, this is trivial:





Case - Solution

With multiple threads, this is trivial:



```
void userInput()
            Handles user
                                   print "ENTER PIN:"
           input as before
                                   get key -> ch
                                   while(ch != "0K")
                                    input += ch
                                    compare(input, pin)
                                void updClock()
           Handles clock
                                   while(true)
              updates
                                    display current time
                                    wait 1s
                                int main()
                                   startThread(userInput)
                                   startThread(updClock)
  Starts threads that run
user input and clock update
        routines
```




Parallel programs - A Solution

- Parallel programs are programs that are divided into execution units that can execute concurrently
 - Processes
 - ▶ Threads, jobs or tasks




Process & Threads in Linux








- Threads, Processes and Memory mapping
 - Each process has its own memory space
 - A mapping exists between virtual and physical memory
 - Not possible for one process to write in another address space
 - Threads share data space
 - Care must be taken NOT to destroy other threads data





MMU - Memory Management Unit




MMU: Memory Management Unit TLB: Translation Lookaside Buffer

More to follow in MPS later




MMU - Memory Management Unit





 Process - A program being executed in Linux


Process Memory Layout





- Process A program being executed in Linux
 - Stack
 - Local variables
 - Function return values
 - LIFO


Process Memory Layout





- Process A program being executed in Linux
 - Stack
 - Local variables
 - Function return values
 - LIFO
 - Heap
 - "Free-store"
 - Dynamically allocated memory

Process Memory Layout






 Process - A program being executed in Linux

1GB

3GB

- Stack
 - Local variables
 - Function return values
 - LIFO
- Heap
 - "Free-store"
 - Dynamically allocated memory
- Memory Mapping
 - File mapped in memory
 - Includes dyn libs
 - Sharing memory between processe


Process Memory Layout





- Process A program being executed in Linux
 - Stack
 - Local variables
 - Function return values
 - LIFO
 - Heap
 - "Free-store"
 - Dynamically allocated memory
- Memory Mapping
 - File mapped in memory
 - Includes dyn libs
 - Sharing memory between processe
- Variables and ELF


Process Memory Layout





Processes and the OS - Sharing memory - IPC


- POSIX Shared Memory
 - Accessing memory affects other process
 - ▶ Pro
 - Speed/Performance
 - ▶ Cons
 - Fragile
 - Death of process
 - Data must abide certain principles
 - Challenge ensuring synchronicity





Threads of execution and the OS (Kernel)


- How are threads mapped for execution?
 - Three different models
 - User level threading
 - Kernel level threading
 - Hybrid level threading





Threading Model


- User-Level Threading
 - Simple implementation no kernel support for threads
 - Very quick thread context switch (no kernel handling needed)
 - Not possible to handle multicores





Threading Model


- Kernel Level Threading
 - Need thread awareness in kernel
 - Maps directly to threads which the scheduler can control
 - Efficient multicore usage
- OS
 - Linux (NPLT), Win32 etc.






Threading Model

- Hybrid Level Threading
 - Complex implementation
 - Requires good coordination between user land and kernel land scheduler
 - Otherwise suboptimal resource usage
- OS
 - ▶ Windows 7






Context switching





Context switching


- A context is the environment of the currently running process
- A context switch is performed by the OS to suspend the currently running process and resume another process
- General steps:
 - Interrupt current process
 - ▶ Save context of current process (SP, PC, registers, ...)
 - Restore context of next process
 - Resume execution of next process






Context switching

- The operating system schedules tasks for execution
 - Preemptive scheduling: Tasks can be interrupted at any time
 - Nonpreemptive scheduling: Tasks voluntarily yield the CPU
- Linux supports both Kernel configuration options





The life and death of a process





Threads - Summary



Threads - Summary

- Threads are strands of execution each process has at least one thread
 - AKA light-weight processes
 - Also called tasks or jobs
- Threads of the same process share memory space (e.g. global variables)
- Threads can harm each other
- We will often work with several threads in the same process



Processes - Summary



Processes - Summary

- A process is an instance of a program that is being executed
 - Image of program (segment),
 - Stack, heap, registers, file descriptors, ...
- Processes have their own individual memory spaces
 - Process A cannot write in memory of process B they are safe from each other
- Processes may only communicate through IPC mechanisms controlled by the OS.
- Processes may spawn other processes, which may execute the same or other programs
- A process may also spawn threads within its own memory space



Multitasking systems: Advantages



Multitasking systems: Advantages

- What are the advantages of multiple tasking a system?
 - Prioritization the highest-priority task gets to run
 - Modularization wrap concurrent activities in a task
 - Resource utilization Don't spend CPU time waiting for I/O etc.
 - **)** ...
- However, the use of multiple tasks in a system creates a number of problems for us
- We must know the problems to be able to identify and counter or avoid them



Multithreaded systems: Disadvantages

Consider the following code. What is the value of shared after 10 seconds?



Multithreaded systems: Disadvantages

Consider the following code. What is the value of shared after 10 seconds?

```
unsigned int shared;
void taskfunc()
  while(true)
  int main()
  shared = 0;
  createThread(taskFunc); // Start two identical threads
  createThread(taskFunc); // that run the same function
  while(true)
   sleep();
```



Let's zoom in:

Program

```
while(true)
{
    shared++;
    sleep(ONE_SECOND);
}
```



Let's zoom in:

```
Program

While(true)
{
    shared++;
    sleep(ONE_SECOND);
}

Pseudo-machine instructions


LOAD R1, shared

INC R1

STORE shared, R1
```



Let's zoom in:





Non-interleaved instructions



Task 1 LOAD R1, shared INC R1 STORE shared, R1

```
Task 2

LOAD R1, shared
INC R1
STORE shared, R1
```

Non-interleaved instructions

```
LOAD R1, shared // shared = 0
INC R1
STORE shared, R1 // shared = 1
LOAD R1, shared // shared = 1
INC R1
STORE shared, R1 // shared = 2
```

```
LOAD R1, shared // shared = 0
LOAD R1, shared // shared = 0
INC R1
STORE shared, R1 // shared = 1
INC R1
STORE shared, R1 // shared = 1
```



Task 1 LOAD R1, shared INC R1 STORE shared, R1

```
Task 2

LOAD R1, shared
INC R1
STORE shared, R1
```

What value is shared suppose to have?

Non-interleaved instructions

```
LOAD R1, shared // shared = 0
INC R1
STORE shared, R1 // shared = 1
LOAD R1, shared // shared = 1
INC R1
STORE shared, R1 // shared = 2
```

```
LOAD R1, shared // shared = 0
LOAD R1, shared // shared = 0
INC R1
STORE shared, R1 // shared = 1
INC R1
STORE shared, R1 // shared = 1
```



Task 1 LOAD R1, shared INC R1 STORE shared, R1

```
Task 2

LOAD R1, shared
INC R1
STORE shared, R1
```

What value is shared suppose to have?

Non-interleaved instructions

```
LOAD R1, shared // shared = 0
INC R1
STORE shared, R1 // shared = 1
LOAD R1, shared // shared = 1
INC R1
STORE shared, R1 // shared = 2
```

Interleaved instructions

```
LOAD R1, shared // shared = 0
LOAD R1, shared // shared = 0
INC R1
STORE shared, R1 // shared = 1
INC R1
STORE shared, R1 // shared = 1
```

Which values can shared in fact have?



Non-interleaved instructions



```
Position pos { 10, 20, 30 };
```

Task 1

```
void newPos(Position& ps, float x, float y, float z)
{
  pos.x = x;
  pos.y = y;
  pos.z = z;
}
```

Task 2

```
void printPos(Position& pos)
{
    std::cout << "X: " << pos.x << std::endl;
    std::cout << "Y: " << pos.y << std::endl;
    std::cout << "Z: " << pos.z << std::endl;
}</pre>
```

Non-interleaved instructions

```
T1  pos.x = x;
T1  pos.y = y;
T1  pos.z = z;

T2  std::cout << "X: " << pos.x << std::endl;
T2  std::cout << "Y: " << pos.y << std::endl;
T2  std::cout << "Z: " << pos.z << std::endl;</pre>
```

```
T1 pos.x = x;

T2 std::cout << "X: " << pos.x << std::endl;
T2 std::cout << "Y: " << pos.y << std::endl;
T2 std::cout << "Z: " << pos.z << std::endl;
T1 pos.y = y;
T1 pos.z = z;
```



```
Position pos { 10, 20, 30 };
```

Task 1

```
void newPos(Position& ps, float x, float y, float z)
{
  pos.x = x;
  pos.y = y;
  pos.z = z;
}
```

Task 2

```
void printPos(Position& pos)
{
    std::cout << "X: " << pos.x << std::endl;
    std::cout << "Y: " << pos.y << std::endl;
    std::cout << "Z: " << pos.z << std::endl;
}</pre>
```

Non-interleaved instructions

```
T1 pos.x = x;

T1 pos.y = y;

T1 pos.z = z;

T2 std::cout << "X: " << pos.x << std::endl;

T2 std::cout << "Y: " << pos.y << std::endl;

T2 std::cout << "Z: " << pos.z << std::endl;
```

newPos called with 11, 22, 33

```
T1 pos.x = x;

T2 std::cout << "X: " << pos.x << std::endl;
T2 std::cout << "Y: " << pos.y << std::endl;
T2 std::cout << "Z: " << pos.z << std::endl;
T1 pos.y = y;
T1 pos.z = z;
```



```
Position pos { 10, 20, 30 };
```

Task 1

```
void newPos(Position& ps, float x, float y, float z)
{
  pos.x = x;
  pos.y = y;
  pos.z = z;
}
```

Task 2

```
void printPos(Position& pos)
{
    std::cout << "X: " << pos.x << std::endl;
    std::cout << "Y: " << pos.y << std::endl;
    std::cout << "Z: " << pos.z << std::endl;
}</pre>
```

Non-interleaved instructions

```
T1 pos.x = x;

T1 pos.y = y;

T1 pos.z = z;

T2 std::cout << "X: " << pos.x << std::endl;

T2 std::cout << "Y: " << pos.y << std::endl;

T2 std::cout << "Z: " << pos.z << std::endl;
```

newPos called with 11, 22, 33

Interleaved instructions

```
T1 pos.x = x;

T2 std::cout << "X: " << pos.x << std::endl;
T2 std::cout << "Y: " << pos.y << std::endl;
T2 std::cout << "Z: " << pos.z << std::endl;
T1 pos.y = y;
T1 pos.z = z;
```



```
Position pos { 10, 20, 30 };
```

Task 1

```
void newPos(Position& ps, float x, float y, float z)
{
  pos.x = x;
  pos.y = y;
  pos.z = z;
}
```

Task 2

```
void printPos(Position& pos)
{
    std::cout << "X: " << pos.x << std::endl;
    std::cout << "Y: " << pos.y << std::endl;
    std::cout << "Z: " << pos.z << std::endl;
}</pre>
```

Non-interleaved instructions

```
T1 pos.x = x;

T1 pos.y = y;

T1 pos.z = z;

T2 std::cout << "X: " << pos.x << std::endl;

T2 std::cout << "Y: " << pos.y << std::endl;

T2 std::cout << "Z: " << pos.z << std::endl;
```

std::cout prints X: 10 Y: 20 Z: 30

newPos called with 11, 22, 33

Interleaved instructions

```
T1 pos.x = x;

T2 std::cout << "X: " << pos.x << std::endl;
T2 std::cout << "Y: " << pos.y << std::endl;
T2 std::cout << "Z: " << pos.z << std::endl;
T1 pos.y = y;
T1 pos.z = z;
```



```
Position pos { 10, 20, 30 };
```

Task 1

```
void newPos(Position& ps, float x, float y, float z)
{
  pos.x = x;
  pos.y = y;
  pos.z = z;
}
```

Task 2

```
void printPos(Position& pos)
{
    std::cout << "X: " << pos.x << std::endl;
    std::cout << "Y: " << pos.y << std::endl;
    std::cout << "Z: " << pos.z << std::endl;
}</pre>
```

Non-interleaved instructions

```
T1 pos.x = x;

T1 pos.y = y;

T1 pos.z = z;

T2 std::cout << "X: " << pos.x << std::endl;

T2 std::cout << "Y: " << pos.y << std::endl;

T2 std::cout << "Z: " << pos.z << std::endl;
```

std::cout prints

X: 10 Y: 20 Z: 30

newPos called with 11, 22, 33

Interleaved instructions

```
T1 pos.x = x;

T2 std::cout << "X: " << pos.x << std::endl;

T2 std::cout << "Y: " << pos.y << std::endl;

T2 std::cout << "Z: " << pos.z << std::endl;

T1 pos.y = y;

T1 pos.z = z;
```

std::cout prints

X: 11 Y: 20 Z: 30



```
Position pos { 10, 20, 30 };
```

Task 1

```
void newPos(Position& ps, float x, float y, float z)
{
  pos.x = x;
  pos.y = y;
  pos.z = z;
}
```

Task 2

```
void printPos(Position& pos)
{
    std::cout << "X: " << pos.x << std::endl;
    std::cout << "Y: " << pos.y << std::endl;
    std::cout << "Z: " << pos.z << std::endl;
}</pre>
```

Non-interleaved instructions

```
T1 pos.x = x;

T1 pos.y = y;

T1 pos.z = z;

T2 std::cout << "X: " << pos.x << std::endl;

T2 std::cout << "Y: " << pos.y << std::endl;

T2 std::cout << "Z: " << pos.z << std::endl;
```

std::cout prints

X: 10 Y: 20 Z: 30

newPos called with 11, 22, 33

Interleaved instructions

```
T1 pos.x = x;

T2 std::cout << "X: " << pos.x << std::endl;
T2 std::cout << "Y: " << pos.y << std::endl;
T2 std::cout << "Z: " << pos.z << std::endl;
T1 pos.y = y;
T1 pos.z = z;

Hey WHAT???
```

std::cout prints

X: 11 Y: 20 Z: 30

AARHUS UNIVERSITY


- The shared data problem is inherent in any preemptive multithreaded system
- Very cumbersome to find a good software solution to the problem
 - Peterson's solution: 2 interest flags, 1 will-wait flag
 - Does not scale
- We need a way to define critical sections of program
 - Sections in which the thread is guaranteed to be allowed to execute uninterrupted
- In a later lecture!

```
void taskfunc()
{
  while(true)
  {
    enterCriticalSection();
    shared++;
    exitCriticalSection();
    sleep(ONE_SECOND);
  }
}
AARHUS
UNIVERSITY
```


Multithreaded systems: Disadvantages

- Consider a system with three threads, HP, MP and LP:
 - HP takes 5 μs, must run once every 10 μs
 - MP takes 3 μs, must run once every 10 μs
 - LP takes 1 μs, must run once every 1000 μs






• Schedule?






Starvation

- Assume we add another MP thread, MP₂
 - MP₂ takes 2 μs, may run once every 10 μs



Schedule?





Starvation



Starvation

- Starvation is an inherent problem in any priority-based system
- It occurs when the schedule is so tight that LP threads are never allowed to run because higher-priority threads "hog" the CPU
- Starvation can be very hard to predict and detect
 - Might only occur in very special situations



Programming with threads



Programming with threads

- C++ does not have the concept of threads built in
 - Relies on 3rd party libraries for this
 - Not entirely true see new ratified C++ standard
- The POSIX (Portable OS Interface for uniX) library is the most widely used threading library
 - Others include boost, Qt, ...
- The POSIX library has the thread type pthread which we will use.
 - Include pthread.h, link with library pthread



PThread functions

- Family of pthread functions you are to use...
 - pthread_create()
 - pthread_join()
 - pthread_exit()
 - pthread_* (and more)
- How they work is for next session

