并发进阶 Advanced Concurrency

#### 现代C++基础 Modern C++ Basics

Jiaming Liang, undergraduate from Peking University

Memory Order Basics

Atomic Variable Details

Advanced Memory Order

Coroutine

Initially, I think that most of the committee members underestimated the problem. We knew that Java had a good memory model [Pugh 2004] and hoped to adopt that. I was highly amused to find that representatives from Intel and IBM effectively vetoed that idea by pointing out that by adopting the Java memory model for C++ we would slow down all JVMs by a factor of at least two. Consequently, to preserve the performance of Java, we had to adopt a far more complex model for C++. Ironically and predictably, C++ was then criticized for having a more complicated memory model than Java.

最开始,我想大多数委员都小瞧了这个问题。我们知道 Java 有一个很好的内存模型 [Pugh 2004],并曾希望采用它。令我感到好笑的是,来自英特尔和 IBM 的代表坚定地否决了这一想法,他们指出,如果在 C++ 中采用 Java 的内存模型,那么我们将使所有 Java 虚拟机的速度减慢至少一半。因此,为了保持 Java 的性能,我们不得不为 C++ 采用一个复杂得多的模型。可以想见而且讽刺的是,C++ 此后因为有一个比 Java 更复杂的内存模型而受到批评。

# Advanced Concurrency

Memory Order Basics

"Even with C++11 support, I consider lock-free programming expert-level work." -- Bjarne Stroustrup, HoPL4, P33

#### Advanced Concurrency

- Memory Order Basics
  - Overview
  - Sequentially consistent model
  - Acquire-release model
  - Relaxed model
  - There also exists consume-release model, but since it's very difficult for users to annotate and for compilers to analyze better optimizations, all compilers strengthen consume-release model to acquire-release model.
    - C++20: [Note 1: Prefer memory\_order::acquire, which provides stronger guarantees than memory\_order::consume. Implementations have found it infeasible to provide performance better than that of memory\_order::acquire. Specification revisions are under consideration. end note]
    - C++26: consume operations are deprecated.

Defang and deprecate memory\_order::consume

- Current programming world stands on the foundation of sequential execution...
  - Compiler / JIT may do aggressive optimization...
    - Here we will "cache" global variables to registers, and eliminate redundant expressions (i.e. b = addend + 1).

- Processors may do out-of-order execution and speculative computation...
- Each processor may have its own L1/L2 cache...

 These optimizations are smart and correct in sequential world, but when it comes to parallelism, some assumptions are not that intuitive...


- What if there is another thread that modifies addend here?
  - b can be something other than tempb + 4, but compiler optimizations make it impossible.


- Among so many compiler optimizations, processor ISA regulations, cache coherence protocols...
  - We need to find a way to unify "as-if" behaviors by abstraction!
- That is what *memory order* for in C++.
  - Three types of memory order:
    - Sequentially consistent model (seq\_cst)
    - Acquire-release model (acq\_rel)
    - Relaxed model (relaxed)
  - BTW, Rust has completely same regulations as C++.

Rust pretty blatantly just inherits the memory model for atomics from C++20. This is not due to this model being particularly excellent or easy to understand. Indeed, this model is quite complex and known to have several flaws. Rather, it is a pragmatic concession to the fact that *everyone* is pretty bad at modeling atomics. At very least, we can benefit from existing tooling and research around the

[1]: A Concurrency Semantics for Relaxed Atomics that Permits Optimisation and Avoids Thin-air Executions | POPL'16, Jean & Peter from Univ. of Cambridge POPL is Top Academic Conference in Programming Language Design.

- But, how to describe memory order is still an unsolved problem even in academia (even seq\_cst model has bug fix in C++20).
  - And C++ is pioneer in this field, so the standard has been revised nearly in every version.
  - But normally this is defect in theoretical model; real-world behaviors are not severely affected.
- The key problem is that memory order is *axiomatic*<sup>[1]</sup>, which is rather weak and cannot exactly describe what we want.
  - Memory order gives constraints, and every outcome that can fulfill the constraint is a valid solution.
    - While some solutions are not really valid...we'll see them later.





Formally, this is regulated by RR/RW/WR/WW coherence in standard; we rephrase it here.

- There are some intuitive basic regulations in memory model.
- 1. Modification order: for a **single atomic** variable, all threads see the same operation sequences.
  - So can r1 == 1 && r2 == 2 && r3 == 2 && r4 == 1?
  - No!
  - Reason: r4 cannot read value newer than r3, and r2 cannot read value newer than r1.
    - r1 == 1 && r2 == 2: 2 is newer than 1;
    - r3 == 2 && r4 == 1: 1 is newer than 2; Conflict!
    - Compilers are not allowed to reorder.
  - But, operations for different atomic variables may have different orders in different threads.

```
-- Initially --
std::atomic<int> x{0};
-- Thread 1 --
x.store(1);
-- Thread 2 --
x.store(2);
-- Thread 3 --
int r1 = x.load();
int r2 = x.load();
-- Thread 4 --
int r3 = x.load();
int r4 = x.load();
```

2. Sequenced before: we've covered evaluation order previously...

#### Expression

- Then, it's order of expression evaluation that computes the whole tree.
  - It is only determined that before the evaluation of root, the left child and the right child will be evaluated first; the order is **unspecified**.
  - e.g. f1() +<sub>1</sub> f2() +<sub>2</sub> f3(), it's root(+<sub>2</sub>) -> <u>lChild(f1() + f2()) -> rChild(f3())</u>, while <u>lChild</u> is root(+<sub>1</sub>) -> <u>lChild(f1()) -> rChild(f2())</u>;
    - We can know before +1 is evaluated, <a href="IChild">IChild</a> and <a href="IChild">IChild</a> is first evaluated.
    - · However, you can evaluate in the sequence of:
      - lChild evaluates f1()
      - rChild evaluates f3(), gets the value.
      - 1Child evaluates f2(), gets the value.
      - This still obeys our rules, e.g. f1() and f2() evaluated before <a href="LChild">LChild</a>.
    - So if we output a in f1(), b in f2(), c in f3(), any permutation of abc is possible!
  - To sum up, evaluation order is hugely determined by how compiler computes the tree.

- So if an evaluation A definitely computes before another one B, then we say A is sequenced before B. | a += 1; // #1 happens before #2
  - For example, for different statements.
  - In the same statement:

b += 2; // #2

- And function parameters are *indeterminately sequenced* since C++17, so there is some order but it's unspecified;
- And some evaluations are not regulated at all, which means they're unsequenced (e.g. a = b++ + b is UB, since b++ and b are unsequenced while b++ has side effect).
- Again, such order is in the sequential view...

Data races occur when non-atomic operations on the same memory location do NOT have some certain happens-before relationship.

- 3. Happens before: in parallel world, which evaluation is executed first is regulated by *happens-before*.
  - If A is sequenced before B, then A happens before B (single-thread case);
  - If A synchronizes with B, then A happens before B (inter-thread case);
  - Or A happens before B & B happens before C, then A happens before C.
  - For non-atomic variables, only when A happens before B will effects of A be visible to B.
    - So compilers can do aggressive optimizations, as long as they aren't visible.
  - For atomic variables, HB order is part of MO; if two operations have no HB relationship, then their order in MO is also random.
    - Namely, if B doesn't happen before A, then effects of A may be visible to B.
  - Memory order mainly regulates such "synchronize-with" relationship.

Note: actually, what we teach here is happens-before since C++26; before that (since C++20) this is called simply-happens-before, but it's equivalent to happens-before (since C++11) when no consume operation is involved (and again, we've said that consume operations are never implemented).

### Advanced Concurrency

- Memory Order Basics
  - Overview
  - Sequentially consistent model
  - Acquire-release model
  - Relaxed model

## Sequential Consistency

 In real world, all events are sequenced in some way, and all observers will see the same sequence.

• Similarly, we may think operations to have some total order, and

all threads observe the same order.

This is the core of sequentially consistent model!

• Back to our example:

```
x.store(1)
x.store(2)
x.load() x.load()
x.load()
```

```
x.load()
x.store(1)
x.load()
r3=1
x.store(2)
x.load()
r4=2
x.load()
r2=2
```

Interleaving them randomly, we get a total order.

```
-- Initially --
std::atomic<int> x{0};
-- Thread 1 --
x.store(1);
-- Thread 2 --
x.store(2);
-- Thread 3 --
int r1 = x.load();
int r2 = x.load();
-- Thread 4 --
int r3 = x.load():
int r4 = x.load();
```

## Sequential Consistency

- Formally, when an atomic load operation B loads a value that's stored by an atomic store operation A, then A synchronizes with B.
  - Then all previous outcomes are visible since B.
- For example:

```
std::atomic<bool> x{false}, y{false};
std::atomic<int> z{0};

void write_x() { x.store(true); }


void write_y() { y.store(true); }

void read_x_then_y()
{
    while (!x.load());
    if (y.load())
        ++z;
}

void read_y_then_x()
{
    while (!y.load());
    if (x.load())
        ++z;
```

Can this assert fire?

- No, z.load() is always non-zero.
- Reason: there is a total order, so either x.store(true) or y.store(true) occurs first.
  - Let's assume x.store(true) happens first since it's completely symmetric.



- Synchronization is implicitly established through reading value.
- Note: x.store(true) and y.store(true) do NOT have happens-before relationship; the order is imposed by total order.

#### Sequential Consistency

- Note 2: start of threads & joining threads will also establish synchronize-with relationship with function start & return.
  - So here thread joining happens before z.load(), and function return happens before thread joining, and ++z happens before function return. Thus z.load() can get 1 or 2 correctly.
- Note 3: operations on atomic variables are indivisible (and thus prevent data races), which is not affected by memory order.
  - Called *atomicity*.
  - Our example in the last lecture:
    - If a is atomic variable, then lock protection is not needed.

```
void Inc(int& a, std::mutex& mut) {
    for (int i = 0; i < 100000; i++)
    {
        std::lock_guard _{ mut };
        a++;
    }
}</pre>
```

### Advanced Concurrency

- Memory Order Basics
  - Overview
  - Sequentially consistent model
  - Acquire-release model
  - Relaxed model

- In many architectures like RISC-V, ARM and Power, such totalorder assumption is quite expensive, while they support weaker model better.
  - Acquire-release is a commonly supported order!
- So what does acquire-release model guarantee?
  - Only read operations can be "acquire", and only write operations can be "release".
  - For an acquire operation B, if it reads the value from a release operation A,
     then A synchronizes with B (and thus A happens before B).
  - There is no total order.

#### • For example:

Sequenced before store, thus happens before store.

Only when ptr loads some value will the program proceed, then store synchronizes with load (and thus happens before load).

Sequenced after load, thus load happens before asserts.

```
std::atomic<std::string*> ptr;
int data:
void producer()
    std::string* p = new std::string("Hello");
    data = 42:
   ptr.store(p, std::memory order release);
void consumer()
    std::string* p2;
    while (!(p2 = ptr.load(std::memory_order_acquire)))
    assert(*p2 == "Hello"); // never fires
    assert(data == 42); // never fires
int main()
    std::thread t1(producer);
    std::thread t2(consumer);
    t1.join(); t2.join();
```

Through three happens-before, we know that data is always 42.

• On the other hand, since it doesn't have total order:

```
Store of x and y have no
void write_x() { x.store(true, std::memory_order_release); }
                                                                happens-before relationship.
void write_y() { y.store(true, std::memory_order_release); }
void read_x_then_y()
   while (!x.load(std::memory_order_acquire));
                                             Here we only know that x is true (synchronize-with), while
   if (y.load(std::memory_order_acquire))
                                             y.load and y.store don't necessarily have happens-before
       ++Z;
                                                                    relationship.
void read_y_then_x()
   while (!y.load(std::memory_order_acquire));
                                                Similarly, x.load and x.store don't necessarily have
   if (x.load(std::memory_order_acquire))
                                                            happens-before relationship.
       ++Z;
```

Thus, z.load() can be 0 here.

- Another example for transitivity:
  - SB(#0, #1)
  - SW(#1, #2)
    - As only when #2 reads true can thread 2 proceed.
  - SB(#2, #3)
  - SW(#3, #4)
  - SB(#4, #5)
- Thus we know HB(#0, #5).

Obviously, acquire-release model can be used to implement spinlock.

```
int data = 0;
std::atomic<bool> sync1{ false },sync2{ false };
void thread 1()
    data = 442;
                                                   // #0
    sync1.store(true,std::memory_order_release);
void thread_2()
    while(!sync1.load(std::memory_order_acquire)); // #2
    sync2.store(true,std::memory_order_release);
void thread_3()
    while(!sync2.load(std::memory_order_acquire)); // #4
    assert(data == 442);
                                                   // #5
```

- By happens-before relationship, acquire-release model implicitly disables compiler reorder optimization.
  - An acquire operation B may happen after another release operation A...
    - If a compiler reorders statements S1 after B to before B;
    - Or if a compiler reorders statements S2 before A to after A;
    - Then S1 may fail to observe results in S2.
  - Thus, acquire & release offers a one-way instruction barrier implicitly.
    - All operations that will cause side effects (that may be used by another threads) cannot go below beyond a release operation;
    - All operations that may rely on side effects cannot go above beyond an acquire operation.
  - Intuitively, acquire-release forms some critical section; you cannot move out code in between.

### Advanced Concurrency

- Memory Order Basics
  - Overview
  - Sequentially consistent model
  - Acquire-release model
  - Relaxed model

- Sometimes we may want even weaker order...
  - That is, we only need to maintain atomicity; no synchronize-with relationship is needed.
  - This is relaxed model.

#### • For example:

```
std::atomic<int> x{0}, y{0};

void read_y_then_write_x(int& r1)
{
    r1 = y.load(std::memory_order_acquire); // #1
    x.store(r1, std::memory_order_release); // #2
}

void read_x_then_write_y(int& r2)
{
    r2 = x.load(std::memory_order_acquire); // #3
    y.store(42, std::memory_order_release); // #4
}
```

Exercise: Can this assert fire?

- No!
- Assuming that r1 == 42,
  - Then #1 reads value from #4, and acquire-release model makes SW(#4, #1).
  - And SB(#3, #4), SB(#1, #2), thus we know HB(#3, #2).
  - Thus, effects of #2 are not visible to #3, and r2 is definitely 0.
- Then what about relaxed model?
  - This assertion may fire...
  - That is, r1 == 42 && r2 == 42 may be true.

```
std::atomic<int> x{0}, y{0};

void read_y_then_write_x(int& r1)
{
    r1 = y.load(std::memory_order_acquire); // #1
     x.store(r1, std::memory_order_release); // #2
}

void read_x_then_write_y(int& r2)
{
    r2 = x.load(std::memory_order_acquire); // #3
    y.store(42, std::memory_order_release); // #4
}
```

```
void read_y_then_write_x(int& r1)
{
    r1 = y.load(std::memory_order_relaxed); // #1
    x.store(r1, std::memory_order_relaxed); // #2
}

void read_x_then_write_y(int& r2)
{
    r2 = x.load(std::memory_order_relaxed); // #3
    y.store(42, std::memory_order_relaxed); // #4
}
```

- Since relaxed model doesn't establish any synchronize-with relationship...
- Remember our effect rules?
  - For atomic variables, HB order is part of MO; if two operations have no HB relationship, then their order in MO is also random.
    - Namely, if B doesn't happen before A, then effects of A may be visible to B.
  - So here #1 doesn't happen before #4, then effects of #4 can be read by #1 so r1 == 42 can be true.
    - And #1 happens before #2, so x can store 42.
  - And #3 doesn't happen before #2, then effects of #2 can be read by #3 so r2 == 42 can be true.
- Thus, r1 == 42 && r2 == 42 can be true.

```
void read_y_then_write_x(int& r1)
{
    r1 = y.load(std::memory_order_relaxed); // #1
    x.store(r1, std::memory_order_relaxed); // #2
}

void read_x_then_write_y(int& r2)
{
    r2 = x.load(std::memory_order_relaxed); // #3
    y.store(42, std::memory_order_relaxed); // #4
}
```

- Note 1: again, we emphasize that there is no total order.
  - If there is, then in thread 2 SB(#3, #4) prevents any possible order to make r2 == 42.
  - In practice, compilers are allowed to reorder #3 and #4, since destroying such HB doesn't affect any visible effects.
- Note 2: this outcome doesn't violate modification order constraint of a single atomic variable.

All threads see this same modification order.



Notice that here it's **can** instead of **must**; #1 and #3 can read older values.

#### Another complex example:

```
void increment(std::atomic<int>* var, ValueContainer* values)
    start.wait(false); Like a spinlock, covered later. \{
    for (unsigned int i = 0; i < loop_num; i++)
        values[i].x = x.load(std::memory_order_relaxed);
        values[i].y = y.load(std::memory_order_relaxed);
        values[i].z = z.load(std::memory_order_relaxed);
        var->store(i + 1, std::memory_order_relaxed);
void read_status(ValueContainer* values)
    start.wait(false):
    for (unsigned int i = 0; i < loop_num; i++)
        values[i].x = x.load(std::memory_order_relaxed);
        values[i].y = y.load(std::memory_order_relaxed);
        values[i].z = z.load(std::memory_order_relaxed);
```

```
std::atomic<int> x{0}, y{0}, z{0};
std::atomic<bool> start{false};

constexpr unsigned int loop_num = 10;
struct ValueStatus { int x, y, z; };

using ValueContainer = std::array<ValueStatus, loop_num>;
```

```
int main()
    std::array<ValueContainer, 5> values;
       std::jthread a{ increment, &x, &values[0] }, b{ increment, &y,
&values[1] }, c{ increment, &z, &values[2] };
       std::jthread d{ read_status, &values[3] }, e{ read_status, &values[4] };
       start.store(true);
       start.notify_all(); All threads start now.
   for (const auto& cont: values)
       std::print("[");
       for (auto val : cont)
            std::print("({}, {}, {}) ", val.x, val.y, val.z);
       std::println("]");
```

- So what it does is:
  - Three threads, with each one only modifying one of the atomic variables, and reading all of them;
  - Two threads that only read all atomic variables.
- It can only guarantee that:
  - The thread that modifies the variable will see it increases one by one, constrained by happens-before relationship.
    - For example, values[0] will have (0, ..., ...), (1, ..., ...), ..., (9, ..., ...).
  - And constrained by single-atomic modification order, other variables that are not modified by itself will have non-decreasing values.
    - That is, once a value is read (not necessarily the newest), values older than it cannot be read.
- [Note 16: The four preceding coherence requirements effectively disallow compiler reordering of atomic operations to a single object, even if both operations are relaxed loads. This effectively makes the cache coherence guarantee provided by most hardware available to C++ atomic operations. end note]

• Courtesy of C++ Concurrency in Action,  $2^{nd}$  ed. by Anthony Williams.

One possible output from this program is as follows:

```
(0,0,0), (1,0,0), (2,0,0), (3,0,0), (4,0,0), (5,7,0), (6,7,8), (7,9,8), (8,9,8), (9,9,10)

(0,0,0), (0,1,0), (0,2,0), (1,3,5), (8,4,5), (8,5,5), (8,6,6), (8,7,9), (10,8,9), (10,9,10)

(0,0,0), (0,0,1), (0,0,2), (0,0,3), (0,0,4), (0,0,5), (0,0,6), (0,0,7), (0,0,8), (0,0,9)

(1,3,0), (2,3,0), (2,4,1), (3,6,4), (3,9,5), (5,10,6), (5,10,8), (5,10,10), (9,10,10), (10,10,10)

(0,0,0), (0,0,0), (0,0,0), (6,3,7), (6,5,7), (7,7,7), (7,8,7), (8,8,7), (8,8,9), (8,8,9)
```

- Relaxed model may cause very astonishing results, so it needs to be used with extreme caution...
  - Usually it either cooperates with other sync operations (like acquirerelease model)...
  - Or it's used to do very simple job that only needs atomicity.
    - For example, std::shared\_ptr has a counter to count its copies; when all copies are destructed, the memory is finally freed.
    - We can check the shared count by .use\_count(), which is normally a relaxed load since it doesn't need to participate in synchronization.

# Advanced Concurrency

**Atomic Variables** 

## Advanced Concurrency

- Atomic variables
  - Basic operations
    - atomic\_flag
  - Specializations
    - atomic\_ref

#### **Basic Operations**

- We can divide atomic operations into three categories:
  - Read operations;
  - Write operations;
  - Read-Modify-Write (RMW) operations.
- And for the most general atomic types std::atomic<T>:
  - Read operations are .load(memory\_order=std::memory\_order\_seq\_cst);
    - And an operator T, which can only use seq\_cst as order.
  - Write operations are .store(T newObj, memory\_order=std::memory\_order\_seq\_cst);
     Not T& or std::atomic<T>&!
    - And operator=(T), which can only use seq\_cst as order and returns T newObj.
    - Notice that atomic types are neither copyable nor moveable.

For methods of atomic operations, if it accepts memory order, then the default parameter is std::memory\_order\_seq\_cst; if it doesn't accept memory order, then it just uses std::memory\_order\_seq\_cst. We'll not repeat them in the following slides.

#### Read-Modify-Write

- And we also need atomic RMW operations...
  - This is not same as atomic read + atomic write, since two atomic operations are divisible.
  - RMW operations are indivisible as a whole.
  - For example: a++;
    - Read: temp = a; Modify: temp++; Write: a = temp.
    - If it's divisible, two threads running Inc may still get value other than 200000.

- And RMW operations are:
  - .exchange(T desired, memory\_order) -> T: read the original value and write desired; then return the original value.
    - Actually no modification, but read & write are atomic as a whole.

- And a composite operation:
  - .compare\_exchange\_strong(T& expected, T desired, memory\_order success, memory order failure) -> bool:
    - Read op: read the value v, compare it with expected;
    - Modify op: no modification;
    - Write op: if equal (or called success), write back desired; otherwise (failure) write back nothing (but assign expected = v).
    - Return value means success or not.
  - So bit of strangely, its operation type depends on its read op:
    - If failure, then it's just a load operation;
    - If success, then it's RMW operation (and the whole operation is atomic).
  - And thus, you can assign two memory order.

BTW such operations are generally called CAS operations (compare-and-swap / compare-and-set). CAS is the basic operation for *lock-free data structures*.

- Since RMW operations involve both read and write, the memory order will constrain both of them.
  - seq\_cst: both read and write use sequential consistent model.
  - relaxed: both read and write use relaxed model.
  - But for acquire-release model, acquire and release are separate...
    - So you can use std::memory\_order::acq\_rel!
  - acq\_rel: use acquire-release model, where read is acquire operation and write is release operation.
  - acquire: read is acquire operation while write is relaxed.
  - release: write is release operation while read is relaxed.

- There also exists a one-memory-order overload:
  - .compare\_exchange\_strong(T& expected, T desired, memory\_order success)-> bool;
    - Failure takes order from success, since RMW order includes read order.

Overloads	Memory model for	
	read-modify-write operation	load operation
(1,2,5,6)	success	failure
(3,4,7,8)	order	<ul> <li>std::memory_order_acquire if         order is std::memory_order_acq_rel</li> <li>std::memory_order_relaxed if         order is std::memory_order_release</li> <li>otherwise order</li> </ul>

Notice that failure is not seq\_cst by default.

Take our previous example:

```
int data = 0;
std::atomic<bool> sync1{ false },sync2{ false };
void thread 1()
    data = 442;
                                                   // #0
    sync1.store(true,std::memory_order_release);
                                                   // #1
void thread_2()
    while(!sync1.load(std::memory_order_acquire)); // #2
    sync2.store(true,std::memory_order_release); // #3
void thread_3()
    while(!sync2.load(std::memory_order_acquire)); // #4
    assert(data == 442);
                                                   // #5
```

Can be rewritten as:

But we notice that it's normally a bad idea to use RMW operation to do spinlock, since write is special in cache coherence protocol (like MESI) and harms efficiency. Here it's just an example.

```
int data = 0;
std::atomic<int> sync{0};
void thread_1()
                                                       // #0
    data = 442:
    sync.store(1, std::memory_order_release);
                                                       // #1
void thread_2()
    int expected = 1;
    while(!sync.compare_exchange_strong(expected, 2, // #2
                                        std::memory_order_acq_rel))
        expected = 1; // Restore expected to compare again.
void thread_3()
    while(sync.load(std::memory_order_acquire) != 2); // #4
    assert(data == 442);
                                                       // #5
```


- Note 1: atomic variables are bitwise-compared and bitwisewritten.
  - A customized operator == doesn't affect CAS operation;
  - 2. Particularly, for floating points, bitwise-comparison is very misleading.
    - For example, -0.0 and 0.0 are not bitwise-equal.

```
std::atomic<float> f{ 0.0 };
float expected = -0.0;
f.compare_exchange_strong(expected, 1.0);
```

- When expected is -0.0, this CAS returns false; when it's 0.0, it's true.
- 3. To make bitwise-written reasonable, std::atomic<T> has constraint on TT should be trivially copyable.

- Note 2: padding bits are NOT compared since C++20.
  - Before C++20, they're compared.
  - Formally, object representation v.s. value representation.

Object Representation



We'll talk about memory layout in detail in *Memory Management*.

```
struct 5
{
    char c;
    char padding[3];
    float f;
};
```

- Reason: padding comparison may lead to astonishing false. If you really want to compare padding, you can manually pad as members.
- But, if it's atomic union, when different types have different value representations (i.e. padding positions are not same), only shared padding parts will be omitted.

### • NOTICE:

- libc++ hasn't implemented it; libstdc++ currently implements it as DR (i.e. since gcc13, no matter what standard you specify, only value representation is compared).
- 2. For union, no matter whether types have shared padding positions, MS-STL will only compare object representation (as of 2025/7). A simple test.

- Note 3: there also exists .compare\_exchange\_weak(...), with completely same parameters as .compare\_exchange\_strong.
  - The effects are also same, except that weak may fail spuriously.
    - That is, it may report failure when it's in fact equal; but when it reports success, then it's definitely equal.
    - So that in some platforms, it may be cheaper to use weak than strong.
  - Normally we don't want that spurious failure, so weak is usually used in a loop.

```
do {
   desired = function(expected);
} while (!current.compare_exchange_weak(expected, desired));
```

- So when the loop body is relatively cheap, weak can be beneficial to performance.
- But if you don't use in loop or loop is very expensive, strong is expected.

## spinlock

- Though we can implement spinlock by acq\_rel, it's very inefficient.

  The rules of spinlocks:
  - 1. don't use spinlocks
  - 2. if you do, make sure you spin on a .load operation
  - 3. insert fallback strategies for when you couldn't acquire: always PAUSE, after a while switch to UMWAIT and if it still doesn't work, futex



- · Normally we should rely on platform-dependent features.
  - Like in x86, there are lots of idle instructions (PAUSE, UMWAIT, etc.) to reduce busy-wait overhead.
  - And in OS layer, we can use lots of native utilities like futex on Linux, WaitOnAddress on Windows, etc.
- To maximize efficiency, C++20 introduces .wait() for atomics.

A brief but good article about idle instructions: <u>漫话Linux之"躺平": IDLE 子系统</u>

- .wait(T old, memory\_order): block when .load(memory\_order) is equal to old.
  - Similar to condition variables:
  - You need to call .notify\_one() and .notify\_all() after modification to waken up waiting side;
    - And pay attention to possible ABA problem.
  - 2. It may spuriously wake up and do comparison, even if not notified.
- For example, again:

```
int data = 0:
std::atomic<bool> sync1{ false },sync2{ false };
void thread 1()
    data = 442;
                                                   // #0
    sync1.store(true,std::memory_order_release);
void thread_2()
   while(!sync1.load(std::memory_order_acquire)); // #2
   sync2.store(true,std::memory_order_release); // #3
void thread_3()
   while(!sync2.load(std::memory_order_acquire)); // #4
    assert(data == 442);
```

```
int data = 0:
std::atomic<bool> sync1{ false },sync2{ false };
void thread_1()
    data = 442:
                                                   // #0
    sync1.store(true, std::memory_order_release); // #1
    sync1.notify_one();
void thread_2()
    sync1.wait(false, std::memory_order_acquire); // #2
    sync2.store(true, std::memory_order_release); // #3
    sync2.notify_one();
void thread_3()
    sync2.wait(false, std::memory_order_acquire); // #4
                                                   // #5
    assert(data == 442);
```

# spinlock\*

- About how .wait() is implemented, FYI.
  - Windows & MS-STL: by WaitOnAddress if supported in Windows SDK; otherwise by e.g. condition variable.
  - Linux & libstdc++:

```
template<typename _Tp, typename _ValFn>
 void
 __atomic_wait_address_v(const _Tp* __addr, _Tp __old,
                      _ValFn __vfn) noexcept
                                            Memory order is
    _detail::__enters_wait __w(__addr);
                                            contained in vfn.
    _w._M_do_wait_v(__old, __vfn);
                            template<typename Tp, typename ValFn>
                              void
                              M do wait v( Tp old, ValFn vfn)
                                     platform wait t val;
                                    if (_base_type::_M_do_spin_v(_old, __vfn, __val))
                                     _base_type::_M_w._M_do_wait(__base_type::_M_addr, __val)
                               while ( detail:: atomic compare( old, vfn()));
```

For article to introduce it, see <u>Implementing C++20 atomic waiting</u> <u>in libstdc++ | Red Hat Developer</u>.

```
struct default spin policy
template<typename _Up, typename _ValFn,
         typename _Spin = __default_spin_policy
                                                                              bool
 bool
                                                                              operator()() const noexcept
  M do spin v(const Up& old, ValFn vfn,
                                                                              { return false; ]
               platform wait t& val,
               Spin spin = Spin{ })
 { return S do spin v( M addr, old, vfn, val, spin);
                                                                                    template<typename Up, typename ValFn,
                                                                                              typename Spin = default spin policy>
                                                                                       static bool
    template<typename Pred,
                                                                                       S do spin v( platform wait t* addr,
           typename _Spin = __default_spin_policy>
                                                                                                     const Up& old, ValFn vfn,
     bool
      __atomic_spin(_Pred& __pred, _Spin __spin = _Spin{ })                         <mark>noexcept</mark>
                                                                                                     platform wait t& val,
                                                                                                    Spin spin = Spin{ })
                                                     Spin for
       for (auto __i = 0; __i < __atomic_spin_count; ++__i)</pre>
                                                      __atomic_spin
                                                     count times
                                                                                         auto const pred = [=]
          if ( pred())
                                                                                           { return ! detail:: atomic compare( old, vfn()); };
            return true;
                                                "Relax" first
          if ( i < atomic spin count relax)</pre>
                                                                                         if constexpr ( platform wait uses type< Up>)
              detail:: thread relax();
                                                                                              builtin memcpy(& val, & old, sizeof( val));
              detail:: thread yield();
                                                                                         else
       while (__spin())
                             false directly, so
                                                                                              atomic load( addr, & val, ATOMIC ACQUIRE);
          if ( pred())
                             this part is jumped.
            return true;
                                                                                          return __atomic_spin(__pred, __spin);
                       inline constexpr auto __atomic_spin_count_relax = 12;
       return false;
                       inline constexpr auto atomic spin count = 16;
```

```
inline void
    thread yield() noexcept
#if defined GLIBCXX HAS GTHREADS && defined GLIBCXX USE SCHED YIELD
      gthread yield();
#endif
   inline void
    thread relax() noexcept
#if defined i386 || defined x86 64
       builtin ia32 pause();
                                By e.g. PAUSE
#else
                                instruction.
       thread yield();
#endif
```

By futex

```
struct __waiter_pool : __waiter_pool_base
     void
      _M do wait(const __platform wait t* __addr, __platform wait t __old) noexcept
#ifdef _GLIBCXX_HAVE_PLATFORM_WAIT
         _platform_wait(__addr, __old);
#else
        __platform_wait_t __val;
        atomic_load(__addr, &__val, __ATOMIC_SEQ_CST);
       if (__val == old)
           lock guard<mutex> l( M mtx);
            __atomic_load(__addr, &__val, __ATOMIC_RELAXED);
           if (__val == __old)
             _M_cv.wait(_M_mtx);
#endif // GLIBCXX HAVE PLATFORM WAIT
    };
template<typename Tp>
  void
   __platform_wait(const _Tp* __addr, __platform_wait_t __val) noexcept
    auto __e = syscall (SYS_futex, static_cast<const void*>(__addr),
                        static_cast<int>(__futex_wait_flags::__wait_private),
                        val, nullptr);
    if (! e || errno == EAGAIN)
      return;
    if (errno != EINTR)
      throw system error(errno);
```

### Lock-free?

- Finally, usually the reason we use atomic variables instead of lock is that they're more efficient.
  - But are atomic variables really lock-free?
- No, not necessary...
  - C++ does NOT regulate that atomic variables should be lock-free.
  - Common platforms will support small types like integers to be lock-free by atomic instructions in ISA;
    - But if you use a very large struct, then no atomic instruction can do that!
    - Or if your platform only supports very weak ISA, then even not all atomic integers are lock-free...
- Instead, C++ provides interface to check whether it's lock-free.

For non-lock-free atomic types, you may need to link additional libraries; like in gcc and clang you need -latomic.

### Lock-free?

- A constexpr static boolean: std::atomic<T>::is\_always\_lock\_free; only when on the current platform std::atomic<T> is definitely lock-free will it be true.
- A normal function: .is\_lock\_free(); some lock-free types may be only determined in runtime (e.g. when its address are over-aligned).
- C++20 adds some aliases that are guaranteed to be lock-free:

#### Aliases for special-purpose types

```
a signed integral atomic type that is lock-free and for which waiting/notifying is most efficient (typedef)
an unsigned integral atomic type that is lock-free and for which waiting/notifying is most efficient (typedef)

Note: std::atomic_intN_t, std::atomic_uintN_t, std::atomic_intptr_t, and std::atomic_uintptr_t are defined if and only if std::intN_t, std::intptr_t, and std::uintptr_t are defined, respectively.

std::atomic_signed_lock_free and std::atomic_unsigned_lock_free are optional in freestanding implementations.

a signed integral atomic type that is lock-free and for which waiting/notifying is most efficient (typedef)
an unsigned integral atomic type that is lock-free and for which waiting/notifying is most efficient (typedef)
and unsigned_lock_free and std::atomic_uintptr_t, and std::atomic_uintptr_t are defined if and only if std::intN_t, std::atomic_uintptr_t, and std::atomic_uintptr_t are defined in freestanding (since C++20)
```

1. ↑ Support for always lock-free integral atomic types and presence of type aliases std::atomic\_signed\_lock\_free and std::atomic\_unsigned\_lock\_free are implementation-defined in a freestanding implementation.(since C++20)

### atomic\_flag

- Besides, C++ standard regulates a special type to be definitely lock-free: std::atomic flag.
  - It's similar to std::atomic<bool>, but the latter is not regulated to be lockfree.
  - And since its value is either true or false, methods are renamed directly.
  - Read op:
    - .test(memory\_order), since C++20.
  - Write op:
    - .clear(memory\_order): set to false.
  - RMW op:
    - .test\_and\_set(memory\_order): set to true and return the previous test result.
  - Spinlock:
    - .wait(bool old, memory\_order), .notify\_one(), .notify\_all(), since C++20.

# atomic\_flag

### std::atomic\_flag::atomic\_flag

And for ctor:

```
Defined in header <atomic>

atomic_flag() noexcept = default; (since C++11)

constexpr atomic_flag() noexcept; (since C++20)

atomic_flag( const atomic_flag& ) = delete; (2) (since C++11)
```

Constructs a new std::atomic\_flag.

- 1) Trivial default constructor, initializes std::atomic\_flag to unspecified state. (until C++20)
- 1) Initializes std::atomic\_flag to clear state.

(since C++20)

(until C++20)

2) The copy constructor is deleted; std::atomic flag is not copyable.

Before C++20

In addition, std::atomic\_flag can be value-initialized to clear state with the expression ATOMIC\_FLAG\_INIT. For an atomic\_flag with static storage duration, this guarantees static initialization: the flag can be used in constructors of static objects.

### ATOMIC FLAG INIT

```
Defined in header <atomic>
#define ATOMIC FLAG INIT /* implementation-defined */ (since C++11)
```

Defines the initializer which can be used to initialize std::atomic\_flag to clear (false) state in the form std::atomic\_flag v = ATOMIC\_FLAG\_INIT; . It is unspecified if it can be used with other initialization contexts.

If the flag has is a complete object with static storage duration, this initialization is static.

This is the only way to initialize std::atomic\_flag to a definite value: the value held after any other initialization is unspecified.

This macro is no longer needed since default constructor of std::atomic\_flag initializes it to clear state. It is kept for the compatibility with C.

# Advanced Concurrency

- Atomic variables
  - Basic operations
    - atomic\_flag
  - Specializations
    - atomic\_ref

## Specializations

- Some atomic types are specialized to provide more convenient methods; we list them here.
  - Integers: The character types char, char8\_t(since C++20), char16\_t, char32\_t, and wchar\_t;
    - The standard signed integer types: signed char, short, int, long, and long long;
    - The standard unsigned integer types: unsigned char, unsigned short, unsigned int, unsigned long, and unsigned long long;
    - Any additional integral types needed by the typedefs in the header <cstdint>.
  - Floating points (since C++20):

When instantiated with one of the cv-unqualified floating-point types (float, double, long double and cv-unqualified extended floating-point types(since C++23)), std::atomic provides additional atomic operations

And raw pointers. Member types

Туре	Definition	
value_type	T (regardless of whether specialized or not)	
difference_type <sup>[1]</sup>	<pre>value_type (only for atomic<integral> and atomic<floating>(since C++20) specializations)</floating></integral></pre>	
uli refence_type:	<pre>std::ptrdiff_t (only for std::atomic<u*> specializations)</u*></pre>	

## Specializations

- They just add common RMW operators and corresponding function overloads (to provide memory order).
  - Operators: +=, -=, ++, --, &=, |=, ^=;
    - But they do NOT return \*this; except for postfix ++, they return the **new** value (i.e. the stored value).
  - Functions: fetch\_xxx, i.e. fetch\_add/sub/and/or/xor(T, memory\_order).
    - And they return the original value.
  - And another two functions since C++26: fetch\_max/min(T, mo), which writes maximum/minimum value back.
- Floating points only provide +=, -=, add, sub;
- Pointers only provide +=, -=, ++, --, add, sub, max, min;

### Specializations

- Note 1: since C++20, there also exist specializations for std::shared\_ptr and std::weak\_ptr, and we'll talk about them in Memory Management.
- Note 2: atomic pointers do NOT mean you access underlying objects atomically; they mean pointer themselves are atomic.
  - And that's why there are no operator\* and operator-> for atomic pointers.
  - Since C++20, std::atomic\_ref is introduced for that atomic access.

### atomic\_ref

 An example adjusted from C++20 the Complete Guide by Nicolai. M. Josuttis.

 Most of methods in std::atomic\_ref<T> are same as std::atomic<T> as if operating on it directly.

So not listed again.

```
std::array<int, 1000> values;
std::fill_n(values.begin(), values.size(), 100);
std::stop source allStopSource;
std::stop token allStopToken{ allStopSource.get token() };
std::vector<std::jthread> threads;
for (int i = 0; i < 9; ++i)
    threads.push back(std::jthread{
        [&values](std::stop_token st) {
            while (!st.stop_requested())
                std::size t idx = GetRandomIndex(values.size());
                std::atomic ref val{ values[idx] };
                auto newVal = --val;
                if (newVal <= 0)
                    std::println("index {} is zero", idx);
        allStopToken // pass the common stop token
allStopSource.request_stop();
```

### atomic\_ref

- To denote const reference, you can use std::atomic\_ref<const T>; then write operations will be disabled.
  - const std::atomic\_ref<T> is shallow const; as reference itself is already const, this shallow const does nothing.
- 2. When an object is accessed by std::atomic\_ref, you shouldn't
  access it by normal reference and pointers to avoid data races.
  - And of course, you need to ensure the lifetime of referenced object doesn't end (i.e. not dangling reference).
  - And different std::atomic\_ref shouldn't overlap. Formally:

through those atomic\_ref instances. No subobject of the object referenced by atomic\_ref shall be concurrently referenced by any other atomic\_ref object.

### atomic\_ref

- 3. And some unique members:
  - Data members:
    - static constexpr std::size\_t required\_alignment, the referenced object should align with required alignment; otherwise UB.
  - Methods:
    - .address(): since C++26, returning pointer to the referenced object.
    - copy ctor: reference the same object as another std::atomic\_ref.
      - But it's not copy assignable.
- 4. Even if std::atomic<T> is lock free, std::atomic\_ref<T> may
  not be lock free; their implementations are different.