



# **Visual Studio Code MV# Extensions**

#### Copyright © 2018 ONgroup Intl

All rights reserved.

ONgroup Intl make no representations that the use of its products in the manner described in this publication will not infringe on existing or future patent rights, nor do the descriptions contained in this publication imply the granting of licenses to make, use, or sell equipment or software in accordance with the description.

Possession, use, or copying of the software described in this publication is authorized only pursuant to a valid written license from ONgroup Intl or an authorised sub licensor.

Neither ONgroup Intl nor its employees are responsible for any errors that may appear in this publication. The information in this publication is subject to change without notice.

All other trademarks and service marks are property of their respective holders.

# **Contents**

| Prefa | ace        |   | 3 |
|-------|------------|---|---|
| 1     | Introduct  | tion                                    | 4 |
| 2     | Pre Requ   | uisites                                 | 5 |
| 3     | Installing | y Visual Studio Code                    | 6 |
| 4     | Configur   | ing Visual Studio Code for MVON#        | 9 |
| 5     | Connecti   | ing to a MVON# Server1                  | 1 |
|       | 5.1        | Testing the connection1                 | 4 |
|       | 5.2        | Associating Programs with MVON#1        | 6 |
|       | 5.3        | Additional MV# Developer Settings1      | 6 |
| 6     | MV# Dev    | eloper Features1                        | 7 |
|       | 6.1        | Syntax Highlighting1                    | 7 |
|       | 6.2        | Intellisense1                           | 8 |
|       | 6.3        | Find All References1                    | 8 |
|       | 6.4        | Goto/Peek Definition                    | 9 |
|       | 6.5        | Internal Subroutine lookup2             | 0 |
|       | 6.6        | Compiling and Cataloging your programs2 |   |
|       | 6.7        | Formatting Programs2                    | 1 |
| 7     | Connecti   | ing to other MV Platforms2              |   |
|       | 7.1        | Universe2                               | 3 |
|       | 7.2        | Unidata2                                |   |
|       | 7.3        | OpenQM2                                 |   |
|       | 7.4        | jBASE2                                  |   |
|       | 7.5        | D3                                      |   |
|       | 7.6        | Testing remote connectivity             |   |
|       | 7.7        | Debugging remote connection issues      | 9 |
| 8     |            | ugger Extension3                        |   |
|       | 8.1        | Starting the debugger3                  |   |
|       | 8.2        | Debugging features3                     |   |
|       | 8.3        | Call Stack3                             | 5 |
| 9     | MV# TCL    | . Extension3                            |   |
|       | 9.1        | Establishing a TCL session3             |   |
|       | 9.2        | TCL Features4                           |   |
|       | 9.2.       |   |   |
|       | 9.2.       |   |   |
|       | 9.2.       |   |   |
|       | 9.2.       | 4 Dictionary details display4           | 4 |

## **PREFACE**

# Purpose of this guide

This document describes how to use Visual Studio Code as the MVON# Development Environment.

#### 1 Introduction

Visual Studio code is a feature rich IDE that allows programmers to develop and debug code is various languages. MVON# provides developers with the ability to program their MV applications with a variety of program languages including BASIC, C#, Python, JavaScript and Typescript. This makes Visual Studio Code and ideal IDE as it supports all the above languages.

In order to fully utilize the power of VSCODE, ONGroup has built a set of extensions to cater for MVON# BASIC language. There are also extensions to support all the MVON# supported languages.

This extensions includes the following features

- 1. Code highlighting for MV# BASIC Programs
- 2. Intellisense for the MV# BASIC Statements and Functions
- 3. Code folding
- 4. Code formatting
- 5. Goto/Peek Definition. Automatically jump to and peek internal subroutines
- 6. Goto/Peek Definition. Automatically peek/load CALL, CHAIN and INCLUDE routines
- 7. Syntax checking for GOTO/GOSUB's, LOOPS, CASE STATEMENTS and IF THE/ELSE statements
- 8. Access your remote MVON# files and programs
- 9. Find all References of a word in current program
- 10. A visual debugger

Visual Studio Code is available on Windows, Linux and Mac OSX.

# 2 PRE REQUISITES

The following environment is required in order to use Visual Studio Code.

1. Windows, Linux or Mac OSX machine.


## 3 INSTALLING VISUAL STUDIO CODE

Visual Sudio Code can be downloaded from the following link:


https://code.visualstudio.com/Download

You can select the version for operating system. This guide describes how to install the Windows version of Visua; I Studio Code.


Depending on your Window operating system, run either the 32 bit VSCodeUserSetup-ia32-1.26.1.exe or the 64 bit VSCodeUserSetup-x64-1.26.1.exe




Select Next




Accept the License Agreement and select Next



Accept the defaults or specify your folder and select Next



Select the options you would like to include in the install and select **Next** 




Visual Studio Code is now installed.

# 4 CONFIGURING VISUAL STUDIO CODE FOR MVON#.


Before we can start using the MVON# features for Visual Studio Code, we need to install the extensions. VSCODE has a automated download and installation process for extensions.

Start VSCODE and select the Extensions Button



In the search box, type MVON and press enter:

#### Configuring Visual Studio Code for MVON#.



You can select the Developer Extension and the Debugger extension by selecting the download image.

Once the extenions are installed we are ready to start accessing our MVON# server.

## 5 CONNECTING TO A MVON# SERVER


The extenion allows us to connect to connect to remote MVON# servers and edit BASIC programs. We need to configure a **Workspace** that will contain all the paramters required to connect and login to the remote MVON# Server.

The simplist method is to create a directory on your machine where we will save the Workspace definitions. If we have multiple server and multiple accounts on each server, we can create multiple Workspace's that points to a a particular server and account.

In order to connect to a MVON# Server, we required the following information:

- 1. Hostname or IP Address of the MVON# server.
- 2. User name to login into the server
- 3. Password for the user above.
- 4. Account name to connect to on the MVON# Server


To create a new Workspace, select "Save Workspace As" from File Menu. I have created a Folder called VSCODE on the E: drive where I store all my Workspace definitions.



#### Connecting to a MVON# Server

The will create a blank Workspace called Demo that we can now configure to point to our MVON# server.


To configure the connection parameters, select **File**, **Preference**, **Setting** from the menu.



This will bring up the Settings pane in VSCODE, make sure you select the **Workspace Tab**, and then type **mvon** in the search box. This will display a list off all the parameters that can be set for the MV# Developer extenion.

Hover your mouse over a parameter and you will be given the option to **Edit** and **Copy to Settings**.

#### Connecting to a MVON# Server




After adding all the parameters to the workspace, you setting should be like this:

(You can copy and paste the above and make the necessary changes for your system)

This is the base settings required to connect to your MVON# Server. Press Ctl-S to save your settings.

# 5.1 Testing the connection


We can test to if our connection to MVON# works by Pressing **F1**. VSCODE will prompt you for the command to run. Type **Connect** to display all commands with Connect in it and is displays:



Select **Connect to MVON# REST FS** and the extension will connect to the server and retrieve a list of Directory files from the server.

If the connection is sucessful, the following 3 messages will appear at the bottom left of the screen.

#### Connecting to a MVON# Server



# 5.2 Associating Programs with MVON#

Most programming languages have an extension that say what language it is. Python is .py, C# is .cs etc and MV BASIC does not follow this concept.

In order to know that we are editing a BASIC program to enable Syntax highlighting. Intellisense and Linting, we need to tell VSCODE that files in the Workspace are linked to MVON#. This is achieved by adding the following setting to your Workspace settings.

# 5.3 Additional MV# Developer Settings

The following settings are availabel to customise your VSCODE MV# Developer experience.

| Setting                | Description  |
|------------------------|--|
| mvon.margin            | The number of characters to use as a margin when formatting.           |
| mvon.indent            | The number of characters to use when indenting code blocks.            |
| mvon.useCamelCase      | Use Camelcase for Intellisense keywords.                               |
| mvon.ignoreGotoScope   | The linter will not highlight goto that jump into the middle of loops. |
| mvon.formattingEnabled | Set to false to disable code formatting.                               |
|                        |  |

## 6 MV# DEVELOPER FEATURES


The following is a list of features that the extensions offer MV Developers when using VSCODE.

## 6.1 Syntax Highlighting

Code is highlighted based on the current theme selected for VSCODE.

#### 6.2 Intellisense

As you type your program, you will be prompted with available statements and functions including the sytax and description.



#### 6.3 Find All References

You can find all references to a word in your program by **right clicking** on a word and selecting **Find All Refrences** from the menu.

The display consists of 2 panels, the right containing the line that the word is in and the actual code block is in the left. Clicking on a line in the right panel will take you to the code block.

```
331
                 CASE UPCASE(ANS) = 'BLOCK'
332
                    IF BLOCK THEN
                                                                                                                       388
333
                       BLOCK = FALSE
D \Netbasic.BP - 90 references
                                                                            BLOCK = TRUE
325
                 CASE UPCASE(ANS) = 'I' OR UPCASE(ANS) = 'IB' OR UPCASE
                                                                            BLOCK.S = "
326
                    GOSUB 1030
327
                                                                            BLOCK.E = "
328
                                                                            ANS) = 'BLOCK'
329
       *----Toggle Block Confirm
                                                                            IF BLOCK THEN
330
                                                                          BLOCK = FALSE
331
                 CASE UPCASE(ANS) = 'BLOCK'
332
                    IF BLOCK THEN
                                                                            CRT 'BLOCK operation verification = disabled.'
333
                       BLOCK = FALSE
                                                                            BLOCK = TRUE
334
                       CRT 'BLOCK operation verification = disabled.
                                                                           CRT 'BLOCK operation verification = enabled.'
                    END ELSE
335
                                                                            IF BLOCK.S = " OR BLOCK.E = " OR BLOCK.E < B...
336
                       BLOCK = TRUE
                                                                            = " OR BLOCK.E = " OR BLOCK.E < BLOCK.S THEN
                       CRT 'BLOCK operation verification = enabled.'
337
338
                    END
                                                                            = " OR BLOCK.E < BLOCK.S THEN
339
                    GOSUB 1000
                                                                            BLOCK.E < BLOCK.S THEN
340
                                                                            CRT 'BLOCK not set up.':BELL
341
      *----Block Commands
                                                                            CRT 'BLOCK from ':BLOCK.S:' through ':BLOCK.F:'
                   CRT 'BLOCK operation verification = disabled.'
334
```

## 6.4 Goto/Peek Definition.

If you **right click** on a internal or external subroutine name and select **Peek Definition**, a window appears showing the internal or external subroutine.

```
ED \Netbasic.BP
                                                                  1100:*
               IF NOT(FOUND) THEN
999
                 POS = B
                  GOSUB 1000
1000
1001
               END
               RETURN
1002
1003
1004
             -----BLOCK SET COMMANDS <>-----
1005
1006
               IF ANS = '<' OR ANS = '<>' THEN
1997
                 CRT 'Block "FROM" set to line ':POS:'.'
1008
1009
                  BLOCK.S = POS
               END
1010
1011
               IF ANS = '>' OR ANS = '<>' THEN
1012
                  CRT 'Block "THROUGH" set to line ':POS:'.'
                  BLOCK.E = POS
1013
               END
1914
 345
       *----Block Copy Command
346
```

If you select **Goto Defnition**, the cursor is moved to start of the subroutine.

## 6.5 Internal Subroutine lookup


Pressing "Ctl-space" after the word GOTO, GOSUB or GO TO, will allow you to select from defined internal subroutines in your program.

```
56
             If ExitFlag Then
                Answer = "Esc"
57
58
                Return
59
             End
60
          End
61
          Gosub
          screen 2 BuildDefaults
62
          Gosub 🖰 BuildInpValues
63
           If RT T BuildScreenInput
65
           Ret 省 CheckMandatory
66
          End 2 ClearMvWindow
67
          IF RTN 2 DeleteMv
          *KeyIn 🔁 DisplayFunctionKeys
68
          coOrdi 🔁 DisplayMvPage
69
70
          If coO 2 DisplayMvWindow
71
             Con 🖰 DisplayScreen
72
             top 🖰 EnquiryDisplay
73
             top TieldsAffectingOthersLab
74
             width = coOrdinates<3>
75
             height = coOrdinates<4>
76
             add = 1
          End
77
```

# 6.6 Compiling and Cataloging your programs.

Right Clicking inside the code window allows you to select 3 options:

- 1. Catalog Basic Program catalogs the BASIC program
- 2. Compile Basic Program compiles the basic program.
- 3. Compile Basic Program with Debug compiles with the debug flag set.



After the option is selected, the results will be displayed in message box at the bottom of the screen. If an error is detected, the editor will place the cursor on the line where error occus.

# **6.7 Formatting Programs**

**Right Clicking** and selecting **Format Document**, will format your BASIC program. The formatting is based on the 2 settings, **mvon.indent** and **mvon.margin** that have default values of 3 and 5.

## 7 CONNECTING TO OTHER MV PLATFORMS

The VSCODE MV# Developer extensions all you to connect to the most MV platforms and provides all the features described above. The MvonGetway is a windows service that acts as a router to access each of the different MV platforms.

As each platform might require different parameters, a Workspace configuration example is provided for each of the following MV platforms.

- 1. Universe
- 2. Unidata
- 3. OpenQM
- 4. jBASE
- 5. D3
- 6. MyBase

The path to the Gateway Installation media is:

C:\Users\{User Name}\.vscode\extensions\ongroup.mvon-1.85.0\Gateway

It is a standard Windows installer module. Copy the installer to the machine that is going to run the Gateway and install. The Gateway exposes a REST File System that can be accessed via VSCODE. The port that REST pipeline is listening on is defaulted to 9005.

## 7.1 Universe

```
{
    "folders":[
        {
            "uri": "RestFS:/",
            "name": "Account - Universe",
        }
    ],
    "settings": {
        "mvon.RestPath": "http://localhost:9005/,
        "mvon.UseGateway": true,
        "mvon.RemoteHost": "192.168.137.102",
        "mvon.GatewayType": "Universe",
        "mvon.UserName": "mvon",
        "mvon.Password": "mvon#",
        "mvon.Account": "SUPER-GROUP",
        "files.associations": {"*":"mvon"}
    }
}
```

| Setting          |                       | Description  |
|------------------|-----------------------|--|
| mvon.useGateway  | true                  | Indicate that the gateway must be used.  |
| mvon.RestPath    | http://localhost:9005 | Path to Gateway  |
| mvon.remoteHost  | 192.168.137.102       | The servers IP/Host name that is running the Universe Database.  |
| mvon.gatewayType | Universe              | Connecting to a Universe server  |
| mvon.UserName    | mvon                  | The Windows/UNIX user id to log into the server.   |
| mvon.Password    | mvon#                 | The password for the user above.   |
| mvon.Account     | SUPER-GROUP           | The account name on Universe to connect to. This must be defined in the UV.ACCOUNT file in the UV account. |

## 7.2 Unidata

```
{
    "folders":[
        {
            "uri": "RestFS:/",
            "name": "Account - SUPER-GROUP",
        }
    ],
    "settings": {
        "mvon.UseGateway": true,
        "mvon.RemoteHost": "192.168.137.102",
        "mvon.gatewayType": "Unidata",
        "mvon.UserName": "mvon",
        "mvon.Password": "mvon#",
        "mvon.Account": "SUPER-GROUP",
        "mvon.AccountPath": "/usr/data/SUPER-GROUP",
        "files.associations": {"*":"mvon"}
   }
}
```

| Setting          |                       | Description  |
|------------------|-----------------------|--|
| Mvon.UseGateway  | true                  | Indicate that the gateway must be used.                        |
| mvon.RestPath    | http://localhost:9005 | Path to Gateway  |
| mvon.RemoteHost  | 192.168.137.102       | The servers IP/Host name that is running the Unidata Database. |
| mvon.GatewayType | Unidata               | Connecting to a Unidata server                                 |
| mvon.Password    | mvon#                 | The password for the user above.                               |
| Mvon.Account     | SUPER-GROUP           | A name for this account.                                       |
| Mvon.AccountPath | /usr/SUPER-GROUP      | The path on the Unidata machine to the Unidata account.        |

# 7.3 OpenQM

```
{
    "folders":[
        {
            "uri": "RestFS:/",
            "name": "Account - PRC",
        }
    ],
    "settings": {
        "mvon.UseGateway": true,
        "mvon.RemoteHost": "192.168.137.102",
        "mvon.gatewayType": "QM",
        "mvon.UserName": "mvon",
        "mvon.Password": "mvon#",
        "mvon.Account": "PRC",
        "files.associations": {"*":"mvon"}
    }
}
```

| Setting          |                 | Description  |
|------------------|-----------------|--|
| Mvon.useGateway  | true            | Indicate that the gateway must be used.  |
| mvon.remoteHost  | 192.168.137.102 | The servers IP/Host name that is running the OpenQM Database.  |
| mvon.gatewayType | QM              | Connecting to a OpenQM server  |
| mvon.UserName    | mvon            | The Windows/UNIX user id to log into the server.   |
| mvon.Password    | mvon#           | The password for the user above.   |
| Mvon.Account     | PRC             | The account name on the QM server to connect to. This must be defined in the ACCOUNTS file in the QMSYS account. |

# 7.4 jBASE

```
{
    "folders":[
        {
            "uri": "GatewayFS:/",
            "name": "Account - PRC",
        }
    ],
    "settings": {
        "mvon.useGateway": true,
        "mvon.remoteHost": "192.168.137.102",
        "mvon.gatewayType": "jBASE",
        "mvon.gatewayPort": 9004,
        "mvon.gatewayHost": "154.73.73.6",
        "mvon.UserName": "mvon",
        "mvon.Password": "mvon#",
        "mvon.Account": "",
        "files.associations": {"*":"mvon"}
    }
}
```

| Setting          |                 | Description   |
|------------------|-----------------|---|
| Mvon.useGateway  | true            | Indicate that the gateway must be used.                                   |
| mvon.remoteHost  | 192.168.137.102 | The servers IP name that is running the jBASE Database.                   |
| mvon.gatewayType | jBASE           | Connecting to a jBASE server  |
| mvon.gatewayPort | 9004            | The default port number that the Gateway is listening for connections on. |
| mvon.UserName    | mvon            | The Windows/UNIX user id to log into the server.                          |
| mvon.Password    | mvon#           | The password for the user above.  |
| Mvon.Account     |                 | This is blank, jBASE uses the default path of the user for the account.   |

A record in the **MD** called **MVONFILES** can used as a list of available files, alternatively all files are displayed.

#### 7.5 D3


```
{
    "folders":[
        {
            "uri": "GatewayFS:/",
            "name": "Account - DM",
        }
    ],
    "settings": {
        "mvon.useGateway": true,
        "mvon.remoteHost": "192.168.137.102",
        "mvon.gatewayType": "D3",
        "mvon.gatewayPort": 9004,
        "mvon.gatewayHost": "154.73.73.6",
        "mvon.UserName": "dm",
        "mvon.AccountPassword": "",
        "mvon.Account": "dm",
        "files.associations": {"*":"mvon"}
    }
}
```

| Setting              |                 | Description   |
|----------------------|-----------------|---|
| Mvon.useGateway      | true            | Indicate that the gateway must be used.                                   |
| mvon.remoteHost      | 192.168.137.102 | The servers IP name that is running the D3 Database.                      |
| mvon.gatewayType     | D3              | Connecting to a D3 server   |
| mvon.gatewayPort     | 9004            | The default port number that the Gateway is listening for connections on. |
| mvon.UserName        | dm              | The D3 User name to log in with   |
| mvon.AccountPassword |                 | Specify the account password if a password is set on the account.         |
| Mvon.Account         | dm              | The D3 account to connect to.   |

MSVP must be configured for the above account and the user must have MSVP access. A record in the **MD** called **VSCODEFILES** can used as a list of available files, alternatively all files are displayed.

# 7.6 Testing remote connectivity

Once your Workspace is configured for your MV platform, you can connect to your MV Platform by pressing **F1** in VSCODE and type Connect in the search field.



Select the **Connect to MVON# Gateway** option. Once the connection is successful, a list of files will be displayed in the Files pane.

# 7.7 Debugging remote connection issues

There is an additional parameter that can be specified in your Workspace

```
"mvon.gatewayDebug": true
```

When this is specified, the MVON# Gateway will write a log of any issues encountered while connecting to your remote MV platform. This can be used to identify any setup issues:

The log file is created in c:\temp called mvonGateway.log

## 8 MV# DEBUGGER EXTENSION

The MVON# Debugger extension enables powerful visual debugging of your MVON# BASIC programs. This feature is ONLY available for MVON# as MVON# supports the real time debugging protocol required by VSCODE.

In order to debug BASIC programs in VSCODE, they programs need to be compiled using the debug option. You can select **Compile Basic program with Debug** by right clicking in the code editor or alternatively you can compile from the command line using:

#### **BASIC BP XX (D**

To enable debugging in VSCODE when need to tell our MVON# environment that the VSCODE debugging is available. An entry VSCODEDEBUG must added to the MVON.CONFIG if the VOC


>CT VOC MVON.CONFIG

MVON.CONFIG


0001 VSCODEDEBUG

## 8.1 Starting the debugger

You need to first load the subroutine that you wish to debug into the code editor. Place a DEBUG statement just prior top where you want the debugging to start and compile the program with debug.



We start the debugger by pressing F5 in the editor window and selecting MVON# Debug from the drop down list:




The debug menu bar will appear to indicate the the debugger is now active.

You can now run you BASIC program and when the program gets the DEBUG point, VSCODE will automatically display the debug panel and the current line of code will be highlighted.

# 8.2 Debugging features

You can step through your code by pressing **F10**, the debugger will move to the next line to be executed. Pressing **F5**, will continue with the program until the next DEBUG statement, breakpoint or the rpgram terminates



If you hover your cursor above a variable, the contents of the variable are displayed in a panel.


A list of all variables and their contents are displayed in the Variables pane on the left hand side:



These values are automatically updated as you step through your code.


#### 8.3 Call Stack

The call stack is powerful deature of the MVON# debugger. It shows the trace of all the programs called and the line number that they were called on>



If no line number is displayed, the program was not compiled with the DEBUG flag.

The call stack is interactive and if you select an entry from the call stack, the editor automatically loads the program and shows you the line where the program was called from



All variable information for the entire call stack is passed to the debugger so you can interogate any variable in any of the programs in the call stack.

## 9 MV# TCL EXTENSION

The MV# TCL Extension gives intellisense, syntax highlighting and syntax checking to a TCL session. It also starts an interactive terminal session where you can execute and see the results of your TCL statements.

Currently the TCL language support is based on MVON#, other MV dialects will be included in the future.

You must have already created the correct settings to connect to your MV platform as described in the above section of the document.

A TCL session is created by opening or creating a document that has a .tcl suffix.

If your target MV platform is not MVON#, you will also need to install the MvonGateway as described in the above section. The Gateway must be the latest that can be found in the path:

#### C:\Users\{User Name}\.vscode\extensions\ongroup.tcl-0.1.0\Gateway


The following additional setting need to be configured for the TCL extension

| Setting        | Description  |
|----------------|--|
| tcl.sshCommand | The command to invoke a session on your MV platform. This can be telnet of ssh if your platform supports it.   |
| tcl.parameters | Parameters to pass to the session once it has been established. This could include login credentials and a LOGTO the account you wish the TCL session to be active in. |

```
"tcl.parameters": [
    "Grant Hart",
    "xxxxxxxx$",
    "LOGTO PRC"
],
"tcl.sshCommand": "telnet localhost 2023",
```


# 9.1 Establishing a TCL session.

Open a document with the suffix of .tcl. and right click in the editor window:



Select the Connect to MV TCL option from the menu bar. This will open a new terminal session and execute the command you configured in the tcl settings.

#### **MV# TCL Extension**




You can right click on the editor window and select Send Parameters to TCL shell from the menu bar to pass the parameters to the session. This automatically connects to you MV platform and loads a list of files that exist in the specified account.

## 9.2 TCL Features


#### 9.2.1 Intellisense

As you begin typing a list of available TCL commands are displayed for your selection. It also display the syntax that will be required.




The intellisence takes congnisance of the type of TCL sentence you are creating and will display a list of filenames, dictionary names and item names if your sentence requires them.

#### **MV# TCL Extension**



## 9.2.2 Automatically execute script lines


You can execute the current statement by **pressing F5** on the line you wish to execute:



Multiple statements can be executed by select the lines you wish to execute and then pressing F5.

## 9.2.3 Error highlighting

You extension evaluates you statement and highlights any errors it have found like invalid files names and invalid dictionary items.



## 9.2.4 Dictionary details display

If you hover your mouse over a dictionary item, the details of that dictionary item are displayed.

