

# Cloudera Security



#### **Important Notice**

(c) 2010-2015 Cloudera, Inc. All rights reserved.

Cloudera, the Cloudera logo, Cloudera Impala, and any other product or service names or slogans contained in this document are trademarks of Cloudera and its suppliers or licensors, and may not be copied, imitated or used, in whole or in part, without the prior written permission of Cloudera or the applicable trademark holder.

Hadoop and the Hadoop elephant logo are trademarks of the Apache Software Foundation. All other trademarks, registered trademarks, product names and company names or logos mentioned in this document are the property of their respective owners. Reference to any products, services, processes or other information, by trade name, trademark, manufacturer, supplier or otherwise does not constitute or imply endorsement, sponsorship or recommendation thereof by us.

Complying with all applicable copyright laws is the responsibility of the user. Without limiting the rights under copyright, no part of this document may be reproduced, stored in or introduced into a retrieval system, or transmitted in any form or by any means (electronic, mechanical, photocopying, recording, or otherwise), or for any purpose, without the express written permission of Cloudera.

Cloudera may have patents, patent applications, trademarks, copyrights, or other intellectual property rights covering subject matter in this document. Except as expressly provided in any written license agreement from Cloudera, the furnishing of this document does not give you any license to these patents, trademarks copyrights, or other intellectual property. For information about patents covering Cloudera products, see http://tiny.cloudera.com/patents.

The information in this document is subject to change without notice. Cloudera shall not be liable for any damages resulting from technical errors or omissions which may be present in this document, or from use of this document.

Cloudera, Inc. 1001 Page Mill Road Bldg 2 Palo Alto, CA 94304 info@cloudera.com US: 1-888-789-1488 Intl: 1-650-362-0488 www.cloudera.com

#### Release Information

Version: 5.4.x Date: May 20, 2015

# **Table of Contents**

About this Guide	7
Authentication	8
Configuring Authentication in Cloudera Manager	8
Cloudera Manager User Accounts	
Configuring External Authentication for Cloudera Manager	10
Kerberos Principals and Keytabs	16
Enabling Kerberos Authentication Using the Wizard	16
Enabling Kerberos Authentication for Single User Mode or Non-Default Users	26
Configuring a Cluster with Custom Kerberos Principals	27
Viewing and Regenerating Kerberos Principals	29
Mapping Kerberos Principals to Short Names	29
Configuring Kerberos for Flume Thrift Source and Sink	3
Configuring YARN for Long-running Applications	32
Enabling Kerberos Authentication Without the Wizard	33
Configuring Authentication in Cloudera Navigator	44
Configuring External Authentication for Cloudera Navigator	
Managing Users and Groups for Cloudera Navigator	49
Configuring Authentication in CDH Using the Command Line	50
Enabling Kerberos Authentication for Hadoop Using the Command Line	51
Flume Authentication	
HBase Authentication	76
HCatalog Authentication	8
Hive Authentication	84
HttpFS Authentication	91
Hue Authentication	94
Impala Authentication	104
Llama Authentication	109
Oozie Authentication	109
Search Authentication	11
Spark Authentication	115
Sqoop Authentication	116
ZooKeeper Authentication	116
FUSE Kerberos Configuration	118
Using kadmin to Create Kerberos Keytab Files	119
Configuring the Mapping from Kerberos Principals to Short Names	120
Enabling Debugging Output for the Sun Kerberos Classes	12

Configuring a Cluster-dedicated MIT KDC with Cross-Realm Trust	
When to use kadmin.local and kadmin	
Setting up a Cluster-Dedicated KDC and Default Realm for the Hadoop Cl	
Integrating Hadoop Security with Active Directory	
Configuring a Local MIT Kerberos Realm to Trust Active Directory	
Integrating Hadoop Security with Alternate Authentication	
Configuring the AuthenticationFilter to use Kerberos	
Creating an AltKerberosAuthenticationHandler Subclass	
Enabling Your AltKerberosAuthenticationHandler Subclass	
Example Implementation for Oozie	
Configuring LDAP Group Mappings	
Using Cloudera Manager	
Using the Command Line	
Hadoop Users in Cloudera Manager and CDH	
Authenticating Kerberos Principals in Java Code	142
Using a Web Browser to Access an URL Protected by Kerberos HTTP	SPNEGO142
Troubleshooting Authentication Issues	145
Sample Kerberos Configuration files: krb5.conf, kdc.conf, kadm5.acl	145
Potential Security Problems and Their Solutions	147
Encryption	156
SSL Certificates Overview	
Creating Certificates	
Creating Java Keystores and Truststores Private Key and Certificate Reuse Across Java Keystores and OpenSSL	
Configuring TLS Security for Cloudera Manager	
Configuring TLS Encryption Only for Cloudera Manager	
Level 1: Configuring TLS Encryption for Cloudera Manager Agents	
Level 2: Configuring TLS Verification of Cloudera Manager Server by the A Level 3: Configuring TLS Authentication of Agents to the Cloudera Manag	
HTTPS Communication in Cloudera Manager	
Troubleshooting SSL/TLS Connectivity	
Configuring SSL for Cloudera Navigator	
Configuring SSL for Cloudera Management Services	
Configuring Encryption for Hadoop Services	
Prerequisites	
Hadoop Services as SSL Servers and Clients	
Configuring SSI for HDES YARN and ManReduce	
Configuring SSL for HDFS, YARN and MapReduce	
Configuring SSL for Flymo Thrift Source and Sink	
Configuring Encrypted Communication Botwoon Hive and Client Drivers	
Configuring Encrypted Communication Between Hive and Client Drivers  Configuring SSL for Hue	
CUITIZUITIZ 33L TUI FIUE	186

Configuration CCI for Oppin	188
Configuring SSL for Oozie	189
Configuring SSL for Solr	191
Configuring HttpFS to use SSL	194
Encrypted Shuffle and Encrypted Web Uls	195
HDFS Data At Rest Encryption	201
Use Cases	201
Architecture	201
crypto Command Line Interface	202
Enabling HDFS Encryption on a Cluster	203
DistCp Considerations	207
Attack Vectors	208
Configuring the Key Management Server (KMS)	209
Securing the Key Management Server (KMS)	212
Configuring CDH Services for HDFS Encryption	
Troubleshooting HDFS Encryption	223
Configuring Encrypted HDFS Data Transport	225
Using Cloudera Manager	225
Using the Command Line	225
User Roles	227
User Roles  Determining the Role of the Currently Logged in User	227
Determining the Role of the Currently Logged in User	227 229
User Roles  Determining the Role of the Currently Logged in User  Removing the Full Administrator User Role  Cloudera Navigator User Roles	227 229 229
User Roles  Determining the Role of the Currently Logged in User  Removing the Full Administrator User Role  Cloudera Navigator User Roles  User Roles	227 229 229 229
User Roles  Determining the Role of the Currently Logged in User  Removing the Full Administrator User Role  Cloudera Navigator User Roles  User Roles  Determining the Roles of the Currently Logged in User	
User Roles  Determining the Role of the Currently Logged in User  Removing the Full Administrator User Role  Cloudera Navigator User Roles  User Roles  Determining the Roles of the Currently Logged in User  HDFS Extended ACLs	
User Roles  Determining the Role of the Currently Logged in User  Removing the Full Administrator User Role  Cloudera Navigator User Roles  User Roles  Determining the Roles of the Currently Logged in User  HDFS Extended ACLs  Enabling ACLs	
User Roles  Determining the Role of the Currently Logged in User  Removing the Full Administrator User Role  Cloudera Navigator User Roles  User Roles  Determining the Roles of the Currently Logged in User  HDFS Extended ACLs  Enabling ACLs  Commands	
User Roles  Determining the Role of the Currently Logged in User  Removing the Full Administrator User Role  Cloudera Navigator User Roles  User Roles  Determining the Roles of the Currently Logged in User  HDFS Extended ACLs  Enabling ACLs  Commands  Authorization With Apache Sentry (Incubating)	
User Roles  Determining the Role of the Currently Logged in User  Removing the Full Administrator User Role  Cloudera Navigator User Roles  User Roles  Determining the Roles of the Currently Logged in User  HDFS Extended ACLs  Enabling ACLs  Commands  Authorization With Apache Sentry (Incubating)  Architecture Overview	
User Roles  Determining the Role of the Currently Logged in User  Removing the Full Administrator User Role  Cloudera Navigator User Roles  User Roles  Determining the Roles of the Currently Logged in User  HDFS Extended ACLs  Enabling ACLs  Commands  Authorization With Apache Sentry (Incubating)  Architecture Overview  Sentry Integration with the Hadoop Ecosystem	
User Roles  Determining the Role of the Currently Logged in User  Removing the Full Administrator User Role  Cloudera Navigator User Roles  User Roles  Determining the Roles of the Currently Logged in User  HDFS Extended ACLs  Enabling ACLs  Commands  Authorization With Apache Sentry (Incubating)  Architecture Overview  Sentry Integration with the Hadoop Ecosystem  The Sentry Service	
User Roles  Determining the Role of the Currently Logged in User  Removing the Full Administrator User Role  Cloudera Navigator User Roles  User Roles  Determining the Roles of the Currently Logged in User  HDFS Extended ACLs  Enabling ACLs  Commands  Authorization With Apache Sentry (Incubating)  Architecture Overview  Sentry Integration with the Hadoop Ecosystem  The Sentry Service  Sentry Policy File Authorization	
User Roles  Determining the Role of the Currently Logged in User  Removing the Full Administrator User Role  Cloudera Navigator User Roles  User Roles  Determining the Roles of the Currently Logged in User  HDFS Extended ACLs  Enabling ACLs  Commands  Authorization With Apache Sentry (Incubating)  Architecture Overview  Sentry Integration with the Hadoop Ecosystem  The Sentry Service  Sentry Policy File Authorization  Enabling Sentry Authorization for Impala	
User Roles  Determining the Role of the Currently Logged in User  Removing the Full Administrator User Role  Cloudera Navigator User Roles  User Roles  Determining the Roles of the Currently Logged in User  HDFS Extended ACLs  Enabling ACLs  Commands  Authorization With Apache Sentry (Incubating)  Architecture Overview  Sentry Integration with the Hadoop Ecosystem  The Sentry Service  Sentry Policy File Authorization  Enabling Sentry Authorization for Impala  Enabling Sentry Authorization for Search using the Command Line.	
User Roles  Determining the Role of the Currently Logged in User  Removing the Full Administrator User Role  Cloudera Navigator User Roles  User Roles  Determining the Roles of the Currently Logged in User  HDFS Extended ACLs  Enabling ACLs  Commands  Authorization With Apache Sentry (Incubating)  Architecture Overview  Sentry Integration with the Hadoop Ecosystem  The Sentry Service  Sentry Policy File Authorization  Enabling Sentry Authorization for Impala  Enabling Sentry Authorization for Search using the Command Line  Configuring HBase Authorization	
User Roles  Determining the Role of the Currently Logged in User  Removing the Full Administrator User Role  Cloudera Navigator User Roles  User Roles  Determining the Roles of the Currently Logged in User  HDFS Extended ACLs  Enabling ACLs  Commands  Authorization With Apache Sentry (Incubating)  Architecture Overview  Sentry Integration with the Hadoop Ecosystem  The Sentry Service  Sentry Policy File Authorization  Enabling Sentry Authorization for Impala  Enabling Sentry Authorization for Search using the Command Line  Configuring HBase Authorization  Understanding HBase Access Levels	
User Roles  Determining the Role of the Currently Logged in User  Removing the Full Administrator User Role  Cloudera Navigator User Roles  User Roles  Determining the Roles of the Currently Logged in User  HDFS Extended ACLs  Enabling ACLs  Commands  Authorization With Apache Sentry (Incubating)  Architecture Overview  Sentry Integration with the Hadoop Ecosystem  The Sentry Service  Sentry Policy File Authorization  Enabling Sentry Authorization for Impala  Enabling Sentry Authorization for Search using the Command Line  Understanding HBase Access Levels  Enable HBase Authorization	
User Roles  Determining the Role of the Currently Logged in User  Removing the Full Administrator User Role  Cloudera Navigator User Roles  User Roles  Determining the Roles of the Currently Logged in User  HDFS Extended ACLs  Enabling ACLs  Commands  Authorization With Apache Sentry (Incubating)  Architecture Overview  Sentry Integration with the Hadoop Ecosystem  The Sentry Service  Sentry Policy File Authorization  Enabling Sentry Authorization for Impala  Enabling Sentry Authorization for Search using the Command Line  Configuring HBase Authorization  Understanding HBase Access Levels	

Sensitive Data Redaction	301
Enabling Log and Query Redaction Using Cloudera Manager	302
Configuring Cloudera Navigator to Redact Personally Identifiable Information	
Overview of Impala Security	304
Security Guidelines for Impala	305
Securing Impala Data and Log Files	305
Installation Considerations for Impala Security	306
Securing the Hive Metastore Database	306
Securing the Impala Web User Interface	
Miscellaneous Topics	308
Jsvc, Task Controller and Container Executor Programs	308
MRv1 and YARN: The jsvc Program	308
MRv1 Only: The Linux TaskController Program	308
YARN Only: The Linux Container Executor Program	308
Task-controller and Container-executor Error Codes	
MRv1 ONLY: Task-controller Error Codes	309
YARN ONLY: Container-executor Error Codes	311
Sqoop, Pig, and Whirr Security Support Status	312
Setting Up a Gateway Node to Restrict Cluster Access	313
Installing and Configuring the Firewall and Gateway	313
Accessing HDFS	313
Submitting and Monitoring Jobs	314
Logging a Security Support Case	314
Kerberos Issues	314
SSL/TLS Issues	314
LDAP Issues	315

# About this Guide

This guide is intended for system administrators who want to secure a cluster using data encryption, user authentication, and authorization techniques. This topic also provides information about Hadoop security programs and shows you how to set up a gateway to restrict access.

The purpose of authentication in Hadoop, as in other systems, is simply to prove that a user or service is who he or she claims to be.

Typically, authentication in enterprises is managed through a single distributed system, such as a Lightweight Directory Access Protocol (LDAP) directory. LDAP authentication consists of straightforward username/password services backed by a variety of storage systems, ranging from file to database.

A common enterprise-grade authentication system is Kerberos. Kerberos provides strong security benefits including capabilities that render intercepted authentication packets unusable by an attacker. It virtually eliminates the threat of impersonation by never sending a user's credentials in cleartext over the network.

Several components of the Hadoop ecosystem are converging to use Kerberos authentication with the option to manage and store credentials in LDAP or AD. For example, Microsoft's Active Directory (AD) is an LDAP directory that also provides Kerberos authentication for added security.

Before you use this guide to configure Kerberos on your cluster, ensure you have a working KDC (MIT KDC or Active Directory), set up. You can then use Cloudera Manager's Kerberos wizard to automate several aspects of Kerberos configuration on your cluster.

## Important:

- You can use either Cloudera Manager or the following command-line instructions to complete this configuration.
- This information applies specifically to CDH 5.4.x. If you use an earlier version of CDH, see the documentation for that version located at Cloudera Documentation.

# Configuring Authentication in Cloudera Manager

#### Why Use Cloudera Manager to Implement Kerberos Authentication?

If you don't use Cloudera Manager to implement Hadoop security, you must manually create and deploy the Kerberos principals and keytabs on every host in your cluster. If you have a large number of hosts, this can be a time-consuming and error-prone process. After creating and deploying the keytabs, you must also manually configure properties in the core-site.xml, hdfs-site.xml, mapred-site.xml, and taskcontroller.cfg files on every host in the cluster to enable and configure Hadoop security in HDFS and MapReduce. You must also manually configure properties in the <code>oozie-site.xml</code> and hue.ini files on certain cluster hosts in order to enable and configure Hadoop security in Oozie and Hue.

Cloudera Manager enables you to automate all of those manual tasks. Cloudera Manager can automatically create and deploy a keytab file for the hdfs user and a keytab file for the mapred user on every host in your cluster, as well as keytab files for the oozie and hue users on select hosts. The hdfs keytab file contains entries for the hdfs principal and a host principal, and the mapred keytab file contains entries for the mapred principal and a host principal. The host principal will be the same in both keytab files. The oozie keytab file contains entries for the oozie principal and a HTTP principal. The hue keytab file contains an entry for the hue principal. Cloudera Manager can also automatically configure the appropriate properties in the core-site.xml, hdfs-site.xml, mapred-site.xml, and taskcontroller.cfg files on every host in the cluster, and the appropriate properties in oozie-site.xml and hue.ini for select hosts. Lastly, Cloudera Manager can automatically start up the NameNode, DataNode, Secondary NameNode, JobTracker, TaskTracker, Oozie Server, and Hue roles once all the appropriate configuration changes have been made.

### Ways to Configure Kerberos Authentication Using Cloudera Manager

You can use *one* of the following ways to set up Kerberos authentication on your cluster using Cloudera Manager:

- Cloudera Manager 5.1 introduced a new wizard to automate the procedure to set up Kerberos on a cluster. Using the KDC information you enter, the wizard will create new principals and keytab files for your CDH services. The wizard can be used to deploy the krb5.conf file cluster-wide, and automate other manual tasks such as stopping all services, deploying client configuration and restarting all services on the cluster.
  - If you want to use the Kerberos wizard, follow the instructions at Enabling Kerberos Authentication Using the Wizard on page 16.
- If you do not want to use the Kerberos wizard, follow the instructions at <u>Enabling Kerberos Authentication</u> Without the Wizard on page 33.

## Cloudera Manager User Accounts

#### User Administrator Full Administrator Required Role:

Access to Cloudera Manager features is controlled by user accounts. A user account identifies how a user is authenticated and determines what privileges are granted to the user.

When you are logged in to the Cloudera Manager Admin Console, the username you are logged in as is at the far right of the top navigation bar—for example, if you are logged in as *admin* you will see 👤 admin

A user with the User Administrator or Full Administrator role manages user accounts through the Administration > Users page.

#### User Authentication

Cloudera Manager provides several mechanisms for authenticating users. You can configure Cloudera Manager to authenticate users against the Cloudera Manager database or against an external authentication service. The external authentication service can be an LDAP server (Active Directory or an OpenLDAP compatible directory), or you can specify another external service. Cloudera Manager also supports using the Security Assertion Markup Language (SAML) to enable single sign-on.

If you are using LDAP or another external service you can configure Cloudera Manager so that it can use both methods of authentication (internal database and external service), and you can determine the order in which it performs these searches. If you select an external authentication mechanism, Full Administrator users can always authenticate against the Cloudera Manager database. This is to prevent locking everyone out if the authentication settings are misconfigured—such as with a bad LDAP URL.

With external authentication, you can restrict login access to members of specific groups, and can specify groups whose members are automatically given Full Administrator access to Cloudera Manager.

Users accounts in the Cloudera Manager database page show Cloudera Manager in the User Type column. User accounts in an LDAP directory or other external authentication mechanism show External in the User Type column.

## User Roles

User accounts include the user's role, which determines the Cloudera Manager features visible to the user and the actions the user can perform. All the tasks in the Cloudera Manager documentation indicate which role is required to perform the task. For more information about user roles, see <u>Cloudera Manager User Roles</u> on page 227.

## Determining the Role of the Currently Logged in User

1. Click the logged-in username at the far right of the top navigation bar. The role displays right under the username. For example:



## Changing the Logged-In Internal User Password

- 1. Right-click the logged-in username at the far right of the top navigation bar and select Change Password.
- 2. Enter the current password and a new password twice, and then click **Update**.

## Adding an Internal User Account

- Select Administration > Users.
- 2. Click the Add User button.
- **3.** Enter a username and password.
- 4. In the Role drop-down, select a role for the new user.
- 5. Click Add.

## **Assigning User Roles**

- Select Administration > Users.
- 2. Check the checkbox next to one or more usernames.
- 3. Select Actions for Selected > Assign User Roles.
- **4.** In the drop-down, select the role.
- 5. Click the Assign Role button.

## Changing an Internal User Account Password

- Select Administration > Users.
- 2. Click the Change Password button next to a username with User Type Cloudera Manager.
- **3.** Type the new password and repeat it to confirm.
- 4. Click the Update button to make the change.

## **Deleting Internal User Accounts**

- 1. Select Administration > Users.
- 2. Check the checkbox next to one or more usernames with User Type Cloudera Manager.
- Select Actions for Selected > Delete.
- 4. Click the OK button. (There is no confirmation of the action.)

## Configuring External Authentication for Cloudera Manager

#### Required Role: User Administrator **Full Administrator**

**Important:** This feature is available only with a Cloudera Enterprise license; it is not available in Cloudera Express. For information on Cloudera Enterprise licenses, see Managing Licenses.

Cloudera Manager supports user authentication against an internal database and against an external service. The following sections describe how to configure the supported external services.

## Configuring Authentication Using Active Directory

- Select Administration > Settings.
- 2. In the left-hand column, select the External Authentication category.
- 3. In the Authentication Backend Order field, select the order in which Cloudera Manager should attempt its authentication. You can choose to authenticate users using just one of the methods (using Cloudera Manager's

own database is the default), or you can set it so that if the user cannot be authenticated by the first method, it will attempt using the second method.

- 4. For External Authentication Type, select Active Directory.
- 5. In the LDAP URL property, provide the URL of the Active Directory server.
- 6. In the Active Directory NT Domain property, provide the NT domain to authenticate against.
- 7. In the LDAP User Groups property, optionally provide a comma-separated list of case-sensitive LDAP group names. If this list is provided, only users who are members of one or more of the groups in the list will be allowed to log into Cloudera Manager. If this property is left empty, all authenticated LDAP users will be able to log into Cloudera Manager. For example, if there is a group called CN=ClouderaManagerUsers,OU=Groups,DC=corp,DC=com,add the group name ClouderaManagerUsers to the LDAP User Groups list to allow members of that group to log in to Cloudera Manager.
- 8. To automatically assign a role to users when they log in, provide a comma-separated list of LDAP group names in the following properties:
  - LDAP Full Administrator Groups
  - LDAP User Administrator Groups
  - LDAP Cluster Administrator Groups
  - LDAP BDR Administrator Groups
  - LDAP Configurator Groups
  - LDAP Navigator Administrator Groups
  - LDAP Operator Groups
  - LDAP Limited Operator Groups
  - LDAP Auditor Groups

If you specify groups in these properties, users must also be a member of at least one of the groups specified in the LDAP User Groups property or they will not be allowed to log in. If these properties are left empty, users will be assigned to the Read-Only role and any other role assignment must be performed manually by an Administrator.

**Note:** A user that is added to an LDAP group will not automatically be assigned the corresponding role in the internal Cloudera Manager database. Hence, the Users page in Cloudera Manager will display such users' roles as Read-Only, as this page only queries the Cloudera Manager database, and not LDAP.

## Configuring Authentication Using an OpenLDAP-compatible Server

For an OpenLDAP-compatible directory, you have several options for searching for users and groups:

- You can specify a single base Distinguished Name (DN) and then provide a "Distinguished Name Pattern" to use to match a specific user in the LDAP directory.
- Search filter options let vou search for a particular user based on somewhat broader search criteria for example Cloudera Manager users could be members of different groups or organizational units (OUs), so a single pattern won't find all those users. Search filter options also let you find all the groups to which a user belongs, to help determine if that user should have login or admin access.
- Select Administration > Settings.
- 2. In the left-hand column, select the External Authentication category.
- 3. In the Authentication Backend Order field, select the order in which Cloudera Manager should attempt its authentication. You can choose to authenticate users using just one of the methods (using Cloudera Manager's own database is the default), or you can set it so that if the user cannot be authenticated by the first method, it will attempt using the second method.
- 4. For External Authentication Type, select LDAP.
- 5. In the LDAP URL property, provide the URL of the LDAP server and (optionally) the base Distinguished Name (DN) (the search base) as part of the URL — for example ldap://ldap-server.corp.com/dc=corp,dc=com.

- 6. If your server does not allow anonymous binding, provide the user DN and password to be used to bind to the directory. These are the LDAP Bind User Distinguished Name and LDAP Bind Password properties. By default, Cloudera Manager assumes anonymous binding.
- 7. To use a single "Distinguished Name Pattern", provide a pattern in the LDAP Distinguished Name Pattern property.

Use {0} in the pattern to indicate where the username should go. For example, to search for a distinguished name where the uid attribute is the username, you might provide a pattern similar to uid={0}, ou=People, dc=corp, dc=com. Cloudera Manager substitutes the name provided at login into this pattern and performs a search for that specific user. So if a user provides the username "foo" at the Cloudera Manager login page, Cloudera Manager will search for the DN uid=foo,ou=People,dc=corp,dc=com.

If you provided a base DN along with the URL, the pattern only needs to specify the rest of the DN pattern. For example, if the URL you provide is ldap://ldap-server.corp.com/dc=corp.dc=com, and the pattern is uid={0},ou=People,then the search DN will be uid=foo,ou=People,dc=corp,dc=com.

8. You can also search using User and/or Group search filters, using the LDAP User Search Base, LDAP User Search Filter, LDAP Group Search Base and LDAP Group Search Filter settings. These allow you to combine a base DN with a search filter to allow a greater range of search targets.

For example, if you want to authenticate users who may be in one of multiple OUs, the search filter mechanism will allow this. You can specify the User Search Base DN as dc=comp, dc=com and the user search filter as uid={0}. Then Cloudera Manager will search for the user anywhere in the tree starting from the Base DN. Suppose you have two OUs—ou=Engineering and ou=Operations—Cloudera Manager will find User "foo" if it exists in either of these OUs, that is, uid=foo, ou=Engineering, dc=corp, dc=com or uid=foo,ou=Operations,dc=corp,dc=com.

You can use a user search filter along with a DN pattern, so that the search filter provides a fallback if the DN pattern search fails.

The Groups filters let you search to determine if a DN or username is a member of a target group. In this case, the filter you provide can be something like member={0} where {0} will be replaced with the DN of the user you are authenticating. For a filter requiring the username, {1} may be used, as memberUid={1}. This will return a list of groups the user belongs to, which will be compared to the list in the group properties discussed in step 8 of Configuring Authentication Using Active Directory on page 10.

9. Restart the Cloudera Manager Server.

#### Configuring Cloudera Manager to Use LDAPS

If the LDAP server certificate has been signed by a trusted Certificate Authority (that is, VeriSign, GeoTrust, and so on), steps 1 and 2 below may not be necessary.

- 1. Copy the CA certificate file to the Cloudera Manager Server host.
- 2. Import the CA certificate(s) from the CA certificate file to the local truststore. The default truststore is located in the \$JAVA\_HOME/jre/lib/security/cacerts file. This contains the default CA information shipped with the JDK. Create an alternate default file called jssecacerts in the same location as the cacerts file. You can now safely append CA certificates for any private or public CAs not present in the default cacerts file, while keeping the original file intact.

For our example, we will follow this recommendation by copying the default cacerts file into the new jssecacerts file, and then importing the CA certificate to this alternate truststore.

```
$ cp $JAVA_HOME/jre/lib/security/cacerts \
 $JAVA_HOME/jre/lib/jssecacerts
$ /usr/java/latest/bin/keytool -import -alias nt_domain_name \
-keystore /usr/java/latest/jre/lib/security/jssecacerts -file path_to_cert
```

- Note:
  - The default password for the cacerts store is **changeit**.
  - The alias can be any name (not just the domain name).
- 3. Configure the LDAP URL property to use ldaps://ldap\_server instead of ldap://ldap\_server.
- 4. Restart the Cloudera Manager Server.

## Configuring Authentication Using an External Program

You can configure Cloudera Manager to use an external authentication program of your own choosing. Typically, this may be a custom script that interacts with a custom authentication service. Cloudera Manager will call the external program with the username as the first command line argument. The password is passed over stdin. Cloudera Manager assumes the program will return the following exit codes identifying the user role for a successful authentication:

- 0 Read-Only
- 1 Full Administrator
- 2 Limited Operator
- 3 Operator
- 4 Configurator
- 5 Cluster Administrator
- 6 BDR Administrator
- 7 Navigator Administrator
- 8 User Administrator
- 9 Auditor

and a negative value is returned for a failure to authenticate.

To configure authentication using an external program:

- Select Administration > Settings.
- 2. In the left-hand column, select the External Authentication category.
- 3. In the Authentication Backend Order field, select the order in which Cloudera Manager should attempt its authentication. You can choose to authenticate users using just one of the methods (using Cloudera Manager's own database is the default), or you can set it so that if the user cannot be authenticated by the first method, it will attempt using the second method.
- 4. For External Authentication Type, select External Program.
- 5. Provide a path to the external program in the External Authentication Program Path property.

## Configuring Authentication Using SAML

Cloudera Manager supports the Security Assertion Markup Language (SAML), an XML-based open standard data format for exchanging authentication and authorization data between parties, in particular, between an identity provider (IDP) and a service provider (SP). The SAML specification defines three roles: the principal (typically a user), the IDP, and the SP. In the use case addressed by SAML, the principal (user agent) requests a service from the service provider. The service provider requests and obtains an identity assertion from the IDP. On the basis of this assertion, the SP can make an access control decision—in other words it can decide whether to perform some service for the connected principal.

The primary SAML use case is called web browser single sign-on (SSO). A user wielding a user agent (usually a web browser) requests a web resource protected by a SAML SP. The SP, wishing to know the identity of the requesting user, issues an authentication request to a SAML IDP through the user agent. In the context of this terminology, Cloudera Manager operates as a SP. This topic discusses the Cloudera Manager part of the configuration process; it assumes that you are familiar with SAML and SAML configuration in a general sense, and that you have a functioning IDP already deployed.

#### Note:

- Cloudera Manager supports both SP- and IDP-initiated SSO.
- The logout action in Cloudera Manager will send a single-logout request to the IDP.
- SAML authentication has been tested with specific configurations of SiteMinder and Shibboleth. While SAML is a standard, there is a great deal of variability in configuration between different IDP products, so it is possible that other IDP implementations, or other configurations of SiteMinder and Shibboleth, may not interoperate with Cloudera Manager.
- To bypass SSO if SAML configuration is incorrect or not working, you can login via a Cloudera Manager local account using the URL: http://cm\_host:7180/cmf/localLogin

Setting up Cloudera Manager to use SAML requires the following steps.

#### **Preparing Files**

You will need to prepare the following files and information, and provide these to Cloudera Manager:

- A Java keystore containing a private key for Cloudera Manager to use to sign/encrypt SAML messages.
- The SAML metadata XML file from your IDP. This file must contain the public certificates needed to verify the sign/encrypt key used by your IDP per the SAML Metadata Interoperability Profile
- The entity ID that should be used to identify the Cloudera Manager instance
- How the user ID is passed in the SAML authentication response:
  - As an attribute. If so, what identifier is used.
  - As the NameID.
- The method by which the Cloudera Manager role will be established:
  - From an attribute in the authentication response:
    - What identifier will be used for the attribute
    - What values will be passed to indicate each role
  - From an external script that will be called for each use:
    - The script takes user ID as \$1
    - The script sets an exit code to reflect successful authentication of the assigned role:
      - 0 Full Administrator
      - 1 Read-Only
      - 2 Limited Operator
      - 3 Operator
      - 4 Configurator
      - 5 Cluster Administrator
      - 6 BDR Administrator
      - 7 Navigator Administrator
      - 8 User Administrator
      - 9 Auditor

and a negative value is returned for a failure to authenticate.

#### Configuring Cloudera Manager

- Select Administration > Settings.
- 2. In the left-hand column, select the External Authentication category.
- 3. Set the External Authentication Type property to SAML (the Authentication Backend Order property is ignored for SAML).
- 4. Set the Path to SAML IDP Metadata File property to point to the IDP metadata file.

- 5. Set the Path to SAML Keystore File property to point to the Java keystore prepared earlier.
- **6.** In the **SAML Keystore Password** property, set the keystore password.
- 7. In the Alias of SAML Sign/Encrypt Private Key property, set the alias used to identify the private key for Cloudera Manager to use.
- 8. In the SAML Sign/Encrypt Private Key Password property, set the private key password.
- **9.** Set the **SAML Entity ID** property if:
  - There is more than one Cloudera Manager instance being used with the same IDP (each instance needs a different entity ID).
  - Entity IDs are assigned by organizational policy.
- 10. In the Source of User ID in SAML Response property, set whether the user ID will be obtained from an attribute or the NamelD.
- 11. If an attribute will be used, set the attribute name in the SAML attribute identifier for user ID property. The default value is the normal OID used for user IDs and so may not need to be changed.
- 12. In the SAML Role assignment mechanism property, set whether the role assignment will be done from an attribute or an external script.
  - If an attribute will be used:
    - In the SAML attribute identifier for user role property, set the attribute name if necessary. The default value is the normal OID used for OrganizationalUnits and so may not need to be changed.
    - In the SAML Attribute Values for Roles property, set which attribute values will be used to indicate the user role.
  - If an external script will be used, set the path to that script in the Path to SAML Role Assignment Script property. Make sure that the script is executable (an executable binary is fine - it doesn't need to be a shell script).
- 13. Save the changes. Cloudera Manager will run a set of validations that ensure it can find the metadata XML and the keystore, and that the passwords are correct. If you see a validation error, correct the problem before
- **14.** Restart the Cloudera Manager Server.

#### Configuring the IDP

After the Cloudera Manager Server is restarted, it will attempt to redirect to the IDP login page instead of showing the normal CM page. This may or may not succeed, depending on how the IDP is configured. In either case, the IDP will need to be configured to recognize CM before authentication will actually succeed. The details of this process are specific to each IDP implementation - refer to your IDP documentation for details.

- 1. Download the Cloudera Manager's SAML metadata XML file from http://hostname:7180/saml/metadata.
- 2. Inspect the metadata file and ensure that any URLs contained in the file can be resolved by users' web browsers. The IDP will redirect web browsers to these URLs at various points in the process. If the browser cannot resolve them, authentication will fail. If the URLs are incorrect, you can manually fix the XML file or set the Entity Base URL in the CM configuration to the right value, and then re-download the file.
- 3. Provide this metadata file to your IDP using whatever mechanism your IDP provides.
- 4. Ensure that the IDP has access to whatever public certificates are necessary to validate the private key that was provided to Cloudera Manager earlier.
- 5. Ensure that the IDP is configured to provide the User ID and Role using the attribute names that Cloudera Manager was configured to expect, if relevant.
- 6. Ensure the changes to the IDP configuration have taken effect (a restart may be necessary).

#### Verifying Authentication and Authorization

- 1. Return to the Cloudera Manager Admin Console and refresh the login page.
- 2. Attempt to log in with credentials for a user that is entitled. The authentication should complete and you should see the Home page.

- 3. If authentication fails, you will see an IDP provided error message. Cloudera Manager is not involved in this part of the process, and you must ensure the IDP is working correctly to complete the authentication.
- 4. If authentication succeeds but the user is not authorized to use Cloudera Manager, they will be taken to an error page by Cloudera Manager that explains the situation. If an user who should be authorized sees this error, then you will need to verify their role configuration, and ensure that it is being properly communicated to Cloudera Manager, whether by attribute or external script. The Cloudera Manager log will provide details on failures to establish a user's role. If any errors occur during role mapping, Cloudera Manager will assume the user is unauthorized.

## Kerberos Principals and Keytabs

Hadoop security uses Kerberos principals and keytabs to perform user authentication on all remote procedure calls.

## Kerberos Principals

A user in Kerberos is called a *principal*, which is made up of three distinct components: the primary, instance, and realm. A Kerberos principal is used in a Kerberos-secured system to represent a unique identity. The first component of the principal is called the *primary*, or sometimes the user component. The primary component is an arbitrary string and may be the operating system username of the user or the name of a service. The primary component is followed by an optional section called the *instance*, which is used to create principals that are used by users in special roles or to define the host on which a service runs, for example. An instance, if it exists, is separated from the primary by a slash and then the content is used to disambiguate multiple principals for a single user or service. The final component of the principal is the realm. The *realm* is similar to a domain in DNS in that it logically defines a related group of objects, although rather than hostnames as in DNS, the Kerberos realm defines a group of principals. Each realm can have its own settings including the location of the KDC on the network and supported encryption algorithms. Large organizations commonly create distinct realms to delegate administration of a realm to a group within the enterprise. Realms, by convention, are written in uppercase characters.

Kerberos assigns tickets to Kerberos principals to enable them to access Kerberos-secured Hadoop services. For the Hadoop daemon principals, the principal names should be of the format username/fully.qualified.domain.name@YOUR-REALM.COM. In this guide, username in the username/fully.qualified.domain.name@YOUR-REALM.COM principal refers to the username of an existing Unix account that is used by Hadoop daemons, such as hdfs or mapred. Human users who want to access the Hadoop cluster also need to have Kerberos principals; in this case, username refers to the username of the user's Unix account, such as joe or jane. Single-component principal names (such as joe@YOUR-REALM.COM) are acceptable for client user accounts. Hadoop does not support more than two-component principal names.

#### Kerberos Keytabs

A *keytab* is a file containing pairs of Kerberos principals and an encrypted copy of that principal's key. A keytab file for a Hadoop daemon is unique to each host since the principal names include the hostname. This file is used to authenticate a principal on a host to Kerberos without human interaction or storing a password in a plain text file. Because having access to the keytab file for a principal allows one to act as that principal, access to the keytab files should be tightly secured. They should be readable by a minimal set of users, should be stored on local disk, and should not be included in host backups, unless access to those backups is as secure as access to the local host.

## Enabling Kerberos Authentication Using the Wizard

Required Role: Cluster Administrator Full Administrator

Important: Ensure you have secured communication between the Cloudera Manager Server and Agents before you enable Kerberos on your cluster. Kerberos keytabs are sent from the Cloudera Manager Server to the Agents, and must be encrypted to prevent potential misuse of leaked keytabs. For secure communication, you should have at least Level 1 TLS enabled as described in Configuring TLS Security for Cloudera Manager (Level 1).

This guide describes how to use Cloudera Manager and the Kerberos wizard (introduced in Cloudera Manager 5.1.0) to automate many of the manual tasks of implementing Kerberos security on your CDH cluster.

• Prerequisites - These instructions assume you know how to install and configure Kerberos, you already have a working Kerberos key distribution center (KDC) and realm setup, and that you've installed the following Kerberos client packages on all cluster hosts and hosts that will be used to access the cluster, depending on the OS in use.

OS	Packages to be Installed
RHEL/CentOS 5, RHEL/CentOS 6	<ul> <li>openIdap-clients on the Cloudera Manager Server host</li> <li>krb5-workstation, krb5-libs on ALL hosts</li> </ul>
SLES	<ul> <li>openldap2-client on the Cloudera Manager Server host</li> <li>krb5-client on ALL hosts</li> </ul>
Ubuntu or Debian	<ul><li>ldap-utils on the Cloudera Manager Server host</li><li>krb5-user on ALL hosts</li></ul>
Windows	■ krb5-workstation,krb5-libs on ALL hosts

Furthermore, Oozie and Hue require that the realm support renewable tickets. Cloudera Manager supports setting up kerberized clusters with MIT KDC and Active Directory.

Important: If you want to integrate Kerberos directly with Active Directory, ensure you have support from your AD administration team to do so. This includes any future support required to troubleshoot issues such as Kerberos TGT/TGS ticket renewal, access to KDC logs for debugging and so on.

For more information about using Active Directory, refer the section below on Considerations when using an Active Directory KDC and the Microsoft AD documentation.

For more information about installing and configuring MIT KDC, see:

- MIT Kerberos Home
- MIT Kerberos Documentation

#### Support

- Kerberos security in Cloudera Manager has been tested on the following version of MIT Kerberos 5:
  - krb5-1.6.1 on Red Hat Enterprise Linux 5 and CentOS 5
- Kerberos security in Cloudera Manager is supported on the following versions of MIT Kerberos 5:
  - krb5-1.6.3 on SLES 11 Service Pack 1
  - krb5-1.8.1 on Ubuntu
  - krb5-1.8.2 on Red Hat Enterprise Linux 6 and CentOS 6
  - krb5-1.9 on Red Hat Enterprise Linux 6.1

Considerations when using an Active Directory KDC

Performance:

As your cluster grows, so will the volume of Authentication Service (AS) and Ticket Granting Service (TGS) interaction between the services on each cluster server. Consider evaluating the volume of this interaction against the Active Directory domain controllers you have configured for the cluster before rolling this feature out to a production environment. If cluster performance suffers, over time it might become necessary to dedicate a set of AD domain controllers to larger deployments.

#### **Network Proximity:**

By default, Kerberos uses UDP for client/server communication. Often, AD services are in a different network than project application services such as Hadoop. If the domain controllers supporting a cluster for Kerberos are not in the same subnet, or they're separated by a firewall, consider using the udp\_preference\_limit = 1 setting in the [libdefaults] section of the krb5.conf used by cluster services. Cloudera strongly recommends against using AD domain controller (KDC) servers that are separated from the cluster by a WAN connection, as latency in this service will significantly impact cluster performance.

Troubleshooting the cluster's operations, especially for Kerberos-enabled services, will need to include AD administration resources. Evaluate your organizational processes for engaging the AD administration team, and how to escalate in case a cluster outage occurs due to issues with Kerberos authentication against AD services. In some situations it might be necessary to enable Kerberos event logging to address desktop and KDC issues within windows environments.

## Step 1: Install Cloudera Manager and CDH

If you have not already done so, Cloudera strongly recommends that you install and configure the Cloudera Manager Server and Cloudera Manager Agents and CDH to set up a fully-functional CDH cluster before you begin doing the following steps to implement Hadoop security features.

#### Overview of the User Accounts and Groups in CDH and Cloudera Manager to Support Security

When you install the CDH packages and the Cloudera Manager Agents on your cluster hosts, Cloudera Manager takes some steps to provide system security such as creating the following Unix accounts and setting directory permissions as shown in the following table. These Unix accounts and directory permissions work with the Hadoop Kerberos security requirements.

This User	Runs These Roles
hdfs	NameNode, DataNodes, and Secondary Node
mapred	JobTracker and TaskTrackers (MR1) and Job History Server (YARN)
yarn	ResourceManager and NodeManagers (YARN)
oozie	Oozie Server
hue	Hue Server, Beeswax Server, Authorization Manager, and Job Designer

The hdfs user also acts as the HDFS superuser.

When you install the Cloudera Manager Server on the server host, a new Unix user account called cloudera-scm is created automatically to support security. The Cloudera Manager Server uses this account to create and deploy the host principals and keytabs on your cluster.

## If you installed CDH and Cloudera Manager at the Same Time

If you have a new installation and you installed CDH and Cloudera Manager at the same time, when you started the Cloudera Manager Agents on your cluster hosts, the Cloudera Manager Agent on each host automatically configured the directory owners shown in the following table to support security. Assuming the owners are configured as shown, the Hadoop daemons can then automatically set the permissions for each of the directories specified by the properties shown below to make sure they are properly restricted. It's critical that the owners are configured exactly as shown below, so don't change them:

Directory Specified in this Property	Owner
dfs.name.dir	hdfs:hadoop
dfs.data.dir	hdfs:hadoop
mapred.local.dir	mapred:hadoop
mapred.system.dirin HDFS	mapred:hadoop
yarn.nodemanager.local-dirs	yarn:yarn
yarn.nodemanager.log-dirs	yarn:yarn
oozie.service.StoreService.jdbc.url(if using Derby)	oozie:oozie
[[database]] name	hue:hue
javax.jdo.option.ConnectionURL	hue:hue

## If you Installed and Used CDH Before Installing Cloudera Manager

If you have been using HDFS and running MapReduce jobs in an existing installation of CDH before you installed Cloudera Manager, you must manually configure the owners of the directories shown in the table above. Doing so enables the Hadoop daemons to automatically set the permissions for each of the directories. It's critical that you manually configure the owners exactly as shown above.

## Step 2: If You are Using AES-256 Encryption, Install the JCE Policy File

If you are using CentOS or Red Hat Enterprise Linux 5.5 or later, which use AES-256 encryption by default for tickets, you must install the Java Cryptography Extension (JCE) Unlimited Strength Jurisdiction Policy File on all cluster and Hadoop user hosts. There are 2 ways to do this:

- In the Cloudera Manager Admin Console, navigate to the Hosts page. Both, the Add New Hosts to Cluster wizard and the Re-run Upgrade Wizard will give you the option to have Cloudera Manager install the JCE Policy file for you.
- You can follow the JCE Policy File installation instructions in the README.txt file included in the jce\_policy-x.zip file.

Alternatively, you can configure Kerberos to not use AES-256 by removing aes256-cts:normal from the supported\_enctypes field of the kdc.conf or krb5.conf file. Note that after changing the kdc.conf file, you'll need to restart both the KDC and the kadmin server for those changes to take affect. You may also need to recreate or change the password of the relevant principals, including potentially the Ticket Granting Ticket principal (krbtgt/REALM@REALM). If AES-256 is still used after all of those steps, it's because the aes256-cts:normal setting existed when the Kerberos database was created. To fix this, create a new Kerberos database and then restart both the KDC and the kadmin server.

#### To verify the type of encryption used in your cluster:

1. For MIT KDC: On the local KDC host, type this command in the kadmin.local or kadmin shell to create a test principal:

```
kadmin: addprinc test
```

**For Active Directory:** Create a new AD account with the name, test.

2. On a cluster host, type this command to start a Kerberos session as test:

```
$ kinit test
```

3. On a cluster host, type this command to view the encryption type in use:

```
$ klist -e
```

If AES is being used, output like the following is displayed after you type the klist command (note that AES-256 is included in the output):

```
Ticket cache: FILE:/tmp/krb5cc_0
Default principal: test@Cloudera Manager
Valid starting Expires Service principal 05/19/11 13:25:04 05/20/11 13:25:04 krbtgt/Cloudera Manager@Cloudera Manager Etype (skey, tkt): AES-256 CTS mode with 96-bit SHA-1 HMAC, AES-256 CTS mode
with 96-bit SHA-1 HMAC
```

## Step 3: Get or Create a Kerberos Principal for the Cloudera Manager Server

In order to create and deploy the host principals and keytabs on your cluster, the Cloudera Manager Server must have the correct Kerberos principal. Specifically, the Cloudera Manager Server must have a Kerberos principal that has privileges to create other accounts.

To get or create the Kerberos principal for the Cloudera Manager Server, you can do either of the following:

- Ask your Kerberos administrator to create a Kerberos administrator principal for the Cloudera Manager
- Create the Kerberos principal for the Cloudera Manager Server yourself by using the following instructions in this step.

#### Creating the Cloudera Manager Principal

The following instructions illustrate an example of creating the Cloudera Manager Server principal for MIT KDC and Active Directory KDC. (If you are using another version of Kerberos, refer to your Kerberos documentation for instructions.)

#### If you are using Active Directory:

- 1. Create an Organizational Unit (OU) in your AD setup where all the principals used by your CDH cluster will
- 2. Add a new user account to Active Directory, for example, <username>@YOUR-REALM.COM. The password for this user should be set to never expire.
- 3. Use AD's Delegate Control wizard to allow this new user to Create, Delete and Manage User Accounts.

#### If you are using MIT KDC:

Typically, principals with the second component of admin in the principal name (for example, username/admin@YOUR-LOCAL-REALM.com) have administrator privileges. This is why admin is shown in the following example.

Note: If you are running kadmin and the Kerberos Key Distribution Center (KDC) on the same host, use kadmin.local in the following steps. If the Kerberos KDC is running on a remote host, you must use kadmin instead of kadmin.local.

In the kadmin.local or kadmin shell, type the following command to create the Cloudera Manager Server principal, replacing YOUR-LOCAL-REALM. COM with the name of your realm:

```
kadmin: addprinc -pw <Password> cloudera-scm/admin@YOUR-LOCAL-REALM.COM
```

## Step 4: Enabling Kerberos Using the Wizard

Required Role: Full Administrator

To start the Kerberos wizard:

- to enable Kerberos authentication.
- 2. Select Enable Kerberos.

## Before you Begin Using the Wizard

The Welcome page lists the following action items that you should complete before you begin to secure the cluster using this wizard:

- Set up a working KDC. Cloudera Manager supports authentication with MIT KDC and Active Directory.
- Configure the KDC to allow renewable tickets with non-zero ticket lifetimes.

Active Directory allows renewable tickets with non-zero lifetimes by default. You can verify this by checking **Domain Security Settings > Account Policies > Kerberos Policy** in Active Directory.

For MIT KDC, make sure you have the following lines in the kdc.conf.

```
max_life = 1d
max_renewable_life = 7d
kdc_tcp_ports = 88
```

- If you are using Active Directory, make sure LDAP over SSL (LDAPS) is enabled for the Domain Controllers.
- Install the following packages on your cluster depending on the OS in use.

OS	Packages to be Installed
RHEL/CentOS 5, RHEL/CentOS 6	<ul> <li>openIdap-clients on the Cloudera Manager Server host</li> <li>krb5-workstation, krb5-libs on ALL hosts</li> </ul>
SLES	<ul> <li>openIdap2-client on the Cloudera Manager Server host</li> <li>krb5-client on ALL hosts</li> </ul>
Ubuntu or Debian	<ul><li>ldap-utils on the Cloudera Manager Server host</li><li>krb5-user on ALL hosts</li></ul>
Windows	krb5-workstation, krb5-libs on ALL hosts

 Create an account for Cloudera Manager that has the permissions to create other accounts in the KDC. This should have been completed as part of Step 3: Get or Create a Kerberos Principal for the Cloudera Manager Server on page 20.

#### Important:

If you have enabled YARN Resource Manager HA in your non-secure cluster, you should clear the StateStore znode in ZooKeeper before enabling Kerberos. To do this:

- 1. Go to the Cloudera Manager Admin Console home page, click to the right of the YARN service and select Stop.
- **2.** When you see a **Finished** status, the service has stopped.
- **3.** Go to the YARN service and select **Actions** > **Format State Store**.
- **4.** When the command completes, click **Close**.

Once you are able to check all the items on this list, click **Continue**.

#### **KDC** Information

On this page, select the KDC type you are using, MIT KDC or Active Directory, and complete the fields as applicable to enable Cloudera Manager to generate principals/accounts for the CDH services running on the cluster.

#### Note:

- If you are using AD and have multiple Domain Controllers behind a Load Balancer, enter the name of the Load Balancer in the KDC Server Host field and any one of the Domain Controllers in Active Directory Domain Controller Override. Hadoop daemons will use the Load Balancer for authentication, but Cloudera Manager will use the override for creating accounts.
- If you have multiple Domain Controllers (in case of AD) or MIT KDC servers, only enter the name of any one of them in the KDC Server Host field. Cloudera Manager will use that server only for creating accounts. If you choose to use Cloudera Manager to manage krb5.conf, you can specify the rest of the Domain Controllers using Safety Valve as explained below.
- Make sure the entries for the Kerberos Encryption Types field matches what your KDC supports.

#### Click **Continue** to proceed.

### **KRB5** Configuration

Manage krb5.conf through Cloudera Manager allows you to choose whether Cloudera Manager should deploy the krb5.conf on your cluster or not. If left unchecked, you must ensure that the krb5.conf is deployed on all hosts in the cluster, including the Cloudera Manager Server's host.

If you check Manage krb5.conf through Cloudera Manager, this page will let you configure the properties that will be emitted in it. In particular, the safety valves on this page can be used to configure cross-realm authentication. More information can be found at Configuring a Cluster-dedicated MIT KDC with Cross-Realm Trust on page 123.

**Note:** Cloudera Manager is unable to use a non-default realm. You must specify the default realm.

#### Click **Continue** to proceed.

#### Import KDC Account Manager Credentials

Enter the username and password for the user that can create principals for CDH cluster in the KDC. This is the user/principal you created in Step 3: Get or Create a Kerberos Principal for the Cloudera Manager Server on page 20. Cloudera Manager encrypts the username and password into a keytab and uses it as needed to create new principals.

Note: The username entered should have the realm portion in upper-case only as shown in the example in the UI.

#### Click Continue to proceed.

#### (Optional) Configuring Custom Kerberos Principals

Starting with Cloudera Manager 5.4, you can configure custom service principals for CDH services. Before you begin making configuration changes, see Configuring a Cluster with Custom Kerberos Principals on page 27 for some additional configuration changes required and limitations.

#### Configure HDFS DataNode Ports

On this page, specify the privileged ports needed by the DataNode's Transceiver Protocol and the HTTP Web UI in a secure cluster.

Use the checkbox to confirm you are ready to restart the cluster. Click **Continue**.

### **Enabling Kerberos**

This page lets you track the progress made by the wizard as it first stops all services on your cluster, deploys the krb5.conf, generates keytabs for other CDH services, deploys client configuration and finally restarts all services. Click Continue.

### Congratulations

The final page lists the cluster(s) for which Kerberos has been successfully enabled. Click Finish to return to the Cloudera Manager Admin Console home page.

## Step 5: Create the HDFS Superuser

In order to be able to create home directories for users you will need access to the HDFS superuser account. (CDH automatically created the HDFS superuser account on each cluster host during CDH installation.) When you enabled Kerberos for the HDFS service, you lost access to the HDFS superuser account via sudo -u hdfs commands. To enable your access to the HDFS superuser account now that Kerberos is enabled, you must create a Kerberos principal or an AD user whose first component is hdfs:

#### If you are using Active Directory

Add a new user account to Active Directory, hdfs@YOUR-REALM.COM.

## If you are using MIT KDC

1. In the kadmin.local or kadmin shell, type the following command to create a Kerberos principal called hdfs:

kadmin: addprinc hdfs@YOUR-LOCAL-REALM.COM

- Note: This command prompts you to create a password for the hdfs principal. You should use a strong password because having access to this principal provides superuser access to all of the files in HDFS.
- 2. To run commands as the HDFS superuser, you must obtain Kerberos credentials for the hdfs principal. To do so, run the following command and provide the appropriate password when prompted.

## Step 6: Get or Create a Kerberos Principal for Each User Account

Now that Kerberos is configured and enabled on your cluster, you and every other Hadoop user must have a Kerberos principal or keytab to obtain Kerberos credentials to be allowed to access the cluster and use the Hadoop services. In the next step of this procedure, you will need to create your own Kerberos principals in order to verify that Kerberos security is working on your cluster. If you and the other Hadoop users already have a Kerberos principal or keytab, or if your Kerberos administrator can provide them, you can skip ahead to the next

The following instructions explain how to create a Kerberos principal for a user account.

#### If you are using Active Directory

Add a new AD user account, <username>@YOUR-REALM.COM for each Cloudera Manager service that should use Kerberos authentication.

#### If you are using MIT KDC

1. In the kadmin.local or kadmin shell, use the following command to create a principal for your account by replacing YOUR-LOCAL-REALM. COM with the name of your realm, and replacing USERNAME with a username:

\_\_\_\_\_\_

kadmin: addprinc USERNAME@YOUR-LOCAL-REALM.COM

**2.** When prompted, enter the password twice.

## Step 7: Prepare the Cluster for Each User

Before you and other users can access the cluster, there are a few tasks you must do to prepare the hosts for each user.

- 1. Make sure all hosts in the cluster have a Linux user account with the same name as the first component of that user's principal name. For example, the Linux account joe should exist on every box if the user's principal name is joe@YOUR-REALM.COM. You can use LDAP for this step if it is available in your organization.
  - Note: Each account must have a user ID that is greater than or equal to 1000. In the /etc/hadoop/conf/taskcontroller.cfg file, the default setting for the banned.users property is mapred, hdfs, and bin to prevent jobs from being submitted via those user accounts. The default setting for the min.user.id property is 1000 to prevent jobs from being submitted with a user ID less than 1000, which are conventionally Unix super users.
- 2. Create a subdirectory under /user on HDFS for each user account (for example, /user/joe). Change the owner and group of that directory to be the user.

```
$ hadoop fs -mkdir /user/joe
$ hadoop fs -chown joe /user/joe
```

Note: sudo -u hdfs is not included in the commands above. This is because it is not required if Kerberos is enabled on your cluster. You will, however, need to have Kerberos credentials for the HDFS super user in order to successfully run these commands. For information on gaining access to the HDFS super user account, see Step 14: Create the HDFS Superuser Principal on page 41

## Step 8: Verify that Kerberos Security is Working

After you have Kerberos credentials, you can verify that Kerberos security is working on your cluster by trying to run MapReduce jobs. To confirm, try launching a sleep or a pi job from the provided Hadoop examples (/usr/lib/hadoop/hadoop-examples.jar).

Note:

This section assumes you have a fully-functional CDH cluster and you have been able to access HDFS and run MapReduce jobs before you followed these instructions to configure and enable Kerberos on your cluster. If you have not already done so, you should at a minimum use the Cloudera Manager Admin Console to generate a client configuration file to enable you to access the cluster. For instructions, see **Deploying Client Configuration Files**.

#### To verify that Kerberos security is working:

**1.** Acquire Kerberos credentials for your user account.

```
$ kinit USERNAME@YOUR-LOCAL-REALM.COM
```

- **2.** Enter a password when prompted.
- 3. Submit a sample pi calculation as a test MapReduce job. Use the following command if you use a package-based setup for Cloudera Manager:

```
$ hadoop jar /usr/lib/hadoop-0.20-mapreduce/hadoop-examples.jar pi 10 10000
Number of Maps = 10
Samples per Map = 10000
Job Finished in 38.572 seconds
```

If you have a parcel-based setup, use the following command instead:

```
$ hadoop jar /opt/cloudera/parcels/CDH/lib/hadoop-0.20-mapreduce/hadoop-examples.jar
pi 10 10000
Number of Maps = 10
Samples per Map = 10000
Job Finished in 30.958 seconds
```

You have now verified that Kerberos security is working on your cluster.

#### Important:

Running a MapReduce job will fail if you do not have a valid Kerberos ticket in your credentials cache. You can examine the Kerberos tickets currently in your credentials cache by running the klist command. You can obtain a ticket by running the kinit command and either specifying a keytab file containing credentials, or entering the password for your principal. If you do not have a valid ticket, vou will receive an error such as:

```
11/01/04 12:08:12 WARN ipc.Client:
Exception encountered while connecting to the server
javax.security.sasl.SaslException:GSS initiate failed
[Caused by GSSException: No valid credentials provided (Mechanism level: Failed
 to find any
Kerberos tgt)]
Bad connection to FS. command aborted. exception: Call to nn-host/10.0.0.2:8020
failed on local exception:
java.io.IOException:javax.security.sasl.SaslException: GSS initiate failed
[Caused by GSSException: No valid credentials provided
(Mechanism level: Failed to find any Kerberos tgt)]
```

## Step 9: (Optional) Enable Authentication for HTTP Web Consoles for Hadoop Roles

## Configurator Cluster Administrator Full Administrator

Authentication for access to the HDFS, MapReduce, and YARN roles' web consoles can be enabled via a configuration option for the appropriate service. To enable this authentication:

- 1. From the Clusters tab, select the service (HDFS, MapReduce, or YARN) for which you want to enable authentication.
- 2. Click the Configuration tab.
- 3. Select Scope > service name Service-Wide.
- Select Category > Security.
- **5.** Type Enable Kerberos in the Search box.
- Select Enable Kerberos Authentication for HTTP Web-Consoles.
- 7. Click Save Changes to commit the changes.
- **8.** When the command finishes, restart all roles of that service.

#### Enabling SPNEGO as an Authentication Backend for Hue

To enable SPNEGO authentication:

1. On the host running the Hue Kerberos Ticket Renewer, switch to the KT\_RENEWER process directory. For example:

```
cd /var/run/cloudera-scm-agent/process/`ls -lrt /var/run/cloudera-scm-agent/process/
| awk '{print $9}' |grep KT_RENEWER| tail -1`/
```

2. Verify that the Hue keytab includes the HTTP principal.

```
,-----
klist -kte ./hue.keytab
```

3. Copy the hue.keytab file to /var/lib/hue and change ownership to the hue user and group.

```
$ cp ./hue.keytab /var/lib/hue/
$ chown hue:hue /var/lib/hue/hue.keytab
```

- 4. Go to the Cloudera Manager Admin Console. From the Clusters tab, select the Hue service.
- **5.** Click the **Configuration** tab.
- 6. Select Scope > Service-Wide.
- 7. Select Category > Security.
- 8. Locate the Authentication Backend property and select desktop.auth.backend.SpnegoDjangoBackend.
- Select Category > Advanced.
- 10. Locate the Hue Service Environment Advanced Configuration Snippet (Safety Valve) property and add the following line:

```
KRB5_KTNAME=/var/lib/hue/hue.keytab
```

- 11. Click Save Changes to commit the changes.
- 12. Restart the Hue service.

## Enabling Kerberos Authentication for Single User Mode or Non-Default Users

The steps described in this topic are only applicable in the following cases:

You are running the Cloudera Manager in the single user mode. In this case, configure all the services described in the table below.

OR

• You are running one or more CDH services with non-default users. This means if you have modified the default value for the System User property for any service in Cloudera Manager, you must only perform the command (as described below) corresponding to that service, to be able to successfully run jobs with the non-default user.

MapReduce	Configure the mapred.system.dir directory to be owned by the mapred user.
	sudo -u hdfs hadoop fs -chown mapred:hadoop \${mapred.system.dir}
	By default, mapred.system.dir is /tmp/mapred/system.
HBase	Give the hbase user ownership of the HBase root directory:
	sudo -u hdfs hadoop fs -chown -R hbase \${hbase.rootdir}
	By default, hbase.rootdir is /hbase.
Hive	Give the hive user ownership of the /user/hive directory.
	sudo -u hdfs hadoop fs -chown hive /user/hive
YARN	For every NodeManager host, for each path in yarn.nodemanager.local-dirs, run:
	rm -rf \${yarn.nodemanager.local-dirs}/usercache/*

This removes the /usercache directory that contains intermediate data stored for previous jobs.

## Configuring a Cluster with Custom Kerberos Principals

By default, Cloudera Manager configures CDH services to use the same Kerberos principals as the default process users. For example, the hdfs principal for the HDFS service, hive principal for the Hive service, and so on. The advantage to this is that when Kerberos is enabled, no HDFS directory permissions need to be changed for the new principals. However, starting with Cloudera Manager 5.4, you can configure custom service principals for CDH services.

#### **Important Considerations**

- Using different Kerberos principals for different services will make it easier to track the HDFS directories being accessed by each service.
- If you are using ShellBasedUnixGroupsMapping to obtain user-group mappings, ensure you have the UNIX accounts for the principals present on all hosts of the cluster.

#### Configuring Directory Permissions

Configure the following HDFS directories to give their corresponding custom service principals read, write and execute permissions.

Service	HDFS Directory
Accumulo	HDFS Directory
	<pre>/user/{principal}</pre>
HBase	HBase Root Directory
Hive	Hive Warehouse Directory
	<pre>/user/{principal}</pre>
Impala	/user/{principal}
MapReduce v1	/tmp/mapred
Oozie	Oozie ShareLib Root Directory
Solr	HDFS Data Directory
Spark on YARN	<pre>/user/{principal}</pre>
	Spark History Location
	Spark Jar Location
Sqoop2	/user/{principal}

## Configuring CDH Services

The following services will require additional settings if you are using custom principals:

- HDFS If you have enabled synchronization of HDFS and Sentry permissions, add the Hive and Impala principals to the **Sentry Authorization Provider Group** property.
  - 1. Navigate to the HDFS service.
  - 2. Click Configuration.
  - 3. Select Scope > HDFS Service-Wide.
  - Select Category > Security.
  - **5.** Locate the **Sentry Authorization Provider Group** property and add the custom Hive and Impala principals.
  - 6. Click Save Changes.

- YARN The principals used by YARN daemons should be part of hadoop group so that they are allowed to read JobHistory Server data.
- Impala If you are running the Hue service with a custom principal, configure Impala to allow the Hue principal to impersonate other users.
  - **1.** Navigate to the Impala service.
  - 2. Click Configuration.
  - 3. Select Scope > Impala (Service-Wide).
  - 4. Select Category > Policy File-Based Sentry.
  - 5. Locate the **Proxy User Configuration** property and add the custom Hue principal.
  - 6. Click Save Changes.
- Hive If the Sentry service is enabled, allow the Kerberos principals used by Hive, Impala, Hue, HDFS and the Service Monitor to bypass Sentry authorization in the Hive metastore.
  - 1. Navigate to the Hive service.
  - **2.** Click Configuration.
  - 3. Select Scope > Impala (Service-Wide).
  - 4. Select Category > Policy File-Based Sentry.
  - 5. Locate the Bypass Sentry Authorization Users property and add the custom Hive, Impala, Hue and HDFS principals to the list.
  - 6. Click Save Changes.
- **Spark on YARN** The principal used by the Spark service should be part of the spark group.
- Sentry Allow the Hive, Impala, Hue and HDFS prinicpals to connect to the Sentry service.
  - 1. Navigate to the Sentry service.
  - **2.** Click Configuration.
  - 3. Search for the Allowed Connecting Users property and add the custom Hive, Impala, Hue and HDFS principals to the list.
  - 4. Search for the Admin Groups property and include the groups to which the Hive, Impala, and Hue principals
  - 5. Click Save Changes.
- Cloudera Management Service Configure the Reports Manager principal and the Navigator principal for HDFS as HDFS superusers.
  - 1. Navigate to the Cloudera Management Service.
  - **2.** Click Configuration.
  - **3.** Search for *kerberos*.
  - 4. Locate the Reports Manager Kerberos Principal property and set it to a principal with administrative and superuser privileges on all HDFS services.
  - 5. Locate the Navigator Kerberos Principal for HDFS property and set it to a principal with administrative and superuser privileges on all HDFS services.
  - 6. Click Save Changes.

#### Incompatibilities

The following features do not work with custom principals:

- Llama must always use the default Kerberos principal 11ama.
- If you are using MapReduce v1, the Activity Monitor and Cloudera Navigator should use the same principal as the Hue service.
- If you are using the Java KeyStore KMS or KeyTrustee KMS with a custom principal, you will need to add the proxy user for the custom principal to the kms-site.xml safety valve.

For example, if you've replaced the default oozie principal with oozieprinc, add the hadoop.kms.proxyuser.oozieprinc.groupsandhadoop.kms.proxyuser.oozieprinc.hostsproperties to the kms-site.xml safety valve.

## Viewing and Regenerating Kerberos Principals

#### **Full Administrator** Required Role:

As soon as you enable Hadoop secure authentication for HDFS and MapReduce service instances, Cloudera Manager starts creating the Kerberos principals for each of the role instances. The amount of time this process will take depends on the number of hosts and HDFS and MapReduce role instances on your cluster. The process can take from a few seconds for a small cluster to several minutes for a larger cluster. After the process is completed, you can use the Cloudera Manager Admin Console to view the list of Kerberos principals that Cloudera Manager has created for the cluster. Make sure there are principals for each of the hosts and HDFS and MapReduce role instances on your cluster. If there are no principals after 10 minutes, then there is most likely a problem with the principal creation. See the Troubleshooting Authentication Issues on page 145 section below for more information. If necessary, you can use Cloudera Manager to regenerate the principals.

If you make a global configuration change in your cluster, such as changing the encryption type, you must use the following instructions to regenerate the principals for your cluster.

## Important:

- Regenerate principals using the following steps in the Cloudera Manager Admin Console and not directly using kadmin shell.
- Do not regenerate the principals for your cluster unless you have made a global configuration change. Before regenerating, be sure to read Configuring a Cluster-dedicated MIT KDC with <u>Cross-Realm Trust</u> on page 123 to avoid making your existing host keytabs invalid.
- If you are using Active Directory, delete the AD accounts with the userPrincipalName (or login names) that you want to manually regenerate before continuing with the steps below.

#### To view and regenerate the Kerberos principals for your cluster:

- Select Administration > Kerberos.
- 2. The currently configured Kerberos principals are displayed. If you are running HDFS, the hdfs/hostname and host/hostname principals are listed. If you are running MapReduce, the mapred/hostname and host/hostname principals are listed. The principals for other running services are also listed.
- **3.** Only if necessary, select the principals you want to regenerate.
- 4. Click Regenerate.

## The Security Inspector

The Security Inspector uses the Host Inspector to run a security-related set of commands on the hosts in your cluster. It reports on things such as how Java is configured for encryption and on the default realms configured on each host:

- Select Administration > Kerberos.
- 2. Click Security Inspector. Cloudera Manager begins several tasks to inspect the managed hosts.
- 3. After the inspection completes, click **Download Result Data** or **Show Inspector Results** to review the results.

## Mapping Kerberos Principals to Short Names

Kerberos user principals typically have the format username@REALM, whereas Hadoop usernames are typically just username. To translate Kerberos principals to Hadoop usernames, Hadoop uses rules defined in the hadoop.security.auth\_to\_local property. The default setting strips the @REALM portion from the Kerberos

principal, where REALM is the Kerberos realm defined by the default\_realm setting in the NameNode krb5.conf

If you configure your cluster's Kerberos realm to trust other realms, such as a trust between your cluster's realm and a central Active Directory or MIT Kerberos realm, you must identify the trusted realms in Cloudera Manager so it can automatically generate the appropriate rules. If you do not do so, user accounts in those realms cannot access the cluster.

To specify trusted realms using Cloudera Manager:

- 1. Navigate to the HDFS Service > Configuration tab.
- Select Scope > HDFS (Service-Wide).
- **3.** Select **Category** > **Security**.
- 4. In the Search field, type Kerberos Realms to find the Trusted Kerberos Realms and Additional Rules to Map Kerberos Principals to Short Names settings.
- 5. Add realms that are trusted by the cluster's Kerberos realm. Realm names, including Active Directory realms, must be specified in uppercase letters (for example, CORP. EXAMPLE. COM). To add multiple realms, use the **♣** button.
- 6. Click Save Changes.

The auto-generated mapping rules strip the Kerberos realm (for example, @CORP.EXAMPLE.COM) for each realm specified in the **Trusted Kerberos Realms** setting. To customize the mapping rules, specify additional rules in the **Additional Rules to Map Kerberos Principals to Short Names** setting, one rule per line. Only enter rules in this field; Cloudera Manager automatically surrounds the rules with the appropriate XML tags for the generated core-site.xml file. For more information on creating custom rules, including how to translate mixed-case Kerberos principals to lowercase Hadoop usernames, see Mapping Rule Syntax on page 121.

If you specify custom mapping rules for a Kerberos realm using the Additional Rules to Map Kerberos Principals to Short Names setting, ensure that the same realm is not specified in the Trusted Kerberos Realms setting. If it is, the auto-generated rule (which only strips the realm from the principal and does no additional transformations) takes precedent, and the custom rule is ignored.

For these changes to take effect, you must restart the cluster and re-deploy the client configuration. On the

Cloudera Manager **Home** page, click the cluster-wide button and select **Deploy Client Configuration**.

## Using Auth-to-Local Rules to Isolate Cluster Users

By default, the Hadoop auth-to-local rules map a principal of the form <username>/<hostname>@<REALM> to <username>. This means if there are multiple clusters in the same realm, then principals associated with hosts of one cluster would map to the same user in all other clusters.

For example, if you have two clusters, cluster1-host-[1..4].example.com and cluster2-host-[1..4].example.com, that are part of the same Kerberos realm, EXAMPLE.COM, then the cluster2 principal, hdfs/cluster2-host1.example.com@EXAMPLE.COM, will map to the hdfs user even on cluster1 hosts.

To prevent this, use auth-to-local rules as follows to ensure only principals containing hostnames of clusterl are mapped to legitimate users.

- 1. Navigate to the HDFS Service > Configuration tab.
- Select Scope > HDFS (Service-Wide).
- Select Category > Security.
- 4. In the Search field, type Additional Rules to find the Additional Rules to Map Kerberos Principals to Short Names settings.
- 5. Additional mapping rules can be added to the Additional Rules to Map Kerberos Principals to Short Names property. These rules will be inserted before the rules generated from the list of trusted realms (configured above) and before the default rule.

```
RULE:[2:$1/$2@$0](hdfs/cluster1-host1.example.com@EXAMPLE.COM)s/(.*)@EXAMPLE.COM/hdfs/
\verb|RULE:[2:\$1/\$2@\$0]| (hdfs/cluster1-host2.example.com@EXAMPLE.COM)s/(.*)@EXAMPLE.COM/hdfs/| (hdfs/cluster1-host2.example.com]s/(.*)@EXAMPLE.COM/hdfs/| (hdfs/cluster1-host2.example.com]s/(.*)@EXAMPLE.Com]s/(.*)@EXAMPLE.Com]s/(.*)@EXAMPLE.Com]s/(.*)@EXAMPLE.Com]s/(.*)@EXAMPLE.Com]s/(.*)@EXAMPLE.Com]s/(.*)@EXAMPLE.Com]s/(.*)@EXAMPLE.Com]s/(.*)@EXAMPLE.Com]s/(.*)@EXAMPLE.Com]s/(.*)@EXAMPLE.Com]s/(.*)@EXAMPLE.Com]s/(.*)@EXAMPLE.Com]s/(.*)@EXAMPLE.Com]s/(.*)@EXAMPLE.Com]s/(.*)@EXAMPLE.Com]s/(.*)@EXAMPLE.Com]s/(.*)@EXAMPLE.Com]s/(.*)@EXAMPLE.Co
```

```
{\tt RULE:[2:\$1/\$2@\$0](hdfs/cluster1-host3.example.com@EXAMPLE.COM)s/(.*)@EXAMPLE.COM/hdfs/}
RULE:[2:$1/$2@$0](hdfs/cluster1-host4.example.com@EXAMPLE.COM)s/(.*)@EXAMPLE.COM/hdfs/
RULE: [2:$1/$2@$0](hdfs.*@EXAMPLE.COM)s/(.*)@EXAMPLE.COM/nobody/
```

In the example, the principal hdfs/<hostname>@REALM is mapped to the hdfs user if <hostname> is one of the cluster hosts. Otherwise it gets mapped to nobody, thus ensuring that principals from other clusters do not have access to cluster1.

If the cluster hosts can be represented with a regular expression, that expression can be used to make the configuration easier and more conducive to scaling. For example:

```
RULE:[2:$1/$2@$0](hdfs/cluster1-host[1-4].example.com@EXAMPLE.COM)s/(.*)@EXAMPLE.COM/hdfs/
\texttt{RULE:[2:\$1/\$2@\$0](hdfs.*@EXAMPLE.COM)s/(.*)@EXAMPLE.COM/nobody/}
```

- Click Save Changes.
- 7. Restart the HDFS service and any dependent services.

## Configuring Kerberos for Flume Thrift Source and Sink

The Thrift source can be configured to start in secure mode by enabling Kerberos authentication. To communicate with a secure Thrift source, the Thrift sink should also be operating in secure mode.

- 1. Open the Cloudera Manager Admin Console and navigate to the Flume service.
- 2. Click the Configuration tab.
- 3. Select Scope > Agent.
- 4. Select Category > Main.
- 5. Edit the Configuration File property and add the Thrift source and sink properties listed in the tables below to the configuration file.

**Table 1: Thrift Source Properties** 

Property	Description
kerberos	Set to true to enable Kerberos authentication. The agent-principal and agent-keytab properties are required for successful authentication. The Thrift source in secure mode, will accept connections only from Thrift sinks that have Kerberos-enabled and are successfully authenticated to the KDC.
agent-principal	The Kerberos principal used by the Thrift Source to authenticate to the KDC.
agent-keytab	The path to the keytab file used by the Thrift Source in combination with the agent-principal to authenticate to the KDC.

**Table 2: Thrift Sink Properties** 

Property	Description
kerberos	Set to true to enable Kerberos authentication. In Kerberos mode, client-principal, client-keytab and server-principal are required for successful authentication and communication to a Kerberos enabled Thrift Source.
client-principal	The principal used by the Thrift Sink to authenticate to the Kerberos KDC.

Property	Description
client-keytab	The path to the keytab file used by the Thrift Sink in combination with the client-principal to authenticate to the KDC.
server-principal	The principal of the Thrift Source to which this Thrift Sink connects.

Make sure you are configuring these properties for *each* Thrift source and sink instance. For example, for agent a1, source r1, and sink k1, you would add the following properties:

```
______
# Kerberos properties for Thrift source s1
al.sources.rl.kerberos=true
al.sources.rl.agent-principal=<source_principal>
al.sources.rl.agent-keytab=<path/to/source/keytab>
# Kerberos properties for Thrift sink k1
al.sinks.kl.kerberos=true
al.sinks.kl.client-principal=<sink_principal>
al.sinks.kl.client-keytab=<path/to/sink/keytab>
al.sinks.kl.server-principal=<path/to/source/keytab>
```

Configure these sets of properties for as many instances of the Thrift source and sink as needed to enable Kerberos.

- 6. Click Save Changes to commit the changes.
- 7. Restart the Flume service.

## Configuring YARN for Long-running Applications

Long-running applications such as Spark Streaming jobs will need additional configuration since the default settings only allow the hdfs user's delegation tokens a maximum lifetime of 7 days which is not always sufficient.

You can work around this by configuring the ResourceManager as a proxy user for the corresponding HDFS NameNode so that the ResourceManager can request new tokens when the existing ones are past their maximum lifetime. YARN will then be able to continue performing localization and log-aggregation on behalf of the hdfs user.

Configure the proxy user in Cloudera Manager as follows:

- 1. Go to the Cloudera Manager Admin Console.
- 2. Using the Clusters tab, navigate to the YARN service.
- 3. Click the Configuration tab.
- 4. Select Scope > Resource Manager.
- Select Category > Advanced.
- 6. Check the Enable ResourceManager Proxy User Privileges property checkbox to give the ResourceManager proxy user privileges.
- 7. Click Save Changes.
- 8. Using the **Clusters** tab, navigate to the **HDFS** service.
- **9.** Click the **Configuration** tab.
- Select Scope > HDFS (Service-Wide).
- Select Category > Advanced.
- 12. Add the following string to the Cluster-wide Advanced Configuration Snippet (Safety Valve) for core-site.xml property.

```
cproperty>
<name>hadoop.proxyuser.yarn.hosts
<value>*</value>
</property>
cproperty>
```

<name>hadoop.proxyuser.yarn.groups <value>\*</value> </property>

#### 13. Click Save Changes.

14. Restart the YARN and HDFS services.

## Enabling Kerberos Authentication Without the Wizard

Configurator Cluster Administrator Full Administrator Required Role:

Note that certain steps in the following procedure to configure Kerberos security may not be completed without Full Administrator role privileges.

- Important: Ensure you have secured communication between the Cloudera Manager Server and Agents before you enable Kerberos on your cluster. Kerberos keytabs are sent from the Cloudera Manager Server to the Agents, and must be encrypted to prevent potential misuse of leaked keytabs. For secure communication, you should have at least Level 1 TLS enabled as described in Configuring TLS Security for Cloudera Manager (Level 1).
- Prerequisites These instructions assume you know how to install and configure Kerberos, you already have a working Kerberos key distribution center (KDC) and realm setup, and that you've installed the following Kerberos client packages on all cluster hosts and hosts that will be used to access the cluster, depending on the OS in use.

OS	Packages to be Installed
RHEL/CentOS 5, RHEL/CentOS 6	<ul> <li>openldap-clients on the Cloudera Manager Server host</li> <li>krb5-workstation, krb5-libs on ALL hosts</li> </ul>
SLES	<ul> <li>openldap2-client on the Cloudera Manager Server host</li> <li>krb5-client on ALL hosts</li> </ul>
Ubuntu or Debian	<ul><li>ldap-utils on the Cloudera Manager Server host</li><li>krb5-user on ALL hosts</li></ul>
Windows	■ krb5-workstation, krb5-libs on ALL hosts

Furthermore, Oozie and Hue require that the realm support renewable tickets. Cloudera Manager supports setting up kerberized clusters with MIT KDC and Active Directory.

Important: If you want to integrate Kerberos directly with Active Directory, ensure you have support from your AD administration team to do so. This includes any future support required to troubleshoot issues such as Kerberos TGT/TGS ticket renewal, access to KDC logs for debugging and so on.

For more information about using Active Directory, refer the section below on Considerations when using an Active Directory KDC and the Microsoft AD documentation.

For more information about installing and configuring MIT KDC, see:

- MIT Kerberos Home
- MIT Kerberos Documentation
- Support
  - Kerberos security in Cloudera Manager has been tested on the following version of MIT Kerberos 5:
    - krb5-1.6.1 on Red Hat Enterprise Linux 5 and CentOS 5

- Kerberos security in Cloudera Manager is supported on the following versions of MIT Kerberos 5:
  - krb5-1.6.3 on SLFS 11 Service Pack 1
  - krb5-1.8.1 on Ubuntu
  - krb5-1.8.2 on Red Hat Enterprise Linux 6 and CentOS 6
  - krb5-1.9 on Red Hat Enterprise Linux 6.1

Here are the general steps to using Cloudera Manager to configure Hadoop security on your cluster, each of which is described in more detail in the following sections:

## Step 1: Install Cloudera Manager and CDH

If you have not already done so, Cloudera strongly recommends that you install and configure the Cloudera Manager Server and Cloudera Manager Agents and CDH to set up a fully-functional CDH cluster before you begin doing the following steps to implement Hadoop security features.

## Overview of the User Accounts and Groups in CDH and Cloudera Manager to Support Security

When you install the CDH packages and the Cloudera Manager Agents on your cluster hosts, Cloudera Manager takes some steps to provide system security such as creating the following Unix accounts and setting directory permissions as shown in the following table. These Unix accounts and directory permissions work with the Hadoop Kerberos security requirements.

Note: Cloudera Manager 5.3 introduces a new single user mode. In single user mode, the Cloudera Manager Agent and all the processes run by services managed by Cloudera Manager are started as a single configured user and group. See Single User Mode Requirements for more information.

This User	Runs These Roles
hdfs	NameNode, DataNodes, and Secondary Node
mapred	JobTracker and TaskTrackers (MR1) and Job History Server (YARN)
yarn	ResourceManager and NodeManagers (YARN)
oozie	Oozie Server
hue	Hue Server, Beeswax Server, Authorization Manager, and Job Designer

The hdfs user also acts as the HDFS superuser.

When you install the Cloudera Manager Server on the server host, a new Unix user account called cloudera-scm is created automatically to support security. The Cloudera Manager Server uses this account to create and deploy the host principals and keytabs on your cluster.

#### If you installed CDH and Cloudera Manager at the Same Time

If you have a new installation and you installed CDH and Cloudera Manager at the same time, when you started the Cloudera Manager Agents on your cluster hosts, the Cloudera Manager Agent on each host automatically configured the directory owners shown in the following table to support security. Assuming the owners are configured as shown, the Hadoop daemons can then automatically set the permissions for each of the directories specified by the properties shown below to make sure they are properly restricted. It's critical that the owners are configured exactly as shown below, so don't change them:

Directory Specified in this Property	Owner
dfs.name.dir	hdfs:hadoop
dfs.data.dir	hdfs:hadoop
mapred.local.dir	mapred:hadoop

Directory Specified in this Property	Owner
mapred.system.dirin HDFS	mapred:hadoop
yarn.nodemanager.local-dirs	yarn:yarn
yarn.nodemanager.log-dirs	yarn:yarn
oozie.service.StoreService.jdbc.url(if using Derby)	oozie:oozie
[[database]] name	hue:hue
javax.jdo.option.ConnectionURL	hue: hue

#### If you Installed and Used CDH Before Installing Cloudera Manager

If you have been using HDFS and running MapReduce jobs in an existing installation of CDH before you installed Cloudera Manager, you must manually configure the owners of the directories shown in the table above. Doing so enables the Hadoop daemons to automatically set the permissions for each of the directories. It's critical that you manually configure the owners exactly as shown above.

## Step 2: If You are Using AES-256 Encryption, Install the JCE Policy File

If you are using CentOS or RHEL 5.5 or later, which use AES-256 encryption by default for tickets, you must install the Java Cryptography Extension (JCE) Unlimited Strength Jurisdiction Policy File on all cluster and Hadoop user hosts. There are 2 ways to do this:

- In the Cloudera Manager Admin Console, navigate to the Hosts page. Both, the Add New Hosts to Cluster wizard and the Re-run Upgrade Wizard will give you the option to have Cloudera Manager install the JCE Policy file for you.
- You can follow the JCE Policy File installation instructions in the README.txt file included in the ice policy-x.zip file.

Alternatively, you can configure Kerberos to not use AES-256 by removing aes256-cts:normal from the supported\_enctypes field of the kdc.conf or krb5.conf file. Note that after changing the kdc.conf file, you'll need to restart both the KDC and the kadmin server for those changes to take affect. You may also need to recreate or change the password of the relevant principals, including potentially the Ticket Granting Ticket principal (for example, krbtqt/EXAMPLE.COM@EXAMPLE.COM). If AES-256 is still used after all of those steps, it's because the aes256-cts:normal setting existed when the Kerberos database was created. To fix this, create a new Kerberos database and then restart both the KDC and the kadmin server.

#### To verify the type of encryption used in your cluster:

1. On the local KDC host, type this command in the kadmin.local or kadmin shell to create a test principal:

```
kadmin: addprinc test
```

2. On a cluster host, type this command to start a Kerberos session as the test principal:

3. After successfully running the previous command, type this command to view the encryption type in use:

```
$ klist -e
```

If AES is being used, output like the following is displayed after you type the klist command (note that AES-256 is included in the output):

```
Ticket cache: FILE:/tmp/krb5cc_0
Default principal: test@EXAMPLE.COM
```

```
Valid starting Expires Service principal 05/19/11 13:25:04 05/20/11 13:25:04 krbtgt/EXAMPLE.COM@EXAMPLE.COM
Valid starting
    Etype (skey, tkt): AES-256 CTS mode with 96-bit SHA-1 HMAC, AES-256 CTS mode
with 96-bit SHA-1 HMAC
```

## Step 3: Get or Create a Kerberos Principal for the Cloudera Manager Server

In order to create and deploy the host principals and keytabs on your cluster, the Cloudera Manager Server must have the correct Kerberos principal. Specifically, the Cloudera Manager Server must have a Kerberos principal that has administrator privileges. Typically, principals with the second component of admin in the principal name (for example, username/admin@EXAMPLE.COM) have administrator privileges. This is why admin is shown in the following instructions and examples.

To get or create the Kerberos principal for the Cloudera Manager Server, you can do either of the following:

- Ask your Kerberos administrator to create a Kerberos administrator principal for the Cloudera Manager
- Create the Kerberos principal for the Cloudera Manager Server yourself by using the following instructions in this step.

### Creating the Cloudera Manager Principal

## If you are using Active Directory

- 1. Create an Organizational Unit (OU) in your AD where all the principals used by your CDH cluster will reside.
- 2. Add a new AD user, for example, <username</pre>@EXAMPLE.COM. The password for this user should be set to never expire.
- 3. Use AD's Delegate Control wizard to allow this new user to Create, Delete and Manage User Accounts.

## If you are using MIT KDC

The instructions in this section illustrate an example of creating the Cloudera Manager Server principal for MIT Kerberos. (If you are using another version of Kerberos, refer to your Kerberos documentation for instructions.)

**Note:** If you are running kadmin and the Kerberos Key Distribution Center (KDC) on the same host, use kadmin.local in the following steps. If the Kerberos KDC is running on a remote host, you must use kadmin instead of kadmin.local.

In the kadmin.local or kadmin shell, type the following command to create the Cloudera Manager Server principal, replacing EXAMPLE. COM with the name of your realm:

```
kadmin: addprinc -pw <Password> cloudera-scm/admin@EXAMPLE.COM
```

## Step 4: Import KDC Account Manager Credentials

- 1. In the Cloudera Manager Admin Console, select Administration > Kerberos.
- Navigate to the Credentials tab and click Import Kerberos Account Manager Credentials.
- 3. In the Import Kerberos Account Manager Credentials dialog box, enter the username and password for the user that can create principals for CDH cluster in the KDC. This is the user/principal you created in Step 3: Get or Create a Kerberos Principal for the Cloudera Manager Server on page 36. Cloudera Manager encrypts the username and password into a keytab and uses it as needed to create new principals.
  - Note: The username entered should have the realm portion in upper-case only as shown in the example in the UI.

Click **Close** when complete.

# Step 5: Configure the Kerberos Default Realm in the Cloudera Manager Admin Console

#### **Full Administrator** Required Role:

Important: Hadoop is unable to use a non-default realm. The Kerberos default realm is configured in the libdefaults property in the /etc/krb5.conf file on every host in the cluster:

```
[libdefaults]
   default_realm = EXAMPLE.COM
```

- 1. In the Cloudera Manager Admin Console, select Administration > Settings.
- 2. Click the Security category, and enter the Kerberos realm for the cluster in the Kerberos Security Realm field (for example, EXAMPLE.COM or HADOOP.EXAMPLE.COM) that you configured in the krb5.conf file.
- 3. Click Save Changes.

### Step 6: Stop All Services

Configurator Cluster Administrator Full Administrator Operator Required Role:

Before you enable security in CDH, you must stop all Hadoop daemons in your cluster and then change some configuration properties. You must stop all daemons in the cluster because after one Hadoop daemon has been restarted with the configuration properties set to enable security. Daemons running without security enabled will be unable to communicate with that daemon. This requirement to stop all daemons makes it impossible to do a rolling upgrade to enable security on a Hadoop cluster.

Stop all running services, and the Cloudera Management service, as follows:

### Stopping All Services

- 1. On the Home page, click to the right of the cluster name and select **Stop**.
- 2. Click **Stop** in the confirmation screen. The **Command Details** window shows the progress of stopping services.

When All services successfully stopped appears, the task is complete and you can close the Command Details window.

### Stopping the Cloudera Management Service

- 1. On the Home page, click to the right of Cloudera Management Service and select Stop.
- 2. Click **Stop** to confirm. The **Command Details** window shows the progress of stopping the roles.
- **3.** When **Command completed with** *n***/** *n* **successful subcommands** appears, the task is complete. Click **Close**.

### Step 7: Enable Hadoop Security

Required Role: Configurator Cluster Administrator Full Administrator

To enable Hadoop security for the cluster, you enable it on an HDFS service. After you do so, the Cloudera Manager Server automatically enables Hadoop security on the MapReduce and YARN services associated with that HDFS service.

- 1. Navigate to the HDFS Service > Configuration tab.
- 2. In the Search field, type Hadoop Secure to show the Hadoop security properties (found under the Service-Wide > **Security** category).
- 3. Click the value for the Hadoop Secure Authentication property and select the kerberos option to enable Hadoop security on the selected HDFS service.
- 4. Click the value for the Hadoop Secure Authorization property and select the checkbox to enable service-level authorization on the selected HDFS service. You can specify comma-separated lists of users and groups

authorized to use Hadoop services and/or perform admin operations using the following properties under the **Service-Wide > Security** section:

- Authorized Users: Comma-separated list of users authorized to use Hadoop services.
- Authorized Groups: Comma-separated list of groups authorized to use Hadoop services.
- Authorized Admin Users: Comma-separated list of users authorized to perform admin operations on Hadoop.
- Authorized Admin Groups: Comma-separated list of groups authorized to perform admin operations on
  - Important: For Cloudera Manager's Monitoring services to work, the hue user should always be added as an authorized user.
- 5. In the Search field, type DataNode Transceiver to find the DataNode Transceiver Port property.
- 6. Click the value for the DataNode Transceiver Port property and specify a privileged port number (below 1024). Cloudera recommends 1004.
  - Note: If there is more than one DataNode Role Group, you must specify a privileged port number for each DataNode Transceiver Port property.
- 7. In the Search field, type DataNode HTTP to find the DataNode HTTP Web UI Port property and specify a privileged port number (below 1024). Cloudera recommends 1006.
  - Note: These port numbers for the two DataNode properties must be below 1024 in order to provide part of the security mechanism to make it impossible for a user to run a MapReduce task that impersonates a DataNode. The port numbers for the NameNode and Secondary NameNode can be anything you want, but the default port numbers are good ones to use.
- 8. In the Search field type **Data Directory Permissions** to find the **DataNode Data Directory Permissions** property.
- 9. Reset the value for the DataNode Data Directory Permissions property to the default value of 700 if not already set to that.
- 10. Make sure you have changed the DataNode Transceiver Port, DataNode Data Directory Permissions and **DataNode HTTP Web UI Port** properties for every DataNode role group.
- **11.** Click **Save Changes** to save the configuration settings.

#### To enable ZooKeeper security:

- 1. Navigate to the ZooKeeper Service > Configuration tab and click View and Edit.
- 2. Click the value for **Enable Kerberos Authentication** property.
- 3. Click Save Changes to save the configuration settings.

### To enable HBase security:

- 1. Navigate to the HBase Service > Configuration tab and click View and Edit.
- 2. In the Search field, type HBase Secure to show the Hadoop security properties (found under the Service-Wide > **Security** category).
- 3. Click the value for the HBase Secure Authorization property and select the checkbox to enable authorization on the selected HBase service.
- 4. Click the value for the HBase Secure Authentication property and select kerberos to enable authorization on the selected HBase service.
- **5.** Click **Save Changes** to save the configuration settings.

### (CDH 4.3 or later) To enable Solr security:

- 1. Navigate to the Solr Service > Configuration tab and click View and Edit.
- 2. In the Search field, type Solr Secure to show the Solr security properties (found under the Service-Wide > **Security** category).

- 3. Click the value for the Solr Secure Authentication property and select kerberos to enable authorization on the selected Solr service.
- 4. Click Save Changes to save the configuration settings.
  - Note: If you use the Cloudera Manager Admin Console to generate a client configuration file after you enable Hadoop security on your cluster, the generated configuration file will not contain the Kerberos principal and keytab file that end users need to authenticate. Users must obtain Kerberos principal and keytab file from your Kerberos administrator and then run the kinit command themselves.

# Step 8: Wait for the Generate Credentials Command to Finish

#### Configurator | Cluster Administrator | Full Administrator Required Role:

After you enable security for any of the services in Cloudera Manager, a command called Generate Credentials will be triggered automatically. You can watch the progress of the command on the top right corner of the screen that shows the running commands. Wait for this command to finish (indicated by a grey box containing "0" in it).

# Step 9: Enable Hue to Work with Hadoop Security using Cloudera Manager

# Required Role: Cluster Administrator Full Administrator

If you are using a Hue service, you must add a role instance of Kerberos Ticket Renewer to the Hue service to enable Hue to work properly with the secure Hadoop cluster using Cloudera Manager. The Kerberos Ticket Renewer role must be located on the same host as the Hue Server role. You add can the necessary Kerberos Ticket Renewer role instances using Cloudera Manager.

The Hue Kerberos Ticket Renewer service will only renew tickets for the Hue service, for the principal hue/<hostname>@<YOUR-REALM.COM>. The Hue principal is then used to impersonate other users for applications within Hue such as the Job Browser, File Browser and so on.

Other services, such as HDFS and MapReduce, do not use the Hue Kerberos Ticket Renewer. They obtain tickets at startup and use those tickets to obtain Delegation Tokens for various access privileges. Each service handles its own ticket renewal as needed.

To add a Kerberos Ticket Renewer role instance using Cloudera Manager:

- 1. Go to the Hue service.
- 2. Click the Instances tab.
- 3. Click the Add Role Instances button.
- 4. Assign the Kerberos Ticket Renewer role instance to the same host as the Hue server.
- 5. When the wizard is finished, the status will display Finished and the Kerberos Ticket Renewer role instance is configured. The Hue service will now work with the secure Hadoop cluster.
- 6. Repeat these steps for each Hue Server role.

#### Troubleshooting the Kerberos Ticket Renewer:

If the Hue Kerberos Ticket Renewer does not start, check your KDC configuration and the ticket renewal property, maxrenewlife, for the hue/<hostname> and krbtgt principals to ensure they are renewable. If not, running the following commands on the KDC will enable renewable tickets for these principals.

```
kadmin.local: modprinc -maxrenewlife 90day krbtqt/YOUR_REALM.COM
kadmin.local: modprinc -maxrenewlife 90day +allow_renewable hue/<hostname>@YOUR-REALM.COM
```

# Step 10: (Flume Only) Use Substitution Variables for the Kerberos Principal and Keytab

Required Role: Configurator Cluster Administrator Full Administrator

As described in Flume Security Configuration in the CDH 4 Security Guide, if you are using Flume on a secure cluster you must configure the HDFS sink with the following configuration options in the flume.conf file:

- hdfs.kerberosPrincipal fully-qualified principal.
- hdfs.kerberosKeytab location on the local host of the keytab containing the user and host keys for the above principal

Here is an example of an HDFS sink configuration in the flume.conf file (the majority of the HDFS sink configuration options have been omitted):

```
agent.sinks.sink-1.type = HDFS
agent.sinks.sink-1.hdfs.kerberosPrincipal = flume/_HOST@YOUR-REALM.COM
agent.sinks.sink-1.hdfs.kerberosKeytab = /etc/flume-ng/conf/flume.keytab
agent.sinks.sink-1.hdfs.proxyUser = weblogs
```

Since Cloudera Manager generates the Flume keytab files for you, and the locations of the keytab files cannot be known beforehand, substitution variables are required for Flume. Cloudera Manager provides two Flume substitution variables called \$kerberos\_principal and \$kerberos\_keytab to configure the principal name and the keytab file path respectively on each host.

Here is an example of using the substitution variables to configure the options shown in the previous example:

```
agent.sinks.sink-1.type = hdfs
agent.sinks.sink-1.hdfs.kerberosPrincipal = $KERBEROS_PRINCIPAL
agent.sinks.sink-1.hdfs.kerberosKeytab = $KERBEROS_KEYTAB
agent.sinks.sink-1.hdfs.proxyUser = weblogs
```

Use the following instructions to have Cloudera Manager add these variables to the flume.conf file on every host that Cloudera Manager manages.

To use the Flume substitution variables for the Kerberos principal and keytab:

- 1. Go to the **Flume service > Configuration** page in Cloudera Manager.
- Click Agent.
- 3. In the Configuration File property, add the configuration options with the substitution variables. For example:

```
agent.sinks.sink-1.type = hdfs
agent.sinks.sink-1.hdfs.kerberosPrincipal = $KERBEROS_PRINCIPAL
agent.sinks.sink-1.hdfs.kerberosKeytab = $KERBEROS_KEYTAB
agent.sinks.sink-1.hdfs.proxyUser = weblogs
```

4. Click Save.

# Step 11: (CDH 4.0 and 4.1 only) Configure Hue to Use a Local Hive Metastore

If using Hue and the Bypass Hive Metastore Server option is not selected (metastore bypass is disabled by default), then Hue will not be able to communicate with Hive with CDH 4.0 or CDH 4.1. This is not a problem with

If you are using CDH 4.0 or 4.1, you can workaround this issue following the instructions in the Known Issues section of the Cloudera Manager 4 Release Notes.

## Step 12: Start All Services

```
Configurator
                        Cluster Administrator Full Administrator
Operator
```

Start all services on your cluster:

### Starting All Services

1. On the Home page, click 💌 to the right of the cluster name and select **Start**.

2. Click Start that appears in the next screen to confirm. The Command Details window shows the progress of starting services.

When All services successfully started appears, the task is complete and you can close the Command Details window.

### Starting the Cloudera Management Service

- 1. On the Home page, click to the right of **Cloudera Management Service** and select **Start**.
- 2. Click **Start** to confirm. The **Command Details** window shows the progress of starting the roles.
- 3. When Command completed with n/n successful subcommands appears, the task is complete. Click Close.

### Step 13: Deploy Client Configurations

Required Role: Configurator Cluster Administrator Full Administrator

- On the Home page, click to the right of the cluster name and select **Deploy Client Configuration**.
- 2. Click Deploy Client Configuration.

# Step 14: Create the HDFS Superuser Principal

To create home directories for users you require access to a superuser account. In HDFS, the user account running the NameNode process (hdfs by default) is a superuser. CDH automatically creates the hdfs superuser account on each cluster host during CDH installation. When you enable Kerberos for the HDFS service, you lose access to the hdfs superuser account via sudo -u hdfs commands. To enable access to the hdfs superuser account when Kerberos is enabled, you must create a Kerberos principal or an AD user whose first or only component is hdfs. Alternatively, you can designate a superuser group, whose members are superusers.

To create the hdfs superuser principal:

#### If you are using Active Directory

Add a new user account to Active Directory, hdfs@EXAMPLE.COM.

### If you are using MIT KDC

In the kadmin.local or kadmin shell, type the following command to create a Kerberos principal named hdfs:

.----kadmin: addprinc hdfs@EXAMPLE.COM

This command prompts you to create a password for the hdfs principal. Use a strong password because this principal provides superuser access to all of the files in HDFS.

To run commands as the hdfs superuser, you must obtain Kerberos credentials for the hdfs principal. To do so, run the following command and provide the password:

\$ kinit hdfs@EXAMPLE.COM

### Designating a Superuser Group

To designate a group of superusers instead of using the default hdfs account, follow these steps:

- 1. Navigate to the HDFS Service > Configuration tab.
- 2. In the Search field, type **Superuser** to display the **Superuser Group** property.
- **3.** Change the value from the default supergroup to the appropriate group name for your environment.
- 4. Click Save Changes.

For this change to take effect, you must restart the cluster.

### Step 15: Get or Create a Kerberos Principal for Each User Account

Now that Kerberos is configured and enabled on your cluster, you and every other Hadoop user must have a Kerberos principal or keytab to obtain Kerberos credentials to be allowed to access the cluster and use the Hadoop services. In the next step of this procedure, you will need to create your own Kerberos principals in order to verify that Kerberos security is working on your cluster. If you and the other Hadoop users already have a Kerberos principal or keytab, or if your Kerberos administrator can provide them, you can skip ahead to the next

The following instructions explain how to create a Kerberos principal for a user account.

### If you are using Active Directory

Add a new AD user account, <username>@EXAMPLE.COM for each Cloudera Manager service that should use Kerberos authentication.

### If you are using MIT KDC

1. In the kadmin.local or kadmin shell, use the following command to create a principal for your account by replacing EXAMPLE. COM with the name of your realm, and replacing username with a username:

```
kadmin: addprinc username@EXAMPLE.COM
```

**2.** When prompted, enter the password twice.

## Step 16: Prepare the Cluster for Each User

Before you and other users can access the cluster, there are a few tasks you must do to prepare the hosts for each user.

- 1. Make sure all hosts in the cluster have a Unix user account with the same name as the first component of that user's principal name. For example, the Unix account joe should exist on every box if the user's principal name is <code>joe@YOUR-REALM.COM</code>. You can use LDAP for this step if it is available in your organization.
  - Note: Each account must have a user ID that is greater than or equal to 1000. In the /etc/hadoop/conf/taskcontroller.cfg file, the default setting for the banned.users property is mapred, hdfs, and bin to prevent jobs from being submitted via those user accounts. The default setting for the min.user.id property is 1000 to prevent jobs from being submitted with a user ID less than 1000, which are conventionally Unix super users.
- 2. Create a subdirectory under /user on HDFS for each user account (for example, /user/joe). Change the owner and group of that directory to be the user.

```
$ hadoop fs -mkdir /user/joe
$ hadoop fs -chown joe /user/joe
```

Note: sudo -u hdfs is not included in the commands above. This is because it is not required if Kerberos is enabled on your cluster. You will, however, need to have Kerberos credentials for the HDFS super user in order to successfully run these commands. For information on gaining access to the HDFS super user account, see Step 14: Create the HDFS Superuser Principal on page 41

### Step 17: Verify that Kerberos Security is Working

After you have Kerberos credentials, you can verify that Kerberos security is working on your cluster by trying to run MapReduce jobs. To confirm, try launching a sleep or a pi job from the provided Hadoop examples (/usr/lib/hadoop/hadoop-examples.jar).

#### Note:

This section assumes you have a fully-functional CDH cluster and you have been able to access HDFS and run MapReduce jobs before you followed these instructions to configure and enable Kerberos on your cluster. If you have not already done so, you should at a minimum use the Cloudera Manager Admin Console to generate a client configuration file to enable you to access the cluster. For instructions, see <u>Deploying Client Configuration Files</u>.

### To verify that Kerberos security is working:

**1.** Acquire Kerberos credentials for your user account.

```
______
$ kinit USERNAME@YOUR-LOCAL-REALM.COM
```

- **2.** Enter a password when prompted.
- 3. Submit a sample pi calculation as a test MapReduce job. Use the following command if you use a package-based setup for Cloudera Manager:

```
$ hadoop jar /usr/lib/hadoop-0.20/hadoop-0.20.2*examples.jar pi 10 10000
Number of Maps = 10
Samples per Map = 10000
Job Finished in 38.572 seconds
```

If you have a parcel-based setup, use the following command instead:

```
_____
$ hadoop jar /opt/cloudera/parcels/CDH/lib/hadoop-0.20-mapreduce/hadoop-examples.jar
pi 10 10000
Number of Maps = 10
Samples per Map = 10000
Job Finished in 30.958 seconds
```

You have now verified that Kerberos security is working on your cluster.

### Important:

Running a MapReduce job will fail if you do not have a valid Kerberos ticket in your credentials cache. You can examine the Kerberos tickets currently in your credentials cache by running the klist command. You can obtain a ticket by running the kinit command and either specifying a keytab file containing credentials, or entering the password for your principal. If you do not have a valid ticket, vou will receive an error such as:

```
11/01/04 12:08:12 WARN ipc.Client:
Exception encountered while connecting to the server :
javax.security.sasl.SaslException:GSS initiate failed
[Caused by GSSException: No valid credentials provided (Mechanism level: Failed
to find any
Kerberos tgt)]
Bad connection to FS. command aborted. exception: Call to nn-host/10.0.0.2:8020
failed on local exception:
java.io.IOException: javax.security.sasl.SaslException: GSS initiate failed
[Caused by GSSException: No valid credentials provided
(Mechanism level: Failed to find any Kerberos tgt)]
```

# Step 18: (Optional) Enable Authentication for HTTP Web Consoles for Hadoop Roles

```
Required Role: Configurator Cluster Administrator Full Administrator
```

Authentication for access to the HDFS, MapReduce, and YARN roles' web consoles can be enabled via a configuration option for the appropriate service. To enable this authentication:

- 1. From the Clusters tab, select the service (HDFS, MapReduce, or YARN) for which you want to enable authentication.
- 2. Click the Configuration tab.
- 3. Select Scope > serviceName Service-Wide.
- Select Category > Security.
- 5. Select Enable Kerberos Authentication for HTTP Web-Consoles.
- 6. Click Save Changes to commit the changes.
- 7. Once the command finishes, restart all roles of that service.

# Configuring Authentication in Cloudera Navigator

Cloudera Navigator supports user authentication against Cloudera Manager user accounts and against an external LDAP or Active Directory service. External authentication enables you to assign Cloudera Navigator user roles to LDAP or Active Directory groups containing the appropriate users for each user role. Authentication with a Cloudera Manager user account requires either the Full Administrator or Navigator Administrator user role, and enables the user to use Cloudera Navigator features or to configure the external authentication service.

# Configuring External Authentication for Cloudera Navigator

Navigator Administrator Full Administrator Required Role:

Important: This feature is available only with a Cloudera Enterprise license; it is not available in Cloudera Express. For information on Cloudera Enterprise licenses, see Managing Licenses.

Cloudera Navigator supports user authentication against Cloudera Manager user accounts and against an external service. The external service can be either LDAP or Active Directory. User authentication against Cloudera Manager user accounts requires users to have one of two Cloudera Manager user roles, either Full Administrator or Navigator Administrator. External authentication enables you to assign Cloudera Navigator user roles to LDAP or Active Directory groups to which the appropriate users belong.

For more information about Cloudera Manager user accounts, see Cloudera Manager User Accounts on page 9. For more information about Cloudera Navigator user roles, see <u>Cloudera Navigator User Roles</u> on page 229.

The following sections describe how to configure the supported external directory services.

# Configuring Cloudera Navigator Authentication Using Active Directory

### Important:

Cloudera Navigator has its own role-based access control and user management scheme. If you want to use LDAP/AD authentication, Cloudera Navigator roles must be explicitly assigned to AD users to allow them to log in to Navigator. To assign roles to AD users, log in to Cloudera Navigator for the first time using a Cloudera Manager admin user. Any non-externally authenticated Cloudera Manager user that has Full Administrator or Navigator Administrator privileges will have admin access to Cloudera Navigator. You can use this account to set up user groups and assign Cloudera Navigator roles to AD users.

Hence, Cloudera recommends that the Authentication Backend Order property be set initially to Cloudera Manager then External. Otherwise, the external authentication system will be checked first, and if the same user credentials also exist in the specified LDAP or Active Directory, the user will be authenticated there, and will not be authenticated as a Cloudera Manager administrator. Since no user roles will have been set up yet for the users in the external authentication system, the user's attempt to log in will fail. Once the groups and user roles for Cloudera Navigator are set up, the Authentication Backend Order can be changed to External then Cloudera Manager or External Only, if desired.

To configure Cloudera Navigator to use AD authentication:

- 1. Select Clusters > Cloudera Management Service.
- 2. Click the Configuration tab.
- 3. Select Scope > Navigator Metadata Server.
- Select Category > External Authentication.
- 5. In the Authentication Backend Order field, select the order in which Cloudera Navigator should attempt its authentication. You can choose to authenticate users using just one of the methods (using Cloudera Manager user accounts is the default), or you can set it so that if the user cannot be authenticated by the first method, it will attempt using the second method.
- **6.** In the **External Authentication Type** property, select **Active Directory**.
- 7. In the LDAP URL property, provide the URL of the Active Directory server.
- 8. In the Bind Distinguished Name, enter the distinguished name of the user to bind as. This is used to connect to Active Directory for searching groups and to get other user information.
- 9. In the LDAP Bind Password, enter the password for the bind user entered above.
- 10. In the Active Directory NT Domain property, provide the NT domain to authenticate against.
- 11. Click Save Changes to commit the changes.
- 12. After changing the configuration settings, restart the Navigator Metadata Service: click the Instances tab on the Cloudera Management Service page, check Navigator Metadata Service, and click Actions for Selected > Restart.

# Configuring Cloudera Navigator Authentication Using an OpenLDAP-compatible Server

For an OpenLDAP-compatible directory, you have several options for searching for users and groups:

- You can specify a single base Distinguished Name (DN) and then provide a "Distinguished Name Pattern" to use to match a specific user in the LDAP directory.
- Search filter options let you search for a particular user based on somewhat broader search criteria for example Cloudera Navigator users could be members of different groups or organizational units (OUs), so a single pattern won't find all those users. Search filter options also let you find all the groups to which a user belongs, to help determine if that user should be allowed to log in.
- 1. Select Clusters > Cloudera Management Service.
- **2.** Click the **Configuration** tab.
- 3. Select Scope > Navigator Metadata Server.
- 4. Select Category > External Authentication.

- 5. In the Authentication Backend Order field, select the order in which Cloudera Navigator should attempt its authentication. You can choose to authenticate users using just one of the methods (using Cloudera Manager user accounts is the default), or you can set it so that if the user cannot be authenticated by the first method, it will attempt using the second method.
- 6. In the External Authentication Type, select LDAP.
- 7. In the LDAP URL property, provide the URL of the LDAP server and (optionally) the base Distinguished Name (DN) (the search base) as part of the URL — for example ldap://ldap-server.corp.com/dc=corp.dc=com.
- 8. In the Bind Distinguished Name property, enter the distinguished name of the user to bind as. This is used to connect to the LDAP server for searching groups and to get other user information.
- 9. In the LDAP Bind Password property, enter the password for the bind user entered above.
- 10. To use a single "Distinguished Name Pattern", provide a pattern in the LDAP Distinguished Name Pattern property.

Use {0} in the pattern to indicate where the username should go. For example, to search for a distinguished name where the uid attribute is the username, you might provide a pattern similar to uid={0}, ou=People, dc=corp, dc=com. Cloudera Navigator substitutes the name provided at login into this pattern and performs a search for that specific user. So if a user provides the username "foo" at the Cloudera Navigator login page, Cloudera Navigator will search for the DN uid=foo,ou=People,dc=corp,dc=com.

If you provided a base DN along with the URL, the pattern only needs to specify the rest of the DN pattern. For example, if the URL you provide is ldap://ldap-server.comp.com/dc=corp,dc=com, and the pattern is uid={0},ou=People, then the search DN will be uid=foo,ou=People,dc=corp,dc=com.

11. You can also search using User and/or Group search filters, using the LDAP User Search Base, LDAP User Search Filter, LDAP Group Search Base and LDAP Group Search Filter settings. These allow you to combine a base DN with a search filter to allow a greater range of search targets.

For example, if you want to authenticate users who may be in one of multiple OUs, the search filter mechanism will allow this. You can specify the User Search Base DN as dc=corp, dc=com and the user search filter as uid={0}. Then Cloudera Navigator will search for the user anywhere in the tree starting from the Base DN. Suppose you have two OUs—ou=Engineering and ou=Operations—Cloudera Navigator will find User "foo" if it exists in either of these OUs, that is, uid=foo, ou=Engineering, dc=corp, dc=com or uid=foo,ou=Operations,dc=corp,dc=com.

You can use a user search filter along with a DN pattern, so that the search filter provides a fallback if the DN pattern search fails.

The Groups filters let you search to determine if a DN or username is a member of a target group. In this case, the filter you provide can be something like member={0} where {0} will be replaced with the **DN** of the user you are authenticating. For a filter requiring the username, {1} may be used, as memberUid={1}. This will return a list of groups to which the user belongs.

- **12.** Click **Save Changes** to commit the changes.
- **13.** After changing the configuration settings, restart the **Navigator Metadata Service**: click the **Instances** tab on the Cloudera Management Service page, check Navigator Metadata Service, and click Actions for Selected > Restart.

### Configuring Cloudera Navigator to Use LDAPS

If the LDAP server certificate has been signed by a trusted Certificate Authority (that is, VeriSign, GeoTrust, and so on), steps 1 and 2 below may not be necessary.

- 1. Copy the CA certificate file to the Cloudera Navigator Server host.
- 2. Import the CA certificate(s) from the CA certificate file to the local truststore. The default truststore is located  $in the \$ \texttt{JAVA\_HOME/jre/lib/security/cacerts} file. This contains the default CA information shipped with the $\texttt{JAVA\_HOME/jre/lib/security/cacerts} file. This contains the default CA information shipped with the think the tensor of the$ the JDK. Create an alternate default file called jssecacerts in the same location as the cacerts file. You can now safely append CA certificates for any private or public CAs not present in the default cacerts file, while keeping the original file intact.

For our example, we will follow this recommendation by copying the default cacerts file into the new jssecacerts file, and then importing the CA certificate to this alternate truststore.

```
$ cp $JAVA_HOME/jre/lib/security/cacerts \
 $JAVA_HOME/jre/lib/jssecacerts
```

```
$ /usr/java/latest/bin/keytool -import -alias nt_domain_name \
-keystore /usr/java/latest/jre/lib/security/jssecacerts -file path_to_cert
```

- Note:
  - The default password for the cacerts store is **changeit**.
  - The alias can be any name (not just the domain name).
- **3.** Configure the LDAP URL property to use ldaps://ldap\_server instead of ldap://ldap\_server.

# Configuring Cloudera Navigator Authentication Using SAML

Cloudera Navigator supports the Security Assertion Markup Language (SAML), an XML-based open standard data format for exchanging authentication and authorization data between parties, in particular, between an identity provider (IDP) and a service provider (SP). The SAML specification defines three roles: the principal (typically a user), the IDP, and the SP. In the use case addressed by SAML, the principal (user agent) requests a service from the service provider. The service provider requests and obtains an identity assertion from the IDP. On the basis of this assertion, the SP can make an access control decision—in other words it can decide whether to perform some service for the connected principal.

The primary SAML use case is called web browser single sign-on (SSO). A user wielding a user agent (usually a web browser) requests a web resource protected by a SAML SP. The SP, wishing to know the identity of the requesting user, issues an authentication request to a SAML IDP through the user agent. In the context of this terminology, Cloudera Navigator operates as a SP. This topic discusses the Cloudera Navigator part of the configuration process; it assumes that you are familiar with SAML and SAML configuration in a general sense, and that you have a functioning IDP already deployed.

Setting up Cloudera Navigator to use SAML requires the following steps.

#### **Preparing Files**

You will need to prepare the following files and information, and provide these to Cloudera Navigator:

- A Java keystore containing a private key for Cloudera Navigator to use to sign/encrypt SAML messages.
- The SAML metadata XML file from your IDP. This file must contain the public certificates needed to verify the sign/encrypt key used by your IDP per the SAML Metadata Interoperability Profile.
- The entity ID that should be used to identify the Navigator Metadata Server instance.
- How the user ID is passed in the SAML authentication response:
  - As an attribute. If so, what identifier is used.
  - As the NamelD.
- The method by which the Cloudera Navigator role will be established:
  - From an attribute in the authentication response:
    - What identifier will be used for the attribute
    - What values will be passed to indicate each role
  - From an external script that will be called for each use:
    - The script takes user ID as \$1
    - The script must assign an exit code to reflect successful authentication of the assigned role:
      - 0 Full Administrator

- 1 User Administrator
- 2 Auditing Viewer
- 4 Lineage Viewer
- 8 Metadata Administrator
- 16 Policy Viewer
- 32 Policy Administrator
- A negative value is returned for a failure to authenticate

To assign more than one role, add the numbers for the roles. For example, to assign the Policy Viewer and User Administrator roles, the exit code should be 17.

### Configuring Cloudera Navigator

- 1. Select Clusters > Cloudera Management Service.
- 2. Click the Configuration tab.
- 3. Select Scope > Navigator Metadata Server.
- Select Category > External Authentication.
- **5.** Type SAML in the Search box.
- 6. Set the External Authentication Type property to SAML (the Authentication Backend Order property is ignored for SAML).
- 7. Set the Path to SAML IDP Metadata File property to point to the IDP metadata file.
- 8. Set the Path to SAML Keystore File property to point to the Java keystore file containing the Cloudera Navigator private key (prepared above).
- **9.** In the **SAML Keystore Password** property, set the SAML keystore password.
- 10. In the Alias of SAML Sign/Encrypt Private Key property, set the alias used to identify the private key for Cloudera Navigator to use.
- 11. In the SAML Sign/Encrypt Private Key Password property, set the password for the sign/encrypt private key.
- **12.** Set the **SAML Entity ID** property if:
  - There is more than one Cloudera Navigator instance being used with the same IDP (each instance needs a different entity ID).
  - Entity IDs are assigned by organizational policy.

The entity ID value should be unique to the current Navigator Metadata Server installation.

13. In the Source of User ID in SAML Response property, set whether the user ID will be obtained from an attribute or the NamelD.

If an attribute will be used, set the attribute name in the SAML Attribute Identifier for User ID property. The default value is the normal OID used for user IDs and so may not need to be changed.

- 14. In the SAML Role Assignment Mechanism property, set whether the role assignment will be done from an attribute or an external script.
  - If an attribute will be used:
    - In the SAML Attribute Identifier for User Role property, set the attribute name if necessary. The default value is the normal OID used for OrganizationalUnits and so may not need to be changed.
    - In the SAML Attribute Values for Roles property, set which attribute values will be used to indicate the user role.
  - If an external script will be used, set the path to that script in the Path to SAML Role Assignment Script property. Make sure that the script is executable (an executable binary is fine - it doesn't need to be a shell script).
- **15.** Click **Save Changes** to commit the changes.
- **16.** Restart the Navigator Metadata Server role.

### Configuring the IDP

After the Cloudera Navigator is restarted, it will attempt to redirect to the IDP login page instead of showing the normal Cloudera Navigator login page. This may or may not succeed, depending on how the IDP is configured. In either case, the IDP will need to be configured to recognize Cloudera Navigator before authentication will actually succeed. The details of this process are specific to each IDP implementation - refer to your IDP documentation for details.

- 1. Download Cloudera Navigator's SAML metadata XML file from http://hostname:7187/saml/metadata.
- 2. Inspect the metadata file and ensure that any URLs contained in the file can be resolved by users' web browsers. The IDP will redirect web browsers to these URLs at various points in the process. If the browser cannot resolve them, authentication will fail. If the URLs are incorrect, you can manually fix the XML file or set the SAML Entity Base URL property in the Navigator Metadata Server configuration to the right value, and then re-download the file.
- 3. Provide this metadata file to your IDP using whatever mechanism your IDP provides.
- 4. Ensure that the IDP has access to whatever public certificates are necessary to validate the private key that was provided by Cloudera Navigator earlier.
- 5. Ensure that the IDP is configured to provide the User ID and Role using the attribute names that Cloudera Navigator was configured to expect, if relevant.
- 6. Ensure the changes to the IDP configuration have taken effect (a restart may be necessary).

### Verifying Authentication and Authorization

- 1. Return to the Cloudera Navigator home page at: http://hostname:7187/.
- 2. Attempt to log in with credentials for a user that is entitled. The authentication should complete and you should see the Home page.
- 3. If authentication fails, you will see an IDP provided error message. Cloudera Navigator is not involved in this part of the process, and you must ensure the IDP is working correctly to complete the authentication.
- 4. If authentication succeeds but the user is not authorized to use Cloudera Navigator, they will be taken to an error page that explains the situation. If a user who should be authorized sees this error, then you will need to verify their role configuration, and ensure that it is being properly communicated to the Navigator Metadata Server, whether by attribute or external script. The Cloudera Navigator log will provide details on failures to establish a user's role. If any errors occur during role mapping, Cloudera Navigator will assume the user is unauthorized.

### Bypassing SAML SSO

You can bypass SAML SSO by directly accessing the Cloudera Navigator login page at http://hostname:7187/login.html. If the Cloudera Management Service property Authentication Backend Order, is set to anything but External Only, a Cloudera Manager user will be able to log in to Cloudera Navigator.

# Managing Users and Groups for Cloudera Navigator

Required Role: User Administrator Full Administrator

Note: The above are Cloudera Navigator user roles. Users with the Cloudera Manager user roles Navigator Administrator or Full Administrator who log into the Cloudera Navigator Web UI with their Cloudera Manager credentials will be logged in with the Full Administrator Cloudera Navigator user

Cloudera Navigator supports user authentication against Cloudera Manager user accounts and against an external LDAP or Active Directory service. External authentication enables you to assign Cloudera Navigator user roles to LDAP or Active Directory groups containing the appropriate users for each user role.

# Assigning Cloudera Navigator User Roles to LDAP or Active Directory Groups

This section assumes that values for your LDAP or Active Directory directory service have been configured in Cloudera Manager as described in Configuring External Authentication for Cloudera Navigator. This section also

assumes that your LDAP or Active Directory service contains user groups that correspond to Cloudera Navigator user roles having the permissions you want each group of users to have. If not, you should assign your users to such groups now. The Cloudera Navigator user roles are as follows:

- Full Administrator
- User Administrator
- Auditing Viewer
- Lineage Viewer
- Metadata Administrator
- Policy Viewer
- Policy Administrator

Each of these roles and the permissions associated with it are described in Cloudera Navigator User Roles.

To add or remove Cloudera Navigator user roles to LDAP or Active Directory user groups, you should know the names of the directory groups you want to configure, and then perform the following steps:

- 1. Open the Cloudera Navigator Web UI in one of the following ways:
  - On the Clusters menu of Cloudera Manager, click Cloudera Navigator in the Cloudera Management Service section for the desired cluster.
  - Click the Instances tab on the Cloudera Management Service page, and click Navigator Metadata Server. In the **Summary** section's **Quick Links**, click **Cloudera Navigator**.
- 2. Log in to Cloudera Navigator with the credentials of a user having one or more of the following user roles:
  - Cloudera Manager Full Administrator
  - Cloudera Manager Navigator Administrator
  - Cloudera Navigator Full Administrator
  - Cloudera Navigator User Administrator
- 3. Click the **Administration** tab in the upper right.
- 4. Search for an LDAP or Active Directory group by entering its name (or the first portion of the name) in the search field.
  - Select **All Groups** to search among all groups in the external directory.
  - Select Groups with Navigator Roles to display only external directory groups that have already been assigned one or more Cloudera Navigator user roles.
- 5. From the LDAP or Active Directory groups displayed, select the group to which you want to assign a Cloudera Navigator user role or roles. If roles have already been assigned to the group, they are listed beneath the name of the group in the main panel.
- **6.** Click **Manage Role Assignment** in the upper right.
- 7. Click the checkbox for each Cloudera Navigator user role you want assigned to that Active Directory or LDAP group. Uncheck any already-assigned roles that you want to remove from the group.
- 8. Click Save.

If a user's role assignments are changed, the changes take effect with the user's next new session, that is, the next time the user logs in to Cloudera Navigator.

# Configuring Authentication in CDH Using the Command Line

The security features in CDH 5 enable Hadoop to prevent malicious user impersonation. The Hadoop daemons leverage Kerberos to perform user authentication on all remote procedure calls (RPCs). Group resolution is performed on the Hadoop master nodes, NameNode, JobTracker and ResourceManager to guarantee that group membership cannot be manipulated by users. Map tasks are run under the user account of the user who submitted the job, ensuring isolation there. In addition to these features, new authorization mechanisms have been introduced to HDFS and MapReduce to enable more control over user access to data.

The security features in CDH 5 meet the needs of most Hadoop customers because typically the cluster is accessible only to trusted personnel. In particular, Hadoop's current threat model assumes that users cannot:

- 1. Have root access to cluster machines.
- 2. Have root access to shared client machines.
- **3.** Read or modify packets on the network of the cluster.

#### Note:

CDH 5 supports encryption of all user data sent over the network. For configuration instructions, see Configuring Encrypted Shuffle, Encrypted Web Uls, and Encrypted HDFS Transport.

Note also that there is no built-in support for on-disk encryption.

# Enabling Kerberos Authentication for Hadoop Using the Command Line

### Important:

These instructions assume you know how to install and configure Kerberos, you already have a working Kerberos Key Distribution Center (KDC) and realm setup, and that you've installed the Kerberos user packages on all cluster machines and machines which will be used to access the cluster. Furthermore, Oozie and Hue require that the realm support renewable tickets. For more information about installing and configuring Kerberos, see:

- MIT Kerberos Home
- MIT Kerberos Documentation
- Kerberos Explained
- Microsoft Kerberos Overview
- Microsoft Kerberos in Windows Server 2008
- Microsoft Kerberos in Windows Server 2003

Here are the general steps to configuring secure Hadoop, each of which is described in more detail in the following sections:

- 1. Install CDH 5.
- 2. Verify User Accounts and Groups in CDH 5 Due to Security.
- 3. If you are Using AES-256 Encryption, install the JCE Policy File.
- 4. Create and Deploy the Kerberos Principals and Keytab Files.
- **5.** Shut Down the Cluster.
- **6.** Enable Hadoop security.
- **7.** Configure secure HDFS.
- 8. Optional: Configuring Security for HDFS High Availability.
- **9.** Optional: Configuring secure WebHDFS.
- **10.** Optional: Configuring secure NFS
- 11. Set Variables for Secure DataNodes.
- **12.** Start up the NameNode.
- **13.** Start up a DataNode.
- **14.** Set the Sticky Bit on HDFS Directories.
- 15. Start up the Secondary NameNode (if used).
- **16.** Configure Either MRv1 Security or YARN Security.

#### Note:

Kerberos security in CDH 5 has been tested with the following version of MIT Kerberos 5:

krb5-1.6.1 on Red Hat Enterprise Linux 5 and CentOS 5

Kerberos security in CDH 5 is supported with the following versions of MIT Kerberos 5:

- krb5-1.6.3 on SUSE Linux Enterprise Server (SLES) 11 Service Pack 1
- krb5-1.8.1 on Ubuntu
- krb5-1.8.2 on Red Hat Enterprise Linux 6 and CentOS 6
- krb5-1.9 on Red Hat Enterprise Linux 6.1

#### Note:

If you want to enable Kerberos SPNEGO-based authentication for the Hadoop web interfaces, see the Hadoop Auth, Java HTTP SPNEGO Documentation.

## Step 1: Install CDH 5

Cloudera strongly recommends that you set up a fully-functional CDH 5 cluster before you begin configuring it to use Hadoop's security features. When a secure Hadoop cluster is not configured correctly, the resulting error messages are in a preliminary state, so it's best to start implementing security after you are sure your Hadoop cluster is working properly without security.

For information about installing and configuring Hadoop and CDH 5 components, and deploying them on a cluster, see Cloudera Installation and Upgrade.

# Step 2: Verify User Accounts and Groups in CDH 5 Due to Security

- Note: CDH 5 introduces a new version of MapReduce: MapReduce 2.0 (MRv2) built on the YARN framework. In this document, we refer to this new version as YARN. CDH 5 also provides an implementation of the previous version of MapReduce, referred to as MRv1 in this document.
- If you are using MRv1, see <a href="Step 2a">Step 2a</a> (MRv1 only): Verify User Accounts and Groups in MRv1 on page 52 for configuration information.
- If you are using YARN, see <u>Step 2b (YARN only)</u>: <u>Verify User Accounts and Groups in YARN</u> on page 54 for configuration information.

#### Step 2a (MRv1 only): Verify User Accounts and Groups in MRv1

Note: If you are using YARN, skip this step and proceed to <a href="Step 2b">Step 2b</a> (YARN only): Verify User Accounts and Groups in YARN.

During CDH 5 package installation of MRv1, the following Unix user accounts are automatically created to support security:

This User	Runs These Hadoop Programs
hdfs	HDFS: NameNode, DataNodes, Secondary NameNode (or Standby NameNode if you are using HA)
mapred	MRv1: JobTracker and TaskTrackers

The hdfs user also acts as the HDFS superuser.

The hadoop user no longer exists in CDH 5. If you currently use the hadoop user to run applications as an HDFS super-user, you should instead use the new hdfs user, or create a separate Unix account for your application such as myhadoopapp.

### MRv1: Directory Ownership in the Local File System

Because the HDFS and MapReduce services run as different users, you must be sure to configure the correct directory ownership of the following files on the local file system of each host:

File System	Directory	Owner	Permissions
Local	dfs.namenode.name.dir (dfs.name.dir is deprecated but will also work)	hdfs:hdfs	drwx
Local	dfs.datanode.data.dir (dfs.data.dir is deprecated but will also work)	hdfs:hdfs	drwx
Local	mapred.local.dir	mapred:mapred	drwxr-xr-x

### See also Deploying MapReduce v1 (MRv1) on a Cluster.

You must also configure the following permissions for the HDFS and MapReduce log directories (the default locations in /var/log/hadoop-hdfs and /var/log/hadoop-0.20-mapreduce), and the \$MAPRED\_LOG\_DIR/userlogs/ directory:

File System	Directory	Owner	Permissions
Local	HDFS_LOG_DIR	hdfs:hdfs	drwxrwxr-x
Local	MAPRED_LOG_DIR	mapred:mapred	drwxrwxr-x
Local	userlogs directory in MAPRED_LOG_DIR	mapred:anygroup	permissions will be set automatically at daemon start time

#### MRv1: Directory Ownership on HDFS

The following directories on HDFS must also be configured as follows:

File System	Directory	Owner	Permissions
HDFS	mapreduce.jdtracker.system.dir (mapred.system.dir is deprecated but will also work)	mapred:hadoop	drwx
HDFS	/ (root directory)	hdfs:hadoop	drwxr-xr-x

<sup>&</sup>lt;sup>1</sup> In CDH 5, package installation and the Hadoop daemons will automatically configure the correct permissions for you if you configure the directory ownership correctly as shown in the table above.

When starting up, MapReduce sets the permissions for the mapreduce.jobtracker.system.dir(or mapred.system.dir) directory in HDFS, assuming the user mapred owns that directory.

### MRv1: Changing the Directory Ownership on HDFS

 If Hadoop security is enabled, use kinit hdfs to obtain Kerberos credentials for the hdfs user by running the following commands before changing the directory ownership on HDFS:

```
$ sudo -u hdfs kinit -k -t hdfs.keytab hdfs/fully.qualified.domain.name@YOUR-REALM.COM
```

If kinit hdfs does not work initially, run kinit -R after running kinit to obtain credentials. (For more information, see <u>Troubleshooting Authentication Issues</u> on page 145). To change the directory ownership on HDFS, run the following commands. Replace the example /mapred/system directory in the commands below with the HDFS directory specified by the mapreduce.jobtracker.system.dir (or mapred.system.dir) property in the conf/mapred-site.xml file:

```
$ sudo -u hdfs hadoop fs -chown mapred:hadoop /mapred/system
$ sudo -u hdfs hadoop fs -chown hdfs:hadoop /
$ sudo -u hdfs hadoop fs -chmod -R 700 /mapred/system
$ sudo -u hdfs hadoop fs -chmod 755 /
```

 In addition (whether or not Hadoop security is enabled) create the /tmp directory. For instructions on creating /tmp and setting its permissions, see these instructions.

### Step 2b (YARN only): Verify User Accounts and Groups in YARN

Note: If you are using MRv1, skip this step and proceed to Step 3: If you are Using AES-256 Encryption, install the JCE Policy File on page 56.

During CDH 5 package installation of MapReduce 2.0 (YARN), the following Unix user accounts are automatically created to support security:

This User	Runs These Hadoop Programs
hdfs	HDFS: NameNode, DataNodes, Standby NameNode (if you are using HA)
yarn	YARN: ResourceManager, NodeManager
mapred	YARN: MapReduce Job History Server

Important: The HDFS and YARN daemons must run as different Unix users; for example, hdfs and yarn. The MapReduce Job History server must run as user mapred. Having all of these users share a common Unix group is recommended; for example, hadoop.

#### YARN: Directory Ownership in the Local File System

Because the HDFS and MapReduce services run as different users, you must be sure to configure the correct directory ownership of the following files on the local file system of each host:

File System	Directory	Owner	Permissions (see <sup>1</sup> )
Local	dfs.namenode.name.dir (dfs.name.dir is deprecated but will also work)	hdfs:hdfs	drwx
Local	dfs.datanode.data.dir (dfs.data.dir is deprecated but will also work)	hdfs:hdfs	drwx
Local	yarn.nodemanager.local-dirs	yarn:yarn	drwxr-xr-x

File System	Directory	Owner	Permissions (see <sup>1</sup> )
Local	yarn.nodemanager.log-dirs	yarn:yarn	drwxr-xr-x
Local	container-executor	root:yarn	Sr-s
Local	conf/container-executor.cfg	root:yarn	r

Important: Configuration changes to the Linux container executor could result in local NodeManager directories (such as usercache) being left with incorrect permissions. To avoid this, when making changes using either Cloudera Manager or the command line, first manually remove the existing NodeManager local directories from all configured local directories (yarn.nodemanager.local-dirs), and let the NodeManager recreate the directory structure.

You must also configure the following permissions for the HDFS, YARN and MapReduce log directories (the default locations in /var/log/hadoop-hdfs, /var/log/hadoop-yarn and /var/log/hadoop-mapreduce):

File System	Directory	Owner	Permissions
Local	HDFS_LOG_DIR	hdfs:hdfs	drwxrwxr-x
Local	\$YARN_LOG_DIR	yarn:yarn	drwxrwxr-x
Local	MAPRED_LOG_DIR	mapred:mapred	drwxrwxr-x

### YARN: Directory Ownership on HDFS

The following directories on HDFS must also be configured as follows:

File System	Directory	Owner	Permissions
HDFS	/ (root directory)	hdfs:hadoop	drwxr-xr-x
HDFS	yarn.nodemanager.remote-app-log-dir	yarn:hadoop	drwxrwxrwxt
HDFS	mapreduce.jobhistory.intermediate-done-dir	mapred:hadoop	drwxrwxrwxt
HDFS	mapreduce.jobhistory.done-dir	mapred:hadoop	drwxr-x

### YARN: Changing the Directory Ownership on HDFS

If Hadoop security is enabled, use kinit hdfs to obtain Kerberos credentials for the hdfs user by running the following commands:

```
$ sudo -u hdfs kinit -k -t hdfs.keytab hdfs/fully.qualified.domain.name@YOUR-REALM.COM
$ hadoop fs -chown hdfs:hadoop /
$ hadoop fs -chmod 755 /
```

If kinit hdfs does not work initially, run kinit -R after running kinit to obtain credentials. See Troubleshooting Authentication Issues on page 145. To change the directory ownership on HDFS, run the following commands:

```
$ sudo -u hdfs hadoop fs -chown hdfs:hadoop /
$ sudo -u hdfs hadoop fs -chmod 755 /
$ sudo -u hdfs hadoop fs -chown yarn:hadoop [yarn.nodemanager.remote-app-log-dir]
$ sudo -u hdfs hadoop fs -chmod 1777 [yarn.nodemanager.remote-app-log-dir]
```

In CDH 5, package installation and the Hadoop daemons will automatically configure the correct permissions for you if you configure the directory ownership correctly as shown in the two tables above. See also Deploying MapReduce v2 (YARN) on a Cluster.

```
$ sudo -u hdfs hadoop fs -chown mapred:hadoop
[mapreduce.jobhistory.intermediate-done-dir]
$ sudo -u hdfs hadoop fs -chmod 1777 [mapreduce.jobhistory.intermediate-done-dir]
$ sudo -u hdfs hadoop fs -chown mapred:hadoop [mapreduce.jobhistory.done-dir]
$ sudo -u hdfs hadoop fs -chmod 750 [mapreduce.jobhistory.done-dir]
```

- In addition (whether or not Hadoop security is enabled) create the /tmp directory. For instructions on creating /tmp and setting its permissions, see Step 7: If Necessary, Create the HDFS /tmp Directory.
- In addition (whether or not Hadoop security is enabled), change permissions on the /user/history Directory. See Step 8: Create the history Directory and Set Permissions and Owner.

# Step 3: If you are Using AES-256 Encryption, install the JCE Policy File

If you are using CentOS/Red Hat Enterprise Linux 5.6 or later, or Ubuntu, which use AES-256 encryption by default for tickets, you must install the Java Cryptography Extension (JCE) Unlimited Strength Jurisdiction Policy File on all cluster and Hadoop user machines. For JCE Policy File installation instructions, see the README.txt file included in the jce\_policy-x.zip file.

Alternatively, you can configure Kerberos to not use AES-256 by removing aes256-cts:normal from the supported\_enctypes field of the kdc.conf or krb5.conf file. Note that after changing the kdc.conf file, you'll need to restart both the KDC and the kadmin server for those changes to take affect. You may also need to recreate or change the password of the relevant principals, including potentially the Ticket Granting Ticket principal (krbtgt/REALM@REALM). If AES-256 is still used after all of those steps, it's because the aes256-cts:normal setting existed when the Kerberos database was created. To fix this, create a new Kerberos database and then restart both the KDC and the kadmin server.

### To verify the type of encryption used in your cluster:

1. On the local KDC host, type this command to create a test principal:

```
$ kadmin -q "addprinc test"
```

**2.** On a cluster host, type this command to start a Kerberos session as test:

```
$ kinit test
```

3. On a cluster host, type this command to view the encryption type in use:

```
$ klist -e
```

If AES is being used, output like the following is displayed after you type the klist command (note that AES-256 is included in the output):

```
Ticket cache: FILE:/tmp/krb5cc 0
Default principal: test@SCM
Valid starting Expires Service princip 05/19/11 13:25:04 05/20/11 13:25:04 krbtgt/SCM@SCM
                                          Service principal
    Etype (skey, tkt): AES-256 CTS mode with 96-bit SHA-1 HMAC, AES-256 CTS mode
with 96-bit SHA-1 HMAC
```

## Step 4: Create and Deploy the Kerberos Principals and Keytab Files

A Kerberos principal is used in a Kerberos-secured system to represent a unique identity. Kerberos assigns tickets to Kerberos principals to enable them to access Kerberos-secured Hadoop services. For Hadoop, the principals should be of the format username/fully.qualified.domain.name@YOUR-REALM.COM. In this guide, the term username in the username/fully.qualified.domain.name@YOUR-REALM.COM principal refers to the username of an existing Unix account, such as hdfs or mapred.

A keytab is a file containing pairs of Kerberos principals and an encrypted copy of that principal's key. The keytab files are unique to each host since their keys include the hostname. This file is used to authenticate a principal on a host to Kerberos without human interaction or storing a password in a plain text file. Because having access to the keytab file for a principal allows one to act as that principal, access to the keytab files should be tightly secured. They should be readable by a minimal set of users, should be stored on local disk, and should not be included in machine backups, unless access to those backups is as secure as access to the local machine.

#### Important:

For both MRv1 and YARN deployments: On every machine in your cluster, there must be a keytab file for the hdfs user and a keytab file for the mapred user. The hdfs keytab file must contain entries for the hdfs principal and a HTTP principal, and the mapred keytab file must contain entries for the mapred principal and a HTTP principal. On each respective machine, the HTTP principal will be the same in both keytab files.

In addition, for YARN deployments only: On every machine in your cluster, there must be a keytab file for the yarn user. The yarn keytab file must contain entries for the yarn principal and a HTTP principal. On each respective machine, the  $\mathtt{HTTP}$  principal in the  $\mathtt{yarn}$  keytab file will be the same as the  $\mathtt{HTTP}$ principal in the hdfs and mapred keytab files.

#### Note:

The following instructions illustrate an example of creating keytab files for MIT Kerberos. If you are using another version of Kerberos, refer to your Kerberos documentation for instructions. You may use either kadmin or kadmin.local to run these commands.

#### When to Use kadmin.local and kadmin

When creating the Kerberos principals and keytabs, you can use kadmin.local or kadmin depending on your access and account:

- If you have root access to the KDC machine, but you don't have a Kerberos admin account, use kadmin.local.
- If you don't have root access to the KDC machine, but you do have a Kerberos admin account, use kadmin.
- If you have both root access to the KDC machine and a Kerberos admin account, you can use either one.

To start kadmin.local (on the KDC machine) or kadmin from any machine, run this command:

\$ sudo kadmin.local

OR:

\$ kadmin

#### Note:

In this guide, kadmin is shown as the prompt for commands in the kadmin shell, but you can type the same commands at the kadmin.local prompt in the kadmin.local shell.

### Note:

Running kadmin.local may prompt you for a password because it is being run via sudo. You should provide your Unix password. Running kadmin may prompt you for a password because you need Kerberos admin privileges. You should provide your Kerberos admin password.

### To create the Kerberos principals

### Important:

If you plan to use Oozie, Impala, or the Hue Kerberos ticket renewer in your cluster, you must configure your KDC to allow tickets to be renewed, and you must configure kmb5.conf to request renewable tickets. Typically, you can do this by adding the max\_renewable\_life setting to your realm in kdc.conf, and by adding the renew\_lifetime parameter to the libdefaults section of krb5.conf. For more information about renewable tickets, see the Kerberos documentation.

Do the following steps for every host in your cluster. Run the commands in the kadmin.local or kadmin shell, replacing the fully.qualified.domain.name in the commands with the fully qualified domain name of each host. Replace YOUR-REALM. COM with the name of the Kerberos realm your Hadoop cluster is in.

1. In the kadmin.local or kadmin shell, create the hdfs principal. This principal is used for the NameNode, Secondary NameNode, and DataNodes.

kadmin: addprinc -randkey hdfs/fully.qualified.domain.name@YOUR-REALM.COM

#### Note:

If your Kerberos administrator or company has a policy about principal names that does not allow you to use the format shown above, you can work around that issue by configuring the <kerberos principal> to <short name> mapping that is built into Hadoop. For more information, see Appendix C - Configuring the Mapping from Kerberos Principals to Short Names.

2. Create the mapred principal. If you are using MRv1, the mapred principal is used for the JobTracker and TaskTrackers. If you are using YARN, the mapred principal is used for the MapReduce Job History Server.

```
kadmin: addprinc -randkey mapred/fully.qualified.domain.name@YOUR-REALM.COM
```

3. YARN only: Create the yarn principal. This principal is used for the ResourceManager and NodeManager.

```
kadmin: addprinc -randkey yarn/fully.qualified.domain.name@YOUR-REALM.COM
```

**4.** Create the HTTP principal.

```
kadmin: addprinc -randkey HTTP/fully.qualified.domain.name@YOUR-REALM.COM
```

#### Important:

The HTTP principal must be in the format HTTP/fully.qualified.domain.name@YOUR-REALM.COM. The first component of the principal must be the literal string "HTTP". This format is standard for HTTP principals in SPNEGO and is hard-coded in Hadoop. It cannot be deviated from.

### To create the Kerberos keytab files

### Important:

The instructions in this section for creating keytab files require using the Kerberos norandkey option in the xst command. If your version of Kerberos does not support the norandkey option, or if you cannot use kadmin.local, then use these alternate instructions in Appendix F to create appropriate Kerberos keytab files. After using those alternate instructions to create the keytab files, continue with the next section To deploy the Kerberos keytab files.

Do the following steps for every host in your cluster. Run the commands in the kadmin.local or kadmin shell, replacing the fully.qualified.domain.name in the commands with the fully qualified domain name of each host:

1. Create the hdfs keytab file that will contain the hdfs principal and HTTP principal. This keytab file is used for the NameNode, Secondary NameNode, and DataNodes.

```
kadmin: xst -norandkey -k hdfs.keytab hdfs/fully.qualified.domain.name
HTTP/fully.qualified.domain.name
```

2. Create the mapred keytab file that will contain the mapred principal and HTTP principal. If you are using MRv1, the mapred kevtab file is used for the JobTracker and TaskTrackers. If you are using YARN, the mapred keytab file is used for the MapReduce Job History Server.

```
kadmin: xst -norandkey -k mapred.keytab mapred/fully.qualified.domain.name
HTTP/fully.qualified.domain.name
```

3. YARN only: Create the yarn keytab file that will contain the yarn principal and HTTP principal. This keytab file is used for the ResourceManager and NodeManager.

```
kadmin: xst -norandkey -k yarn.keytab yarn/fully.qualified.domain.name
HTTP/fully.qualified.domain.name
```

4. Use klist to display the keytab file entries; a correctly-created hdfs keytab file should look something like

```
$ klist -e -k -t hdfs.keytab
Keytab name: WRFILE:hdfs.keytab
slot KVNO Principal
           HTTP/fully.qualified.domain.name@YOUR-REALM.COM (DES cbc mode with
CRC-32)
2 7 HTTP/fully.qualified.domain.name@YOUR-REALM.COM (Triple DES cbc mode
with HMAC/shal)
  3
          hdfs/fully.qualified.domain.name@YOUR-REALM.COM (DES cbc mode with
CRC-32)
           hdfs/fully.qualified.domain.name@YOUR-REALM.COM (Triple DES cbc mode
 with HMAC/shal)
```

**5.** Continue with the next section To deploy the Kerberos keytab files.

#### To deploy the Kerberos keytab files

On every node in the cluster, repeat the following steps to deploy the hdfs.keytab and mapred.keytab files. If you are using YARN, you will also deploy the yarn.keytab file.

- 1. On the host machine, copy or move the keytab files to a directory that Hadoop can access, such as /etc/hadoop/conf.
  - a. If you are using MRv1:

```
$ sudo mv hdfs.keytab mapred.keytab /etc/hadoop/conf/
```

### If you are using YARN:

```
$ sudo mv hdfs.keytab mapred.keytab yarn.keytab /etc/hadoop/conf/
```

b. Make sure that the hdfs.keytab file is only readable by the hdfs user, and that the mapred.keytab file is only readable by the mapred user.

```
$ sudo chown hdfs:hadoop /etc/hadoop/conf/hdfs.keytab
$ sudo chown mapred:hadoop /etc/hadoop/conf/mapred.keytab
$ sudo chmod 400 /etc/hadoop/conf/*.keytab
```

#### Note:

To enable you to use the same configuration files on every host, Cloudera recommends that you use the same name for the keytab files on every host.

c. YARN only: Make sure that the yarn.keytab file is only readable by the yarn user.

```
$ sudo chown yarn:hadoop /etc/hadoop/conf/yarn.keytab
$ sudo chmod 400 /etc/hadoop/conf/yarn.keytab
```

#### Important:

If the NameNode, Secondary NameNode, DataNode, JobTracker, TaskTrackers, HttpFS, or Oozie services are configured to use Kerberos HTTP SPNEGO authentication, and two or more of these services are running on the same host, then all of the running services must use the same HTTP principal and keytab file used for their HTTP endpoints.

## Step 5: Shut Down the Cluster

To enable security in CDH, you must stop all Hadoop daemons in your cluster and then change some configuration properties. You must stop all daemons in the cluster because after one Hadoop daemon has been restarted with the configuration properties set to enable security, daemons running without security enabled will be unable to communicate with that daemon. This requirement to shut down all daemons makes it impossible to do a rolling upgrade to enable security on a Hadoop cluster.

To shut down the cluster, run the following command on every node in your cluster (as root):

```
$ for x in `cd /etc/init.d ; ls hadoop-*` ; do sudo service $x stop ; done
```

### Step 6: Enable Hadoop Security

Cloudera recommends that all of the Hadoop configuration files throughout the cluster have the same contents.

To enable Hadoop security, add the following properties to the core-site.xml file on every machine in the

```
<name>hadoop.security.authentication</name>
 <value>kerberos</value> <!-- A value of "simple" would disable security. -->
</property>
 <name>hadoop.security.authorization</name>
 <value>true</value>
</property>
```

### Enabling Service-Level Authorization for Hadoop Services

The hadoop-policy.xml file maintains access control lists (ACL) for Hadoop services. Each ACL consists of comma-separated lists of users and groups separated by a space. For example:

```
user_a,user_b group_a,group_b
```

If you only want to specify a set of users, add a comma-separated list of users followed by a blank space. Similarly, to specify only authorized groups, use a blank space at the beginning. A \* can be used to give access to all users. For example, to give users, ann, bob, and groups, group\_a, group\_b access to Hadoop's DataNodeProtocol service, modify the security.datanode.protocol.acl property in hadoop-policy.xml. Similarly, to give all users access to the InterTrackerProtocol service, modify security.inter.tracker.protocol.acl as follows:

```
cproperty>
    <name>security.datanode.protocol.acl</name>
    <value>ann,bob group_a,group_b</value>
    <description>ACL for DatanodeProtocol, which is used by datanodes to
   communicate with the namenode.</description>
</property>
property>
    <name>security.inter.tracker.protocol.acl</name>
    <value>*</value>
    <description>ACL for InterTrackerProtocol, which is used by tasktrackers to
   communicate with the jobtracker.</description>
</property>
```

For more details, see Service-Level Authorization in Hadoop.

# Step 7: Configure Secure HDFS

When following the instructions in this section to configure the properties in the hdfs-site.xml file, keep the following important guidelines in mind:

- The properties for each daemon (NameNode, Secondary NameNode, and DataNode) must specify both the HDFS and HTTP principals, as well as the path to the HDFS keytab file.
- The Kerberos principals for the NameNode, Secondary NameNode, and DataNode are configured in the hdfs-site.xml file. The same hdfs-site.xml file with all three of these principals must be installed on every host machine in the cluster. That is, it is not sufficient to have the NameNode principal configured on the NameNode host machine only. This is because, for example, the DataNode must know the principal name of the NameNode in order to send heartbeats to it. Kerberos authentication is bi-directional.
- The special string \_HOST in the properties is replaced at run-time by the fully-qualified domain name of the host machine where the daemon is running. This requires that reverse DNS is properly working on all the hosts configured this way. You may use \_HOST only as the entirety of the second component of a principal name. For example, hdfs/\_HOST@YOUR-REALM.COM is valid, but hdfs.\_HOST@YOUR-REALM.COM and hdfs/\_HOST.example.com@YOUR-REALM.COM are not.
- When performing the \_HOST substitution for the Kerberos principal names, the NameNode determines its own hostname based on the configured value of fs.default.name, whereas the DataNodes determine their hostnames based on the result of reverse DNS resolution on the DataNode hosts. Likewise, the JobTracker uses the configured value of mapred.job.tracker to determine its hostname whereas the TaskTrackers, like the DataNodes, use reverse DNS.
- The dfs.datanode.address and dfs.datanode.http.address port numbers for the DataNode *must* be below 1024, because this provides part of the security mechanism to make it impossible for a user to run a map task which impersonates a DataNode. The port numbers for the NameNode and Secondary NameNode can be anything you want, but the default port numbers are good ones to use.

### To configure secure HDFS

Add the following properties to the hdfs-site.xml file on every machine in the cluster. Replace these example values shown below with the correct settings for your site: path to the HDFS keytab, YOUR-REALM.COM, fully qualified domain name of NN, and fully qualified domain name of 2NN

```
<!-- General HDFS security config -->
cproperty>
 <name>dfs.block.access.token.enable
 <value>true</value>
</property>
<!-- NameNode security config -->
cproperty>
  <name>dfs.namenode.keytab.file
  <value>/etc/hadoop/conf/hdfs.keytab</value> <!-- path to the HDFS keytab -->
```

```
</property>
cproperty>
 <name>dfs.namenode.kerberos.principal</name>
  <value>hdfs/_HOST@YOUR-REALM.COM</value>
</property>
property>
  <name>dfs.namenode.kerberos.internal.spnego.principal/name>
  <value>HTTP/_HOST@YOUR-REALM.COM</value>
<!-- Secondary NameNode security config -->
cproperty>
  <name>dfs.secondary.namenode.keytab.file
  <value>/etc/hadoop/conf/hdfs.keytab<!-- path to the HDFS keytab -->
</property>
cproperty>
 <name>dfs.secondary.namenode.kerberos.principal
  <value>hdfs/_HOST@YOUR-REALM.COM</value>
</property>
property>
  <name>dfs.secondary.namenode.kerberos.internal.spnego.principal/name>
  <value>HTTP/_HOST@YOUR-REALM.COM</value>
</property>
<!-- DataNode security config -->
cproperty>
  <name>dfs.datanode.data.dir.perm
  <value>700</value>
</property>
opertv>
  <name>dfs.datanode.address
  <value>0.0.0.0:1004</value>
</property>
cproperty>
 <name>dfs.datanode.http.address</name>
  <value>0.0.0.0:1006
</property>
cproperty>
 <name>dfs.datanode.keytab.file
  <value>/etc/hadoop/conf/hdfs.keytab<!-- path to the HDFS keytab -->
</property>
cproperty>
  <name>dfs.datanode.kerberos.principal</name>
  <value>hdfs/_HOST@YOUR-REALM.COM</value>
</property>
<!-- Web Authentication config -->
property>
 <name>dfs.web.authentication.kerberos.principal
 <value>HTTP/_HOST@YOUR_REALM</value>
 </property>
```

#### To enable SSL for HDFS

Add the following property to hdfs-site.xml on every machine in your cluster.

### Optional Step 8: Configuring Security for HDFS High Availability

CDH 5 supports the HDFS High Availability (HA) feature with Kerberos security enabled. There are two use cases that affect security for HA:

If you are not using Quorum-based Storage (see <u>Software Configuration for Quorum-based Storage</u>), then no extra configuration for HA is necessary if automatic failover is not enabled. If automatic failover is enabled then access to ZooKeeper should be secured. See the <u>Software Configuration for Shared Storage Using NFS</u> documentation for details.  If you are using Quorum-based Storage, then you must configure security for Quorum-based Storage by following the instructions in this section.

### To configure security for Quorum-based Storage:

Add the following Quorum-based Storage configuration properties to the hdfs-site.xml file on all of the machines in the cluster:

```
property>
 <name>dfs.journalnode.keytab.file
  <value>/etc/hadoop/conf/hdfs.keytab</value> <!-- path to the HDFS keytab -->
</property>
cproperty>
 <name>dfs.journalnode.kerberos.principal
  <value>hdfs/_HOST@YOUR-REALM.COM</value>
</property>
property>
  <name>dfs.journalnode.kerberos.internal.spnego.principal</name>
  <value>HTTP/_HOST@YOUR-REALM.COM</value>
</property>
```

Note:

If you already have principals and keytabs created for the machines where the JournalNodes are running, then you should reuse those principals and keytabs in the configuration properties above. You will likely have these principals and keytabs already created if you are collocating a JournalNode on a machine with another HDFS daemon.

# Optional Step 9: Configure secure WebHDFS

Note:

If you are not using WebHDFS, you can skip this step.

Security for WebHDFS is disabled by default. If you want use WebHDFS with a secure cluster, this is the time to enable and configure it.

### To configure secure WebHDFS:

1. If you have not already done so, enable WebHDFS by adding the following property to the hdfs-site.xml file on every machine in the cluster".

```
property>
 <name>dfs.webhdfs.enabled</name>
  <value>true</value>
</property>
```

2. Add the following properties to the hdfs-site.xml file on every machine in the cluster. Replace the example values shown below with the correct settings for your site.

```
<name>dfs.web.authentication.kerberos.principal</name>
  <value>HTTP/_HOST@YOUR-REALM.COM</value>
</property>
cproperty>
 <name>dfs.web.authentication.kerberos.keytab
 <value>/etc/hadoop/conf/HTTP.keytab<!-- path to the HTTP keytab -->
</property>
```

# Optional Step 10: Configuring a secure HDFS NFS Gateway

To deploy a Kerberized HDFS NFS gateway, add the following configuration properties to hdfs-site.xml on the NFS server.

```
property>
<name>dfs.nfs.keytab.file</name>
<value>/etc/hadoop/conf/hdfs.keytab</value> <!-- path to the HDFS or NFS gateway keytab
</property>
cproperty>
<name>dfs.nfs.kerberos.principal</name>
<value>hdfs/_HOST@YOUR-REALM.COM</value>
</property>
```

### Step 11: Set Variables for Secure DataNodes

In order to allow DataNodes to start on a secure Hadoop cluster, you must set the following variables on all DataNodes in /etc/default/hadoop-hdfs-datanode.

```
export HADOOP_SECURE_DN_USER=hdfs
export HADOOP_SECURE_DN_PID_DIR=/var/lib/hadoop-hdfs
export HADOOP_SECURE_DN_LOG_DIR=/var/log/hadoop-hdfs
export JSVC_HOME=/usr/lib/bigtop-utils/
```

Note:

Depending on the version of Linux you are using, you may not have the /usr/lib/bigtop-utils directory on your system. If that is the case, set the JSVC\_HOME variable to the /usr/libexec/bigtop-utils directory by using this command:

```
______
export JSVC_HOME=/usr/libexec/bigtop-utils
```

# Step 12: Start up the NameNode

You are now ready to start the NameNode. Use the service command to run the /etc/init.d script.

```
$ sudo service hadoop-hdfs-namenode start
```

You'll see some extra information in the logs such as:

```
10/10/25 17:01:46 INFO security.UserGroupInformation:
Login successful for user hdfs/fully.qualified.domain.name@YOUR-REALM.COM using keytab
file /etc/hadoop/conf/hdfs.keytab
```

#### and:

```
12/05/23 18:18:31 INFO http.HttpServer: Adding Kerberos (SPNEGO) filter to
getDelegationToken
12/05/23 18:18:31 INFO http.HttpServer: Adding Kerberos (SPNEGO) filter to
renewDelegationToken
12/05/23 18:18:31 INFO http.HttpServer: Adding Kerberos (SPNEGO) filter to
cancelDelegationToken
12/05/23 18:31 INFO http.HttpServer: Adding Kerberos (SPNEGO) filter to fsck
12/05/23 18:18:31 INFO http.HttpServer: Adding Kerberos (SPNEGO) filter to getimage
12/05/23 18:18:31 INFO http.HttpServer: Jetty bound to port 50070 12/05/23 18:18:31 INFO mortbay.log: jetty-6.1.26
12/05/23 18:18:31 INFO server.KerberosAuthenticationHandler: Login using keytab
/etc/hadoop/conf/hdfs.keytab, for principal
HTTP/fully.qualified.domain.name@YOUR-REALM.COM
12/05/23 18:18:31 INFO server.KerberosAuthenticationHandler: Initialized, principal
```

[HTTP/fully.qualified.domain.name@YOUR-REALM.COM] from keytab [/etc/hadoop/conf/hdfs.keytab]

You can verify that the NameNode is working properly by opening a web browser to http://machine:50070/ where machine is the name of the machine where the NameNode is running.

Cloudera also recommends testing that the NameNode is working properly by performing a metadata-only HDFS operation, which will now require correct Kerberos credentials. For example:

\$ hadoop fs -ls

#### Information about the kinit Command

### Important:

Running the hadoop fs -ls command will fail if you do not have a valid Kerberos ticket in your credentials cache. You can examine the Kerberos tickets currently in your credentials cache by running the klist command. You can obtain a ticket by running the kinit command and either specifying a keytab file containing credentials, or entering the password for your principal. If you do not have a valid ticket, you will receive an error such as:

11/01/04 12:08:12 WARN ipc.Client: Exception encountered while connecting to the server : javax.security.sasl.SaslException: GSS initiate failed [Caused by GSSException: No valid credentials provided (Mechanism level: Failed to find any Kerberos tgt)] Bad connection to FS. command aborted. exception: Call to nn-host/10.0.0.2:8020 failed on local exception: java.io.IOException: javax.security.sasl.SaslException: GSS initiate failed [Caused by GSSException: No valid credentials provided (Mechanism level: Failed to find any Kerberos

#### Note:

The kinit command must either be on the path for user accounts running the Hadoop client, or else the hadoop.kerberos.kinit.command parameter in core-site.xml must be manually configured to the absolute path to the kinit command.

### Note:

If you are running MIT Kerberos 1.8.1 or higher, a bug in versions of the Oracle JDK 6 Update 26 and earlier causes Java to be unable to read the Kerberos credentials cache even after you have successfully obtained a Kerberos ticket using kinit. To workaround this bug, run kinit -R after running kinit initially to obtain credentials. Doing so will cause the ticket to be renewed, and the credentials cache rewritten in a format which Java can read. For more information about this problem, see Troubleshooting.

### Step 12: Start up a DataNode

Begin by starting one DataNode only to make sure it can properly connect to the NameNode. Use the service command to run the /etc/init.d script.

\$ sudo service hadoop-hdfs-datanode start

You'll see some extra information in the logs such as:

```
10/10/25 17:21:41 INFO security.UserGroupInformation:
Login successful for user hdfs/fully.qualified.domain.name@YOUR-REALM.COM using keytab
file /etc/hadoop/conf/hdfs.keytab
```

If you can get a single DataNode running and you can see it registering with the NameNode in the logs, then start up all the DataNodes. You should now be able to do all HDFS operations.

### Step 14: Set the Sticky Bit on HDFS Directories

This step is optional but strongly recommended for security. In CDH 5, HDFS file permissions have support for the sticky bit. The sticky bit can be set on directories, preventing anyone except the superuser, directory owner, or file owner from deleting or moving the files within the directory. Setting the sticky bit for a file has no effect. This is useful for directories such as /tmp which previously had to be set to be world-writable. To set the sticky bit on the /tmp directory, run the following command:

```
$ sudo -u hdfs kinit -k -t hdfs.keytab hdfs/fully.qualified.domain.name@YOUR-REALM.COM
$ sudo -u hdfs hadoop fs -chmod 1777 /tmp
```

After running this command, the permissions on /tmp will appear as shown below. (Note the "t" instead of the final "x".)

```
$ hadoop fs -ls /
Found 2 items
drwxrwxrwt - hdfs supergroup 0 2011-02-14 15:55 /tmp
drwxr-xr-x - hdfs supergroup 0 2011-02-14 14:01 /user
```

### Step 15: Start up the Secondary NameNode (if used)

At this point, you should be able to start the Secondary NameNode if you are using one:

```
$ sudo service hadoop-hdfs-secondarynamenode start
```

Note:

If you are using HDFS HA, do not use the Secondary NameNode. See Configuring HDFS High Availability for instructions on configuring and deploying the Standby NameNode.

You'll see some extra information in the logs such as:

```
10/10/26 12:03:18 INFO security.UserGroupInformation:
Login successful for user hdfs/fully.qualified.domain.name@YOUR-REALM using keytab file
 /etc/hadoop/conf/hdfs.keytab
```

and:

```
12/05/23 18:33:06 INFO http.HttpServer: Adding Kerberos (SPNEGO) filter to getimage
12/05/23 18:33:06 INFO http.HttpServer: Jetty bound to port 50090
12/05/23 18:33:06 INFO mortbay.log: jetty-6.1.26 12/05/23 18:33:06 INFO server.KerberosAuthenticationHandler: Login using keytab
/etc/hadoop/conf/hdfs.keytab, for principal
HTTP/fully.qualified.domain.name@YOUR-REALM.COM
12/05/23 18:33:06 INFO server.KerberosAuthenticationHandler: Initialized, principal
[HTTP/fully.qualified.domain.name@YOUR-REALM.COM] from keytab
[/etc/hadoop/conf/hdfs.keytab]
```

You should make sure that the Secondary NameNode not only starts, but that it is successfully checkpointing.

If you're using the service command to start the Secondary NameNode from the /etc/init.d scripts, Cloudera recommends setting the property fs.checkpoint.period in the hdfs-site.xml file to a very low value (such as 5), and then monitoring the Secondary NameNode logs for a successful startup and checkpoint. Once you are satisfied that the Secondary NameNode is checkpointing properly, you should reset the fs.checkpoint.period to a reasonable value, or return it to the default, and then restart the Secondary NameNode.

You can make the Secondary NameNode perform a checkpoint by doing the following:

```
$ sudo -u hdfs hdfs secondarynamenode -checkpoint force
```

Note that this will not cause a running Secondary NameNode to checkpoint, but rather will start up a Secondary NameNode that will immediately perform a checkpoint and then shut down. This can be useful for debugging.

#### Note:

If you encounter errors during Secondary NameNode checkpointing, it may be helpful to enable Kerberos debugging output. For instructions, see Appendix D - Enabling Debugging Output for the Sun Kerberos Classes.

## Step 16: Configure Either MRv1 Security or YARN Security

At this point, you are ready to configure either MRv1 Security or YARN Security.

- If you are using MRv1, do the steps in Configuring MRv1 Security to configure, start, and test secure MRv1.
- If you are using YARN, do the steps in <u>Configuring YARN Security</u> to configure, start, and test secure YARN.

### Configuring MRv1 Security

If you are using YARN, skip this section and see Configuring YARN Security.

If you are using MRv1, do the following steps to configure, start, and test secure MRv1.

- 1. Step 1: Configure Secure MRv1 on page 67
- 2. Step 2: Start up the JobTracker on page 69
- 3. Step 3: Start up a TaskTracker on page 69
- 4. Step 4: Try Running a Map/Reduce Job on page 69

### Step 1: Configure Secure MRv1

Keep the following important information in mind when configuring secure MapReduce:

- The properties for Job Tracker and Task Tracker must specify the mapred principal, as well as the path to the mapred keytab file.
- The Kerberos principals for the Job Tracker and Task Tracker are configured in the mapred-site.xml file. The same mapred-site.xml file with both of these principals must be installed on every host machine in the cluster. That is, it is not sufficient to have the Job Tracker principal configured on the Job Tracker host machine only. This is because, for example, the TaskTracker must know the principal name of the JobTracker in order to securely register with the JobTracker. Kerberos authentication is bi-directional.
- Do not use \${user.name} in the value of the mapred.local.dir or hadoop.log.dir properties in mapred-site.xml. Doing so can prevent tasks from launching on a secure cluster.
- Make sure that each user who will be running MRv1 jobs exists on all cluster nodes (that is, on every node that hosts any MRv1 daemon).
- Make sure the value specified for mapred.local.dir is identical in mapred-site.xml and taskcontroller.cfg. If the values are different, this error message is returned.
- Make sure the value specified in taskcontroller.cfg for hadoop.log.dir is the same as what the Hadoop daemons are using, which is /var/log/hadoop-0.20-mapreduce by default and can be configured in mapred-site.xml. If the values are different, this error message is returned.

#### To configure secure MapReduce:

1. Add the following properties to the mapred-site.xml file on every machine in the cluster:

```
<!-- JobTracker security configs -->
cproperty>
 <name>mapreduce.jobtracker.kerberos.principal
  <value>mapred/_HOST@YOUR-REALM.COM</value>
cpropert.v>
  <name>mapreduce.jobtracker.keytab.file
 <value>/etc/hadoop/conf/mapred.keytab</value> <!-- path to the MapReduce keytab</pre>
</property>
<!-- TaskTracker security configs -->
cproperty>
  <name>mapreduce.tasktracker.kerberos.principal
  <value>mapred/_HOST@YOUR-REALM.COM</value>
</property>
cproperty>
 <name>mapreduce.tasktracker.keytab.file
 <value>/etc/hadoop/conf/mapred.keytab</value> <!-- path to the MapReduce keytab</pre>
</property>
<!-- TaskController settings -->
cproperty>
  <name>mapred.task.tracker.task-controller</name>
  <value>org.apache.hadoop.mapred.LinuxTaskController</value>
</property>
opertv>
 <name>mapreduce.tasktracker.group</name>
  <value>mapred</value>
</property>
```

2. Create a file called taskcontroller.cfg that contains the following information:

```
hadoop.log.dir=<Path to Hadoop log directory. Should be same value used to start
the TaskTracker. This is required to set proper permissions on the log files so
that they can be written to by the user's tasks and read by the TaskTracker for
serving on the web UI.>
mapreduce.tasktracker.group=mapred
banned.users=mapred,hdfs,bin
min.user.id=1000
```

#### Note:

In the taskcontroller.cfg file, the default setting for the banned.users property is mapred, hdfs, and bin to prevent jobs from being submitted via those user accounts. The default setting for the min.user.id property is 1000 to prevent jobs from being submitted with a user ID less than 1000, which are conventionally Unix super users. Note that some operating systems such as CentOS 5 use a default value of 500 and above for user IDs, not 1000. If this is the case on your system, change the default setting for the min.user.id property to 500. If there are user accounts on your cluster that have a user ID less than the value specified for the min.user.id property, the TaskTracker returns an error code of 255.

3. The path to the taskcontroller.cfg file is determined relative to the location of the task-controller  $binary. \ Specifically, the \ path \ is \ < path \ of \ task-controller \ binary>/../../conf/taskcontroller.cfg.$ If you installed the CDH 5 package, this path will always correspond to /etc/hadoop/conf/taskcontroller.cfg.

#### Note:

For more information about the task-controller program, see Information about Other Hadoop Security Programs.

### Important:

The same mapred-site.xml file and the same hdfs-site.xml file must both be installed on every host machine in the cluster so that the NameNode, Secondary NameNode, DataNode, Job Tracker and Task Tracker can all connect securely with each other.

### Step 2: Start up the JobTracker

You are now ready to start the JobTracker.

If you're using the /etc/init.d/hadoop-0.20-mapreduce-jobtracker script, then you can use the service command to run it now:

\$ sudo service hadoop-0.20-mapreduce-jobtracker start

You can verify that the JobTracker is working properly by opening a web browser to http://machine:50030/ where machine is the name of the machine where the JobTracker is running.

### Step 3: Start up a TaskTracker

You are now ready to start a TaskTracker.

If you're using the /etc/init.d/hadoop-0.20-mapreduce-tasktracker script, then you can use the service command to run it now:

\$ sudo service hadoop-0.20-mapreduce-tasktracker start

### Step 4: Try Running a Map/Reduce Job

You should now be able to run Map/Reduce jobs. To confirm, try launching a sleep or a pi job from the provided Hadoop examples (/usr/lib/hadoop-0.20-mapreduce/hadoop-examples.jar). Note that you will need Kerberos credentials to do so.

Important:

Remember that the user who launches the job must exist on every node.

### Configuring YARN Security

If you are using MRv1, skip this section and see Configuring MRv1 Security.

If you are using YARN, do the following steps to configure, start, and test secure YARN.

- 1. Configure Secure YARN.
- 2. Start up the ResourceManager.
- 3. Start up the NodeManager.
- 4. Start up the MapReduce Job History Server.
- **5.** Try Running a Map/Reduce YARN Job.
- 6. (Optional) Step 6: Configuring YARN for long-running applications on page 72

### Step 1: Configure Secure YARN

### Before you start:

- The Kerberos principals for the ResourceManager and NodeManager are configured in the yarn-site.xml file. The same yarn-site.xml file must be installed on every host machine in the cluster.
- Make sure that each user who will be running YARN jobs exists on all cluster nodes (that is, on every node that hosts any YARN daemon).

# To configure secure YARN:

1. Add the following properties to the yarn-site.xml file *on every machine* in the cluster:

```
______
<!-- ResourceManager security configs -->
cproperty>
 <name>yarn.resourcemanager.keytab
 <value>/etc/hadoop/conf/yarn.keytab</value> <!-- path to the YARN keytab -->
</property>
cproperty>
 <name>yarn.resourcemanager.principal
  <value>yarn/_HOST@YOUR-REALM.COM</value>
</property>
<!-- NodeManager security configs -->
cproperty>
 <name>yarn.nodemanager.keytab</name>
 <value>/etc/hadoop/conf/yarn.keytab</value> <!-- path to the YARN keytab -->
</property>
property>
 <name>yarn.nodemanager.principal
  <value>yarn/_HOST@YOUR-REALM.COM</value>
</property>
cproperty>
 <name>yarn.nodemanager.container-executor.class
 <value>org.apache.hadoop.yarn.server.nodemanager.LinuxContainerExecutor</value>
</property>
property>
 <name>yarn.nodemanager.linux-container-executor.group/name>
 <value>yarn</value>
</property>
<!-- To enable SSL -->
cproperty>
 <name>yarn.http.policy</name>
  <value>HTTPS_ONLY</value>
</property>
```

2. Add the following properties to the mapred-site.xml file on every machine in the cluster:

```
_____
<!-- MapReduce Job History Server security configs -->
property>
 <name>mapreduce.jobhistory.address
 <value>host:port</value> <!-- Host and port of the MapReduce Job History Server;</pre>
default port is 10020 -->
</property>
property>
 <name>mapreduce.jobhistory.keytab
 <value>/etc/hadoop/conf/mapred.keytab</value> <!-- path to the MAPRED keytab for</pre>
the Job History Server -->
</property>
property>
 <name>mapreduce.jobhistory.principal</name>
  <value>mapred/_HOST@YOUR-REALM.COM</value>
</property>
<!-- To enable SSL -->
cproperty>
 <name>mapreduce.jobhistory.http.policy</name>
 <value>HTTPS_ONLY</value>
</property>
   ______
```

3. Create a file called container-executor.cfg for the Linux Container Executor program that contains the following information:

```
yarn.nodemanager.local-dirs=<comma-separated list of paths to local NodeManager
directories. Should be same values specified in yarn-site.xml. Required to validate
paths passed to container-executor in order.>
yarn.nodemanager.linux-container-executor.group=yarn
yarn.nodemanager.log-dirs=<comma-separated list of paths to local NodeManager log
directories. Should be same values specified in yarn-site.xml. Required to set
proper permissions on the log files so that they can be written to by the user's
containers and read by the NodeManager for log aggregation.
```

banned.users=hdfs,yarn,mapred,bin min.user.id=1000

#### Note:

In the container-executor.cfg file, the default setting for the banned.users property is hdfs, yarn, mapred, and bin to prevent jobs from being submitted via those user accounts. The default setting for the min.user.id property is 1000 to prevent jobs from being submitted with a user ID less than 1000, which are conventionally Unix super users. Note that some operating systems such as CentOS 5 use a default value of 500 and above for user IDs, not 1000. If this is the case on your system, change the default setting for the min.user.id property to 500. If there are user accounts on your cluster that have a user ID less than the value specified for the min.user.id property, the NodeManager returns an error code of 255.

- 4. The path to the container-executor.cfg file is determined relative to the location of the container-executor binary. Specifically, the path is <dirname of container-executor binary>/../etc/hadoop/container-executor.cfg. If you installed the CDH 5 package, this path will always correspond to /etc/hadoop/conf/container-executor.cfg.
  - Note:

The container-executor program requires that the paths including and leading up to the directories specified in yarn.nodemanager.local-dirs and yarn.nodemanager.log-dirs to be set to 755 permissions as shown in this table on permissions on directories.

5. Verify that the ownership and permissions of the container-executor program corresponds to:

---Sr-s--- 1 root yarn 36264 May 20 15:30 container-executor

Note:

For more information about the Linux Container Executor program, see Appendix B - Information about Other Hadoop Security Programs.

### Step 2: Start up the ResourceManager

You are now ready to start the ResourceManager.

Note:

Make sure you always start ResourceManager before starting NodeManager.

If you're using the /etc/init.d/hadoop-yarn-resourcemanager script, then you can use the service command to run it now:

\$ sudo service hadoop-yarn-resourcemanager start

You can verify that the ResourceManager is working properly by opening a web browser to http://host:8088/ where host is the name of the machine where the ResourceManager is running.

### Step 3: Start up the NodeManager

You are now ready to start the NodeManager.

If you're using the /etc/init.d/hadoop-yarn-nodemanager script, then you can use the service command to run it now:

```
$ sudo service hadoop-yarn-nodemanager start
```

You can verify that the NodeManager is working properly by opening a web browser to http://host:8042/ where host is the name of the machine where the NodeManager is running.

### Step 4: Start up the MapReduce Job History Server

You are now ready to start the MapReduce Job History Server.

If you're using the /etc/init.d/hadoop-mapreduce-historyserver script, then you can use the service command to run it now:

```
$ sudo service hadoop-mapreduce-historyserver start
```

You can verify that the MapReduce JobHistory Server is working properly by opening a web browser to http://host:19888/ where host is the name of the machine where the MapReduce JobHistory Server is running.

### Step 5: Try Running a Map/Reduce YARN Job

You should now be able to run Map/Reduce jobs. To confirm, try launching a sleep or a pi job from the provided Hadoop examples (/usr/lib/hadoop-mapreduce/hadoop-mapreduce-examples.jar). Note that you will need Kerberos credentials to do so.

Important:

Remember that the user who launches the job must exist on every node.

To try running a MapReduce job using YARN, set the <code>HADOOP\_MAPRED\_HOME</code> environment variable and then submit the job. For example:

```
$ export HADOOP_MAPRED_HOME=/usr/lib/hadoop-mapreduce
$ /usr/bin/hadoop jar /usr/lib/hadoop-mapreduce/hadoop-mapreduce-examples.jar pi 10
10000
```

#### (Optional) Step 6: Configuring YARN for long-running applications

Long-running applications such as Spark Streaming jobs will need additional configuration since the default settings only allow the hdfs user's delegation tokens a maximum lifetime of 7 days which is not always sufficient.

You can work around this by configuring the ResourceManager as a proxy user for the corresponding HDFS NameNode so that the ResourceManager can request new tokens when the existing ones are past their maximum lifetime. YARN will then be able to continue performing localization and log-aggregation on behalf of the hdfs user.

Set the following property in yarn-site.xml to true:

```
opertv>
<name>yarn.resourcemanager.proxy-user-privileges.enabled</name>
<value>true</value>
</property>
```

Configure the following properties in core-site.xml on the HDFS NameNode. You can use a more restrictive configuration by specifying hosts/groups instead of \* as in the example below.

```
<name>hadoop.proxyuser.yarn.hosts
<value>*</value>
</property>
cproperty>
```

```
<name>hadoop.proxyuser.yarn.groups
<value>*</value>
</property>
```

### Flume Authentication

Flume agents have the ability to store data on an HDFS filesystem configured with Hadoop security. The Kerberos system and protocols authenticate communications between clients and services. Hadoop clients include users and MapReduce jobs on behalf of users, and the services include HDFS and MapReduce. Flume acts as a Kerberos principal (user) and needs Kerberos credentials to interact with the Kerberos security-enabled service. Authenticating a user or a service can be done using a Kerberos keytab file. This file contains a key that is used to obtain a ticket-granting ticket (TGT). The TGT is used to mutually authenticate the client and the service via the Kerberos KDC.

The following sections describe how to use Flume 1.3.x and CDH 5 with Kerberos security on your Hadoop cluster:

- Configuring Flume's Security Properties on page 73
- Flume Account Requirements on page 75
- Testing the Flume HDFS Sink Configuration on page 75
- Writing to a Secure HBase cluster on page 75

For instructions on enabling Kerberos for Flume's Thrift Src/Sink, see Configuring Kerberos for Flume Thrift Source and Sink on page 31.

### Important:

To enable Flume to work with Kerberos security on your Hadoop cluster, make sure you perform the installation and configuration steps in Configuring Hadoop Security in CDH 5.

#### Note:

These instructions have been tested with CDH 5 and MIT Kerberos 5 only. The following instructions describe an example of how to configure a Flume agent to be a client as the user flume to a secure HDFS service. This section does not describe how to secure the communications between Flume agents, which is not currently implemented.

# Configuring Flume's Security Properties Writing as a single user for all HDFS sinks in a given Flume agent

The Hadoop services require a three-part principal that has the form of username/fully.qualified.domain.name@YOUR-REALM.COM.Clouderarecommends using flume as the first component and the fully qualified domain name of the host machine as the second. Assuming that Kerberos and security-enabled Hadoop have been properly configured on the Hadoop cluster itself, you must add the following parameters to the Flume agent's flume.conf configuration file, which is typically located at /etc/flume-ng/conf/flume.conf:

```
agentName.sinks.sinkName.hdfs.kerberosPrincipal =
flume/fully.qualified.domain.name@YOUR-REALM.COM
agentName.sinks.sinkName.hdfs.kerberosKeytab = /etc/flume-ng/conf/flume.keytab
```

#### where:

agentName is the name of the Flume agent being configured, which in this release defaults to the value "agent". sinkName is the name of the HDFS sink that is being configured. The respective sink's type must be HDFS.

In the previous example, flume is the first component of the principal name, fully.qualified.domain.name is the second, and YOUR-REALM. COM is the name of the Kerberos realm your Hadoop cluster is in. The

/etc/flume-ng/conf/flume.keytab file contains the keys necessary for flume/fully.qualified.domain.name@YOUR-REALM.COM to authenticate with other services.

Flume and Hadoop also provide a simple keyword, HOST, that gets expanded to be the fully qualified domain name of the host machine where the service is running. This allows you to have one flume.conf file with the same hdfs.kerberosPrincipal value on all of your agent host machines.

```
agentName.sinks.sinkName.hdfs.kerberosPrincipal = flume/_HOST@YOUR-REALM.COM
```

#### Writing as different users across multiple HDFS sinks in a single Flume agent

In this release, support has been added for secure impersonation of Hadoop users (similar to "sudo" in UNIX). This is implemented in a way similar to how Oozie implements secure user impersonation.

The following steps to set up secure impersonation from Flume to HDFS assume your cluster is configured using Kerberos. (However, impersonation also works on non-Kerberos secured clusters, and Kerberos-specific aspects should be omitted in that case.)

Configure Hadoop to allow impersonation. Add the following configuration properties to your core-site.xml.

```
property>
    <name>hadoop.proxyuser.flume.groups</name>
    <value>group1,group2</value>
    <description>Allow the flume user to impersonate any members of group1 and
group2</description>
</property>
property>
    <name>hadoop.proxyuser.flume.hosts
    <value>host1,host2</value>
    <description>Allow the flume user to connect only from host1 and host2 to
impersonate a user</description>
</property>
```

You can use the wildcard character \* to enable impersonation of any user from any host. For more information, see Secure Impersonation.

- 2. Set up a Kerberos keytab for the Kerberos principal and host Flume is connecting to HDFS from. This user must match the Hadoop configuration in the preceding step. For instructions, see Configuring Hadoop Security in CDH 5.
- 3. Configure the HDFS sink with the following configuration options:
- 4. hdfs.kerberosPrincipal fully-qualified principal. Note: \_HOST will be replaced by the hostname of the local machine (only in-between the / and @ characters)
- 5. hdfs.kerberosKeytab location on the local machine of the keytab containing the user and host keys for the above principal
- **6.** hdfs.proxyUser the proxy user to impersonate

Example snippet (the majority of the HDFS sink configuration options have been omitted):

```
agent.sinks.sink-1.type = HDFS
agent.sinks.sink-1.hdfs.kerberosPrincipal = flume/_HOST@YOUR-REALM.COM
agent.sinks.sink-1.hdfs.kerberosKeytab = /etc/flume-ng/conf/flume.keytab
agent.sinks.sink-1.hdfs.proxyUser = weblogs
agent.sinks.sink-2.type = HDFS
agent.sinks.sink-2.hdfs.kerberosPrincipal = flume/_HOST@YOUR-REALM.COM
agent.sinks.sink-2.hdfs.kerberosKeytab = /etc/flume-ng/conf/flume.keytab
agent.sinks.sink-2.hdfs.proxyUser = applogs
```

In the above example, the flume Kerberos principal impersonates the user weblogs in sink-1 and the user applogs in sink-2. This will only be allowed if the Kerberos KDC authenticates the specified principal (flume in this case), and the if NameNode authorizes impersonation of the specified proxy user by the specified principal.

#### Limitations

At this time, Flume does not support using multiple Kerberos principals or keytabs in the same agent. Therefore, if you want to create files as multiple users on HDFS, then impersonation must be configured, and exactly one principal must be configured in Hadoop to allow impersonation of all desired accounts. In addition, the same keytab path must be used across all HDFS sinks in the same agent. If you attempt to configure multiple principals or keytabs in the same agent, Flume will emit the following error message:

Cannot use multiple kerberos principals in the same agent. Must restart agent to use new principal or keytab.

# Flume Account Requirements

This section provides an overview of the account and credential requirements for Flume to write to a Kerberized HDFS. Note the distinctions between the Flume agent machine, DataNode machine, and NameNode machine, as well as the flume Unix user account versus the flume Hadoop/Kerberos user account.

 Each Flume agent machine that writes to HDFS (via a configured HDFS sink) needs a Kerberos principal of the form:

flume/fully.qualified.domain.name@YOUR-REALM.COM

where fully qualified.domain.name is the fully qualified domain name of the given Flume agent host machine, and YOUR-REALM. COM is the Kerberos realm.

- Each Flume agent machine that writes to HDFS does not need to have a flume Unix user account to write files owned by the flume Hadoop/Kerberos user. Only the keytab for the flume Hadoop/Kerberos user is required on the Flume agent machine.
- DataNode machines do not need Flume Kerberos keytabs and also do not need the flume Unix user account.
- TaskTracker (MRv1) or NodeManager (YARN) machines need a flume Unix user account if and only if MapReduce jobs are being run as the flume Hadoop/Kerberos user.
- The NameNode machine needs to be able to resolve the groups of the flume user. The groups of the flume user on the NameNode machine are mapped to the Hadoop groups used for authorizing access.
- The NameNode machine does *not* need a Flume Kerberos keytab.

# Testing the Flume HDFS Sink Configuration

To test whether your Flume HDFS sink is properly configured to connect to your secure HDFS cluster, you must run data through Flume. An easy way to do this is to configure a Netcat source, a Memory channel, and an HDFS sink. Start Flume with that configuration, and use the no command (available freely online and with many UNIX distributions) to send events to the Netcat source port. The resulting events should appear on HDFS in the configured location. If the events do not appear, check the Flume log at /var/log/flume-ng/flume.log for any error messages related to Kerberos.

# Writing to a Secure HBase cluster

If you want to write to a secure HBase cluster, be aware of the following:

- Flume must be configured to use Kerberos security as documented above, and HBase must be configured to use Kerberos security as documented in <u>HBase Security Configuration</u>.
- The hbase-site.xml file, which must be configured to use Kerberos security, must be in Flume's classpath or HBASE HOME/conf.
- HBaseSink org.apache.flume.sink.hbase.HBaseSink supports secure HBase, but AsyncHBaseSink org.apache.flume.sink.hbase.AsyncHBaseSink does not.
- The Flume HBase Sink takes these two parameters:
- kerberosPrincipal specifies the Kerberos principal to be used

kerberosKeytab – specifies the path to the Kerberos keytab These are defined as:

```
agent.sinks.hbaseSink.kerberosPrincipal =
flume/fully.qualified.domain.name@YOUR-REALM.COM
agent.sinks.hbaseSink.kerberosKeytab = /etc/flume-ng/conf/flume.keytab
```

- If HBase is running with the AccessController coprocessor, the flume user (or whichever user the agent is running as) must have permissions to write to the same table and the column family that the sink is configured to write to. You can grant permissions using the grant command from HBase shell as explained in HBase Security Configuration.
- The Flume HBase Sink does not currently support impersonation; it will write to HBase as the user the agent is being run as.
- If you want to use HDFS Sink and HBase Sink to write to HDFS and HBase from the same agent respectively, both sinks have to use the same principal and keytab. If you want to use different credentials, the sinks have to be on different agents.
- Each Flume agent machine that writes to HBase (via a configured HBase sink) needs a Kerberos principal of the form:

```
flume/fully.qualified.domain.name@YOUR-REALM.COM
 ______
```

where fully qualified.domain.name is the fully qualified domain name of the given Flume agent host machine, and YOUR-REALM.COM is the Kerberos realm.

### HBase Authentication

There are two major parts in the process of configuring HBase security:

- 1. Configure HBase Authentication: You must establish a mechanism for HBase servers and clients to securely identify themselves with HDFS, ZooKeeper, and each other (called authentication). This ensures that, for example, a host claiming to be an HBase Region Server or a particular HBase client are in fact who they claim
- 2. Configure HBase Authorization: You must establish rules for the resources that clients are allowed to access (called authorization). For more information, see Configuring HBase Authorization on page 297.

For more background information, see this blog post.

The following sections describe how to use Apache HBase and CDH 5 with Kerberos security on your Hadoop cluster:

- Configuring Kerberos Authentication for HBase on page 77
- Configuring Secure HBase Replication on page 82
- Configuring the HBase Client TGT Renewal Period on page 83

#### Important:

To enable HBase to work with Kerberos security on your Hadoop cluster, make sure you perform the installation and configuration steps in Configuring Hadoop Security in CDH 5 and ZooKeeper Security Configuration.

Note:

These instructions have been tested with CDH and MIT Kerberos 5 only.

#### Important:

Although an HBase Thrift server can connect to a secured Hadoop cluster, access is not secured from clients to the HBase Thrift server.

# Configuring Kerberos Authentication for HBase

Follow these high-level steps to configure HBase authentication:

Step 1: Configure HBase Servers to Authenticate with a Secure HDFS Cluster on page 77

Step 2: Configure HBase Servers and Clients to Authenticate with a Secure ZooKeeper on page 78.

Step 1: Configure HBase Servers to Authenticate with a Secure HDFS Cluster

To configure HBase servers to authenticate with a secure HDFS cluster, you must do the following:

- Enable HBase Authentication
- Configure HBase Kerberos Principals

## **Enabling HBase Authentication**

To enable HBase Authentication, set the hbase.security.authentication property to kerberos in hbase-site.xml on every host acting as an HBase master, region server, or client. In CDH 5, hbase.rpc.engine is automatically detected and does not need to be set.

```
<name>hbase.security.authentication</name>
   <value>kerberos</value>
</property>
```

### Configuring HBase Kerberos Principals

To run on a secure HDFS cluster, HBase must authenticate itself to the HDFS services. HBase acts as a Kerberos principal and needs Kerberos credentials to interact with the Kerberos-enabled HDFS daemons. You can authenticate a service by using a keytab file, which contains a key that allows the service to authenticate to the Kerberos Key Distribution Center (KDC).

1. Create a service principal for the HBase server using the following syntax. This principal is used to authenticate the HBase server with the HDFS services. Cloudera recommends using hbase as the username portion of this principal.

```
$ kadmin
kadmin: addprinc -randkey hbase/fully.qualified.domain.name@YOUR-REALM.COM
```

fully.qualified.domain.name is the host where the HBase server is running, and YOUR-REALM is the name of your Kerberos realm.

**2.** Create a keytab file for the HBase server.

```
$ kadmin
kadmin: xst -k hbase.keytab hbase/fully.qualified.domain.name
```

3. Copy the hbase.keytab file to the /etc/hbase/conf directory on the HBase server host. The owner of the hbase.keytab file should be the hbase user, and the file should have owner-only read permissions—that is, assign the file 0400 permissions and make it owned by hbase: hbase.

```
1343 2012-01-09 10:39 hbase.keytab
-r---- 1 hbase hbase
```

4. To test that the keytab file was created properly, try to obtain Kerberos credentials as the HBase principal using only the keytab file. Substitute your fully.qualified.domain.name and realm in the following command:

```
$ kinit -k -t /etc/hbase/conf/hbase.keytab
hbase/fully.qualified.domain.name@YOUR-REALM.COM
```

5. In the /etc/hbase/conf/hbase-site.xml configuration file on all cluster hosts running the HBase daemon, add the following lines:

```
cproperty>
 <name>hbase.regionserver.kerberos.principal
  <value>hbase/_HOST@YOUR-REALM.COM</value>
</property>
property>
 <name>hbase.regionserver.keytab.file</name>
 <value>/etc/hbase/conf/hbase.keytab</value>
</property>
 <name>hbase.master.kerberos.principal</name>
  <value>hbase/_HOST@YOUR-REALM.COM</value>
</property>
cproperty>
<name>hbase.master.keytab.file</name>
<value>/etc/hbase/conf/hbase.keytab</value>
</property>
```

### Step 2: Configure HBase Servers and Clients to Authenticate with a Secure ZooKeeper

To run a secure HBase, you must also use a secure ZooKeeper. To use a secure ZooKeeper, each HBase host machine (Master, RegionServer, and client) must have a principal that allows it to authenticate with your secure ZooKeeper ensemble.

- Note: This section assumes the following:
  - Your secure ZooKeeper is already configured according to the instructions in the ZooKeeper Security <u>Configuration</u> section and is *not* managed by HBase.
  - You have successfully completed the previous steps and already have a principal and keytab file created and in place for every HBase server and client.

### Configure HBase JVMs (all Masters, Region Servers, and clients) to use JAAS

1. On each host, set up a Java Authentication and Authorization Service (JAAS) by creating a /etc/hbase/conf/zk-jaas.conf file that contains the following:

```
com.sun.security.auth.module.Krb5LoginModule required
useKeyTab=true
useTicketCache=false
keyTab="/etc/hbase/conf/hbase.keytab"
principal="hbase/fully.qualified.domain.name@<YOUR-REALM>";
```

2. Modify the hbase-env. sh file on HBase server and client hosts to include the following:

```
_____
  export HBASE_OPTS="$HBASE_OPTS
-Djava.security.auth.login.config=/etc/hbase/conf/zk-jaas.conf"
 export HBASE_MANAGES_ZK=false
```

### Configure the HBase Servers (Masters and Region Servers) to use Authentication to connect to ZooKeeper

1. Update your hbase-site.xml on each HBase server host with the following properties:

```
<configuration>
  operty>
     <name>hbase.zookeeper.quorum</name>
```

```
<value>$ZK_NODES</value>
  </property>
  cproperty>
     <name>hbase.cluster.distributed</name>
     <value>true</value>
  </property>
</configuration>
```

\$ZK\_NODES is the comma-separated list of hostnames of the ZooKeeper Quorum hosts that you configured according to the instructions in **ZooKeeper Security Configuration**.

2. Add the following lines to the ZooKeeper configuration file zoo.cfg:

```
kerberos.removeHostFromPrincipal=true
kerberos.removeRealmFromPrincipal=true
```

### Configure HBase for REST Gateway Impersonation

By default, the REST gateway does not support impersonation, but accesses HBase as a statically-configured user. The actual user who initiated the request is not tracked. With impersonation, the REST gateway user is a proxy user. The HBase server knows the actual user who initiates each request and uses this information to apply authorization.

1. Enable support for proxy users by adding the following properties to hbase-site.xml. Substitute the REST gateway proxy user for \$USER, and the allowed group list for \$GROUPS.

```
property>
 <name>hadoop.security.authorization
 <value>true</value>
</property>
property>
 <name>hadoop.proxyuser.$USER.groups</name>
  <value>$GROUPS</value>
</property>
cproperty>
 <name>hadoop.proxyuser.$USER.hosts
  <value>$GROUPS</value>
</property>
```

2. Enable REST gateway impersonation by adding the following to the hbase-site.xml file for every REST gateway:

```
property>
 <name>hbase.rest.authentication.type</name>
  <value>kerberos</value>
</property>
property>
 <name>hbase.rest.authentication.kerberos.principal</name>
 <value>HTTP/fully.qualified.domain.name@<YOUR-REALM/value>
cproperty>
 <name>hbase.rest.authentication.kerberos.keytab
 <value>/etc/hbase/conf/hbase.keytab</value>
</property>
```

## Configure Authentication for the HBase Thrift Gateway

These instructions configure Thrift to authenticate to HBase as a static Kerberos principal. In CDH, doAs Impersonation allows the client to direct the Thrift gateway to authenticate using different Kerberos principals as needed. For more information, see Configure doAs Impersonation for the HBase Thrift Gateway on page 80 and HBASE-12640.

- 1. Configure impersonation support by following the instructions in Configure HBase for REST Gateway Impersonation on page 79.
- 2. Add the following properties to hbase-site.xml for each Thrift gateway, replacing the Kerberos principal with a valid value:

```
property>
 <name>hbase.thrift.keytab.file</name>
  <value>/etc/hbase/conf/hbase.keytab</value>
</property>
property>
 <name>hbase.thrift.kerberos.principal</name>
  <value>hbase/fully.qualified.domain.name@<YOUR-REALM</value>
</property>
```

3. To use the Thrift API principal to interact with HBase, add the hbase.thrift.kerberos.principal to the acl table. For example, to provide administrative access to the Thrift API principal thrift server, run an HBase Shell command like the following:

```
hbase> grant'thrift_server', 'RWCA'
```

4. Optional: Configure HTTPS transport for Thrift by configuring the following parameters, substituting the placeholders with actual values:

```
property>
 <name>hbase.thrift.ssl.enabled
 <value>true</value>
</property>
property>
 <name>hbase.thrift.ssl.keystore.store</name>
 <value>LOCATION_OF_KEYSTORE</value>
</property>
cproperty>
 <name>hbase.thrift.ssl.keystore.password</name>
 <value>KEYSTORE_PASSWORD</value>
</property>
cproperty>
 <name>hbase.thrift.ssl.keystore.keypassword</name>
  <value>LOCATION_OF_KEYSTORE_KEY_PASSWORD</value>
</property>
```

The Thrift gateway will authenticate with HBase using the supplied credential. No authentication is performed by the Thrift gateway itself. All client access via the Thrift gateway uses the Thrift gateway's credential, and all clients have its privileges.

Configure doAs Impersonation for the HBase Thrift Gateway

Note:

## **Limitations with Thrift Framed Transport**

If you use framed transport, you cannot use this feature, because SASL does not work with Thrift framed transport.

doas Impersonation provides a flexible way to use the same client to impersonate multiple principals. The doas feature is only supported in Thrift 1, not Thrift 2. All of the following instructions involve editing the hbase-site.xml on each Thrift gateway.

1. Configure Thrift to run in secure mode, following the instructions in Configure Authentication for the HBase Thrift Gateway on page 79.

2. Enable support for proxy users by adding the following properties to hbase-site.xml. Substitute the REST gateway proxy user for \$USER, and the allowed group list for \$GROUPS.

```
cproperty>
 <name>hadoop.security.authorization</name>
  <value>true</value>
</property>
property>
 <name>hadoop.proxyuser.$USER.groups</name>
 <value>$GROUPS</value>
</property>
cproperty>
 <name>hadoop.proxyuser.$USER.hosts
  <value>$GROUPS</value>
</property>
```

3. To use the Thrift API principal to interact with HBase, add the hbase.thrift.kerberos.principal to the ac1 table. For example, to provide administrative access to the Thrift API principal thrift\_server, run an HBase Shell command like the following:

```
hbase> grant'thrift_server', 'RWCA'
```

- 4. In hbase-site.xml for each cluster node running a Thrift gateway, set the property hbase.thrift.security.qop to one of the following values:
  - auth-conf authentication, integrity, and confidentiality checking
  - auth-int authentication and integrity checking
  - auth authentication checking only
- **5.** Enable doAs support by adding the following properties to hbase-site.xml:

```
property>
 <name>hbase.regionserver.thrift.http</name>
  <value>true</value>
</property>
 <name>hbase.thrift.support.proxyuser</name>
  <value>true/value>
</property>
```

6. Optional: Configure HTTPS transport for Thrift by configuring the following parameters, substituting the placeholders with actual values:

```
property>
 <name>hbase.thrift.ssl.enabled</name>
 <value>true</value>
</property>
cpropert.v>
 <name>hbase.thrift.ssl.keystore.store</name>
 <value>LOCATION_OF_KEYSTORE</value>
</property>
cproperty>
 <name>hbase.thrift.ssl.keystore.password</name>
 <value>KEYSTORE_PASSWORD</value>
</property>
property>
 <name>hbase.thrift.ssl.keystore.keypassword</name>
  <value>LOCATION_OF_KEYSTORE_KEY_PASSWORD</value>
</property>
```

See the demo client for information on using doas impersonation in your client applications.

#### Start HBase

If the configuration worked, you see something similar to the following in the HBase Master and Region Server logs when you start the cluster:

```
INFO zookeeper.ZooKeeper: Initiating client connection,
connectString=ZK_QUORUM_SERVER:2181 sessionTimeout=180000 watcher=master:60000
INFO zookeeper.ClientCnxn: Opening socket connection to server /ZK_QUORUM_SERVER:2181
INFO zookeeper.RecoverableZooKeeper: The identifier of this process is
PID@ZK_QUORUM_SERVER
INFO zookeeper.Login: successfully logged in.
INFO client.ZooKeeperSaslClient: Client will use GSSAPI as SASL mechanism.
INFO zookeeper.Login: TGT refresh thread started.
INFO zookeeper.ClientCnxn: Socket connection established to ZK_QUORUM_SERVER:2181,
initiating session
INFO zookeeper.Login: TGT valid starting at:
                                                    Sun Apr 08 22:43:59 UTC 2012
INFO zookeeper.Login: TGT expires:
                                                   Mon Apr 09 22:43:59 UTC 2012
INFO zookeeper.Login: TGT refresh sleeping until: Mon Apr 09 18:30:37 UTC 2012
INFO zookeeper.ClientCnxn: Session establishment complete on server
ZK_QUORUM_SERVER:2181, sessionid = 0x134106594320000, negotiated timeout = 180000
```

# Configuring Secure HBase Replication

If you are using HBase Replication and you want to make it secure, read this section for instructions. Before proceeding, you should already have configured HBase Replication by following the instructions in the HBase Replication section of the CDH 5 Installation Guide.

To configure secure HBase replication, you must configure cross realm support for Kerberos, ZooKeeper, and Hadoop.

### To configure secure HBase replication:

1. Create krbtgt principals for the two realms. For example, if you have two realms called ONE. COM and TWO. COM, you need to add the following principals: krbtqt/ONE.COM@TWO.COM and krbtqt/TWO.COM@ONE.COM. Add these two principals at both realms. Note that there must be at least one common encryption mode between these two realms.

```
kadmin: addprinc -e "<enc_type_list>" krbtgt/ONE.COM@TWO.COM
kadmin: addprinc -e "<enc_type_list>" krbtgt/TWO.COM@ONE.COM
```

2. Add rules for creating short names in Zookeeper. To do this, add a system level property in java.env, defined in the conf directory. Here is an example rule that illustrates how to add support for the realm called ONE.COM, and have two members in the principal (such as service/instance@ONE.COM):

```
-Dzookeeper.security.auth\_to\_local=RULE: [2:\$1@\$0](.*@\QONE.COM\E\$)s/@\QONE.COM\E\$//DEFAULT
```

The above code example adds support for the ONE. COM realm in a different realm. So, in the case of replication, you must add a rule for the master cluster realm in the slave cluster realm. DEFAULT is for defining the default rule.

3. Add rules for creating short names in the Hadoop processes. To do this, add the hadoop.security.auth\_to\_local property in the core-site.xml file in the slave cluster. For example, to add support for the ONE.COM realm:

```
property>
 <name>hadoop.security.auth_to_local
  <value>
   RULE:[2:$1@$0](.*@\QONE.COM\E$)s/@\QONE.COM\E$//
 DEFAULT
 </value>
</property>
```

For more information about adding rules, see Appendix C - Configuring the Mapping from Kerberos Principals to Short Names.

# Configuring the HBase Client TGT Renewal Period

An HBase client user must also have a Kerberos principal which typically has a password that only the user knows. You should configure the maxrenewlife setting for the client's principal to a value that allows the user enough time to finish HBase client processes before the ticket granting ticket (TGT) expires. For example, if the HBase client processes require up to four days to complete, you should create the user's principal and configure the maxrenewlife setting by using this command:

```
kadmin: addprinc -maxrenewlife 4days
```

# **HCatalog Authentication**

This section describes how to configure HCatalog in CDH 5 with Kerberos security in a Hadoop cluster:

- Before You Start on page 83
- Step 1: Create the HTTP keytab file on page 83
- Step 2: Configure WebHCat to Use Security on page 83
- Step 3: Create Proxy Users on page 84
- Step 4: Verify the Configuration on page 84

For more information about HCatalog see Installing and Using HCatalog.

### Before You Start

Secure Web HCatalog requires a running remote Hive metastore service configured in secure mode. See Hive MetaStoreServer Security Configuration for instructions. Running secure WebHCat with an embedded repository is not supported.

# Step 1: Create the HTTP keytab file

You need to create a keytab file for WebHCat. Follow these steps:

**1.** Create the file:

```
kadmin: addprinc -randkey HTTP/fully.qualified.domain.name@YOUR-REALM.COM
kadmin: xst -k HTTP.keytab HTTP/fully.qualified.domain.name
```

2. Move the file into the WebHCat configuration directory and restrict its access exclusively to the heatalog user:

```
$ mv HTTP.keytab /etc/webhcat/conf/
$ chown hcatalog /etc/webhcat/conf/HTTP.keytab
$ chmod 400 /etc/webhcat/conf/HTTP.keytab
```

## Step 2: Configure WebHCat to Use Security

Create or edit the WebHCat configuration file webhcat-site.xml in the configuration directory and set following properties:

Property	Value
templeton.kerberos.secret	Any random value
templeton.kerberos.keytab	/etc/webhcat/conf/HTTP.keytab
templeton.kerberos.principal	HTTP/fully.qualified.domain.name@YOUR-REALM.COM

### **Example configuration:**

```
opertv>
   <name>templeton.kerberos.secret</name>
   <value>SuPerS3c3tV@lue!</value>
 </property>
 opertv>
   <name>templeton.kerberos.keytab
   <value>/etc/webhcat/conf/HTTP.keytab</value>
  </property>
 cproperty>
   <name>templeton.kerberos.principal</name>
   <value>HTTP/fully.qualified.domain.name@YOUR-REALM.COM</value>
 </property>
```

# Step 3: Create Proxy Users

WebHCat needs access to your NameNode in order to work properly, and so you must configure Hadoop to allow impersonation from the heatalog user. To do this, edit your core-site.xml configuration file and set the hadoop.proxyuser.HTTP.hosts and hadoop.proxyuser.HTTP.groups properties to specify the hosts from which HCatalog can do the impersonation and what users can be impersonated. You can use the value \* for "any".

### Example configuration:

```
cpropertv>
 <name>hadoop.proxyuser.HTTP.hosts
 <value>*</value>
</property>
property>
 <name>hadoop.proxyuser.HTTP.groups</name>
 <value>*</value>
</property>
```

# Step 4: Verify the Configuration

After restarting WebHcat you can verify that it is working by using curl (you may need to run kinit first):

```
$ curl --negotiate -i -u :
'http://fully.qualified.domain.name:50111/templeton/v1/ddl/database'
```

## Hive Authentication

Here is a summary of the status of Hive security in CDH 5:

- Sentry enables role-based, fine-grained authorization for HiveServer2. See Sentry Policy File Authorization on page 258.
- HiveServer2 supports authentication of the Thrift client using Kerberos or user/password validation backed by LDAP. For configuration instructions, see <u>HiveServer2 Security Configuration</u>.
- Earlier versions of HiveServer do not support Kerberos authentication for clients. However, the Hive MetaStoreServer does support Kerberos authentication for Thrift clients. For configuration instructions, see Hive MetaStoreServer Security Configuration.

See also: Using Hive to Run Queries on a Secure HBase Server on page 91

## HiveServer2 Security Configuration

HiveServer2 supports authentication of the Thrift client using either of these methods:

- Kerberos authentication
- LDAP authentication

If Kerberos authentication is used, authentication is supported between the Thrift client and HiveServer2, and between HiveServer2 and secure HDFS. If LDAP authentication is used, authentication is supported only between the Thrift client and HiveServer2.

## Enabling Kerberos Authentication for HiveServer2

If you configure HiveServer2 to use Kerberos authentication, HiveServer2 acquires a Kerberos ticket during start-up. HiveServer2 requires a principal and keytab file specified in the configuration. The client applications (for example JDBC or Beeline) must get a valid Kerberos ticket before initiating a connection to HiveServer2.

## Configuring HiveServer2 for Kerberos-Secured Clusters

To enable Kerberos Authentication for HiveServer2, add the following properties in the /etc/hive/conf/hive-site.xml file:

```
<name>hive.server2.authentication</name>
 <value>KERBEROS</value>
</property>
property>
 <name>hive.server2.authentication.kerberos.principal
 <value>hive/_HOST@YOUR-REALM.COM</value>
</property>
property>
 <name>hive.server2.authentication.kerberos.keytab</name>
  <value>/etc/hive/conf/hive.keytab</value>
</property>
```

### where:

- hive.server2.authentication in particular, is a client-facing property that controls the type of authentication HiveServer2 uses for connections to clients. In this case, HiveServer2 uses Kerberos to authenticate incoming clients.
- The \_HOST@YOUR-REALM. COM value in the example above is the Kerberos principal for the host where HiveServer2 is running. The special string HOST in the properties is replaced at run-time by the fully-qualified domain name of the host machine where the daemon is running. This requires that reverse DNS is properly working on all the hosts configured this way. Replace YOUR-REALM. COM with the name of the Kerberos realm your Hadoop cluster is in.
- The /etc/hive/conf/hive.keytab value in the example above is a keytab file for that principal.

If you configure HiveServer2 to use both Kerberos authentication and secure impersonation, JDBC clients and Beeline can specify an alternate session user. If these clients have proxy user privileges, HiveServer2 will impersonate the alternate user instead of the one connecting. The alternate user can be specified by the JDBC connection string proxyUser=userName

#### Configuring JDBC Clients for Kerberos Authentication with HiveServer2

JDBC-based clients must include principal=<hive.server2.authentication.principal> in the JDBC connection string. For example:

```
String url =
"jdbc:hive2://node1:10000/default;principal=hive/HiveServer2Host@YOUR-REALM.COM"
Connection con = DriverManager.getConnection(url);
```

where hive is the principal configured in hive-site.xml and HiveServer2Host is the host where HiveServer2 is running.

For ODBC Clients, refer the <u>Cloudera ODBC Driver for Apache Hive</u> documentation.

## Using Beeline to Connect to a Secure HiveServer2

Use the following command to start beeline and connect to a secure running HiveServer2 process. In this example, the HiveServer2 process is running on localhost at port 10000:

```
$ /usr/lib/hive/bin/beeline
beeline> !connect
jdbc:hive2://localhost:10000/default;principal=hive/HiveServer2Host@YOUR-REALM.COM
0: jdbc:hive2://localhost:10000/default>
```

For more information about the Beeline CLI, see <u>Using the Beeline CLI</u>.

### Using LDAP Username/Password Authentication with HiveServer2

As an alternative to Kerberos authentication, you can configure HiveServer2 to use user and password validation backed by LDAP. In this case, the client sends a user name and password during the connection initiation. HiveServer2 validates these credentials using an external LDAP service.

You can enable LDAP Authentication with HiveServer2 using Active Directory or OpenLDAP.

Important: When using LDAP username/password authentication with HiveServer2, make sure you have enabled encrypted communication between HiveServer2 and its client drivers to avoid sending cleartext passwords. For instructions, see Configuring Encrypted Communication Between Hive and Client Drivers on page 184. Also see Configuring LDAPS Authentication with HiveServer2 on page 87.

### Enabling LDAP Authentication with HiveServer2 using Active Directory

To enable the LDAP mode of authentication using Active Directory, include the following properties in the hive-site.xml file:

```
property>
 <name>hive.server2.authentication
 <value>LDAP</value>
</property>
property>
 <name>hive.server2.authentication.ldap.url
 <value>LDAP_URL</value>
</property>
property>
 <name>hive.server2.authentication.ldap.Domain
  <value>DOMAIN</value>
</property>
```

### where:

■ The LDAP\_URL value is the access URL for your LDAP server. For example, ldap://ldaphost@company.com.

### Enabling LDAP Authentication with HiveServer2 using OpenLDAP

To enable the LDAP mode of authentication using OpenLDAP, include the following properties in the hive-site.xml file:

```
<name>hive.server2.authentication
  <value>LDAP</value>
</property>
opertv>
  <name>hive.server2.authentication.ldap.url
  <value>LDAP_URL</value>
</property>
property>
 <name>hive.server2.authentication.ldap.baseDN</name>
  <value>LDAP_BaseDN</value>
</property>
```

#### where:

- The LDAP\_URL value is the access URL for your LDAP server.
- The LDAP\_BaseDN value is the base LDAP DN for your LDAP server. For example, ou=People, dc=example, dc=com.

### Configuring JDBC Clients for LDAP Authentication with HiveServer2

The IDBC client needs to use a connection URL as shown below. -

JDBC-based clients must include user=LDAP\_Userid; password=LDAP\_Password in the JDBC connection string.

```
String url = "jdbc:hive2://node1:10000/default;user=LDAP_Userid;password=LDAP_Password"
Connection con = DriverManager.getConnection(url);
```

where the LDAP\_Userid value is the user id and LDAP\_Password is the password of the client user.

For ODBC Clients, refer the Cloudera ODBC Driver for Apache Hive documentation.

### Configuring LDAPS Authentication with HiveServer2

HiveServer2 supports <u>LDAP username/password authentication</u> for clients. Clients send LDAP credentials to HiveServer2 which in turn verifies them with the configured LDAP provider such as OpenLDAP or Microsoft's Active Directory. Most vendors now support LDAPS (LDAP over SSL), an authentication protocol that uses SSL to encrypt communication between the LDAP service and its client (in this case, HiveServer2) to avoid sending LDAP credentials in cleartext.

Perform the following steps to configure the LDAPS service with HiveServer2:

- Import either the LDAP server issuing Certificate Authority's SSL certificate into a local truststore, or import the SSL server certificate for a specific trust. If you import the CA certificate, HiveServer2 will trust any server with a certificate issued by the LDAP server's CA. If you only import the SSL certificate for a specific trust, HiveServer2 will trust only that server. In both cases, the SSL certificate must be imported on to the same host as HiveServer2. Refer the keytool documentation for more details.
- Make sure the truststore file is readable by the hive user.
- Set the hive.server2.authentication.ldap.url configuration property in hive-site.xml to the LDAPS URL. For example, ldaps://sample.myhost.com.
  - **Note:** The URL scheme should be ldaps and *not* ldap.
- Set the environment variable HADOOP\_OPTS as follows. You can refer the Creating Java Keystores and <u>Truststores</u> on page 158 topic for details on adding CA certificates to existing truststores or creating new truststores:

```
HADOOP_OPTS="-Djavax.net.ssl.trustStore=<trustStore-file-path>
-Djavax.net.ssl.trustStorePassword=<trustStore-password>
```

For clusters managed by Cloudera Manager, go to the Hive service and select Configuration > View and Edit. Under the HiveServer2 category, go to the Advanced section and set the HiveServer2 Environment Safety Valve property.

Restart HiveServer2.

### Pluggable Authentication

Pluggable authentication allows you to provide a custom authentication provider for HiveServer2.

To enable pluggable authentication:

Set the following properties in /etc/hive/conf/hive-site.xml:

```
property>
 <name>hive.server2.authentication
  <value>CUSTOM</value>
 <description>Client authentication types.
 NONE: no authentication check
 LDAP: LDAP/AD based authentication
 KERBEROS: Kerberos/GSSAPI authentication
 CUSTOM: Custom authentication provider
 (Use with property hive.server2.custom.authentication.class)
  </description>
</property>
cproperty>
  <name>hive.server2.custom.authentication.class/name>
  <value>pluggable-auth-class-name</value>
  <description>
 Custom authentication class. Used when property
  'hive.server2.authentication' is set to 'CUSTOM'. Provided class
 must be a proper implementation of the interface
 org.apache.hive.service.auth.PasswdAuthenticationProvider. HiveServer2
 will call its Authenticate(user, passed) method to authenticate requests.
 The implementation may optionally extend the Hadoop's
 org.apache.hadoop.conf.Configured class to grab Hive's Configuration object.
 </description>
</property>
```

2. Make the class available in the CLASSPATH of HiveServer2.

### Trusted Delegation with HiveServer2

HiveServer2 determines the identity of the connecting user from the underlying authentication subsystem (Kerberos or LDAP). Any new session started for this connection runs on behalf of this connecting user. If the server is configured to proxy the user at the Hadoop level, then all MapReduce jobs and HDFS accesses will be performed with the identity of the connecting user. If Apache Sentry is configured, then this connecting userid can also be used to verify access rights to underlying tables, views and so on.

In CDH 4.5, a connecting user (for example, hue) with Hadoop-level superuser privileges, can request an alternate user for the given session. HiveServer2 will check if the connecting user has Hadoop-level privileges to proxy the requested userid (for example, bob). If it does, then the new session will be run on behalf of the alternate user, bob, requested by connecting user, hue.

To specify an alternate user for new connections, the JDBC client needs to add the hive.server2.proxy.user=<alternate\_user\_id> property to the JDBC connection URL. Note that the connecting user needs to have Hadoop-level proxy privileges over the alternate user. For example, if user hue requests access to run a session as user bob, the JDBC connection string should be as follows:

```
# Login as super user Hue
kinit hue -k -t hue.keytab hue@MY-REALM.COM
# Connect using following JDBC connection string
jdbc:hive2://myHost.myOrg.com:10000/default;principal=hive/_HOST@MY-REAIM.COM;hive.server2.proxy.user=bob
```

#### HiveServer2 Impersonation

**Note:** This is not the recommended method to implement HiveServer2 impersonation. Cloudera recommends you use <u>Sentry</u> to implement this instead.

Impersonation support in HiveServer2 allows users to execute queries and access HDFS files as the connected user rather than the super user who started the HiveServer2 daemon. Impersonation allows admins to enforce an access policy at the file level using HDFS file and directory permissions.

To enable impersonation in HiveServer2:

1. Add the following property to the /etc/hive/conf/hive-site.xml file and set the value to true. (The default value is false.)

```
property>
 <name>hive.server2.enable.impersonation</name>
 <description>Enable user impersonation for HiveServer2</description>
</property>
```

2. In HDFS or MapReduce configurations, add the following property to the core-site.xml file:

```
cproperty>
 <name>hadoop.proxyuser.hive.hosts
 <value>*</value>
</property>
cproperty>
 <name>hadoop.proxyuser.hive.groups</name>
 <value>*</value>
</property>
```

See also File System Permissions.

### Securing the Hive Metastore

Note: This is not the recommended method to protect the Hive Metastore. Cloudera recommends you use **Sentry** to implement this instead.

To prevent users from accessing the Hive metastore and the Hive metastore database using any method other than through HiveServer2, the following actions are recommended:

- Add a firewall rule on the metastore service host to allow access to the metastore port only from the HiveServer2 host. You can do this using iptables.
- Grant access to the metastore database only from the metastore service host. This is specified for MySQL

```
GRANT ALL PRIVILEGES ON metastore.* TO 'hive'@'metastorehost';
```

where metastorehost is the host where the metastore service is running.

Make sure users who are not admins cannot log on to the host on which HiveServer2 runs.

#### Disabling the Hive Security Configuration

Hive's security related metadata is stored in the configuration file hive-site.xml. The following sections describe how to disable security for the Hive service.

#### Disable Client/Server Authentication

To disable client/server authentication, set hive.server2.authentication to NONE. For example,

```
cproperty>
 <name>hive.server2.authentication</name>
 <value>NONE</value>
 <description>
   Client authentication types.
      NONE: no authentication check
       LDAP: LDAP/AD based authentication
       KERBEROS: Kerberos/GSSAPI authentication
       CUSTOM: Custom authentication provider
               (Use with property hive.server2.custom.authentication.class)
 </description>
</property>
```

#### Disable Hive Metastore security

To disable Hive Metastore security, perform the following steps:

- Set the hive.metastore.sasl.enabled property to false in all configurations, the metastore service side as well as for all clients of the metastore. For example, these might include HiveServer2, Impala, Pig and so
- Remove or comment the following parameters in hive-site.xml for the metastore service. Note that this is a server-only change.
  - hive.metastore.kerberos.keytab.file
  - hive.metastore.kerberos.principal

## Disable Underlying Hadoop Security

If you also want to disable the underlying Hadoop security, remove or comment out the following parameters in hive-site.xml.

- hive.server2.authentication.kerberos.keytab
- hive.server2.authentication.kerberos.principal

# Hive Metastore Server Security Configuration

Important:

This section describes how to configure security for the Hive metastore server. If you are using HiveServer2, see <u>HiveServer2 Security Configuration</u>.

Here is a summary of Hive metastore server security in CDH 5:

- No additional configuration is required to run Hive on top of a security-enabled Hadoop cluster in standalone mode using a local or embedded metastore.
- HiveServer does not support Kerberos authentication for clients. While it is possible to run HiveServer with a secured Hadoop cluster, doing so creates a security hole since HiveServer does not authenticate the Thrift clients that connect to it. Instead, you can use HiveServer2 HiveServer2 Security Configuration.
- The Hive metastore server supports Kerberos authentication for Thrift clients. For example, you can configure a standalone Hive metastore server instance to force clients to authenticate with Kerberos by setting the following properties in the hive-site.xml configuration file used by the metastore server:

```
cproperty>
 <name>hive.metastore.sasl.enabled</name>
  <value>true</value>
  <description>If true, the metastore thrift interface will be secured with SASL.
Clients must authenticate with Kerberos.</description>
</property>
cproperty>
 <name>hive.metastore.kerberos.keytab.file
  <value>/etc/hive/conf/hive.keytab</value>
 <description>The path to the Kerberos Keytab file containing the metastore thrift
server's service principal.</description>
</property>
cproperty>
 <name>hive.metastore.kerberos.principal</name>
  <value>hive/_HOST@YOUR-REALM.COM</value>
 <description>The service principal for the metastore thrift server. The special
string _HOST will be replaced automatically with the correct host
name.</description>
</property>
```

Note:

The values shown above for the hive.metastore.kerberos.keytab.file and hive.metastore.kerberos.principal properties are examples which you will need to replace with the appropriate values for your cluster. Also note that the Hive keytab file should have its access permissions set to 600 and be owned by the same account that is used to run the Metastore server, which is the hive user by default.

Requests to access the metadata are fulfilled by the Hive metastore impersonating the requesting user. This includes read access to the list of databases, tables, properties of each table such as their HDFS location, file type and so on. You can restrict access to the Hive metastore service by allowing it to impersonate only a subset of Kerberos users. This can be done by setting the hadoop.proxyuser.hive.groups property in core-site.xml on the Hive metastore host.

For example, if you want to give the hive user permission to impersonate members of groups hive and user1:

```
property>
<name>hadoop.proxyuser.hive.groups</name>
<value>hive,user1</value>
</property>
```

In this example, the Hive metastore can impersonate users belonging to only the hive and user1 groups. Connection requests from users not belonging to these groups will be rejected.

# Using Hive to Run Queries on a Secure HBase Server

To use Hive to run queries on a secure HBase Server, you must set the following <code>HIVE\_OPTS</code> environment variable:

```
env HIVE OPTS="-hiveconf hbase.security.authentication=kerberos -hiveconf
hbase.master.kerberos.principal=hbase/_HOST@YOUR-REALM.COM -hiveconf
hbase.zookeeper.quorum=zookeeper1,zookeeper2,zookeeper3" hive
```

#### where:

- You replace YOUR-REALM with the name of your Kerberos realm
- You replace zookeeper1, zookeeper2, zookeeper3 with the names of your ZooKeeper servers. The hbase.zookeeper.quorum property is configured in the hbase-site.xml file.
- The special string \_HOST is replaced at run-time by the fully-qualified domain name of the host machine where the HBase Master or Region Server is running. This requires that reverse DNS is properly working on all the hosts configured this way.

In the following, \_HOST is the name of the host where the HBase Master is running:

```
-hiveconf hbase.master.kerberos.principal=hbase/_HOST@YOUR-REALM.COM
```

In the following, \_HOST is the host name of the HBase Region Server that the application is connecting to:

```
-hiveconf hbase.regionserver.kerberos.principal=hbase/_HOST@YOUR-REALM.COM
```

Tip:

You can also set the HIVE\_OPTS environment variable in your shell profile.

# HttpFS Authentication

This section describes how to configure HttpFS CDH 5 with Kerberos security on a Hadoop cluster:

- Configuring the HttpFS Server to Support Kerberos Security on page 92
- Using curl to access an URL Protected by Kerberos HTTP SPNEGO on page 93

For more information about HttpFS, see

http://archive.cloudera.com/cdh5/cdh/5/hadoop/hadoop-hdfs-httpfs/index.html.

#### Important:

To enable HttpFS to work with Kerberos security on your Hadoop cluster, make sure you perform the installation and configuration steps in Configuring Hadoop Security in CDH 5.

### Important:

If the NameNode, Secondary NameNode, DataNode, JobTracker, TaskTrackers, ResourceManager, NodeManagers, HttpFS, or Oozie services are configured to use Kerberos HTTP SPNEGO authentication, and two or more of these services are running on the same host, then all of the running services must use the same HTTP principal and keytab file used for their HTTP endpoints.

# Configuring the HttpFS Server to Support Kerberos Security

1. Create an HttpFS service user principal that is used to authenticate with the Hadoop cluster. The syntax of the principal is: httpfs/<fully.qualified.domain.name>@<YOUR-REALM> where: fully.qualified.domain.name is the host where the HttpFS server is running YOUR-REALM is the name of your Kerberos realm

```
kadmin: addprinc -randkey httpfs/fully.qualified.domain.name@YOUR-REALM.COM
```

2. Create a HTTP service user principal that is used to authenticate user requests coming to the HttpFS HTTP web-services. The syntax of the principal is: HTTP/<fully.qualified.domain.name>@<YOUR-REALM> where: 'fully.qualified.domain.name' is the host where the HttpFS server is running YOUR-REALM is the name of your Kerberos realm

```
kadmin: addprinc -randkey HTTP/fully.qualified.domain.name@YOUR-REALM.COM
```

Important:

The HTTP/ component of the HTTP service user principal must be upper case as shown in the syntax and example above.

**3.** Create keytab files with both principals.

```
$ kadmin
kadmin: xst -k httpfs.keytab httpfs/fully.qualified.domain.name
kadmin: xst -k http.keytab HTTP/fully.qualified.domain.name
```

**4.** Merge the two keytab files into a single keytab file:

```
$ ktutil
ktutil: rkt httpfs.keytab
ktutil: rkt http.keytab
ktutil: wkt httpfs-http.keytab
```

**5.** Test that credentials in the merged keytab file work. For example:

```
______
$ klist -e -k -t httpfs-http.keytab
```

- 6. Copy the httpfs-http.keytab file to the HttpFS configuration directory. The owner of the httpfs-http.keytab file should be the httpfs user and the file should have owner-only read permissions.
- 7. Edit the HttpFS server httpfs-site.xml configuration file in the HttpFS configuration directory by setting the following properties:

Property	Value
httpfs.authentication.type	kerberos
httpfs.hadoop.authentication.type	kerberos
httpfs.authentication.kerberos.principal	HTTP/ <httpfs-hostname>@<your-realm.com></your-realm.com></httpfs-hostname>
httpfs.authentication.kerberos.keytab	/etc/hadoop-httpfs/conf/httpfs-http.keytab
httpfs.hadoop.authentication.kerberos.principal	httpfs/ <httpfs-hostname>@<your-realm.com></your-realm.com></httpfs-hostname>
httpfs.hadoop.authentication.kerberos.keytab	/etc/hadoop-httpfs/conf/httpfs-http.keytab
httpfs.authentication.kerberos.name.rules	Use the value configured for 'hadoop.security.auth_to_local' in 'core-site.xml'

Important:

You must restart the HttpFS server to have the configuration changes take effect.

# Using curl to access an URL Protected by Kerberos HTTP SPNEGO

Important:

Your version of curl must support GSS and be capable of running curl -v.

## To configure curl to access an URL protected by Kerberos HTTP SPNEGO:

1. Run curl -V:

```
$ curl -V
curl 7.19.7 (universal-apple-darwin10.0) libcurl/7.19.7 OpenSSL/0.9.81
zlib/1.2.3
Protocols: tftp ftp telnet dict ldap http file https ftps
Features: GSS-Negotiate IPv6 Largefile NTLM SSL libz
```

2. Login to the KDC using kinit.

```
$ kinit
Please enter the password for tucu@LOCALHOST:
```

**3.** Use curl to fetch the protected URL:

```
$ curl --negotiate -u : -b ~/cookiejar.txt -c ~/cookiejar.txt
http://localhost:14000/webhdfs/v1/?op=liststatus
```

where: The -negotiate option enables SPNEGO in curl. The -u : option is required but the user name is ignored (the principal that has been specified for kinit is used). The -b and -c options are used to store and send HTTP cookies.

### Hue Authentication

The following sections describe how to configure Kerberos security, enable single sign-on with SAML and encrypt session communication between Hue and other CDH services.

- Configuring Kerberos Authentication for Hue on page 95
- Integrating Hue with LDAP on page 97
- Configuring Hue for SAML on page 101

### Important:

To enable Hue to work with Kerberos security on your Hadoop cluster, make sure you perform the installation and configuration steps in Configuring Hadoop Security in CDH 5.

# Hue Security Enhancements

## Enabling LDAP Authentication with HiveServer2 and Impala

LDAP authentication with HiveServer2 and Impala can be enabled by setting the following properties under the [desktop] section in hue.ini.

ldap_username	LDAP username of the Hue user to be authenticated.
ldap_password	LDAP password for the Hue user to be authenticated.

#### Session Timeout

Session timeouts can be set by specifying the ttl configuration property under the [desktop]>[[session]] section in hue.ini.

The cookie containing the users' session ID will expire after this amount of time in seconds.
Default: 60*60*24*14

#### Secure Cookies

Secure session cookies can be enable by specifying the secure configuration property under the [desktop]>[[session]] section in hue.ini. Additionally, you can set the http-only flag for cookies containing users' session IDs.

secure	The cookie containing the users' session ID will be secure. Should only be enabled with HTTPS.  Default: false
http-only	The cookie containing the users' session ID will use the HTTP only flag.
	Default: false

#### Allowed HTTP Methods

You can specify the HTTP request methods that the server should respond to using the http\_allowed\_methods property under the [desktop] section in hue.ini.

http_allowed_methods	Default: options, get, head, post, put, delete, connect	
----------------------	---	--

## Restricting the Cipher List

Cipher list support with HTTPS can be restricted by specifying the ssl\_cipher\_list configuration property under the [desktop] section in hue.ini.

ssl_cipher_list	Default: !anull: !enull: !Low: !Export: !SSLv2
asi_cipiici_iisc	Detail: : anoun : : cnoun : : Low : : Export : : 550 v 2

#### **URL Redirect Whitelist**

Restrict the domains or pages to which Hue can redirect users. The redirect\_whitelist property can be found under the [desktop] section in hue.ini.

redirect_whitelist	For example, to restrict users to your local domain and FQDN, the followin value can be used:
	^\/.*\$,^http:\/\/www.mydomain.com\/.*\$

# Configuring Kerberos Authentication for Hue

You can configure Hue in CDH 5 to support Hadoop security on a cluster using Kerberos.

### To configure the Hue server to support Hadoop security using Kerberos:

1. Create a Hue user principal in the same realm as the Hadoop cluster of the form:

```
kadmin: addprinc -randkey hue/hue.server.fully.qualified.domain.name@YOUR-REALM.COM
```

where: hue is the principal the Hue server is running as, hue.server.fully.qualified.domain.name is the fully-qualified domain name (FQDN) of your Hue server, YOUR-REALM. COM is the name of the Kerberos realm your Hadoop cluster is in

- 2. Create a keytab file for the Hue principal using the same procedure that you used to create the keytab for the hdfs or mapred principal for a specific host. You should name this file hue.keytab and put this keytab file in the directory /etc/hue on the machine running the Hue server. Like all keytab files, this file should have the most limited set of permissions possible. It should be owned by the user running the hue server (usually hue) and should have the permission 400.
- 3. To test that the keytab file was created properly, try to obtain Kerberos credentials as the Hue principal using only the keytab file. Substitute your FQDN and realm in the following command:

```
$ kinit -k -t /etc/hue/hue.keytab
hue/hue.server.fully.qualified.domain.name@YOUR-REALM.COM
```

4. In the /etc/hue/hue.ini configuration file, add the following lines in the sections shown. Replace the kinit path value, /usr/kerberos/bin/kinit, shown below with the correct path on the user's system.

```
[desktop]
[[kerberos]]
# Path to Hue's Kerberos keytab file
hue_keytab=/etc/hue/hue.keytab
# Kerberos principal name for Hue
hue_principal=hue/FQDN@REALM
# add kinit path for non root users
kinit_path=/usr/kerberos/bin/kinit
[beeswax]
# If Kerberos security is enabled, use fully-qualified domain name (FQDN)
  ## hive_server_host=<FQDN of Hive Server>
 # Hive configuration directory, where hive-site.xml is located
  ## hive_conf_dir=/etc/hive/conf
[impala]
   ## server_host=localhost
 # The following property is required when impalad and Hue
```

```
# are not running on the same host
   ## impala_principal=impala/impalad.hostname.domainname.com
[search]
# URL of the Solr Server
  ## solr_url=http://localhost:8983/solr/
 # Requires FQDN in solr_url if enabled
  ## security_enabled=false
[hadoop]
[[hdfs_clusters]]
[[[default]]]
# Enter the host and port on which you are running the Hadoop NameNode
namenode_host=FQDN
hdfs_port=8020
http_port=50070
security_enabled=true
# Thrift plugin port for the name node
   ## thrift_port=10090
 # Configuration for YARN (MR2)
[[yarn_clusters]]
[[[default]]]
# Enter the host on which you are running the ResourceManager
  ## resourcemanager_host=localhost
# Change this if your YARN cluster is Kerberos-secured
  ## security_enabled=false
# Thrift plug-in port for the JobTracker
   ## thrift_port=9290
[liboozie]
# The URL where the Oozie service runs on. This is required in order for users
to submit jobs.
  ## oozie_url=http://localhost:11000/oozie
 # Requires FQDN in oozie_url if enabled
  ## security_enabled=false
```

### Important:

In the /etc/hue/hue.ini file, verify the following:

- Make sure the jobtracker\_host property is set to the fully-qualified domain name of the host running the JobTracker. The JobTracker host name must be fully-qualified in a secured environment.
- Make sure the fs.defaultfs property under each [[hdfs\_clusters]] section contains the fully-qualified domain name of the file system access point, which is typically the NameNode.
- Make sure the hive\_conf\_dir property under the [beeswax] section points to a directory containing a valid hive-site.xml (either the original or a synced copy).
- Make sure the FQDN specified for HiveServer2 is the same as the FQDN specified for the hue\_principal configuration property. Without this, HiveServer2 will not work with security enabled.
- 5. In the /etc/hadoop/conf/core-site.xml configuration file on all of your cluster nodes, add the following lines:

```
<!-- Hue security configuration -->
property>
 <name>hue.kerberos.principal.shortname</name>
  <value>hue</value>
```

```
</property>
property>
 <name>hadoop.proxyuser.hue.groups
  <value>*</value> <!-- A group which all users of Hue belong to, or the wildcard
value "*" -->
</property>
cproperty>
 <name>hadoop.proxyuser.hue.hosts
 <value>hue.server.fully.qualified.domain.name/value>
</property>
```

Important:

Make sure you change the /etc/hadoop/conf/core-site.xml configuration file on all of your cluster nodes.

6. If Hue is configured to communicate to Hadoop via HttpFS, then you must add the following properties to httpfs-site.xml:

```
<name>httpfs.proxyuser.hue.hosts
 <value>fully.qualified.domain.name
</property>
property>
 <name>httpfs.proxyuser.hue.groups</name>
 <value>*</value>
</property>
```

7. Add the following properties to the Oozie server oozie-site.xml configuration file in the Oozie configuration directory:

```
cproperty>
  <name>oozie.service.ProxyUserService.proxyuser.hue.hosts/name>
  <value>*</value>
</property>
opertv>
  <name>oozie.service.ProxyUserService.proxyuser.hue.groups/name>
   <value>*</value>
</property>
```

8. Restart the JobTracker to load the changes from the core-site.xml file.

```
$ sudo service hadoop-0.20-mapreduce-jobtracker restart
```

**9.** Restart Oozie to load the changes from the oozie-site.xml file.

```
$ sudo service oozie restart
```

10. Restart the NameNode, JobTracker, and all DataNodes to load the changes from the core-site.xml file.

```
$ sudo service hadoop-0.20-(namenode|jobtracker|datanode) restart
```

## Integrating Hue with LDAP

When Hue is integrated with LDAP users can use their existing credentials to authenticate and inherit their existing groups transparently. There is no need to save or duplicate any employee password in Hue. There are several other ways to authenticate with Hue such as PAM, SPNEGO, OpenID, OAuth, SAML2 and so on. This topic details how you can configure Hue to authenticate against an LDAP directory server.

When authenticating via LDAP, Hue validates login credentials against an LDAP directory service if configured with the LDAP authentication backend:

```
[desktop]
[[auth]]
backend=desktop.auth.backend.LdapBackend
```

The LDAP authentication backend will automatically create users that don't exist in Hue by default. Hue needs to import users in order to properly perform the authentication. Passwords are never imported when importing users. If you want to disable automatic import set the <code>create\_users\_on\_login</code> property under the <code>[desktop]</code> > [[ldap]] section of hue.ini to false.

```
[desktop]
[[ldap]]
create_users_on_login=false
```

The purpose of disabling the automatic import is to allow only a predefined list of manually imported users to

There are two ways to authenticate with a directory service through Hue:

- Search Bind
- Direct Bind

You can specify the authentication mechanism using the search\_bind\_authentication property under the [desktop] > [[ldap]] section of hue.ini.

search_bind_authentication	Uses search bind authentication by default. Set this property to false to use direct bind authentication.
	Default: true

## Search Bind

The search bind mechanism for authenticating will perform an <u>ldapsearch</u> against the directory service and bind using the found distinguished name (DN) and password provided. This is the default method of authentication used by Hue with LDAP.

The following configuration properties under the [desktop] > [[ldap]] > [[[users]]] section in hue.ini can be set to restrict the search process.

user_filter	General <u>LDAP filter</u> to restrict the search.
	Default: "objectclass=*"
user_name_attr	The attribute that will be considered the username to be searched against. Typical attributes to search for include: uid, sAMAccountName.
	Default: samaccountName

With the above configuration, the LDAP search filter will take on the form:

```
(&(objectClass=*)(sAMAccountName=<user entered username>))
```

Important: Setting search\_bind\_authentication=true in hue.ini tells Hue to perform an LDAP search using the bind credentials specified for the bind\_dn and bind\_password configuration properties. Hue will start searching the subtree starting from the base DN specified for the base\_dn property. It will then search the base DN for an entry whose attribute, specified in user\_name\_attr, has the same value as the short name provided on login. The search filter, defined in user\_filter will also be used to limit the search.

#### Direct Bind

The direct bind mechanism for authenticating will bind to the LDAP server using the username and password provided at login.


The following configuration properties can be used to determine how Hue binds to the LDAP server. These can be set under the [desktop] > [[ldap]] section of hue.ini.

nt_domain	The NT domain to connect to (only for use with Active Directory). This AD-specific property allows Hue to authenticate with AD without having to follow LDAP references to other partitions. This typically maps to the
	email address of the user or the user's ID in conjunction with the domain.
	If provided, Hue will use <u>User Principal Names</u> (UPNs) to bind to the LDAP service.
	Default: mycompany.com
ldap_username_pattern	Provides a template for the DN that will ultimately be sent to the directory service when authenticating. The <username> parameter will be replaced with the username provided at login.</username>
	Default: "uid= <username>,ou=People,dc=mycompany,dc=com"</username>


- Important: Setting search\_bind\_authentication=false in hue.ini tells Hue to perform a direct bind to LDAP using the credentials provided (notbind\_dn and bind\_password specified in hue.ini). There are two ways direct bind works depending on whether the nt\_domain property is specified in hue.ini:
  - nt\_domain is specified: This is used to connect to an Active Directory service. In this case, the User Principal Name (UPN) is used to perform a direct bind. Hue forms the UPN by concatenating the short name provided at login with the nt\_domain. For example, <short name>@<nt\_domain>. The ldap\_username\_pattern property is ignored.
  - nt\_domain is not specified: This is used to connect to all other directory services (can handle Active Directory, but nt\_domain is the preferred way for AD). In this case, ldap\_username\_pattern is used and it should take on the form cn=<username>,dc=example,dc=com where <username> will be replaced with the username provided at login.

## Importing LDAP Users and Groups

If an LDAP user needs to be part of a certain group and be given a particular set of permissions, you can import this user with the User Admin interface in Hue.



Groups can also be imported using the User Admin interface, and users can be added to this group. As in the image below, not only can groups be discovered via DN and <u>rDN</u> search, but users that are members of the group or members of its subordinate groups can be imported as well.



You have the following options available when importing a user/group:

- Distinguished name: If checked, the username provided must be a full distinguished name (for example, uid=hue, ou=People, dc=gethue, dc=com). Otherwise, the Username provided should be a fragment of a Relative Distinguished Name (rDN) (for example, the username hue maps to the rDN uid=hue). Hue will perform an LDAP search using the same methods and configurations as described above. That is, Hue will take the provided username and create a search filter using the user\_filter and user\_name\_attr configurations.
- Create home directory: If checked, when the user is imported, their home directory in HDFS will automatically be created if it doesn't already exist.

Important: When managing LDAP entries, the User Admin app will always perform an LDAP search and will always use bind\_dn, bind\_password, base\_dn, as defined in hue.ini.

### Synchronizing LDAP Users and Groups

Users and groups can be synchronized with the directory service via the User Admin interface or via a command line utility. The image from the Importing LDAP Users and Groups section uses the words Add/Sync to indicate that when a user or group that already exists in Hue is being added, it will in fact be synchronized instead. In the case of importing users for a particular group, new users will be imported and existing users will be synchronized.

Note: Users that have been deleted from the directory service will not be deleted from Hue. Those users can be manually deactivated from Hue via the User Admin interface.

### Attributes Synchronized

Currently, only the first name, last name, and email address are synchronized. Hue looks for the LDAP attributes givenName, sn, and mail when synchronizing. The user\_name\_attr configuration property is used to appropriately choose the username in Hue. For instance, if user\_name\_attr' is set to uid", then the "uid" returned by the directory service will be used as the username of the user in Hue.

#### User Admin interface

The Sync LDAP users/groups button in the User Admin interface will automatically synchronize all users and groups.

# Synchronize Using a Command-Line Interface

For example, to synchronize users and groups using a command-line interface:

<hue root>/build/env/bin/hue sync\_ldap\_users\_and\_groups

## LDAPS/StartTLS support

Secure communication with LDAP is provided using the SSL/TLS and StartTLS protocols. They allow Hue to validate the directory service it is going to converse with. Hence, if a Certificate Authority certificate file is provided, Hue will communicate using LDAPS. You can specify the path to the CA certificate under:

```
[desktop]
   [[ldap]]
    ldap_cert=/etc/hue/ca.crt
```

The StartTLS protocol can be used as well:

```
[desktop]
   [[ldap]]
   use_start_tls=true
```

## Configuring Hue for SAML

This section describes the configuration changes required to use Hue with SAML 2.0 (Security Assertion Markup Language) to enable single sign-on (SSO) authentication.

The <u>SAML 2.0 Web Browser SSO</u> profile has three components: a *Security Provider*, a *User Agent* and an *Identity* Provider. In this case, Hue is the Service Provider (SP), you can use an Identity Provider (IdP) of your choice, and you are the user acting through your browser (User Agent). When a user requests access to an application, Hue uses your browser to send an authentication request to the Identity Provider which then authenticates the user and redirects them back to Hue.

This blog post guides users through setting up SSO with Hue, using the SAML backend and Shibboleth as the Identity Provider.

Note: The following instructions assume you already have an Identity Provider set up and running.

## Step 1: Install swig and openssl packages

Install swig and openss1. For example, on RHEL systems, use the following commands:

```
yum install swig
yum install openssl
```

### Step 2: Install libraries to support SAML in Hue

Install the djangosam12 and pysam12 libraries to support SAML in Hue. These libraries are dependent on the xmlsec1 package to be installed and available on the machine for Hue to use. Follow these instructions to install the xmlsec1 package on your system.

### RHEL, CentOS and SLES:

For RHEL, CentOS and SLES systems, the xmlsec1 package is available for download from the EPEL repository. In order to install packages from the EPEL repository, first download the appropriate the rpm package to your machine, substituting the version in the package URL with the one required for your system. For example, use the following commands for CentOS 5 or RHEL 5:

```
rpm -Uvh http://download.fedoraproject.org/pub/epel/5/i386/epel-release-5-4.noarch.rpm
yum install xmlsec1
```

#### Oracle Linux:

For Oracle Linux systems, download the xmlsec1 package from http://www.aleksey.com/xmlsec/ and execute the following commands:

```
tar -xvzf xmlsec1-<version>.tar.gz
cd xmlsec1-<version>
./configure && make
sudo make install
```

**Important:** The xmlsec1 package must be executable by the user running Hue.

You should now be able to install djangosaml and pysam12 on your machines.

```
build/env/bin/pip install -e git+https://github.com/abec/pysaml2@HEAD#egg=pysaml2
build/env/bin/pip install -e git+https://github.com/abec/djangosaml2@HEAD#egg=djangosaml2
```

### Step 3: Update the Hue configuration file

Several configuration parameters need to be updated in Hue's configuration file, hue.ini to enable support for SAML. The table given below describes the available parameters for SAML in hue.ini under the [libsaml] section.

Parameter	Description
xmlsec_binary	This is a path to the xmlsec_binary, an executable used to sign, verify, encrypt and decrypt SAML requests and assertions. This program should be executable by the user running Hue.
create_users_on_login	Create Hue users received in assertion response upon successful login. The value for this parameter can be either "true" or "false".

Parameter	Description
required_attributes	Attributes Hue asks for from the IdP. This is a comma-separated list of attributes. For example, uid, email and so on.
optional_attributes	Optional attributes Hue can ask for from the IdP. Also a comma-separated list of attributes.
metadata_file	This is a path to the IdP metadata copied to a local file. This file should be readable.
key_file	Path to the private key used to encrypt the metadata. File format .PEM
cert_file	Path to the X.509 certificate to be sent along with the encrypted metadata. File format .PEM
user_attribute_mapping	Mapping from attributes received from the IdP to the Hue's django user attributes. For example, {'uid':'username', 'email':email'}.
logout_requests_signed	Have Hue initiated logout requests be signed and provide a certificate.

### Step 3a: Update the SAML metadata file

Update the metadata file pointed to by your Hue configuration file, hue.ini. Check your IdP documentation for details on how to procure the XML metadata and paste it into the <metadata\_file\_name>.xml file at the location specified by the configuration parameter metadata\_file.

For example, if you were using the Shibboleth IdP, you would visit https://<IdPHOST>:8443/idp/shibboleth, copy the metadata content available there and paste it into the Hue metadata file.

#### Note:

You may have to edit the content copied over from your IdP's metadata file in case of missing fields such as port numbers (8443), from URLs that point to the IdP.

## Step 3b: Private key and certificate files

To enable Hue to communicate with the IdP, you will need to specify the location of a private key, for the, key\_file property, that can be used to sign requests sent to the IdP. You will also need to specify the location of the certificate file, for the cert\_pem property, which you will use to verify and decrypt messages from the IdP.

Note: The key and certificate files specified by the key\_file and cert\_file parameters must be .PEM files.

### Step 3c: Configure Hue to use SAML Backend

To enable SAML to allow user logins and create users, update the backend configuration property in hue.ini to use the SAML authentication backend. You will find the backend property in the [[auth]] sub-section under

```
backend=libsaml.backend.SAML2Backend
```

Here is an example configuration of the [libsaml] section from hue.ini.

```
xmlsec binary=/usr/local/bin/xmlsec1
create_users_on_login=true
metadata_file=/etc/hue/saml/metadata.xml
key_file=/etc/hue/saml/key.pem
cert_file=/etc/hue/saml/cert.pem
logout_requests_signed=true
```

### Step 4: Restart the Hue server

Use the following command to restart the Hue server.

sudo service hue restart

## Impala Authentication

Authentication is the mechanism to ensure that only specified hosts and users can connect to Impala. It also verifies that when clients connect to Impala, they are connected to a legitimate server. This feature prevents spoofing such as impersonation (setting up a phony client system with the same account and group names as a legitimate user) and *man-in-the-middle attacks* (intercepting application requests before they reach Impala and eavesdropping on sensitive information in the requests or the results).

Impala supports authentication using either Kerberos or LDAP.

Impala currently does not support application data wire encryption.

Note: Regardless of the authentication mechanism used, Impala always creates HDFS directories and data files owned by the same user (typically impala). To implement user-level access to different databases, tables, columns, partitions, and so on, use the Sentry authorization feature, as explained in Enabling Sentry Authorization for Impala on page 276.

Once you are finished setting up authentication, move on to authorization, which involves specifying what databases, tables, HDFS directories, and so on can be accessed by particular users when they connect through Impala. See Enabling Sentry Authorization for Impala on page 276 for details.

# **Enabling Kerberos Authentication for Impala**

Impala supports Kerberos authentication. For more information on enabling Kerberos authentication, see the topic on Configuring Hadoop Security in the CDH4 Security Guide or the CDH 5 Security Guide.

Impala currently does not support application data wire encryption.

When using Impala in a managed environment, Cloudera Manager automatically completes Kerberos configuration. In an unmanaged environment, create a Kerberos principal for each host running impalad or statestored. Cloudera recommends using a consistent format, such as impala/\_HOST@Your-Realm, but you can use any three-part Kerberos server principal.

In Impala 2.0 and later, user() returns the the full Kerberos principal string, such as user@example.com, in a Kerberized environment.

Note: Regardless of the authentication mechanism used, Impala always creates HDFS directories and data files owned by the same user (typically impala). To implement user-level access to different databases, tables, columns, partitions, and so on, use the Sentry authorization feature, as explained in Enabling Sentry Authorization for Impala on page 276.

An alternative form of authentication you can use is LDAP, described in Enabling LDAP Authentication for Impala on page 107.

### Requirements for Using Impala with Kerberos

On version 5 of Red Hat Enterprise Linux and comparable distributions, some additional setup is needed for the impala-shell interpreter to connect to a Kerberos-enabled Impala cluster:

sudo yum install python-devel openssl-devel python-pip sudo pip-python install ssl

### Important:

If you plan to use Impala in your cluster, you must configure your KDC to allow tickets to be renewed, and you must configure krb5. conf to request renewable tickets. Typically, you can do this by adding the max\_renewable\_life setting to your realm in kdc.conf, and by adding the renew\_lifetime parameter to the libdefaults section of krb5.conf. For more information about renewable tickets, see the Kerberos documentation.

Currently, you cannot use the resource management feature in CDH 5 on a cluster that has Kerberos authentication enabled.

Start all impalad and statestored daemons with the --principal and --keytab-file flags set to the principal and full path name of the keytab file containing the credentials for the principal.

Impala supports the Cloudera ODBC driver and the Kerberos interface provided. To use Kerberos through the ODBC driver, the host type must be set depending on the level of the ODBD driver:

- SecImpala for the ODBC 1.0 driver.
- SecBeeswax for the ODBC 1.2 driver.
- Blank for the ODBC 2.0 driver or higher, when connecting to a secure cluster.
- HS2NoSas1 for the ODBC 2.0 driver or higher, when connecting to a non-secure cluster.

To enable Kerberos in the Impala shell, start the impala-shell command using the -k flag.

To enable Impala to work with Kerberos security on your Hadoop cluster, make sure you perform the installation and configuration steps in Authentication in the CDH 5 Security Guide or the topic on Configuring Hadoop Security in the CDH4 Security Guide. Also note that when Kerberos security is enabled in Impala, a web browser that supports Kerberos HTTP SPNEGO is required to access the Impala web console (for example, Firefox, Internet Explorer, or Chrome).

If the NameNode, Secondary NameNode, DataNode, JobTracker, TaskTrackers, ResourceManager, NodeManagers, HttpFS, Oozie, Impala, or Impala statestore services are configured to use Kerberos HTTP SPNEGO authentication, and two or more of these services are running on the same host, then all of the running services must use the same HTTP principal and keytab file used for their HTTP endpoints.

## Configuring Impala to Support Kerberos Security

Enabling Kerberos authentication for Impala involves steps that can be summarized as follows:

- Creating service principals for Impala and the HTTP service. Principal names take the form: serviceName/fully.qualified.domain.name@KERBEROS.REALM
- Creating, merging, and distributing key tab files for these principals.
- Editing /etc/default/impala (in cluster not managed by Cloudera Manager), or editing the Security settings in the Cloudera Manager interface, to accommodate Kerberos authentication.

## Enabling Kerberos for Impala

1. Create an Impala service principal, specifying the name of the OS user that the Impala daemons run under, the fully qualified domain name of each node running impalad, and the realm name. For example:

```
kadmin: addprinc -requires_preauth -randkey
impala/impala_host.example.com@TEST.EXAMPLE.COM
```

**2.** Create an HTTP service principal. For example:

```
kadmin: addprinc -randkey HTTP/impala_host.example.com@TEST.EXAMPLE.COM
```

Note: The HTTP component of the service principal must be uppercase as shown in the preceding example.

**3.** Create keytab files with both principals. For example:

```
kadmin: xst -k impala.keytab impala/impala_host.example.com
| kadmin: xst -k http.keytab HTTP/impala_host.example.com
| kadmin: quit
```

4. Use ktutil to read the contents of the two keytab files and then write those contents to a new file. For example:

```
$ ktutil
ktutil: rkt impala.keytab
ktutil: rkt http.keytab
ktutil: wkt impala-http.keytab
ktutil: quit
```

**5.** (Optional) Test that credentials in the merged keytab file are valid, and that the "renew until" date is in the future. For example:

```
$ klist -e -k -t impala-http.keytab
```

6. Copy the impala-http.keytab file to the Impala configuration directory. Change the permissions to be only read for the file owner and change the file owner to the impala user. By default, the Impala user and group are both named impala. For example:

```
$ cp impala-http.keytab /etc/impala/conf
$ cd /etc/impala/conf
$ chmod 400 impala-http.keytab
$ chown impala:impala impala-http.keytab
```

7. Add Kerberos options to the Impala defaults file, /etc/default/impala. Add the options for both the impalad and statestored daemons, using the IMPALA\_SERVER\_ARGS and IMPALA\_STATE\_STORE\_ARGS variables. For example, you might add:

```
-kerberos_reinit_interval=60
-principal=impala_1/impala_host.example.com@TEST.EXAMPLE.COM
-keytab_file=/var/run/cloudera-scm-agent/process/3212-impala-IMPALAD/impala.keytab
```

For more information on changing the Impala defaults specified in /etc/default/impala, see Modifying Impala Startup Options.

• Note: Restart impalad and statestored for these configuration changes to take effect.

#### Enabling Kerberos for Impala with a Proxy Server

A common configuration for Impala with High Availability is to use a proxy server to submit requests to the actual impalad daemons on different hosts in the cluster. This configuration avoids connection problems in case of machine failure, because the proxy server can route new requests through one of the remaining hosts in the cluster. This configuration also helps with load balancing, because the additional overhead of being the "coordinator node" for each query is spread across multiple hosts.

Although you can set up a proxy server with or without Kerberos authentication, typically users set up a secure Kerberized configuration. For information about setting up a proxy server for Impala, including Kerberos-specific steps, see <u>Using Impala through a Proxy for High Availability</u>.

### Using a Web Browser to Access a URL Protected by Kerberos HTTP SPNEGO

Your web browser must support Kerberos HTTP SPNEGO. For example, Chrome, Firefox, or Internet Explorer.

# To configure Firefox to access a URL protected by Kerberos HTTP SPNEGO:

- 1. Open the advanced settings Firefox configuration page by loading the about:config page.
- 2. Use the Filter text box to find network.negotiate-auth.trusted-uris.

- 3. Double-click the network.negotiate-auth.trusted-uris preference and enter the hostname or the domain of the web server that is protected by Kerberos HTTP SPNEGO. Separate multiple domains and hostnames with a comma.
- 4. Click OK.

# Enabling LDAP Authentication for Impala

Authentication is the process of allowing only specified named users to access the server (in this case, the Impala server). This feature is crucial for any production deployment, to prevent misuse, tampering, or excessive load on the server. Impala users LDAP for authentication, verifying the credentials of each user who connects through impala-shell, Hue, a Business Intelligence tool, JDBC or ODBC application, and so on.

Note: Regardless of the authentication mechanism used, Impala always creates HDFS directories and data files owned by the same user (typically impala). To implement user-level access to different databases, tables, columns, partitions, and so on, use the Sentry authorization feature, as explained in Enabling Sentry Authorization for Impala on page 276.

An alternative form of authentication you can use is Kerberos, described in **Enabling Kerberos Authentication** for Impala on page 104.

## Requirements for Using Impala with LDAP

Authentication against LDAP servers is available in Impala 1.2.2 and higher. Impala 1.4.0 adds support for secure LDAP authentication through SSL and TLS.

The Impala LDAP support lets you use Impala with systems such as Active Directory that use LDAP behind the scenes.

#### Client-Server Considerations for LDAP

Only client->Impala connections can be authenticated by LDAP.

You must Kerberos authentication mechanism for connections between internal Impala components, such as between the impalad, statestored, and catalogd daemons. See Enabling Kerberos Authentication for Impala on page 104 for how to set up Kerberos for Impala.

### Server-Side LDAP Setup

These requirements apply on the server side when configuring and starting Impala:

To enable LDAP authentication, set the following startup options for impalad:

- --enable\_ldap\_auth enables LDAP-based authentication between the client and Impala.
- --ldap\_uri sets the URI of the LDAP server to use. Typically, the URI is prefixed with ldap: //. In Impala 1.4.0 and higher, you can specify secure SSL-based LDAP transport by using the prefix ldaps://. The URI can optionally specify the port, for example: ldap://ldap\_server.cloudera.com: 389 or ldaps://ldap\_server.cloudera.com:636.(389 and 636 are the default ports for non-SSL and SSL LDAP connections, respectively.)
- For ldaps://connections secured by SSL, --ldap\_ca\_certificate="/path/to/certificate/pem" specifies the location of the certificate in standard . PEM format. Store this certificate on the local filesystem, in a location that only the impala user and other trusted users can read.

### Support for Custom Bind Strings

When Impala connects to LDAP it issues a bind call to the LDAP server to authenticate as the connected user. Impala clients, including the Impala shell, provide the short name of the user to Impala. This is necessary so that Impala can use Sentry for role-based access, which uses short names.

However, LDAP servers often require more complex, structured usernames for authentication. Impala supports three ways of transforming the short name (for example, 'henry') to a more complicated string. If necessary, specify one of the following configuration options when starting the impalad daemon on each data node:

• --ldap\_domain: Replaces the username with a string username@ldap\_domain.

- --ldap\_baseDN: Replaces the username with a "distinguished name" (DN) of the form: uid=userid,ldap\_baseDN. (This is equivalent to a Hive option).
- --ldap\_bind\_pattern: This is the most general option, and replaces the username with the string ldap\_bind\_pattern where all instances of the string #UID are replaced with userid. For example, an ldap\_bind\_pattern Of "user=#UID,OU=foo,CN=bar" with a username of henry will construct a bind name of "user=henry,OU=foo,CN=bar".

For clusters not managed by Cloudera Manager, specify the option on the impalad command line. For clusters managed by Cloudera Manager 5.4.0 and higher, search for the configuration field names ldap\_domain, ldap\_basedn, or ldap\_bind\_pattern, fill in and save the appropriate field values, and restart the Impala service. Prior to Cloudera Manager 5.4.0, these values were filled in using the Impala Daemon Command Line Argument Advanced Configuration Snippet (Safety Valve) field.

These options are mutually exclusive; Impala does not start if more than one of these options is specified.

### Secure LDAP Connections

To avoid sending credentials over the wire in cleartext, you must configure a secure connection between both the client and Impala, and between Impala and the LDAP server. The secure connection could use SSL or TLS.

### Secure LDAP connections through SSL:

For SSL-enabled LDAP connections, specify a prefix of ldaps://instead of ldap://. Also, the default port for SSL-enabled LDAP connections is 636 instead of 389.

### Secure LDAP connections through TLS:

TLS, the successor to the SSL protocol, is supported by most modern LDAP servers. Unlike SSL connections, TLS connections can be made on the same server port as non-TLS connections. To secure all connections using TLS, specify the following flags as startup options to the impalad daemon:

- --ldap\_tls tells Impala to start a TLS connection to the LDAP server, and to fail authentication if it cannot be done.
- --ldap\_ca\_certificate="/path/to/certificate/pem" specifies the location of the certificate in standard
   . PEM format. Store this certificate on the local filesystem, in a location that only the impala user and other trusted users can read.

### LDAP Authentication for impala-shell Interpreter

To connect to Impala using LDAP authentication, you specify command-line options to the impala-shell command interpreter and enter the password when prompted:

- -1 enables LDAP authentication.
- -u sets the user. Per Active Directory, the user is the short user name, not the full LDAP distinguished name.
   If your LDAP settings include a search base, use the --ldap\_bind\_pattern on the impalad daemon to translate the short user name from impala-shell automatically to the fully qualified name.
- impala-shell automatically prompts for the password.

For the full list of available impala-shell options, see impala-shell Configuration Options.

**LDAP authentication for JDBC applications:** See <u>Configuring Impala to Work with JDBC</u> for the format to use with the JDBC connection string for servers using LDAP authentication.

### LDAP Restrictions for Impala

The LDAP support is preliminary. It currently has only been tested against Active Directory.

# Using Multiple Authentication Methods with Impala

Impala 2.0 and later automatically handles both Kerberos and LDAP authentication. Each impalad daemon can accept both Kerberos and LDAP requests through the same port. No special actions need to be taken if some users authenticate through Kerberos and some through LDAP.

Prior to Impala 2.0, you had to configure each impalad to listen on a specific port depending on the kind of authentication, then configure your network load balancer to forward each kind of request to a data node that

was set up with the appropriate authentication type. Once the initial request was made using either Kerberos or LDAP authentication, Impala automatically handled the process of coordinating the work across multiple nodes and transmitting intermediate results back to the coordinator node.

#### Llama Authentication

This section describes how to configure Llama in CDH 5 with Kerberos security in a Hadoop cluster.

Note: Llama has been tested only in a Cloudera Manager deployment. For information on using Cloudera Manager to configure Llama and Impala, see Installing Impala.

## Configuring Llama to Support Kerberos Security

1. Create a Llama service user principal using the syntax: llama/fully.qualified.domain.name@YOUR-REALM. This principal is used to authenticate with the Hadoop cluster, where fully qualified domain name is the host where Llama is running and YOUR-REALM is the name of your Kerberos realm:

```
$ kadmin
kadmin: addprinc -randkey
llama/fully.qualified.domain.name@YOUR-REALM
```

**2.** Create a keytab file with the Llama principal:

```
$ kadmin
kadmin: xst -k llama.keytab llama/fully.qualified.domain.name
```

**3.** Test that the credentials in the keytab file work. For example:

```
$ klist -e -k -t llama.keytab
```

- 4. Copy the llama.keytab file to the Llama configuration directory. The owner of the llama.keytab file should be the llama user and the file should have owner-only read permissions.
- 5. Edit the Llama 11ama-site.xml configuration file in the Llama configuration directory by setting the following properties:

Property	Value
llama.am.server.thrift.security	true
llama.am.server.thrift.kerberos.keytab.file	llama/conf.keytab
llama.am.server.thrift.kerberos.server.principal.name	llama/fully.qualified.domain.name
llama.am.server.thrift.kerberos.notification.principal.name	impala

6. Restart Llama to make the configuration changes take effect.

#### Oozie Authentication

This section describes how to configure Oozie CDH 5 with Kerberos security on a Hadoop cluster:

- Configuring the Oozie Server to Support Kerberos Security on page 110
- Configuring Oozie HA with Kerberos on page 111
  - Important:

To enable Oozie to work with Kerberos security on your Hadoop cluster, make sure you perform the installation and configuration steps in Configuring Hadoop Security in CDH 5. Also note that when Kerberos security is enabled in Oozie, a web browser that supports Kerberos HTTP SPNEGO is required to access the Oozie web-console (for example, Firefox, Internet Explorer or Chrome).

#### Important:

If the NameNode, Secondary NameNode, DataNode, JobTracker, TaskTrackers, ResourceManager, NodeManagers, HttpFS, or Oozie services are configured to use Kerberos HTTP SPNEGO authentication, and two or more of these services are running on the same host, then all of the running services must use the same HTTP principal and keytab file used for their HTTP endpoints.

## Configuring the Oozie Server to Support Kerberos Security

1. Create a Oozie service user principal using the syntax:

oozie/<fully.qualified.domain.name>@<YOUR-REALM>. This principal is used to authenticate with the

Hadoop cluster, where: fully.qualified.domain.name is the host where the Oozie server is running

Hadoop cluster. where: fully.qualified.domain.name is the host where the Oozie server is running YOUR-REALM is the name of your Kerberos realm.

```
kadmin: addprinc -randkey oozie/fully.qualified.domain.name@YOUR-REALM.COM
```

2. Create a HTTP service user principal using the syntax:

HTTP/<fully.qualified.domain.name>@<YOUR-REALM>. This principal is used to authenticate user requests coming to the Oozie web-services. where: fully.qualified.domain.name is the host where the Oozie server is running YOUR-REALM is the name of your Kerberos realm.

```
kadmin: addprinc -randkey HTTP/fully.qualified.domain.name@YOUR-REALM.COM
```

Important:

The HTTP/ component of the HTTP service user principal must be upper case as shown in the syntax and example above.

**3.** Create keytab files with both principals.

```
$ kadmin
kadmin: xst -k oozie.keytab oozie/fully.qualified.domain.name
kadmin: xst -k http.keytab HTTP/fully.qualified.domain.name
```

**4.** Merge the two keytab files into a single keytab file:

```
$ ktutil
ktutil: rkt oozie.keytab
ktutil: rkt http.keytab
ktutil: wkt oozie-http.keytab
```

**5.** Test that credentials in the merged keytab file work. For example:

```
$ klist -e -k -t oozie-http.keytab
```

- **6.** Copy the <code>oozie-http.keytab</code> file to the Oozie configuration directory. The owner of the <code>oozie-http.keytab</code> file should be the <code>oozie</code> user and the file should have owner-only read permissions.
- 7. Edit the Oozie server <code>oozie-site.xml</code> configuration file in the Oozie configuration directory by setting the following properties:
  - Important: You must restart the Oozie server to have the configuration changes take effect.

Property	Value
oozie.service.HadoopAccessorService.kerberos.enabled	true
local.realm	<realm></realm>

Property	Value
oozie.service.HadoopAccessorService.keytab.file	/etc/oozie/conf/oozie-http.keytabfora package installation, or <expanded_dir>/conf/oozie-http.keytabfora tarball installation</expanded_dir>
oozie.service.HadoopAccessorService.kerberos.principal	oozie/ <fully.qualified.domain.name>@<your-realm.com></your-realm.com></fully.qualified.domain.name>
oozie.authentication.type	kerberos
oozie.authentication.kerberos.principal	HTTP/ <fully.qualified.domain.name>@<your-realm.com></your-realm.com></fully.qualified.domain.name>
oozie.authentication.kerberos.name.rules	Use the value configured for hadoop.security.auth_to_local in core-site.xml

## Configuring Oozie HA with Kerberos

In CDH 5, you can configure multiple active Oozie servers against the same database, providing high availability for Oozie. For instructions on setting up Oozie HA, see Oozie High Availability

Let's assume you have three hosts running Oozie servers, host1.example.com, host2.example.com, host3.example.com and the Load Balancer running on oozie.example.com. The Load Balancer directs traffic to the Oozie servers: host1, host2 and host3. For such a configuration, assuming your Kerberos realm is EXAMPLE. COM, create the following Kerberos principals:

- oozie/host1.example.com@EXAMPLE.COM
- oozie/host2.example.com@EXAMPLE.COM
- oozie/host3.example.com@EXAMPLE.COM
- HTTP/host1.example.com@EXAMPLE.COM
- HTTP/host2.example.com@EXAMPLE.COM
- HTTP/host3.example.com@EXAMPLE.COM
- HTTP/oozie.example.com@EXAMPLE.COM

On each of the hosts, host1, host2 and host3, create a keytab file with its corresponding oozie and HTTP principals from the list above. All keytab files should also have the load balancer's HTTP principal. Hence, each keytab file should have 3 principals in all.

Edit the following property in the Oozie server configuration file, oozie-site.xml:

```
property>
<name>oozie.authentication.kerberos.principal
<value>*</value>
</property>
```

## Search Authentication

This section describes how to configure Search in CDH 5 to enable Kerberos security and Sentry.

## Configuring Search to Use Kerberos

Cloudera Search supports Kerberos authentication. All necessary packages are installed when you install Search. To enable Kerberos, create principals and keytabs and then modify default configurations.

The following instructions only apply to configuring Kerberos in an unmanaged environment. Kerberos configuration is automatically handled by Cloudera Manager if you are using Search in a Cloudera Manager environment.

#### To create principals and keytabs

Repeat this process on all Solr server hosts.

1. Create a Solr service user principal using the syntax: solr/<fully.qualified.domain.name>@<YOUR-REALM>. This principal is used to authenticate with the Hadoop cluster. where: fully.qualified.domain.name is the host where the Solr server is running YOUR-REALM is the name of your Kerberos realm.

```
$ kadmin
kadmin: addprinc -randkey solr/fully.qualified.domain.name@YOUR-REALM.COM
```

2. Create a HTTP service user principal using the syntax:

HTTP/<fully.qualified.domain.name>@<YOUR-REALM>. This principal is used to authenticate user requests coming to the Solr web-services. where: fully.qualified.domain.name is the host where the Solr server is running YOUR-REALM is the name of your Kerberos realm.

kadmin: addprinc -randkey HTTP/fully.qualified.domain.name@YOUR-REALM.COM

Note:

The HTTP/ component of the HTTP service user principal must be upper case as shown in the syntax and example above.

3. Create keytab files with both principals.

**4.** Test that credentials in the merged keytab file work. For example:

```
$ klist -e -k -t solr.keytab
```

**5.** Copy the solr.keytab file to the Solr configuration directory. The owner of the solr.keytab file should be the solr user and the file should have owner-only read permissions.

#### To modify default configurations

Repeat this process on all Solr server hosts.

1. Ensure that the following properties appear in /etc/default/solr or /opt/cloudera/parcels/CDH-\*/etc/default/solr and that they are uncommented. Modify these properties to match your environment. The relevant properties to be uncommented and modified are:

```
SOLR_AUTHENTICATION_TYPE=kerberos
SOLR_AUTHENTICATION_SIMPLE_ALLOW_ANON=true
SOLR_AUTHENTICATION_KERBEROS_KEYTAB=/etc/solr/conf/solr.keytab
SOLR_AUTHENTICATION_KERBEROS_PRINCIPAL=HTTP/localhost@LOCALHOST
SOLR_AUTHENTICATION_KERBEROS_NAME_RULES=DEFAULT
SOLR_AUTHENTICATION_JAAS_CONF=/etc/solr/conf/jaas.conf
```

- Note: Modify the values for these properties to match your environment. For example, the SOLR\_AUTHENTICATION\_KERBEROS\_PRINCIPAL=HTTP/localhost@LOCALHOST must include the principal instance and Kerberos realm for your environment. That is often different from localhost@LOCALHOST.
- 2. Set hadoop.security.auth\_to\_local to match the value specified by SOLR\_AUTHENTICATION\_KERBEROS\_NAME\_RULES in /etc/default/solr or /opt/cloudera/parcels/CDH-\*/etc/default/solr.
  - Note: For information on how to configure the rules, see <u>Configuring the Mapping from Kerberos</u> <u>Principals to Short Names</u> on page 120. For additional information on using Solr with HDFS, see <u>Configuring Solr for Use with HDFS</u>.
- 3. If using applications that use the solrj library, set up the Java Authentication and Authorization Service (JAAS).

a. Create a jaas conf file in the Solr configuration directory containing the following settings. This file and its location must match the SOLR\_AUTHENTICATION\_JAAS\_CONF value. Make sure that you substitute a value for principal that matches your particular environment.

```
com.sun.security.auth.module.Krb5LoginModule required
useKeyTab=true
useTicketCache=false
keyTab="/etc/solr/conf/solr.keytab"
principal="solr/fully.qualified.domain.name@<YOUR-REALM>";
```

## Using Kerberos

The process of enabling Solr clients to authenticate with a secure Solr is specific to the client. This section demonstrates:

- Using Kerberos and curl
- Using solrctl
- Configuring SolrJ Library Usage.

This enables technologies including:

- Command line solutions
- Java applications
- The MapReduceIndexerTool
- Configuring Flume Morphline Solr Sink Usage

Secure Solr requires that the CDH components that it interacts with are also secure. Secure Solr interacts with HDFS, ZooKeeper and optionally HBase, MapReduce, and Flume. See Cloudera Security or the CDH 4 Security Guide for more information.

#### Using Kerberos and curl

You can use Kerberos authentication with clients such as curl. To use curl, begin by acquiring valid Kerberos credentials and then execute the desired command. For example, you might use commands similar to the following:

```
$ kinit -kt username.keytab username
$ curl --negotiate -u foo:bar http://solrserver:8983/solr/
```

Note: Depending on the tool used to connect, additional arguments may be required. For example, with curl, --negotiate and -u are required. The username and password specified with -u is not actually checked because Kerberos is used. As a result, any value such as foo:bar or even just: is acceptable. While any value can be provided for -u, note that the option is required. Omitting -u results in a 401 Unauthorized error, even though the -u value is not actually used.

#### Using solrctl

If you are using solrctl to manage your deployment in an environment that requires Kerberos authentication, you must have valid Kerberos credentials, which you can get using kinit. For more information on solrctl, see Solrctl Reference

## Configuring SolrJ Library Usage

If using applications that use the solrj library, begin by establishing a Java Authentication and Authorization Service (JAAS) configuration file.

#### Create a JAAS file:

• If you have already used kinit to get credentials, you can have the client use those credentials. In such a case, modify your jaas-client.conf file to appear as follows:

```
Client {
  com.sun.security.auth.module.Krb5LoginModule required
  useKeyTab=false
  useTicketCache=true
  principal="user/fully.qualified.domain.name@<YOUR-REALM>";
  };
```

where user/fully.qualified.domain.name@<YOUR-REALM> is replaced with your credentials.

• You want the client application to authenticate using a keytab you specify:

```
Client {
  com.sum.security.auth.module.Krb5LoginModule required
  useKeyTab=true
  keyTab="/path/to/keytab/user.keytab"
  storeKey=true
  useTicketCache=false
  principal="user/fully.qualified.domain.name@<YOUR-REALM>";
  };
```

where /path/to/keytab/user.keytab is the keytab file you wish to use and user/fully.qualified.domain.name@<YOUR-REALM> is the principal in that keytab you wish to use.

#### Use the JAAS file to enable solutions:

#### Command line solutions

Set the property when invoking the program. For example, if you were using a jar, you might use:

```
java -Djava.security.auth.login.config=/home/user/jaas-client.conf -jar app.jar
```

## Java applications

Set the Java system property java.security.auth.login.config. For example, if the JAAS configuration file is located on the filesystem as /home/user/jaas-client.conf. The Java system property java.security.auth.login.config must be set to point to this file. Setting a Java system property can be done programmatically, for example using a call such as:

```
System.setProperty("java.security.auth.login.config",
"/home/user/jaas-client.conf");
```

#### The MapReduceIndexerTool

The MapReduceIndexerTool uses SolrJ to pass the JAAS configuration file. Using the MapReduceIndexerTool in a secure environment requires the use of the HADOOP\_OPTS variable to specify the JAAS configuration file. For example, you might issue a command such as the following:

```
HADOOP_OPTS="-Djava.security.auth.login.config=/home/user/jaas.conf" \ hadoop jar MapReduceIndexerTool
```

#### Configuring the hbase-indexer CLI

Certain hbase-indexer CLI commands such as replication-status attempt to read ZooKeeper hosts owned by HBase. To successfully use these commands in Search for CDH 5 in a secure environment, specify a JAAS configuration file with the HBase principal in the HBASE\_INDEXER\_OPTS environment variable. For example, you might issue a command such as the following:

```
HBASE_INDEXER_OPTS="-Djava.security.auth.login.config=/home/user/hbase-jaas.conf"
\
hbase-indexer replication-status
```

#### Configuring Flume Morphline Solr Sink Usage

Repeat this process on all Flume hosts:

- 1. If you have not created a keytab file, do so now at /etc/flume-ng/conf/flume.keytab. This file should contain the service principal flume/<fully.qualified.domain.name>@<YOUR-REALM>. See the CDH 5 Security Guide for more information.
- 2. Create a JAAS configuration file for flume at /etc/flume-ng/conf/jaas-client.conf. The file should appear as follows:

```
Client {
com.sun.security.auth.module.Krb5LoginModule required
useKeyTab=true
useTicketCache=false
keyTab="/etc/flume-ng/conf/flume.keytab"
principal="flume/<fully.qualified.domain.name>@<YOUR-REALM>";
```

3. Add the flume JAAS configuration to the JAVA\_OPTS in /etc/flume-ng/conf/flume-env.sh. For example, you might change:

```
JAVA_OPTS="-Xmx500m"
to:
```

```
JAVA_OPTS="-Xmx500m
-Djava.security.auth.login.config=/etc/flume-ng/conf/jaas-client.conf"
```

## Spark Authentication

- Important:
  - If you want to enable Spark event logging on a Kerberos-enabled cluster, you will need to enable Kerberos authentication for Spark as well, since Spark's event logs are written to HDFS.
  - You can use Spark on a Kerberos-enabled cluster only in the YARN mode, not in the Standalone mode.

This topic describes how to set up Kerberos authentication for Spark using the command line.

## Create the Spark Principal and Keytab File

1. Create the spark principal and spark.keytab file:

```
kadmin: addprinc -randkey spark/fully.qualified.domain.name@YOUR-REALM.COM
kadmin: xst -k spark.keytab spark/fully.qualified.domain.name
```

Move the file into the Spark configuration directory and restrict its access exclusively to the spark user:

```
$ mv spark.keytab /etc/spark/conf/
$ chown spark /etc/spark/conf/spark.keytab
$ chmod 400 /etc/spark/conf/spark.keytab
```

For more details on creating Kerberos principals and keytabs, see <a href="Step 4">Step 4</a>: Create and Deploy the Kerberos Principals and Keytab Files on page 56.

## Configure the Spark History Server to Use Kerberos

Open the Spark configuration file /etc/spark/conf/spark-env.sh file and add the following properties:

```
SPARK_HISTORY_OPTS=-Dspark.history.kerberos.enabled=true \
-Dspark.history.kerberos.principal=spark/fully.qualified.domain.name@YOUR-REALM.COM \
-Dspark.history.kerberos.keytab=/etc/spark/conf/spark.keytab
```

## Sgoop Authentication

This section describes how to configure Sqoop2 with Kerberos security in a Hadoop cluster:

## Create the Sqoop 2 Principal and Keytab File

You need to create a sqoop2. keytab file for Sqoop2. Follow these steps:

1. Create the principal and keytab file:

```
kadmin: addprinc -randkey sqoop2/fully.qualified.domain.name@YOUR-REALM.COM
kadmin: xst -k sqoop2.keytab sqoop2/fully.qualified.domain.name
```

2. Move the file into the Sqoop configuration directory and restrict its access exclusively to the sqoop2 user:

```
$ mv sqoop2.keytab /etc/sqoop2/conf/
$ chown sqoop2 /etc/sqoop2/conf/sqoop2.keytab
$ chmod 400 /etc/sqoop2/conf/sqoop2.keytab
```

For more details on creating Kerberos principals and keytabs, see <u>Step 4: Create and Deploy the Kerberos Principals and Keytab Files</u> on page 56.

## Configure Sqoop2 to Use Kerberos

Edit the Sqoop2 configuration file sqoop.properties file in the /etc/sqoop2/conf directory and add the following properties:

```
org.apache.sqoop.authentication.type=KERBEROS org.apache.sqoop.authentication.handler=org.apache.sqoop.security.KerberosAuthenticationHandler org.apache.sqoop.authentication.kerberos.principal=sqoop2/fully.qualified.domain.name@YOUR-REALM.COM org.apache.sqoop.authentication.kerberos.keytab=/etc/sqoop2/conf/sqoop2.keytab
```

#### ZooKeeper Authentication

This section describes how to configure ZooKeeper in CDH 5 to enable Kerberos security:

- Configuring the ZooKeeper Server to Support Kerberos Security on page 116
- Configuring the ZooKeeper Client Shell to Support Kerberos Security on page 117
- Verifying the Configuration on page 118
  - Important:

Prior to enabling ZooKeeper to work with Kerberos security on your cluster, make sure you first review the requirements in <u>Configuring Hadoop Security in CDH 5</u>.

## Configuring the ZooKeeper Server to Support Kerberos Security

Note:

It is strongly recommended that you ensure a properly functioning ZooKeeper ensemble prior to enabling security. See <u>ZooKeeper Installation</u>.

1. Create a service principal for the ZooKeeper server using the syntax: zookeeper/<fully.qualified.domain.name>@<YOUR-REALM>. This principal is used to authenticate the ZooKeeper server with the Hadoop cluster, where: fully, qualified.domain.name is the host where the ZooKeeper server is running YOUR-REALM is the name of your Kerberos realm.

```
kadmin: addprinc -randkey zookeeper/fully.qualified.domain.name@YOUR-REALM.COM
```

**2.** Create a keytab file for the ZooKeeper server.

```
$ kadmin
kadmin: xst -k zookeeper.keytab zookeeper/fully.qualified.domain.name
```

- 3. Copy the zookeeper.keytab file to the ZooKeeper configuration directory on the ZooKeeper server host. For a package installation, the ZooKeeper configuration directory is /etc/zookeeper/conf/. For a tar ball installation, the ZooKeeper configuration directory is <EXPANDED\_DIR>/conf. The owner of the zookeeper.keytab file should be the zookeeper user and the file should have owner-only read permissions.
- 4. Add the following lines to the ZooKeeper configuration file zoo.cfg:

```
authProvider.1=org.apache.zookeeper.server.auth.SASLAuthenticationProvider
jaasLoginRenew=3600000
```

5. Set up the Java Authentication and Authorization Service (JAAS) by creating a jass.conf file in the ZooKeeper configuration directory containing the following settings. Make sure that you substitute fully.qualified.domain.name as appropriate.

```
com.sun.security.auth.module.Krb5LoginModule required
useKeyTab=true
keyTab="/etc/zookeeper/conf/zookeeper.keytab"
storeKey=true
useTicketCache=false
principal="zookeeper/fully.qualified.domain.name@<YOUR-REALM>";
```

6. Add the following setting to the java. env file located in the ZooKeeper configuration directory. (Create the file if it does not already exist.)

```
export JVMFLAGS="-Djava.security.auth.login.config=/etc/zookeeper/conf/jaas.conf"
```

- 7. If you have multiple ZooKeeper servers in the ensemble, repeat steps 1 through 6 above for each ZooKeeper server. When you create each new Zookeeper Server keytab file in step 2, you can overwrite the previous keytab file and use the same name (zookeeper.keytab) to maintain consistency across the ZooKeeper servers in the ensemble. The difference in the keytab files will be the hostname where each server is running.
- 8. Restart the ZooKeeper server to have the configuration changes take effect. For instructions, see ZooKeeper

## Configuring the ZooKeeper Client Shell to Support Kerberos Security

1. If you want to use the ZooKeeper client shell zookeeper-client with Kerberos authentication, create a principal using the syntax: zkcli@<YOUR-REALM>. This principal is used to authenticate the ZooKeeper client shell to the ZooKeeper service, where: YOUR-REALM is the name of your Kerberos realm.

```
kadmin: addprinc -randkey zkcli@YOUR-REALM.COM
```

**2.** Create a keytab file for the ZooKeeper client shell.

```
$ kadmin
kadmin: xst -norandkey -k zkcli.keytab zkcli@YOUR-REALM.COM
```

Note:

Some versions of kadmin do not support the <code>-norandkey</code> option in the command above. If your version does not, you can omit it from the command. Note that doing so will result in a new password being generated every time you export a keytab, which will invalidate previously-exported keytabs.

**3.** Set up JAAS in the configuration directory on the host where the ZooKeeper client shell is running. For a package installation, the configuration directory is /etc/zookeeper/conf/. For a tar ball installation, the configuration directory is <EXPANDED\_DIR>/conf. Create a jaas.conf file containing the following settings:

```
Client {
   com.sun.security.auth.module.Krb5LoginModule required
   useKeyTab=true
   keyTab="/path/to/zkcli.keytab"
   storeKey=true
   useTicketCache=false
   principal="zkcli@<YOUR-REALM>";
};
```

4. Add the following setting to the java.env file located in the configuration directory. (Create the file if it does not already exist.)

```
export JVMFLAGS="-Djava.security.auth.login.config=/etc/zookeeper/conf/jaas.conf"
```

## Verifying the Configuration

- 1. Make sure that you have restarted the ZooKeeper cluster with Kerberos enabled, as described above.
- 2. Start the client (where the hostname is the name of a ZooKeeper server):

```
zookeeper-client -server hostname:port
```

**3.** Create a protected znode from within the ZooKeeper CLI. Make sure that you substitute YOUR-REALM as appropriate.

```
create /znode1 znode1data sas1:zkcli@{{YOUR-REALM}}:cdwra
```

**4.** Verify the znode is created and the ACL is set correctly:

```
getAcl /znode1
```

The results from getAcl should show that the proper scheme and permissions were applied to the znode.

## **FUSE Kerberos Configuration**

This section describes how to use <u>FUSE</u> (Filesystem in Userspace) and CDH with Kerberos security on your Hadoop cluster. FUSE enables you to mount HDFS, which makes HDFS files accessible just as if they were UNIX files.

## To use FUSE and CDH with Kerberos security, follow these guidelines:

- For each HDFS user, make sure that there is a UNIX user with the same name. If there isn't, some files in the FUSE mount point will appear to be owned by a non-existent user. Although this is harmless, it can cause confusion.
- When using Kerberos authentication, users must run kinit before accessing the FUSE mount point. Failure to do this will result in I/O errors when the user attempts to access the mount point. For security reasons, it is not possible to list the files in the mount point without first running kinit.

• When a user runs kinit, all processes that run as that user can use the Kerberos credentials. It is not necessary to run kinit in the same shell as the process accessing the FUSE mount point.

## Using kadmin to Create Kerberos Keytab Files

If your version of Kerberos does not support the Kerberos -norandkey option in the xst command, or if you must use kadmin because you cannot use kadmin.local, then you can use the following procedure to create Kerberos keytab files. Using the -norandkey option when creating keytabs is optional and a convenience, but it is not required.

Important:

For both MRv1 and YARN deployments: On every machine in your cluster, there must be a keytab file for the hdfs user and a keytab file for the mapred user. The hdfs keytab file must contain entries for the hdfs principal and an HTTP principal, and the mapred keytab file must contain entries for the mapred principal and an HTTP principal. On each respective machine, the HTTP principal will be the same in both keytab files.

In addition, for YARN deployments only: On every machine in your cluster, there must be a keytab file for the yarn user. The yarn keytab file must contain entries for the yarn principal and an HTTP principal. On each respective machine, the HTTP principal in the yarn keytab file will be the same as the HTTP principal in the hdfs and mapred keytab files.

For instructions, see To create the Kerberos keytab files on page 119.

Note:

These instructions illustrate an example of creating keytab files for MIT Kerberos. If you are using another version of Kerberos, refer to your Kerberos documentation for instructions. You can use either kadmin or kadmin, local to run these commands.

## To create the Kerberos keytab files

Do the following steps for every host in your cluster, replacing the fully.qualified.domain.name in the commands with the fully qualified domain name of each host:

1. Create the hdfs keytab file, which contains an entry for the hdfs principal. This keytab file is used for the NameNode, Secondary NameNode, and DataNodes.

```
$ kadmin
kadmin: xst -k hdfs-unmerged.keytab hdfs/fully.qualified.domain.name
```

2. Create the mapred keytab file, which contains an entry for the mapred principal. If you are using MRv1, the mapred keytab file is used for the JobTracker and TaskTrackers. If you are using YARN, the mapred keytab file is used for the MapReduce Job History Server.

```
kadmin: xst -k mapred-unmerged.keytab mapred/fully.qualified.domain.name
             ______
```

3. YARN only: Create the yarn keytab file, which contains an entry for the yarn principal. This keytab file is used for the ResourceManager and NodeManager.

```
kadmin: xst -k yarn-unmerged.keytab yarn/fully.qualified.domain.name
```

4. Create the http keytab file, which contains an entry for the HTTP principal.

```
kadmin: xst -k http.keytab HTTP/fully.qualified.domain.name
```

**5.** Use the ktutil command to merge the previously-created keytabs:

```
$ ktutil
ktutil: rkt hdfs-unmerged.keytab
ktutil: rkt http.keytab
ktutil: wkt hdfs.keytab
ktutil: clear
ktutil: rkt mapred-unmerged.keytab
ktutil: rkt mapred-unmerged.keytab
ktutil: wkt mapred.keytab
ktutil: wkt mapred.keytab
ktutil: clear
ktutil: rkt yarn-unmerged.keytab
ktutil: rkt yarn-unmerged.keytab
ktutil: rkt yarn-unmerged.keytab
ktutil: rkt http.keytab
ktutil: wkt yarn.keytab
```

This procedure creates three new files: hdfs.keytab, mapred.keytab and yarn.keytab. These files contain entries for the hdfs and HTTP principals, the mapred and HTTP principals, and the yarn and HTTP principals respectively.

**6.** Use klist to display the keytab file entries. For example, a correctly-created hdfs keytab file should look something like this:

```
$ klist -e -k -t hdfs.keytab
Keytab name: WRFILE:hdfs.keytab
slot KVNO Principal

1     7     HTTP/fully.qualified.domain.name@YOUR-REALM.COM (DES cbc mode with
CRC-32)
2     7     HTTP/fully.qualified.domain.name@YOUR-REALM.COM (Triple DES cbc mode
with HMAC/shal)
3     7     hdfs/fully.qualified.domain.name@YOUR-REALM.COM (DES cbc mode with
CRC-32)
4     7     hdfs/fully.qualified.domain.name@YOUR-REALM.COM (Triple DES cbc mode
with HMAC/shal)
```

7. To verify that you have performed the merge procedure correctly, make sure you can obtain credentials as both the hdfs and HTTP principals using the single merged keytab:

```
$ kinit -k -t hdfs.keytab hdfs/fully.qualified.domain.name@YOUR-REALM.COM
$ kinit -k -t hdfs.keytab HTTP/fully.qualified.domain.name@YOUR-REALM.COM
```

If either of these commands fails with an error message such as "kinit: Key table entry not found while getting initial credentials", then something has gone wrong during the merge procedure. Go back to step 1 of this document and verify that you performed all the steps correctly.

**8.** To continue the procedure of configuring Hadoop security in CDH 5, follow the instructions in the section To deploy the Kerberos keytab files.

## Configuring the Mapping from Kerberos Principals to Short Names

You configure the mapping from Kerberos principals to short names in the hadoop.security.auth\_to\_local property setting in the core-site.xml file. Kerberos has this support natively, and Hadoop's implementation reuses Kerberos's configuration language to specify the mapping.

A mapping consists of a set of rules that are evaluated in the order listed in the hadoop.security.auth\_to\_local property. The first rule that matches a principal name is used to map that principal name to a short name. Any later rules in the list that match the same principal name are ignored.

You specify the mapping rules on separate lines in the hadoop.security.auth\_to\_local property as follows:

DEFAULT </value> </property>

## Mapping Rule Syntax

To specify a mapping rule, use the prefix string RULE: followed by three sections—principal translation, acceptance filter, and short name substitution—described in more detail below. The syntax of a mapping rule is:

RULE: [<principal translation>](<acceptance filter>)<short name substitution>

#### **Principal Translation**

The first section of a rule, <principal translation>, performs the matching of the principal name to the rule. If there is a match, the principal translation also does the initial translation of the principal name to a short name. In the <pri>principal translation> section, you specify the number of components in the principal name and the pattern you want to use to translate those principal component(s) and realm into a short name. In Kerberos terminology, a principal name is a set of components separated by slash ("/") characters.

The principal translation is composed of two parts that are both specified within "[]" using the following syntax:

[<number of components in principal name>:<initial specification of short name>]

#### where:

<number of components in principal name> - This first part specifies the number of components in the principal name (not including the realm) and must be 1 or 2. A value of 1 specifies principal names that have a single component (for example, hdfs), and 2 specifies principal names that have two components (for example, hdfs/fully.qualified.domain.name). A principal name that has only one component will only match single-component rules, and a principal name that has two components will only match two-component rules.

<initial specification of short name> - This second part specifies a pattern for translating the principal component(s) and the realm into a short name. The variable \$0 translates the realm, \$1 translates the first component, and \$2 translates the second component.

Here are some examples of principal translation sections. These examples use atm@YOUR-REALM.COM and atm/fully.qualified.domain.name@YOUR-REALM.COM as principal name inputs:

This Principal Translation	Translates atm@YOUR-REALM.COM into this short name	Translates atm/fully.qualified.domain.name@YOUR-REALM.COM into this short name		
[1:\$1@\$0]	atm@YOUR-REALM.COM	Rule does not match <sup>1</sup>		
[1:\$1]	atm	Rule does not match <sup>1</sup>		
[1:\$1.foo]	atm.foo	Rule does not match <sup>1</sup>		
[2:\$1/\$2@\$0]	Rule does not match <sup>2</sup>	atm/fully.qualified.domain.name@YOUR-REALM.COM		
[2:\$1/\$2]	Rule does not match <sup>2</sup>	atm/fully.qualified.domain.name		
[2:\$1@\$0]	Rule does not match <sup>2</sup>	atm@YOUR-REALM.COM		
[2:\$1]	Rule does not match <sup>2</sup>	atm		

#### Footnotes:

<sup>&</sup>lt;sup>1</sup>Rule does not match because there are two components in principal name atm/fully.qualified.domain.name@YOUR-REALM.COM

<sup>&</sup>lt;sup>2</sup>Rule does not match because there is one component in principal name atm@YOUR-REALM.COM

#### Acceptance Filter

The second section of a rule, (<acceptance filter>), matches the translated short name from the principal translation (that is, the output from the first section). The acceptance filter is specified in "()" characters and is a standard regular expression. A rule matches only if the specified regular expression matches the entire translated short name from the principal translation. That is, there's an implied ^ at the beginning of the pattern and an implied \$ at the end.

#### Short Name Substitution

The third and final section of a rule is the (<short name substitution>). If there is a match in the second section, the acceptance filter, the (<short name substitution>) section does a final translation of the short name from the first section. This translation is a sed replacement expression (s/.../.../g) that translates the short name from the first section into the final short name string. The short name substitution section is optional. In many cases, it is sufficient to use the first two sections only.

### Converting Principal Names to Lowercase

In some organizations, naming conventions result in mixed-case usernames (for example, John.Doe) or even uppercase usernames (for example, JDOE) in Active Directory or LDAP. This can cause a conflict when the Linux username and HDFS home directory are lowercase.

To convert principal names to lowercase, append /L to the rule.

#### **Example Rules**

Suppose all of your service principals are either of the form

App.service-name/fully.qualified.domain.name@YOUR-REALM.COM Or

App.service-name@YOUR-REALM.COM, and you want to map these to the short name string service-name. To do this, your rule set would be:

```
property>
  <name>hadoop.security.auth_to_local
 <value>
RULE:[1:$1](App\..*)s/App\.(.*)/$1/g
 RULE: [2:$1](App\..*)s/App\.(.*)/$1/g
 DEFAULT
  </value>
</property>
```

The first \$1 in each rule is a reference to the first component of the full principal name, and the second \$1 is a regular expression back-reference to text that is matched by (.\*).

In the following example, suppose your company's naming scheme for user accounts in Active Directory is FirstnameLastname (for example, JohnDoe), but user home directories in HDFS are /user/firstnamelastname. The following rule set converts user accounts in the CORP. EXAMPLE. COM domain to lowercase.

```
cproperty>
                 <name>hadoop.security.auth_to_local
                    < value > RULE : [1:\$1@\$0] (.*@\QCORP.EXAMPLE.COM\E\$) s/@\QCORP.EXAMPLE.COM\E\$///LEARTH = (1.81@\$0) (.*@\QCORP.EXAMPLE.COM\E\$///LEARTH = (1.81@\$0) (.*@\QCORP.EXAMPLE.COM\E\$//LEARTH = (1.81@\$0) (.*@\QCORP.EXAMPLE.COM\EXAMPLE.COM\EXAMPLE.COM\EXAMPLE.COM\EXAMPLE.COM\EXAMPLE.COM\EXAMPLE.COM\EXAMPLE.COM\EXAMPLE.COM\EXAMPLE.COM\EXAMPLE.COM\EXAMPLE.COM\EXAMPLE.COM\EXAMPLE.COM\EXAMPLE.COM\EXAMPLE.COM\EXAMPLE.COM\EXAMPLE.COM\EXAMPLE.COM\EXAMPLE.COM\EXAMPLE.COM\EXAMPLE.COM\EXAMPLE.COM\EXAMPLE.COM\EXAMPLE.COM\EXAMPLE.COM\EXAMPLE.COM\EXAMPLE.COM\EXAMPLE.COM\EXAMPLE.COM\EXAMPLE.COM\EXAMPLE.COM\EXAMPLE.COM\EXAMPLE.COM\EXAMPLE.COM\EXAMPLE.COM\EXAMPLE.COM\EXAMPLE.COM\EXAMPLE.COM\EXAMPLE.COM\EXAMPLE.COM\EXAMPLE.COM\EXAMPLE.COM\EXAMPLE.COM\EXAMPLE.COM\EXAMPLE.COM\EXAMPLE.COM\EXAMPLE.COM\EXAMPLE.COM\EXAMPLE.COM\EXAMPLE.COM\EXAMPLE.COM\EXAMPLE.COM\EXAMPLE.COM\EXAMPLE.COM\EXAMPLE.COM\EXAMPLE.COM\EXAMPLE.COM\EXAMPLE.COM\EXAMPLE.COM\EXAMPLE.COM\EXAMPLE.COM\EXAMPLE.COM\EXAMPLE.COM\EXAMPLE.COM\EXAMPLE.COM\EXAMPLE.COM\EXAMPLE.COM\EXAMPLE.COM\EXAMPLE.COM\EXAMPLE.COM\EXAMPLE.COM\EXAMPLE.COM\EXAMPLE.COM\EXAMPLE.COM\EXAMPLE.COM\EXAMPLE.COM\EXAMPLE.COM\EXAMPLE.COM\EXAMPLE.COM\EXAMPLE.COM\EXAMPLE.COM\EXAMPLE.COM\EXAMPLE.COM\EXAMPLE.COM\EXAMPLE.COM\EXAMP
RULE: [2:$1@$0](.*@\QCORP.EXAMPLE.COM\E$)s/@\QCORP.EXAMPLE.COM\E$///L
DEFAULT</value>
</property>
```

In this example, the JohnDoe@CORP.EXAMPLE.COM principal becomes the johndoe HDFS user.

#### Default Rule

You can specify an optional default rule called DEFAULT (see example above). The default rule reduces a principal name down to its first component only. For example, the default rule reduces the principal names atm@YOUR-REALM.COM Or atm/fully.qualified.domain.name@YOUR-REALM.COM down to atm, assuming that the default domain is YOUR-REALM.COM.

The default rule applies only if the principal is in the default realm.

If a principal name does not match any of the specified rules, the mapping for that principal name will fail.

#### **Testing Mapping Rules**

You can test mapping rules for a long principal name by running:

\$ hadoop org.apache.hadoop.security.HadoopKerberosName name1 name2 name3

## **Enabling Debugging Output for the Sun Kerberos Classes**

Initially getting a secure Hadoop cluster configured properly can be tricky, especially for those who are not yet familiar with Kerberos. To help with this, it can be useful to enable debugging output for the Sun Kerberos classes. To do so, set the HADOOP\_OPTS environment variable to the following:

HADOOP\_OPTS="-Dsun.security.krb5.debug=true"

# Configuring a Cluster-dedicated MIT KDC with Cross-Realm Trust

\_\_\_\_\_\_

If you use Cloudera Manager to enable Hadoop security on your cluster, the Cloudera Manager Server will create several principals and then generate keytabs for those principals. Cloudera Manager will then deploy the keytab files on every host in the cluster. See <u>Hadoop Users in Cloudera Manager and CDH</u> on page 137 for a complete listing of the principals created by Cloudera Manager.

Note: The following instructions illustrate an example of creating and deploying the principals and keytab files for MIT Kerberos. (If you are using another version of Kerberos, refer to the Kerberos documentation for the version of the operating system you are using, for instructions.)

#### When to use kadmin.local and kadmin

When performing the Kerberos commands in this document, you can use kadmin.local or kadmin depending on your access and account:

- If you can log on to the KDC host directly, and have root access or a Kerberos admin account, use the kadmin.local command.
- When accessing the KDC from a remote host, use the kadmin command.

To start kadmin.local on the KDC host or kadmin from any host, run one of the following:

- \$ kadmin

#### Note:

- In this guide, kadmin is shown as the prompt for commands in the kadmin shell, but you can type the same commands at the kadmin.local prompt in the kadmin.local shell.
- Running kadmin.local may prompt you for a password because it is being run via sudo. You should provide your Unix password. Running kadmin may prompt you for a password because you need Kerberos admin privileges. You should provide your Kerberos admin password.

## Setting up a Cluster-Dedicated KDC and Default Realm for the Hadoop Cluster

Cloudera has tested the following configuration approaches to Kerberos security for clusters managed by Cloudera Manager. For administration teams that are just getting started with Kerberos security, we recommend starting with these approaches to the configuration of KDC services for a number of reasons.

The number of Service Principal Names (SPNs) that are created and managed by the Cloudera Manager server for a CDH cluster can be significant, so it is important to realize the potential impact on cluster uptime and overall operations if you choose to manage keytabs manually instead. The Cloudera Manager server manages the creation of service keytabs on the proper hosts based on the current configuration of the database. Manual keytab management can be error prone and introduce delays when deploying or moving services within the cluster, especially under time-sensitive conditions.

Cloudera Manager creates SPNs within a KDC that it can access with the kadmin command based on configuration of the /etc/krb5.conf file on the Cloudera Manager host. SPNs are created with the format service-name/host.fqdn.name@EXAMPLE.COM where service-name is the relevant CDH service name such as hue or hbase or hdfs.

If your site already has a working KDC, and any existing principals share the same name as any of the principals that Cloudera Manager creates, the Cloudera Manager Server generates a new randomized key for those principals, and consequently causes existing keytabs to become invalid.

This is why Cloudera recommends using a dedicated local MIT Kerberos KDC and realm for the Hadoop cluster. You can set up a one-way cross-realm trust from the cluster-dedicated KDC and realm to your existing central MIT Kerberos KDC, or to an existing Active Directory realm. Using this method, there is no need to create Hadoop service principals in the central MIT Kerberos KDC or in Active Directory, but principals (users) in the central MIT KDC or in Active Directory can be authenticated to Hadoop. The steps to implement this approach are as follows:

- 1. Install and configure a cluster-dedicated MIT Kerberos KDC that will be managed by Cloudera Manager for creating and storing the service principals for your Hadoop cluster.
- 2. See the example kdc.conf and krb5.conf files in Sample Kerberos Configuration files: krb5.conf, kdc.conf, <u>kadm5.acl</u> on page 145 for configuration considerations for the KDC and Kerberos clients.
- 3. Configure a default Kerberos realm for the cluster you want Cloudera Manager to manage and set up one-way cross-realm trust between the cluster-dedicated KDC and either your central KDC or Active Directory. Follow the appropriate instructions below for your deployment: Using a Cluster-Dedicated KDC with a Central MIT KDC on page 124 or Using a Cluster-Dedicated MIT KDC with Active Directory on page 126.

Cloudera strongly recommends the method above because:

- It requires minimal configuration in Active Directory.
- It is comparatively easy to script the creation of many principals and keytabs. A principal and keytab must be created for every daemon in the cluster, and in a large cluster this can be extremely onerous to do directly in Active Directory.
- There is no need to involve central Active Directory administrators in order to get service principals created.
- It allows for incremental configuration. The Hadoop administrator can completely configure and verify the functionality the cluster independently of integrating with Active Directory.

## Using a Cluster-Dedicated KDC with a Central MIT KDC

- Important: If you plan to use Oozie or the Hue Kerberos Ticket Renewer in your cluster, you must configure your KDC to allow tickets to be renewed, and you must configure krb5.conf to request renewable tickets. Typically, you can do this by adding the max\_renewable\_life setting to your realm in kdc.conf, and by adding the renew\_lifetime parameter to the libdefaults section of krb5.conf. For more information about renewable tickets, see the Kerberos documentation. This is demonstrated in the Sample Kerberos Configuration files: krb5.conf, kdc.conf, kadm5.acl on page 145.
- 1. In the /var/kerberos/krb5kdc/kdc.conf file on the local dedicated KDC server host, configure the default realm for the Hadoop cluster by substituting your Kerberos realm in the following realms property:

```
HADOOP.EXAMPLE.COM = {
```

2. In the /etc/krb5.conf file on all cluster hosts and all Hadoop client user hosts, configure the default realm for the Hadoop cluster by substituting your Kerberos realm in the following realms property. Also specify the local dedicated KDC server host name in the /etc/krb5.conf file (for example, kdc01.example.com).

```
[libdefaults]
 default_realm = HADOOP.EXAMPLE.COM
[realms]
 HADOOP.EXAMPLE.COM = {
   kdc = kdc01.hadoop.example.com:88
   admin_server = kdc01.hadoop.example.com:749
   default_domain = hadoop.example.com
 ÉXAMPLE.COM = {
   kdc = kdc01.example.com:88
   admin_server = kdc01.example.com:749
   default_domain = example.com
[domain_realm]
  .hadoop.example.com = HADOOP.EXAMPLE.COM
 hadoop.example.com = HADOOP.EXAMPLE.COM
  .example.com = EXAMPLE.COM
 example.com = EXAMPLE.COM
```

3. To set up the cross-realm trust in the cluster-dedicated KDC, type the following command in the kadmin.local or kadmin shell on the cluster-dedicated KDC host to create a krbtgt principal. Substitute your cluster-dedicated KDC realm for HADOOP. EXAMPLE. COM, and substitute your central KDC realm for EXAMPLE.COM. Enter a trust password when prompted. Note the password because you will need to enter the exact same password in the central KDC in the next step.

```
kadmin: addprinc krbtgt/HADOOP.EXAMPLE.COM@EXAMPLE.COM
```

- 4. Each of your Hadoop client users must also place this information in their local core-site.xml file. The easiest way to do so is by using the Cloudera Manager Admin Console to generate a client configuration file.
- 5. To set up the cross-realm trust in the central KDC, type the same command in the kadmin.local or kadmin shell on the central KDC host to create the exact same krbtgt principal and password.

```
kadmin: addprinc krbtgt/HADOOP.EXAMPLE.COM@EXAMPLE.COM
```

- Important: In order for a cross-realm trust to operate properly, both KDCs must have the same krbtgt principal and password, and both KDCs must be configured to use the same encryption type.
- 6. To properly translate principal names from the central KDC realm into the cluster-dedicated KDC realm for the Hadoop cluster, configure the Trusted Kerberos Realms property of the HDFS service.
  - a. Open the Cloudera Manager Admin Console.
  - b. Go to the HDFS service.
  - **c.** Click the **Configuration** tab.
  - d. Select Scope > HDFS (Service Wide)
  - e. Select Category > Security.
  - f. Type Kerberos in the Search box.
  - g. Edit the Trusted Kerberos Realms property to add the name of your central KDC realm. If you need to use more advanced mappings which do more than just allow principals from another domain, you may enter them in the Additional Rules to Map Kerberos Principals to Short Names property. For more information about name mapping rules, see Configuring the Mapping from Kerberos Principals to Short Names (CDH 4) or Configuring the Mapping from Kerberos Principals to Short Names on page 120.
- 7. Each of your Hadoop client users must also place this information in their local core-site.xml file. The easiest way to do so is by using the Cloudera Manager Admin Console to generate a client configuration file.

**8.** Proceed to <u>Step 2: If You are Using AES-256 Encryption, Install the JCE Policy File</u> on page 35. Later in this procedure, you will restart the services to have the configuration changes in core-site.xml take effect.

## Using a Cluster-Dedicated MIT KDC with Active Directory

Important: If you are using Cloudera Manager, ensure you have installed the openldap-clients package on the Cloudera Manager Server host before you begin configuring Kerberos authentication.

#### On the Active Directory Server

1. On the Active Directory server host, type the following command to add the local realm trust to Active Directory:

```
netdom trust HADOOP.EXAMPLE.COM /Domain:EXAMPLE.COM /add /realm /passwordt:TrustPassword
```

\_\_\_\_\_\_

2. On the Active Directory server host, type the following command to set the proper encryption type:

#### Windows 2003 RC2

Windows 2003 server installations do not support AES encryption for Kerberos. Therefore RC4 should be used. Please see the <u>Microsoft reference documentation</u> for more information.

```
ktpass /MITRealmName HADOOP.EXAMPLE.COM /TrustEncryp RC4
```

#### Windows 2008

- Note: When using AES 256 encryption with Windows 2008 you must update the proper Java Cryptography Extension (JCE) policy files for the version of JDK you are using.
  - JCE Policy Files JDK 1.6
  - JCE Policy Files JDK 1.7

```
ksetup /SetEncTypeAttr HADOOP.EXAMPLE.COM <enc_type>
```

Where the <enc\_type> parameter can be replaced with parameter strings for AES, DES, or RC4 encryption modes. For example, for AES encryption, replace <enc\_type> with AES256-CTS-HMAC-SHA1-96 or AES128-CTS-HMAC-SHA1-96 and for RC4 encryption, replace with RC4-HMAC-MD5. See the Microsoft reference documentation for more information.

• Important: Make sure that the encryption type you specify is supported on both your version of Windows Active Directory and your version of MIT Kerberos.

#### On the MIT KDC Server

1. In the /var/kerberos/krb5kdc/kdc.conf file on the local dedicated KDC server host, configure the default realm for the Hadoop cluster by substituting your Kerberos realm in the following realms property:

```
[realms]
HADOOP.EXAMPLE.COM = {
```

- 2. Each of your Hadoop client users must also place this information in their local core-site.xml file. The easiest way to do so is by using the Cloudera Manager Admin Console to generate a <u>client configuration file</u>.
- **3.** On the local MIT KDC server host, type the following command in the kadmin.local or kadmin shell to add the cross-realm krbtgt principal:

```
kadmin: addprinc -e "<enc_type_list>" krbtgt/HADOOP.EXAMPLE.COM@EXAMPLE.COM
```

where the <enc type list> parameter specifies the types of encryption this cross-realm krbtgt principal will support: either AES, DES, or RC4 encryption. You can specify multiple encryption types using the parameter in the command above. Make sure that at least one of the encryption types corresponds to the encryption types found in the tickets granted by the KDC in the remote realm.

#### Examples by Active Directory Domain or Forest "Functional level"

Active Directory will, based on the Domain or Forest functional level, use encryption types supported by that release of the Windows Server operating system. It is not possible to use AES encryption types with an AD 2003 functional level. If you notice that DES encryption types are being used when authenticating or requesting service tickets to Active Directory then it might be necessary to enable weak encryption types in the /etc/krb5.conf. See Sample Kerberos Configuration files: krb5.conf, kdc.conf, kadm5.acl on page 145 for an example.

Windows 2003

```
kadmin: addprinc -e "rc4-hmac:normal" krbtgt/HADOOP.EXAMPLE.COM@EXAMPLE.COM
```

Windows 2008

```
kadmin: addprinc -e "aes256-cts:normal aes128-cts:normal rc4-hmac:normal"
krbtgt/HADOOP.EXAMPLE.COM@EXAMPLE.COM
```

Note: The cross-realm krbtgt principal that you add in this step must have at least one entry that uses the same encryption type as the tickets that are issued by the remote KDC. If there are no matching encryption types, principals in the local realm can successfully access the Hadoop cluster, but principals in the remote realm are unable to.

#### On All Cluster Hosts

1. In the /etc/krb5.conf file on all cluster hosts and all Hadoop client user hosts, configure both Kerberos realms. Note that default\_realm should be configured as the local MIT Kerberos realm for the cluster. Your krb5.conf may contain more configuration properties than those demonstrated below. This example is provided to clarify configuration parameters. See Sample Kerberos Configuration files: krb5.conf, kdc.conf, kadm5.acl on page 145 for more information.

```
[libdefaults]
 default_realm = HADOOP.EXAMPLE.COM
[realms]
 EXAMPLE.COM = {
   kdc = dc01.example.com:88
   admin_server = dc01.example.com:749
 HADOOP.EXAMPLE.COM = {
   kdc = kdc01.hadoop.example.com:88
   admin_server = kdc01.hadoop.example.com:749
[domain_realm]
  .hadoop.example.com = HADOOP.EXAMPLE.COM
 hadoop.example.com = HADOOP.EXAMPLE.COM
  .example.com = EXAMPLE.COM
 example.com = EXAMPLE.COM
```

- 2. Use one of the following methods to properly translate principal names from the Active Directory realm into the cluster-dedicated KDC realm for the Hadoop cluster.
  - Using Cloudera Manager: Configure the Trusted Kerberos realms property of the HDFS service:
    - 1. Open the Cloudera Manager Admin Console.
    - 2. Go to the HDFS service.
    - **3.** Click the **Configuration** tab.

- 4. Select Scope > HDFS (Service Wide)
- 5. Select Category > Security.
- **6.** Type Kerberos in the **Search** box.
- 7. Edit the Trusted Kerberos Realms property to add the name of your central KDC realm. If you need to use more advanced mappings which do more than just allow principals from another domain, you may enter them in the Additional Rules to Map Kerberos Principals to Short Names property. For more information about name mapping rules, see Configuring the Mapping from Kerberos Principals to Short Names (CDH 4) or Configuring the Mapping from Kerberos Principals to Short Names on page 120.
- Using the Command Line: Configure the hadoop.security.auth\_to\_local setting in the core-site.xml file on all of the cluster hosts. The following example translates all principal names with the realm EXAMPLE.COM into the first component of the principal name only. It also preserves the standard translation for the default realm (the cluster realm).

# Integrating Hadoop Security with Active Directory

#### Considerations when using an Active Directory KDC

#### Performance:

As your cluster grows, so will the volume of Authentication Service (AS) and Ticket Granting Service (TGS) interaction between the services on each cluster server. Consider evaluating the volume of this interaction against the Active Directory domain controllers you have configured for the cluster before rolling this feature out to a production environment. If cluster performance suffers, over time it might become necessary to dedicate a set of AD domain controllers to larger deployments.

#### **Network Proximity:**

By default, Kerberos uses UDP for client/server communication. Often, AD services are in a different network than project application services such as Hadoop. If the domain controllers supporting a cluster for Kerberos are not in the same subnet, or they're separated by a firewall, consider using the udp\_preference\_limit = 1 setting in the [libdefaults] section of the krb5.conf used by cluster services. Cloudera strongly recommends against using AD domain controller (KDC) servers that are separated from the cluster by a WAN connection, as latency in this service will significantly impact cluster performance.

#### Process

Troubleshooting the cluster's operations, especially for Kerberos-enabled services, will need to include AD administration resources. Evaluate your organizational processes for engaging the AD administration team, and how to escalate in case a cluster outage occurs due to issues with Kerberos authentication against AD services. In some situations it might be necessary to enable Kerberos event logging to address desktop and KDC issues within windows environments.

Important: With CDH 5.1 and later, clusters managed by Cloudera Manager 5.1 (and later) do not require a local MIT KDC and are able to integrate directly with an Active Directory KDC. Cloudera recommends you use a direct-to-AD setup. For instructions, see <a href="Enabling Kerberos Authentication Using the Wizard">Enabling Kerberos Authentication Using the Wizard</a> on page 16.

If direct integration with AD is not currently possible, use the following instructions to configure a local MIT KDC to trust vour AD server:

1. Run an MIT Kerberos KDC and realm local to the cluster and create all service principals in this realm.

\_\_\_\_\_\_

2. Set up one-way cross-realm trust from this realm to the Active Directory realm. Using this method, there is no need to create service principals in Active Directory, but Active Directory principals (users) can be authenticated to Hadoop. See Configuring a Local MIT Kerberos Realm to Trust Active Directory on page 129.

## Configuring a Local MIT Kerberos Realm to Trust Active Directory

## On the Active Directory Server

1. Type the following command to add the local realm trust to Active Directory:

```
netdom trust YOUR-LOCAL-REALM.COMPANY.COM /Domain:AD-REALM.COMPANY.COM /add /realm
/passwordt:<TrustPassword>
```

**2.** Type the following command to set the proper encryption type:

#### On Windows 2003 RC2:

```
ktpass /MITRealmName YOUR-LOCAL-REALM.COMPANY.COM /TrustEncryp <enc_type>
```

#### On Windows 2008:

```
ksetup /SetEncTypeAttr YOUR-LOCAL-REALM.COMPANY.COM <enc_type>
```

where the <enc\_type> parameter specifies AES, DES, or RC4 encryption. Refer to the documentation for your version of Windows Active Directory to find the <enc type> parameter string to use.

Important: Make sure the encryption type you specify is supported on both your version of Windows Active Directory and your version of MIT Kerberos.

#### On the MIT KDC Server

Type the following command in the kadmin.local or kadmin shell to add the cross-realm krbtgt principal. Use the same password you used in the netdom command on the Active Directory Server.

```
kadmin: addprinc -e "<enc_type_list>"
krbtqt/YOUR-LOCAL-REALM.COMPANY.COM@AD-REALM.COMPANY.COM
```

where the <enc\_type\_list> parameter specifies the types of encryption this cross-realm krbtgt principal will support: either AES, DES, or RC4 encryption. You can specify multiple encryption types using the parameter in the command above, what's important is that at least one of the encryption types corresponds to the encryption type found in the tickets granted by the KDC in the remote realm. For example:

```
kadmin: addprinc -e "rc4-hmac:normal des3-hmac-shal:normal"
krbtgt/YOUR-LOCAL-REALM.COMPANY.COM@AD-REALM.COMPANY.COM
```

Note: The cross-realm krbtgt principal that you add in this step must have at least one entry that uses the same encryption type as the tickets that are issued by the remote KDC. If no entries have the same encryption type, then the problem you will see is that authenticating as a principal in the local realm will allow you to successfully run Hadoop commands, but authenticating as a principal in the remote realm will not allow you to run Hadoop commands.

#### On All of the Cluster Hosts

1. Verify that both Kerberos realms are configured on all of the cluster hosts. Note that the default realm and the domain realm should remain set as the MIT Kerberos realm which is local to the cluster.

```
[realms]
AD-REALM.CORP.FOO.COM = {
   kdc = ad.corp.foo.com:88
   admin_server = ad.corp.foo.com:749
   default_domain = foo.com
}
CLUSTER-REALM.CORP.FOO.COM = {
   kdc = cluster01.corp.foo.com:88
   admin_server = cluster01.corp.foo.com:749
   default_domain = foo.com
}
```

2. To properly translate principal names from the Active Directory realm into local names within Hadoop, you must configure the hadoop.security.auth\_to\_local setting in the core-site.xml file on all of the cluster machines. The following example translates all principal names with the realm AD-REALM.CORP.FOO.COM into the first component of the principal name only. It also preserves the standard translation for the default realm (the cluster realm).

For more information about name mapping rules, see <u>Configuring the Mapping from Kerberos Principals to Short Names</u> on page 120.

# Integrating Hadoop Security with Alternate Authentication

One of the ramifications of enabling security on a Hadoop cluster is that every user who interacts with the cluster must have a Kerberos principal configured. For some of the services, specifically Oozie and Hadoop (for example, JobTracker and TaskTracker), it can be convenient to run a mixed form of authentication where Kerberos authentication is used for API or command line access while some other form of authentication (for example, SSO and LDAP) is used for accessing Web UIs. Using an alternate authentication deployment is considered an advanced topic because only a partial implementation is provided in this release: you will have to implement some of the code yourself.

**Note:** The following instructions assume you already have a Kerberos-enabled cluster.

#### Proceed as follows:

- Configuring the AuthenticationFilter to use Kerberos on page 131
- Creating an AltKerberosAuthenticationHandler Subclass on page 131
- Enabling Your AltKerberosAuthenticationHandler Subclass on page 131

See also the Example Implementation for Oozie on page 132.

## Configuring the AuthenticationFilter to use Kerberos

First, you must do all of the steps in the Server Side Configuration section of the Hadoop Auth, Java HTTP SPNEGO Documentation to configure AuthenticationFilter to use Kerberos. You must configure AuthenticationFilter to use Kerberos before doing the steps below.

## Creating an AltKerberosAuthenticationHandler Subclass

An AuthenticationHandler is installed on the server-side to handle authenticating clients and creating an AuthenticationToken.

- 1. Subclass the org.apache.hadoop.security.authentication.server.AltKerberosAuthenticationHandlerclass (in the hadoop-auth package).
- 2. When a client sends a request, the authenticate method will be called. For browsers, AltKerberosAuthenticationHandler will call the alternateAuthenticate method, which is what you need to implement to interact with the desired authentication mechanism. For non-browsers, AltKerberosAuthenticationHandler will follow the Kerberos SPNEGO sequence (this is provided for you).
- 3. The alternateAuthenticate(HttpServletRequest request, HttpServletResponse response) method in your subclass should following these rules:
- 4. Return null if the authentication is still in progress; the response object can be used to interact with the
- 5. Throw an AuthenticationException if the authentication failed.
- **6.** Return an AuthenticationToken if the authentication completed successfully.

## Enabling Your AltKerberosAuthenticationHandler Subclass

You can enable the alternate authentication on Hadoop Web Uls, Oozie Web Uls, or both. You will need to include a JAR containing your subclass on the classpath of Hadoop and/or Oozie. All Kerberos-related configuration properties will still apply.

## Enabling Your AltKerberosAuthenticationHandler Subclass on Hadoop Web Uls

1. Stop Hadoop by running the following command on every node in your cluster (as root):

```
$ for x in `cd /etc/init.d ; ls hadoop-*`; do sudo service $x stop ; done
```

2. Set the following property in core-site.xml, where

org.my.subclass.of.AltKerberosAuthenticationHandler is the classname of your subclass:

```
<name>hadoop.http.authentication.type</name>
 <value>org.my.subclass.of.AltKerberosAuthenticationHandler/value>
</property>
```

3. (Optional) You can also specify which user-agents you do not want to be considered as browsers by setting the following property as required (default value is shown). Note that all Java-based programs (such as Hadoop client) will use java as their user-agent.

```
<name>hadoop.http.authentication.alt-kerberos.non-browser.user-agents/name>
  <value>java,curl,wget,perl</value>
</property>
```

- 4. Copy the JAR containing your subclass into /usr/lib/hadoop/lib/.
- **5.** Start Hadoop by running the following command:

```
$ for x in `cd /etc/init.d ; ls hadoop-*` ; do sudo service $x start ; done
```

## Enabling Your AltKerberosAuthenticationHandler Subclass on Oozie Web UI

Note:

These instructions assume you have already performed the installation and configuration steps in Oozie Security Configuration.

**1.** Stop the Oozie Server:

```
sudo /sbin/service oozie stop
```

2. Set the following property in oozie-site.xml, where

org.my.subclass.of.AltKerberosAuthenticationHandler is the classname of your subclass:

```
<name>oozie.authentication.type</name>
  <value>org.my.subclass.of.AltKerberosAuthenticationHandler/value>
</property>
```

3. (Optional) You can also specify which user-agents you do not want to be considered as browsers by setting the following property as required (default value is shown). Note that all Java-based programs (such as Hadoop client) will use java as their user-agent.

```
cproperty>
 <name>oozie.authentication.alt-kerberos.non-browser.user-agents/name>
 <value>java,curl,wget,perl</value>
</property>
```

- **4.** Copy the JAR containing your subclass into /var/lib/oozie.
- **5.** Start the Oozie Server:

```
sudo /sbin/service oozie start
```

## Example Implementation for Oozie

Warning:

The example implementation is **NOT SECURE**. Its purpose is to be as simple as possible, as an example of how to write your own AltKerberosAuthenticationHandler subclass.

It should NOT be used in a production environment

An example implementation of AltkerberosAuthenticationHandler is included (though not built by default) with Oozie. Also included is a simple Login Server with two implementations. The first one will authenticate any user who is using a username and password that are identical, such as foo: foo. The second one can be configured against an LDAP server to use LDAP for authentication.

You can read comprehensive documentation on the example at Creating Custom Authentication.

#### Important:

If you installed Oozie from the CDH packages and are deploying oozie-login.war alongside oozie.war, you will also need to run the following commands after you copy the oozie-login.war file to /usr/lib/oozie/oozie-server (if using YARN or /usr/lib/oozie/oozie-server-0.20 if using MRv1) because it won't automatically be expanded:

```
jar xvf oozie-login.war
mkdir oozie-login
mv META-INF oozie-login/
mv WEB-INF oozie-login/
```

# Configuring LDAP Group Mappings

**Important:** Cloudera strongly recommends *against* using Hadoop's LdapGroupsMapping provider. LdapGroupsMapping should only be used in cases where OS-level integration is not possible. Production clusters require an identity provider that works well with all applications, not just Hadoop. Hence, often the preferred mechanism is to use tools such as SSSD, VAS or Centrify to replicate LDAP groups.

When configuring LDAP for group mappings in Hadoop, you must create the users and groups for your Hadoop services in LDAP. When using the default shell-based group mapping provider

(org.apache.hadoop.security.ShellBasedUnixGroupsMapping), the requisite user and group relationships already exist because they are created during the installation procedure. When you switch to LDAP as the group mapping provider, you must re-create these relationships within LDAP.

Not that if you have modified the **System User** or **System Group** setting within Cloudera Manager for any service, you must use those custom values to provision the users and groups in LDAP.

The table below lists users and their group members for CDH services:

Note: Cloudera Manager 5.3 introduces a new *single user mode*. In single user mode, the Cloudera Manager Agent and all the processes run by services managed by Cloudera Manager are started as a single configured user and group. See Single User Mode Requirements for more information.

#### Table 3: Users and Groups

Component (Version)	Unix User ID	Groups	Notes		
Cloudera Manager (all versions)	cloudera-scm	cloudera-scm	Cloudera Manager processes such as the Cloud Manager Server and the monitoring roles run this user.		
			The Cloudera Manager keytab file must be name cmf.keytab since that name is hard-coded in Cloudera Manager.		
			• Note: Applicable to clusters managed by Cloudera Manager only.		
Apache Accumulo (Accumulo 1.4.3 and higher)	accumulo	accumulo	Accumulo processes run as this user.		

Component (Version)	Unix User ID	Groups	Notes		
Apache Avro			No special users.		
Apache Flume (CDH 4, CDH 5)	flume	flume	The sink that writes to HDFS as this user must have write privileges.		
Apache HBase (CDH 4, CDH 5)	hbase	hbase	The Master and the RegionServer processes run as this user.		
HDFS (CDH 4, CDH 5)	hdfs	hdfs, hadoop	The NameNode and DataNodes run as this user, and the HDFS root directory as well as the directories used for edit logs should be owned by it.		
Apache Hive (CDH 4, CDH 5)	hive	hive	The HiveServer2 process and the Hive Metastore processes run as this user.		
			A user must be defined for Hive access to its Metastore DB (e.g. MySQL or Postgres) but it can be any identifier and does not correspond to a Unix uid. This is		
			javax.jdo.option.ConnectionUserName in hive-site.xml.		
Apache HCatalog (CDH 4.2 and higher, CDH 5)	hive	hive	The WebHCat service (for REST access to Hive functionality) runs as the hive user.		
HttpFS (CDH 4, CDH 5)	httpfs	httpfs	The HttpFS service runs as this user. See HttpFS Security Configuration for instructions on how to generate the merged httpfs-http.keytab file.		
Hue (CDH 4, CDH 5)	hue	hue	Hue services run as this user.		
Cloudera Impala (CDH 4.1 and higher, CDH 5)	impala	impala, hadoop, hdfs, hive	Impala services run as this user.		
Apache Kafka (Cloudera Distribution of Kafka 1.2.0)	kafka	kafka	Kafka services run as this user.		
Java KeyStore KMS (CDH 5.2.1 and higher)	kms	kms	The Java KeyStore KMS service runs as this user.		
Key Trustee KMS (CDH 5.3 and higher)	kms	kms	The Key Trustee KMS service runs as this user.		
Key Trustee Server (CDH 5.4 and higher)	keytrustee	keytrustee	The Key Trustee Server service runs as this user.		
Llama (CDH 5)	llama	llama	Llama runs as this user.		
Apache Mahout			No special users.		

Component (Version)	Unix User ID	Groups	Notes		
MapReduce (CDH 4, CDH 5)	mapred	mapred, hadoop	Without Kerberos, the JobTracker and tasks run as this user. The LinuxTaskController binary is owned by this user for Kerberos.		
Apache Oozie (CDH 4, CDH 5)	oozie	oozie	The Oozie service runs as this user.		
Parquet			No special users.		
Apache Pig			No special users.		
Cloudera Search (CDH 4.3 and higher, CDH 5)	solr	solr	The Solr processes run as this user.		
Apache Spark (CDH 5)	spark	spark	The Spark History Server process runs as this user.		
Apache Sentry (incubating) (CDH 5.1 and higher)	sentry	sentry	The Sentry service runs as this user.		
Apache Sqoop (CDH 4, CDH 5)	aqoop	aqoop	This user is only for the Sqoop1 Metastore, a configuration option that is not recommended.		
Apache Sqoop2 (CDH 4.2 and higher, CDH 5)	sqoop2	sqoop, sqoop2	The Sqoop2 service runs as this user.		
Apache Whirr			No special users.		
YARN (CDH 4, CDH 5)	yarn	yarn, hadoop	Without Kerberos, all YARN services and applications run as this user. The LinuxContainerExecutor binary is owned by this user for Kerberos.		
Apache ZooKeeper (CDH 4, CDH 5)	zookeeper	zookeeper	The ZooKeeper processes run as this user. It is no configurable.		

#### Important:

- You can use either Cloudera Manager or the following command-line instructions to complete this configuration.
- This information applies specifically to CDH 5.4.x. If you use an earlier version of CDH, see the documentation for that version located at Cloudera Documentation.

# Using Cloudera Manager

Required Role: Configurator Cluster Administrator Full Administrator

Make the following changes to the HDFS service's security configuration:

- 1. Open the Cloudera Manager Admin Console and navigate to the HDFS service.
- **2.** Click the **Configuration** tab.
- 3. Select Scope > HDFS (Service Wide)
- 4. Select Category > Security.

**5.** Modify the following configuration properties using values from the table below:

Configuration Property	Value
Hadoop User Group Mapping Implementation	org.apache.hadoop.security.LdapGroupsMapping
Hadoop User Group Mapping LDAP URL	ldap:// <server></server>
Hadoop User Group Mapping LDAP Bind User	Administrator@example.com
Hadoop User Group Mapping LDAP Bind User Password	***
Hadoop User Group Mapping Search Base	dc=example,dc=com

Although the above changes are sufficient to configure group mappings for Active Directory, some changes to the remaining default configurations might be required for OpenLDAP.

## Using the Command Line

Add the following properties to the core-site.xml on the NameNode:

```
property>
<name>hadoop.security.group.mapping</name>
<value>org.apache.hadoop.security.LdapGroupsMapping</value>
property>
<name>hadoop.security.group.mapping.ldap.url</name>
<value>ldap://server</value>
</property>
property>
<name>hadoop.security.group.mapping.ldap.bind.user</name>
<value>Administrator@example.com</value>
</property>
property>
<name>hadoop.security.group.mapping.ldap.bind.password</name>
<value>****
</property>
cproperty>
<name>hadoop.security.group.mapping.ldap.base</name>
<value>dc=example,dc=com</value>
</property>
<name>hadoop.security.group.mapping.ldap.search.filter.user/name>
<value>(&amp;(objectClass=user)(sAMAccountName={0})))/value>
</property>
<name>hadoop.security.group.mapping.ldap.search.filter.group/name>
<value>(objectClass=group)</value>
</property>
<name>hadoop.security.group.mapping.ldap.search.attr.member/name>
<value>member</value>
</property>
cproperty>
<name>hadoop.security.group.mapping.ldap.search.attr.group.name/name>
<value>cn</value>
</property>
```

- Note: In addition:
  - If you are using Sentry with Hive, you will also need to add these properties on the HiveServer2
  - If you are using Sentry with Impala, add these properties on all hosts

See <u>Users and Groups in Sentry</u> for more information.

# Hadoop Users in Cloudera Manager and CDH

A number of special users are created by default when installing and using CDH and Cloudera Manager. Given below is a list of users and groups as of the latest release. Also listed are the corresponding Kerberos principals and keytab files that should be created when you configure Kerberos security on your cluster.

Note: Cloudera Manager 5.3 introduces a new single user mode. In single user mode, the Cloudera Manager Agent and all the processes run by services managed by Cloudera Manager are started as a single configured user and group. See Single User Mode Requirements for more information.

#### Table 4: Users and Groups

Component (Version)	Unix User ID	Groups	Notes		
Cloudera Manager (all versions)	cloudera-scm	cloudera-scm	Cloudera Manager processes such as the Cloudera Manager Server and the monitoring roles run as this user.		
			The Cloudera Manager keytab file must be named cmf . keytab since that name is hard-coded in Cloudera Manager.		
			• Note: Applicable to clusters managed by Cloudera Manager only.		
Apache Accumulo (Accumulo 1.4.3 and higher)	accumulo	accumulo	Accumulo processes run as this user.		
Apache Avro			No special users.		
Apache Flume (CDH 4, CDH 5)	flume	flume	The sink that writes to HDFS as this user must have write privileges.		
Apache HBase (CDH 4, CDH 5)	hbase	hbase	The Master and the RegionServer processes run as this user.		
HDFS (CDH 4, CDH 5)	hdfs	hdfs, hadoop	The NameNode and DataNodes run as this use and the HDFS root directory as well as the directories used for edit logs should be owned tit.		
Apache Hive (CDH 4, CDH 5)	hive	hive	The HiveServer2 process and the Hive Metastore processes run as this user.		
			A user must be defined for Hive access to its Metastore DB (e.g. MySQL or Postgres) but it can be any identifier and does not correspond to a Unix		

Component (Version)	Unix User ID	Groups	Notes	
			uid. This is javax.jdo.option.ConnectionUserName in hive-site.xml.	
Apache HCatalog (CDH 4.2 and higher, CDH 5)	hive	hive	The WebHCat service (for REST access to Hive functionality) runs as the hive user.	
HttpFS (CDH 4, CDH 5)	httpfs	httpfs	The HttpFS service runs as this user. See HttpFS Security Configuration for instructions on how to generate the merged httpfs-http.keytab file.	
Hue (CDH 4, CDH 5)	hue	hue	Hue services run as this user.	
Cloudera Impala (CDH 4.1 and higher, CDH 5)	impala	impala, hadoop, hdfs, hive	Impala services run as this user.	
Apache Kafka (Cloudera Distribution of Kafka 1.2.0)	kafka	kafka	Kafka services run as this user.	
Java KeyStore KMS (CDH 5.2.1 and higher)	kms	kms	The Java KeyStore KMS service runs as this user.	
Key Trustee KMS (CDH 5.3 and higher)	kms	kms	The Key Trustee KMS service runs as this user.	
Key Trustee Server (CDH 5.4 and higher)	keytrustee	keytrustee	The Key Trustee Server service runs as this user.	
Llama (CDH 5)	llama	llama	Llama runs as this user.	
Apache Mahout			No special users.	
MapReduce (CDH 4, CDH 5)	mapred	mapred, hadoop	Without Kerberos, the JobTracker and tasks run as this user. The LinuxTaskController binary is owned by this user for Kerberos.	
Apache Oozie (CDH 4, CDH 5)	oozie	oozie	The Oozie service runs as this user.	
Parquet			No special users.	
Apache Pig			No special users.	
Cloudera Search (CDH 4.3 and higher, CDH 5)	solr	solr	The Solr processes run as this user.	
Apache Spark (CDH 5)	spark	spark	The Spark History Server process runs as this user.	

Component (Version)	Unix User ID	Groups	Notes
Apache Sentry (incubating) (CDH 5.1 and higher)	sentry	sentry	The Sentry service runs as this user.
Apache Sqoop (CDH 4, CDH 5)	goop	goop	This user is only for the Sqoop1 Metastore, a configuration option that is not recommended.
Apache Sqoop2 (CDH 4.2 and higher, CDH 5)	sqoop2	sqoop, sqoop2	The Sqoop2 service runs as this user.
Apache Whirr			No special users.
YARN (CDH 4, CDH 5)	yarn	yarn, hadoop	Without Kerberos, all YARN services and applications run as this user. The LinuxContainerExecutor binary is owned by this user for Kerberos.
Apache ZooKeeper (CDH 4, CDH 5)	zookeeper	zookeeper	The ZooKeeper processes run as this user. It is not configurable.

#### Keytabs and Keytab File Permissions

#### Note:

The Kerberos principal names should be of the format, username/fully.qualified.domain.name@YOUR-REALM.COM, where the term username refers to the username of an existing UNIX account, such as hdfs or mapred. The table below lists the usernames to be used for the Kerberos principal names. For example, the Kerberos principal for Apache Flume

For keytabs with multiple principals, Cloudera Manager merges them appropriately from individual keytabs. If you do not use Cloudera Manager, you must merge the keytabs manually.

would be flume/fully.qualified.domain.name@YOUR-REALM.COM.

Table 5: Clusters Managed by Cloudera Manager

Component (Unix User ID)	Service	Kerberos Principals	Filename (*.keytab)	Keytab File Owner	Keytab File Group	File Permission (octal)
Cloudera Manager (cloudera-scm)	NA	cloudera-scm	cmf	cloudera-scm	cloudera-scm	600
Cloudera Management Service (cloudera-scm)	cloudera-mgmt- REPORTSMANAGER	cloudera-scm	hdfs	cloudera-scm	cloudera-scm	600
	cloudera-mgmt- ACTIVITYMONITOR					
	cloudera-mgmt- SERVICEMONITOR					
	cloudera-mgmt- HOSTMONITOR					

Component (Unix User ID)	Service	Kerberos Principals	Filename (*.keytab)	Keytab File Owner	Keytab File Group	File Permission (octal)
Apache Accumulo (accumulo)	accumulo16-ACCUMULO16_MASTER	accumulo	accumulo16	cloudera-scm	cloudera-scm	600
	accumulo16-ACCUMULO16_TRACER					
	accumulo16-ACCUMULO16_MONTOR					
	accumulo16-ACCUMULO16_GC					
	accumulo16-ACCUMULO16_TSERVER					
Flume (flume)	flume-AGENT	flume	flume	cloudera-scm	cloudera-scm	600
HBase (hbase)	hbase-REGIONSERVER	hbase	hbase	cloudera-scm	cloudera-scm	600
	hbase- HBASETHRIFTSERVER					
	hbase- HBASERESTSERVER					
	hbase-MASTER					
HDFS (hdfs)	hdfs-NAMENODE	hdfs, HTTP	hdfs	cloudera-scm	cloudera-scm	600
	hdfs-DATANODE					
	hdfs- SECONDARYNAMENODE					
Hive (hive)	hive-HIVESERVER2	hive	hive	cloudera-scm	cloudera-scm	600
	hive-WEBHCAT	HTTP	HTTP			
	hive-HIVEMETASTORE	hive	hive			
HttpFS (httpfs)	hdfs-HTTPFS	httpfs	httpfs	cloudera-scm	cloudera-scm	600
Hue (hue)	hue-KT_RENEWER	hue	hue	cloudera-scm	cloudera-scm	600
Impala (impala)	impala-STATESTORE	impala	impala	cloudera-scm	cloudera-scm	600
	impala-CATALOGSERVER					
	impala-IMPALAD					
Java KeyStore KMS (kms)	kms-KMS	HTTP	kms	cloudera-scm	cloudera-scm	600
Key Trustee KMS (kms)	keytrustee-KMS_KEYTRUSTEE	HTTP	keytrustee	cloudera-scm	cloudera-scm	600
Llama (llama)	impala-LLAMA	Ilama, HTTP	Ilama	cloudera-scm	cloudera-scm	600
MapReduce (mapred)	mapreduce-JOBTRACKER	mapred, HTTP	mapred	cloudera-scm	cloudera-scm	600
	mapreduce- TASKTRACKER					
Oozie (oozie)	oozie-00ZIE_SERVER	oozie, HTTP	oozie	cloudera-scm	cloudera-scm	600
Search (solr)	solr-SOLR_SERVER	solr, HTTP	solr	cloudera-scm	cloudera-scm	600
Sentry (sentry)	sentry-SENTRY_SERVER	sentry	sentry	cloudera-scm	cloudera-scm	600

Component (Unix User ID)	Service	Kerberos Principals	Filename (*.keytab)	Keytab File Owner	Keytab File Group	File Permission (octal)
Spark (spark)	spark_on_yarn- SPARK_YARN_HISTORY_SERVER	spark	spark	cloudera-scm	cloudera-scm	600
YARN (yarn)	yarn-NODEMANAGER	yarn, HTTP	yarn	cloudera-scm	cloudera-scm	644
	yarn- RESOURCEMANAGER					600
	yarn-JOBHISTORY					600
ZooKeeper (zookeeper)	zookeeper-server	zookeeper	zookeeper	cloudera-scm	cloudera-scm	600

Table 6: CDH Clusters Not Managed by Cloudera Manager

Component (Unix User ID)	Service	Kerberos Principals	Filename (*.keytab)	Keytab File Owner	Keytab File Group	File Permission (octal)
Apache Accumulo (accumulo)	accumulo16-ACCUMULO16_MASTER	accumulo	accumulo16	accumulo	accumulo	600
	accumulo16-ACCUMULO16_TRACER					
	accumulo16-ACCUMULO16_MONITOR					
	accumulo16-ACCUMULO16_GC					
	accumulo16-ACCUMULO16_TSERVER					
Flume (flume)	flume-AGENT	flume	flume	flume	flume	600
HBase (hbase)	hbase-REGIONSERVER	hbase	hbase	hbase	hbase	600
	hbase- HBASETHRIFTSERVER					
	hbase- HBASERESTSERVER					
	hbase-MASTER					
HDFS (hdfs)	hdfs-NAMENODE	hdfs, HTTP	hdfs	hdfs	hdfs	600
	hdfs-DATANODE					
	hdfs- SECONDARYNAMENODE					
Hive (hive)	hive-HIVESERVER2	hive	hive	hive	hive	600
	hive-WEBHCAT	HTTP	HTTP			
	hive-HIVEMETASTORE	hive	hive			
HttpFS (httpfs)	hdfs-HTTPFS	httpfs	httpfs	httpfs	httpfs	600
Hue (hue)	hue-KT_RENEWER	hue	hue	hue	hue	600
Impala (impala)	impala-STATESTORE	impala	impala	impala	impala	600
	impala-CATALOGSERVER					
	impala-IMPALAD					
Llama (llama)	impala-LLAMA	llama, HTTP	llama	llama	llama	600

Component (Unix User ID)	Service	Kerberos Principals	Filename (*.keytab)	Keytab File Owner	Keytab File Group	File Permission (octal)
Java KeyStore KMS (kms)	kms-KMS	HTTP	kms	kms	kms	600
Key Trustee KMS (kms)	kms-KEYTRUSTEE	HTTP	kms	kms	kms	600
MapReduce (mapred)	mapreduce-JOBTRACKER	mapred, HTTP	mapred	mapred	hadoop	600
	mapreduce- TASKTRACKER					
Oozie (oozie)	oozie-OOZIE_SERVER	oozie, HTTP	oozie	oozie	oozie	600
Search (solr)	solr-SOLR_SERVER	solr, HTTP	solr	solr	solr	600
Sentry (sentry)	sentry-SENTRY_SERVER	sentry	sentry	sentry	sentry	600
Spark (spark)	spark_on_yarn- SPARK_YARN_HISTORY_SERVER	spark	spark	spark	spark	600
YARN (yarn)	yarn-NODEMANAGER	yarn, HTTP	yarn	yarn	hadoop	644
	yarn- RESOURCEMANAGER					600
	yarn-JOBHISTORY					600
ZooKeeper (zookeeper)	zookeeper-server	zookeeper	zookeeper	zookeeper	zookeeper	600

# Authenticating Kerberos Principals in Java Code

This topic provides an example of how to authenticate a Kerberos principal in a Java application using the org.apache.hadoop.security.UserGroupInformation class.

The following code snippet authenticates the cloudera principal using the cloudera.keytab file:

```
// Authenticating Kerberos principal
System.out.println("Principal Authentication: ");
final String user = "cloudera@CLOUDERA.COM";
final String keyPath = "cloudera.keytab";
UserGroupInformation.loginUserFromKeytab(user, keyPath);
```


# Using a Web Browser to Access an URL Protected by Kerberos HTTP SPNEGO

To access an URL protected by Kerberos HTTP SPNEGO, use the following instructions for the browser you are using.

#### To configure Mozilla Firefox:

- 1. Open the low level Firefox configuration page by loading the about:config page.
- 2. In the Search text box, enter: network.negotiate-auth.trusted-uris
- 3. Double-click the network.negotiate-auth.trusted-uris preference and enter the hostname or the domain of the web server that is protected by Kerberos HTTP SPNEGO. Separate multiple domains and hostnames with a comma.

#### 4. Click OK.




## To configure Internet Explorer:

Follow the instructions given below to configure Internet Explorer to access URLs protected by


#### Configuring the Local Intranet Domain

- 1. Open Internet Explorer and click the Settings "gear" icon in the top-right corner. Select Internet options.
- 2. Select the Security tab.
- 3. Select the Local Intranet zone and click the Sites button.
- 4. Make sure that the first two options, Include all local (intranet) sites not listed in other zones and Include all sites that bypass the proxy server are checked.
- 5. Click Advanced and add the names of the domains that are protected by Kerberos HTTP SPNEGO, one at a time, to the list of websites. For example, myhost.example.com. Click Close.
- **6.** Click **OK** to save your configuration changes.



#### **Configuring Intranet Authentication**

- 1. Click the Settings "gear" icon in the top-right corner. Select Internet options.
- **2.** Select the **Security** tab.
- 3. Select the Local Intranet zone and click the Custom level... button to open the Security Settings Local Intranet Zone dialog box.
- 4. Scroll down to the User Authentication options and select Automatic logon only in Intranet zone.
- 5. Click OK to save these changes.



## **Verifying Proxy Settings**

You need to perform the following steps only if you have a proxy server already enabled.

- 1. Click the Settings "gear" icon in the top-right corner. Select Internet options.
- 2. Select the Connections tab and click LAN Settings.

- 3. Verify that the proxy server **Address** and **Port** number settings are correct.
- 4. Click Advanced to open the Proxy Settings dialog box.
- **5.** Add the Kerberos-protected domains to the **Exceptions** field.
- **6.** Click **OK** to save any changes.



### To configure Google Chrome:

If you are using Windows, use the Control Panel to navigate to the Internet Options dialogue box. Configuration changes required are the same as those described above for Internet Explorer.

On MacOS or Linux, add the --auth-server-whitelist parameter to the google-chrome command. For example, to run Chrome from a Linux prompt, run the google-chrome command as follows,

```
-----
> google-chrome --auth-server-whitelist = "hostname/domain"
```

# Troubleshooting Authentication Issues

Typically, if there are problems with security, Hadoop will display generic messages about the cause of the problem. This topic contains some sample Kerberos configuration files for your reference. It also has solutions to potential problems you might face when configuring a secure cluster:

# Sample Kerberos Configuration files: krb5.conf, kdc.conf, kadm5.acl

kdc.conf:

```
[kdcdefaults]
kdc\_ports = 88
kdc_tcp_ports = 88
[realms]
  EXAMPLE.COM = {
  #master_key_type = aes256-cts
  max_renewable_life = 7d 0h 0m 0s
  acl_file = /var/kerberos/krb5kdc/kadm5.acl
  dict_file = /usr/share/dict/words
  admin_keytab = /var/kerberos/krb5kdc/kadm5.keytab
\# note that aes256 is ONLY supported in Active Directory in a domain / forrest operating
at a 2008 or greater functional level.
# aes256 requires that you download and deploy the JCE Policy files for your JDK release
```

```
level to provide
# strong java encryption extension levels like AES256. Make sure to match based on the
encryption configured within AD for
# cross realm auth, note that RC4 = arcfour when comparing windows and linux encrypes
supported_encrypes = aes256-cts:normal aes128-cts:normal arcfour-hmac:normal
default_principal_flags = +renewable, +forwardable
}
```

#### krb5.conf:

```
[logging]
default = FILE:/var/log/krb5libs.log
kdc = FILE:/var/log/krb5kdc.log
admin_server = FILE:/var/log/kadmind.log
[libdefaults]
default_realm = EXAMPLE.COM
dns_lookup_realm = false
dns_lookup_kdc = false
ticket_lifetime = 24h
renew_lifetime = 7d
forwardable = true
# udp_preference_limit = 1
# set udp_preference_limit = 1 when TCP only should be
# used. Consider using in complex network environments when
# troubleshooting or when dealing with inconsistent
# client behavior or GSS (63) messages.
# uncomment the following if AD cross realm auth is ONLY providing DES encrypted tickets
# allow-weak-crypto = true
[realms]
AD-REALM.EXAMPLE.COM = {
 kdc = AD1.ad-realm.example.com:88
  kdc = AD2.ad-realm.example.com:88
  admin_server = AD1.ad-realm.example.com:749
  admin_server = AD2.ad-realm.example.com:749
  default_domain = ad-realm.example.com
EXAMPLE.COM = {
 kdc = kdc1.example.com:88
  admin_server = kdc1.example.com:749
  default_domain = example.com
# The domain_realm is critical for mapping your host domain names to the kerberos realms
# that are servicing them. Make sure the lowercase left hand portion indicates any
domains or subdomains
# that will be related to the kerberos REALM on the right hand side of the expression.
REALMs will
# always be UPPERCASE. For example, if your actual DNS domain was test.com but your
kerberos REALM is
# EXAMPLE.COM then you would have,
[domain_realm]
test.com = EXAMPLE.COM
#AD domains and realms are usually the same
ad-domain.example.com = AD-REALM.EXAMPLE.COM
ad-realm.example.com = AD-REALM.EXAMPLE.COM
```

#### kadm5.acl:

```
*/admin@HADOOP.COM *
cloudera-scm@HADOOP.COM * flume/*@HADOOP.COM
cloudera-scm@HADOOP.COM * hbase/*@HADOOP.COM
cloudera-scm@HADOOP.COM * hdfs/*@HADOOP.COM
cloudera-scm@HADOOP.COM * hive/*@HADOOP.COM
cloudera-scm@HADOOP.COM * httpfs/*@HADOOP.COM
```

```
cloudera-scm@HADOOP.COM * HTTP/*@HADOOP.COM
cloudera-scm@HADOOP.COM * hue/*@HADOOP.COM
cloudera-scm@HADOOP.COM * impala/*@HADOOP.COM
cloudera-scm@HADOOP.COM * mapred/*@HADOOP.COM
cloudera-scm@HADOOP.COM * oozie/*@HADOOP.COM
cloudera-scm@HADOOP.COM * solr/*@HADOOP.COM
cloudera-scm@HADOOP.COM * sqoop/*@HADOOP.COM
cloudera-scm@HADOOP.COM * yarn/*@HADOOP.COM
cloudera-scm@HADOOP.COM * zookeeper/*@HADOOP.COM
```

# Potential Security Problems and Their Solutions

This Troubleshooting appendix contains sample Kerberos configuration files, krb5.conf and kdc.conf for your reference. It also has solutions to potential problems you might face when configuring a secure cluster:

### Issues with Generate Credentials

Cloudera Manager uses a command called Generate Credentials to create the accounts needed by CDH for enabling authentication using Kerberos. The command is triggered automatically when you are using the Kerberos Wizard or making changes to your cluster that will require new Kerberos principals.

When configuring Kerberos, if CDH services don't start, and on the Cloudera Manager Home page you see a validation error, Role is missing Kerberos keytab, it means the Generate Credentials command failed. To see the output of the command, navigate to the Home page and click the All Recent Commands tab.

Here are some common error messages:

Problems	Possible Causes	Solutions
With Active Directory		
<pre>ldap_sasl_interactive_bind_s: Can't contact LDAP server (-1)</pre>	The Domain Controller specified is incorrect or LDAPS has not been enabled for it.	Verify the KDC configuration by going to the Cloudera Manager Admin Console and navigate to <b>Administration&gt; Settings&gt; Kerberos</b> . Also check that LDAPS is enabled for Active Directory.
ldap_add: Insufficient access (50)	The Active Directory account you are using for Cloudera Manager does not have permissions to create other accounts.	Use the Delegate Control wizard to grant permission to the Cloudera Manager account to create other accounts. You can also login to Active Directory as the Cloudera Manager user to check that it can create other accounts in your Organizational Unit.
With MIT KDC		
kadmin: Cannot resolve network address for admin server in requested realm while initializing kadmin interface.	The hostname for the KDC server is incorrect.	Check the kdc field for your default realm in krb5.conf and make sure the hostname is correct.

# Running any Hadoop command fails after enabling security.

#### Description:

A user must have a valid Kerberos ticket in order to interact with a secure Hadoop cluster. Running any Hadoop command (such as hadoop fs -ls) will fail if you do not have a valid Kerberos ticket in your credentials cache. If you do not have a valid ticket, you will receive an error such as:

```
11/01/04 12:08:12 WARN ipc.Client: Exception encountered while connecting to the server : javax.security.sasl.SaslException:
GSS initiate failed [Caused by GSSException: No valid credentials provided (Mechanism level: Failed to find any Kerberos tgt)]
Bad connection to FS. command aborted. exception: Call to nn-host/10.0.0.2:8020 failed on local exception: java.io.IOException: javax.security.sasl.SaslException: GSS initiate failed [Caused by GSSException: No valid credentials provided (Mechanism level: Failed to find any Kerberos tgt)]
```

#### Solution:

You can examine the Kerberos tickets currently in your credentials cache by running the klist command. You can obtain a ticket by running the kinit command and either specifying a keytab file containing credentials, or entering the password for your principal.

Java is unable to read the Kerberos credentials cache created by versions of MIT Kerberos 1.8.1 or higher.

### Description:

If you are running MIT Kerberos 1.8.1 or higher, the following error will occur when you attempt to interact with the Hadoop cluster, even after successfully obtaining a Kerberos ticket using kinit:

```
11/01/04 12:08:12 WARN ipc.Client: Exception encountered while connecting to the server : javax.security.sasl.SaslException:
GSS initiate failed [Caused by GSSException: No valid credentials provided (Mechanism level: Failed to find any Kerberos tgt)]
Bad connection to FS. command aborted. exception: Call to nn-host/10.0.0.2:8020 failed on local exception: java.io.IOException: javax.security.sasl.SaslException: GSS initiate failed [Caused by GSSException: No valid credentials provided (Mechanism level: Failed to find any Kerberos tgt)]
```

Because of a change [1] in the format in which MIT Kerberos writes its credentials cache, there is a bug [2] in the Oracle JDK 6 Update 26 and earlier that causes Java to be unable to read the Kerberos credentials cache created by versions of MIT Kerberos 1.8.1 or higher. Kerberos 1.8.1 is the default in Ubuntu Lucid and later releases and Debian Squeeze and later releases. (On RHEL and CentOS, an older version of MIT Kerberos which does not have this issue, is the default.)

### Footnotes:

- [1] MIT Kerberos change: http://krbdev.mit.edu/rt/Ticket/Display.html?id=6206
- [2] Report of bug in Oracle JDK 6 Update 26 and earlier: <a href="http://bugs.sun.com/bugdatabase/view\_bug.do?bug\_id=6979329">http://bugs.sun.com/bugdatabase/view\_bug.do?bug\_id=6979329</a>

#### Solution:

If you encounter this problem, you can work around it by running kinit—R after running kinit initially to obtain credentials. Doing so will cause the ticket to be renewed, and the credentials cache rewritten in a format which Java can read. To illustrate this:

```
$ klist
klist: No credentials cache found (ticket cache FILE:/tmp/krb5cc_1000)
```

```
$ hadoop fs -ls
11/01/04 13:15:51 WARN ipc.Client: Exception encountered while connecting to the server
 : javax.security.sasl.SaslException:
GSS initiate failed [Caused by GSSException: No valid credentials provided (Mechanism
level: Failed to find any Kerberos tgt)]
Bad connection to FS. command aborted. exception: Call to nn-host/10.0.0.2:8020 failed on local exception: java.io.IOException:
javax.security.sasl.SaslException: GSS initiate failed [Caused by GSSException: No
valid credentials provided (Mechanism level: Failed to find any Kerberos tgt)]
$ kinit
Password for atm@YOUR-REALM.COM:
$ klist
Ticket cache: FILE:/tmp/krb5cc_1000
Default principal: atm@YOUR-REALM.COM
Valid starting Expires Service principal 01/04/11 13:19:31 01/04/11 23:19:31 krbtgt/YOUR-REALM.COM@YOUR-REALM.COM
renew until 01/05/11 13:19:30
$ hadoop fs -ls
11/01/04 13:15:59 WARN ipc.Client: Exception encountered while connecting to the server
 : javax.security.sasl.SaslException:
GSS initiate failed [Caused by GSSException: No valid credentials provided (Mechanism
 level: Failed to find any Kerberos tgt)]
Bad connection to FS. command aborted. exception: Call to nn-host/10.0.0.2:8020 failed
on local exception: java.io.IOException:
javax.security.sasl.SaslException: GSS initiate failed [Caused by GSSException: No
valid credentials provided (Mechanism level: Failed to find any Kerberos tqt)]
$ kinit -R
$ hadoop fs -ls
Found 6 items
drwx---- - atm atm
                                 0 2011-01-02 16:16 /user/atm/.staging
```

#### Note:

This workaround for Problem 2 requires the initial ticket to be renewable. Note that whether or not you can obtain renewable tickets is dependent upon a KDC-wide setting, as well as a per-principal setting for both the principal in question and the Ticket Granting Ticket (TGT) service principal for the realm. A non-renewable ticket will have the same values for its "valid starting" and "renew until" times. If the initial ticket is not renewable, the following error message is displayed when attempting to renew the ticket:

```
kinit: Ticket expired while renewing credentials
```

### java.io.IOException: Incorrect permission

#### Description:

An error such as the following example is displayed if the user running one of the Hadoop daemons has a umask of 0002, instead of 0022:

```
at org.apache.hadoop.hdfs.MiniDFSCluster.startDataNodes(MiniDFSCluster.java:418)
       at org.apache.hadoop.hdfs.MiniDFSCluster.<init>(MiniDFSCluster.java:279)
       at org.apache.hadoop.hdfs.MiniDFSCluster.<init>(MiniDFSCluster.java:203)
org.apache.hadoop.test.MiniHadoopClusterManager.start(MiniHadoopClusterManager.java:152)
org.apache.hadoop.test.MiniHadoopClusterManager.run(MiniHadoopClusterManager.java:129)
org.apache.hadoop.test.MiniHadoopClusterManager.main(MiniHadoopClusterManager.java:308)
       at sun.reflect.NativeMethodAccessorImpl.invoke0(Native Method)
      at sun.reflect.NativeMethodAccessorImpl.invoke(NativeMethodAccessorImpl.java:39)
sun.reflect.DelegatingMethodAccessorImpl.invoke(DelegatingMethodAccessorImpl.java:25)
       at java.lang.reflect.Method.invoke(Method.java:597)
org.apache.hadoop.util.ProgramDriver$ProgramDescription.invoke(ProgramDriver.java:68)
       at org.apache.hadoop.util.ProgramDriver.driver(ProgramDriver.java:139)
       at org.apache.hadoop.test.AllTestDriver.main(AllTestDriver.java:83)
       at sun.reflect.NativeMethodAccessorImpl.invoke0(Native Method)
      at sun.reflect.NativeMethodAccessorImpl.invoke(NativeMethodAccessorImpl.java:39)
\verb|sun.reflect.DelegatingMethodAccessorImpl.invoke(DelegatingMethodAccessorImpl.java:25)| \\
       at java.lang.reflect.Method.invoke(Method.java:597)
       at org.apache.hadoop.util.RunJar.main(RunJar.java:186)
```

#### Solution:

Make sure that the umask for hdfs and mapred is 0022.

# A cluster fails to run jobs after security is enabled.

### **Description:**

A cluster that was previously configured to *not* use security may fail to run jobs for certain users on certain TaskTrackers (MRv1) or NodeManagers (YARN) after security is enabled due to the following sequence of events:

- 1. A cluster is at some point in time configured without security enabled.
- **2.** A user X runs some jobs on the cluster, which creates a local user directory on each TaskTracker or NodeManager.
- 3. Security is enabled on the cluster.
- **4.** User X tries to run jobs on the cluster, and the local user directory on (potentially a subset of) the TaskTrackers or NodeManagers is owned by the wrong user or has overly-permissive permissions.

The bug is that after step 2, the local user directory on the TaskTracker or NodeManager should be cleaned up, but isn't.

If you're encountering this problem, you may see errors in the TaskTracker or NodeManager logs. The following example is for a TaskTracker on MRv1:

```
10/11/03 01:29:55 INFO mapred.JobClient: Task Id : attempt_201011021321_0004_m_000011_0, Status : FAILED  
Error initializing attempt_201011021321_0004_m_000011_0: java.io.IOException: org.apache.hadoop.util.Shell$ExitCodeException: at org.apache.hadoop.mapred.LinuxTaskController.runCommand(LinuxTaskController.java:212)  
at org.apache.hadoop.mapred.LinuxTaskController.initializeUser(LinuxTaskController.java:442)  
at org.apache.hadoop.mapreduce.server.tasktracker.Localizer.initializeUserDirs(Localizer.java:272)
```

```
at org.apache.hadoop.mapred.TaskTracker.localizeJob(TaskTracker.java:963)
at org.apache.hadoop.mapred.TaskTracker.startNewTask(TaskTracker.java:2209)
at org.apache.hadoop.mapred.TaskTracker$TaskLauncher.run(TaskTracker.java:2174)
Caused by: org.apache.hadoop.util.Shell$ExitCodeException:
at org.apache.hadoop.util.Shell.runCommand(Shell.java:250)
at org.apache.hadoop.util.Shell.run(Shell.java:177)
at org.apache.hadoop.util.Shell$ShellCommandExecutor.execute(Shell.java:370)
at org.apache.hadoop.mapred.LinuxTaskController.runCommand(LinuxTaskController.java:203)
... 5 more
```

#### Solution:

Delete the mapred.local.dir Or yarn.nodemanager.local-dirs directories for that user across the cluster.

The NameNode does not start and KrbException Messages (906) and (31) are displayed.

### Description:

When you attempt to start the NameNode, a login failure occurs. This failure prevents the NameNode from starting and the following KrbException messages are displayed:

```
Caused by: KrbException: Integrity check on decrypted field failed (31) -
PREAUTH_FAILED \ \ \
```

#### and

```
Caused by: KrbException: Identifier doesn't match expected value (906)
```

Note:

These KrbException error messages are displayed only if you enable debugging output. See Appendix D - Enabling Debugging Output for the Sun Kerberos Classes.

#### Solution:

Although there are several possible problems that can cause these two KrbException error messages to display, here are some actions you can take to solve the most likely problems:

- If you are using CentOS/Red Hat Enterprise Linux 5.6 or later, or Ubuntu, which use AES-256 encryption by default for tickets, you must install the Java Cryptography Extension (JCE) Unlimited Strength Jurisdiction Policy File on all cluster and Hadoop user machines. For information about how to verify the type of encryption used in your cluster, see Step 3: If you are Using AES-256 Encryption, install the JCE Policy File on page 56. Alternatively, you can change your kdc.conf or krb5.conf to not use AES-256 by removing aes256-cts:normal from the supported\_enctypes field of the kdc.conf or krb5.conf file. Note that after changing the kdc.conf file, you'll need to restart both the KDC and the kadmin server for those changes to take affect. You may also need to recreate or change the password of the relevant principals, including potentially the TGT principal (krbtgt/REALM@REALM).
- In the [realms] section of your kdc.conf file, in the realm corresponding to HADOOP.LOCALDOMAIN, add (or replace if it's already present) the following variable:

```
supported_enctypes = des3-hmac-shal:normal arcfour-hmac:normal des-hmac-shal:normal
des-cbc-md5:normal des-cbc-crc:normal des-cbc-crc:v4 des-cbc-crc:afs3
```

### Authentication

 Recreate the hdfs keytab file and mapred keytab file using the -norandkey option in the xst command (for details, see <u>Step 4</u>: <u>Create and Deploy the Kerberos Principals and Keytab Files</u> on page 56).

```
kadmin.local: xst -norandkey -k hdfs.keytab hdfs/fully.qualified.domain.name
HTTP/fully.qualified.domain.name
kadmin.local: xst -norandkey -k mapred.keytab mapred/fully.qualified.domain.name
HTTP/fully.qualified.domain.name
```

# The NameNode starts but clients cannot connect to it and error message contains enctype code 18.

#### **Description:**

The NameNode keytab file does not have an AES256 entry, but client tickets do contain an AES256 entry. The NameNode starts but clients cannot connect to it. The error message doesn't refer to "AES256", but does contain an enctype code "18".

#### Solution:

Make sure the "Java Cryptography Extension (JCE) Unlimited Strength Jurisdiction Policy File" is installed or remove aes256-cts:normal from the supported\_enctypes field of the kdc.conf or krb5.conf file. For more information, see the first suggested solution above for Problem 5.

For more information about the Kerberos encryption types, see <a href="http://www.iana.org/assignments/kerberos-parameters.xml">http://www.iana.org/assignments/kerberos-parameters.xml</a>.

(MRv1 Only) Jobs won't run and TaskTracker is unable to create a local mapred directory.

#### Description:

The TaskTracker log contains the following error message:

```
11/08/17 14:44:06 INFO mapred.TaskController: main : user is atm
11/08/17 14:44:06 INFO mapred. TaskController: Failed to create directory
/var/log/hadoop/cache/mapred/mapred/local1/taskTracker/atm - No such file or directory
11/08/17 14:44:06 WARN mapred.TaskTracker: Exception while localization
java.io.IOException: Job initialization failed (20)
org.apache.hadoop.mapred.LinuxTaskController.initializeJob(LinuxTaskController.java:191)
        at org.apache.hadoop.mapred.TaskTracker$4.run(TaskTracker.java:1199)
        at java.security.AccessController.doPrivileged(Native Method)
        at javax.security.auth.Subject.doAs(Subject.java:396)
        at
org.apache.hadoop.security.UserGroupInformation.doAs(UserGroupInformation.java:1127)
        at org.apache.hadoop.mapred.TaskTracker.initializeJob(TaskTracker.java:1174)
        at org.apache.hadoop.mapred.TaskTracker.localizeJob(TaskTracker.java:1089)
        at org.apache.hadoop.mapred.TaskTracker.startNewTask(TaskTracker.java:2257)
       at org.apache.hadoop.mapred.TaskTracker$TaskLauncher.run(TaskTracker.java:2221)
Caused by: org.apache.hadoop.util.Shell$ExitCodeException:
        at org.apache.hadoop.util.Shell.runCommand(Shell.java:255)
        at org.apache.hadoop.util.Shell.run(Shell.java:182)
        at org.apache.hadoop.util.Shell$ShellCommandExecutor.execute(Shell.java:375)
        at
org.apache.hadoop.mapred.LinuxTaskController.initializeJob(LinuxTaskController.java:184)
        ... 8 more
```

### Solution:

Make sure the value specified for mapred.local.dirisidenticalin mapred-site.xml and taskcontroller.cfg. If the values are different, the error message above is returned.

# (MRv1 Only) Jobs won't run and TaskTracker is unable to create a Hadoop logs directory.

#### Description:

The TaskTracker log contains an error message similar to the following:

```
11/08/17 14:48:23 INFO mapred. TaskController: Failed to create directory
/home/atm/src/cloudera/hadoop/build/hadoop-0.23.2-cdh3u1-SNAPSHOT/logs1/userlogs/job_201108171441_0004
 - No such file or directory
11/08/17 14:48:23 WARN mapred.TaskTracker: Exception while localization
java.io.IOException: Job initialization failed (255)
        at
org.apache.hadoop.mapred.LinuxTaskController.initializeJob(LinuxTaskController.java:191)
        at org.apache.hadoop.mapred.TaskTracker$4.run(TaskTracker.java:1199)
        at java.security.AccessController.doPrivileged(Native Method)
        at javax.security.auth.Subject.doAs(Subject.java:396)
org.apache.hadoop.security.UserGroupInformation.doAs(UserGroupInformation.java:1127)
        at org.apache.hadoop.mapred.TaskTracker.initializeJob(TaskTracker.java:1174)
        at org.apache.hadoop.mapred.TaskTracker.localizeJob(TaskTracker.java:1089)
        at org.apache.hadoop.mapred.TaskTracker.startNewTask(TaskTracker.java:2257)
       at org.apache.hadoop.mapred.TaskTracker$TaskLauncher.run(TaskTracker.java:2221)
Caused by: org.apache.hadoop.util.Shell$ExitCodeException:
        at org.apache.hadoop.util.Shell.runCommand(Shell.java:255)
        at org.apache.hadoop.util.Shell.run(Shell.java:182)
        at org.apache.hadoop.util.Shell$ShellCommandExecutor.execute(Shell.java:375)
org.apache.hadoop.mapred.LinuxTaskController.initializeJob(LinuxTaskController.java:184)
        ... 8 more
```

#### Solution:

In MRv1, the default value specified for hadoop.log.dir in mapred-site.xml is /var/log/hadoop-0.20-mapreduce. The path must be owned and be writable by the mapred user. If you change the default value specified for hadoop.log.dir, make sure the value is identical in mapred-site.xml and taskcontroller.cfg. If the values are different, the error message above is returned.

After you enable cross-realm trust, you can run Hadoop commands in the local realm but not in the remote realm.

#### Description:

After you enable cross-realm trust, authenticating as a principal in the local realm will allow you to successfully run Hadoop commands, but authenticating as a principal in the remote realm will not allow you to run Hadoop commands. The most common cause of this problem is that the principals in the two realms either don't have the same encryption type, or the cross-realm principals in the two realms don't have the same password. This issue manifests itself because you are able to get Ticket Granting Tickets (TGTs) from both the local and remote realms, but you are unable to get a service ticket to allow the principals in the local and remote realms to communicate with each other.

### Solution:

On the local MIT KDC server host, type the following command in the kadmin.local or kadmin shell to add the cross-realm krbtgt principal:

```
kadmin: addprinc -e "<enc_type_list>"
krbtgt/YOUR-LOCAL-REALM.COMPANY.COM@AD-REALM.COMPANY.COM
```

where the <enc\_type\_list> parameter specifies the types of encryption this cross-realm krbtgt principal will support: AES, DES, or RC4 encryption. You can specify multiple encryption types using the parameter in the

#### Authentication

command above, what's important is that at least one of the encryption types parameters corresponds to the encryption type found in the tickets granted by the KDC in the remote realm. For example:

```
kadmin: addprinc -e "aes256-cts:normal rc4-hmac:normal des3-hmac-shal:normal"
krbtqt/YOUR-LOCAL-REALM.COMPANY.COM@AD-REALM.COMPANY.COM
```

### (MRv1 Only) Jobs won't run and can't access files in mapred.local.dir

### **Description:**

The TaskTracker log contains the following error message:

```
WARN org.apache.hadoop.mapred.TaskTracker: Exception while localization
java.io.IOException: Job initialization failed (1)
```

#### Solution:

- 1. Add the mapred user to the mapred and hadoop groups on all hosts.
- 2. Restart all TaskTrackers.

Users are unable to obtain credentials when running Hadoop jobs or commands.

### **Description:**

This error occurs because the ticket message is too large for the default UDP protocol. An error message similar to the following may be displayed:

```
13/01/15 17:44:48 DEBUG ipc.Client: Exception encountered while connecting to the server
 : javax.security.sasl.SaslException:
GSS initiate failed [Caused by GSSException: No valid credentials provided (Mechanism
level: Fail to create credential.
(63) - No service creds)]
```

#### Solution:

Force Kerberos to use TCP instead of UDP by adding the following parameter to libdefaults in the krb5.conf file on the client(s) where the problem is occurring.

```
[libdefaults]
udp_preference_limit = 1
```

If you choose to manage krb5.conf through Cloudera Manager, this will automatically get added to krb5.conf.

#### Note:

When sending a message to the KDC, the library will try using TCP before UDP if the size of the ticket message is larger than the setting specified for the udp\_preference\_limit property. If the ticket message is smaller than udp\_preference\_limit setting, then UDP will be tried before TCP. Regardless of the size, both protocols will be tried if the first attempt fails.

Request is a replay exceptions in the logs.

#### Description:

Symptom: The following exception shows up in the logs for one or more of the Hadoop daemons:

```
2013-02-28 22:49:03,152 INFO ipc.Server (Server.java:doRead(571)) - IPC Server listener
on 8020: readAndProcess threw exception javax.security.sasl.SaslException: GSS initiate
failed [Caused by GSSException: Failure unspecified at GSS-API level (Mechanism 1
javax.security.sasl.SaslException: GSS initiate failed [Caused by GSSException: Failure
unspecified at GSS-API level (Mechanism level: Request is a replay (34))]
com.sun.security.sasl.gsskerb.GssKrb5Server.evaluateResponse(GssKrb5Server.java:159)
       at org.apache.hadoop.ipc.Server$Connection.saslReadAndProcess(Server.java:1040)
        at org.apache.hadoop.ipc.Server$Connection.readAndProcess(Server.java:1213)
        at org.apache.hadoop.ipc.Server$Listener.doRead(Server.java:566)
        at org.apache.hadoop.ipc.Server$Listener$Reader.run(Server.java:363)
Caused by: GSSException: Failure unspecified at GSS-API level (Mechanism level: Request
is a replay (34))
        at sun.security.jgss.krb5.Krb5Context.acceptSecContext(Krb5Context.java:741)
        at sun.security.jgss.GSSContextImpl.acceptSecContext(GSSContextImpl.java:323)
        at sun.security.jgss.GSSContextImpl.acceptSecContext(GSSContextImpl.java:267)
        at
com.sun.security.sasl.gsskerb.GssKrb5Server.evaluateResponse(GssKrb5Server.java:137)
        ... 4 more
Caused by: KrbException: Request is a replay (34)
        at sun.security.krb5.KrbApReq.authenticate(KrbApReq.java:300)
        at sun.security.krb5.KrbApReq.<init>(KrbApReq.java:134)
      at sun.security.jgss.krb5.InitSecContextToken.<init>(InitSecContextToken.java:79)
        at sun.security.jgss.krb5.Krb5Context.acceptSecContext(Krb5Context.java:724)
        ... 7 more
```

In addition, this problem can manifest itself as performance issues for all clients in the cluster, including dropped connections, timeouts attempting to make RPC calls, and so on.

### Likely causes:

- Multiple services in the cluster are using the same kerberos principal. All secure clients that run on multiple machines should use unique kerberos principals for each machine. For example, rather than connecting as a service principal myservice@EXAMPLE.COM, services should have per-host principals such as myservice/host123.example.com@EXAMPLE.COM.
- Clocks not in synch: All hosts should run NTP so that clocks are kept in synch between clients and servers.

### CDH services fail to start

Possible Causes: Check that the encryption types are matched between your KDC and krb5.conf on all hosts.

Solution: If you are using AES-256, follow the instructions at Step 2: If You are Using AES-256 Encryption, Install the JCE Policy File on page 19 to deploy the JCE policy file on all hosts.

The goal of encryption is to ensure that only authorized users can view, use, or contribute to a data set. These security controls add another layer of protection against potential threats by end-users, administrators and other malicious actors on the network. Data protection can be applied at a number of levels within Hadoop:

- OS Filesystem-level Encryption can be applied at the Linux operating system file system level to cover all files in a volume. An example of this approach is <u>Cloudera Navigator Encrypt</u> (formerly Gazzang zNcrypt) which is available for Cloudera customers licensed for Cloudera Navigator. Navigator Encrypt operates at the Linux volume level, so it can encrypt cluster data inside and outside HDFS, such as temp/spill files, configuration files and metadata databases (to be used only for data related to a CDH cluster). Navigator Encrypt must be used with Navigator Key Trustee (formerly Gazzang zTrustee).
- HDFS-level Encryption applied by the HDFS client software. HDFS Data At Rest Encryption on page 201 operates at the HDFS folder level, enabling encryption to be applied only to the HDFS folders where it is needed. Cannot encrypt any data outside HDFS. To ensure reliable key storage (so that data is not lost), Navigator Key Trustee should be used, while the default Java keystore can be used for test purposes.
- **Network-level** Encryption can be applied to encrypt data just before it gets sent across a network and to decrypt it as soon as it is received. In Hadoop this means coverage for data sent from client user interfaces as well as service-to-service communication like remote procedure calls (RPCs). This protection uses industry-standard protocols such as SSL/TLS.

# SSL Certificates Overview

This topic will guide you through the different certificate strategies that you can employ on your cluster to allow SSL clients to securely connect to servers using trusted certificates or certificates issued by trusted authorities. The set of certificates required depends upon the certificate provisioning strategy you implement. The following strategies, among others, are possible:

- **Certificate per host:** In this strategy, you obtain one certificate for each host on which at least one SSL daemon role is running. All services on a given host will share this single certificate.
- Certificate for multiple hosts: Using the SubjectAltName extension, it is possible to obtain a certificate that is bound to a list of specific DNS names. One such certificate could be used to protect all hosts in the cluster, or some subset of the cluster hosts. The advantage of this approach over a wildcard certificate is that it allows you to limit the scope of the certificate to a specific set of hosts. The disadvantage is that it requires you to update and re-deploy the certificate whenever a host is added or removed from the cluster.
- Wildcard certificate: You may also choose to obtain a single wildcard certificate to be shared by all services on all hosts in the cluster. This strategy requires that all hosts belong to the same domain. For example, if the hosts in the cluster have DNS names node1.example.com ... node100.example.com, you can obtain a certificate for \*.example.com. Note that only one level of wildcarding is allowed; a certificate bound to \*.example.com will not work for a daemon running on node1.subdomain.example.com.
  - Note: Wildcard domain certificates and certificates using the SubjectAlternativeName extension are not supported.

When choosing an approach to certificate provisioning, bear in mind that SSL must be enabled for all core Hadoop services (HDFS, MapReduce, and YARN) as a group. For example, if you are running HDFS and YARN on your cluster, you cannot choose to enable SSL for HDFS, but not for YARN. You must enable it for both services, which implies that you must make certificates available to all daemon roles of both services. With a certificate-per-host strategy, for example, you will need to obtain a certificate for each host on which an HDFS or YARN daemon role is running.

# **Creating Certificates**

The following sections will walk you through obtaining certificates from commercial Certificate Authorities and creating self-signed test certificates.

# Using Keytool

Keytool is a utility for creating and managing certificates and cryptographic keys, and is part of the standard JDK distribution. The keytool executable usually resides in \$JAVA\_HOME/bin.

Keytool stores certificates and keys in a file known as a keystore. While several different keystore types are supported, by default keytool uses the Java KeyStore (JKS) format.

Java-based services such as HDFS, MapReduce, and YARN use the JKS format by default. For this reason it is particularly convenient to use keytool for managing keys and certificates for these services. In the following topics, we assume you are using keytool.

For additional information on keytool, refer the keytool documentation.

# Using OpenSSL

Python-based services such as Hue expect certificates and keys to be stored in PEM format. When managing certificates and keys for such services, you may find it convenient to use the openss1 tool.

Refer the openss1 documentation for more information.

# Obtaining a Production Certificate from a Commercial CA

Once you have decided on a certificate-provisioning strategy, and have determined which hosts require certificates, you will typically purchase the necessary certificates from a commercial Certificate Authority (CA). The procedure for applying for a certificate varies from one CA to another, but typically involves providing some form of proof that you are the legitimate owner of the domain name for which you are requesting a certificate, generating a key pair, and submitting a Certificate Signing Request (CSR) to the CA.

As noted above, you may find it convenient to use the Java keytool utility to generate your key pair and CSR, and to manage your certificates. The CA you choose will provide instructions for obtaining and installing a certificate; typically, there will be separate sets of instructions for different web and application servers. The instructions for Java-based servers (Tomcat, for example), will usually describe the following process comprising three keytool commands to obtain a certificate:

- 1. keytool -genkeypair to generate a public/private key pair and create the keystore.
- **2.** keytool -certreg to create the CSR.
- **3.** keytool -importcert to import the signed certificate into the keystore.

For example, to generate a public/private key pair for the domain name node1.example.com, you would use a command similar to the one shown below:

```
$ keytool -qenkeypair -keystore nodel.keystore -alias nodel \
-dname "CN=node1.example.com,O=Hadoop" -keyalg RSA \
-keysize 2048 -storepass changeme -keypass changeme
```

This command generates a pair of 2048-bit keys using the RSA key algorithm, one of several available. The keys are stored in a keystore file called node1.keystore, in a keystore entry identified by by the alias node1. The keystore password (which protects the keystore as a whole) and the key password (which protects the private key stored in the node1 entry) are set via the -storepass and -keypass options (respectively). -keypass must be set to the same password value as -storepass for Cloudera Manager to access the keystore.

To create a CSR, you would use a command similar to the following:

```
$ keytool -certreq -keystore nodel.keystore -alias nodel \
-storepass changeme -keypass changeme -file nodel.csr
```

This command generates the CSR, and stores it in a file called node1.csr. Once you've submitted your CSR to the CA, and received the CA's reply (containing the signed certificate), you will use the following keytool -importcert command to import the reply into your keystore:

```
$ keytool -importcert -keystore nodel.keystore -alias nodel \
-storepass changeme -keypass changeme -trustcacerts -file nodel.crt
```

Here we assume that the CA's reply is stored in the file node1.crt.

Important: This section describes a generic procedure using keytool to obtain a certificate from a commercial Certificate Authority. This procedure will differ from one CA to another and Cloudera recommends you consult your CA's documentation for more specifics.

# Creating Self-Signed Test Certificates

**Important:** Cloudera strongly recommends against the use of self-signed certificates in production clusters.

It is also possible to create your own test certificates. These certificates are typically self-signed; that is, they are signed by your own private key, rather than that of an external CA. Such test certificates are useful during testing and bringup of a cluster.

To generate a self-signed certificate, use keytool <code>-genkeypair</code>. (In addition to creating a public/private key pair, this command wraps the public key into a self-signed certificate.) For example, the following command creates a self-signed test certificate for the host node1.example.com, and stores it in a keystore named node1.keystore:

```
$ keytool -genkeypair -keystore nodel.keystore -keyalg RSA \
-alias nodel -dname "CN=nodel.example.com,O=Hadoop"
-storepass changeme -keypass changeme
```

By default, self-signed certificates as created above are only valid for 90 days. To increase this period, use the -validity <val\_days> parameter to specify the number of days for which the certificate should be considered valid.

# Creating Java Keystores and Truststores

Typically, a keystore is used in one of two distinct ways:

- The keystore contains private keys and certificates used by SSL servers to authenticate themselves to SSL clients. By convention, such files are referred to as keystores.
- When used as a truststore, the file contains certificates of trusted SSL servers, or of Certificate Authorities trusted to identify servers. There are no private keys in the truststore.
  - Note: The foregoing assumes that certificate-based authentication is being used in one direction only—that is, SSL servers are using certificates to authenticate themselves to clients. It is also possible for clients to authenticate themselves to servers using certificates. (This is known as mutual authentication.) Throughout this document, we assume that client certificates are not in use.

While all SSL clients must have access to a truststore, it is not always necessary to create and deploy truststores across a cluster. The standard JDK distribution includes a default truststore which is pre-provisioned with the root certificates of a number of well-known Certificate Authorities. If you do not provide a custom truststore, the Hadoop daemons load this default truststore. Therefore, if you are using certificates issued by a CA in the default truststore, you do not need to provide custom truststores. However, you must consider the following before you decide to use the default truststore:

 If you choose to use the default truststore, it is your responsibility to maintain it. You may need to remove the certificates of CAs you do not deem trustworthy, or add or update the certificates of CAs you trust. Use the keytool utility to perform these actions.

# Security Considerations for Keystores and Truststores

Note: While the strategy for certificate deployment you select will ultimately depend upon the security policies you wish to implement, the following guidelines may prove useful.

Because keystores contain private keys, while truststores do not, the security requirements for keystores are more stringent. In particular:

- Hadoop SSL requires that truststores and the truststore password be stored, in plaintext, in a configuration file that is readable by all.
- Keystore and key passwords are stored, in plaintext, in a file that is readable only by members of the appropriate group.

These considerations should inform your choice of which keys and certificates to store in the keystores and truststores you will deploy across your cluster.

 Keystores should contain a minimal set of keys and certificates. A reasonable strategy would be to create a unique keystore for each host, which would contain only the keys and certificates needed by the Hadoop SSL services running on the host. In most cases, the keystore would contain a single key/certificate entry.

**Modifying Keystores:** CDH services and processes must be restarted in case changes are made to a keystore. However, this is relatively rare since keystores do not need to be updated when hosts are added or deleted from a cluster.

- On the other hand, because truststores do not contain sensitive information, it is reasonable to create a single truststore for an entire cluster. On a production cluster, such a truststore would often contain a single CA certificate (or certificate chain), since you would typically choose to have all certificates issued by a single CA.
  - **Important:** Do not use the same password for truststores and keystores/keys.

Since truststore passwords are stored in the clear in files readable by all, doing so would compromise the security of the private keys in the keystore.

### **Creating Keystores**

Once you have settled on a storage plan for your keys and certificates, you can use keytool to create or update the necessary keystores and truststores. To create a new keystore with a certificate see <u>Creating Certificates</u> on page 157.

In many cases, you will already have created the set of keystores that you need. If you have followed the approach of creating a separate keystore for each private key and certificate, and wish to maintain this arrangement when deploying the keystores, no additional steps are required to prepare the keystores for deployment. If you wish to reorganize your keys and certificates into a different set of keystores, you can use keytool -importkeystore to transfer entries from one keystore to another.

# **Creating Truststores**

The steps involved in preparing the truststores to be used in your deployment depend on whether you have decided to use the default Java truststore, or to create custom truststores:

- If you are using the default truststore, you may need to add CA certificates (or certificate chains) to the truststore, or delete them from the truststore.
- If you are creating custom truststores, you will need to build the truststores by importing trusted certificates into new truststores. The trusted certificates can be CA certificates (typically downloaded from the CA's website), or self-signed certificates that you have created.

As shown in the examples below, when creating a truststore you must select a password. All truststore passwords for a given service must be the same. In practice, this restriction rarely comes into play, since it is only relevant when you wish to create distinct custom truststores for each host.

The following sections provide examples of the steps required for several common scenarios:

### Example 1: Adding a CA Certificate to the alternative Default Truststore

In this example, we assume that you have chosen to use the default Java truststore, but have obtained a certificate from a CA not included in the truststore. (This situation can also arise if the CA that issued your certificate has an entry in the default truststore, but the particular certificate product you purchased requires an alternate CA certificate chain.)

1. Locate the default truststore on your system. The default truststore is located in the \$JAVA\_HOME/jre/lib/security/cacerts file. This contains the default CA information shipped with the JDK. Create an alternate default file called jssecacerts in the same location as the cacerts file. You can now safely append CA certificates for any private or public CAs not present in the default cacerts file, while keeping the original file intact.

The alternate file will always be read unless the <code>javax.net.ssl.trustStore</code> flag is set in the arguments for the startup of the <code>java</code> process.

For our example, we will be following this recommendation by copying the default cacerts file into the new jssecacerts file.

```
$ cp $JAVA_HOME/jre/lib/security/cacerts \
$JAVA_HOME/jre/lib/security/jssecacerts
```

If you use a copy of the cacerts file, remember the default keystore password is changeit.

- 2. Import the CA certificate into the default truststore. Assuming that the file myCA-root.cer contains the CA's certificate, which you have previously downloaded from the CA's web site, the following command imports this certificate into the alternative default truststore.
  - **Note:** Test the trust relationship before you import any intermediary CA certificates. Trust should be derived from the root CA only. Import intermediary CA certificates only if necessary.

```
$ keytool -importcert -file myCA-root.cer -alias myCA \
-keystore /usr/java/default/jre/lib/security/jssecacerts \
-storepass changeit
```

When you give this command, you will be prompted to confirm that you trust the certificate. Be sure to verify that the certificate is genuine before importing it.

Important: Any updates you make to the default truststore must be made on all hosts in the cluster.

### Example 2: Creating a Custom Truststore Containing a Single CA Certificate Chain

In this example, we demonstrate how to use keytool to create a custom truststore. We assume all certificates were issued by a single CA, so a truststore containing the certificate chain for that CA will serve for all hosts in the cluster.

Our example certificate chain consists of a root certificate and a single intermediate certificate. We assume that you have downloaded these and saved them in the files <code>myCA-root.cer</code> and <code>myCA-intermediate.cer</code> (respectively). The steps below show the commands needed to build a custom truststore containing the root and intermediate certificates.

**1.** Import the root certificate and create the truststore:

```
$ keytool -importcert -keystore my.truststore -alias myCA-root \
-storepass trustchangeme -file myCA-root.cer
```

You will be prompted to confirm that the root certificate is trustworthy. Be sure to verify that the certificate is genuine before you import it.

2. Import the intermediate certificate into the truststore created in Step 1:

```
$ keytool -importcert -keystore my.truststore \
-alias myCA-intermediate -storepass trustchangeme \
-file myCA-intermediate.cer
```

### Example 3: Creating a Custom Truststore Containing Self-Signed Test Certificates

**Important:** Cloudera strongly recommends against the use of self-signed certificates in production clusters.

This example is particularly relevant when setting up a test cluster. We assume that you have generated a set of self-signed test certificates for the hosts in the cluster, and wish to create a single truststore that can be deployed on all hosts. Because the certificates are self-signed, we cannot simply construct a truststore containing a single certificate chain, as in the previous example. When a client receives a self-signed certificate from a server during the SSL handshake, it must be able to find the server's certificate in the truststore, since no other signing certificate exists to establish trust. Therefore, the truststore must contain all the test certificates.

We assume that the test certificates reside in keystores named node1.keystore ... node100.keystore, which were created following the steps described in Creating Self-Signed Test Certificates.

**1.** Export the test certificate for node1.example.com:

```
$ keytool -exportcert -keystore node1.keystore -alias node1 \
-storepass changeme -file nodel.cer
```

**2.** Import the test certificate into the truststore:

```
keytool -importcert -keystore my.truststore -alias nodel \
-storepass trustchangeme -file nodel.cer -noprompt
```

Here we specify the -noprompt option to suppress the prompt asking you to confirm that the certificate is trustworthy. Since you created the certificate yourself, this confirmation is unnecessary.

3. Repeat Steps 1 and 2 for node2.keystore ... node100.keystore.

### Private Key and Certificate Reuse Across Java Keystores and OpenSSL

This topic provides a quick tutorial on exporting/importing private keys for reuse from a Java keystore to OpenSSL and vice versa. Regardless of the procedure followed to create host private keys and certificates, sometimes it becomes necessary to reuse those private keys and certificates by other services on the same host. For example, if you used OpenSSL to create private keys and certificates for a service, you can reuse those keys for a Java-based service on the same host by converting them to the Java keystore format.

The documentation for Configuring TLS Security for Cloudera Manager describes both approaches to creating private keys, using Java keystore, and OpenSSL.

### Why Reuse a Private Key?

Certificate authorities generally revoke previous generations of certificates issued to a host. Hence, a host cannot have 2 sets of CA-issued certificates and have both be valid. Once a certificate is issued to a host, it then becomes

necessary to reuse the private key that requested the certificate, and the CA-issued certificate across different services, lava-based and otherwise.

Note: This following sections assume the default paths set up in Configuring TLS Encryption Only for Cloudera Manager.

# Conversion from Java Keystore to OpenSSL

First, use keytool to export the private key and certificate to a PKCS12 file as a transitional file format that can then be split up into individual key and certificate files by the openss1 command line. Replace cmhost and hostname in the commands below with the actual hostname of the server that is managing the certificate and keys.

```
$ keytool -importkeystore -srckeystore /opt/cloudera/security/jks/hostname-keystore.jks
-srcstorepass password -srckeypass password -destkeystore /tmp/hostname-keystore.pl2
-deststoretype PKCS12 -srcalias hostname -deststorepass password -destkeypass password
```

Now use openss1 to split the PKCS12 file created above into first, the certificate file, and then the private key file. While the CA-issued certificate can be used as is, the command has been provided here for completeness.

```
$ openssl pkcs12 -in /tmp/hostname-keystore.p12 -passin pass:password -nokeys \
-out /opt/cloudera/security/x509/hostname.pem
$ openssl pkcs12 -in /tmp/hostname-keystore.p12 -passin pass:password -nocerts \
-out /opt/cloudera/security/x509/hostname.key -passout pass:password
```

Note that the method above generates a key with a password. For services such as Impala that require keys without passwords, you can use the following command:

```
$ openssl rsa -in /opt/cloudera/security/x509/hostname.key \
-passin pass:password -out /opt/cloudera/security/x509/hostname.pem
```

# Conversion from OpenSSL to Java Keystore

First, convert the openss1 private key and certificate files into a PKCS12 file. The PKCS12 file can then be imported into a Java keystore file. Replace hostname in the commands below with the FQDN for the host whose certificate is being imported.

```
$ openss1 pkcs12 -export -in /opt/cloudera/security/x509/hostname.pem
-inkey /opt/cloudera/security/x509/hostname.key -out /tmp/hostname.p12
-name hostname -passin pass:password -passout pass:password
$ keytool -importkeystore -srckeystore /tmp/hostname.pl2 -srcstoretype PKCS12 \
-srcstorepass password -alias hostname -deststorepass password
-destkeypass password -destkeystore /opt/cloudera/security/jks/hostname-keystore.jks
```

# Configuring TLS Security for Cloudera Manager

### Important:

- Cloudera strongly recommends that you set up a fully functional CDH cluster and Cloudera Manager before you configure the Cloudera Manager Server and Agents to use TLS.
- When TLS is enabled, Cloudera Manager continues to accept HTTP requests on port 7180 (default) but immediately redirects clients to port 7183 for HTTPS connectivity.
- When Level 3 TLS is configured, to add new hosts running Agents, you must manually deploy the Cloudera Manager agent and daemon packages for your platform, issue a new certificate for the host, configure /etc/cloudera-scm-agent/config.ini to use SSL/TLS, and then bring the host online.
  - Or, you can disable TLS to add the host, configure the new host for TLS, and then re-enable with the proper configuration in place. Either approach is valid, based on your needs.
- For all hosts running Agents, Cloudera recommends that you first create the keystore in Java, and then export the key and certificate using openSSLfor use by the Agent or Hue.

Transport Layer Security (TLS) provides encryption and authentication in communication between the Cloudera Manager Server and Agents. Encryption prevents snooping, and authentication helps prevent problems caused by malicious servers or agents.

Cloudera Manager supports three levels of TLS security.

- Level 1 (Good) This level encrypts communication between the browser and Cloudera Manager, and between Agents and the Cloudera Manager Server. See Configuring TLS Encryption Only for Cloudera Manager on page 163 followed by Level 1: Configuring TLS Encryption for Cloudera Manager Agents on page 167 for instructions. Level 1 encryption prevents snooping of commands and controls ongoing communication between Agents and Cloudera Manager.
- Level 2 (Better) This level encrypts communication between the Agents and the Server, and provides strong verification of the Cloudera Manager Server certificate by Agents. See Level 2: Configuring TLS Verification of Cloudera Manager Server by the Agents on page 168. Level 2 provides Agents with additional security by verifying trust for the certificate presented by the Cloudera Manager Server.
- Level 3 (Best) This includes encrypted communication between the Agents and the Server, strong verification of the Cloudera Manager Server certificate by the Agents, and authentication of Agents to the Cloudera Manager Server using self-signed or CA-signed certs. See <u>Level 3: Configuring TLS Authentication of Agents</u> to the Cloudera Manager Server on page 170. Level 3 TLS prevents cluster Servers from being spoofed by untrusted Agents running on a host. Cloudera recommends that you configure Level 3 TLS encryption for untrusted network environments before enabling Kerberos authentication. This provides secure communication of keytabs between the Cloudera Manager Server and verified Agents across the cluster.
  - Important: You must finish configuring Level 1 and Level 2 TLS to configure Level 3 encryption. To enable TLS encryption for all connections between your Web browser running the Cloudera Manager Admin Console and the Cloudera Manager Server, see the first 2 steps of Level 1: Configuring TLS Encryption for Cloudera Manager Agents on page 167.

For details on how HTTPS communication is handled Cloudera Manager Agents and Cloudera Management Services daemons, see <u>HTTPS Communication in Cloudera Manager</u> on page 175.

### Configuring TLS Encryption Only for Cloudera Manager

Required Role: Cluster Administrator Full Administrator

Important: The sequence of steps described in the following topics to configure Level 1 through 3 TLS will each build upon the steps of the previous level. The procedure and examples provided in these topics, are based on this concept.

Before enabling TLS security for Cloudera Manager, you must create a keystore, submit a certificate-signing request, and install the issued certificate for the Server. You do this using the Oracle JDK keytool command-line tool. If you are using a Private CA, append its certificate (and any required intermediary certificates) to the alternate default truststore provided with the JDK for inherent trust. This process is described in detail in Configuring SSL Encryption in Cloudera Manager Deployments.

The table below shows the paths for managing certificates in the following examples. These paths persist during any upgrades and should be removed manually if the host is removed from a CDH cluster. Note that the folders and filepaths listed here can reside anywhere on the system and must be created on every host, especially as later sections move on to creating certificates for each host.

Note: Set permissions on the paths such that scm-user, hue, Hadoop service users (or groups), and root users can read the private key, certificate, and keystore and truststore files.

Example Property Values	Description
cmhost.sec.cloudera.com	FQDN for Cloudera Manager Server host.
/opt/cloudera/security	Base location for security-related files.
/opt/cloudera/security/x509	Location for openss1 key/, cert/and cacerts/ files to be used by the Cloudera Manager Agent and Hue.
/opt/cloudera/security/jks	Location for the Java-based keystore/ and truststore/ files for use by Cloudera Manager and Java-based cluster services.
/opt/cloudera/security/CAcerts	Location for CA certificates (root and intermediary/subordinate CAs). One PEM file per CA in the chain is required.

Important: You must use the Oracle JDK keytool. The following procedure requires use of the Cloudera-installed Oracle JDK (or JDK downloaded from Oracle). Do not mix with OpenJDK or between versions of JDK command line tools like keytool.

If necessary, set your PATH so that the Oracle JDKis first. For example:

```
$ export JAVA_HOME=/usr/java/jdk1.7.0_67-cloudera
$ export PATH=$JAVA_HOME/bin:$PATH
```

# Step 1: Create the Cloudera Manager Server Keystore, Generate a Certificate Request, and Install the Certificate

The following procedure assumes that a private Certificate Authority is used, and therefore trust must be established for that private CA. If a known public CA such as Verisign or GeoTrust is used, you may not need to explicitly establish trust for the issued certificates. Newer public CAs might not be present yet in the JDK default cacerts file. If you have problems with the import process (such as keytool error: java.lang.Exception: Failed to establish chain from reply), follow the steps for trusting private CAs below.

1. Assuming the paths documented in the table above have been created, use keytool to generate a Java keystore and Certificate Signing Request (CSR) for the Cloudera Manager Server. Replace cmhost and cmhost.sec.cloudera.com in the commands below with your hostname and FQDN. For example:

```
$ keytool -genkeypair -alias cmhost -keyalg RSA -keystore \
/opt/cloudera/security/jks/cmhost-keystore.jks -keysize 2048 -dname \
"CN=cmhost.sec.cloudera.com,OU=Support,O=Cloudera,L=Denver,ST=Colorado,C=US" \
-storepass password -keypass password
```

- -alias is a label used only in the keystore. In this example, the hostname is used for easy tracking and management of the key and certificate. Ensure that -alias is consistent across all your commands.
- -keyalg is the algorithm used to generate the key. RSA allows key lengths greater than 1024 bits for certificate requests.
- -dname allows you to provide the certificate subject as a single line. If not specified, you will be prompted for the values of the certificate subject information. In that case, use the host FQDN that agents and browsers will use to connect to in the subject First and Last name (CN) question prompt.
- /opt/cloudera/security/jks/cmhost-keystore.jks is an example path to the keystore where you store the keystore file and where the Cloudera Manager Server host can access it.
- -keypass must be set to the same password value as -storepass for Cloudera Manager to access the keystore.
- **2.** Generate a certificate signing request for the host (in this example, cmhost).

```
$ keytool -certreg -alias cmhost \
-keystore /opt/cloudera/security/jks/cmhost-keystore.jks \
-file /opt/cloudera/security/x509/cmhost.csr -storepass password \
-keypass password
```

3. Submit the .csr file created by the -certreg command to your Certificate Authority to obtain a server certificate. When possible, work with certificates in the default Base64 (ASCII) format. You can easily modify Base64-encoded files from .CER or .CRT to .PEM. The file is in ASCII format if you see the opening and closing lines as follows:

```
----BEGIN CERTIFICATE----
( the encoded certificate is represented by multiple lines of exactly 64 characters,
for the last line which can contain 64 characters or less.)
----END CERTIFICATE----
```

If your issued certificate is in binary (DER) format, adjust the commands according to the keytool documentation.

- 4. Copy the root CA certificate and any intermediary or subordinate CA certificates to /opt/cloudera/security/CAcerts/.
  - Important: For a private CA, you must import the private CA and intermediary or subordinate CA certificates into an alternative default JDK truststore jssecacerts, before importing them to your Java keystore.
  - a. Import the root CA certificate first, followed by any intermediary or subordinate CA certificates. Substitute \$JAVA\_HOME in the command below with the path for your Oracle JDK.

```
$ sudo cp $JAVA_HOME/jre/lib/security/cacerts
$JAVA_HOME/jre/lib/security/jssecacerts
$ sudo keytool -importcert -alias RootCA -keystore
$JAVA_HOME/jre/lib/security/jssecacerts \
-file /opt/cloudera/security/CAcerts/RootCA.cer -storepass changeit
$ sudo keytool -importcert -alias SubordinateCA -keystore \
```

```
$JAVA_HOME/jre/lib/security/jssecacerts \
-file /opt/cloudera/security/CAcerts/SubordinateCA.cer -storepass changeit
```

Repeat for as many subordinate or intermediary CA certificates as needed. The default -storepass for the cacerts file is changeit. After completing this step, copy the jssecacerts file created to the same path on all cluster hosts.

**b.** Import the Private CA certificates into your Java keystore file. Import the root CA certificate first.

```
$ keytool -importcert -trustcacerts -alias RootCA -keystore \
/opt/cloudera/security/jks/<cmhost-keystore>.jks -file \
/opt/cloudera/security/CAcerts/RootCA.cer -storepass password
$ keytool -importcert -trustcacerts -alias SubordinateCA -keystore \
/opt/cloudera/security/jks/<cmhost-keystore>.jks -file \
/opt/cloudera/security/CAcerts/SubordinateCA.cer -storepass password
```

Repeat for as many subordinate/intermediary CA certificates as needed.

5. Copy the signed certificate file provided to a location where it can be used by the Cloudera Manager Agents (and Hue if necessary).

```
$ cp certificate-file.cer /opt/cloudera/security/x509/cmhost.pem
```

Install it with the following keytool command:

```
$ keytool -importcert -trustcacerts -alias cmhost \
-file /opt/cloudera/security/x509/cmhost.pem \
-keystore /opt/cloudera/security/jks/cmhost-keystore.jks -storepass password
```

You must see the following response verifying that the certificate has been properly imported against its private key.

```
Certificate reply was installed in keystore
```

Because the issued certificate has been imported by the Java keystore, the original certificate-signing request (.CSR) and certificate files are no longer needed by Java services on that host, and the certificate and private key are now accessed through the keystore.

However, you still must export the private key from the Jave keystore to make the certificate usable by Hue and the Cloudera Manager Agent. For instructions on reusing certificates, see Private Key and Certificate Reuse Across Java Keystores and OpenSSL on page 161.

# Step 2: Enable HTTPS for the Cloudera Manager Admin Console and Specify Server Keystore **Properties**

- 1. Log into the Cloudera Manager Admin Console.
- Select Administration > Settings.
- **3.** Click the **Security** category.
- **4.** Configure the following TLS settings:

Property	Description
Path to TLS Keystore File	The complete path to the keystore file. In the example, this path would be:
	/opt/cloudera/security/jks/cmhost-keystore.jks
Keystore Password	The password for keystore: password
Use TLS Encryption for Admin Console	Check this box to enable TLS encryption for Cloudera Manager.

5. Click Save Changes to save the settings.

# Step 3: Specify SSL Truststore Properties for Cloudera Management Services

When enabling TLS for the Cloudera Manager UI, you must set the Java truststore location and password in the Cloudera Management Services configuration. If this is not done, roles such as the Host Monitor and Service Monitor will be unable to connect to Cloudera Manager and will not start.

- 1. Open the Cloudera Manager Administration Console and navigate to the Cloudera Management Service.
- 2. Click the Configuration tab.
- 3. Select Scope > Cloudera Management Service (Service-Wide).
- Select Category > Security.
- **5.** Edit the following SSL properties according to your cluster configuration.

Property	Description
SSL Client Truststore File Location	Path to the client truststore file used in HTTPS communication. The contents of this truststore can be modified without restarting the Cloudera Management Service roles. By default, changes to its contents are picked up within ten seconds.
SSL Client Truststore File Password	Password for the client truststore file.

- 6. Click Save Changes to commit the changes.
- 7. Restart the Cloudera Management Service. For more information, see HTTPS Communication in Cloudera Manager on page 175.

# Step 4: Restart the Cloudera Manager Server

Restart the Cloudera Manager Server by running service cloudera-scm-server restart from the Cloudera Manager host command prompt.

You should now be able to connect to the Cloudera Manager Admin Console using an HTTPS browser connection. If a private CA certificate or self-signed certificate is used, you must establish trust in the browser for your certificate. Certificates issued by public commercial CAs should be trusted by your browser and other Java or OpenSSL-based services.

For more information on establishing trust for certificates, see SSL Certificates Overview on page 156 or the relevant JDK documentation.

# Level 1: Configuring TLS Encryption for Cloudera Manager Agents

Required Role: Cluster Administrator Full Administrator

### Prerequisite:

You must have completed the steps described at Configuring TLS Encryption Only for Cloudera Manager.

### Step 1: Enable Agent Connections to Cloudera Manager to use TLS

In this step, you enable TLS properties for Cloudera Manager Agents and their connections to the Cloudera Manager Server. To configure agents to connect to Cloudera Manager over TLS, log into the Cloudera Manager Admin Console.

- Note: If you are using a private certificate authority to sign certificate requests, see information on establishing trust for this CA in Configuring TLS Encryption Only for Cloudera Manager on page 163.
- 1. Log into the Cloudera Manager Admin Console.
- Select Administration > Settings.

- 3. Click the **Security** category.
- 4. Configure the following TLS settings in the Cloudera Manager Server:

Property	Description
Use TLS Encryption for Agents	Enable TLS encryption for Agents connecting to the Server. The Agents will still connect to the defined agent listener port for Cloudera Manager (default: 7182). This property negotiates TLS connections to the service at this point.

5. Click Save Changes.

# Step 2: Enable and Configure TLS on the Agent Hosts

To enable and configure TLS, you must specify values for the TLS properties in the /etc/cloudera-scm-agent/config.ini configuration file on all Agent hosts.

1. On the Agent host, open the /etc/cloudera-scm-agent/config.ini configuration file and edit the following property:

Property	Description
use_tls	Specify 1 to enable TLS on the Agent, or 0 (zero) to disable TLS.

2. Repeat this step on every Agent host. You can copy the Agent's <code>config.ini</code> file across all hosts since this file by default does not have host specific information within it. If you modify properties such as <code>listening\_hostnameOrlistening\_ip</code> address in <code>config.ini</code>, you must configure the file individually for each host.

# Step 3: Restart the Cloudera Manager Server

Restart the Cloudera Manager Server with the following command to activate the TLS configuration settings.

\$ sudo service cloudera-scm-server restart

# Step 4: Restart the Cloudera Manager Agents

On every Agent host, restart the Agent:

\$ sudo service cloudera-scm-agent restart

# Step 5: Verify that the Server and Agents are Communicating

In the Cloudera Manager Admin Console, open the **Hosts** page. If the Agents heartbeat successfully, TLS encryption is working properly.

# Level 2: Configuring TLS Verification of Cloudera Manager Server by the Agents

Required Role: Cluster Administrator Full Administrator

This level of TLS security requires that you provide a server certificate that is signed, either directly or through a chain, by a trusted root certificate authority (CA), to the Cloudera Manager Server. You must also provide the certificate of the CA that signed the Server certificate. For test environments, you can use a self-signed server certificate.

Note: If the Cloudera Manager Server certificate or the associated CA certificate is missing or expired, Agents will not communicate with the Cloudera Manager Server.

# Step 1: Configure TLS encryption

If you have not done so, configure TLS encryption to use this level of security. For instructions, see Configuring TLS Encryption Only for Cloudera Manager on page 163 and Level 1: Configuring TLS Encryption for Cloudera Manager Agents on page 167.

# Step 2: Copy the CA Certificate or Cloudera Manager Server's .pem file to the Agents

- 1. Agents can verify the Cloudera Manager Server using either the Server certificate or the associated root CA certificate. Pick any one of the following approaches to proceed:
  - Copy the Cloudera Manager Server .pem file to the Agent host
    - 1. For verification by the Agent, copy the Server .pem file (for example, cmhost .pem ) to any directory on the Agent host. In the examples, this path is /opt/cloudera/security/x509/cmhost.pem.
    - 2. On the Agent host, open the /etc/cloudera-scm-agent/config.ini configuration file and edit the following properties.

Property	Description
verify_cert_file	Point this property to the copied .pem file on the Agent host; in this example, /opt/cloudera/security/x509/cmhost-cert.pem.
use_tls	Set this property to 1.

#### OR

- Copy the CA certificates to the Agent host
  - 1. If you have a CA-signed certificate, copy the root CA or intermediate CA certificates in PEM format to  $the \ Agent \ host. \ In \ the \ example, the \ CA \ certificates \ are \ copied \ to \ / \texttt{opt/cloudera/security/CAcerts/*}.$
  - 2. On the Agent host, open the /etc/cloudera-scm-agent/config.ini configuration file and edit the following properties.

Property	Description
verify_cert_dir	Point this property to the directory on the Agent host with the copied CA certificates; in the example, /opt/cloudera/security/CAcerts/.
use_tls	Set this property to 1.

• Note: When configuring the verify\_cert\_dir property, the openss-perl package is required to provide the c\_rehash command that is necessary to generate the Subject Name hash values that need to be linked to the certificates to make them usable. See the comments in the config.ini file for more information.

The following example is for RHEL-compatible systems. The package name for Debian-based systems is the same. After the package is installed, go to the CA certificate path and run the c\_rehash command. This generates symbolic links to the certificate in that location, with "." being the current path, as follows:

```
$ yum -y install openssl-perl
$ cd /opt/cloudera/security/CAcerts/
$ c_rehash .
    Doing .
    w2k8-1-root.pem => 4507f087.0
    w2k8-2-intermediary.pem => 082ba6df.0
$1s -1
total 8.0K
lrwxrwxrwx 1 root root 23 Oct 6 22:44 082ba6df.0 ->
w2k8-2-intermediary.pem
lrwxrwxrwx 1 root root 15 Oct 6 22:44 4507f087.0 -> w2k8-1-root.pem
-rw-r---- 1 root root 2.1K Oct 6 17:23 w2k8-1-root.pem
-rw-r---- 1 root root 2.8K Oct 6 17:23 w2k8-2-intermediary.pem
```

2. Based on the approach you select in step 1, repeat the steps on every Agent host. You can copy the Agent's config.ini file across all hosts. However, if you modify properties such as listening\_hostname or listening\_ip address in config.ini, you must configure config.ini for each host individually.

# Step 3: Restart the Cloudera Manager Agents

On every Agent host, restart the Agent:

```
$ sudo service cloudera-scm-agent restart
```

### Step 4: Restart the Cloudera Management Services

To restart the Cloudera Management Service from the Cloudera Manager Admin Console:

- 1. On the Home page, click to the right of the service name and select **Restart**.
- 2. Click Start on the next screen to confirm. When you see a Finished status, the service has restarted.

# Step 5: Verify that the Server and Agents are communicating

In the Cloudera Manager Admin Console, open the **Hosts** page. If the Agents heartbeat successfully, the Server and Agents are communicating. If not, check the Agent log

/var/log/cloudera-scm-agent/cloudera-scm-agent.log, which shows errors if the connection fails.

# Level 3: Configuring TLS Authentication of Agents to the Cloudera Manager Server

```
Required Role: Cluster Administrator Full Administrator
```

This is the highest level of TLS security supported for Cloudera Manager Server-Agent communications, and requires you to create private keys and certificate signing requests (CSR) for each cluster node. A certificate authority (CA) can then sign the CSR, providing a server certificate for each host. Agents then need to authenticate themselves to Cloudera Manager using this server certificate.

Self-signed certificates have not been documented since Cloudera does not recommend using them in enterprise production environments.

Note: Wildcard domain certificates and certificates using the SubjectAlternativeName extension are not supported.

# Step 1: Configure TLS encryption

If you have not already done so, you must configure TLS encryption to use this third level of security. For instructions, see Configuring TLS Encryption Only for Cloudera Manager on page 163 and Configuring TLS Encryption for Cloudera Manager.

# Step 2: Configure TLS Verification of Server Trust by Agents

If you have not already done so, you must configure TLS Verification of Server Trust by Agents. For instructions, see Configuring TLS Authentication of Server to Agents.

### Important:

Steps 3, 4, and 5 can be completed one of two ways, depending on the approach you choose to configuring TLS on your cluster.

- Approach A Use OpenSSL to create private keys and request CA-signed certificates for every Agent on your cluster. Approach A is faster if you only need to enable TLS for Cloudera Manager Server-Agent communication.
- Approach B Create a Java truststore file that contains the Agent and CA certificates, and authenticate Agents against this truststore file. If you plan to enable TLS communication for all CDH services cluster-wide, including Java-based components, consider using Approach B.

Irrespective of the path you select, it will still be possible to reuse OpenSSL private keys and certificates by exporting to a Java keystore and vice versa. For instructions, see Private Key and Certificate Reuse Across Java Keystores and OpenSSL on page 161.

After choosing an approach, follow steps 3-5 for all hosts in your cluster.

# Approach A: Using OpenSSL to Create Private Keys and Request Agent Certificates

If the Cloudera Manager Server is running Management Services or CDH components (and therefore, has a Cloudera Manager Agent installed), you do not need to re-create a private key for the Server host. Follow the steps in Private Key and Certificate Reuse Across Java Keystores and OpenSSL on page 161 to reuse the host certificate. Follow steps 3-5 for all remaining cluster hosts.

### Approach A Step 3: Generate the private key and certificate signing request for the Agent using OpenSSL.

Run the following command on the Agent, replacing hostname with your actual hostname. The -subj command line option allows you to provide the certificate subject as a single line. If you do not specify the certificate subject (-subj) as an argument, you will be prompted for the values of the certificate subject information. In that case, use the host FQDN that Agents will use to connect from in the subject First and Last name (CN) question prompt. Country (C) requires a 2 letter country code. The "/" is replaced with ", " in the actual CSR and private key file.

```
$ openssl req -subj
'/CN=hostname.sec.cloudera.com/OU=Support/O=Cloudera/L=Denver/ST=Colorado/C=US' \
-out /opt/cloudera/security/x509/hostname.csr -new -newkey rsa:2048 \
-keyout /opt/cloudera/security/x509/hostname.key -passout pass:password
```

password provides a password to protect the private key file. Keep the password in a safe place; you must provide a key password file to the Agent to complete configuration.

#### Approach A Step 4: Submit the certificate signing request to your CA and distribute the issued certificates.

The CSR file created (/opt/cloudera/security/x509/hostname.csr) is collected from cluster hosts for submission to the certificate authority (CA) for signing. In the example paths, you copy the issued CA-signed

certificate file to /opt/cloudera/security/x509 on each cluster host. For easy management and tracking of files, name the files in the hostname. pem format, replacing hostname with the actual hostname.

Note: Certificate file extensions of .cer, .crt, and .pem are interchangeable. Rename the files so they have a .pem extension, and can therefore be used by the Agent and Hue (or any other Python-based component).

The CSR can be examined with the following command:

```
$ openssl req -text -noout -verify -in /opt/cloudera/security/x509/hostname.csr
```

```
$ openssl x509 -in /opt/cloudera/security/x509/hostname.pem -text -noout
```

Approach A Step 5 (Optional): Import the OpenSSL private key and certificate into the per-host Java keystore.

Follow the steps in Private Key and Certificate Reuse Across Java Keystores and OpenSSL on page 161 for this step.

Important: If you are using Approach A, skip to <a href="step 6">step 6</a> to continue.

# Approach B: Creating a Java Keystore and Importing Signed Agent Certificates into it

If the Cloudera Manager Server is running Management Services or CDH components (and therefore, has a Cloudera Manager Agent installed), you do not need to re-create a private key for the Server host. Follow the steps in Private Key and Certificate Reuse Across Java Keystores and OpenSSL on page 161 to reuse the host certificate. Follow steps 3-5 for all remaining cluster hosts.

### Approach B - Step 3: Create a Java Keystore and private key for a host

Create a Java Keystore and private key files for an Agent host as follows:

```
$ keytool -genkeypair -alias hostname -keyalg RSA -keystore \
/opt/cloudera/security/jks/hostname-keystore.jks -keysize 2048 -dname \
"CN=cmhost.sec.cloudera.com,OU=Support,O=Cloudera,L=Denver,ST=Colorado,C=US" \
-storepass password -keypass password
```

password provides a password to protect the private key file. Note the password in a safe place; you must provide a key password file to the Agent to complete configuration.

### Approach B - Step 4: Generate a certificate signing request and install the issued certificate into the Java Keystore

1. Generate a certificate signing request (CSR) and submit it to your CA for a signed certificate.

```
$ keytool -certreq -alias hostname \
-keystore /opt/cloudera/security/jks/hostname-keystore.jks \
-file /opt/cloudera/security/x509/hostname.csr \
-storepass password -keypass password
```

2. If you are using a Private CA, first import the root CA certificate followed by the intermediary/subordinate CA certificates into the Java keystore created previously.

```
$ keytool -importcert -trustcacerts -alias RootCA -keystore \
/opt/cloudera/security/jks/hostname-keystore.jks -file \
/opt/cloudera/security/CAcerts/RootCA.cer -storepass password
```

Repeat the following for all subordinate/intermediary CA certificates presented.

```
$ keytool -importcert -trustcacerts -alias SubordinateCA -keystore \
/opt/cloudera/security/jks/hostname-keystore.jks -file \
/opt/cloudera/security/CAcerts/SubordinateCA.cer -storepass password
```

3. Copy the issued signed certificate file provided by your CA to the location from where it will be imported by the Cloudera Manager Agent and possibly Hue.

```
$ cp certificate-file.cer /opt/cloudera/security/x509/hostname.pem
```

4. Import the issued certificate file into the previously created Java keystore (.jks) with the following command:

```
$ keytool -import -trustcacerts -alias <hostname> \
-keystore /opt/cloudera/security/jks/<hostname>-keystore.jks \
-file /opt/cloudera/security/x509/<hostname>.pem -storepass password
```

# Approach B - Step 5: Export the private key from the Java keystore and convert it with OpenSSL for reuse by Agent

Follow the steps in Private Key and Certificate Reuse Across Java Keystores and OpenSSL on page 161.

# Step 6: Create a File that Contains the Password for the Key

The Agent reads the password from a text file, not from the command line. The password file allows you to use file permissions to protect the password. For our example the password file was created at, /etc/cloudera-scm-agent/agentkey.pw.

# Step 7: Configure the Agent with its Private Key and Certificate

1. On the Agent host, open the /etc/cloudera-scm-agent/config.ini configuration file and edit the following properties:

Property	Description
client_key_file	Name of the client key file.
client_keypw_file	Name of the client key password file, agentkey.pw.
client_cert_file	Name of the client certificate file.

2. Repeat these steps on every Agent host.

# Step 8: Verify that steps 3-7 Were Completed for every Agent Host in Your Cluster

Make sure each Agent's private key and certificate that you import into the Cloudera Manager Server's truststore is unique.

### Step 9: Create a Truststore by Importing CA and Agent Certificates

Perform this step on the Cloudera Manager server, where the new truststore is used to authenticate Agents.

Create a new truststore file (/opt/cloudera/security/jks/truststore.jks) and import the CA root and intermediary/subordinate certificates to this truststore. The new truststore functions like a keystore, containing only certificates and no private key.

Note: Alternatively, you can use the existing Cloudera Manager keystore, containing the CA intermediate and root certificates, as the truststore. However, Cloudera recommends separating the two files, because the new truststore can be copied to and used by all hosts in the cluster when enabling SSL/TLS for CDH services.

1. Create a trusted keystore using the keytool command and import the root CA certificate to this truststore.

```
$ keytool -importcert -noprompt -keystore /opt/cloudera/security/jks/truststore.jks
\
-alias root_CA -file root.crt -storepass password
```

2. Import any remaining intermediary/subordinate CA certificates into the truststore.

```
$ keytool -importcert -noprompt -keystore /opt/cloudera/security/jks/truststore.jks
-alias int_CA -file intermediate-CA.pem -storepass password
```

3. Save the hostname.pem certificate files from all cluster hosts in a single location. The Cloudera Manager Server can now import these host certificates (hostname.pem) into the new truststore.

```
$ keytool -keystore /opt/cloudera/security/jks/truststore.jks \
-importcert -alias hostname -file hostname.pem -storepass password
```

Consider creating a for loop on a list of host names to speed up this process.

```
$ for HOST in 'cat hostlist.txt'; do keytool -keystore
/opt/cloudera/security/jks/truststore.jks \
-importcert -alias $HOST -file $HOST.pem -storepass password
```

# Step 10: Enable Agent Authentication and Configure the Cloudera Manager Server to Use the New Truststore

- 1. Log into the Cloudera Manager Admin Console.
- Select Administration > Settings.
- 3. Click the Security category.
- **4.** Configure the following TLS settings:

Setting	Description
Use TLS Authentication of Agents to Server	Select this option to enable TLS authentication of Agents to the Server.
Path to Truststore	Specify the full filesystem path to the truststore located on the Cloudera Manager Server host; in the example, /opt/cloudera/security/jks/truststore.jks
Truststore Password	Specify the password for the truststore.

**5.** Click **Save Changes** to save the settings.

### Step 12: Restart the Cloudera Manager Server

```
$ sudo service cloudera-scm-server restart
```

### Step 13: Restart the Cloudera Manager Agents

On every Agent host, restart the Agent:

```
$ sudo service cloudera-scm-agent restart
```

# Step 14: Verify that the Server and Agents Are Communicating

In Cloudera Manager Admin Console, open the **Hosts** page. If the Agents heartbeat successfully, the Server and Agents are communicating. If they are not, you may see an error in the Server, such as a null CA chain error. This implies that either the truststore does not contain the Agent certificate, or the Agent is not presenting the

certificate. Check all of your settings, and check the Server log to verify that TLS and Agent validation have been enabled correctly.

# HTTPS Communication in Cloudera Manager

Both the Cloudera Manager Agent and the roles that make up the Cloudera Management Service use HTTPS to communicate with Cloudera Manager and CDH services. This topic aims to explain how the various aspects of HTTPS communication are handled by the Cloudera Manager Agents and the Cloudera Management Service

Cloudera Manager Agents use HTTPS to communicate with HBase, HDFS, Impala, MapReduce, and YARN to collect monitoring data.

# Cloudera Manager Agent

Configuring TLS communication between the Cloudera Manager Server and Agents is outlined in Configuring TLS Security for Cloudera Manager on page 163. You can configure the certificates available for server certificate verification using the verify\_cert\_dir parameter in the Agent config. ini file. See the comments in the config.ini file for a detailed explanation of this property. You can also use the existing value for the verify cert file parameter.

When the Cloudera Manager Agent communicates with CDH services using HTTPS:

- If verify\_cert\_file and/or verify\_cert\_dir are configured in the Agent config.ini, the Agent uses these settings to verify the server certificates. If these settings are not configured, no certificate verification occurs. If certificate verification is performed for the Cloudera Manager Server, it must also be performed for CDH daemons.
- An Agent never participates in mutual TLS authentication with any CDH service. Instead, each service has its own authentication scheme. Most services use Kerberos authentication, but Impala uses HTTP digest.

### **User Impact**

This depends on how you use certificates.

- If you do not need certificate verification, do not configure verify\_cert\_file or verify\_cert\_dir. However, this leaves you vulnerable to man-in-the-middle attacks.
- If you are using a CA-signed certificate, configure the Agent accordingly. Adding new services or enabling SSL/TLS on a service requires no changes to the Agent configuration because the CA verifies the certificates used by any new servers brought online.
- If you are using self-signed certificates, the certificate for each new service that uses HTTPS must be available to the Agent. Modify the file pointed to by verify cert\_file (Agent restart required), or the directory pointed to by verify cert dir, to contain the new certificate.

### Cloudera Management Services

Some Cloudera Management Service roles act as HTTPS clients when communicating with Cloudera Manager entities and CDH services.

You can verify server certificates in two ways:

- Configure a truststore through Cloudera Manager to perform certificate verification on the certificates of the servers with which it communicates. If this truststore is configured, it is used to verify server certificates. OR
- If no truststore is configured through Cloudera Manager, the default Java truststore (cacerts) is used to verify certificates.

The following table shows Cloudera Management Service roles that act as HTTPS clients as Cloudera Manager entities, and CDH services that communicate with them as HTTPS servers. This table does not depict the entirety of the roles' communication, only communications over HTTPS.

Table 7: HTTPS Communication Between Cloudera Management Service Roles and Cloudera Manager Entities

Roles as HTTPS Clients	Communicating HTTPS Servers
Activity Monitor	<ul> <li>Cloudera Manager Server</li> <li>JobTracker Web Server</li> <li>Oozie server (may involve the load balancer in an HA configuration)</li> </ul>
Host Monitor	Cloudera Manager Server
Service Monitor	<ul> <li>Cloudera Manager Server</li> <li>NameNode(s) Web Server(s)</li> <li>Impala StateStore Web Server</li> <li>YARN ResourceManager(s) Web Server(s)</li> <li>YARN JobHistory Web Server</li> <li>Oozie server (directly, not through the load balancer)</li> </ul>
Event Server	Cloudera Manager Server
Reports Manager	<ul><li>Cloudera Manager Server</li><li>NameNode(s) Web Servers</li></ul>

Note: The Cloudera Navigator roles also act as HTTPS clients, but are outside the scope of this document.

The Cloudera Management Service roles communicate using HTTPS as follows:

- If the Cloudera Management Service **SSL Client Truststore File Location** parameter is configured, the roles use this truststore to verify server certificates. If this parameter is not set, the default Java truststore is used to verify certificates. Without using safety valves, you cannot verify certificates for some Cloudera Management Service roles but not for others. Nor can you verify certificates for only a subset of the HTTPS communication by a role.
- The Cloudera Management Service roles never participate in mutual TLS authentication with any CDH service
  or with the Cloudera Manager Server. Instead, each service has its own authentication scheme: Kerberos for
  most services, HTTP digest for Impala. For the Cloudera Manager Server, this authentication is session-based.

### User Impact

This depends on how you use certificates:

- If you use a CA-signed certificate, configure the Cloudera Management Service SSL Client Truststore File Location parameter to point to a truststore that contains the CA certificate. Adding a new service or enabling TLS on an existing service requires no changes to the Cloudera Management Service configuration because the CA certificate verifies the certificates used by any new servers brought online. Alternatively, this CA-signed certificate can be added to the default Java truststore.
- If you are using self-signed certificates, the certificate for each new service that uses HTTPS must be available
  to the Agent.. You must modify the truststore pointed to by the Cloudera Management Service SSL Client
  Truststore File Location parameter. Truststore changes are required on each host on which a Cloudera
  Management Service daemon is running. Changes to the truststore do not require a role restart, and should
  be picked up within 10 seconds by default.

If the Cloudera Management Service **SSL Client Truststore File Location** is not used, the certificate must be made available in the default Java truststore. The Cloudera Management Service role must be restarted for this change to take effect.

# Troubleshooting SSL/TLS Connectivity

The openss1 tool can be run from the host that is running the Cloudera Manager Agent or client service that should be inspected for connectivity issues. You should also test whether the certificate in use by the host is recognized by a trusted CA during the TLS/SSL negotiation.

Use the following command to inspect the connection.

```
$ openssl s_client -connect [host.fqdn.name]:[port]
```

For example:

```
$ openssl s_client -connect test1.sec.cloudera.com:7183
```

A return code 0 means opensal was able to establish trust of the server through its library of trusted public CAs. If the certificate was self-signed or provided by a private CA it might be necessary to add the private CA or self-signed certificate to the truststore using the openssl command. Adding the path to the root CA, -CAfile </path/to/root-ca.pem>, should allow openss1 to verify your self-signed or private CA-signed certificate as follows:

```
$ openssl s_client -connect test1.sec.cloudera.com:7183 -CAfile \
/opt/cloudera/security/CAcerts/RootCA.pem
```

Note that providing only the Root CA certificate is necessary to eatablish trust for this test. The result from the command is successful when you see the return code 0 as follows:

```
Verify return code: 0 (ok)
```

By default, the Cloudera Manager Server writes logs to the

/etc/cloudera-scm-server/cloudera-scm-server.log file on startup. Successful start of the server process with the certificate will show logs similar to the following:

```
2014-10-06 21:33:47,515 INFO WebServerImpl:org.mortbay.log: jetty-6.1.26.cloudera.2
2014-10-06 21:33:47,572 INFO WebServerImpl:org.mortbay.log: Started
SslSelectChannelConnector@0.0.0:7183
2014-10-06 21:33:47,573 INFO WebServerImpl:org.mortbay.log: Started
SelectChannelConnector@0.0.0:7180
2014-10-06 21:33:47,573 INFO WebServerImpl:com.cloudera.server.cmf.WebServerImpl:
Started Jetty server.
```

# Configuring SSL for Cloudera Navigator

**Important:** The following instructions assume you have a Java keystore set up on the Navigator Metadata Server host.

To enable SSL communication between the Cloudera Navigator Metadata Server and its clients:

- 1. Open the Cloudera Manager Admin Console and navigate to the Cloudera Management Service.
- 2. Click the Configuration tab.
- 3. Select Scope > Navigator Metadata Server.
- Select Category > Security.
- **5.** Edit the following SSL properties according to your cluster configuration.

Property	Description
Enable TLS/SSL for Navigator Metadata Server	Encrypt communication between clients and Navigator Metadata Server using Transport Layer Security (TLS) (formerly known as Secure Socket Layer (SSL)).
SSL Keystore File Location	The path to the TLS/SSL keystore file containing the server certificate and private key used for TLS/SSL. Used when Navigator Metadata Server is acting as a TLS/SSL server. The keystore must be in JKS format.
SSL Keystore File Password	The password for the Navigator Metadata Server JKS keystore file.
SSL Keystore Key Password	The password that protects the private key contained in the JKS keystore used when Navigator Metadata Server is acting as a TLS/SSL server.

- 6. Click Save Changes to commit the changes.
- 7. Restart the Navigator Metadata server.
  - Note: Once you have enabled SSL, the Quick Links in Cloudera Manager pointing to the Cloudera Navigator UI will not work as they use HTTP, not HTTPS.

# Configuring SSL for Cloudera Management Services

To enable SSL communication between Cloudera Management Services, and CDH services and the Cloudera Manager Server:

- 1. Open the Cloudera Manager Administration Console and navigate to the Cloudera Management Service.
- 2. Click the Configuration tab.
- 3. Select Scope > Cloudera Management Service (Service-Wide).
- **4.** Select **Category** > **Security**.
- **5.** Edit the following SSL properties according to your cluster configuration.

Property	Description
SSL Client Truststore File Location	Path to the client truststore file used in HTTPS communication. The contents of this truststore can be modified without restarting the Cloudera Management Service roles. By default, changes to its contents are picked up within ten seconds.
SSL Client Truststore File Password	Password for the client truststore file.

- **6.** Click **Save Changes** to commit the changes.
- Restart the Cloudera Management Service. For more information, see <u>HTTPS Communication in Cloudera</u> <u>Manager</u> on page 175.

# Configuring Encryption for Hadoop Services

This section describes how to configure encryption for CDH services (HDFS, MapReduce, YARN, HBase, Hive, Impala, Hue and Oozie) focussing on SSL.

# **Prerequisites**

- Cloudera recommends securing a cluster using Kerberos authentication before enabling encryption such as SSL on a cluster. If you enable SSL for a cluster that does not already have Kerberos authentication configured, a warning will be displayed.
- The following sections assume that you have created all the certificates required for SSL communication. If not, for information on how to do this, see Creating Certificates.
- The certificates and keys to be deployed in your cluster should be organized into the appropriate set of keystores and truststores. For more information, see Creating Java Keystores and Truststores on page 158.

# Hadoop Services as SSL Servers and Clients

Hadoop services differ in their use of SSL as follows:

- HDFS, MapReduce, and YARN daemons act as both SSL servers and clients.
- HBase daemons act as SSL servers only.
- Oozie daemons act as SSL servers only.
- Hue acts as an SSL client to all of the above.

Daemons that act as SSL servers load the keystores when starting up. When a client connects to an SSL server daemon, the server transmits the certificate loaded at startup time to the client, which then uses its truststore to validate the server's certificate.

# Compatible Certificate Formats for Hadoop Components

Component	Compatible Certificate Format
HDFS	Java Keystore
MapReduce	Java Keystore
YARN	Java Keystore
Hue	PEM
Hive (for communication between Hive clients and HiveServer2)	Java Keystore
HBase	Java Keystore
Impala	PEM
Oozie	Java Keystore

# Configuring SSL for HDFS, YARN and MapReduce

Required Role: Configurator Cluster Administrator **Full Administrator** 

### Before You Begin

- Before enabling SSL, keystores containing certificates bound to the appropriate domain names will need to be accessible on all hosts on which at least one HDFS, MapReduce, or YARN daemon role is running.
- Since HDFS, MapReduce, and YARN daemons act as SSL clients as well as SSL servers, they must have access to truststores. In many cases, the most practical approach is to deploy truststores to all hosts in the cluster, as it may not be desirable to determine in advance the set of hosts on which clients will run.
- Keystores for HDFS, MapReduce and YARN must be owned by the hadoop group, and have permissions 0440 (that is, readable by owner and group). Truststores must have permissions 0444 (that is, readable by all)
- Cloudera Manager supports SSL configuration for HDFS, MapReduce and YARN at the service level. For each of these services, you must specify absolute paths to the keystore and truststore files. These settings apply

to all hosts on which daemon roles of the service in question run. Therefore, the paths you choose must be valid on all hosts.

An implication of this is that the keystore file names for a given service must be the same on all hosts. If, for example, you have obtained separate certificates for HDFS daemons on hosts node1.example.com and node2.example.com, you might have chosen to store these certificates in files called hdfs-node1.keystore and hdfs-node2.keystore (respectively). When deploying these keystores, you must give them both the same name on the target host — for example, hdfs.keystore.

• Multiple daemons running on a host can share a certificate. For example, in case there is a DataNode and an Oozie server running on the same host, they can use the same certificate.

### Configuring SSL for HDFS

- 1. Go to the HDFS service.
- 2. Click the Configuration tab.
- 3. Select Scope > HDFS (Service-Wide).
- 4. Select Category > Security.
- **5.** In the Search field, type **SSL** to show the SSL properties (found under the **Service-Wide** > **Security** category).
- **6.** Edit the following properties according to your cluster configuration:

Property	Description
Hadoop SSL Server Keystore File Location	Path to the keystore file containing the server certificate and private key.
Hadoop SSL Server Keystore File Password	Password for the server keystore file.
Hadoop SSL Server Keystore Key Password	Password that protects the private key contained in the server keystore.

- 7. If you are not using the default truststore, configure SSL client truststore properties:
  - Important: The HDFS properties below define a cluster-wide default truststore that can be overridden by YARN and MapReduce (see the Configuring SSL for YARN and MapReduce section below).

Property	Description
Cluster-Wide Default SSL Client Truststore Location	Path to the client truststore file. This truststore contains certificates of trusted servers, or of Certificate Authorities trusted to identify servers.
Cluster-Wide Default SSL Client Truststore Password	Password for the client truststore file.

8. Cloudera recommends you enable Web UI authentication for the HDFS service.

Enter web consoles in the Search field to bring up the Enable Authentication for HTTP Web-Consoles property (found under the Service-Wide>Security category). Check the property to enable web UI authentication.

Enable Authentication for HTTP Web-Consoles	Enables authentication for Hadoop HTTP web-consoles for all roles of this service.	
	• Note: This is effective only if security is enabled for the HDFS service.	

9. Click Save Changes.

10. Follow the procedure described in the following Configuring SSL for YARN and MapReduce section, at the end of which you will be instructed to restart all the affected services (HDFS, MapReduce and/or YARN).

#### Configuring SSL for YARN and MapReduce

Perform the following steps to configure SSL for the YARN or MapReduce services:

- 1. Navigate to the YARN or MapReduce service.
- **2.** Click the **Configuration** tab.
- 3. Select Scope > service name (Service-Wide).
- **4.** Select **Category** > **Security**.
- 5. Locate the <property name > property or search for it by typing its name in the Search box.
- 6. In the Search field, type SSL to show the SSL properties (found under the Service-Wide > Security category).
- **7.** Edit the following properties according to your cluster configuration:

Property	Description
Hadoop SSL Server Keystore File Location	Path to the keystore file containing the server certificate and private key.
Hadoop SSL Server Keystore File Password	Password for the server keystore file.
Hadoop SSL Server Keystore Key Password	Password that protects the private key contained in the server keystore.

8. Configure the following SSL client truststore properties for MRv1 or YARN only if you want to override the cluster-wide defaults set by the HDFS properties configured above.

Property	Description
SSL Client Truststore File Location	Path to the client truststore file. This truststore contains certificates of trusted servers, or of Certificate Authorities trusted to identify servers.
SSL Client Truststore File Password	Password for the client truststore file.

9. Cloudera recommends you enable Web UI authentication for the service in question.

Enter web consoles in the Search field to bring up the Enable Authentication for HTTP Web-Consoles property (found under the Service-Wide>Security category). Check the property to enable web UI authentication.

Enable Authentication for HTTP Web-Consoles	Enables authentication for Hadoop HTTP web-consoles for all roles of this service.
	Note: This is effective only if security is enabled for the HDFS service.

- **10.** Click **Save Changes** to commit the changes.
- 11. Navigate to the HDFS service
- 12. Click the Configuration tab.
- **13.** Type **Hadoop SSL Enabled** in the Search box.
- 14. Restart all affected services (HDFS, MapReduce and/or YARN), as well as their dependent services.
- 15. Select the Hadoop SSL Enabled property to enable SSL communication for HDFS, MapReduce, and YARN.

## Encryption

Property	Description
Hadoop SSL Enabled	Enable SSL encryption for HDFS, MapReduce, and YARN web Uls, as well as encrypted shuffle for MapReduce and YARN.

**16.** Click **Save Changes** to commit the changes.

# Configuring SSL for HBase

Required Role: Configurator Cluster Administrator **Full Administrator** 

#### Before You Begin

- Before enabling SSL, ensure that keystores containing certificates bound to the appropriate domain names will need to be accessible on all hosts on which at least one HBase daemon role is running.
- Keystores for HBase must be owned by the hbase group, and have permissions 0440 (that is, readable by owner and group).
- You must specify absolute paths to the keystore and truststore files. These settings apply to all hosts on which daemon roles of the HBase service run. Therefore, the paths you choose must be valid on all hosts.
- Cloudera Manager supports the SSL configuration for HBase at the service level. Ensure you specify absolute paths to the keystore and truststore files. These settings apply to all hosts on which daemon roles of the service in question run. Therefore, the paths you choose must be valid on all hosts.

An implication of this is that the keystore file names for a given service must be the same on all hosts. If, for example, you have obtained separate certificates for HBase daemons on hosts node1.example.com and node2.example.com, you might have chosen to store these certificates in files called hbase-node1.keystore and hbase-node2.keystore (respectively). When deploying these keystores, you must give them both the same name on the target host — for example, hbase.keystore.

#### Procedure

The steps for configuring and enabling SSL for HBase are similar to those for HDFS, YARN and MapReduce:

- 1. Go to the HBase service
- 2. Click the Configuration tab.
- Select Scope > HBASE (Service-Wide).
- 4. Select > Security.
- **5.** In the Search field, type **SSL** to show the HBase SSL properties.
- **6.** Edit the following SSL properties according to your cluster configuration:

#### **Table 8: HBase SSL Properties**

Property	Description
SSL Server Keystore File Location	Path to the keystore file containing the server certificate and private key.
SSL Server Keystore File Password	Password for the server keystore file.
SSL Server Keystore Key Password	Password that protects the private key contained in the server keystore.

### 7. Check the Web UI SSL Encryption Enabled property.

Web UI SSL Encryption	Enable SSL encryption for the HBase Master, Region Server, Thrift Server,
Enabled	and REST Server web Uls.

- 8. Click Save Changes.
- 9. Restart the HBase service.

# Configuring SSL for Flume Thrift Source and Sink

This topic describes how to enable SSL communication between Flume's Thrift source and sink.

The following tables list the properties that must be configured to enable SSL communication between Flume's Thrift source and sink instances.

#### **Table 9: Thrift Source SSL Properties**

Property	Description
ssl	Set to true to enable SSL encryption.
keystore	Path to a Java keystore file. Required for SSL.
keystore-password	Password for the Java keystore. Required for SSL.
keystore-type	The type of the Java keystore. This can be JKS or PKCS12.

#### **Table 10: Thrift Sink SSL Properties**

Property	Description
ssl	Set to true to enable SSL for this ThriftSink.
	When configuring SSL, you can optionally set the following truststore, truststore-password and truststore-type properties. If a custom truststore is not specified, Flume will use the default Java JSSE truststore (typically jssecacerts or cacerts in the Oracle JRE) to verify the remote Thrift Source's SSL credentials.
truststore	(Optional) The path to a custom Java truststore file.
truststore-password	(Optional) The password for the specified truststore.
truststore-type	(Optional) The type of the Java truststore. This can be JKS or any other supported Java truststore type.

Make sure you are configuring SSL for each Thrift source and sink instance. For example, to the existing flume.conf file, for agent a1, source r1, and sink k1, you would add the following properties:

```
# SSL properties for Thrift source s1
al.sources.rl.ssl=true
al.sources.rl.keystore=<path/to/keystore>
al.sources.rl.keystore-password=<keystore password>
al.sources.rl.keystore-type=<keystore type>
# SSL properties for Thrift sink k1
al.sinks.kl.ssl=true
al.sinks.kl.truststore=<path/to/truststore>
al.sinks.kl.truststore-password=<truststore password>
al.sinks.kl.truststore-type=<truststore type>
```

Configure these sets of properties for more instances of the Thrift source and sink as required. You can use either Cloudera Manager or the command line to edit the flume.conf file.

# Using Cloudera Manager

- 1. Open the Cloudera Manager Admin Console and navigate to the **Flume** service.
- **2.** Click the **Configuration** tab.

## Encryption

- 3. Select Scope > Agent.
- 4. Select Category > Main.
- 5. Edit the Configuration File property and add the Thrift source and sink properties for each Thrift source and sink instance as described above to the configuration file.
- 6. Click Save Changes to commit the changes.
- 7. Restart the Flume service.

# Using the Command Line

Navigate to the /etc/flume-ng/conf/flume.conf file and add the Thrift source and sink properties for each Thrift source and sink instance as described above.

# Configuring Encrypted Communication Between Hive and Client Drivers

This topic describes how to set up encrypted communication between HiveServer2 and its clients. Encrypting Hive communication depends on whether you are using Kerberos authentication for communications between HiveServer2 and JDBC/ODBC client drivers.

#### With Kerberos Enabled

With Kerberos authentication enabled, traffic between the Hive JDBC or ODBC drivers and HiveServer2 can be encrypted using SASL-QOP which allows you to preserve both data integrity (using checksums to validate message integrity) and confidentiality (by encrypting messages). For instructions, see Configuring Encrypted Client/Server Communication for Kerberos-enabled HiveServer2 Connections on page 184.

#### Without Kerberos Enabled

If you are using any alternate means of authentication, such as LDAP, between HiveServer2 and its clients, you can configure Secure Socket Layer (SSL) communication between them. For instructions, see Configuring Encrypted Client/Server Communication for non-Kerberos HiveServer2 Connections on page 185. For more information on configuring SSL truststores and keystores, see <u>SSL Certificates Overview</u> on page 156.

# Configuring Encrypted Client/Server Communication for Kerberos-enabled HiveServer2 Connections

With Kerberos authentication enabled, traffic between the Hive JDBC or ODBC drivers and HiveServer2 can be encrypted which allows you to preserve data integrity (using checksums to validate message integrity) and confidentiality (by encrypting messages). This can be enabled by setting the hive.server2.thrift.sasl.qop property in hive-site.xml. For example,

```
<name>hive.server2.thrift.sasl.qop</name>
<value>auth-conf</value>
<description>Sasl QOP value; one of 'auth', 'auth-int' and 'auth-conf'</description>
</property>
```

Valid settings for the value field are:

- auth: Authentication only (default)
- auth-int: Authentication with integrity protection
- auth-conf: Authentication with confidentiality protection

The parameter value that you specify above in the HiveServer2 configuration, should match that specified in the Beeline client connection JDBC URL. For example:

```
!connect jdbc:hive2://ip-10-5-15-197.us-west-2.compute.internal:10000/default;
principal=hive/_HOST@US-WEST-2.COMPUTE.INTERNAL;sasl.qop=auth-conf
```

# Configuring Encrypted Client/Server Communication for non-Kerberos HiveServer2 Connections

You can use either Cloudera Manager or the command-line to enable SSL encryption for non-Kerberized client connections to HiveServer2.

#### Using Cloudera Manager

The steps for configuring and enabling SSL for Hive are as follows:

- 1. Open the Cloudera Manager Admin Console and navigate to the Hive service.
- 2. Click the Configuration tab.
- 3. Select Scope > Hive (Service-Wide).
- 4. Select Category > Security.
- **5.** In the Search field, type **SSL** to show the Hive SSL properties.
- **6.** Edit the following SSL properties according to your cluster configuration.

## **Table 11: Hive SSL Properties**

Property	Description
Enable TLS/SSL for HiveServer2	Enable support for encrypted client-server communication using Secure Socket Layer (SSL) for HiveServer2 connections. Not applicable for Kerberos-enabled connections.
HiveServer2 TLS/SSL Server JKS Keystore File Location	Path to the SSL keystore.
HiveServer2 TLS/SSL Server JKS Keystore File Password	Password for the keystore.

- 7. Click Save Changes to commit the changes.
- 8. Restart the Hive service.

#### Using the Command Line

To enable SSL, add the following configuration parameters to hive-site.xml:

```
property>
 <name>hive.server2.use.SSL</name>
 <value>true</value>
  <description>enable/disable SSL </description>
</property>
property>
  <name>hive.server2.keystore.path
  <value>keystore-file-path</value>
  <description>path to keystore file</description>
</property>
property>
  <name>hive.server2.keystore.password</name>
  <value>keystore-file-password</value>
  <description>keystore password</description>
</property>
```

- The keystore must contain the server's certificate.
- The JDBC client must add the following properties in the connection URL when connecting to a HiveServer2 using SSL:

```
;ssl=true[;sslTrustStore=<Trust-Store-Path>;trustStorePassword=<Trust-Store-password>]
```

Make sure one of the following is true:

## Encryption

• *Either:* sslTrustStore points to the trust store file containing the server's certificate; for example:

```
jdbc:hive2://localhost:10000/default;ssl=true;\
sslTrustStore=/home/usr1/ssl/trust_store.jks;trustStorePassword=xyz
```

or: the Trust Store arguments are set using the Java system properties javax.net.ssl.trustStore
 and javax.net.ssl.trustStorePassword; for example:

```
java -Djavax.net.ssl.trustStore=/home/usr1/ssl/trust_store.jks
-Djavax.net.ssl.trustStorePassword=xyz \
MyClass jdbc:hive2://localhost:10000/default;ssl=true
```

For more information on using self-signed certificates and the Trust Store, see the Oracle Java SE keytool page.

# Configuring SSL for Hue

This topic describes how to enable SSL communication for Hue:

#### Hue as an SSL Client

```
Required Role: Configurator Cluster Administrator Full Administrator
```

Hue acts as an SSL client when communicating with Oozie, HBase and core Hadoop services. This means it may have to authenticate authenticate HDFS, MapReduce, and YARN daemons, as well as the HBase Thrift Server, and will need their certificates (or the relevant CA certificate) in its truststore.

#### Deploying the Hue Truststore:

You can create the Hue truststore by consolidating certificates of all SSL-enabled servers (or a single CA certificate chain) that Hue communicates with into one file. This will generally include certificates of all the HDFS, MapReduce and YARN daemons, and other SSL-enabled services such as Oozie..

The Hue truststore must be in PEM format whereas other services use JKS format by default. Hence, to populate the Hue truststore, you will need to extract the certificates from Hadoop's JKS keystores and convert them to PEM format. The following example assumes that hadoop-server.keystore contains the server certificate identified by alias foo-1.example.com and password example123.

```
$ keytool -exportcert -keystore hadoop-server.keystore -alias foo-1.example.com \
    -storepass example123 -file foo-1.cert
$ openssl x509 -inform der -in foo-1.cert > foo-1.pem
```

Once you've done this for each host in the cluster, you can concatenate the PEM files into one PEM file that can serve as the Hue truststore.

```
cat foo-1.pem foo-2.pem ... > huetrust.pem
```

Note: Ensure the final PEM truststore is deployed in a location that is accessible by the Hue service.

In Cloudera Manager, set REQUESTS\_CA\_BUNDLE to the path of the consolidated PEM file, huetrust.pem created above. To do this:

- 1. Open the Cloudera Manager Admin Console and navigate to the **Hue service**.
- 2. Click Configuration.
- **3.** Select **Scope** > **Hue** .
- Select Category > Advanced.
- 5. In the Search field, type Hue Service Environment to show the Hue Service Environment Advanced Configuration Snippet (Safety Valve) property.
- **6.** Edit the value and add the REQUESTS\_CA\_BUNDLE property set to the path of the Hue truststore in PEM format.

If more than one role group applies to this configuration, edit the value for the appropriate role group. See Modifying Configuration Properties.

- 7. Click Save Changes.
- 8. Restart the Hue service.

#### Hue as an SSL Server

Hue expects certificates and keys to be stored in PEM format. When managing certificates and keys for such services, using the openss1 tool may be more convenient. To configure Hue to use HTTPS, you can generate a private key and certificate as described in <u>Creating Certificates</u> on page 157.

Ensure secure session cookies for Hue have been enabled in hue.ini under [desktop]>[[session]].

```
[desktop]
 [[session]]
  secure=true
```

## Enabling SSL for the Hue Server using the Command Line

If you are not using Cloudera Manager, update the following properties in hue.ini under [desktop].

```
[desktop]
ssl_certificate=/path/to/server.cert
ssl_private_key=/path/to/server.key
ssl_password=<private_key_password>
```

#### Enabling SSL for the Hue Server in Cloudera Manager

#### Configurator Cluster Administrator Full Administrator Required Role:

Perform the following steps in Cloudera Manager to enable SSL for the Hue web server.

- 1. Open the Cloudera Manager Admin Console and navigate to the **Hue service**.
- 2. Click Configuration.
- 3. In the Search field, type SSL to show the Hue SSL properties.
- **4.** Edit the following properties according to your cluster configuration.

Property	Description
Enable HTTPS	Enable HTTPS for the Hue web server.
Local Path to SSL Certificate	Path to the SSL certificate on the host running the Hue web server.
Local Path to SSL Private Key	Path to the SSL private key on the host running the Hue web server.

If the private key has a password:

- a. In the Search field, type Hue Service Environment to show the Hue Service Environment Advanced Configuration Snippet (Safety Valve) property.
- **b.** Add the SSL password parameter as follows:

```
ssl_password=<private_key_password>
```

If more than one role group applies to this configuration, edit the value for the appropriate role group. See Modifying Configuration Properties.

- 5. Click Save Changes.
- **6.** Restart the Hue service.

For more details on configuring Hue with SSL, see this <u>blog post</u>.

# Enabling Hue SSL Communication with HiveServer2

By providing a CA certificate, private key, and public certificate, Hue can communicate with HiveServer2 over SSL. You can now configure the following properties in the [beeswax] section under [[ssl]] in the Hue configuration file, hue.ini.

enabled	Choose to enable/disable SSL communication for this server.
	Default: false
cacerts	Path to Certificate Authority certificates.
	Default:/etc/hue/cacerts.pem
key	Path to the private key file.
	Default:/etc/hue/key.pem
cert	Path to the public certificate file.
	Default:/etc/hue/cert.pem
validate	Choose whether Hue should validate certificates received from the server.
	Default: true

# Securing Database Connections using SSL

Connections vary depending on the database. Hue uses different clients to communicate with each database internally. They all specify a common interface known as the DBAPI version 2 interface. Client specific options, such as secure connectivity, can be passed through the interface. For example, for MySQL you can enable SSL communication by specifying the options configuration property under the desktop>[[database]] section in hue.ini.

```
[desktop]
  [[databases]]
    ...
    options={"ssl":{"ca":"/tmp/ca-cert.pem"}}
```

# Configuring SSL for Impala

Impala supports SSL network encryption, between Impala and client programs, and between the Impala-related daemons running on different nodes in the cluster. This feature is important when you also use other features such as Kerberos authentication or Sentry authorization, where credentials are being transmitted back and forth.

- Important:
  - You can use either Cloudera Manager or the following command-line instructions to complete this configuration.
  - This information applies specifically to CDH 5.4.x. If you use an earlier version of CDH, see the documentation for that version located at <u>Cloudera Documentation</u>.

# Using Cloudera Manager

To configure Impala to listen for Beeswax and HiveServer2 requests on SSL-secured ports:

- 1. Open the Cloudera Manager Admin Console and navigate to the Impala service.
- 2. Click the Configuration tab.
- 3. Select Scope > Impala (Service-Wide).

- Select Category > Security.
- **5.** Edit the following SSL properties:

**Table 12: Impala SSL Properties** 

Property	Description
Enable TLS/SSL for Impala Client Services	Encrypt communication between clients (like ODBC, JDBC, and the Impala shell) and the Impala daemon using Transport Layer Security (TLS) (formerly known as Secure Socket Layer (SSL)).
SSL/TLS Certificate for Clients	Local path to the X509 certificate that will identify the Impala daemon to clients during SSL/TLS connections. This file must be in PEM format.
SSL/TLS Private Key for Clients	Local path to the private key that matches the certificate specified in the Certificate for Clients. This file must be in PEM format.

- **6.** Click **Save Changes** to commit the changes.
- 7. Restart the Impala service.

For information on configuring SSL communication with the impala-shell interpreter, see Configuring SSL Communication for the Impala Shell on page 189.

# Using the Command Line

To enable SSL for Impala network communication, add both of the following flags to the impalad startup options:

- --ssl\_server\_certificate: the full path to the server certificate, on the local filesystem.
- --ssl\_private\_key: the full path to the server private key, on the local filesystem.

If either of these flags are set, both must be set. In that case, Impala starts listening for Beeswax and HiveServer2 requests on SSL-secured ports only. (The port numbers stay the same; see Ports Used by Impala for details.)

### Configuring SSL Communication for the Impala Shell

Typically, a client program has corresponding configuration properties in Cloudera Manager to verify that it is connecting to the right server. For example, with SSL enabled for Impala, you use the following options when starting the impala-shell interpreter:

- --ssl: enables SSL for impala-shell.
- --ca\_cert: the local pathname pointing to the third-party CA certificate, or to a copy of the server certificate for self-signed server certificates.

If --ca\_cert is not set, impala-shell enables SSL, but does not validate the server certificate. This is useful for connecting to a known-good Impala that is only running over SSL, when a copy of the certificate is not available (such as when debugging customer installations).

# Configuring SSL for Oozie

Required Role: Configurator Cluster Administrator Full Administrator

### Before You Begin

- Keystores for Oozie must be readable by the oozie user. This could be a copy of the Hadoop services' keystore with permissions 0440 and owned by the oozie group.
- Truststores must have permissions 0444 (that is, readable by all).
- Specify absolute paths to the keystore and truststore files. These settings apply to all hosts on which daemon roles of the Oozie service run. Therefore, the paths you choose must be valid on all hosts.
- In case there is a DataNode and an Oozie server running on the same host, they can use the same certificate.

# Encryption

For more information on obtaining signed certificates and creating keystores, see <u>SSL Certificates Overview</u> on page 156. You can also view the upstream documentation located <u>here</u>.

- Important:
  - You can use either Cloudera Manager or the following command-line instructions to complete this configuration.
  - This information applies specifically to CDH 5.4.x. If you use an earlier version of CDH, see the
    documentation for that version located at Cloudera Documentation.

# Using Cloudera Manager

The steps for configuring and enabling Hadoop SSL for Oozie are as follows:

- 1. Open the Cloudera Manager Admin Console and navigate to the **Oozie service**.
- 2. Click the Configuration tab.
- 3. Select Scope > All.
- 4. Select Category > All.
- **5.** In the Search field, type **SSL** to show the Oozie SSL properties.
- **6.** Edit the following SSL properties according to your cluster configuration.

#### **Table 13: Oozie SSL Properties**

Property	Description
Enable TLS/SSL for Oozie	Check this field to enable SSL for Oozie.
Oozie TLS/SSL Server Keystore File Location	Location of the keystore file on the local file system.
Oozie TLS/SSL Server JKS Keystore File Password	Password for the keystore.

- 7. Click Save Changes.
- 8. Restart the Oozie service.

## Using the Command Line

To configure the Oozie server to use SSL:

1. Stop Oozie by running

```
sudo /sbin/service oozie stop
```

- 2. To enable SSL, set the MapReduce version that the Oozie server should work with using the alternatives command.
  - Note: The alternatives command is only available on RHEL systems. For SLES, Ubuntu and Debian systems, the command is update-alternatives.

For RHEL systems, to use YARN with SSL:

```
alternatives --set oozie-tomcat-conf /etc/oozie/tomcat-conf.https
```

For RHEL systems, to use MapReduce (MRv1) with SSL:

```
alternatives --set oozie-tomcat-conf /etc/oozie/tomcat-conf.https.mrl
```

#### Important:

The OOZIE\_HTTPS\_KEYSTORE\_PASS variable must be the same as the password used when creating the keystore file. If you used a password other than password, you'll have to change the value of the OOZIE\_HTTPS\_KEYSTORE\_PASS variable in this file.

#### 3. Start Oozie by running

sudo /sbin/service oozie start

#### Connect to the Oozie Web UI using SSL (HTTPS)

Use https://oozie.server.hostname:11443/oozie though most browsers should automatically redirect you if you use http://oozie.server.hostname:11000/oozie.

# Additional Considerations when Configuring SSL for Oozie HA

Configure the load balancer to perform SSL pass-through. This will allow clients talking to Oozie to use the SSL certificate provided by the Oozie servers (so the load balancer will not need one). Consult your load balancer's documentation on how to configure this. Make sure to point the load balancer at the https://host:https\_port addresses for your Oozie servers. Clients can then connect to the load balancer at https://LOAD\_BALANCER\_HOST:PORT.

# Configuring SSL for Solr

Required Role: Configurator Cluster Administrator Full Administrator

## Before You Begin

- The Solr service must be running.
- Keystores for Solr must be readable by the solr user. This could be a copy of the Hadoop services' keystore with permissions 0440 and owned by the solr group.
- Truststores must have permissions 0444 (that is, readable by all).
- Specify absolute paths to the keystore and truststore files. These settings apply to all hosts on which daemon roles of the Solr service run. Therefore, the paths you choose must be valid on all hosts.
- In case there is a DataNode and a Solr server running on the same host, they can use the same certificate.

For more information on obtaining signed certificates and creating keystores, see SSL Certificates Overview on page 156. You can also view the upstream documentation located here.

#### Important:

- You can use either Cloudera Manager or the following command-line instructions to complete this configuration.
- This information applies specifically to CDH 5.4.x. If you use an earlier version of CDH, see the documentation for that version located at Cloudera Documentation.

# Configuring SSL for Solr Using Cloudera Manager

The steps for configuring and enabling Hadoop SSL for Search are as follows:

- 1. Open the Cloudera Manager Admin Console and navigate to the Solr service.
- 2. Click the Configuration tab.
- 3. Select Scope > All.
- **4.** Select **Category** > **All**.
- 5. In the Search field, type SSL to show the Solr SSL properties.

- **6.** Edit the following SSL properties according to your cluster configuration.
  - **Note:** These values must be the same for all hosts running the Solr role.

## **Table 14: Solr SSL Properties**

Property	Description
Enable TLS/SSL for Solr	Check this field to enable SSL for Solr.
Solr TLS/SSL Server Keystore File Location	The path to the TLS/SSL keystore file containing the server certificate and private key used for TLS/SSL. Used when Solr is acting as a TLS/SSL server. The keystore must be in JKS format.
Solr TLS/SSL Server JKS Keystore File Password	Password for the Solr JKS keystore.
Solr TLS/SSL Certificate Trust Store File	Required in case of self-signed or internal CA signed certificates. The location on disk of the trust store, in .jks format, used to confirm the authenticity of TLS/SSL servers that Solr might connect to. This is used when Solr is the client in a TLS/SSL connection. This trust store must contain the certificate(s) used to sign the service(s) being connected to. If this parameter is not provided, the default list of well-known certificate authorities is used instead.
Solr TLS/SSL Certificate Trust Store Password	The password for the Solr TLS/SSL Certificate Trust Store File. Note that this password is not required to access the trust store: this field can be left blank. This password provides optional integrity checking of the file. The contents of trust stores are certificates, and certificates are public information.

- 7. Click Save Changes to commit the changes.
- 8. Restart the service.

# Configuring SSL for Solr Using the Command Line

To configure the Search to use SSL:

1. Use solrctl to modify the urlScheme setting to specify https. For example:

```
solrctl --zk myZKEnsemble:2181/solr cluster --set-property urlScheme https
```

-----

2. Stop Solr by running

```
sudo /sbin/service solr stop
```

Edit /etc/default/solr to include the following environment variable settings:

```
SOLR_SSL_ENABLED=true
SOLR_KEYSTORE_PATH=<absolute_path_to_keystore_file>
SOLR_KEYSTORE_PASSWORD=<keystore_password>
#Following required only in case of self-signed or internal CA signed certificates
SOLR_TRUSTSTORE_PATH=<absolute_path_to_truststore_file>
SOLR_TRUSTSTORE_PASSWORD=<truststore_password>
```

4. Start Solr by running

```
sudo /sbin/service solr start
```

# Configuring SSL for the Key-Value Store Indexer Using Cloudera Manager

The steps for configuring and enabling Hadoop SSL for the Keystore Indexer are as follows:

- 1. Open the Cloudera Manager Admin Console and navigate to the Key-Value Store Indexer.
- 2. Click the Configuration tab.
- 3. Select Scope > All.
- **4.** Select **Category** > **All**.
- **5.** In the Search field, type **SSL** to show the Solr SSL properties.
- **6.** Edit the following SSL properties according to your cluster configuration.
  - **Note:** These values must be the same for all hosts running the Key-Value Store Indexer role.

### **Table 15: Key-Value Store SSL Properties**

Property	Description
HBase Indexer TLS/SSL Certificate Trust Store File	The location on disk of the trust store, in .jks format, used to confirm the authenticity of TLS/SSL servers that HBase Indexer might connect to. This is used when HBase Indexer is the client in a TLS/SSL connection. This trust store must contain the certificate(s) used to sign the service(s) being connected to. If this parameter is not provided, the default list of well-known certificate authorities is used instead.
HBase Indexer TLS/SSL Certificate Trust Store Password (Optional)	The password for the HBase Indexer TLS/SSL Certificate Trust Store File. Note that this password is not required to access the trust store: this field can be left blank. This password provides optional integrity checking of the file. The contents of trust stores are certificates, and certificates are public information.

#### 7. Restart the service.

# Configuring SSL for the Key-Value Store Indexer Using the Command Line

For every host running Key-Value Store Indexer server, specify Solr Trust Store details using the HBASE\_INDEXER\_OPTS environmental variable using following Java system properties:

- -Djavax.net.ssl.trustStore=<absolute\_path\_to\_truststore\_file>
- -Djavax.net.ssl.trustStorePassword=<truststore\_password> (Optional)

Restart the Key-Value Store Indexer servers to apply these changes.

## Configuring SSL for Flume Using Cloudera Manager

The steps for configuring and enabling Hadoop SSL for Flume are as follows:

- 1. Open the Cloudera Manager Admin Console and navigate to Flume.
- 2. Click the Configuration tab.
- 3. Select Scope > All.
- 4. Select Category > All.
- **5.** In the Search field, type **SSL** to show the Solr SSL properties.
- **6.** Edit the following SSL properties according to your cluster configuration.
  - **Note:** These values must be the same for all hosts running the Flume role.

Table 16: Key-Value Store SSL Properties

Property	Description
Flume TLS/SSL Certificate Trust Store File	The location on disk of the trust store, in .jks format, used to confirm the authenticity of TLS/SSL servers that Flume might connect to. This is used when Flume is the client in a TLS/SSL connection. This trust store must contain the certificate(s) used to sign the service(s) being connected to. If this parameter is not provided, the default list of well-known certificate authorities is used instead.
Flume TLS/SSL Certificate Trust Store Password (Optional)	The password for the Flume TLS/SSL Certificate Trust Store File. Note that this password is not required to access the trust store: this field can be left blank. This password provides optional integrity checking of the file. The contents of trust stores are certificates, and certificates are public information.

- 7. Click Save Changes to commit the changes.
- 8. Restart the service.

# Configuring SSL for Flume Using the Command Line

For every host running Flume agent, specify Solr Trust Store details using the FLUME\_AGENT\_JAVA\_OPTS environmental variable using following Java system properties:

- -Djavax.net.ssl.trustStore=<absolute\_path\_to\_truststore\_file>
- Djavax.net.ssl.trustStorePassword=<truststore\_password> (Optional)

Restart the Flume agents to apply these changes.

# Configuring HttpFS to use SSL

## Configure the HttpFS Server to use SSL (HTTPS)

1. Stop HttpFS by running

sudo /sbin/service hadoop-httpfs stop

- 2. To enable SSL, change which configuration the HttpFS server should work with using the alternatives command.
  - Note: The alternatives command is only available on RHEL systems. For SLES, Ubuntu and Debian systems, the command is update-alternatives.

\_\_\_\_\_

For RHEL systems, to use SSL:

Important:

The HTTPFS\_SSL\_KEYSTORE\_PASS variable must be the same as the password used when creating the keystore file. If you used a password other than password, you'll have to change the value of the HTTPFS\_SSL\_KEYSTORE\_PASS variable in /etc/hadoop-httpfs/conf/httpfs-env.sh.

**3.** Start HttpFS by running

sudo /sbin/service hadoop-httpfs start

## Connect to the HttpFS Web UI using SSL (HTTPS)

Use https://<httpfs\_server\_hostname>:14000/webhdfs/v1/though most browsers should automatically redirect you if you use http://<httpfs\_server\_hostname>:14000/webhdfs/v1/

#### Important:

If using a Self-Signed Certificate, your browser will warn you that it can't verify the certificate or something similar. You will probably have to add your certificate as an exception.

# Encrypted Shuffle and Encrypted Web Uls

Once you've enabled Kerberos, which provides for strong authentication, you can optionally enable network encryption if you so desire. CDH 5 supports the Encrypted Shuffle and Encrypted Web UIs feature that allows encryption of the MapReduce shuffle and web server ports using HTTPS with optional client authentication (also known as bi-directional HTTPS, or HTTPS with client certificates). It includes:

- Hadoop configuration setting for toggling the shuffle between HTTP and HTTPS.
- Hadoop configuration setting for toggling the Web UIs to use either HTTP or HTTPS.
- Hadoop configuration settings for specifying the keystore and truststore properties (location, type, passwords) that are used by the shuffle service, web server UIs and the reducers tasks that fetch shuffle data.
- A way to re-read truststores across the cluster (when a node is added or removed).

CDH 5 supports Encrypted Shuffle for both MRv1 and MRv2 (YARN), with common configuration properties used for both versions. The only configuration difference is in the parameters used to enable the features:

- For MRv1, setting the hadoop.ssl.enabled parameter in the core-site.xml file enables both the Encrypted Shuffle and the Encrypted Web Uls. In other words, the encryption toggling is coupled for the two features.
- For MRv2, setting the hadoop.ssl.enabled parameter enables the Encrypted Web UI feature; setting the mapreduce.shuffle.ssl.enabled parameter in the mapred-site.xml file enables the Encrypted Shuffle feature.

All other configuration properties apply to both the Encrypted Shuffle and Encrypted Web UI functionality.

When the Encrypted Web UI feature is enabled, all Web UIs for Hadoop components are served over HTTPS. If you configure the systems to require client certificates, browsers must be configured with the appropriate client certificates in order to access the Web Uls.

## Important:

When the Web UIs are served over HTTPS, you must specify https://as the protocol; there is no redirection from http://. If you attempt to access an HTTPS resource over HTTP, your browser will probably show an empty screen with no warning.

Most components that run on top of MapReduce automatically use Encrypted Shuffle when it is configured.

## Configuring Encrypted Shuffle and Encrypted Web Uls

To configure Encrypted Shuffle and Encrypted Web Uls, set the appropriate property/value pairs in the following:

- core-site.xml enables these features and defines the implementation
- mapred-site.xml enables Encrypted Shuffle for MRv2
- ssl-server.xml stores keystone and truststore settings for the server
- ssl-client.xml stores keystone and truststore settings for the client

#### core-site.xml Properties

To configure encrypted shuffle, set the following properties in the core-site.xml files of all nodes in the cluster:

Property	Default Value	Explanation
hadoop.ssl.enabled	false	For MRv1, setting this value to true enables both the Encrypted Shuffle and the Encrypted Web UI features. For MRv2, this property only enables the Encrypted WebUI; Encrypted Shuffle is enabled with a property in the mapred-site.xml file as described below.
hadoop.ssl.require.client.cert	false	When this property is set to true, client certificates are required for all shuffle operations and all browsers used to access Web UIs.
		Cloudera recommends that this be set to false. See Client Certificates on page 200.
badaan aal baatmana marifian		The best name verifier to provide for

hadoop.ssl.hostname.verifier	DEFAULT	The hostname verifier to provide for HttpsURLConnections. Valid values are: DEFAULT, STRICT, STRICT_I6, DEFAULT_AND_LOCALHOST and ALLOW_ALL.
hadoop.ssl.keystores.factory.class	org.apache.hadoop .security.ssl. FileBasedKeyStoresFactory	The KeyStoresFactory implementation to use.
hadoop.ssl.server.conf	ssl-server.xml	Resource file from which ssl server keystore information is extracted. This file is looked up in the classpath; typically it should be in the /etc/hadoop/conf/ directory.
hadoop.ssl.client.conf	ssl-client.xml	Resource file from which ssl server keystore information is extracted. This file is looked up in the classpath; typically it should be in the /etc/hadoop/conf/ directory.

#### Note:

All these properties should be marked as final in the cluster configuration files.

# Example

```
<name>hadoop.ssl.hostname.verifier</name>
      <value>DEFAULT</value>
      <final>true</final>
    </property>
   property>
      <name>hadoop.ssl.keystores.factory.class
      <value>org.apache.hadoop.security.ssl.FileBasedKeyStoresFactory</value>
      <final>true</final>
    </property>
    cproperty>
      <name>hadoop.ssl.server.conf</name>
      <value>ssl-server.xml</value>
     <final>true</final>
    </property>
    property>
      <name>hadoop.ssl.client.conf</name>
      <value>ssl-client.xml</value>
      <final>true</final>
    </property>
    property>
     <name>hadoop.ssl.enabled</name>
      <value>true</value>
    </property>
</configuration>
```

The cluster should be configured to use the Linux Task Controller in MRv1 and Linux container executor in MRv2 to run job tasks so that they are prevented from reading the server keystore information and gaining access to the shuffle server certificates. Refer to <u>Appendix B - Information about Other Hadoop Security Programs</u> for more information.

#### mapred-site.xml Property (MRv2 only)

To enable Encrypted Shuffle for MRv2, set the following property in the mapred-site.xml file on every node in the cluster:

Property	Default Value	Explanation
mapreduce.shuffle.ssl.enabled	false	If this property is set to true, encrypted shuffle is enabled. If this property is not specified, it defaults to the value of hadoop.ssl.enabled. This value can be false when hadoop.ssl.enabled is true but can not be true when hadoop.ssl.enabled is false

This property should be marked as final in the cluster configuration files.

#### Example:

```
<configuration>
   cproperty>
     <name>mapreduce.shuffle.ssl.enabled</name>
     <value>true</value>
     <final>true</final>
   </property>
</configuration>
```

#### **Keystore and Truststore Settings**

 $\label{thm:currently} File \texttt{BasedKeyStoresFactory} \ is \ the \ only \ \texttt{KeyStoresFactory} \ that \ is \ currently \ implemented. \ It \ uses \ properties \\ in \ the \ ssl-server. \ xml \ and \ ssl-client. \ xml \ files \ to \ configure \ the \ keystores \ and \ truststores.$ 

ssl-server.xml (Shuffle server and Web UI) Configuration

Use the following settings to configure the keystores and truststores in the ssl-server.xml file.

#### Note:

The ssl-server.xml should be owned by the hdfs or mapred Hadoop system user, belong to the hadoop group, and it should have 440 permissions. Regular users should not belong to the hadoop group.

Property	Default Value	Description
ssl.server.keystore.type	jks	Keystore file type
ssl.server.keystore.location	NONE	Keystore file location. The mapred user should own this file and have exclusive read access to it.
ssl.server.keystore.password	NONE	Keystore file password
ssl.server.keystore.keypassword	NONE	Key password
ssl.server.truststore.type	jks	Truststore file type
ssl.server.truststore.location	NONE	Truststore file location. The mapred user should own this file and have exclusive read access to it.
ssl.server.truststore.password	NONE	Truststore file password
ssl.server.truststore.reload.interval	10000	Truststore reload interval, in milliseconds

#### Example

```
<configuration>
<!-- Server Certificate Store -->
property>
 <name>ssl.server.keystore.type</name>
    <value>jks</value>
</property>
property>
 <name>ssl.server.keystore.location</name>
  <value>${user.home}/keystores/server-keystore.jks</value>
cproperty>
 <name>ssl.server.keystore.password</name>
  <value>serverfoo</value>
</property>
property>
 <name>ssl.server.keystore.keypassword</name>
  <value>serverfoo</value>
</property>
<!-- Server Trust Store -->
property>
  <name>ssl.server.truststore.type</name>
  <value>iks</value>
</property>
cproperty>
 <name>ssl.server.truststore.location</name>
  <value>${user.home}/keystores/truststore.jks</value>
</property>
```

```
cproperty>
  <name>ssl.server.truststore.password</name>
  <value>clientserverbar</value>
</property>
property>
 <name>ssl.server.truststore.reload.interval
  <value>10000</value>
</property>
</configuration>
```

#### ssl-client.xml (Reducer/Fetcher) Configuration

Use the following settings to configure the keystores and truststores in the ssl-client.xml file. This file should be owned by the mapred user for MRv1 and by the yarn user for MRv2; the file permissions should be 444 (read access for all users).

Property	Default Value	Description
ssl.client.keystore.type	jks	Keystore file type
ssl.client.keystore.location	NONE	Keystore file location. The mapred user should own this file and it should have default permissions.
ssl.client.keystore.password	NONE	Keystore file password
ssl.client.keystore.keypassword	NONE	Key password
ssl.client.truststore.type	jks	Truststore file type
ssl.client.truststore.location	NONE	Truststore file location. The mapred user should own this file and it should have default permissions.
ssl.client.truststore.password	NONE	Truststore file password
ssl.client.truststore.reload.interval	10000	Truststore reload interval, in milliseconds

#### Example

```
<configuration>
 <!-- Client certificate Store -->
 property>
   <name>ssl.client.keystore.type</name>
   <value>jks</value>
 </property>
 property>
   <name>ssl.client.keystore.location</name>
   <value>${user.home}/keystores/client-keystore.jks</value>
 </property>
 cproperty>
   <name>ssl.client.keystore.password</name>
    <value>clientfoo</value>
 </property>
 property>
   <name>ssl.client.keystore.keypassword</name>
   <value>clientfoo</value>
 </property>
 <!-- Client Trust Store -->
 cproperty>
   <name>ssl.client.truststore.type</name>
    <value>jks</value>
 </property>
```

# **Activating Encrypted Shuffle**

When you have made the above configuration changes, activate Encrypted Shuffle by re-starting all TaskTrackers in MRv1 and all NodeManagers in YARN.

#### Important:

Encrypted shuffle has a significant performance impact. You should benchmark this before implementing it in production. In many cases, one or more additional cores are needed to maintain performance.

#### **Client Certificates**

Client Certificates are supported but they do not guarantee that the client is a reducer task for the job. The Client Certificate keystore file that contains the private key must be readable by all users who submit jobs to the cluster, which means that a rogue job could read those keystore files and use the client certificates in them to establish a secure connection with a Shuffle server. The JobToken mechanism that the Hadoop environment provides is a better protector of the data; each job uses its own JobToken to retrieve only the shuffle data that belongs to it. Unless the rogue job has a proper JobToken, it cannot retrieve Shuffle data from the Shuffle server.

#### Important:

If your certificates are signed by a certificate authority (CA), you must include the complete chain of CA certificates in the keystore that has the server's key.

# **Reloading Truststores**

By default, each truststore reloads its configuration every 10 seconds. If a new truststore file is copied over the old one, it is re-read, and its certificates replace the old ones. This mechanism is useful for adding or removing nodes from the cluster, or for adding or removing trusted clients. In these cases, the client, TaskTracker or NodeManager certificate is added to (or removed from) all the truststore files in the system, and the new configuration is picked up without requiring that the TaskTracker in MRv1 and NodeManager in YARN daemons are restarted.

#### Note:

The keystores are not automatically reloaded. To change a keystore for a TaskTracker in MRv1 or a NodeManager in YARN, you must restart the TaskTracker or NodeManager daemon.

The reload interval is controlled by the ssl.client.truststore.reload.interval and ssl.server.truststore.reload.interval configuration properties in the ssl-client.xml and ssl-server.xml files described above.

# Debugging

#### Important:

Enable debugging only for troubleshooting, and then only for jobs running on small amounts of data. Debugging is very verbose and slows jobs down significantly.

To enable SSL debugging in the reducers, set -Djavax.net.debug=all in the mapred.reduce.child.java.opts property; for example:

You can do this on a per-job basis, or by means of a cluster-wide setting in mapred-site.xml.

To set this property in TaskTrackersfor MRv1, set it in hadoop-env.sh:

```
HADOOP_TASKTRACKER_OPTS="-Djavax.net.debug=all $HADOOP_TASKTRACKER_OPTS"
```

To set this property in NodeManagers for YARN, set it in hadoop-env.sh:

```
YARN_OPTS="-Djavax.net.debug=all $YARN_OPTS"
```

# HDFS Data At Rest Encryption

HDFS Encryption implements transparent, end-to-end encryption of data read from and written to HDFS, without requiring changes to application code. Because the encryption is end-to-end, data can be encrypted and decrypted only by the client. HDFS does not store or have access to unencrypted data or encryption keys. This supports both, at-rest encryption (data on persistent media, such as a disk) and in-transit encryption (data traveling over a network).

#### **Use Cases**

Data encryption is required by a number of different government, financial, and regulatory entities. For example, the healthcare industry has HIPAA regulations, the card payment industry has PCI DSS regulations, and the United States government has FISMA regulations. Transparent encryption in HDFS makes it easier for organizations to comply with these regulations. Encryption can also be performed at the application-level, but by integrating it into HDFS, existing applications can operate on encrypted data without changes. This integrated architecture implements stronger encrypted file semantics and better coordination with other HDFS functions.

#### Architecture

## **Encryption Zones**

An encryption zone is a directory in HDFS with all of its contents, that is, every file and subdirectory in it, encrypted. The files in this directory will be transparently encrypted upon write and transparently decrypted upon read. Each encryption zone is associated with a key which is specified when the zone is created. Each file within an encryption zone also has its own encryption/decryption key, called the Data Encryption Key (DEK). These DEKs are never stored persistently unless they are encrypted with the encryption zone's key. This encrypted DEK is known as the EDEK. The EDEK is then stored persistently as part of the file's metadata on the NameNode.

## Encryption

A key can have multiple key versions, where each key version has its own distinct key material (that is, the portion of the key used during encryption and decryption). Key rotation is achieved by modifying the encryption zone's key, that is, bumping up its version. Per-file key rotation is then achieved by re-encrypting the file's DEK with the new encryption zone key to create new EDEKs. An encryption key can be fetched either by its key name, returning the latest version of the key, or by a specific key version.

**Note:** An encryption zone cannot be created on top of an existing directory. Each encryption zone begins as an empty directory and distop can be used to add data to the zone.

# Key Management Server

A new service needs to be added to your cluster to store, manage, and access encryption keys, called the **Hadoop** Key Management Server (KMS). The KMS service is a proxy that interfaces with a backing key store on behalf of HDFS daemons and clients. Both the backing key store and the KMS implement the Hadoop KeyProvider client API.

Encryption and decryption of EDEKs happens entirely on the KMS. More importantly, the client requesting creation or decryption of an EDEK never handles the EDEK's encryption key (that is, the encryption zone key). When a new file is created in an encryption zone, the NameNode asks the KMS to generate a new EDEK encrypted with the encryption zone's key. When reading a file from an encryption zone, the NameNode provides the client with the file's EDEK and the encryption zone key version that was used to encrypt the EDEK. The client then asks the KMS to decrypt the EDEK, which involves checking that the client has permission to access the encryption zone key version. Assuming that is successful, the client uses the DEK to decrypt the file's contents. All the steps for read and write take place automatically through interactions between the DFSClient, the NameNode, and the KMS.

Access to encrypted file data and metadata is controlled by normal HDFS filesystem permissions. Typically, the backing key store is configured to only allow end-user access to the encryption zone keys used to encrypt DEKs. This means that EDEKs can be safely stored and handled by HDFS, since the hdfs user will not have access to EDEK encryption keys. This means that if HDFS is compromised (for example, by gaining unauthorized access to a superuser account), a malicious user only gains access to the ciphertext and EDEKs. This does not pose a security threat since access to encryption zone keys is controlled by a separate set of permissions on the KMS and key store.

For more details on configuring the KMS, see Configuring the Key Management Server (KMS) on page 209.

## Navigator Key Trustee

By default, the current implementation of HDFS encryption uses a local Java KeyStore for key management. This may not be sufficient for large enterprises where a more robust and secure key management solution is required. Navigator Key Trustee Server is a key store for managing encryption keys and other secure deposits.

In order to leverage the manageable, highly-available key management capabilities of the Navigator Key Trustee Server, Cloudera provides a custom KMS service, the Key Trustee KMS.

For more information on integrating Navigator Key Trustee with HDFS encryption, you can contact your Cloudera account team.

#### crypto Command Line Interface

#### createZone

Use this command to create a new encryption zone.

```
-createZone -keyName <keyName> -path <path>
```

#### Where:

path: The path of the encryption zone to be created. It must be an empty directory.

• keyName: Name of the key to use for the encryption zone.

#### listZones

List all encryption zones. This command requires superuser permissions.

```
-listZones
```

# Enabling HDFS Encryption on a Cluster

# Required Role: Full Administrator

The following sections will guide you through enabling HDFS encryption on your cluster, using the default Java KeyStore KMS. If you want to use Navigator Key Trustee Server, and not the default JavaKeyStoreProvider, to store HDFS encryption keys, contact your Cloudera account team.

# Optimizing for HDFS Data at Rest Encryption

CDH implements the Advanced Encryption Standard New Instructions (AES-NI), which provide substantial performance improvements. To get these improvements, you need a recent version of libcrytpto.so on HDFS and MapReduce client hosts -- that is, any host from which you originate HDFS or MapReduce requests. Many OS versions have an older version of the library that does not support AES-NI. The instructions that follow tell you what you need to do for each OS version that CDH supports.

#### RHEL/CentOS 6.5 or later

The installed version of libcrypto.so supports AES-NI, but you need to install the openssl-devel package on all clients:

```
$ sudo yum install openssl-devel
```

#### RHEL/CentOS 6.4 or earlier 6.x versions, or SLES 11

Download and extract a newer version of libcrypto.so from a CentOS 6.5 repository and install it on all clients in /var/lib/hadoop/extra/native/:

**1.** Download the latest version of the openss1 package. For example:

```
http://mirror.centos.org/centos/6/os/x86_64/Packages/openssl-1.0.1e-30.el6.x86_64.rpm
```

The libcrytpto.so file in this package can be used on SLES 11 as well as RHEL/CentOS.

**2.** Decompress the files in the package, but **do not** install it:

```
$ rpm2cpio openssl-1.0.1e-30.el6.x86 64.rpm | cpio -idmv
```

3. If you are using parcels, create the /var/lib/hadoop/extra/native/directory:

```
$ sudo mkdir -p /var/lib/hadoop/extra/native
```

**4.** Copy the shared library into /var/lib/hadoop/extra/native/. Name the target file libcrypto.so, with no suffix at the end, exactly as in the command that follows.

```
$ sudo cp ./usr/lib64/libcrypto.so.1.0.le /var/lib/hadoop/extra/native/libcrypto.so
```

#### RHEL/CentOS 5

In this case, you need to build libcrypto.so and copy it to all clients:

**1.** On one client, compile and install openss1 from source:

```
$ wget http://www.openssl.org/source/openssl-1.0.1j.tar.gz
$ cd openssl-1.0.1j
$ ./config --shared --prefix=/opt/openssl-1.0.1j
$ sudo make install
```

If you are using parcels, create the /var/lib/hadoop/extra/native/directory:

```
______
$ sudo mkdir -p /var/lib/hadoop/extra/native
i.....
```

3. Copy the files into /var/lib/hadoop/extra/native/:

```
$ sudo cp /opt/openssl-1.0.1j/lib/libcrypto.so /var/lib/hadoop/extra/native
```

4. Copy the files to the remaining clients using a utility such as rsync

#### Debian Wheezy

The installed version of libcrypto.so supports AES-NI, but you need to install the libssl-devel package on all clients:

```
$ sudo apt-get install libssl-dev
```

#### Ubuntu Precise and Ubuntu Trusty

Install the libssl-devel package on all clients:

```
$ sudo apt-get install libssl-dev
```

#### Testing if encryption optimization works

To verify that a client host is ready to make use of the AES-NI instruction set optimization for HDFS encryption at rest, use the following command:

```
hadoop checknative
```

You should see a response such as the following:

```
______
14/12/12 13:48:39 INFO bzip2.Bzip2Factory: Successfully loaded & initialized native-bzip2
library system-native14/12/12 13:48:39 INFO zlib.ZlibFactory: Successfully loaded & initialized native-zlib library
Native library checking:
hadoop: true /usr/lib/hadoop/lib/native/libhadoop.so.1.0.0
zlib:
        true /lib64/libz.so.1
snappy: true /usr/lib64/libsnappy.so.1
lz4: true revision:99
bzip2: true /lib64/libbz2.so.1
openssl: true /usr/lib64/libcrypto.so
```

If you see true in the openss1 row, Hadoop has detected the right version of libcrypto. so and optimization will work. If you see false in this row, you do not have the right version.

# Adding the KMS Service

- 1. Make sure you have performed the steps described in Optimizing for HDFS Data at Rest Encryption on page 203, depending on the operating system you are using.
- On the Cloudera Manager Home page, click to the right of the cluster name and select Add a Service. A list of service types display. You can add one type of service at a time.
- 3. Select the Java KeyStore KMS service and click Continue.
- 4. Customize the assignment of role instances to hosts. You can click the View By Host button for an overview of the role assignment by hostname ranges.

Click the field below the Key Management Server (KMS) role to display a dialog containing a list of hosts. Select the host for the new KMS role and click **OK**.

- 5. Review and modify the JavaKeyStoreProvider Directory configuration setting if required and click Continue. The Java KeyStore KMS service is started.
- **6.** Click **Continue**, then click **Finish**. You are returned to the **Home** page.
- 7. Verify the new Java KeyStore KMS service has started properly by checking its health status. If the Health Status is **Good**, then the service started properly.
- **8.** Follow the steps

# Enabling Java KeyStore KMS for the HDFS Service

- 1. Go to the HDFS service.
- 2. Click the Configuration tab.
- 3. Select Scope > HDFS (Service-Wide).
- Select Category > All.
- 5. Locate the KMS Service property or search for it by typing its name in the Search box.
- **6.** Select the **Java KeyStore KMS** radio button for the **KMS Service** property.
- 7. Click Save Changes.
- **8.** Restart your cluster.
  - a. On the Home page, click to the right of the cluster name and select **Restart**.
  - b. Click **Restart** that appears in the next screen to confirm. The **Command Details** window shows the progress of stopping services.

When All services successfully started appears, the task is complete and you can close the Command Details window.

- 9. Deploy client configuration.
  - a. On the Home page, click to the right of the cluster name and select **Deploy Client Configuration**.
  - b. Click Deploy Client Configuration.

# Configuring Encryption Properties for the HDFS and NameNode

Configure the following properties to select the encryption algorithm and KeyProvider that will be used during encryption. If you do not modify these properties, the default values will use AES-CTR to encrypt your data.

Note: You may notice many of the properties described in the table below are absent from your kms-site.xml. In such a case, the default values listed here are being used.

For a managed cluster, since the properties listed below have not been exposed in Cloudera Manager, use the corresponding safety valves if you want to specify a different value.

Property	Description	
Selecting an Encryption Algorithm: Set the following properties in the core-site.xml safety valve and redeploclient configuration.		
hadoop.security.crypto.codec.classes.EXAMPLECIPHERSUITE	The prefix for a given crypto codec, contains a comma-separated list of implementation classes for a given crypto codec (for example, EXAMPLECIPHERSUITE). The first implementation will be used if available, others are fallbacks.	
	By default, the cipher suite used is AES/CTR/NoPadding and its default classes are	

Property	Description	
	org.apache.hadoop.crypto.OpensslAesCtrCryptoCodec and org.apache.hadoop.crypto.JceAesCtrCryptoCodec as described in the following properties.	
hadoop.security.crypto.cipher.suite	Cipher suite for crypto codec.	
	Default: AES/CTR/NoPadding	
hadoop.security.crypto.codec.classes.aes.ctr.nopadding	Comma-separated list of crypto codec implementations for the default cipher suite: AES/CTR/NoPadding. The first implementation will be used if available, others are fallbacks.	
	Default: org.apache.hadoop.crypto.OpensslAesCtrCryptoCodec, org.apache.hadoop.crypto.JceAesCtrCryptoCodec	
hadoop.security.crypto.jce.provider	The JCE provider name used in CryptoCodec.	
	Default: None	
hadoop.security.crypto.buffer.size	The buffer size used by CryptoInputStream and CryptoOutputStream.	
	Default: 8192	
KeyProvider Configuration: Set this property in the had	Es-site.xml safety valve and restart the NameNode.	
dfs.encryption.key.provider.uri	The KeyProvider to be used when interacting with encryption keys that are used to read and write to an encryption zone.	
	If you have a managed cluster, Cloudera Manager will point to the KMS server you have enabled above.	
NameNode Configuration: Set this property in the hdfs-site.xml safety valve and restart the NameNode		
dfs.namenode.list.encryption.zones.num.responses	When listing encryption zones, the maximum number of zones that will be returned in a batch. Fetching the list incrementally in batches improves NameNode performance.	
	Default: 100	

# **Creating Encryption Zones**

Once a KMS has been set up and the NameNode and HDFS clients have been correctly configured, an admin user can use the  $hadoop\ key$  and  $hdfs\ crypto$  command-line tools to create encryption keys and set up new encryption zones.

Start by creating an encryption key for your zone.

```
$ sudo hadoop key create <key_name>
```

• As a superuser, create a new empty directory and make it an encryption zone using the key generated above.

```
$ hadoop fs -mkdir /zone
$ hdfs crypto -createZone -keyName <key_name> -path /zone
```

You can verify creation of the new encryption zone by running the -listZones command. You should see the encryption zone along with its key listed as follows:

```
$ sudo -u hdfs hdfs crypto -listZones
/zone <key_name>
```

• Warning: Do not delete an encryption key as long as it is still in use for an encryption zone. This will result in loss of access to data in that zone.

For more information and recommendations on creating encryption zones for each CDH component, see <u>Configuring CDH Services for HDFS Encryption</u> on page 220.

# Adding Files to an Encryption Zone

Existing data can be encrypted by coping it copied into the new encryption zones using tools like distcp. See the **DistCp Considerations** section below for information on using DistCp with encrypted data files.

You can add files to an encryption zone by copying them over to the encryption zone. For example:

```
sudo -u hdfs hadoop distcp /user/dir /user/enczone
```

#### Additional Information:

- For more information on KMS setup and high availability configuration, see <u>Configuring the Key Management Server (KMS)</u> on page 209.
- For instructions on securing the KMS using Kerberos, SSL communication and ACLs, see <u>Securing the Key Management Server (KMS)</u> on page 212.
- If you want to use the KMS to encrypt data used by other CDH services, see <u>Configuring CDH Services for HDFS Encryption</u> on page 220 for information on recommended encryption zones for each service.

## DistCp Considerations

A common usecase for DistCp is to replicate data between clusters for backup and disaster recovery purposes. This is typically performed by the cluster administrator, who is an HDFS superuser. To retain this workflow when using HDFS encryption, a new virtual path prefix has been introduced, /.reserved/raw/, that gives superusers direct access to the underlying block data in the filesystem. This allows superusers to distop data without requiring access to encryption keys, and avoids the overhead of decrypting and re-encrypting data. It also means the source and destination data will be byte-for-byte identical, which would not have been true if the data was being re-encrypted with a new EDEK.

#### Warning:

When using /.reserved/raw/ to distop encrypted data, make sure you preserve extended attributes with the -px flag. This is because encrypted attributes such as the EDEK are exposed through extended attributes and *must* be preserved to be able to decrypt the file.

This means that if the <code>distop</code> is initiated at or above the encryption zone root, it will automatically create a new encryption zone at the destination if it does not already exist. Hence, Cloudera recommends you first create identical encryption zones on the destination cluster to avoid any potential mishaps.

#### Copying between encrypted and unencrypted locations

By default, distep compares checksums provided by the filesystem to verify that data was successfully copied to the destination. When copying between an unencrypted and encrypted location, the filesystem checksums will not match since the underlying block data is different.

In this case, you can specify the -skipcrccheck and -update flags to avoid verifying checksums.

# Attack Vectors

Type of Exploit	Issue	Mitigation	
Hardware Access Exploit			
These exploits assume the attacker has gained physical access to hard drives from cluster machines, that is, DataNodes and NameNodes.	Access to swap files of processes containing DEKs. This exploit does not expose cleartext, as it also requires access to encrypted block files.	It can be mitigated by disabling swap, using encrypted swap, or using mlock to prevent keys from being swapped out.	
	Access to encrypted block files. This exploit does not expose cleartext, as it also requires access to the DEKs.		
Root Access Exploits			
These exploits assume the attacker	Access to encrypted block files.	No mitigation required.	
has gained root shell access to cluster machines, i.e. datanodes and namenodes. Many of these exploits cannot be addressed in HDFS, since	By itself, this does not expose cleartext, as it also requires access to encryption keys.		
a malicious root user has access to the in-memory state of processes holding encryption keys and cleartext. For these exploits, the only	Dump memory of client processes to obtain DEKs, delegation tokens, cleartext.	No mitigation.	
mitigation technique is carefully restricting and monitoring root shell access.	Recording network traffic to sniff encryption keys and encrypted data in transit.	No mitigation required.	
	By itself, insufficient to read cleartext without the EDEK encryption key.		
	Dump memory of datanode process to obtain encrypted block data.	No mitigation required.	
	By itself, insufficient to read cleartext without the DEK.		
	Dump memory of namenode process to obtain encrypted data encryption keys.	No mitigation required.	
	By itself, insufficient to read cleartext without the EDEK's encryption key and encrypted block files.		
HDFS Admin Exploits			
These exploits assume that the attacker has compromised HDFS, but does not have root or hdfs user shell access.	Access to encrypted block files.	No mitigation required.	
	By itself, insufficient to read cleartext without the EDEK and EDEK encryption key.		
	Access to encryption zone and encrypted file metadata (including	No mitigation required.	

Type of Exploit	Issue	Mitigation
	encrypted data encryption keys), via -fetchImage.	
	By itself, insufficient to read cleartext without EDEK encryption keys.	
Root Access Exploits		
	A rogue user can collect keys to which they have access, and use them later to decrypt encrypted data.	This can be mitigated through periodic key rolling policies.

# Configuring the Key Management Server (KMS)

Hadoop KMS is a cryptographic key management server based on Hadoop's **KeyProvider** API. It provides a client which is a KeyProvider implementation that interacts with the KMS using the HTTP REST API. Both the KMS and its client support HTTP SPNEGO Kerberos authentication and SSL-secured communication. The KMS is a Java-based web application which runs using a pre-configured Tomcat server bundled with the Hadoop distribution.

For instructions on securing the KMS, see Securing the Key Management Server (KMS) on page 212.

# Setup Configuration **KeyProvider Configuration**

Configure the KMS backing KeyProvider properties in the /etc/hadoop-kms/conf/kms-site.xml configuration

```
cproperty>
   <name>hadoop.kms.key.provider.uri
   <value>jceks://file@/${user.home}/kms.keystore</value>
</property>
property>
   <name>hadoop.security.keystore.java-keystore-provider.password-file/name>
   <value>kms.keystore.password</value>
</property>
```

The password file is looked up in Hadoop's configuration directory using CLASSPATH.

Restart the KMS for configuration changes to take effect.

#### KMS Cache

KMS caches keys for short periods of time to avoid excessive hits to the underlying key provider. The cache is enabled by default and can be disabled by setting the hadoop.kms.cache.enable property to false.

The cache is used with the following methods only: getCurrentKey(), getKeyVersion() and getMetadata().

For the getCurrentKey() method, cached entries are kept for a maximum of 30000 milliseconds regardless of the number of times the key is accessed. This is to prevent stale keys from being considered current.

For the getKeyVersion() method, cached entries are kept with a default inactivity timeout of 600000 milliseconds (10 minutes). The cache and its timeout value is configurable using the following properties in the /etc/hadoop-kms/conf/kms-site.xml configuration file:

```
<name>hadoop.kms.cache.enable
   <value>true</value>
</property>
```

## Encryption

#### **KMS Client Configuration**

The KMS client KeyProvider uses the kms scheme, and the embedded URL must be the URL of the KMS.

For example, for a KMS running on http://localhost:16000/kms, the KeyProvider URI is kms://http@localhost:16000/kms. And for a KMS running on https://localhost:16000/kms, the KeyProvider URI is kms://https@localhost:16000/kms.

#### Starting/Stopping the KMS

To start or stop KMS use KMS's bin/kms.sh script. For example, to start the KMS:

```
hadoop-3.0.0 $ sbin/kms.sh start
```

Invoking the script without any parameters will list all possible parameters.

#### KMS Aggregated Audit logs

Audit logs are aggregated for API accesses to the GET\_KEY\_VERSION, GET\_CURRENT\_KEY, DECRYPT\_EEK, and GENERATE\_EEK operations.

Entries are grouped by the <user,key,operation> for a configurable aggregation interval after which the number of accesses to the specified end-point by the user for a given key is flushed to the audit log.

The aggregation interval is configured using the following property:

## Configuring the Embedded Tomcat Server

The embedded Tomcat server can be configured using the

/etc/hadoop-kms/tomcat-conf.http/conf/server.xml.conf file. KMS pre-configures the HTTP and Admin ports in Tomcat's server.xml.conf to 16000 and 16001. Tomcat logs are also preconfigured to go to Hadoop's logs/directory.

The following environment variables can be set in KMS's /etc/hadoop-kms/conf/kms-env.sh script and can be used to alter the default ports and log directory:

- KMS\_HTTP\_PORT
- KMS\_ADMIN\_PORT
- KMS LOG

Restart the KMS for the configuration changes to take effect.

# Configuring KMS High Availability/Multiple KMSs

KMS supports multiple KMS instances behind a load balancer or VIP for scalability and HA purposes. These instances must be specially configured to work properly as a single logical service. When using multiple KMS instances, requests from the same user may be handled by different KMS instances.

## HTTP Kerberos Principals Configuration

When KMS instances are behind a load balancer or VIP, clients will use the hostname of the VIP. For Kerberos SPNEGO authentication, the VIP hostname is used to construct the Kerberos principal for the server, HTTP/<FQDN-VIP>. This means for client communication, all KMS instances must have the load balancer or VIP's principal.

However, in order to allow clients to directly access a specific KMS instance, the KMS instance must also have a Kerberos principal with its own hostname.

Both the Kerberos service principals (for the load balancer/VIP and the actual KMS host) must be in the keytab file. The principal name specified in the kms-site.xml configuration file must be '\*' as follows:

If using HTTPS, the SSL certificate used by the KMS instance must be configured to support multiple hostnames (see Java 7 keytool SAN extension support for details on how to do this).

#### HTTP Authentication Signature

KMS uses Hadoop Authentication for HTTP authentication. Hadoop Authentication issues a signed HTTP Cookie once a client has been authenticated successfully. This HTTP Cookie has an expiration time, after which it triggers a new authentication sequence. This is done to avoid requiring authentication for every HTTP request of a client.

A KMS instance must verify the HTTP Cookie signatures signed by other KMS instances. To do this all KMS instances must share the signing secret which can be configured by the hadoop.kms.authentication.signer.secret.provider property.

This secret can be shared using a Zookeeper service which must be configured in the kms-site.xml:

```
cproperty>
   <name>hadoop.kms.authentication.signer.secret.provider</name>
   <value>zookeeper</value>
    <description>
     Indicates how the secret to sign the authentication cookies will be
      stored. Options are 'random' (default), 'string' and 'zookeeper'.
     If using a setup with multiple KMS instances, 'zookeeper' should be used.
    </description>
</property>
property>
    <name>hadoop.kms.authentication.signer.secret.provider.zookeeper.path/name>
    <value>/hadoop-kms/hadoop-auth-signature-secret</value>
    <description>
     The Zookeeper ZNode path where the KMS instances will store and retrieve
      the secret from.
   </description>
</property>
property>
<name>hadoop.kms.authentication.signer.secret.provider.zookeeper.connection.string/name>
    <value>#HOSTNAME#:#PORT#,...
    <description>
     The Zookeeper connection string, a list of hostnames and port comma
     separated.
    </description>
</property>
    <name>hadoop.kms.authentication.signer.secret.provider.zookeeper.auth.type</name>
    <value>kerberos</value>
   <description>
     The Zookeeper authentication type, 'none' or 'sasl' (Kerberos).
    </description>
```

```
</property>
opertv>
<name>hadoop.kms.authentication.signer.secret.provider.zookeeper.kerberos.keytab/name>
    <value>/etc/hadoop/conf/kms.keytab</value>
   <description>
     The absolute path for the Kerberos keytab with the credentials to
     connect to Zookeeper.
   </description>
</property>
property>
<name>hadoop.kms.authentication.signer.secret.provider.zookeeper.kerberos.principal</name>
   <value>kms/#HOSTNAME#</value>
   <description>
     The Kerberos service principal used to connect to Zookeeper.
   </description>
</property>
```

# Securing the Key Management Server (KMS)

This topic contains information on securing the Hadoop KMS using Kerberos, SSL-communication and Access Control Lists for operations on encryption keys.

# **Enabling Kerberos Authentication**

- Important:
  - You can use either Cloudera Manager or the following command-line instructions to complete this configuration.
  - This information applies specifically to CDH 5.4.x. If you use an earlier version of CDH, see the documentation for that version located at <u>Cloudera Documentation</u>.

#### **Using Cloudera Manager**

# Required Role: Full Administrator

To enable Kerberos for the Java KeyStore KMS using Cloudera Manager:

- 1. Open the Cloudera Manager Admin Console and navigate to the Java KeyStore KMS service.
- 2. Click Configuration.
- **3.** Set the **Authentication Type** property to kerberos.
- 4. Click Save Changes.
- 5. Since Cloudera Manager does not automatically create the principal and keytab file for the KMS, you will need to manually run the Generate Credentials command. Using the top navigation bar, go to Administration > Kerberos > Credentials and click Generate Credentials.
  - **Note:** No new principals will be created since KMS uses its host's HTTP principal.

#### Kerberos Mapping Rules:

The hadoop.kms.authentication.kerberos.name.rules property can only be changed using the **Key Management Server Advanced Configuration Snippet (Safety Valve) for kms-site.xml** property.

To modify, the value should be copied from the hadoop.security.auth\_to\_local configuration property, found in the core-site.xml file of the service.

## Using the Command Line

Configure the etc/krb5.conf file with information for your KDC server. Create an HTTP principal and keytab file for the KMS.

Configure the etc/hadoop/kms-site.xml with the following properties:

```
property>
    <name>hadoop.kms.authentication.type</name>
    <value>kerberos</value>
</property>
property>
    <name>hadoop.kms.authentication.kerberos.keytab
    <value>${user.home}/kms.keytab</value>
</property>
cproperty>
    <name>hadoop.kms.authentication.kerberos.principal</name>
    <value>HTTP/localhost</value>
</property>
property>
   <name>hadoop.kms.authentication.kerberos.name.rules/name>
   <value>DEFAULT</value>
</property>
```

Restart the Java KeyStore KMS service for the configuration changes to take effect.

# Configuring the KMS Proxyuser

Each proxyuser must be configured in etc/hadoop/kms-site.xml using the following properties:

```
______
cproperty>
   <name>hadoop.kms.proxyuser.#USER#.users
   <value>*</value>
</property>
property>
   <name>hadoop.kms.proxyuser.#USER#.groups
   <value>*</value>
</property>
cproperty>
   <name>hadoop.kms.proxyuser.#USER#.hosts
   <value>*</value>
</property>
```

Where #USER# is the username of the proxyuser to be configured.

The hadoop.kms.proxyuser.#USER#.users property indicates the users that can be impersonated. The hadoop.kms.proxyuser.#USER#.groups property indicates the groups to which the users being impersonated must belong. At least one of these properties must be defined. If both are defined, then the configured proxyuser will be able to impersonate any user in the users list and any user belonging to a group listed in the groups list.

The hadoop.kms.proxyuser.#USER#.hosts property indicates the host from which the proxyuser can make impersonation requests. "\*" means there are no restrictions for the #USER# regarding users, groups or hosts.

### Configuring SSL for the KMS

- Important:
  - You can use either Cloudera Manager or the following command-line instructions to complete this configuration.
  - This information applies specifically to CDH 5.4.x. If you use an earlier version of CDH, see the documentation for that version located at Cloudera Documentation.

## Using Cloudera Manager

Required Role: Configurator Cluster Administrator Full Administrator

The steps for configuring and enabling Hadoop SSL for the KMS are as follows:

- 1. Open the Cloudera Manager Admin Console and navigate to the Java KeyStore KMS service.
- 2. Click Configuration.
- 3. In the Search field, type SSL to show the KMS SSL properties (found under the Key Management Server Default Group > Security category).
- 4. Edit the following SSL properties according to your cluster configuration.

#### **Table 17: KMS SSL Properties**

Property	Description	
Enable TLS/SSL for Key Management Server	Encrypt communication between clients and Key Management Server using Transport Layer Security (TLS) (formerly known as Secure Socket Layer (SSL)).	
Key Management Server TLS/SSL Server JKS Keystore File Location	The path to the TLS/SSL keystore file containing the server certificate and private key used for TLS/SSL. Used when Key Management Server is acting as a TLS/SSL server. The keystore must be in JKS format.	
Key Management Server TLS/SSL Server JKS Keystore File Password	The password for the Key Management Server JKS keystore file.	

- 5. Click Save Changes.
- 6. Restart the KMS service.

#### Using the Command Line

To configure KMS to work over HTTPS by setting the following properties in the etc/hadoop/kms\_env.shscript:

- KMS\_SSL\_KEYSTORE\_FILE
- KMS\_SSL\_KEYSTORE\_PASS

In the KMS tomcat/conf directory, replace the server.xml file with the provided ssl-server.xml file.

You need to create an SSL certificate for the KMS. As the kms user, use the Java keytool command to create the SSL certificate:

\$ keytool -genkey -alias tomcat -keyalg RSA

You will be asked a series of questions in an interactive prompt. It will create the keystore file, which will be named .keystore and located in the kms user's home directory. The password you enter for the keystore must match the value of the kms\_ssl\_keystore\_pass environment variable set in the kms-env.sh script in the configuration directory.

The answer to "What is your first and last name?" (CN) must be the hostname of the machine where the KMS will be running.

**Note:** Restart the KMS for the configuration changes to take effect.

# Configuring Access Control Lists for the KMS

By default, the KMS ACLs are fully permissive, that is, everyone is allowed to perform all operations. However, a key design requirement is to be able to restrict HDFS superusers from having access to key material. This prevents a malicious superuser from having access to both (a) all the key material and (b) all the encrypted data, and thus being able to decrypt everything.

The KMS supports both whitelist and blacklist ACLs where the blacklist overrides the whitelist. A user or group accessing KMS is first checked for inclusion in the ACL for the requested operation and then checked for exclusion in the blacklist for the operation before access is granted. Hence, add HDFS superusers to the blacklist, while allowing everyone else.

The ACL syntax for both blacklist and whitelist entries is as follows:

Users Only:

user1.user2.userN

- Note: There are no spaces following the commas separating the users in the list.
- Groups Only:

group1,group2,groupN

- **Note:** There is a leading space before the comma-separated group list.
- Users and Groups:

user1, user2, userN group1, group2, groupN

**Note:** The comma-separated user list is separated from the comma-separated group list by a space.

- Important:
  - You can use either Cloudera Manager or the following command-line instructions to complete this configuration.
  - This information applies specifically to CDH 5.4.x. If you use an earlier version of CDH, see the documentation for that version located at Cloudera Documentation.

#### Using Cloudera Manager

Configurator Cluster Administrator Full Administrator Required Role:

- Important: See related Known Issue and listed workaround: KMS and Key Trustee ACLs do not work in Cloudera Manager 5.3.
- 1. Open the Cloudera Manager Admin Console and navigate to the Java KeyStore KMS service.
- 2. Click Configuration.
- 3. In the Search field, type acl to show the Key Management Server Advanced Configuration Snippet (Safety Valve) for kms-acls.xml (found under the Key Management Server Default Group category).
- 4. Add or edit the ACL properties according to your cluster configuration. See Using the Command Line on page 216 for example ACL entries.
- 5. Click Save Changes.
- **6.** Restart the Java KeyStore KMS service.

#### Using the Command Line

KMS ACLs configuration are defined in the KMS /etc/hadoop/kms-acls.xml configuration file. This file is hot-reloaded when it changes.

```
property>
   <name>hadoop.kms.acl.CREATE</name>
   <value>*</value>
    <description>
     ACL for create-key operations.
     If the user does is not in the GET ACL, the key material is not returned
     as part of the response.
    </description>
</property>
property>
   <name>hadoop.kms.blacklist.CREATE
    <value>hdfs,foo</value>
    <description>
     Blacklist for create-key operations.
     If the user does is in the Blacklist, the key material is not returned
     as part of the response.
    </description>
</property>
property>
   <name>hadoop.kms.acl.DELETE</name>
    <value>*</value>
    <description>
     ACL for delete-key operations.
    </description>
</property>
property>
    <name>hadoop.kms.blacklist.DELETE
    <value>hdfs,foo</value>
    <description>
     Blacklist for delete-key operations.
    </description>
</property>
opertv>
    <name>hadoop.kms.acl.ROLLOVER</name>
    <value>*</value>
   <description>
     ACL for rollover-key operations.
     If the user does is not in the GET ACL, the key material is not returned
     as part of the response.
    </description>
</property>
cproperty>
    <name>hadoop.kms.blacklist.ROLLOVER</name>
    <value>hdfs,foo</value>
    <description>
     Blacklist for rollover-key operations.
    </description>
</property>
property>
   <name>hadoop.kms.acl.GET</name>
    <value>*</value>
    <description>
     ACL for get-key-version and get-current-key operations.
    </description>
</property>
property>
    <name>hadoop.kms.blacklist.GET</name>
    <value>hdfs,foo</value>
   <description>
     ACL for get-key-version and get-current-key operations.
    </description>
```

```
</property>
opertv>
    <name>hadoop.kms.acl.GET_KEYS</name>
    <value>*</value>
    <description>
     ACL for get-keys operation.
    </description>
</property>
cproperty>
    <name>hadoop.kms.blacklist.GET_KEYS</name>
    <value>hdfs,foo</value>
    <description>
     Blacklist for get-keys operation.
    </description>
</property>
opertv>
    <name>hadoop.kms.acl.GET_METADATA
    <value>*</value>
    <description>
     ACL for get-key-metadata and get-keys-metadata operations.
    </description>
</property>
property>
    <name>hadoop.kms.blacklist.GET_METADATA
    <value>hdfs,foo</value>
    <description>
     Blacklist for get-key-metadata and get-keys-metadata operations.
    </description>
</property>
cproperty>
    <name>hadoop.kms.acl.SET_KEY_MATERIAL</name>
    <value>*</value>
    <description>
       Complimentary ACL for CREATE and ROLLOVER operation to allow the client
       to provide the key material when creating or rolling a key.
    </description>
</property>
property>
    <name>hadoop.kms.blacklist.SET_KEY_MATERIAL
    <value>hdfs,foo</value>
    <description>
        Complimentary Blacklist for CREATE and ROLLOVER operation to allow the client
        to provide the key material when creating or rolling a key.
    </description>
</property>
property>
    <name>hadoop.kms.acl.GENERATE_EEK</name>
    <value>*</value>
    <description>
     ACL for generateEncryptedKey
      CryptoExtension operations
    </description>
</property>
cproperty>
    <name>hadoop.kms.blacklist.GENERATE_EEK</name>
    <value>hdfs,foo</value>
    <description>
     Blacklist for generateEncryptedKey
      CryptoExtension operations
    </description>
</property>
property>
    <name>hadoop.kms.acl.DECRYPT_EEK</name>
    <value>*</value>
```

# Configuring Key Access Control

KMS supports access control for all non-read operations at the Key level. All Key Access operations are classified as:

```
    MANAGEMENT - createKey, deleteKey, rolloverNewVersion
    GENERATE_EEK - generateEncryptedKey, warmUpEncryptedKeys
    DECRYPT_EEK - decryptEncryptedKey
    READ - getKeyVersion, getKeyVersions, getMetadata, getKeysMetadata, getCurrentKey
    ALL - all of the above.
```

These can be defined in the etc/hadoop/kms-acls.xml as follows:

```
<name>key.acl.testKey1.MANAGEMENT
  <value>*</value>
 <description>
   ACL for create-key, deleteKey and rolloverNewVersion operations.
  </description>
</property>
property>
  <name>key.acl.testKey2.GENERATE_EEK</name>
  <value>*</value>
 <description>
   ACL for generateEncryptedKey operations.
  </description>
</property>
cproperty>
  <name>key.acl.testKey3.DECRYPT_EEK</name>
  <value>*</value>
  <description>
   ACL for decryptEncryptedKey operations.
  </description>
</property>
cproperty>
  <name>key.acl.testKey4.READ
  <value>*</value>
  <description>
   ACL for getKeyVersion, getKeyVersions, getMetadata, getKeysMetadata,
    getCurrentKey operations
  </description>
</property>
propertv>
  <name>key.acl.testKey5.ALL
  <value>*</value>
 <description>
   ACL for ALL operations.
 </description>
</property>
```

```
property>
  <name>default.key.acl.MANAGEMENT
  <value>user1,user2</value>
  <description>
   default ACL for MANAGEMENT operations for all keys that are not
    explicitly defined.
  </description>
</property>
property>
  <name>default.key.acl.GENERATE_EEK</name>
  <value>user1,user2</value>
  <description>
   default ACL for GENERATE EEK operations for all keys that are not
   explicitly defined.
  </description>
</property>
property>
  <name>default.key.acl.DECRYPT_EEK</name>
  <value>user1,user2</value>
  <description>
   default ACL for DECRYPT_EEK operations for all keys that are not
    explicitly defined.
  </description>
</property>
property>
 <name>default.key.acl.READ</name>
  <value>user1,user2</value>
  <description>
   default ACL for READ operations for all keys that are not
   explicitly defined.
  </description>
</property>
```

For all keys for which an ACL has not been explicitly configured, you can configure a default key ACL for a subset of the operation types.

If no ACL is configured for a specific key, and no default ACL is configured for the requested operation, access will be denied.

**Note:** The default ACL does not support the ALL operation qualifier.

# KMS Delegation Token Configuration

KMS delegation token secret manager can be configured using the following properties:

```
property>
 <name>hadoop.kms.authentication.delegation-token.update-interval.sec</name>
  <value>86400</value>
 <description>
   How often the master key is rotated, in seconds. Default value 1 day.
  </description>
</property>
cproperty>
  <name>hadoop.kms.authentication.delegation-token.max-lifetime.sec/name>
  <value>604800</value>
  <description>
   Maximum lifetime of a delegation token, in seconds. Default value 7 days.
  </description>
</property>
cproperty>
  <name>hadoop.kms.authentication.delegation-token.renew-interval.sec/name>
  <value>86400</value>
  <description>
   Renewal interval of a delegation token, in seconds. Default value 1 day.
  </description>
```

# Encryption

# Configuring CDH Services for HDFS Encryption

The following topics contain recommendations for setting up HDFS encryption with various CDH services.

### Hive

HDFS encryption has been designed such that files cannot be moved from one encryption zone to another encryption zone or from encryption zones to unencrypted directories. Hence, the landing zone for data when using the LOAD DATA INPATH command should always be inside the destination encryption zone.

If you want to use HDFS encryption with Hive, ensure you are using one of the following configurations:

# Single Encryption Zone

With this configuration, you can use HDFS encryption by having all Hive data inside the same encryption zone. Additionally, in Cloudera Manager, configure the Hive Scratch Directory (hive.exec.scratchdir) to be inside the encryption zone.

### Recommended HDFS Path: /user/hive

For example, to configure a single encryption zone for the entire Hive warehouse, you can rename /user/hive to /user/hive-old, create an encryption zone at /user/hive, and then distop all the data from /user/hive-old to /user/hive.

Additionally, in Cloudera Manager, configure the Hive Scratch Directory (hive.exec.scratchdir) to be inside the encryption zone by setting it to /user/hive/tmp, ensuring the permissions are 1777 on /user/hive/tmp.

# Multiple Encryption Zones

With this configuration, you can use encrypted databases and/or tables with different encryption keys. The only limitation is that in order to read data from read-only encrypted tables, users must have access to a temporary directory which is encrypted with at least as strong encryption as the table.

For example, you can configure two encrypted tables, ezTbl1 and ezTbl2. Create two new encryption zones, /data/ezTbl1 and /data/ezTbl2. Load data to the tables in Hive as usual using LOAD statements. See the Changed Behavior after HDFS Encryption is Enabled section below for more information.

## Other Encrypted Directories

- LOCALSCRATCHDIR: The MapJoin optimization in Hive writes HDFS tables out to a local directory and then uploads them to the distributed cache. If you want to enable encryption, you will either need to disable MapJoin or encrypt the *local* Hive Scratch directory (hive.exec.local.scratchdir).
- **DOWNLOADED\_RESOURCES\_DIR**: Jars which are added to a user session and stored in HDFS are downloaded to hive.downloaded.resources.dir. If you want these Jar files to be encrypted, configure hive.downloaded.resources.dir to be part of an encryption zone. This directory is local to the HiveServer2.
- NodeManager Local Directory List: Since Hive stores Jars and MapJoin files in the distributed cache, if you'd
  like to use MapJoin or encrypt Jars and other resource files, the YARN configuration property, NodeManager
  Local Directory List (yarn.nodemanager.local-dirs), must be configured to a set of encrypted local
  directories on all nodes.

Alternatively, you can disable MapJoin by setting hive.auto.convert.join to false.

# Changed Behavior after HDFS Encryption is Enabled

- Loading data from one encryption zone to another will result in a copy of the data. Distcp will be used to speed up the process if the size of the files being copied is higher than the value specified by HIVE\_EXEC\_COPYFILE\_MAXSIZE. The minimum size limit for HIVE\_EXEC\_COPYFILE\_MAXSIZE is 32 MB, which can be modified by changing the value for the hive.exec.copyfile.maxsize configuration property.
- When loading data to encrypted tables, Cloudera strongly recommends using a landing zone inside the same encryption zone as the table.
  - Example 1: Loading unencrypted data to an encrypted table There are 2 approaches to doing this.
    - If you're loading new unencrypted data to an encrypted table, just load the data using the LOAD DATA ... statement. Since the source data does not reside inside the encryption zone, the LOAD statement will result in a copy. This is why Cloudera recommends landing data (that you expect to encrypt) inside the destination encryption zone. However, this approach may use distop to speed up the copying process if your data is inside HDFS.
    - If the data to be loaded is already inside a Hive table, you can create a new table with a LOCATION inside an encryption zone as follows:

```
CREATE TABLE encrypted_table [STORED AS] LOCATION ... AS SELECT * FROM
<unencrypted table>
```

Note that the location specified in the CREATE TABLE statement above needs to be inside an encryption zone. Creating a table pointing LOCATION to an unencrypted directory will not encrypt your source data. You must copy your data to an encryption zone, and then point LOCATION to that encryption zone.

 Example 2: Loading encrypted data to an encrypted table - If the data to be loaded is already encrypted, use the CREATE TABLE statement pointing LOCATION to the encrypted source directory where your data is. This is the fastest way to create encrypted tables.

```
CREATE TABLE encrypted table [STORED AS] LOCATION ... AS SELECT * FROM
<encrypted_source_directory>
```

- Users reading data from encrypted tables which are read-only, must have access to a temp directory which is encrypted with at least as strong encryption as the table.
- Temp data is now written to a directory named .hive-staging within each table or partition
- Previously, an INSERT OVERWRITE on a partitioned table inherited permissions for new data from the existing partition directory. With encryption enabled, permissions are inherited from the table.

#### Impala

#### Recommendations

- If HDFS encryption is enabled, configure Impala to encrypt data spilled to local disk.
- Prior to Impala 2.2.0 / CDH 5.4.0, Impala does not support the LOAD DATA statement when the source and destination are in different encryption zones. If you are running an affected release and need to use LOAD DATA with HDFS encryption enabled, copy the data to the table's encryption zone prior to running the statement.
- Use Cloudera Navigator to lock down the local directory where Impala UDFs are copied during execution. By default, Impala copies UDFs into /tmp, and you can configure this location through the --local\_library\_dir startup flag for the impalad daemon.
- Limit the rename operations for internal tables once encryption zones are set up. Impala cannot do an ALTER TABLE RENAME operation to move an internal table from one database to another, if the root directories for those databases are in different encryption zones. If the encryption zone covers a table directory but not the

# Encryption

parent directory associated with the database, Impala cannot do an ALTER TABLE RENAME operation to rename an internal table even within the same database.

Avoid structuring partitioned tables where different partitions reside in different encryption zones, or where
any partitions reside in an encryption zone that is different from the root directory for the table. Impala
cannot do an INSERT operation into any partition that is not in the same encryption zone as the root directory
of the overall table.

# Steps

Start every impalad process with the --disk\_spill\_encryption=true flag set. This encrypts all spilled data using AES-256-CFB. Set this flag using the Impala service configuration property, Impala Daemon Command Line Argument Advanced Configuration Snippet (Safety Valve), found under Impala Daemon Default Group > Advanced.

• Important: Impala does not selectively encrypt data based on whether the source data is already encrypted in HDFS. This will result in at most 15 percent performance degradation when data is spilled.

## **HBase**

#### Recommendations

Make  $/ {\tt hbase}$  an encryption zone. Do not create encryption zones as subdirectories under  $/ {\tt hbase}$ , as HBase may need to rename files across those subdirectories.

## Steps

On a cluster without HBase currently installed, create the /hbase directory and make that an encryption zone.

On a cluster with HBase already installed, perform the following steps:

- 1. Stop the HBase service.
- 2. Move data from the /hbase directory to /hbase-tmp.
- **3.** Create an empty /hbase directory and make it an encryption zone.
- 4. Distcp all data from /hbase-tmp to /hbase preserving user-group permissions and extended attributes.
- **5.** Start the HBase service and verify that it is working as expected.
- **6.** Remove the /hbase-tmp directory.

### Search

#### Recommendations

Make /solr an encryption zone.

#### Steps

On a cluster without Solr currently installed, create the /solr directory and make that an encryption zone. On a cluster with Solr already installed, create an empty /solr-tmp directory, make /solr-tmp an encryption zone, distop all data from /solr into /solr-tmp, remove /solr and rename /solr-tmp to /solr.

### Sqoop

#### Recommendations

• For Hive support: Ensure that you are using Sqoop with the --target-dir parameter set to a directory that is inside the Hive encryption zone. For more details, see <u>Hive</u> on page 220

- For append/incremental support: Make sure that the sqoop.test.import.rootDir property points to the same encryption zone as the above -- target-dir argument.
- For HCatalog support: No special configuration should be required

### Hue

#### Recommendations

Make /user/hue an encryption zone since that's where Oozie workflows and other Hue specific data are stored by default.

# Steps

On a cluster without Hue currently installed, create the /user/hue directory and make that an encryption zone. On a cluster with Hue already installed, create an empty /user/hue-tmp directory, make /user/hue-tmp an encryption zone, distcp all data from /user/hue into /user/hue-tmp, remove /user/hue and rename /user/hue-tmp to /user/hue.

# Spark

#### Recommendations

- By default, application event logs are stored at /user/spark/applicationHistory which can be made into an encryption zone.
- Spark also optionally caches its jar file at /user/spark/share/lib (by default), but encrypting this directory is not necessary.
- Spark does not encrypt shuffle data. However, if that is desired, you should configure Spark's local directory, spark.local.dir (in Standalone mode), to reside on an encrypted disk. For YARN mode, make the corresponding YARN configuration changes.

# MapReduce and YARN MapReduce v1

#### Recommendations

MRv1 stores both history and logs on local disks by default. Even if you do configure history to be stored on HDFS, the files are not renamed. Hence, no special configuration is required.

# MapReduce v2 (YARN)

#### Recommendations

Make /user/history a single encryption zone, since history files are moved between the intermediate and done directories, and HDFS encryption does not allow moving encrypted files across encryption zones.

### Steps

On a cluster with MRv2 (YARN) installed, create the /user/history directory and make that an encryption zone. If /user/history already exists and is not empty, create an empty /user/history-tmp directory, make /user/history-tmp an encryption zone, distop all data from /user/history into /user/history-tmp, remove /user/history and rename /user/history-tmp to /user/history.

# Troubleshooting HDFS Encryption

This topic contains HDFS Encryption-specific troubleshooting information in the form of issues you might face when encrypting HDFS files/directories and their workarounds.

# Retrieval of encryption keys fails

#### Description

You see the following error when trying to list encryption keys

```
userl@example-sles-4:~> hadoop key list
Cannot list keys for KeyProvider: KMSClientProvider[https:
//example-sles-2.example.com:16000/kms/v1/]: Retrieval of all keys failed.
```

#### Solution

Make sure your truststore has been updated with the relevant certificate(s), such as the Key Trustee server certificate.

# DistCp between unencrypted and encrypted locations fails

#### Description

By default, DistCp compares checksums provided by the filesystem to verify that data was successfully copied to the destination. However, when copying between unencrypted and encrypted locations, the filesystem checksums will not match since the underlying block data is different.

#### Solution

Specify the -skipcrccheck and -update distcp flags to avoid verifying checksums.

# Cannot move encrypted files to trash

## Description

With HDFS encryption enabled, you cannot move encrypted files or directories to the trash directory.

#### Solution

To remove encrypted files/directories, use the following command with the -skipTrash flag specified to bypass trash.

```
rm -r -skipTrash /testdir
```

# NameNode - KMS communication fails after long periods of inactivity

### Description

Encrypted files and encryption zones cannot be created if a long period of time (by default, 20 hours) has passed since the last time the KMS and NameNode communicated.

#### Solution

Important: Upgrading your cluster to the latest CDH 5 release will fix this problem. For instructions, see Upgrading from an Earlier CDH 5 Release to the Latest Release.

For earlier CDH 5 releases, there are two possible workarounds to this issue:

You can increase the KMS authentication token validity period to a very high number. Since the default value is 10 hours, this bug will only be encountered after 20 hours of no communication between the NameNode and the KMS. Add the following property to the kms-site.xmlSafety Valve:

```
<pname>hadoop.kms.authentication.token.validity</name>
```

```
<value>SOME VERY HIGH NUMBER</value>
</property>
```

 You can switch the KMS signature secret provider to the string secret provider by adding the following property to the kms-site.xml Safety Valve:

```
property>
<name>hadoop.kms.authentication.signature.secret</name>
<value>SOME VERY SECRET STRING</value>
</property>
```

# Configuring Encrypted HDFS Data Transport

This topic describes how to configure encrypted HDFS data transport using both, Cloudera Manager, and the command line.

# Using Cloudera Manager

# Required Role: Full Administrator

To enable encryption of data transfered between DataNodes and clients, and among DataNodes, proceed as follows:

- 1. Enable Hadoop security using Kerberos.
- 2. Select the HDFS service.
- 3. Click the Configuration tab.
- 4. Select Scope > HDFS (Service Wide)
- Select Category > Security.
- 6. Configure the following properties: (You can type the property name in the Search box to locate the property.)

Property	Description
Enable Data Transfer Encryption	Check this field to enable wire encryption.
Data Transfer Encryption Algorithm	Optionally configure the algorithm used to encrypt data.
Hadoop RPC Protection	Select privacy.

- 7. Click Save Changes.
- 8. Restart the HDFS service.

# Using the Command Line

- Important:
  - You can use either Cloudera Manager or the following command-line instructions to complete this configuration.
  - This information applies specifically to CDH 5.4.x. If you use an earlier version of CDH, see the documentation for that version located at Cloudera Documentation.

To enable encrypted data transport using the command line, proceed as follows:

- 1. Enable the Hadoop Security using Kerberos, following these instructions.
- 2. Set the optional RPC encryption by setting hadoop.rpc.protection to "privacy" in the core-site.xml file in both client and server configurations.

# Encryption

Note:

If RPC encryption is not enabled, transmission of other HDFS data is also insecure.

- **3.** Set dfs.encrypt.data.transfer to true in the hdfs-site.xml file on all server systems.
- **4.** Restart all daemons.

Authorization is concerned with who or what has access or control over a given resource or service. Since Hadoop merges together the capabilities of multiple varied, and previously separate IT systems as an enterprise data hub that stores and works on all data within an organization, it requires multiple authorization controls with varying granularities. In such cases, Hadoop management tools simplify setup and maintenance by:

- Tying all users to groups, which can be specified in existing LDAP or AD directories.
- Providing role-based access control for similar interaction methods, like batch and interactive SQL queries. For example, Apache Sentry permissions apply to Hive (HiveServer2) and Impala.

CDH currently provides the following forms of access control:

- Traditional POSIX-style permissions for directories and files, where each directory and file is assigned a single owner and group. Each assignment has a basic set of permissions available; file permissions are simply read, write, and execute, and directories have an additional permission to determine access to child directories.
- Extended Access Control Lists (ACLs) for HDFS that provide fine-grained control of permissions for HDFS files by allowing you to set different permissions for specific named users and/or named groups.
- Apache HBase uses ACLs to authorize various operations (READ, WRITE, CREATE, ADMIN) by column, column family, and column family qualifier. HBase ACLs are granted and revoked to both users and groups.
- Role-based access control with Apache Sentry. As of Cloudera Manager 5.1.x, Sentry permissions can be configured using either policy files or the database-backed Sentry service.
  - The Sentry service is the preferred way to set up Sentry permissions. See <u>The Sentry Service</u> on page 236 for more information.
  - For the policy file approach to configuring Sentry, see Sentry Policy File Authorization on page 258.

# Cloudera Manager User Roles

User Administrator Full Administrator Required Role:

Access to Cloudera Manager features is controlled by user accounts. For more information about user accounts, see Cloudera Manager User Accounts. Among the properties of a user account is the user role, which determines the Cloudera Manager features visible to the user and the actions the user can perform. All the tasks in the Cloudera Manager documentation indicate which role is required to perform the task.

Note: The full set of roles are available with Cloudera Enterprise; Cloudera Express supports only the Read-Only and Full Administrator roles. When a Cloudera Enterprise Data Hub Edition trial license expires, only users with Read-Only and Full Administrator roles are allowed to log in. A Full Administrator must change the role of any other user to Read-Only or Full Administrator before that user can log in.

# **User Roles**

A user account can be assigned one of the following roles:

- Auditor Allows the user to:
  - View data in Cloudera Manager.
  - View audit events.
- Read-Only Allows the user to:
  - View data in Cloudera Manager.
  - View service and monitoring information.

The Read-Only role does not allow the user to add services or take any actions that affect the state of the cluster.

- Limited Operator Allows the user to:
  - View data in Cloudera Manager.
  - View service and monitoring information.
  - Decommission hosts (except hosts running Cloudera Management Service roles).

The Limited Operator role does not allow the user to add services or take any other actions that affect the state of the cluster.

- Operator Allows the user to:
  - View data in Cloudera Manager.
  - View service and monitoring information.
  - Stop, start, and restart clusters, services (except the Cloudera Management Service), and roles.
  - Decommission and recommission hosts (except hosts running Cloudera Management Service roles).
  - Decommission and recommission roles (except Cloudera Management Service roles).

The Operator role does not allow the user to add services, roles, or hosts, or take any other actions that affect the state of the cluster.

- Configurator Allows the user to:
  - View data in Cloudera Manager.
  - Perform all Operator operations.
  - Configure services (except the Cloudera Management Service).
  - Enter and exit maintenance mode.
  - Manage dashboards (including Cloudera Management Service dashboards).
- Cluster Administrator Allows the user to view all data and perform all actions except the following:
  - Administer Cloudera Navigator.
  - Perform replication and snapshot operations.
  - View audit events.
  - Manage user accounts and configuration of external authentication.
- **BDR Administrator** Allows the user to:
  - View data in Cloudera Manager.
  - View service and monitoring information.
  - Perform replication and snapshot operations.
- Navigator Administrator Allows the user to:
  - View data in Cloudera Manager.
  - View service and monitoring information.
  - Administer Cloudera Navigator.
  - View audit events.
- User Administrator Allows the user to:
  - View data in Cloudera Manager.
  - View service and monitoring information.
  - Manage user accounts and configuration of external authentication.
- **Full Administrator** Full Administrators have permissions to view all data and do all actions, including reconfiguring and restarting services, and administering other users.

# Determining the Role of the Currently Logged in User

1. Click the logged-in username at the far right of the top navigation bar. The role displays right under the username. For example:



# Removing the Full Administrator User Role

In some organizations, security policies may prohibit the use of the Full Administrator role. The Full Administrator role is created during Cloudera Manager installation, but you can remove it as long as you have at least one remaining user account with User Administrator privileges.

To remove the Full Administrator user role, perform the following steps.

- 1. Add at least one user account with User Administrator privileges, or ensure that at least one such user account already exists.
- **2.** Ensure that there is only a single user account with Full Administrator privileges.
- 3. While logged in as the single remaining Full Administrator user, select your own user account and either delete it or assign it a new user role.
  - Warning: After you delete the last Full Administrator account, you will be logged out immediately and will not be able to log in unless you have access to another user account. Also, it will no longer be possible to create or assign Full Administrators.

A consequence of removing the Full Administrator role is that some tasks may require collaboration between two or more users with different user roles. For example:

- If the machine that the Cloudera Navigator roles are running on needs to be replaced, the Cluster Administrator will want to move all the roles running on that machine to a different machine. The Cluster Administrator can move any non-Navigator roles by deleting and re-adding them, but would need a Navigator Administrator to perform the stop, delete, add, and start actions for the Cloudera Navigator roles.
- In order to take HDFS snapshots, snapshots must be enabled on the cluster by a Cluster Administrator, but the snapshots themselves must be taken by a BDR Administrator.

# Cloudera Navigator User Roles

User roles determine the Cloudera Navigator features visible to the user and the actions the user can perform.

# User Roles

A Cloudera Navigator user account can be assigned one of the following user roles:

- Lineage Viewer Search for entities, view metadata, and view lineage.
- Auditing Viewer View audit events and create audit reports.
- Policy Viewer View metadata policies.
- Metadata Administrator Search for entities, view metadata, view lineage, and edit metadata.
- Policy Administrator View, create, update, and delete metadata and metadata policies.
- User Administrator Administer role assignments to groups.
- Full Administrator Full access, including role assignments to groups.

The user roles and associated permissions are summarized as follows:

**Table 18: Cloudera Navigator User Roles** 

User Role	Read Audit	Read Lineage	Read Metadata (Search)	Write Metadata (Edit)	Read Policies	Write Policies	Administer Role Group Mapping
Full Administrator							
User Administrator							
Auditing Viewer							
Lineage Viewer							
Metadata Administrator							
Policy Viewer							
Policy Administrator							

# Determining the Roles of the Currently Logged in User

To display the Cloudera Navigator user roles for the currently logged-in user:

- 1. Click the username in the upper right.
- 2. Click My roles.
- **3.** The **Roles** pop-up window will appear, displaying all roles assigned to the LDAP or Active Directory groups to which the current user belongs.

The selection of menus displayed in the upper right indicates the user's access to Cloudera Navigator features, as determined by the roles associated with the user's LDAP or Active Directory groups. For example, a Full Administrator will see the **Search**, **Audits**, **Policies**, and **Administration** menus, while a user with the Policy Administrator role will only see the **Search** and **Policies** menus.

# **HDFS Extended ACLs**

HDFS supports POSIX Access Control Lists (ACLs), in addition to the traditional POSIX permissions model already supported. ACLs provide fine-grained control of permissions for HDFS files by providing a way to set different permissions for specific named users or named groups.

# **Enabling ACLs**

By default, ACLs are disabled on a cluster. To enable them, set the dfs.namenode.acls.enabled property to true in the NameNode's hdfs-site.xml.

• Important: Ensure that all users and groups resolve on the NameNode for ACLs to work as expected.

```
<value>true</value>
</property>
```

### Commands

You can use the File System Shell commands, setfacl and getfacl, to modify and retrieve files' ACLs.

## getfacl

```
hdfs dfs -getfacl [-R] <path>
<!-- COMMAND OPTIONS
<path>: Path to the file or directory for which ACLs should be listed.
-R: Use this option to recursively list ACLs for all files and directories.
-->
```

#### Examples:

```
<!-- To list all ACLs for the file located at /user/hdfs/file -->
hdfs dfs -getfacl /user/hdfs/file
<!-- To recursively list ACLs for /user/hdfs/file -->
hdfs dfs -getfacl -R /user/hdfs/file
```

#### setfacl

```
hdfs dfs -setfacl [-R] [-b|-k -m|-x <acl_spec> <path>]|[--set <acl_spec> <path>]

<!-- COMMAND OPTIONS

<path>: Path to the file or directory for which ACLs should be set.

-R: Use this option to recursively list ACLs for all files and directories.

-b: Revoke all permissions except the base ACLs for user, groups and others.

-k: Remove the default ACL.

-m: Add new permissions to the ACL with this option. Does not affect existing permissions.

-x: Remove only the ACL specified.

<acl_spec>: Comma-separated list of ACL permissions.

--set: Use this option to completely replace the existing ACL for the path specified.

Previous ACL entries will no longer apply.

-->
```

### **Examples:**

```
<!-- To give user ben read & write permission over /user/hdfs/file -->
hdfs dfs -setfacl -m user:ben:rw- /user/hdfs/file

<!-- To remove user alice's ACL entry for /user/hdfs/file -->
hdfs dfs -setfacl -x user:alice /user/hdfs/file

<!-- To give user hadoop read & write access, and group or others read-only access -->
hdfs dfs -setfacl --set user:hadoop:rw-,group::r--,other::r-- /user/hdfs/file
```


More details about using this feature can be found <u>here</u>.

# Authorization With Apache Sentry (Incubating)

Apache Sentry (incubating) is a granular, role-based authorization module for Hadoop. Sentry provides the ability to control and enforce precise levels of privileges on data for authenticated users and applications on a Hadoop cluster. Sentry currently works out of the box with Apache Hive, Hive Metastore/HCatalog, Apache Solr, Cloudera Impala and HDFS (limited to Hive table data).

Sentry is designed to be a pluggable authorization engine for Hadoop components. It allows you to define authorization rules to validate a user or application's access requests for Hadoop resources. Sentry is highly modular and can support authorization for a wide variety of data models in Hadoop.

### **Architecture Overview**



There are three components involved in the authorization process:

## Sentry Server

The Sentry RPC server manages the authorization metadata. It supports interfaces to securely retrieve and manipulate the metadata.

## Data Engine

This is a data processing application such as Hive or Impala that needs to authorize access to data or metadata resources. The data engine loads the Sentry plugin and all client requests for accessing resources are intercepted and routed to the Sentry plugin for validation.

## Sentry Plugin

The Sentry plugin runs in the data engine. It offers interfaces to manipulate authorization metadata stored in the Sentry server, and includes the authorization policy engine that evaluates access requests using the authorization metadata retrieved from the server.

# **Key Concepts**

- Authentication Verifying credentials to reliably identify a user
- Authorization Limiting the user's access to a given resource
- User Individual identified by underlying authentication system
- Group A set of users, maintained by the authentication system
- Privilege An instruction or rule that allows access to an object
- Role A set of privileges; a template to combine multiple access rules
- Authorization models Defines the objects to be subject to authorization rules and the granularity of actions allowed. For example, in the SQL model, the objects can be databases or tables, and the actions are SELECT, INSERT, CREATE and so on. For the Search model, the objects are indexes, collections and documents; the access modes are query, update and so on.

#### User Identity and Group Mapping

Sentry relies on underlying authentication systems such as Kerberos or LDAP to identify the user. It also uses the group mapping mechanism configured in Hadoop to ensure that Sentry sees the same group mapping as other components of the Hadoop ecosystem.

Consider users Alice and Bob who belong to an Active Directory (AD) group called finance-department. Bob also belongs to a group called finance-managers. In Sentry, you first create roles and then grant privileges to these roles. For example, you can create a role called Analyst and grant SELECT on tables Customer and Sales to this role.

The next step is to join these authentication entities (users and groups) to authorization entities (roles). This can be done by granting the Analyst role to the finance-department group. Now Bob and Alice who are members of the finance-department group get SELECT privilege to the Customer and Sales tables.


#### Role-Based Access Control

Role-based access control (RBAC) is a powerful mechanism to manage authorization for a large set of users and data objects in a typical enterprise. New data objects get added or removed, users join, move, or leave organisations all the time. RBAC makes managing this a lot easier. Hence, as an extension of the discussed previously, if Carol joins the Finance Department, all you need to do is add her to the finance-department group in AD. This will give Carol access to data from the Sales and Customer tables.

#### Unified Authorization

Another important aspect of Sentry is the unified authorization. The access control rules once defined, work across multiple data access tools. For example, being granted the Analyst role in the previous example will allow Bob, Alice, and others in the finance-department group to access table data from SQL engines such as Hive and Impala, as well as via MapReduce, Pig applications or metadata access via HCatalog.

# Sentry Integration with the Hadoop Ecosystem



As illustrated above, Apache Sentry works with multiple Hadoop components. At the heart you have the Sentry Server which stores authorization metadata and provides APIs for tools to retrieve and modify this metadata securely.


Note that the Sentry server only facilitates the metadata. The actual authorization decision is made by a policy engine which runs in data processing applications such as Hive or Impala. Each component loads the Sentry plugin which includes the service client for dealing with the Sentry service and the policy engine to validate the authorization request.

# Hive and Sentry

Consider an example where Hive gets a request to access an object in a certain mode by a client. If Bob submits the following Hive query:

```
select * from production.sales
```


Hive will identify that user Bob is requesting SELECT access to the Sales table. At this point Hive will ask the Sentry plugin to validate Bob's access request. The plugin will retrieve Bob's privileges related to the Sales table and the policy engine will determine if the request is valid.



Hive works with both, the Sentry service and policy files. Cloudera recommends you use the Sentry service which makes it easier to manage user privileges. For more details and instructions, see The Sentry Service on page 236 or Sentry Policy File Authorization on page 258.

# Impala and Sentry


Authorization processing in Impala is similar to that in Hive. The main difference is caching of privileges. Impala's Catalog server manages caching schema metadata and propagating it to all Impala server nodes. This Catalog server caches Sentry metadata as well. As a result, authorization validation in Impala happens locally and much faster.



For detailed documentation, see **Enabling Sentry Authorization for Impala** on page 276.

# Sentry-HDFS Synchronization

Sentry-HDFS authorization is focused on Hive warehouse data - that is, any data that is part of a table in Hive or Impala. The real objective of this integration is to expand the same authorization checks to Hive warehouse data being accessed from any other components such as Pig, MapReduce or Spark. At this point, this feature does not replace HDFS ACLs. Tables that are not associated with Sentry will retain their old ACLs.



The mapping of Sentry privileges to HDFS ACL permissions is as follows:

- SELECT privilege -> Read access on the file.
- INSERT privilege -> Write access on the file.
- ALL privilege -> Read and Write access on the file.

The NameNode loads a Sentry plugin that caches Sentry privileges as well Hive metadata. This helps HDFS to keep file permissions and Hive tables privileges in sync. The Sentry plugin periodically polls the Sentry and Metastore to keep the metadata changes in sync.

For example, if Bob runs a Pig job that is reading from the Sales table data files, Pig will try to get the file handle from HDFS. At that point the Sentry plugin on the NameNode will figure out that the file is part of Hive data and overlay Sentry privileges on top of the file ACLs. As a result, HDFS will enforce the same privileges for this Pig client that Hive would apply for a SQL query.

For HDFS-Sentry synchronization to work, you must use the Sentry service, not policy file authorization. See Synchronizing HDFS ACLs and Sentry Permissions on page 254, for more details.

# Search and Sentry

Sentry can apply a range of restrictions to various Search tasks, such accessing data or creating collections. These restrictions are consistently applied, regardless of the way users attempt to complete actions. For example, restricting access to data in a collection restricts that access whether queries come from the command line, from a browser, or through the admin console.

With Search, Sentry stores its privilege policies in a policy file (for example, sentry-provider.ini) which is stored in an HDFS location such as hdfs://ha-nn-uri/user/solr/sentry/sentry-provider.ini.

Sentry with Search does not support multiple policy files for multiple databases. However, you must use a separate policy file for each Sentry-enabled service. For example, Hive and Search were using policy file authorization, using a combined Hive and Search policy file would result in an invalid configuration and failed authorization on both services.

Note: While Hive and Impala are compatible with the database-backed Sentry service, Search still uses Sentry's policy file authorization. Note that it is possible for a single cluster to use both, the Sentry service (for Hive and Impala as described above) and Sentry policy files (for Solr).

For detailed documentation, see <u>Enabling Sentry Authorization for Search using the Command Line</u> on page 288.

#### Authorization Administration

The Sentry server supports APIs to securely manipulate roles and privileges. Both Hive and Impala support SQL statements to manage privileges natively. For example, you can use either Beeline or the Impala shell to execute the following statement:

GRANT ROLE Analyst TO GROUP finance-managers

Note:

When Sentry is enabled, you must use Beeline to execute Hive queries. Hive CLI is not supported with Sentry.

Sentry assumes that HiveServer2 and Impala run as superusers, usually called hive and impala. To initiate top-level permissions for Sentry, an admin must login as a superuser.

Hue now supports a Security app to manage Sentry authorization. This allows users to explore and change table permissions. Here/s a video blog that demonstrates its functionality.

# The Sentry Service

Important: This is the documentation for the Sentry service introduced in CDH 5.1. If you want to use Sentry's previous policy file approach to secure your data, see Sentry Policy File Authorization on page 258.

The Sentry service is a RPC server that stores the authorization metadata in an underlying relational database and provides RPC interfaces to retrieve and manipulate privileges. It supports secure access to services using Kerberos. The service serves authorization metadata from the database backed storage; it does not handle actual privilege validation. The Hive and Impala services are clients of this service and will enforce Sentry privileges when configured to use Sentry.

The motivation behind introducing a new Sentry service is to make it easier to handle user privileges than the existing policy file approach. Providing a database instead, allows you to use the more traditional GRANT/REVOKE statements to modify privileges.

For more information on installing, upgrading and configuring the Sentry service, see:

# Prerequisites

- CDH 5.1.x (or later) managed by Cloudera Manager 5.1.x (or later). See the <u>Cloudera Manager Administration</u> Guide and Cloudera Installation and Upgrade for instructions.
- HiveServer2 and the Hive Metastore running with strong authentication. For HiveServer2, strong authentication is either Kerberos or LDAP. For the Hive Metastore, only Kerberos is considered strong authentication (to override, see Securing the Hive Metastore on page 249).
- Impala 1.4.0 (or later) running with strong authentication. With Impala, either Kerberos or LDAP can be configured to achieve strong authentication.
- Implement Kerberos authentication on your cluster. For instructions, see <a href="Enabling Kerberos Authentication"><u>Enabling Kerberos Authentication</u></a> Using the Wizard on page 16.

# **Terminologies**

- An object is an entity protected by Sentry's authorization rules. The objects supported in the current release are server, database, table, and URI.
- A **role** is a collection of rules for accessing a given Hive object.
- A privilege is granted to a role to govern access to an object. Supported privileges are:

Table 19: Valid privilege types and the objects they apply to

Privilege	Object
INSERT	DB, TABLE
SELECT	DB, TABLE
ALL	SERVER, TABLE, DB, URI

- A user is an entity that is permitted by the authentication subsystem to access the Hive service. This entity can be a Kerberos principal, an LDAP userid, or an artifact of some other pluggable authentication system supported by HiveServer2.
- A group connects the authentication system with the authorization system. It is a collection of one or more users who have been granted one or more authorization roles. Sentry allows a set of roles to be configured for a group.
- A configured group provider determines a user's affiliation with a group. The current release supports HDFS-backed groups and locally configured groups.

# Privilege Model

Sentry uses a role-based privilege model with the following characteristics.

- Allows any user to execute show function, desc function, and show locks.
- Allows the user to see only those tables and databases for which this user has privileges.
- Requires a user to have the necessary privileges on the URI to execute HiveQL operations that take in a location. Examples of such operations include LOAD, IMPORT, and EXPORT.
- Privileges granted on URIs are recursively applied to all subdirectories. That is, privileges only need to be granted on the parent directory.

### Important:


- When Sentry is enabled, you must use Beeline to execute Hive queries. Hive CLI is not supported with Sentry.
- When Sentry is enabled, a user with no privileges on a database will not be allowed to connect to HiveServer2. This is because the use <database> command is now executed as part of the connection to HiveServer2, which is why the connection fails. See HIVE-4256.

For more information, see Appendix: Authorization Privilege Model for Hive and Impala on page 238.

# User to Group Mapping

Required Role: Configurator Cluster Administrator Full Administrator

Group mappings in Sentry can be summarized as in the figure below.



The Sentry service only uses HadoopUserGroup mappings. You can refer <u>Configuring LDAP Group Mappings</u> on page 133 for details on configuring LDAP group mappings in Hadoop.

Important: Cloudera strongly recommends against using Hadoop's LdapGroupsMapping provider. LdapGroupsMapping should only be used in cases where OS-level integration is not possible. Production clusters require an identity provider that works well with all applications, not just Hadoop. Hence, often the preferred mechanism is to use tools such as SSSD, VAS or Centrify to replicate LDAP groups.

# Appendix: Authorization Privilege Model for Hive and Impala

Privileges can be granted on different objects in the Hive warehouse. Any privilege that can be granted is associated with a level in the object hierarchy. If a privilege is granted on a container object in the hierarchy, the base object automatically inherits it. For instance, if a user has ALL privileges on the database scope, then (s)he has ALL privileges on all of the base objects contained within that scope.

# Object Hierarchy in Hive

```
Server

Database

Table

Partition

Columns

View

Index

Function/Routine
Lock
```

### Table 20: Valid privilege types and objects they apply to

Privilege	Object
INSERT	DB, TABLE
SELECT	DB, TABLE
ALL	SERVER, TABLE, DB, URI

Table 21: Privilege hierarchy

Base Object	Granular privileges on object	Container object that contains the base object	Privileges on container object that implies privileges on the base object
DATABASE	ALL	SERVER	ALL
TABLE	INSERT	DATABASE	ALL
TABLE	SELECT	DATABASE	ALL
VIEW	SELECT	DATABASE	ALL

Table 22: Privilege table for Hive & Impala operations

Operation	Scope	Privileges	URI	Others
CREATE DATABASE	SERVER	ALL		
DROP DATABASE	DATABASE	ALL		
CREATE TABLE	DATABASE	ALL		
DROP TABLE	TABLE	ALL		
CREATE VIEW	DATABASE; SELECT on TABLE	ALL		SELECT on TABLE
DROP VIEW	VIEW/TABLE	ALL		
ALTER TABLE ADD COLUMNS	TABLE	ALL		
ALTER TABLE REPLACE COLUMNS	TABLE	ALL		
ALTER TABLE CHANGE column	TABLE	ALL		
ALTER TABLE RENAME	TABLE	ALL		
ALTER TABLE SET TBLPROPERTIES	TABLE	ALL		
ALTER TABLE SET FILEFORMAT	TABLE	ALL		
ALTER TABLE SET LOCATION	TABLE	ALL	URI	
ALTER TABLE ADD PARTITION	TABLE	ALL		
ALTER TABLE ADD PARTITION location	TABLE	ALL	URI	
ALTER TABLE DROP PARTITION	TABLE	ALL		
ALTER TABLE PARTITION SET FILEFORMAT	TABLE	ALL		
SHOW CREATE TABLE	TABLE	SELECT/INSERT		

Operation	Scope	Privileges	URI	Others
SHOW PARTITIONs	TABLE	SELECT/INSERT		
DESCRIBE TABLE	TABLE	SELECT/INSERT		
LOAD DATA	TABLE	INSERT	URI	
SELECT	TABLE	SELECT		
INSERT OVERWRITE TABLE	TABLE	INSERT		
CREATE TABLE AS SELECT	DATABASE; SELECT on TABLE	ALL		SELECT on TABLE
USE <dbname></dbname>	Any			
CREATE FUNCTION	SERVER	ALL		
ALTER TABLE SET SERDEPROPERTIES	TABLE	ALL		
ALTER TABLE PARTITION SET SERDEPROPERTIES	TABLE	ALL		
Hive-Only Operations				
INSERT OVERWRITE DIRECTORY	TABLE	INSERT	URI	
Analyze TABLE	TABLE	SELECT + INSERT		
IMPORT TABLE	DATABASE	ALL	URI	
EXPORT TABLE	TABLE	SELECT	URI	
ALTER TABLE TOUCH	TABLE	ALL		
ALTER TABLE TOUCH PARTITION	TABLE	ALL		
ALTER TABLE CLUSTERED BY SORTED BY	TABLE	ALL		
ALTER TABLE ENABLE/DISABLE	TABLE	ALL		
ALTER TABLE PARTITION ENABLE/DISABLE	TABLE	ALL		
ALTER TABLE PARTITION RENAME TO PARTITION	TABLE	ALL		
MSCK REPAIR TABLE	TABLE	ALL		
ALTER DATABASE	DATABASE	ALL		
DESCRIBE DATABASE	DATABASE	SELECT/INSERT		
SHOW COLUMNS	TABLE	SELECT/INSERT		
CREATE INDEX	TABLE	ALL		

Operation	Scope	Privileges	URI	Others
DROP INDEX	TABLE	ALL		
SHOW INDEXES	TABLE	SELECT/INSERT		
GRANT PRIVILEGE	Allowed only for Sentry admin users			
REVOKE PRIVILEGE	Allowed only for Sentry admin users			
SHOW GRANTS	Allowed only for Sentry admin users			
SHOW TBLPROPERTIES	TABLE	SELECT/INSERT		
DESCRIBE TABLE PARTITION	TABLE	SELECT/INSERT		
ADD JAR	Not Allowed			
ADD FILE	Not Allowed			
DFS	Not Allowed			
Impala-Only Operations				
EXPLAIN	TABLE	SELECT		
INVALIDATE METADATA	SERVER	ALL		
INVALIDATE METADATA	TABLE	SELECT/INSERT		
REFRESH	TABLE	SELECT/INSERT		
DROP FUNCTION	SERVER	ALL		
COMPUTE STATS	TABLE	ALL		

# Installing and Upgrading the Sentry Service

This topic describes how to install and upgrade the Sentry service. If you are migrating from Sentry policy files to the database-backed Sentry service, see Migrating from Sentry Policy Files to the Sentry Service on page 244.

## Adding the Sentry Service

Use one of the following sections to add/install the Sentry service:

# Adding the Sentry Service Using Cloudera Manager

# Required Role: Cluster Administrator Full Administrator

- 1. On the Home page, click to the right of the cluster name and select Add a Service. A list of service types display. You can add one type of service at a time.
- 2. Select the **Sentry** service and click **Continue**.
- 3. Select the radio button next to the services on which the new service should depend and click Continue.
- 4. Customize the assignment of role instances to hosts. The wizard evaluates the hardware configurations of the hosts to determine the best hosts for each role. These assignments are typically acceptable, but you can reassign role instances to hosts of your choosing, if desired.

Click a field below a role to display a dialog containing a pageable list of hosts. If you click a field containing multiple hosts, you can also select All Hosts to assign the role to all hosts or Custom to display the pageable hosts dialog.

The following shortcuts for specifying host names are supported:

Range of hostnames (without the domain portion)

Range Definition	Matching Hosts
10.1.1.[1-4]	10.1.1.1, 10.1.1.2, 10.1.1.3, 10.1.1.4
host[1-3].company.com	host1.company.com, host2.company.com, host3.company.com
host[07-10].company.com	host07.company.com, host08.company.com, host09.company.com, host10.company.com

- IP addresses
- Rack name

Click the View By Host button for an overview of the role assignment by host ranges.

- 5. Configure database settings. You can use either an embedded or a custom database.
  - a. Choose the database type:
    - Leave the default setting of Use Embedded Database to have Cloudera Manager create and configure required databases. Make a note of the auto-generated passwords.
    - Select Use Custom Databases to specify external databases.
      - 1. Enter the database host, database type, database name, username, and password for the database that you created when you set up the database.
  - b. Click Test Connection to confirm that Cloudera Manager can communicate with the database using the information you have supplied. If the test succeeds in all cases, click Continue; otherwise check and correct the information you have provided for the database and then try the test again. (For some servers, if you are using the embedded database, you will see a message saying the database will be created at a later step in the installation process.) The Review Changes page displays.
- **6.** Click **Continue** then click **Finish**. You are returned to the <u>Home</u> page.
- 7. Verify the new service is started properly by checking the health status for the new service. If the Health Status is **Good**, then the service started properly.
- **8.** To use the Sentry service, begin by enabling <u>Hive</u> and <u>Impala</u> for the service.

# Installing Sentry Using the Command Line

Use the following the instructions, depending on your operating system, to install the latest version of Sentry.

- Important: Configuration files
  - If you install a newer version of a package that is already on the system, configuration files that you have modified will remain intact.
  - If you uninstall a package, the package manager renames any configuration files you have modified from <file> to <file>.rpmsave. If you then re-install the package (probably to install a new version) the package manager creates a new <file> with applicable defaults. You are responsible for applying any changes captured in the original configuration file to the new configuration file. In the case of Ubuntu and Debian upgrades, you will be prompted if you have made changes to a file for which there is a new version; for details, see Automatic handling of configuration files by dpkq.

OS	Command	
RHEL	\$ sudo yum install sentry	
SLES	\$ sudo zypper install sentry	

OS	Command
Ubuntu or Debian	<pre>\$ sudo apt-get update; \$ sudo apt-get install sentry</pre>

### Starting the Sentry Service

Perform the following steps to start the Sentry service on your cluster.

- 1. Set the SENTRY\_HOME and HADOOP\_HOME parameters.
- 2. Create the Sentry database schema using the Sentry schematool. Sentry, by default, does not initialize the schema. The schematool is a built-in way for you to deploy the backend schema required by the Sentry service. For example, the following command uses the schematool to initialize the schema for a MySQL

```
bin/sentry --command schema-tool --conffile <sentry-site.xml> --dbType mysql
--initSchema
```

Alternatively, you can set the sentry.verify.schema.version configuration property to false. However, this is not recommended.

**3.** Start the Sentry service.

```
bin/sentry --command service --conffile <sentry-site.xml>
```

# Upgrading the Sentry Service

Use one of the following sections to upgrade the Sentry service:

# Upgrading the Sentry Service Using Cloudera Manager

If you have a cluster managed by Cloudera Manager, go to Upgrading CDH and Managed Services Using Cloudera Manager and follow the instructions depending on the version of CDH you are upgrading to. If you are upgrading from CDH 5.1, you will notice an extra step in the procedure to upgrade the Sentry database schema.

For command-line instructions, continue reading.

## Upgrading the Sentry Service Using the Command Line

1. Stop the Sentry service by identifying the PID of the Sentry Service and use the kill command to end the process:

```
ps -ef | grep sentry
kill -9 <PID>
```

Replace <PID> with the PID of the Sentry Service.

2. Remove the previous version of Sentry.

OS	Command	
RHEL	\$ sudo yum remove sentry	
SLES	\$ sudo zypper remove sentry	
Ubuntu or Debian	\$ sudo apt-get remove sentry	

3. Install the new version of Sentry.

OS	Command
RHEL	\$ sudo yum install sentry
SLES	\$ sudo zypper install sentry

OS	Command
Ubuntu or Debian	<pre>\$ sudo apt-get update; \$ sudo apt-get install sentry</pre>

## 4. (From CDH 5.1 to CDH 5.x) Upgrade Sentry Database Schema

Use the Sentry schematool to upgrade the database schema as follows:

```
bin/sentry --command schema-tool --conffile <sentry-site.xml> --dbType <db-type> --upgradeSchema
```

Where <db-type> should be either mysql, postgres or oracle.

## 5. Start the Sentry Service

- **a.** Set the SENTRY\_HOME and HADOOP\_HOME parameters.
- **b.** Run the following command:

```
bin/sentry --command service --conffile <sentry-site.xml>
```

# Migrating from Sentry Policy Files to the Sentry Service

Required Role: Cluster Administrator Full Administrator

The following steps describe how you can upgrade from Sentry's policy file-based approach to the new database-backed Sentry service.

- 1. If you haven't already done so, upgrade your cluster to the latest version of CDH and Cloudera Manager. Refer the <u>Cloudera Manager Administration Guide</u> for instructions.
- 2. Disable the existing Sentry policy file for any Hive or Impala services on the cluster. To do this:
  - **a.** Navigate to the Hive or Impala service.
  - **b.** Click the **Configuration** tab.
  - c. Select Scope > Service Name (Service-Wide).
  - d. Select Category > Policy File Based Sentry.
  - **e.** Deselect **Enable Sentry Authorization using Policy Files**. Cloudera Manager will throw a validation error if you attempt to configure the Sentry service while this property is checked.
  - f. Repeat for any remaining Hive or Impala services.
- 3. Add the new Sentry service to your cluster. For instructions, see Adding the Sentry Service on page 241.
- **4.** To begin using the Sentry service, see <u>Enabling the Sentry Service Using Cloudera Manager</u> on page 244 and <u>Configuring Impala as a Client for the Sentry Service</u> on page 248.
- 5. Use the command-line interface Beeline to issue grants to the Sentry service to match the contents of your old policy file(s). For more details on the Sentry service and examples on using Grant/Revoke statements to match your policy file, see <a href="Hive SQL Syntax">Hive SQL Syntax</a> on page 250.

# Configuring the Sentry Service

This topic describes how to enable the Sentry service for Hive and Impala, and configuring the Hive metastore to communicate with the service.

Enabling the Sentry Service Using Cloudera Manager

Required Role: Configurator Cluster Administrator Full Administrator

# Before Enabling the Sentry Service

• Ensure you satisfy all the <u>Prerequisites</u> on page 236 for the Sentry service.

- The Hive warehouse directory (/user/hive/warehouse or any path you specify as hive.metastore.warehouse.dir in your hive-site.xml) must be owned by the Hive user and group.
  - Permissions on the warehouse directory must be set as follows (see following Note for caveats):
    - 771 on the directory itself (for example, /user/hive/warehouse)
    - 771 on all subdirectories (for example, /user/hive/warehouse/mysubdir)
    - All files and subdirectories should be owned by hive:hive

## For example:

```
$ sudo -u hdfs hdfs dfs -chmod -R 771 /user/hive/warehouse
$ sudo -u hdfs hdfs dfs -chown -R hive:hive /user/hive/warehouse
```

#### Note:

- If you set hive.warehouse.subdir.inherit.perms to true in hive-site.xml, the permissions on the subdirectories will be set when you set permissions on the warehouse directory itself.
- If a user has access to any object in the warehouse, that user will be able to execute use
  default. This ensures that use default commands issued by legacy applications work
  when Sentry is enabled.
- Important: These instructions override the recommendations in the Hive section of the CDH 5 Installation Guide.
- Disable impersonation for HiveServer2 in the Cloudera Manager Admin Console:
  - 1. Go to the Hive service.
  - 2. Click the Configuration tab.
  - **3.** Select **Scope** > **HiveServer2**.
  - 4. Select Category > Main.
  - 5. Select HiveServer2 Enable Impersonation.
  - 6. Click Save Changes to commit the changes.
- If you are using MapReduce, enable the Hive user to submit MapReduce jobs.
  - 1. Open the Cloudera Manager Admin Console and go to the MapReduce service.
  - 2. Click the Configuration tab.
  - **3.** Select **Scope** > **TaskTracker**.
  - 4. Select Category > Security.
  - 5. Set the Minimum User ID for Job Submission property to zero (the default is 1000).
  - **6.** Click **Save Changes** to commit the changes.
  - 7. Repeat steps 1-6 for *every* TaskTracker role group for the MapReduce service that is associated with Hive, if more than one exists.
  - **8.** Restart the MapReduce service.
- If you are using YARN, enable the Hive user to submit YARN jobs.
  - 1. Open the Cloudera Manager Admin Console and go to the YARN service.
  - 2. Click the Configuration tab.
  - 3. Select Scope > NodeManager.
  - 4. Select Category > Security.
  - 5. Ensure the Allowed System Users property includes the hive user. If not, add hive.
  - **6.** Click **Save Changes** to commit the changes.

- 7. Repeat steps 1-6 for *every* NodeManager role group for the YARN service that is associated with Hive, if more than one exists.
- 8. Restart the YARN service.
- Important: Ensure you have unchecked the Enable Sentry Authorization using Policy Files configuration property for both Hive and Impala under the Policy File Based Sentry category before you proceed.

# Enabling the Sentry Service for Hive

- 1. Go to the Hive service.
- 2. Click the Configuration tab.
- 3. Select Scope > Hive (Service-Wide).
- 4. Select Category > Main.
- **5.** Locate the **Sentry Service** property and select Sentry.
- 6. Click Save Changes to commit the changes.
- 7. Restart the Hive service.

## Enabling the Sentry Service for Impala

- 1. Enable the Sentry service for Hive (as instructed above).
- 2. Go to the Impala service.
- 3. Click the Configuration tab.
- 4. Select Scope > Impala (Service-Wide).
- **5.** Select Category > Main.
- **6.** Locate the **Sentry Service** property and select Sentry.
- 7. Click Save Changes to commit the changes.
- 8. Restart Impala.

# Enabling the Sentry Service for Hue

To interact with Sentry using Hue, enable the Sentry service as follows:

- 1. Enable the Sentry service for Hive and/or Impala (as instructed above).
- 2. Go to the Hue service.
- 3. Click the Configuration tab.
- 4. Select Scope > Hue (Service-Wide).
- 5. Select Category > Main.
- **6.** Locate the **Sentry Service** property and select Sentry.
- 7. Click Save Changes to commit the changes.
- 8. Restart Hue.

# Enabling the Sentry Service Using the Command Line

- Important:
  - If you use Cloudera Manager, do not use these command-line instructions.
  - This information applies specifically to CDH 5.4.x. If you use an earlier version of CDH, see the
    documentation for that version located at <u>Cloudera Documentation</u>.

# Before Enabling the Sentry Service

- The Hive warehouse directory (/user/hive/warehouse or any path you specify as hive.metastore.warehouse.dir in your hive-site.xml) must be owned by the Hive user and group.
  - Permissions on the warehouse directory must be set as follows (see following Note for caveats):

- 771 on the directory itself (for example, /user/hive/warehouse)
- 771 on all subdirectories (for example, /user/hive/warehouse/mysubdir)
- All files and subdirectories should be owned by hive:hive

## For example:

```
$ sudo -u hdfs hdfs dfs -chmod -R 771 /user/hive/warehouse
$ sudo -u hdfs hdfs dfs -chown -R hive:hive /user/hive/warehouse
```

#### Note:

- If you set hive.warehouse.subdir.inherit.perms to true in hive-site.xml, the permissions on the subdirectories will be set when you set permissions on the warehouse directory itself.
- If a user has access to any object in the warehouse, that user will be able to execute use default. This ensures that use default commands issued by legacy applications work when Sentry is enabled.
- Important: These instructions override the recommendations in the Hive section of the CDH 5 Installation Guide.
- HiveServer2 impersonation must be turned off.
- If you are using MapReduce, you must enable the Hive user to submit MapReduce jobs. You can ensure that this is true by setting the minimum user ID for job submission to 0. Edit the taskcontroller.cfg file and set min.user.id=0.

If you are using YARN, you must enable the Hive user to submit YARN jobs, add the user hive to the allowed.system.users configuration property. Edit the container-executor.cfg file and add hive to the allowed.system.users property. For example,

```
allowed.system.users = nobody,impala,hive
```

Important: You must restart the cluster and HiveServer2 after changing these values.

# Configuring HiveServer2 for the Sentry Service

Add the following properties to hive-site.xml to allow the Hive service to communicate with the Sentry service.

```
property>
  <name>hive.security.authorization.task.factory</name>
  <value>org.apache.sentry.binding.hive.SentryHiveAuthorizationTaskFactoryImpl</value>
</property>
cpropert.v>
  <name>hive.server2.session.hook</name>
   <value>org.apache.sentry.binding.hive.HiveAuthzBindingSessionHook</value>
</property>
cproperty>
  <name>hive.sentry.conf.url</name>
  <value>file:///{{PATH/TO/DIR}}/sentry-site.xml</value>
</property>
property>
  <name>hive.security.authorization.task.factory</name>
  <value>org.apache.sentry.binding.hive.SentryHiveAuthorizationTaskFactoryImpl</value>
```

## Configuring the Hive Metastore for the Sentry Service

Add the following properties to hive-site.xml to allow the Hive metastore to communicate with the Sentry service.

```
property>
    <name>hive.metastore.client.impl</name>
    <value>org.apache.sentry.binding.metastore.SentryHiveMetaStoreClient</value>
    <description>Sets custom Hive metastore client which Sentry uses to filter out
metadata.</description>
</property>
cproperty>
    <name>hive.metastore.pre.event.listeners
    <value>org.apache.sentry.binding.metastore.MetastoreAuthzBinding/value>
    <description>list of comma separated listeners for metastore events.</description>
</property>
property>
   <name>hive.metastore.event.listeners</name>
   <value>org.apache.sentry.binding.metastore.SentryMetastorePostEventListener</value>
    <description>list of comma separated listeners for metastore, post
events.</description>
</property>
```

## Configuring Impala as a Client for the Sentry Service

Set the following configuration properties in sentry-site.xml.

```
opertv>
  <name>sentry.service.client.server.rpc-port</name>
  <value>3893</value>
</property>
cproperty>
  <name>sentry.service.client.server.rpc-address
  <value>hostname</value>
</property>
cproperty>
  <name>sentry.service.client.server.rpc-connection-timeout</name>
  <value>200000
</property>
property>
  <name>sentry.service.security.mode
   <value>none</value>
</property>
```

You must also add the following configuration properties to Impala's /etc/default/impala file. For more information, see Configuring Impala Startup Options through the Command Line.

• On the catalogd and the impalad.

```
--sentry_config=<absolute path to sentry service configuration file>
```

On the impalad.

```
--server_name=<server name>
```

If the --authorization\_policy\_file flag is set, Impala will use the policy file-based approach. Otherwise, the database-backed approach will be used to implement authorization.

### Configuring Pig and HCatalog for the Sentry Service

Once you have the Sentry service up and running, and Hive has been configured to use the Sentry service, there are some configuration changes you must make to your cluster to allow Pig, MapReduce (using HCatLoader, HCatStorer) and WebHCat queries to access Sentry-secured data stored in Hive.

Since the Hive warehouse directory is owned by hive: hive, with its permissions set to 771, with these settings, other user requests such as commands coming through Pig jobs, WebHCat queries, and MapReduce jobs, may fail. In order to give these users access, perform the following configuration changes:

- Use HDFS ACLs to define permissions on a specific directory or file of HDFS. This directory/file is generally mapped to a database, table, partition, or a data file.
- Users running these jobs should have the required permissions in Sentry to add new metadata or read metadata from the Hive Metastore Server. For instructions on how to set up the required permissions, see Hive SQL Syntax on page 250. You can use HiveServer2's command line interface, Beeline to update the Sentry database with the user privileges.

#### Examples:

- A user who is using Pig HCatLoader will require read permissions on a specific table or partition. In such a case, you can GRANT read access to the user in Sentry and set the ACL to read and execute, on the file being
- A user who is using Pig HCatStorer will require ALL permissions on a specific table. In this case, you grant ALL access to the user in Sentry and set the ACL to write and execute, on the table being used.

## Securing the Hive Metastore

It's important that the Hive metastore be secured. If you want to override the Kerberos prerequisite for the Hive metastore, set the sentry. hive.testing.mode property to true to allow Sentry to work with weaker authentication mechanisms. Add the following property to the HiveServer2 and Hive metastore's sentry-site.xml:

```
cproperty>
 <name>sentry.hive.testing.mode</name>
  <value>true</value>
</property>
```

Impala does not require this flag to be set.

Warning: Cloudera strongly recommends against enabling this property in production. Use Sentry's testing mode only in test environments.

You canturn on Hive metastore security using the instructions in <u>Cloudera Security</u>. To secure the Hive metastore; see <u>Hive Metastore Server Security Configuration</u> on page 90.

### Using User-Defined Functions with HiveServer2

The ADD JAR command does not work with HiveServer2 and the Beeline client when Beeline runs on a different host. As an alternative to ADD JAR, Hive's auxiliary paths functionality should be used. There are some differences in the procedures for creating permanent functions and temporary functions when Sentry is enabled. For detailed instructions, see:

- User-Defined Functions (UDFs) with HiveServer2 Using Cloudera Manager OR
- User-Defined Functions (UDFs) with HiveServer2 Using the Command Line

# Sentry Debugging and Failure Scenarios

This topic describes how Sentry deals with conflicting policies, how to debug Sentry authorization request failures and how different CDH components respond when the Sentry service fails.

## **Resolving Policy Conflicts**

Sentry treats all policies independently. Hence, for any operation, if Sentry can find a policy that allows it, that operation will be allowed. Consider an example with a table, test\_db.test\_tbl, whose HDFS directory is located at hdfs://user/hive/warehouse/test\_db.db/test\_tbl, and grant the following conflicting privileges to a

user with the role, test\_role. That is, you are granting ALL privilege to the role test\_role on the URI, but only the SELECT privilege on the table itself.

```
GRANT ALL ON URI 'hdfs:///user/hive/warehouse/test_db.db/test_tbl' to role test_role;

USE test_db;

GRANT SELECT ON TABLE test_tbl to role test_role;
```

With these privileges, all users with the role test\_role will be able to carry out the EXPORT TABLE operation even though they should only have SELECT privileges on test\_db.test\_tbl:

```
EXPORT TABLE <another-table-user-can-read> TO 'hdfs://user/hive/warehouse/test_db.db/test_tbl'
```

# Debugging Failed Sentry Authorization Requests

Sentry logs all facts that lead up to authorization decisions at the debug level. If you do not understand why Sentry is denying access, the best way to debug is to temporarily turn on debug logging:

- In Cloudera Manager, add log4j.logger.org.apache.sentry=DEBUG to the logging settings for your service through the corresponding Logging Safety Valve field for Impala or HiveServer2.
- On systems not managed by Cloudera Manager, add log4j.logger.org.apache.sentry=DEBUG to the log4j.properties file on each host in the cluster, in the appropriate configuration directory for each service.

Specifically, look for exceptions and messages such as:

```
FilePermission server..., RequestPermission server..., result [true|false]
```

which indicate each evaluation Sentry makes. The FilePermission is from the policy file, while RequestPermission is the privilege required for the query. A RequestPermission will iterate over all appropriate FilePermission settings until a match is found. If no matching privilege is found, Sentry returns false indicating "Access Denied".

# Sentry Service Failure Scenarios

If the Sentry service fails and you attempt to access the Hive warehouse, Hive, Impala and HDFS will behave as follows:

- Hive: Queries to the Hive warehouse will fail with an authentication error.
- Impala: The Impala Catalog server caches Sentry privileges. If Sentry goes down, Impala queries will continue to work and will be authorized against this cached copy of the metadata. However, authorization DDLs such as CREATE ROLE OF GRANT ROLE will fail.
- HDFS/Sentry Synchronized Permissions: Affected HDFS files will continue to use a cached copy of the synchronized ACLs for a configurable period of time (by default, 60 seconds), after which they will fall back to NameNode ACLs.
- **Solr:** Solr does not use the Sentry service, hence there will be no impact.

# Hive SQL Syntax

Sentry permissions can be configured through Grant and Revoke statements issued either interactively or programmatically through the HiveServer2 SQL command line interface, Beeline (documentation available <a href="here">here</a>). The syntax described below is very similar to the GRANT/REVOKE commands available in well-established relational database systems.

- Important:
  - When Sentry is enabled, you must use Beeline to execute Hive queries. Hive CLI is not supported with Sentry.
  - There are some differences in syntax between Hive and the corresponding Impala SQL statements. For the Impala syntax, see <u>SQL Statements</u>.

#### **CREATE ROLE Statement**

The CREATE ROLE statement creates a role to which privileges can be granted. Privileges can be granted to roles, which can then be assigned to users. A user that has been assigned a role will only be able to exercise the privileges of that role.

Only users that have administrative privileges can create/drop roles. By default, the hive, impala and hue users have admin privileges in Sentry.

```
CREATE ROLE [role_name];
```

#### **DROP ROLE Statement**

The DROP ROLE statement can be used to remove a role from the database. Once dropped, the role will be revoked for all users to whom it was previously assigned. Queries that are already executing will not be affected. However, since Hive checks user privileges before executing each query, active user sessions in which the role has already been enabled will be affected.

```
DROP ROLE [role_name];
```

#### **GRANT ROLE Statement**

The GRANT ROLE statement can be used to grant roles to groups. Only Sentry admin users can grant roles to a group.

```
GRANT ROLE role_name [, role_name]
   TO GROUP <groupName> [,GROUP <groupName>]
```

#### **REVOKE ROLE Statement**

The REVOKE ROLE statement can be used to revoke roles from groups. Only Sentry admin users can revoke the role from a group.

```
REVOKE ROLE role_name [, role_name]
   FROM GROUP <groupName> [,GROUP <groupName>]
```

#### GRANT < PRIVILEGE > Statement

In order to grant privileges on an object to a role, the user must be a Sentry admin user.

```
<PRIVILEGE> [ , <PRIVILEGE> ]
ON <OBJECT> <object_name>
TO ROLE <roleName> [,ROLE <roleName>]
```

# REVOKE < PRIVILEGE > Statement

Since only authorized admin users can create roles, consequently only Sentry admin users can revoke privileges from a group.

```
REVOKE
    <PRIVILEGE> [ , <PRIVILEGE>
    ON <OBJECT> <object_name>
    FROM ROLE <roleName> [,ROLE <roleName>]
```

### GRANT < PRIVILEGE > ... WITH GRANT OPTION

With CDH 5.2, you can delegate granting and revoking privileges to other roles. For example, a role that is granted a privilege with Grant Option can Grant/Revoke the same privilege to/from other roles. Hence, if a role has

the ALL privilege on a database and the WITH GRANT OPTION set, users granted that role can execute GRANT/REVOKE statements only for that database or child tables of the database.

```
<PRIVILEGE>
ON <OBJECT> <object_name>
TO ROLE <roleName>
WITH GRANT OPTION
```

Only a role with grant option on a specific privilege or its parent privilege can revoke that privilege from other roles. Once the following statement is executed, all privileges with and without grant option are revoked.

```
REVOKE
   <PRIVILEGE>
   ON <OBJECT> <object_name>
   FROM ROLE <roleName>
```

Hive does not currently support revoking only the WITH GRANT OPTION from a privilege previously granted to a role. To remove the WITH GRANT OPTION, revoke the privilege and grant it again without the WITH GRANT OPTION flag.

#### **SET ROLE Statement**

The SET ROLE statement can be used to specify a role to be enabled for the current session. A user can only enable a role that has been granted to them. Any roles not listed and not already enabled are disabled for the current session. If no roles are enabled, the user will have the privileges granted by any of the roles that (s)he belongs to.

To enable a specific role:

```
SET ROLE <roleName>;
```

To enable all roles:

```
SET ROLE ALL;
```

No roles enabled:

```
SET ROLE NONE;
```

## SHOW Statement

To list all the roles in the system (only for sentry admin users):

```
SHOW ROLES;
```

To list all the roles in effect for the current user session:

```
SHOW CURRENT ROLES;
```

To list all the roles assigned to the given <groupName> (only allowed for Sentry admin users and others users that are part of the group specified by <groupName>):

```
SHOW ROLE GRANT GROUP <groupName>;
```

The SHOW statement can also be used to list the privileges that have been granted to a role or all the grants given to a role for a particular object.

To list all the grants for the given <roleName> (only allowed for Sentry admin users and other users that have been granted the role specified by <roleName>):

```
SHOW GRANT ROLE <roleName>;
```

To list all the grants for a role on the given <objectName> (only allowed for Sentry admin users and other users that have been granted the role specified by <roleName>):

```
SHOW GRANT ROLE <roleName> on OBJECT <objectName>;
```

# Example: Using Grant/Revoke Statements to Match an Existing Policy File

Here is a sample policy file:

```
[groups]
# Assigns each Hadoop group to its set of roles
manager = analyst_role, junior_analyst_role
analyst = analyst_role
jranalyst = junior_analyst_role
customers_admin = customers_admin_role
admin = admin role
[roles] # The uris below define a define a landing skid which
# the user can use to import or export data from the system.
# Since the server runs as the user "hive" files in that directory
# must either have the group hive and read/write set or
# be world read/write.
analyst_role = server=server1->db=analyst1, \
   server=server1->db=jranalyst1->table=*->action=select
    server=server1->uri=hdfs://ha-nn-uri/landing/analyst1
junior_analyst_role = server=server1->db=jranalyst1,
    server=server1->uri=hdfs://ha-nn-uri/landing/jranalyst1
# Implies everything on server1.
admin role = server=server1
```

The following sections show how you can use the new GRANT statements to assign privileges to roles (and assign roles to groups) to match the sample policy file above.

### Grant privileges to analyst\_role:

```
CREATE ROLE analyst_role;
GRANT ALL ON DATABASE analyst1 TO ROLE analyst_role;
GRANT SELECT ON DATABASE jranalyst1 TO ROLE analyst_role;
GRANT ALL ON URI 'hdfs://ha-nn-uri/landing/analyst1' \
TO ROLE analyst_role;
```

# Grant privileges to junior\_analyst\_role:

```
CREATE ROLE junior_analyst_role;
| GRANT ALL ON DATABASE jranalyst1 TO ROLE junior_analyst_role;
| GRANT ALL ON URI 'hdfs://ha-nn-uri/landing/jranalyst1' \
| TO ROLE junior_analyst_role;
```

### Grant privileges to admin\_role:

```
CREATE ROLE admin_role
GRANT ALL ON SERVER server TO ROLE admin_role;
```

### Grant roles to groups:

```
GRANT ROLE admin_role TO GROUP admin;
GRANT ROLE analyst_role TO GROUP analyst;
GRANT ROLE jranalyst_role TO GROUP jranalyst;
```

# Synchronizing HDFS ACLs and Sentry Permissions

This topic introduces an HDFS-Sentry plugin that allows you to configure synchronization of Sentry privileges with HDFS ACLs for specific HDFS directories.

Previously, when Sentry was used to secure data in Hive or Impala, it was difficult to securely share the same HDFS data files with other components such as Pig, MapReduce, Spark, HDFS client and so on. You had two options:

- You could set ownership for the entire Hive warehouse to hive:hive and not allow other components any access to the data. While this is secure, it does not allow for sharing.
- Use HDFS ACLs and synchronize Sentry privileges and HDFS ACLs manually. For example, if a user only has the Sentry SELECT privilege on a table, that user should only be able to read the table data files, and not write to those HDFS files.

# Introduction

To solve the problem stated above, CDH 5.3 introduces integration of Sentry and HDFS permissions that will automatically keep HDFS ACLs in sync with the privileges configured with Sentry. This feature offers the easiest way to share data between Hive, Impala and other components such as MapReduce, Pig, and so on, while setting permissions for that data with just one set of rules through Sentry. It maintains the ability of Hive and Impala to set permissions on views, in addition to tables, while access to data outside of Hive and Impala (for example, reading files off HDFS) requires table permissions. HDFS permissions for some or all of the files that are part of tables defined in the Hive Metastore will now be controlled by Sentry.

This change consists of three components:

- An HDFS NameNode plugin
- A Sentry-Hive Metastore plugin
- A Sentry Service plugin

Sentry will translate table permissions to the appropriate corresponding ACL on the underlying table files in HDFS. For example, if a user group is assigned to a Sentry role that has SELECT permission on a particular table, then that user group will also have read access to the HDFS files that are part of that table. When listing those files in HDFS, you will see this permission listed as an HDFS ACL. The mapping of Sentry privileges to HDFS ACL permissions is as follows:

- SELECT privilege -> Read access on the file.
- INSERT privilege -> Write access on the file.
- ALL privilege -> Read and Write access on the file.

### Important:

 With synchronization enabled, your ability to set HDFS permissions for those files is disabled. Permissions for those particular files can be set only through Sentry, and when examined through HDFS these permissions appear as HDFS ACLs.

A configurable set of users (such as hive and impala) will have full access to the files automatically. This ensures that a key requirement of using Sentry with Hive and Impala — giving these processes full access to regulate permissions on underlying data files — is met automatically.

- Tables that are not associated with Sentry (that is, have no user with Sentry privileges to access them) will retain their old ACLs.
- Synchronized privileges are not persisted to HDFS. This means that when this feature is disabled, HDFS privileges will return to their original values.
- Sentry HDFS synchronization does not support Hive metastore HA.

### Prerequisites

- CDH 5.3.0 (or later) managed by Cloudera Manager 5.3.0 (or later)
- (Strongly Recommended) Implement Kerberos authentication on your cluster.

The following conditions must be also be true when enabling Sentry-HDFS synchronization. Failure to comply with any of these will result in validation errors.

- You must use the Sentry service, not policy file-based authorization.
- Enabling HDFS Extended Access Control Lists (ACLs) is required.
- There must be exactly one Sentry service dependent on HDFS.
- The Sentry service must have exactly one Sentry Server role.
- The Sentry service must have exactly one dependent Hive service.
- The Hive service must have exactly one Hive Metastore role (that is, High Availability should not be enabled).

# Enabling the HDFS-Sentry Plugin Using Cloudera Manager

- 1. Go to the HDFS service.
- 2. Click the Configuration tab.
- Select Scope > HDFS (Service-Wide).
- Select Category > All.
- **5.** Type Check HDFS Permissions in the Search box.
- 6. Select Check HDFS Permissions.
- 7. Select Enable Sentry Synchronization.
- 8. Locate the Sentry Synchronization Path Prefixes property or search for it by typing its name in the Search
- 9. Edit the Sentry Synchronization Path Prefixes property to list HDFS path prefixes where Sentry permissions should be enforced. Multiple HDFS path prefixes can be specified. By default, this property points to user/hive/warehouse and must always be non-empty. HDFS privilege synchronization will not occur for tables located outside the HDFS regions listed here.
- 10. Click Save Changes.
- 11. Restart the cluster. Note that it may take an additional two minutes after cluster restart for privilege synchronization to take effect.

## Enabling the HDFS-Sentry Plugin Using the Command Line

- Important:
  - If you use Cloudera Manager, do not use these command-line instructions.
  - This information applies specifically to CDH 5.3.x. If you use an earlier version of CDH, see the documentation for that version located at Cloudera Documentation.

To enable the Sentry plugins on an unmanaged cluster, you must explicitly allow the hdfs user to interact with Sentry, and install the plugin packages as described in the following sections.

### Allowing the hdfs user to connect with Sentry

For an unmanaged cluster, add hdfs to the sentry.service.allow.connect property in sentry-site.xml.

```
property>
   <name>sentry.service.allow.connect
   <value>impala,hive,hue,hdfs</value>
</property>
```

# Installing the HDFS-Sentry Plugin

Note: Install Cloudera Repository

Before using the instructions on this page to install the package, install the Cloudera yum, zypper/YaST or apt repository, and install or upgrade CDH 5 and make sure it is functioning correctly. For instructions, see <a href="Installing the Latest CDH 5 Release">Installing the Latest CDH 5 Release</a>.

Use the following the instructions, depending on your operating system, to install the sentry-hdfs-plugin package. The package must be installed (at a minimum) on the following hosts:

- The host running the NameNode and Secondary NameNode
- The host running the Hive Metastore
- The host running the Sentry Service

OS	Command	
RHEL-compatible	\$ sudo yum install sentry-hdfs-plugin	
SLES	\$ sudo zypper install sentry-hdfs-plugin	
Ubuntu or Debian	\$ sudo apt-get install sentry-hdfs-plugin	

# Configuring the HDFS NameNode Plugin

Add the following properties to the hdfs-site.xml file on the NameNode host.

```
cproperty>
<name>dfs.namenode.acls.enabled
<value>true</value>
</property>
property>
<name>dfs.namenode.authorization.provider.class
<value>org.apache.sentry.hdfs.SentryAuthorizationProvider</value>
</property>
cproperty>
<name>dfs.permissions
<value>true</value>
</property>
<!-- Comma-separated list of HDFS path prefixes where Sentry permissions should be
enforced. -->
<!-- Privilege synchronization will occur only for tables located in HDFS regions
specified here. -->
property>
<name>sentry.authorization-provider.hdfs-path-prefixes</name>
<value>/user/hive/warehouse</value>
</property>
property>
<name>sentry.hdfs.service.security.mode
<value>kerberos</value>
</property>
cproperty>
<name>sentry.hdfs.service.server.principal</name>
<value> SENTRY_SERVER_PRINCIPAL (for eg : sentry/_HOST@VPC.CLOUDERA.COM )/value>
</property>
cproperty>
<name>sentry.hdfs.service.client.server.rpc-port</name>
<value>SENTRY_SERVER_PORT</value>
</property>
property>
<name>sentry.hdfs.service.client.server.rpc-address</name>
```

```
<value>SENTRY_SERVER_HOST</value>
</property>
```

# Configuring the Hive Metastore Plugin

Add the following properties to hive-site.xml on the Hive Metastore Server host.

```
property>
<name>sentry.metastore.plugins
<value>org.apache.sentry.hdfs.MetastorePlugin</value>
</property>
property>
<name>sentry.hdfs.service.client.server.rpc-port</name>
<value> SENTRY_SERVER_PORT </value>
</property>
<name>sentry.hdfs.service.client.server.rpc-address</name>
<value> SENTRY_SERVER_HOSTNAME </value>
</property>
property>
<name>sentry.hdfs.service.client.server.rpc-connection-timeout</name>
<value>200000</value>
</property>
property>
<name>sentry.hdfs.service.security.mode
<value>kerberos</value>
</property>
property>
<name>sentry.hdfs.service.server.principal
<value> SENTRY_SERVER_PRINCIPAL (for eg : sentry/_HOST@VPC.CLOUDERA.COM )
</property>
```

### Configuring the Sentry Service Plugin

Add the following properties to the sentry-site.xml file on the NameNode host.

```
cpropertv>
<name>sentry.service.processor.factories
<value>org.apache.sentry.provider.db.service.thrift.SentryPolicyStoreProcessorFactory,
org.apache.sentry.hdfs.SentryHDFSServiceProcessorFactory</value>
</property>
property>
<name>sentry.policy.store.plugins
<value>org.apache.sentry.hdfs.SentryPlugin</value>
</property>
```

**Important:** Once all the configuration changes are complete, restart your cluster. Note that it may take an additional two minutes after cluster restart for privilege synchronization to take effect.

### Testing the Sentry Synchronization Plugins

The following tasks should help you make sure that Sentry-HDFS synchronization has been enabled and configured correctly:

For a folder that has been enabled for the plugin, such as the Hive warehouse, try accessing the files in that folder outside Hive and Impala. For this, you should know what tables those HDFS files belong to and the Sentry permissions on those tables. Attempt to view or modify the Sentry permissions settings over those tables using one of the following tools:

- (Recommended) Hue's Security application
- HiveServer2 CLI

- Impala CLI
- Access the table files directly in HDFS. For example:
  - List files inside the folder and verify that the file permissions shown in HDFS (including ACLs) match what was configured in Sentry.
  - Run a MapReduce, Pig or Spark job that accesses those files. Pick any tool besides HiveServer2 and Impala

# Reporting Metrics for the Sentry Service

Metrics for the Sentry service can now be reported using either JMX or console. To obtain the metrics in JSON format, you can use the Sentry Web Server which by default, listens on port 51000. Use the following properties to enable and configure metric reports.

sentry.service.reporter	Specify the tool being used to report metrics.
	Value: jmx Or console
sentry.service.web.enable	Set this property to true to enable reporting of metrics by the Sentry Web Server.
	Default: false
sentry.service.web.port	Configure the port on which the Sentry Web Server listens for metrics.
	Default: 51000

# Sentry Policy File Authorization

• Important: This is the documentation for configuring Sentry using the policy file approach. Cloudera recommends you use the database-backed Sentry service introduced in CDH 5.1 to secure your data. See <a href="The Sentry Service">The Sentry Service</a> on page 236 for more information.

Sentry enables role-based, fine-grained authorization for HiveServer2, Cloudera Impala and Cloudera Search.

For more information on installing, upgrading and configuring policy file authorization, see:

# Prerequisites

Sentry depends on an underlying authentication framework to reliably identify the requesting user. It requires:

- CDH 4.3.0 or later.
- HiveServer2 and the Hive Metastore running with strong authentication. For HiveServer2, strong authentication is either Kerberos or LDAP. For the Hive Metastore, only Kerberos is considered strong authentication (to override, see <a href="Securing the Hive Metastore">Securing the Hive Metastore</a> on page 275).
- Impala 1.2.1 (or later) running with strong authentication. With Impala, either Kerberos or LDAP can be configured to achieve strong authentication. Auditing of authentication failures is supported only with CDH 4.4.0 and Impala 1.2.1 or later.
- Implement Kerberos authentication on your cluster. This is to prevent a user bypassing the authorization and gaining direct access to the underlying data.

## **Terminologies**

- An **object** is an entity protected by Sentry's authorization rules. The objects supported in the current release are server, database, table, and URI.
- A **role** is a collection of rules for accessing a given Hive object.
- A privilege is granted to a role to govern access to an object. Supported privileges are:

Table 23: Valid privilege types and the objects they apply to

Privilege	Object
INSERT	DB, TABLE
SELECT	DB, TABLE
ALL	SERVER, TABLE, DB, URI

- A user is an entity that is permitted by the authentication subsystem to access the Hive service. This entity can be a Kerberos principal, an LDAP userid, or an artifact of some other pluggable authentication system supported by HiveServer2.
- A group connects the authentication system with the authorization system. It is a collection of one or more users who have been granted one or more authorization roles. Sentry allows a set of roles to be configured for a group.
- A configured group provider determines a user's affiliation with a group. The current release supports HDFS-backed groups and locally configured groups.

# Privilege Model

Sentry uses a role-based privilege model with the following characteristics.

- Allows any user to execute show function, desc function, and show locks.
- Allows the user to see only those tables and databases for which this user has privileges.
- Requires a user to have the necessary privileges on the URI to execute HiveQL operations that take in a location. Examples of such operations include LOAD, IMPORT, and EXPORT.
- Privileges granted on URIs are recursively applied to all subdirectories. That is, privileges only need to be granted on the parent directory.

### Important:

- When Sentry is enabled, you must use Beeline to execute Hive queries. Hive CLI is not supported with Sentry.
- When Sentry is enabled, a user with no privileges on a database will not be allowed to connect to HiveServer2. This is because the use <database> command is now executed as part of the connection to HiveServer2, which is why the connection fails. See HIVE-4256.

For more information, see <u>Authorization Privilege Model for Hive and Impala</u> on page 265.

# **Granting Privileges**


For example, a rule for the Select privilege on table customers from database sales would be formulated as follows:

Each object must be specified as a hierarchy of the containing objects, from server to table, followed by the privilege granted for that object. A role can contain multiple such rules, separated by commas. For example, a role might contain the Select privilege for the customer and items tables in the sales database, and the Insert privilege for the sales\_insights table in the reports database. You would specify this as follows:

```
sales reporting =
\server=server1->db=sales->table=customer->action=Select,
\server=server1->db=sales->table=items>action=Select,
\server=server1->db=reports->table=sales_insights>action=Insert
```

# User to Group Mapping

You can configure Sentry to use either Hadoop groups or groups defined in the policy file. By default, Sentry looks up groups locally, but it can be configured to look up Hadoop groups using LDAP (for Active Directory). Local groups will be looked up on the host Sentry runs on. For Hive, this will be the host running HiveServer2. Group mappings in Sentry can be summarized as in the figure below:



Important: You can use either Hadoop groups or local groups, but not both at the same time. Local groups are traditionally used for a quick proof-of-concept, while Hadoop groups are more commonly used in production. Refer <a href="Configuring LDAP Group Mappings">Configuring LDAP Group Mappings</a> on page 133 for details on configuring LDAP group mappings in Hadoop.

# Policy File

The sections that follow contain notes on creating and maintaining the policy file, and using URIs to load external data and IARs.

• Warning: An invalid policy file will be ignored while logging an exception. This will lead to a situation where users will lose access to all Sentry-protected data, since default Sentry behaviour is *deny* unless a user has been explicitly granted access. (Note that if only the per-DB policy file is invalid, it will invalidate only the policies in that file.)

# Storing the Policy File

Considerations for storing the policy file(s) in HDFS include:

- 1. Replication count Because the file is read for each query in Hive and read once every five minutes by all Impala daemons, you should increase this value; since it is a small file, setting the replication count equal to the number of slave nodes in the cluster is reasonable.
- 2. Updating the file Updates to the file are reflected immediately, so you should write them to a temporary copy of the file first, and then replace the existing file with the temporary one after all the updates are complete. This avoids race conditions caused by reads on an incomplete file.

# **Defining Roles**

Keep in mind that role definitions are not cumulative; the definition that is further down in the file replaces the older one. For example, the following results in role1 having privilege2, not privilege1 and privilege2.

```
role1 = privilege1
role1 = privilege2
```

Role names are scoped to a specific file. For example, if you give role1 the ALL privilege on db1 in the global policy file and give role1 ALL on db2 in the per-db db2 policy file, the user will be given both privileges.

Any command which references a URI such as CREATE TABLE EXTERNAL, LOAD, IMPORT, EXPORT, and more, in addition to CREATE TEMPORARY FUNCTION requires the URI privilege. This is an important security control because without this users could simply create an external table over an existing table they do not have access to and bypass Sentry.

URIs must start with either hdfs://orfile://. If a URI starts with anything else, it will cause an exception and the policy file will be invalid.

When defining URIs for HDFS, you must also specify the NameNode. For example:

```
data_read = server=server1->uri=file:///path/to/dir,\
server=server1->uri=hdfs://namenode:port/path/to/dir
```

**Important:** Because the NameNode host and port must be specified, Cloudera strongly recommends you use High Availability (HA). This ensures that the URI will remain constant even if the NameNode changes.

# Loading Data

Data can be loaded using a landing skid, either in HDFS or via a local/NFS directory where HiveServer2/Impala run. The following privileges can be used to grant a role access to a loading skid:

Load data from a local/NFS directory:

```
server=server1->uri=file:///path/to/nfs/local/to/nfs
```

Load data from HDFS (MapReduce, Pig, and so on):

```
server=server1->uri=hdfs://ha-nn-uri/data/landing-skid
```

In addition to the privilege in Sentry, the hive or impala user will require the appropriate file permissions to access the data being loaded. Groups can be used for this purpose. For example, create a group hive-users, and add the hive and impala users along with the users who will be loading data, to this group.

The example usermod and groupadd commands below are only applicable to locally defined groups on the NameNode, JobTracker, and ResourceManager. If you use another system for group management, equivalent changes should be made in your group management system.

```
$ groupadd hive-users
$ usermod -G someuser, hive-users someuser
$ usermod -G hive, hive-users hive
```

# **External Tables**

External tables require the ALL@database privilege in addition to the URI privilege. When data is being inserted through the EXTERNAL TABLE statement, or is referenced from an HDFS location outside the normal Hive

database directories, the user needs appropriate permissions on the URIs corresponding to those HDFS locations. This means that the URI location must either be owned by the hive:hive user OR the hive/impala users must be members of the group that owns the directory.

You can configure access to the directory using a URI as follows:

```
[roles]
someuser_home_dir_role = server=serverl->uri=hdfs://ha-nn-uri/user/someuser
```

You should now be able to create an external table:

```
CREATE EXTERNAL TABLE ...
LOCATION 'hdfs://ha-nn-uri/user/someuser/mytable';
```

# Sample Sentry Configuration Files

This section provides a sample configuration.

### **Policy Files**

The following is an example of a policy file with a per-DB policy file. In this example, the first policy file, sentry-provider.ini would exist in HDFS; hdfs://ha-nn-uri/etc/sentry/sentry-provider.ini might be an appropriate location. The per-DB policy file is for the customer's database. It is located at hdfs://ha-nn-uri/etc/sentry/customers.ini.

### sentry-provider.ini

```
[databases]
# Defines the location of the per DB policy file for the customers DB/schema
customers = hdfs://ha-nn-uri/etc/sentry/customers.ini
# Assigns each Hadoop group to its set of roles
manager = analyst_role, junior_analyst_role
analyst = analyst_role
jranalyst = junior_analyst_role
customers_admin = customers_admin_role
admin = admin role
[roles]
\sharp The uris below define a define a landing skid which
# the user can use to import or export data from the system.
# Since the server runs as the user "hive" files in that directory
# must either have the group hive and read/write set or
# be world read/write.
analyst_role = server=server1->db=analyst1, \
    server=server1->db=jranalyst1->table=*->action=select
    server=server1->uri=hdfs://ha-nn-uri/landing/analyst1
junior_analyst_role = server=server1->db=jranalyst1,
   server=server1->uri=hdfs://ha-nn-uri/landing/jranalyst1
# Implies everything on server1 -> customers. Privileges for
# customers can be defined in the global policy file even though
# customers has its only policy file. Note that the Privileges from
# both the global policy file and the per-DB policy file
# are merged. There is no overriding.
customers_admin_role = server=server1->db=customers
# Implies everything on server1.
admin role = server=server1
```

### customers.ini

```
[groups]
manager = customers_insert_role, customers_select_role
analyst = customers_select_role
```

```
[roles]
customers_insert_role = server=server1->db=customers->table=*->action=insert
customers_select_role = server=server1->db=customers->table=*->action=select
```

Important: Sentry does not support using the view keyword in policy files. If you want to define a role against a view, use the keyword table instead. For example, to define the role analyst\_role against the view col\_test\_view:

```
[roles]
analyst_role = server=server1->db=default->table=col_test_view->action=select
```

# Sentry Configuration File

The following is an example of a sentry-site.xml file.

Important: If you are using Cloudera Manager 4.6 (or earlier), make sure you do not store sentry-site.xml in /etc/hive/conf; that directory is regenerated whenever the Hive client configurations are redeployed. Instead, use a directory such as /etc/sentry to store the sentry file.

If you are using Cloudera Manager 4.7 (or later), Cloudera Manager will create and deploy sentry-site.xml for you. See <u>The Sentry Service</u> on page 236 for more details on configuring Sentry with Cloudera Manager.

### sentry-site.xml

```
<configuration>
 cproperty>
   <name>hive.sentry.provider</name>
<value>org.apache.sentry.provider.file.HadoopGroupResourceAuthorizationProvider/value>
 </property>
    <name>hive.sentry.provider.resource</name>
    <value>/path/to/authz-provider.ini</value>
    <!--
      If the hdfs-site.xml points to HDFS, the path will be in HDFS;
       alternatively you could specify a full path, e.g.:
      hdfs://namenode:port/path/to/authz-provider.ini
      file:///path/to/authz-provider.ini
 </property>
 cproperty>
   <name>sentry.hive.server</name>
    <value>server1</value>
 </property>
</configuration>
```

# Accessing Sentry-Secured Data Outside Hive/Impala

When Sentry is enabled, the hive user owns all data within the Hive warehouse. However, unlike traditional database systems the enterprise data hub allows for multiple engines to execute over the same dataset.

**Note:** Cloudera strongly recommends you use Hive/Impala SQL queries to access data secured by Sentry, as opposed to accessing the data files directly.

However, there are scenarios where fully vetted and reviewed jobs will also need to access the data stored in the Hive warehouse. A typical scenario would be a secured MapReduce transformation job that is executed

automatically as an application user. In such cases it's important to know that the user executing this job will also have full access to the data in the Hive warehouse.

# Scenario One: Authorizing Jobs

### Problem

A reviewed, vetted, and automated job requires access to the Hive warehouse and cannot use Hive/Impala to access the data.

#### Solution

Create a group which contains hive, impala, and the user executing the automated job. For example, if the etl user is executing the automated job, you can create a group called hive-users which contains the hive, impala, and etl users.

The example usermod and groupadd commands below are only applicable to locally defined groups on the NameNode, JobTracker, and ResourceManager. If you use another system for group management, equivalent changes should be made in your group management system.

```
$ groupadd hive-users
$ usermod -G hive,impala,hive-users hive
$ usermod -G hive,impala,hive-users impala
$ usermod -G etl,hive-users etl
```

Once you have added users to the hive-users group, change directory permissions in the HDFS:

```
$ hadoop fs -chgrp -R hive:hive-users /user/hive/warehouse
$ hadoop fs -chmod -R 770 /user/hive/warehouse
```

# Scenario Two: Authorizing Group Access to Databases

### **Problem**

One group of users, grp1 should have full access to the database, db1, outside of Sentry. The database, db1 should not be accessible to any other groups, outside of Sentry. Sentry should be used for all other authorization needs.

### Solution

Place the hive and impala users in grp1.

```
$ usermod -G hive,impala,grp1 hive
$ usermod -G hive,impala,grp1 impala
```

Then change group ownerships of all directories and files in db1 to grp1, and modify directory permissions in the HDFS. This example is only applicable to local groups on a single host.

```
$ hadoop fs -chgrp -R hive:grp1 /user/hive/warehouse/db1.db
$ hadoop fs -chmod -R 770 /user/hive/warehouse/db1.db
```

# Debugging Failed Sentry Authorization Requests

Sentry logs all facts that lead up to authorization decisions at the debug level. If you do not understand why Sentry is denying access, the best way to debug is to temporarily turn on debug logging:

- In Cloudera Manager, add log4j.logger.org.apache.sentry=DEBUG to the logging settings for your service through the corresponding Logging Safety Valve field for the Impala, Hive Server 2, or Solr Server services.
- On systems not managed by Cloudera Manager, add log4j.logger.org.apache.sentry=DEBUG to the log4j.properties file on each host in the cluster, in the appropriate configuration directory for each service.

Specifically, look for exceptions and messages such as:

```
FilePermission server..., RequestPermission server..., result [true|false]
```

which indicate each evaluation Sentry makes. The FilePermission is from the policy file, while RequestPermission is the privilege required for the query. A RequestPermission will iterate over all appropriate FilePermission settings until a match is found. If no matching privilege is found, Sentry returns false indicating "Access Denied".

# Authorization Privilege Model for Hive and Impala

Privileges can be granted on different objects in the Hive warehouse. Any privilege that can be granted is associated with a level in the object hierarchy. If a privilege is granted on a container object in the hierarchy, the base object automatically inherits it. For instance, if a user has ALL privileges on the database scope, then (s)he has ALL privileges on all of the base objects contained within that scope.

# Object Hierarchy in Hive

```
Server
    Database
         Table
            Partition
            Columns
         View
         Index
     Function/Routine
     Lock
```

# Table 24: Valid privilege types and objects they apply to

Privilege	Object
INSERT	DB, TABLE
SELECT	DB, TABLE
ALL	SERVER, TABLE, DB, URI

# Table 25: Privilege hierarchy

Base Object	Granular privileges on object	Container object that contains the base object	Privileges on container object that implies privileges on the base object
DATABASE	ALL	SERVER	ALL
TABLE	INSERT	DATABASE	ALL
TABLE	SELECT	DATABASE	ALL
VIEW	SELECT	DATABASE	ALL

# Table 26: Privilege table for Hive & Impala operations

Operation	Scope	Privileges	URI	Others
CREATE DATABASE	SERVER	ALL		
DROP DATABASE	DATABASE	ALL		
CREATE TABLE	DATABASE	ALL		
DROP TABLE	TABLE	ALL		
CREATE VIEW	DATABASE; SELECT on TABLE	ALL		SELECT on TABLE

Operation	Scope	Privileges	URI	Others
DROP VIEW	VIEW/TABLE	ALL		
ALTER TABLE ADD COLUMNS	TABLE	ALL		
ALTER TABLE REPLACE COLUMNS	TABLE	ALL		
ALTER TABLE CHANGE column	TABLE	ALL		
ALTER TABLE RENAME	TABLE	ALL		
ALTER TABLE SET TBLPROPERTIES	TABLE	ALL		
ALTER TABLE SET FILEFORMAT	TABLE	ALL		
ALTER TABLE SET LOCATION	TABLE	ALL	URI	
ALTER TABLE ADD PARTITION	TABLE	ALL		
ALTER TABLE ADD PARTITION location	TABLE	ALL	URI	
ALTER TABLE DROP PARTITION	TABLE	ALL		
ALTER TABLE PARTITION SET FILEFORMAT	TABLE	ALL		
SHOW CREATE TABLE	TABLE	SELECT/INSERT		
SHOW PARTITIONs	TABLE	SELECT/INSERT		
DESCRIBE TABLE	TABLE	SELECT/INSERT		
LOAD DATA	TABLE	INSERT	URI	
SELECT	TABLE	SELECT		
INSERT OVERWRITE TABLE	TABLE	INSERT		
CREATE TABLE AS SELECT	DATABASE; SELECT on TABLE	ALL		SELECT on TABLE
USE <dbname></dbname>	Any			
CREATE FUNCTION	SERVER	ALL		
ALTER TABLE SET SERDEPROPERTIES	TABLE	ALL		
ALTER TABLE PARTITION SET SERDEPROPERTIES	TABLE	ALL		
Hive-Only Operations				

Operation	Scope	Privileges	URI	Others
INSERT OVERWRITE DIRECTORY	TABLE	INSERT	URI	
Analyze TABLE	TABLE	SELECT + INSERT		
IMPORT TABLE	DATABASE	ALL	URI	
EXPORT TABLE	TABLE	SELECT	URI	
ALTER TABLE TOUCH	TABLE	ALL		
ALTER TABLE TOUCH PARTITION	TABLE	ALL		
ALTER TABLE CLUSTERED BY SORTED BY	TABLE	ALL		
ALTER TABLE ENABLE/DISABLE	TABLE	ALL		
ALTER TABLE PARTITION ENABLE/DISABLE	TABLE	ALL		
ALTER TABLE PARTITION RENAME TO PARTITION	TABLE	ALL		
MSCK REPAIR TABLE	TABLE	ALL		
ALTER DATABASE	DATABASE	ALL		
DESCRIBE DATABASE	DATABASE	SELECT/INSERT		
SHOW COLUMNS	TABLE	SELECT/INSERT		
CREATE INDEX	TABLE	ALL		
DROP INDEX	TABLE	ALL		
SHOW INDEXES	TABLE	SELECT/INSERT		
GRANT PRIVILEGE	Allowed only for Sentry admin users			
REVOKE PRIVILEGE	Allowed only for Sentry admin users			
SHOW GRANTS	Allowed only for Sentry admin users			
SHOW TBLPROPERTIES	TABLE	SELECT/INSERT		
DESCRIBE TABLE PARTITION	TABLE	SELECT/INSERT		
ADD JAR	Not Allowed			
ADD FILE	Not Allowed			
DFS	Not Allowed			
Impala-Only Operations		•	•	
EXPLAIN	TABLE	SELECT		

Operation	Scope	Privileges	URI	Others
INVALIDATE METADATA	SERVER	ALL		
INVALIDATE METADATA	TABLE	SELECT/INSERT		
REFRESH	TABLE	SELECT/INSERT		
DROP FUNCTION	SERVER	ALL		
COMPUTE STATS	TABLE	ALL		

# Installing and Upgrading Sentry for Policy File Authorization

Sentry stores the configuration as well as privilege policies in files. The sentry-site.xml file contains configuration options such as group association provider, privilege policy file location, and so on. The policy file contains the privileges and groups. It has a .ini file format and can be stored on a local file system or HDFS.

Sentry is plugged into Hive as session hooks which you <u>configure</u> in hive-site.xml. The vsentry package must be installed; it contains the required JAR files. You must also configure properties in the <u>Sentry Configuration</u> <u>File</u> on page 263.

# Important:

If you have not already done so, install Cloudera's yum, zypper/YaST or apt repository before using the following commands. For instructions, see Installing the Latest CDH 5 Release.

# **Installing Sentry**

Use the following the instructions, depending on your operating system, to install the latest version of Sentry.

### Important: Configuration files

- If you install a newer version of a package that is already on the system, configuration files that you have modified will remain intact.
- If you uninstall a package, the package manager renames any configuration files you have modified from <file> to <file>.rpmsave. If you then re-install the package (probably to install a new version) the package manager creates a new <file> with applicable defaults. You are responsible for applying any changes captured in the original configuration file to the new configuration file. In the case of Ubuntu and Debian upgrades, you will be prompted if you have made changes to a file for which there is a new version; for details, see <a href="Automatic handling of configuration files by dokg">Automatic handling of configuration files by dokg</a>.

OS	Command	
RHEL	\$ sudo yum install sentry	
SLES	\$ sudo zypper install sentry	
Ubuntu or Debian	<pre>\$ sudo apt-get update; \$ sudo apt-get install sentry</pre>	

# **Upgrading Sentry**

If you are upgrading Sentry from CDH 4 to CDH 5, you must uninstall the old version and install the new version. If you are upgrading from CDH 5.x to the latest CDH release, see <a href="Installing Sentry">Installing Sentry</a> on page 268 to install the latest version.

# Removing the CDH 4 Version of Sentry:

Note: If you have already performed the steps to uninstall CDH 4 and all components, as described under <u>Upgrading from CDH 4 to CDH 5</u>, you can skip this step and proceed with <u>installing the latest</u> version of Sentry.

OS	Command	
RHEL	\$ sudo yum remove sentry	
SLES	\$ sudo zypper remove sentry	
Ubuntu or Debian	\$ sudo apt-get remove sentry	

# Configuring Sentry Policy File Authorization Using Cloudera Manager

This topic describes how to configure Sentry policy files and enable policy file authorization for CDH services using Cloudera Manager.

# Configuring User to Group Mappings

Required Role: Configurator Cluster Administrator **Full Administrator** 

# Hadoop Groups

- 1. Go to the Hive service.
- 2. Click the Configuration tab.
- 3. Select Scope > Hive (Service-Wide).
- 4. Select Category > Policy File Based Sentry.
- 5. Locate the Sentry User to Group Mapping Class property or search for it by typing its name in the Search box.
- **6.** Set the **Sentry User to Group Mapping Class** property to org.apache.sentry.provider.file.HadoopGroupResourceAuthorizationProvider.
- Click Save Changes.
- 8. Restart the Hive service.

### **Local Groups**

1. Define local groups in the [users] section of the Policy File on page 260. For example:

```
[users]
user1 = group1, group2, group3
user2 = group2, group3
```

- 2. Modify Sentry configuration as follows:
  - a. Go to the Hive service.
  - **b.** Click the **Configuration** tab.
  - c. Select Scope > Hive (Service-Wide).
  - d. Select Category > Policy File Based Sentry.
  - e. Locate the Sentry User to Group Mapping Class property or search for it by typing its name in the Search box.
  - f. Set the Sentry User to Group Mapping Class property to  $\verb|org.apache.sentry.provider.file.LocalGroupResourceAuthorizationProvider|.\\$
  - g. Click Save Changes.
  - h. Restart the Hive service.

# Enabling URIs for Per-DB Policy Files

The ADD JAR command does *not* work with HiveServer2 and the Beeline client when Beeline runs on a different host. As an alternative to ADD JAR, Hive's *auxiliary paths* functionality should be used as described in the following steps.

• Important: Enabling URIs in per-DB policy files introduces a security risk by allowing the owner of the db-level policy file to grant himself/herself load privileges to anything the hive user has read permissions for in HDFS (including data in other databases controlled by different db-level policy files).

Add the following string to the Java configuration options for HiveServer2 during startup.

```
-Dsentry.allow.uri.db.policyfile=true
```

Using User-Defined Functions with HiveServer2

```
Required Role: Configurator Cluster Administrator Full Administrator
```

The ADD JAR command does *not* work with HiveServer2 and the Beeline client when Beeline runs on a different host. As an alternative to ADD JAR, Hive's *auxiliary paths* functionality should be used. There are some differences in the procedures for creating permanent functions and temporary functions. For detailed instructions, see <u>User-Defined Functions</u> (UDFs) with <u>HiveServer2 Using Cloudera Manager</u>.

Enabling Policy File Authorization for Hive

# Required Role: Configurator Cluster Administrator Full Administrator

- 1. Ensure the <u>Prerequisites</u> on page 258 have been satisfied.
- 2. The Hive warehouse directory (/user/hive/warehouse or any path you specify as hive.metastore.warehouse.dir in your hive-site.xml) must be owned by the Hive user and group.
  - Permissions on the warehouse directory must be set as follows (see following Note for caveats):
    - 771 on the directory itself (for example, /user/hive/warehouse)
    - 771 on all subdirectories (for example, /user/hive/warehouse/mysubdir)
    - All files and subdirectories should be owned by hive:hive

For example:

```
$ sudo -u hdfs hdfs dfs -chmod -R 771 /user/hive/warehouse
$ sudo -u hdfs hdfs dfs -chown -R hive:hive /user/hive/warehouse
```

### Note:

- If you set hive.warehouse.subdir.inherit.perms to true in hive-site.xml, the permissions on the subdirectories will be set when you set permissions on the warehouse directory itself.
- If a user has access to any object in the warehouse, that user will be able to execute use
   default. This ensures that use default commands issued by legacy applications work
   when Sentry is enabled. Note that you can protect objects in the default database (or any
   other database) by means of a policy file.
- Important: These instructions override the recommendations in the Hive section of the CDH 5 Installation Guide.
- 3. Disable impersonation for HiveServer2:

- a. Go to the Hive service.
- **b.** Click the **Configuration** tab.
- c. Select Scope > HiveServer2.
- d. Select Category > All.
- e. Locate the HiveServer2 Enable Impersonation property or search for it by typing its name in the Search
- f. Under the HiveServer2 role group, deselect the HiveServer2 Enable Impersonation property.
- g. Click Save Changes to commit the changes.
- 4. Create the Sentry policy file, sentry-provider.ini, as an HDFS file.
- 5. Enable the Hive user to submit MapReduce jobs.
  - a. Go to the MapReduce service.
  - **b.** Click the **Configuration** tab.
  - c. Select Scope > TaskTracker.
  - d. Select Category > Security.
  - e. Locate the Minimum User ID for Job Submission property or search for it by typing its name in the Search
  - f. Set the Minimum User ID for Job Submission property to 0 (the default is 1000).
  - g. Click Save Changes to commit the changes.
  - h. Repeat steps 5.a-5.d for every TaskTracker role group for the MapReduce service that is associated with Hive, if more than one exists.
  - i. Restart the MapReduce service.
- 6. Enable the Hive user to submit YARN jobs.
  - a. Go to the YARN service.
  - **b.** Click the **Configuration** tab.
  - c. Select Scope > NodeManager.
  - d. Select Category > Security.
  - e. Ensure the Allowed System Users property includes the hive user. If not, add hive.
  - f. Click Save Changes to commit the changes.
  - g. Repeat steps 6.a-6.d for every NodeManager role group for the YARN service that is associated with Hive, if more than one exists.
  - h. Restart the YARN service.
- 7. Go to the Hive service.
- 8. Click the Configuration tab.
- 9. Select Scope > Hive (Service-Wide).
- 10. Select Category > Policy File Based Sentry.
- 11. Select Enable Sentry Authorization Using Policy Files.
- **12.** Click **Save Changes** to commit the changes.
- 13. Restart the cluster and HiveServer2 after changing these values, whether you use Cloudera Manager or not.

# Configuring Group Access to the Hive Metastore

# Required Role: Configurator Cluster Administrator Full Administrator

You can configure the Hive Metastore to reject connections from users not listed in the Hive group proxy list (in HDFS). If you don't configure this override, the Hive Metastore will use the value in the core-site HDFS configuration. To configure the Hive group proxy list:

- 1. Go to the Hive service.
- 2. Click the Configuration tab.
- 3. Select Scope > Hive (Service-Wide).
- 4. Select Category > Proxy.

- 5. In the Hive Metastore Access Control and Proxy User Groups Override property, specify a list of groups whose users are allowed to access the Hive Metastore. If you do not specify "\*" (wildcard), you will be warned if the groups do not include hive and impala (if the Impala service is configured) in the list of groups.
- 6. Click Save Changes.
- 7. Restart the Hive service.

# Enabling Policy File Authorization for Impala

For a cluster managed by Cloudera Manager, perform the following steps to enable policy file authorization for Impala.

- **1.** Enable Sentry's policy file based authorization for Hive. For details, see <u>Enabling Policy File Authorization for Hive</u> on page 270.
- 2. Go to the Cloudera Manager Admin Console and navigate to the Impala service.
- 3. Click the Configuration tab.
- 4. Select Scope > Impala (Service-Wide).
- 5. Select Category > Policy File-Based Sentry.
- 6. Select Enable Sentry Authorization Using Policy Files.
- 7. Click Save Changes to commit the changes.
- 8. Restart the Impala service.

For more details, see Starting the impalad Daemon with Sentry Authorization Enabled on page 277.

# **Enabling Sentry Authorization for Solr**

# Required Role: Full

**Full Administrator** 

- 1. Ensure the following requirements are satisfied:
  - Cloudera Search 1.1.1 or later or CDH 5 or later.
  - A secure Hadoop cluster.
- 2. Create the policy file sentry-provider.ini as an HDFS file. When you create the policy file sentry-provider.ini follow the instructions in the Policy File section in Configuring Sentry for Search (CDH 4) or Search Authentication on page 111. The file must be owned by owned by the solr user in the solr group, with perms=600. By default Cloudera Manager assumes the policy file is in the HDFS location /user/solr/sentry. To configure the location:
  - a. Go to the Solr service.
  - **b.** Click the **Configuration** tab.
  - c. Select Scope > SOLR (Service-Wide).
  - d. Select Category > Policy File Based Sentry.
  - e. Locate the Sentry Global Policy File property.
  - f. Modify the path in the Sentry Global Policy File property.
  - g. Select Enable Sentry Authorization.
  - h. Click Save Changes.
- 3. Restart the Solr service.

For more details, see **Enabling Sentry Authorization for Search using the Command Line** on page 288.

# Configuring Sentry to Enable BDR Replication

Cloudera recommends the following steps when configuring Sentry and data replication is enabled.

- Group membership should be managed outside of Sentry (as typically OS groups, LDAP groups, and so on are managed) and replication for them also should be handled outside of Cloudera Manager.
- In Cloudera Manager, set up <u>HDFS replication</u> for the Sentry files of the databases that are being replicated (separately via Hive replication).
- On the source cluster:

- Use a separate Sentry policy file for every database
- Avoid placing any group or role info (except for server admin info) in the global Sentry policy file (to avoid manual replication/merging with the global file on the target cluster)
- In order to avoid manual fix up of URI privileges, ensure that the URIs for the data are the same on both the source and target cluster
- On the target cluster:
  - In the global Sentry policy file, manually add the DB name DB file mapping entries for the databases being replicated
  - Manually copy the server admin info from the global Sentry policy file on the source to the policy on the target cluster
  - For the databases being replicated, avoid adding more privileges (adding tables specific to target cluster may sometimes require adding extra privileges to allow access to those tables). If any target cluster specific privileges absolutely need to be added for a database, add them to the global Sentry policy file on the target cluster since the per database files would be overwritten periodically with source versions during scheduled replication.

# Configuring Sentry Policy File Authorization Using the Command Line

This topic describes how to configure Sentry policy files and enable policy file authorization for unmanaged CDH services using the command line.

# Configuring User to Group Mappings

# Hadoop Groups

Set the hive.sentry.provider property in sentry-site.xml.

```
property>
<name>hive.sentry.provider</name>
<value>org.apache.sentry.provider.file.HadoopGroupResourceAuthorizationProvider/value>
</property>
```

### **Local Groups**

1. Define local groups in the [users] section of the Policy File on page 260. For example:

```
[users]
user1 = group1, group2, group3
user2 = group2, group3
```

**2.** Modify Sentry configuration as follows:

In sentry-site.xml, set hive.sentry.provider as follows:

```
property>
<name>hive.sentry.provider</name>
<value>org.apache.sentry.provider.file.LocalGroupResourceAuthorizationProvider/value>
</property>
```

### Enabling URIs for Per-DB Policy Files

The ADD JAR command does not work with HiveServer2 and the Beeline client when Beeline runs on a different host. As an alternative to ADD JAR, Hive's auxiliary paths functionality should be used as described in the following steps.

• Important: Enabling URIs in per-DB policy files introduces a security risk by allowing the owner of the db-level policy file to grant himself/herself load privileges to anything the hive user has read permissions for in HDFS (including data in other databases controlled by different db-level policy files).

Add the following string to the Java configuration options for HiveServer2 during startup.

```
-Dsentry.allow.uri.db.policyfile=true
```

# Using User-Defined Functions with HiveServer2

The ADD JAR command does *not* work with HiveServer2 and the Beeline client when Beeline runs on a different host. As an alternative to ADD JAR, Hive's *auxiliary paths* functionality should be used as described in the following steps. There are some differences in the procedures for creating permanent functions and temporary functions. For detailed instructions, see <u>User-Defined Functions</u> (UDFs) with <u>HiveServer2 Using the Command Line</u>.

Enabling Policy File Authorization for Hive

### Prerequisites

In addition to the <u>Prerequisites</u> on page 258 above, make sure that the following are true:

- The Hive warehouse directory (/user/hive/warehouse or any path you specify as hive.metastore.warehouse.dir in your hive-site.xml) must be owned by the Hive user and group.
  - Permissions on the warehouse directory must be set as follows (see following Note for caveats):
    - 771 on the directory itself (for example, /user/hive/warehouse)
    - 771 on all subdirectories (for example, /user/hive/warehouse/mysubdir)
    - All files and subdirectories should be owned by hive:hive

### For example:

```
$ sudo -u hdfs hdfs dfs -chmod -R 771 /user/hive/warehouse
$ sudo -u hdfs hdfs dfs -chown -R hive:hive /user/hive/warehouse
```

# Note:

- If you set hive.warehouse.subdir.inherit.perms to true in hive-site.xml, the permissions on the subdirectories will be set when you set permissions on the warehouse directory itself.
- If a user has access to any object in the warehouse, that user will be able to execute use default. This ensures that use default commands issued by legacy applications work when Sentry is enabled. Note that you can protect objects in the default database (or any other database) by means of a policy file.
- Important: These instructions override the recommendations in the Hive section of the CDH 5 Installation Guide.
- HiveServer2 impersonation must be turned off.
- The Hive user must be able to submit MapReduce jobs. You can ensure that this is true by setting the minimum user ID for job submission to 0. Edit the taskcontroller.cfg file and set min.user.id=0.

To enable the Hive user to submit YARN jobs, add the user hive to the allowed.system.users configuration property. Edit the container-executor.cfg file and add hive to the allowed.system.users property. For example,

```
allowed.system.users = nobody,impala,hive
```

- Important:
  - You must restart the cluster and HiveServer2 after changing this value, whether you use Cloudera Manager or not.
  - These instructions override the instructions under <u>Configuring MRv1 Security</u> on page 67
  - These instructions override the instructions under Configuring YARN Security on page 69

# Configuration Changes Required

To enable Sentry, add the following properties to hive-site.xml:

```
cproperty>
<name>hive.server2.session.hook
<value>org.apache.sentry.binding.hive.HiveAuthzBindingSessionHook</value>
</property>
property>
<name>hive.sentry.conf.url</name>
<value></value>
<description>sentry-site.xml file location</description>
</property>
property>
<name>hive.metastore.client.impl</name>
<value>org.apache.sentry.binding.metastore.SentryHiveMetaStoreClient</value>
<description>Sets custom Hive Metastore client which Sentry uses to filter out
metadata.</description>
</property>
```

### Securing the Hive Metastore

It's important that the Hive metastore be secured. If you want to override the Kerberos prerequisite for the Hive metastore, set the sentry.hive.testing.mode property to true to allow Sentry to work with weaker authentication mechanisms. Add the following property to the HiveServer2 and Hive metastore's sentry-site.xml:

```
<name>sentry.hive.testing.mode</name>
  <value>true</value>
</property>
```

Impala does not require this flag to be set.

Warning: Cloudera strongly recommends against enabling this property in production. Use Sentry's testing mode only in test environments.

You canturn on Hive metastore security using the instructions in <u>Cloudera Security</u>. To secure the Hive metastore; see <u>Hive Metastore Server Security Configuration</u> on page 90.

# Enabling Policy File Authorization for Impala

First, enable Sentry's policy file based authorization for Hive. For details, see Enabling Policy File Authorization for Hive on page 274.

See Enabling Sentry Authorization for Impala on page 276 for details on configuring Impala to work with Sentry policy files.

# Enabling Sentry in Cloudera Search

See Enabling Sentry in Cloudera Search for CDH 5 on page 291 for details on securing Cloudera Search with Sentry.

# Enabling Sentry Authorization for Impala

Authorization determines which users are allowed to access which resources, and what operations they are allowed to perform. In Impala 1.1 and higher, you use the Sentry open source project for authorization. Sentry adds a fine-grained authorization framework for Hadoop. By default (when authorization is not enabled), Impala does all read and write operations with the privileges of the impala user, which is suitable for a development/test environment but not for a secure production environment. When authorization is enabled, Impala uses the OS user ID of the user who runs impala-shell or other client program, and associates various privileges with each user.

Note: Sentry is typically used in conjunction with Kerberos authentication, which defines which hosts are allowed to connect to each server. Using the combination of Sentry and Kerberos prevents malicious users from being able to connect by creating a named account on an untrusted machine. See <a href="Enabling Kerberos Authentication for Impala">Enabling Kerberos Authentication for Impala</a> on page 104 for details about Kerberos authentication.

# The Sentry Privilege Model

Privileges can be granted on different objects in the schema. Any privilege that can be granted is associated with a level in the object hierarchy. If a privilege is granted on a container object in the hierarchy, the child object automatically inherits it. This is the same privilege model as Hive and other database systems such as MySQL.

The object hierarchy covers Server, URI, Database, and Table. (The Table privileges apply to views as well; anywhere you specify a table name, you can specify a view name instead.) Currently, you cannot assign privileges at the partition or column level. The way you implement column-level or partition-level privileges is to create a view that queries just the relevant columns or partitions, and assign privileges to the view rather than the underlying table or tables.

A restricted set of privileges determines what you can do with each object:

### **SELECT** privilege

Lets you read data from a table or view, for example with the SELECT statement, the INSERT...SELECT syntax, or CREATE TABLE...LIKE. Also required to issue the DESCRIBE statement or the EXPLAIN statement for a query against a particular table. Only objects for which a user has this privilege are shown in the output for SHOW DATABASES and SHOW TABLES statements. The REFRESH statement and INVALIDATE METADATA statements only access metadata for tables for which the user has this privilege.

# **INSERT** privilege

Lets you write data to a table. Applies to the INSERT and LOAD DATA statements.

### **ALL** privilege

Lets you create or modify the object. Required to run DDL statements such as CREATE TABLE, ALTER TABLE, OR DROP TABLE for a table, CREATE DATABASE OR DROP DATABASE for a database, or CREATE VIEW, ALTER VIEW, OR DROP VIEW for a view. Also required for the URI of the "location" parameter for the CREATE EXTERNAL TABLE and LOAD DATA statements.

Privileges can be specified for a table or view before that object actually exists. If you do not have sufficient privilege to perform an operation, the error message does not disclose if the object exists or not.

Originally, privileges were encoded in a policy file, stored in HDFS. This mode of operation is still an option, but the emphasis of privilege management is moving towards being SQL-based. Although currently Impala does not have GRANT or REVOKE statements, Impala can make use of privileges assigned through GRANT and REVOKE statements done through Hive. The mode of operation with GRANT and REVOKE statements instead of the policy file requires that a special Sentry service be enabled; this service stores, retrieves, and manipulates privilege information stored inside the metastore database.

# Starting the impalad Daemon with Sentry Authorization Enabled

To run the impalad daemon with authorization enabled, you add one or more options to the IMPALA\_SERVER\_ARGS declaration in the /etc/default/impala configuration file:

- The -server name option turns on Sentry authorization for Impala. The authorization rules refer to a symbolic server name, and you specify the name to use as the argument to the -server\_name option.
- If you specify just -server\_name, Impala uses the Sentry service for authorization, relying on the results of GRANT and REVOKE statements issued through Hive. (This mode of operation is available in Impala 1.4.0 and higher.) Prior to Impala 1.4.0, or if you want to continue storing privilege rules in the policy file, also specify the -authorization\_policy\_file option as in the following item.
- Specifying the -authorization policy file option in addition to -server name makes Impala read privilege information from a policy file, rather than from the metastore database. The argument to the -authorization\_policy\_file option specifies the HDFS path to the policy file that defines the privileges on different schema objects.

For example, you might adapt your /etc/default/impala configuration to contain lines like the following. To use the Sentry service rather than the policy file:

```
IMPALA_SERVER_ARGS=" \
-server_name=server1 \
```

Or to use the policy file, as in releases prior to Impala 1.4:

```
IMPALA_SERVER_ARGS=" \
-authorization_policy_file=/user/hive/warehouse/auth-policy.ini \
-server_name=server1
```

The preceding examples set up a symbolic name of server1 to refer to the current instance of Impala. This symbolic name is used in the following ways:

- In an environment managed by Cloudera Manager, the server name is specified through Impala (Service-Wide) > Category > Advanced > Sentry Service and Hive > Service-Wide > Advanced > Sentry Service. The values must be the same for both, so that Impala and Hive can share the privilege rules. Restart the Impala and Hive services after setting or changing this value.
- In an environment not managed by Cloudera Manager, you specify this value for the sentry.hive.server property in the sentry-site.xml configuration file for Hive, as well as in the -server\_name option for impalad.
  - If the impalad daemon is not already running, start it as described in Starting Impala. If it is already running, restart it with the command sudo /etc/init.d/impala-server restart. Run the appropriate commands on all the nodes where impalad normally runs.
- If you use the mode of operation using the policy file, the rules in the [roles] section of the policy file refer to this same <code>server1</code> name. For example, the following rule sets up a role <code>report\_generator</code> that lets users with that role query any table in a database named reporting db on a node where the impalad daemon was started up with the -server\_name=server1 option:

```
[roles]
report_generator = server=server1->db=reporting_db->table=*->action=SELECT
```

When impalad is started with one or both of the -server\_name=server1 and -authorization\_policy\_file options, Impala authorization is enabled. If Impala detects any errors or inconsistencies in the authorization settings or the policy file, the daemon refuses to start.

# Using Impala with the Sentry Service (CDH 5.1 or higher only)

When you use the Sentry service rather than the policy file, you set up privileges through GRANT and REVOKE statement in either Impala or Hive, then both components use those same privileges automatically. (Impala added the GRANT and REVOKE statements in Impala 2.0.0 / CDH 5.2.0.)

Hive already had GRANT and REVOKE statements prior to CDH 5.1, but those statements were not production-ready. CDH 5.1 is the first release where those statements use the Sentry framework and are considered GA level. If you used the Hive GRANT and REVOKE statements prior to CDH 5.1, you must set up these privileges with the CDH 5.1 versions of GRANT and REVOKE to take advantage of Sentry authorization.

For information about using the updated Hive GRANT and REVOKE statements, see Sentry service topic in the CDH 5 Security Guide.

# Using Impala with the Sentry Policy File

The policy file is a file that you put in a designated location in HDFS, and is read during the startup of the impalad daemon when you specify both the -server\_name and -authorization\_policy\_file startup options. It controls which objects (databases, tables, and HDFS directory paths) can be accessed by the user who connects to impalad, and what operations that user can perform on the objects.

Note: This mode of operation works on both CDH 4 and CDH 5, but in CDH 5 the emphasis is shifting towards managing privileges through SQL statements, as described in Using Impala with the Sentry Service (CDH 5.1 or higher only) on page 278. If you are still using policy files, plan to migrate to the new approach some time in the future.

The location of the policy file is listed in the auth-site.xml configuration file. To minimize overhead, the security information from this file is cached by each impalad daemon and refreshed automatically, with a default interval of 5 minutes. After making a substantial change to security policies, restart all Impala daemons to pick up the changes immediately.

# Policy File Location and Format

The policy file uses the familiar .ini format, divided into the major sections [groups] and [roles]. There is also an optional [databases] section, which allows you to specify a specific policy file for a particular database, as explained in <u>Using Multiple Policy Files for Different Databases</u> on page 283. Another optional section, [users], allows you to override the OS-level mapping of users to groups; that is an advanced technique primarily for testing and debugging, and is beyond the scope of this document.

In the [groups] section, you define various categories of users and select which roles are associated with each category. The group and user names correspond to Linux groups and users on the server where the impalad daemon runs.

The group and user names in the [groups] section correspond to Linux groups and users on the server where the impalad daemon runs. When you access Impala through the impalad interpreter, for purposes of authorization, the user is the logged-in Linux user and the groups are the Linux groups that user is a member of. When you access Impala through the ODBC or JDBC interfaces, the user and password specified through the connection string are used as login credentials for the Linux server, and authorization is based on that user name and the associated Linux group membership.

In the [roles] section, you a set of roles. For each role, you specify precisely the set of privileges is available. That is, which objects users with that role can access, and what operations they can perform on those objects. This is the lowest-level category of security information; the other sections in the policy file map the privileges to higher-level divisions of groups and users. In the [groups] section, you specify which roles are associated with which groups. The group and user names correspond to Linux groups and users on the server where the impalad daemon runs. The privileges are specified using patterns like:

```
server=server_name->db=database_name->table=table_name->action=SELECT
server=server_name->db=database_name->table=table_name->action=CREATE
server=server_name->db=database_name->table=table_name->action=ALL
```

For the server name value, substitute the same symbolic name you specify with the impalad -server name option. You can use \* wildcard characters at each level of the privilege specification to allow access to all such objects. For example:

```
server=impala-host.example.com->db=default->table=t1->action=SELECT
server=impala-host.example.com->db=*->table=*->action=CREATE
server=impala-host.example.com->db=*->table=audit_log->action=SELECT
server=impala-host.example.com->db=default->table=t1->action=*
```

When authorization is enabled, Impala uses the policy file as a whitelist, representing every privilege available to any user on any object. That is, only operations specified for the appropriate combination of object, role, group, and user are allowed; all other operations are not allowed. If a group or role is defined multiple times in the policy file, the last definition takes precedence.

To understand the notion of whitelisting, set up a minimal policy file that does not provide any privileges for any object. When you connect to an Impala node where this policy file is in effect, you get no results for SHOW DATABASES, and an error when you issue any SHOW TABLES, USE database\_name, DESCRIBE table\_name, SELECT, and or other statements that expect to access databases or tables, even if the corresponding databases and tables exist.

The contents of the policy file are cached, to avoid a performance penalty for each query. The policy file is re-checked by each impalad node every 5 minutes. When you make a non-time-sensitive change such as adding new privileges or new users, you can let the change take effect automatically a few minutes later. If you remove or reduce privileges, and want the change to take effect immediately, restart the impalad daemon on all nodes, again specifying the -server\_name and -authorization\_policy\_file options so that the rules from the updated policy file are applied.

# Examples of Policy File Rules for Security Scenarios

The following examples show rules that might go in the policy file to deal with various authorization-related scenarios. For illustration purposes, this section shows several very small policy files with only a few rules each. In your environment, typically you would define many roles to cover all the scenarios involving your own databases, tables, and applications, and a smaller number of groups, whose members are given the privileges from one or more roles.

### A User with No Privileges

If a user has no privileges at all, that user cannot access any schema objects in the system. The error messages do not disclose the names or existence of objects that the user is not authorized to read.

This is the experience you want a user to have if they somehow log into a system where they are not an authorized Impala user. In a real deployment with a filled-in policy file, a user might have no privileges because they are not a member of any of the relevant groups mentioned in the policy file.

# **Examples of Privileges for Administrative Users**

When an administrative user has broad access to tables or databases, the associated rules in the [roles] section typically use wildcards and/or inheritance. For example, in the following sample policy file, db=\* refers to all databases and db=\*->table=\* refers to all tables in all databases.

Omitting the rightmost portion of a rule means that the privileges apply to all the objects that could be specified there. For example, in the following sample policy file, the all\_databases role has all privileges for all tables in all databases, while the one\_database role has all privileges for all tables in one specific database. The all\_databases role does not grant privileges on URIs, so a group with that role could not issue a CREATE TABLE statement with a LOCATION clause. The entire\_server role has all privileges on both databases and URIs within the server.

```
[groups]
supergroup = all_databases
[roles]
read_all_tables = server=server1->db=*->table=*->action=SELECT
all_tables = server=server1->db=*->table=*
```

```
all_databases = server=server1->db=*
one_database = server=server1->db=test_db
entire_server = server=server1
```

# A User with Privileges for Specific Databases and Tables

If a user has privileges for specific tables in specific databases, the user can access those things but nothing else. They can see the tables and their parent databases in the output of SHOW TABLES and SHOW DATABASES, USE the appropriate databases, and perform the relevant actions (SELECT and/or INSERT) based on the table privileges. To actually create a table requires the ALL privilege at the database level, so you might define separate roles for the user that sets up a schema and other users or applications that perform day-to-day operations on the tables.

The following sample policy file shows some of the syntax that is appropriate as the policy file grows, such as the # comment syntax, \ continuation syntax, and comma separation for roles assigned to groups or privileges assigned to roles.

```
[groups]
cloudera = training_sysadmin, instructor
visitor = student

[roles]
training_sysadmin = server=server1->db=training, \
server=server1->db=instructor_private, \
server=server1->db=lesson_development
instructor = server=server1->db=training->table=*->action=*, \
server=server1->db=instructor_private->table=*->action=*, \
server=server1->db=instructor_private->table=lesson*
# This particular course is all about queries, so the students can SELECT but not INSERT or CREATE/DROP.
student = server=server1->db=training->table=lesson_*->action=SELECT
```

# Privileges for Working with External Data Files

When data is being inserted through the LOAD DATA statement, or is referenced from an HDFS location outside the normal Impala database directories, the user also needs appropriate permissions on the URIs corresponding to those HDFS locations.

In this sample policy file:

- The external\_table role lets us insert into and query the Impala table, external\_table.sample.
- The staging\_dir role lets us specify the HDFS path /user/cloudera/external\_data with the LOAD DATA statement. Remember, when Impala queries or loads data files, it operates on all the files in that directory, not just a single file, so any Impala LOCATION parameters refer to a directory rather than an individual file.
- We included the IP address and port of the Hadoop name node in the HDFS URI of the staging\_dir rule. We found those details in /etc/hadoop/conf/core-site.xml, under the fs.default.name element. That is what we use in any roles that specify URIs (that is, the locations of directories in HDFS).
- We start this example after the table <code>external\_table.sample</code> is already created. In the policy file for the example, we have already taken away the <code>external\_table\_admin</code> role from the cloudera group, and replaced it with the lesser-privileged <code>external\_table</code> role.
- We assign privileges to a subdirectory underneath /user/cloudera in HDFS, because such privileges also apply to any subdirectories underneath. If we had assigned privileges to the parent directory /user/cloudera, it would be too likely to mess up other files by specifying a wrong location by mistake.
- The cloudera under the [groups] section refers to the cloudera group. (In the demo VM used for this example, there is a cloudera user that is a member of a cloudera group.)

## Policy file:

```
[groups]
cloudera = external_table, staging_dir
[roles]
```

```
external_table_admin = server=server1->db=external_table
external_table = server=server1->db=external_table->table=sample->action=*
staging dir =
server=server1->uri=hdfs://127.0.0.1:8020/user/cloudera/external_data->action=*
```

impala-shell session:

```
[localhost:21000] > use external_table;
Query: use external_table
[localhost:21000] > show tables;
Query: show tables
Query finished, fetching results ...
name
sample
Returned 1 row(s) in 0.02s
[localhost:21000] > select * from sample;
Query: select * from sample
Query finished, fetching results ...
 1
  5
150
Returned 3 row(s) in 1.04s
[localhost:21000] > load data inpath '/user/cloudera/external_data' into table sample;
Query: load data inpath '/user/cloudera/external_data' into table sample
Query finished, fetching results ...
summary
| Loaded 1 file(s). Total files in destination location: 2 |
Returned 1 row(s) in 0.26s
[localhost:21000] > select * from sample;
Query: select * from sample
Query finished, fetching results ...
X
  2
  64738
 49152
150
Returned 9 row(s) in 0.22s
[localhost:21000] > load data inpath '/user/cloudera/unauthorized_data' into table
Query: load data inpath '/user/cloudera/unauthorized_data' into table sample
ERROR: AuthorizationException: User 'cloudera' does not have privileges to access:
hdfs://127.0.0.1:8020/user/cloudera/unauthorized_data
```

# Controlling Access at the Column Level through Views

If a user has SELECT privilege for a view, they can query the view, even if they do not have any privileges on the underlying table. To see the details about the underlying table through EXPLAIN OR DESCRIBE FORMATTED statements on the view, the user must also have SELECT privilege for the underlying table.

### Important:

The types of data that are considered sensitive and confidential differ depending on the jurisdiction the type of industry, or both. For fine-grained access controls, set up appropriate privileges based on all applicable laws and regulations.

Be careful using the ALTER VIEW statement to point an existing view at a different base table or a new set of columns that includes sensitive or restricted data. Make sure that any users who have SELECT privilege on the view do not gain access to any additional information they are not authorized to see.

The following example shows how a system administrator could set up a table containing some columns with sensitive information, then create a view that only exposes the non-confidential columns.

```
[localhost:21000] > create table sensitive_info
               > (
                   name string,
                   address string,
                  credit_card string,
                  taxpayer_id string
[localhost:21000] > create view name_address_view as select name, address from
sensitive_info;
```

Then the following policy file specifies read-only privilege for that view, without authorizing access to the underlying table:

```
[groups]
cloudera = view_only_privs
[roles]
view_only_privs = server=server1->db=reports->table=name_address_view->action=SELECT
```

Thus, a user with the view\_only\_privs role could access through Impala queries the basic information but not the sensitive information, even if both kinds of information were part of the same data file.

You might define other views to allow users from different groups to query different sets of columns.

# Separating Administrator Responsibility from Read and Write Privileges

Remember that to create a database requires full privilege on that database, while day-to-day operations on tables within that database can be performed with lower levels of privilege on specific table. Thus, you might set up separate roles for each database or application: an administrative one that could create or drop the database, and a user-level one that can access only the relevant tables.

For example, this policy file divides responsibilities between users in 3 different groups:

- Members of the supergroup group have the training\_sysadmin role and so can set up a database named training.
- Members of the cloudera group have the instructor role and so can create, insert into, and query any tables in the training database, but cannot create or drop the database itself.
- Members of the visitor group have the student role and so can query those tables in the training database.

```
[groups]
supergroup = training_sysadmin
cloudera = instructor
visitor = student
training_sysadmin = server=server1->db=training
instructor = server=server1->db=training->table=*->action=*
student = server=server1->db=training->table=*->action=SELECT
```

# Using Multiple Policy Files for Different Databases

For an Impala cluster with many databases being accessed by many users and applications, it might be cumbersome to update the security policy file for each privilege change or each new database, table, or view. You can allow security to be managed separately for individual databases, by setting up a separate policy file for each database:

- Add the optional [databases] section to the main policy file.
- Add entries in the [databases] section for each database that has its own policy file.
- For each listed database, specify the HDFS path of the appropriate policy file.

# For example:

```
[databases]
# Defines the location of the per-DB policy files for the 'customers' and 'sales'
databases.
customers = hdfs://ha-nn-uri/etc/access/customers.ini
sales = hdfs://ha-nn-uri/etc/access/sales.ini
```

To enable URIs in per-DB policy files, add the following string in the Cloudera Manager field Impala Service Environment Advanced Configuration Snippet (Safety Valve):

```
JAVA TOOL OPTIONS="-Dsentry.allow.uri.db.policyfile=true"
```

Important: Enabling URIs in per-DB policy files introduces a security risk by allowing the owner of the db-level policy file to grant himself/herself load privileges to anything the impala user has read permissions for in HDFS (including data in other databases controlled by different db-level policy files).

# Setting Up Schema Objects for a Secure Impala Deployment

Remember that in your role definitions, you specify privileges at the level of individual databases and tables, or all databases or all tables within a database. To simplify the structure of these rules, plan ahead of time how to name your schema objects so that data with different authorization requirements is divided into separate databases.

If you are adding security on top of an existing Impala deployment, remember that you can rename tables or even move them between databases using the ALTER TABLE statement. In Impala, creating new databases is a relatively inexpensive operation, basically just creating a new directory in HDFS.

You can also plan the security scheme and set up the policy file before the actual schema objects named in the policy file exist. Because the authorization capability is based on whitelisting, a user can only create a new database or table if the required privilege is already in the policy file: either by listing the exact name of the object being created, or a \* wildcard to match all the applicable objects within the appropriate container.

# Privilege Model and Object Hierarchy

Privileges can be granted on different objects in the schema. Any privilege that can be granted is associated with a level in the object hierarchy. If a privilege is granted on a container object in the hierarchy, the child object automatically inherits it. This is the same privilege model as Hive and other database systems such as MySQL.

The kinds of objects in the schema hierarchy are:

```
Server
TIRT
Database
  Table
```

The server name is specified by the -server\_name option when impalad starts. Specify the same name for all impalad nodes in the cluster.

URIs represent the HDFS paths you specify as part of statements such as CREATE EXTERNAL TABLE and LOAD DATA. Typically, you specify what look like UNIX paths, but these locations can also be prefixed with hdfs://to make clear that they are really URIs. To set privileges for a URI, specify the name of a directory, and the privilege applies to all the files in that directory and any directories underneath it.

There are not separate privileges for individual table partitions or columns. To specify read privileges at this level, you create a view that queries specific columns and/or partitions from a base table, and give SELECT privilege on the view but not the underlying table. See <u>Views</u> for details about views in Impala.

URIs must start with either hdfs://orfile://. If a URI starts with anything else, it will cause an exception and the policy file will be invalid. When defining URIs for HDFS, you must also specify the NameNode. For example:

```
data_read = server=server1->uri=file:///path/to/dir, \
server=server1->uri=hdfs://namenode:port/path/to/dir
```

# Warning:

Because the NameNode host and port must be specified, Cloudera strongly recommends you use High Availability (HA). This ensures that the URI will remain constant even if the namenode changes.

```
data_read = server=server1->uri=file:///path/to/dir,\
server=server1->uri=hdfs://ha-nn-uri/path/to/dir
```

Table 27: Valid privilege types and objects they apply to

Privilege	Object
INSERT	DB, TABLE
SELECT	DB, TABLE
ALL	SERVER, TABLE, DB, URI

### Note:

Although this document refers to the ALL privilege, currently if you use the policy file mode, you do not use the actual keyword ALL in the policy file. When you code role entries in the policy file:

- To specify the ALL privilege for a server, use a role like server=server\_name.
- To specify the ALL privilege for a database, use a role like server=server\_name->db=database\_name.
- To specify the ALL privilege for a table, use a role like server=server\_name->db=database\_name->table=table\_name->action=\*.

Operation	Scope	Privileges	URI	Others
EXPLAIN	TABLE	SELECT		
LOAD DATA	TABLE	INSERT	URI	
CREATE DATABASE	SERVER	ALL		
DROP DATABASE	DATABASE	ALL		
CREATE TABLE	DATABASE	ALL		
DROP TABLE	TABLE	ALL		
DESCRIBE TABLE	TABLE	SELECT/INSERT		

Operation	Scope	Privileges	URI	Others
ALTER TABLE ADD COLUMNS	TABLE	ALL		
ALTER TABLE REPLACE COLUMNS	TABLE	ALL		
ALTER TABLE CHANGE column	TABLE	ALL		
ALTER TABLE RENAME	TABLE	ALL		
ALTER TABLE SET TBLPROPERTIES	TABLE	ALL		
ALTER TABLE SET FILEFORMAT	TABLE	ALL		
ALTER TABLE SET LOCATION	TABLE	ALL	URI	
ALTER TABLE ADD PARTITION	TABLE	ALL		
ALTER TABLE ADD PARTITION location	TABLE	ALL	URI	
ALTER TABLE DROP PARTITION	TABLE	ALL		
ALTER TABLE PARTITION SET FILEFORMAT	TABLE	ALL		
ALTER TABLE SET SERDEPROPERTIES	TABLE	ALL		
CREATE VIEW	DATABASE; SELECT on TABLE	ALL		SELECT on TABLE
DROP VIEW	VIEW/TABLE	ALL		
ALTER VIEW	You need ALL privilege on the named view and the parent database, plus SELECT privilege for any tables or views referenced by the view query. Once the view is created or altered by a high-privileged system administrator, it can be queried by a lower-privileged user who does not have full query privileges for the base tables. (This is how you implement column-level security.)	ALL, SELECT		

Operation	Scope	Privileges	URI	Others
ALTER TABLE SET LOCATION	TABLE	ALL	URI	
CREATE EXTERNAL TABLE	Database (ALL), URI (SELECT)	ALL, SELECT		
SELECT	TABLE	SELECT		
USE <dbname></dbname>	Any			
CREATE FUNCTION	SERVER	ALL		
DROP FUNCTION	SERVER	ALL		
REFRESH	TABLE	SELECT/INSERT		
INVALIDATE METADATA	SERVER	ALL		
INVALIDATE METADATA	TABLE	SELECT/INSERT		
COMPUTE STATS	TABLE	ALL		
SHOW TABLE STATS, SHOW PARTITIONS	TABLE	SELECT/INSERT		
SHOW COLUMN STATS	TABLE	SELECT/INSERT		
SHOW FUNCTIONS	DATABASE	SELECT		
SHOW TABLES		No special privileges needed to issue the statement, but only shows objects you are authorized for		
SHOW DATABASES, SHOW SCHEMAS		No special privileges needed to issue the statement, but only shows objects you are authorized for		

# Debugging Failed Sentry Authorization Requests

Sentry logs all facts that lead up to authorization decisions at the debug level. If you do not understand why Sentry is denying access, the best way to debug is to temporarily turn on debug logging:

- In Cloudera Manager, add log4j.logger.org.apache.sentry=DEBUG to the logging settings for your service through the corresponding Logging Safety Valve field for the Impala, Hive Server 2, or Solr Server services.
- On systems not managed by Cloudera Manager, add log4j.logger.org.apache.sentry=DEBUG to the log4j.properties file on each host in the cluster, in the appropriate configuration directory for each service.

Specifically, look for exceptions and messages such as:

which indicate each evaluation Sentry makes. The FilePermission is from the policy file, while RequestPermission is the privilege required for the query. A RequestPermission will iterate over all appropriate FilePermission settings until a match is found. If no matching privilege is found, Sentry returns false indicating "Access Denied".

# Configuring Per-User Access for Hue

When users connect to Impala directly through the impala-shell interpreter, the Impala authorization feature determines what actions they can take and what data they can see. When users submit Impala queries through a separate application, such as Hue, typically all requests are treated as coming from the same user. In Impala 1.2 and higher, authorization is extended by a new feature that allows applications to pass along credentials for the users that connect to them (known as "delegation"), and issue Impala queries with the privileges for those users. Currently, the delegation feature is available only for Impala queries submitted through the Hue interface; for example, Impala cannot issue queries using the privileges of the HDFS user.

A new startup option for impalad, --authorized\_proxy\_user\_config, is available in Impala 1.2 and higher. When you specify this option, users whose names you specify (such as hue) can delegate the execution of a query to another user. The query runs with the privileges of the delegated user, not the original user such as hue. The name of the delegated user is passed using the HiveServer2 configuration property impala.doas.user.

You can specify a list of users that the application user can delegate to, or \* to allow a superuser to delegate to any other user. For example:

```
impalad --authorized_proxy_user_config 'hue=user1,user2;admin=*' ...
```

**Note:** Make sure to use single quotes or escape characters to ensure that any \* characters do not undergo wildcard expansion when specified in command-line arguments.

See Modifying Impala Startup Options for details about adding or changing impalad startup options. See this Cloudera blog post for background information about the delegation capability in HiveServer2.

# Managing Sentry for Impala through Cloudera Manager

To enable the Sentry service for Impala and Hive, set Hive/Impala > Service-Wide > Sentry Service parameter to the Sentry service. Then restart Impala and Hive. Simply adding Sentry service as a dependency and restarting enables Impala and Hive to use the Sentry service.

To set the server name to use when granting server level privileges, set the Hive > Service-Wide > Advanced > Server Name for Sentry Authorization parameter. When using Sentry with the Hive Metastore, you can specify the list of users that are allowed to bypass Sentry Authorization in Hive Metastore using Hive > Service-Wide > Security > Bypass Sentry Authorization Users. These are usually service users that already ensure all activity has been authorized.

Note: The Hive/Impala > Service-Wide > Policy File Based Sentry tab contains parameters only relevant to configuring Sentry using policy files. In particular, make sure that Enable Sentry Authorization using Policy Files parameter is unchecked when using the Sentry service. Cloudera Manager throws a validation error if you attempt to configure the Sentry service and policy file at the same time.

# The DEFAULT Database in a Secure Deployment

Because of the extra emphasis on granular access controls in a secure deployment, you should move any important or sensitive information out of the DEFAULT database into a named database whose privileges are specified in the policy file. Sometimes you might need to give privileges on the DEFAULT database for administrative reasons; for example, as a place you can reliably specify with a USE statement when preparing to drop a database.

# Enabling Sentry Authorization for Search using the Command Line

Sentry enables role-based, fine-grained authorization for Cloudera Search. Sentry can apply a range of restrictions to various tasks, such as accessing data or creating collections. These restrictions are consistently applied, regardless of the way users attempt to complete actions. For example, restricting access to data in a collection restricts that access whether queries come from the command line, from a browser, Hue, or through the admin console.

- You can use either Cloudera Manager or the following command-line instructions to complete this configuration.
- This information applies specifically to CDH 5.4.x. If you use an earlier version of CDH, see the documentation for that version located at Cloudera Documentation.

For information on enabling Sentry authorization using Cloudera Manager, see Configuring Sentry Policy File Authorization Using Cloudera Manager on page 269.

Follow the instructions below to configure Sentry under CDH 4.5 or later or CDH 5. Sentry is included in the Search installation.

Note: Sentry for Search depends on Kerberos authentication. For additional information on using Kerberos with Search, see <u>Search Authentication</u> on page 111.

This document describes configuring Sentry for Cloudera Search. For information about alternate ways to configure Sentry or for information about installing Sentry for other services, see:

- Enabling Sentry Authorization for Solr on page 272 for instructions for using Cloudera Manager to configure Search Authorization with Sentry.
- Impala Security for instructions on using Impala with Sentry.
- Sentry Installation to install the version of Sentry that was provided with CDH 4.
- Sentry Installation to install the version of Sentry that was provided with CDH 5.

# Roles and Collection-Level Privileges

Sentry uses a role-based privilege model. A role is a set of rules for accessing a given Solr collection. Access to each collection is governed by privileges: Query, Update, or All (\*).

For example, a rule for the Query privilege on collection logs would be formulated as follows:

```
collection=logs->action=Ouerv
```

A role can contain multiple such rules, separated by commas. For example the engineer\_role might contain the Query privilege for hive logs and hbase logs collections, and the Update privilege for the current bugs collection. You would specify this as follows:

```
engineer_role = collection=hive_logs->action=Query, collection=hbase_logs->action=Query,
collection=current_bugs->action=Update
```

# Users and Groups

- A user is an entity that is permitted by the Kerberos authentication system to access the Search service.
- A group connects the authentication system with the authorization system. It is a set of one or more users who have been granted one or more authorization roles. Sentry allows a set of roles to be configured for a
- A configured group provider determines a user's affiliation with a group. The current release supports HDFS-backed groups and locally configured groups. For example,

```
dev_ops = dev_role, ops_role
```

Here the group dev\_ops is granted the roles dev\_role and ops\_role. The members of this group can complete searches that are allowed by these roles.

### User to Group Mapping

You can configure Sentry to use either Hadoop groups or groups defined in the policy file.

**Important:** You can use either Hadoop groups or local groups, but not both at the same time. Use local groups if you want to do a quick proof-of-concept. For production, use Hadoop groups.

## To configure Hadoop groups:

```
Set the sentry.provider property in sentry-site.xml to
org.apache.sentry.provider.file.HadoopGroupResourceAuthorizationProvider.
```

By default, this uses local shell groups. See the Group Mapping section of the HDFS Permissions Guide for more information.

In this case, Sentry uses the Hadoop configuration described in Configuring LDAP Group Mappings on page 133. Cloudera Manager automatically uses this configuration. In a deployment not managed by Cloudera Manager, manually set these configuration parameters parameters in the hadoop-conf file that is passed to Solr.

### To configure local groups:

1. Define local groups in a [users] section of the Sentry Policy file. For example:

```
[users]
user1 = group1, group2, group3
user2 = group2, group3
```

2. In sentry-site.xml, set search.sentry.provider as follows:

```
property>
    <name>sentry.provider</name>
<value>org.apache.sentry.provider.file.LocalGroupResourceAuthorizationProvider</value>
  </property>
```

## Setup and Configuration

This release of Sentry stores the configuration as well as privilege policies in files. The sentry-site.xml file contains configuration options such as privilege policy file location. The Policy File on page 289 contains the privileges and groups. It has a .ini file format and should be stored on HDFS.

Sentry is automatically installed when you install Cloudera Search for CDH or Cloudera Search 1.1.0 or later.

### Policy File

The sections that follow contain notes on creating and maintaining the policy file.

**Warning:** An invalid configuration disables all authorization while logging an exception.

### Storing the Policy File

Considerations for storing the policy file(s) include:

- 1. Replication count Because the file is read for each query, you should increase this; 10 is a reasonable value.
- 2. Updating the file Updates to the file are only reflected when the Solr process is restarted.

### **Defining Roles**

Keep in mind that role definitions are not cumulative; the newer definition replaces the older one. For example, the following results in role1 having privilege2, not privilege1 and privilege2.

```
role1 = privilege1
role1 = privilege2
```

## Sample Configuration

This section provides a sample configuration.

Note: Sentry with CDH Search does not support multiple policy files. Other implementations of Sentry such as Sentry for Hive do support different policy files for different databases, but Sentry for CDH Search has no such support for multiple policies.

### Policy File

The following is an example of a CDH Search policy file. The sentry-provider.ini would exist in an HDFS location such as hdfs://ha-nn-uri/user/solr/sentry/sentry-provider.ini. This location must be readable by Solr.

• Note: Use separate policy files for each Sentry-enabled service. Using one file for multiple services results in each service failing on the other services' entries. For example, with a combined Hive and Search file, Search would fail on Hive entries and Hive would fail on Search entries.

### sentry-provider.ini

```
[groups]
# Assigns each Hadoop group to its set of roles
engineer = engineer_role
ops = ops_role
dev_ops = engineer_role, ops_role
hbase_admin = hbase_admin_role
[roles]
# The following grants all access to source_code.
# "collection = source_code" can also be used as syntactic
# sugar for "collection = source_code->action=*"
engineer_role = collection = source_code->action=*
# The following imply more restricted access.
ops_role = collection = hive_logs->action=Query
dev_ops_role = collection = hbase_logs->action=Query
#give hbase_admin_role the ability to create/delete/modify the hbase_logs collection
hbase_admin_role = collection=admin->action=*, collection=hbase_logs->action=*
```

### Sentry Configuration File

The following is an example of a sentry-site.xml file.

#### sentry-site.xml

```
If the HDFS configuration files (core-site.xml, hdfs-site.xml)
     pointed to by SOLR_HDFS_CONFIG in /etc/default/solr
     point to HDFS, the path will be in HDFS;
     alternatively you could specify a full path,
     e.g.:hdfs://namenode:port/path/to/authz-provider.ini
</property>
```

## Enabling Sentry in Cloudera Search for CDH 5

You can enable Sentry using Cloudera Manager or by manually modifying files. For more information on enabling Sentry using Cloudera Manager, see Configuring Sentry Policy File Authorization Using Cloudera Manager on page 269 and Enabling Sentry Authorization for Solr on page 272.

Sentry is enabled with addition of two properties to /etc/default/solr or /opt/cloudera/parcels/CDH-\*/etc/default/solr.

- In a Cloudera Manager deployment, these properties are added automatically when you click Enable Sentry **Authorization** in the Solr configuration page in Cloudera Manager.
- In a deployment not managed by Cloudera Manager, you must make these changes yourself. The variable SOLR\_AUTHORIZATION\_SENTRY\_SITE specifies the path to sentry-site.xml. The variable SOLR AUTHORIZATION SUPERUSER specifies the first part of SOLR KERBEROS PRINCIPAL. This is solr for the majority of users, as solr is the default. Settings are of the form:

```
SOLR_AUTHORIZATION_SENTRY_SITE=/location/to/sentry-site.xml
SOLR_AUTHORIZATION_SUPERUSER=solr
```

To enable sentry collection-level authorization checking on a new collection, the instancedir for the collection must use a modified version of solrconfig.xml with Sentry integration. Each collection has a separate solrconfig.xml file, meaning you can define different behavior for each collection. The command solrctl instancedir --generate generates two versions of solrconfig.xml:the standard solrconfig.xml without sentry integration, and the sentry-integrated version called solrconfig.xml.secure. To use the sentry-integrated version, replace solrconfig.xml with solrconfig.xml.secure before creating the instancedir.

You can enable Sentry on an existing collection by modifying the settings that are stored in instancedir. For example, you might have an existing collection named foo and a standard solrconfig.xml. By default, collections are stored in instancedirs that use the the collection's name, which is £00 in this case. In such a situation, you could enable Sentry from the command line by executing the following commands:

```
# generate a fresh instancedir
solrctl instancedir --generate foosecure
# download the existing instancedir from ZK into subdirectory foo
solrctl instancedir --get foo foo
# replace the existing solrconfig.xml with the sentry-enabled one
cp foosecure/conf/solrconfig.xml.secure foo/conf/solrconfig.xml
# update the instancedir in ZK
solrctl instancedir --update foo foo
# reload the collection
solrctl collection --reload foo
```

If you have an existing collection using a version of solrconfig.xml that you have modified, contact Support for assistance.

### Providing Document-Level Security Using Sentry

For role-based access control of a collection, an administrator modifies a Sentry role so it has query, update, or administrative access, as described above.

Collection-level authorization is useful when the access control requirements for the documents in the collection are the same, but users may want to restrict access to a subset of documents in a collection. This finer-grained

### Authorization

restriction could be achieved by defining separate collections for each subset, but this is difficult to manage, requires duplicate documents for each collection, and requires that these documents be kept synchronized.

Document-level access control solves this issue by associating authorization tokens with each document in the collection. This enables granting Sentry roles access to sets of documents in a collection.

### **Document-Level Security Model**

Document-level security depends on a chain of relationships between users, groups, roles, and documents.

- Users are assigned to groups.
- Groups are assigned to roles.
- Roles are stored as "authorization tokens" in a specified field in the documents.

Document-level security supports restricting which documents can be viewed by which users. Access is provided by adding roles as "authorization tokens" to a specified document field. Conversely, access is implicitly denied by omitting roles from the specified field. In other words, in a document-level security enabled environment, a user might submit a query that matches a document; if the user is not part of a group that has a role has been granted access to the document, the result is not returned.

For example, Alice might belong to the administrators group. The administrators group may belong to the doc-mgmt role. A document could be ingested and the doc-mgmt role could be added at ingest time. In such a case, if Alice submitted a query that matched the document, Search would return the document, since Alice is then allowed to see any document with the "doc-mgmt" authorization token.

Similarly, Bob might belong to the guests group. The guests group may belong to the public-browser role. If Bob tried the same query as Alice, but the document did not have the public-browser role, Search would not return the result because Bob does not belong to a group that is associated with a role that has access.

Note that collection-level authorization rules still apply, if enabled. Even if Alice is able to view a document given document-level authorization rules, if she is not allowed to query the collection, the query will fail.

Roles are typically added to documents when those documents are ingested, either via the standard Solr APIs or, if using morphlines, the <u>setValues</u> morphline command.

#### **Enabling Document-Level Security**

Cloudera Search supports document-level security in Search for CDH 5.1 and later. Document-level security requires collection-level security. Configuring collection-level security is described earlier in this topic.

Document-level security is disabled by default, so the first step in using document-level security is to enable the feature by modifying the solrconfig.xml.secure file. Remember to replace the solrconfig.xml with this file, as described in **Enabling Sentry in Cloudera Search for CDH 5** on page 291.

To enable document-level security, change solrconfig.xml.secure. The default file contents are as follows:

```
<searchComponent name="queryDocAuthorization">
   <!-- Set to true to enabled document-level authorization -->
    <bool name="enabled">false</bool>
    <!-- Field where the auth tokens are stored in the document -->
    <str name="sentryAuthField">sentry_auth</str>
    <!-- Auth token defined to allow any role to access the document.
        Uncomment to enable. -->
    <!--<str name="allRolesToken">*</str>-->
</searchComponent>
```

The enabled Boolean determines whether document-level authorization is enabled. To enable document level security, change this setting to true.

- The sentryAuthField string specifies the name of the field that is used for storing authorization information. You can use the default setting of sentry\_auth or you can specify some other string to be used for assigning values during ingest.
  - Note: This field must exist as an explicit or dynamic field in the schema for the collection you are creating with document-level security. sentry\_auth exists in the default schema.xml, which is automatically generated and can be found in the same directory as solrconfig.xml.
    - for the collection you are creating with document-level security. Schema.xml is in the generated configuration in the same directory as the solrconfig.xml
- The allRolesToken string represents a special token defined to allow any role access to the document. By default, this feature is disabled. To enable this feature, uncomment the specification and specify the token. This token should be different from the name of any sentry role to avoid collision. By default it is "\*". This feature is useful when first configuring document level security or it can be useful in granting all roles access to a document when the set of roles may change. See Best Practices for additional information.

### **Best Practices**

### Using allGroupsToken

You may want to grant every user that belongs to a role access to certain documents. One way to accomplish this is to specify all known roles in the document, but this requires updating or re-indexing the document if you add a new role. Alternatively, an alluser role, specified in the Sentry .ini file, could contain all valid groups, but this role would need to be updated every time a new group was added to the system. Instead, specifying allgroupsToken allows any user that belongs to a valid role to access the document. This access requires no updating as the system evolves.

In addition, allgroupsToken may be useful for transitioning a deployment to use document-level security. Instead of having to define all the roles upfront, all the documents can be specified with allgroupsToken and later modified as the roles are defined.

### Consequences of Document-Level Authorization Only Affecting Queries

Document-level security does not prevent users from modifying documents or performing other update operations on the collection. Update operations are only governed by collection-level authorization.

Document-level security can be used to prevent documents being returned in query results. If users are not granted access to a document, those documents are not returned even if that user submits a query that matches those documents. This does not have affect attempted updates.

Consequently, it is possible for a user to not have access to a set of documents based on document-level security, but to still be able to modify the documents via their collection-level authorization update rights. This means that a user can delete all documents in the collection. Similarly, a user might modify all documents, adding their authorization token to each one. After such a modification, the user could access any document via querying. Therefore, if you are restricting access using document-level security, consider granting collection-level update rights only to those users you trust and assume they will be able to access every document in the collection.

### Limitations on Query Size

By default queries support up to 1024 Boolean clauses. As a result, queries containing more that 1024 clauses may cause errors. Because authorization information is added by Sentry as part of a query, using document-level security can increase the number of clauses. In the case where users belong to many roles, even simple queries can become quite large. If a query is too large, an error of the following form occurs:

org.apache.lucene.search.BooleanQuery\$TooManyClauses: maxClauseCount is set to 1024

### Authorization

To change the supported number of clauses, edit the maxBooleanClauses setting in solrconfig.xml. For example, to allow 2048 clauses, you would edit the setting so it appears as follows:

For maxBooleanClauses to be applied as expected, make any change to this value to all collections and then restart the service. You must make this change to all collections because this option modifies a global Lucene property, affecting all Solr cores. If different solrconfig.xml files have different values for this property, the effective value is determined per host, based on the first Solr core to be initialized.

# **Enabling Secure Impersonation**

Secure Impersonation is a feature that allows a user to make requests as another user in a secure way. For example, to allow the following impersonations:

- User hue can make requests as any user from any host.
- User foo can make requests as any member of group bar, from host1 or host2.

Configure the following properties in /etc/default/solr or /opt/cloudera/parcels/CDH-\*/etc/default/solr:

```
SOLR_SECURITY_ALLOWED_PROXYUSERS=hue, foo
SOLR_SECURITY_PROXYUSER_hue_HOSTS=*
SOLR_SECURITY_PROXYUSER_hue_GROUPS=*
SOLR_SECURITY_PROXYUSER_foo_HOSTS=host1,host2
SOLR_SECURITY_PROXYUSER_foo_GROUPS=bar
```

SOLR SECURITY ALLOWED PROXYUSERS lists all of the users allowed to impersonate. For a user x in SOLR SECURITY ALLOWED PROXYUSERS, SOLR SECURITY PROXYUSER x HOSTS list the hosts x is allowed to connect from in order to impersonate, and SOLR\_SECURITY\_PROXYUSERS\_X\_GROUPS lists the groups that the users is allowed to impersonate members of. Both GROUPS and HOSTS support the wildcard \* and both GROUPS and HOSTS must be defined for a specific user.

Note: Cloudera Manager has its own management of secure impersonation for Hue. To add additional users for Secure Impersonation, use the environment variable safety value for Solr to set the environment variables as above. Be sure to include hue in SOLR\_SECURITY\_ALLOWED\_PROXYUSERS if you want to use secure impersonation for hue.

## Debugging Failed Sentry Authorization Requests

Sentry logs all facts that lead up to authorization decisions at the debug level. If you do not understand why Sentry is denying access, the best way to debug is to temporarily turn on debug logging:

- In Cloudera Manager, add log4j.logger.org.apache.sentry=DEBUG to the logging settings for your service through the corresponding Logging Safety Valve field for the Impala, Hive Server 2, or Solr Server services.
- On systems not managed by Cloudera Manager, add log4j.logger.org.apache.sentry=DEBUG to the log4j.properties file on each host in the cluster, in the appropriate configuration directory for each service.

Specifically, look for exceptions and messages such as:

```
______
FilePermission server..., RequestPermission server..., result [true|false]
```

which indicate each evaluation Sentry makes. The FilePermission is from the policy file, while RequestPermission is the privilege required for the query. A RequestPermission will iterate over all appropriate FilePermission settings until a match is found. If no matching privilege is found, Sentry returns false indicating "Access Denied".

# Appendix: Authorization Privilege Model for Search

The tables below refer to the request handlers defined in the generated solrconfig.xml.secure. If you are not using this configuration file, the below may not apply.

admin is a special collection in sentry used to represent administrative actions. A non-administrative request may only require privileges on the collection on which the request is being performed. This is called collection1 in this appendix. An administrative request may require privileges on both the admin collection and collection1. This is denoted as admincollection1 in the tables below.

Table 28: Privilege table for non-administrative request handlers

Request Handler	Required Privilege	Collections that Require Privilege
select	QUERY	collection1
query	QUERY	collection1
get	QUERY	collection1
browse	QUERY	collection1
tvrh	QUERY	collection1
clustering	QUERY	collection1
terms	QUERY	collection1
elevate	QUERY	collection1
analysis/field	QUERY	collection1
analysis/document	QUERY	collection1
update	UPDATE	collection1
update/json	UPDATE	collection1
update/csv	UPDATE	collection1

Table 29: Privilege table for collections admin actions

Collection Action	Required Privilege	Collections that Require Privilege	
create	UPDATE	admin, collection1	
delete	UPDATE	admin, collection1	
reload	UPDATE	admin, collection1	
createAlias	UPDATE	admin, collection1  Note: collection1 here refers to the name of the alias, not the underlying collection(s). For example, http://YOUR-HOST:8983/solr/admin/collections?action=CREATEALIAS&name=collection1&collections=underlyingOblection	

# Authorization

Collection Action	Required Privilege	Collections that Require Privilege	
deleteAlias	UPDATE	admin, collection1	
		**Note: collection1 here refers to the name of the alias, not the underlying collection(s). For example, http://YOUR-HOST:8983/solr/admin/collections?action=DELETEALIAS&name=collection1	
syncShard	UPDATE	admin, collection1	
splitShard	UPDATE	admin, collection1	
deleteShard	UPDATE	admin, collection1	

Table 30: Privilege table for core admin actions

Collection Action	Required Privilege	Collections that Require Privilege
create	UPDATE	admin, collection1
rename	UPDATE	admin, collection1
load	UPDATE	admin, collection1
unload	UPDATE	admin, collection1
status	UPDATE	admin, collection1
persist	UPDATE	admin
reload	UPDATE	admin, collection1
swap	UPDATE	admin, collection1
mergeIndexes	UPDATE	admin, collection1
split	UPDATE	admin, collection1
prepRecover	UPDATE	admin, collection1
requestRecover	UPDATE	admin, collection1
requestSyncShard	UPDATE	admin, collection1
requestApplyUpdates	UPDATE	admin, collection1

Table 31: Privilege table for Info and AdminHandlers

Request Handler	Required Privilege	Collections that Require Privilege
LukeRequestHandler	QUERY	admin
SystemInfoHandler	QUERY	admin
SolrInfoMBeanHandler	QUERY	admin
PluginInfoHandler	QUERY	admin
ThreadDumpHandler	QUERY	admin
PropertiesRequestHandler	QUERY	admin

Request Handler	Required Privilege	Collections that Require Privilege
LogginHandler	QUERY, UPDATE (or *)	admin
ShowFileRequestHandler	QUERY	admin

# Configuring HBase Authorization

After you have configured HBase authentication as described in the previous section, you must establish authorization rules for the resources that a client is allowed to access. In this release, HBase only allows you to establish authorization rules on a column or table level. Authorization at the row or cell-level is supported starting in CDH 5.2.

# Understanding HBase Access Levels

HBase access levels are granted independently of each other and allow for different types of operations at a given scope.

- Read (R) can read data at the given scope
- Write (W) can write data at the given scope
- Execute (X) can execute coprocessor endpoints at the given scope
- Create (C) can create tables or drop tables (even those they did not create) at the given scope
- Admin (A) can perform cluster operations such as balancing the cluster or assigning regions at the given scope

### The possible scopes are:

- **Superuser** superusers can perform any operation available in HBase, to any resource. The user who runs HBase on your cluster is a superuser, as are any principals assigned to the configuration property hbase.superuser in hbase-site.xml on the HMaster.
- Global permissions granted at global scope allow the admin to operate on all tables of the cluster.
- Namespace permissions granted at namespace scope apply to all tables within a given namespace.
- Table permissions granted at table scope apply to data or metadata within a given table.
- ColumnFamily permissions granted at ColumnFamily scope apply to cells within that ColumnFamily.
- Cell permissions granted at Cell scope apply to that exact cell coordinate. This allows for policy evolution along with data. To change an ACL on a specific cell, write an updated cell with new ACL to the precise coordinates of the original. If you have a multi-versioned schema and want to update ACLs on all visible versions, you'll need to write new cells for all visible versions. The application has complete control over policy evolution. The exception is append and increment processing. Appends and increments can carry an ACL in the operation. If one is included in the operation, then it will be applied to the result of the append or increment. Otherwise, the ACL of the existing cell being appended to or incremented is preserved.

The combination of access levels and scopes creates a matrix of possible access levels that can be granted to a user. In a production environment, it is useful to think of access levels in terms of what is needed to do a specific job. The following list describes appropriate access levels for some common types of HBase users. It is important not to grant more access than is required for a given user to perform their required tasks.

- **Superusers** In a production system, only the HBase user should have superuser access. In a development environment, an administrator may need superuser access in order to quickly control and manage the cluster. However, this type of administrator should usually be a Global Admin rather than a superuser.
- Global Admins A global admin can perform tasks and access every table in HBase. In a typical production environment, an admin should not have Read or Write permissions to data within tables.
  - A global admin with Admin permissions can perform cluster-wide operations on the cluster, such as balancing, assigning or unassigning regions, or calling an explicit major compaction. This is an operations role.

### Authorization

 A global admin with Create permissions can create or drop any table within HBase. This is more of a DBA-type role.

In a production environment, it is likely that different users will have only one of Admin and Create permissions.

## Warning:

In the current implementation, a Global Admin with Admin permission can grant himself Read and Write permissions on a table and gain access to that table's data. For this reason, only grant Global Admin permissions to trusted user who actually need them.

Also be aware that a Global Admin with Create permission can perform a Put operation on the ACL table, simulating a grant or revoke and circumventing the authorization check for Global Admin permissions. This issue (but not the first one) is fixed in CDH 5.3 and newer, as well as CDH 5.2.1. It is not fixed in CDH 4.x or CDH 5.1.x.

Due to these issues, be cautious with granting Global Admin privileges.

- Namespace Admin a namespace admin with Create permissions can create or drop tables within that namespace, and take and restore snapshots. A namespace admin with Admin permissions can perform operations such as splits or major compactions on tables within that namespace. Prior to CDH 5.4, only global admins could create namespaces. In CDH 5.4, any user with Namespace Create privileges can create namespaces.
- Table Admins A table admin can perform administrative operations only on that table. A table admin with Create permissions can create snapshots from that table or restore that table from a snapshot. A table admin with Admin permissions can perform operations such as splits or major compactions on that table.
- Users Users can read or write data, or both. Users can also execute coprocessor endpoints, if given Executable permissions.

#### Important:

If you are using Kerberos principal names when setting ACLs for users, note that Hadoop uses only the first part (short) of the Kerberos principal when converting it to the user name. Hence, for the principal ann/fully.qualified.domain.name@YOUR-REALM.COM, HBase ACLs should only be set for user ann.

### Table 32: Real-World Example of Access Levels

This table shows some typical job descriptions at a hypothetical company and the permissions they might require in order to get their jobs done using HBase.

Job Title	Scope	Permissions	Description
Senior Administrator	Global	Access, Create	Manages the cluster and gives access to Junior Administrators.
Junior Administrator	Global	Create	Creates tables and gives access to Table Administrators.
Table Administrator	Table	Access	Maintains a table from an operations point of view.
Data Analyst	Table	Read	Creates reports from HBase data.

Job Title	Scope	Permissions	Description
Web Application	Table		Puts data into HBase and uses HBase data to perform operations.

### Further Reading

- Access Control Matrix
- Security Apache HBase Reference Guide

### **Enable HBase Authorization**

HBase authorization is built on top of the Coprocessors framework, specifically AccessController Coprocessor.

Note: Once the Access Controller coprocessor is enabled, any user who uses the HBase shell will be subject to access control. Access control will also be in effect for native (Java API) client access to HBase.

### Enable HBase Authorization Using Cloudera Manager

- 1. Go to Clusters and select the HBase cluster.
- 2. Select Configuration.
- 3. Search for HBase Secure Authorization and select it.
- 4. Optionally, search for and configure HBase Coprocessor Master Classes and HBase Coprocessor Region Classes.

### Enable HBase Authorization Using the Command Line

- Important:
  - If you use Cloudera Manager, do not use these command-line instructions.
  - This information applies specifically to CDH 5.4.x. If you use an earlier version of CDH, see the documentation for that version located at Cloudera Documentation.

To enable HBase authorization, add the following properties to the hbase-site.xml file on every HBase server host (Master or RegionServer):

```
cproperty>
    <name>hbase.security.authorization
    <value>true</value>
</property>
opertv>
     <name>hbase.coprocessor.master.classes
     <value>org.apache.hadoop.hbase.security.access.AccessController</value>
</property>
property>
     <name>hbase.coprocessor.region.classes</name>
<value>org.apache.hadoop.hbase.security.token.TokenProvider,org.apache.hadoop.hbase.security.access.AccessController
</property>
```

## Configure Access Control Lists for Authorization

Now that HBase has the security coprocessor enabled, you can set ACLs via the HBase shell. Start the HBase shell as usual.

### Authorization

#### Important:

The host running the shell must be configured with a keytab file as described in <u>Configuring Kerberos</u> Authentication for HBase.

The commands that control ACLs are of the form of:

```
grant <user> <permissions>[ [ <column family>[ <column qualifier> ] ]
#grants permissions
revoke <user> <permissions> [  [ <column family> [ <column qualifier> ] ]
# revokes permissions
user_permission  # displays existing permissions
```

In the above commands, fields encased in <> are variables, and fields in [] are optional. The permissions variable must consist of zero or more character from the set "RWCA".

- R denotes read permissions, which is required to perform Get, Scan, or Exists calls in a given scope.
- W denotes write permissions, which is required to perform Put, Delete, LockRow, UnlockRow, IncrementColumnValue, CheckAndDelete, CheckAndPut, Flush, Or Compact in a given scope.
- x denotes execute permissions, which is required to execute coprocessor endpoints.
- C denotes create permissions, which is required to perform Create, Alter, or Drop in a given scope.
- A denotes admin permissions, which is required to perform Enable, Disable, Snapshot, Restore, Clone, Split, MajorCompact, Grant, Revoke, and Shutdown in a given scope.

### For example:

```
grant 'user1', 'RWC'
grant 'user2', 'RW', 'tableA'
```

Be sure to review the information in <u>Understanding HBase Access Levels</u> on page 297 to understand the implications of the different access levels.

# Sensitive Data Redaction

Data redaction in Hadoop means suppressing data that is considered sensitive - for example, any Personally Identifiable Information (PII). Personally identifiable information (PII) is information that can be used on its own or with other information to identify or locate a single person, or to identify an individual in context. Enabling redaction on a cluster would allow you to transform such data to a pattern that does not contain any identifiable information. For example, you could replace all Social Security numbers (SSN) like 123-45-6789 with an unintelligible pattern like xxx-xx-xxxx, or replace only part of the SSN to be left with xxx-xx-6789.

While there are a few encryption techniques available to protect Hadoop data, the underlying problem with using encryption is that an admin who has complete access to the cluster will also have access to unencrypted sensitive user data. Additionally, even users with appropriate ACLs on the data could have access to logs and queries where the sensitive data might have leaked.

Introducing data redaction results in compliance with industry regulations such as PCI and HIPAA which require that the ability to view PII be restricted to only those users whose job requires them to have such access. PII or any other sensitive data should not be available through any other channels to users like cluster administrators or data analysts. However, note that if you already have the permissions to access PII through queries, the query results will not be redacted. Redaction only applies to any incidental leak of data. This means queries/query results must not show up in cleartext in places such as logs, configuration files or Uls.

### Scope

Data redaction in CDH 5.4 targets sensitive SQL data and log files. Currently, you can enable or disable this feature for the whole cluster with a simple HDFS service-wide configuration change. This feature has been implemented with the assumption that sensitive information resides in the data itself, not the metadata. Hence, if you enable redaction for a file, only sensitive data inside the file will be redacted. Metadata such as the name of the file, or name of the file-owner will not be subject to redaction. This assumption limits the scope of the feature by focussing on the data and not the metadata, since metadata such as table names or column names can be displayed in several places in the product, but the data itself is seldom displayed.

The following cluster components will be affected by enabling data redaction.

- HDFS and any dependant cluster services Logs will be redacted.
- Cloudera Navigator All audit data sent to Navigator will be redacted.
- Hue, Hive and Impala SQL query strings displayed by these services will be redacted.
  - **Note:** Log redaction is not available for Isilon-based clusters.

### **Redaction Rules**

Sensitive data redaction is based on pattern-matching. You can use regular expressions to define redaction rules that search for patterns of sensitive information such as Social Security numbers, credit card numbers, dates, and so on.

Rules can be configured using Cloudera Manager and have the following components:

- Search This is a regular expression that will be matched against the data. If the expression matches any part of the data, the match will be replaced by the contents of the "replace" string. For example, if you are redacting credit card numbers, your regular expression will be  $d\{4\}[^w]d\{4\}[^w]d\{4\}[^w]d\{4\}[^w]$
- Replace The string to be used to replace the data that will be redacted. For example, to replace any matched credit card digits with Xs, the replace string should be xxxx-xxxx-xxxx-xxxx.
- Trigger Trigger is an optional field. It can be used to specify a simple string which will be searched in the data. If the string is found, only then will the redactor attempt to find a match for the Search regex. If no Trigger is specified, redaction will always be carried out by matching the Search regular expression. The Trigger field exists solely for performance reasons: simple string matching is faster than regular expression matching.

### Sensitive Data Redaction

The following redaction rules are available pre-configured (not enabled) in Cloudera Manager. Note that the order in which the rules are specified matters. Hence, according to the list of rules below, credit card numbers will be redacted first, followed by SSNs, email addresses and finally, hostnames.

Redaction Rule	Search Expression	Replace Expression
Credit Card numbers (with separator)	\d{4}[^\w]\d{4}[^\w]\d{4}	XXXX-XXXX-XXXX
Social Security numbers (with separator)	\d{3}[^\w]\d{2}[^\w]\d{4}	XXX-XX-XXXX
Email addresses	######################################	email@redacted.host
Hostnames	\(\(\Az\)\\\\\\\\\\\\\\\\\\\\\\\\\\\\\\\	HOSTNAME.REDACTED

# Enabling Log and Query Redaction Using Cloudera Manager

Note: Do not enable redaction using Cloudera Manager's classic layout. Switch to the new layout for a better UI experience that allows you to add preconfigured redaction rules and test your rules inline.

Log and query redaction can be enabled cluster-wide using the following HDFS configuration properties:

- 1. Navigate to the HDFS service.
- 2. Click the Configuration tab.
- **3.** In the Search box, type *redaction* to bring up the following redaction properties.

Property	Description
Enable Log and Query Redaction	Check this property to enable log and query redaction for the cluster.
Log and Query Redaction Policy	List of rules to be followed for redacting sensitive information from log files and query strings. You can choose one of the pre-configured rules or add a custom rule.
	Test your rules by entering sample text into the <b>Test Redaction Rules</b> text box and click <b>Test Redaction</b> . If no rules match, the text you entered will be returned unchanged.

- **4.** Optionally, enter a reason for the configuration changes made.
- 5. Click Save Changes to commit the changes.
- 6. Restart the cluster.

# Configuring Cloudera Navigator to Redact Personally Identifiable Information

**Important:** This feature is superseded by cluster-wide redaction of logs and SQL queries, as described above. If you have already enabled redaction, you do not need to perform the steps described in this section. Use the following instructions only if you want to enable redaction for the Navigator Audit and Metadata servers only, and not cluster-wide.

This feature allows you to specify credit card number patterns (or other PII) that are masked in audit events, in the properties of entities displayed in lineage diagrams, and in information retrieved from the Audit Server database and the Metadata Server persistent storage. Redacting data other than credit card numbers is not

supported out-of-the-box. You may use a different regular expression to redact Social Security numbers or other PII.

Note: Masking is not applied to audit events and lineage entities that existed before the mask was enabled.

#### Required Role: Navigator Administrator **Full Administrator**

- 1. Do one of the following:
  - Select Clusters > Cloudera Management Service > Cloudera Management Service.
  - On the Status tab of the Home page, in Cloudera Management Service table, click the Cloudera Management Service link.
- 2. Click the Configuration tab.
- 3. Expand the Navigator Audit Server Default Group category.
- 4. Click the Advanced category.
- 5. Configure the PII Masking Regular Expression property with a regular expression that matches the credit card number formats to be masked. The default expression is:

```
(4[0-9]{12}(?:[0-9]{3})?)|(5[1-5][0-9]{14})|(3[47][0-9]{13})
 \big| \big( 3(?:0[0-5] \big| [68][0-9] \big) \big[ 0-9] \big\{ 11 \big\} \big) \big| \big( 6(?:011 \big| 5[0-9] \big\{ 2 \big\} \big) [0-9] \big\{ 12 \big\} \big) \big| \big( (?:2131 \big| 1800 \big| 35 \big) \big| \big( 11 \big\} \big) \big| \big( (3(2) 11 \big| 1800 \big| 1
```

which is constructed from the following subexpressions:

- Visa (4[0-9]{12}(?:[0-9]{3})?)
- MasterCard (5[1-5][0-9]{14})
- American Express (3[47][0-9]{13})
- Diners Club (3(?:0[0-5] | [68] [0-9]) [0-9] {11})
- Discover (6(?:011|5[0-9]{2})[0-9]{12})
- JCB ((?:2131|1800|35\\d{3})\\d{11})

If the property is left blank, PII information is not masked.

6. Click Save Changes to commit the changes.

# Overview of Impala Security

Impala includes a fine-grained authorization framework for Hadoop, based on the Sentry open source project. Sentry authorization was added in Impala 1.1.0. Together with the Kerberos authentication framework, Sentry takes Hadoop security to a new level needed for the requirements of highly regulated industries such as healthcare, financial services, and government. Impala also includes an auditing capability; Impala generates the audit data, the Cloudera Navigator product consolidates the audit data from all nodes in the cluster, and Cloudera Manager lets you filter, visualize, and produce reports. The auditing feature was added in Impala 1.1.1.

The security features of Cloudera Impala have several objectives. At the most basic level, security prevents accidents or mistakes that could disrupt application processing, delete or corrupt data, or reveal data to unauthorized users. More advanced security features and practices can harden the system against malicious users trying to gain unauthorized access or perform other disallowed operations. The auditing feature provides a way to confirm that no unauthorized access occurred, and detect whether any such attempts were made. This is a critical set of features for production deployments in large organizations that handle important or sensitive data. It sets the stage for multi-tenancy, where multiple applications run concurrently and are prevented from interfering with each other.

The material in this section presumes that you are already familiar with administering secure Linux systems. That is, you should know the general security practices for Linux and Hadoop, and their associated commands and configuration files. For example, you should know how to create Linux users and groups, manage Linux group membership, set Linux and HDFS file permissions and ownership, and designate the default permissions and ownership for new files. You should be familiar with the configuration of the nodes in your Hadoop cluster, and know how to apply configuration changes or run a set of commands across all the nodes.

The security features are divided into these broad categories:

#### authorization

Which users are allowed to access which resources, and what operations are they allowed to perform? Impala relies on the open source Sentry project for authorization. By default (when authorization is not enabled), Impala does all read and write operations with the privileges of the impala user, which is suitable for a development/test environment but not for a secure production environment. When authorization is enabled, Impala uses the OS user ID of the user who runs impala-shell or other client program, and associates various privileges with each user. See Enabling Sentry Authorization for Impala on page 276 for details about setting up and managing authorization.

### authentication

How does Impala verify the identity of the user to confirm that they really are allowed to exercise the privileges assigned to that user? Impala relies on the Kerberos subsystem for authentication. See Enabling Kerberos Authentication for Impala on page 104 for details about setting up and managing authentication.

### auditing

What operations were attempted, and did they succeed or not? This feature provides a way to look back and diagnose whether attempts were made to perform unauthorized operations. You use this information to track down suspicious activity, and to see where changes are needed in authorization policies. The audit data produced by this feature is collected by the Cloudera Manager product and then presented in a user-friendly form by the Cloudera Manager product. See Auditing Impala Operations for details about setting up and managing auditing.

These other topics in the Security Guide cover how Impala integrates with security frameworks such as Kerberos, LDAP, and Sentry:

- Impala Authentication on page 104
- Enabling Sentry Authorization for Impala on page 276

# Security Guidelines for Impala

The following are the major steps to harden a cluster running Impala against accidents and mistakes, or malicious attackers trying to access sensitive data:

- Secure the root account. The root user can tamper with the impalad daemon, read and write the data files in HDFS, log into other user accounts, and access other system services that are beyond the control of Impala.
- Restrict membership in the sudoers list (in the /etc/sudoers file). The users who can run the sudo command can do many of the same things as the root user.
- Ensure the Hadoop ownership and permissions for Impala data files are restricted.
- Ensure the Hadoop ownership and permissions for Impala log files are restricted.
- Ensure that the Impala web UI (available by default on port 25000 on each Impala node) is password-protected. See Impala Web User Interface for Debugging for details.
- Create a policy file that specifies which Impala privileges are available to users in particular Hadoop groups (which by default map to Linux OS groups). Create the associated Linux groups using the groupadd command if necessary.
- The Impala authorization feature makes use of the HDFS file ownership and permissions mechanism; for background information, see the CDH HDFS Permissions Guide. Set up users and assign them to groups at the OS level, corresponding to the different categories of users with different access levels for various databases, tables, and HDFS locations (URIs). Create the associated Linux users using the useradd command if necessary, and add them to the appropriate groups with the usermod command.
- Design your databases, tables, and views with database and table structure to allow policy rules to specify simple, consistent rules. For example, if all tables related to an application are inside a single database, you can assign privileges for that database and use the \* wildcard for the table name. If you are creating views with different privileges than the underlying base tables, you might put the views in a separate database so that you can use the \* wildcard for the database containing the base tables, while specifying the precise names of the individual views. (For specifying table or database names, you either specify the exact name or \* to mean all the databases on a server, or all the tables and views in a database.)
- Enable authorization by running the impalad daemons with the -server\_name and -authorization\_policy\_file options on all nodes. (The authorization feature does not apply to the statestored daemon, which has no access to schema objects or data files.)
- Set up authentication using Kerberos, to make sure users really are who they say they are.

# Securing Impala Data and Log Files

One aspect of security is to protect files from unauthorized access at the filesystem level. For example, if you store sensitive data in HDFS, you specify permissions on the associated files and directories in HDFS to restrict read and write permissions to the appropriate users and groups.

If you issue queries containing sensitive values in the WHERE clause, such as financial account numbers, those values are stored in Impala log files in the Linux filesystem and you must secure those files also. For the locations of Impala log files, see Using Impala Logging.

All Impala read and write operations are performed under the filesystem privileges of the impala user. The impala user must be able to read all directories and data files that you query, and write into all the directories and data files for INSERT and LOAD DATA statements. At a minimum, make sure the impala user is in the hive group so that it can access files and directories shared between Impala and Hive. See User Account Requirements for more details.

# Overview of Impala Security

Setting file permissions is necessary for Impala to function correctly, but is not an effective security practice by itself:

- The way to ensure that only authorized users can submit requests for databases and tables they are allowed to access is to set up Sentry authorization, as explained in <a href="Enabling Sentry Authorization for Impala">Enabling Sentry Authorization for Impala</a> on page 276. With authorization enabled, the checking of the user ID and group is done by Impala, and unauthorized access is blocked by Impala itself. The actual low-level read and write requests are still done by the impala user, so you must have appropriate file and directory permissions for that user ID.
- You must also set up Kerberos authentication, as described in <u>Enabling Kerberos Authentication for Impala</u> on page 104, so that users can only connect from trusted hosts. With Kerberos enabled, if someone connects a new host to the network and creates user IDs that match your privileged IDs, they will be blocked from connecting to Impala at all from that host.

# Installation Considerations for Impala Security

Impala 1.1 comes set up with all the software and settings needed to enable security when you run the impalad daemon with the new security-related options (-server\_name and -authorization\_policy\_file). You do not need to change any environment variables or install any additional JAR files. In a cluster managed by Cloudera Manager, you do not need to change any settings in Cloudera Manager.

# Securing the Hive Metastore Database

It is important to secure the Hive metastore, so that users cannot access the names or other information about databases and tables the through the Hive client or by querying the metastore database. Do this by turning on Hive metastore security, using the instructions in the <u>CDH 5 Security Guide</u> or the <u>CDH 4 Security Guide</u> for securing different Hive components:

- Secure the Hive Metastore.
- In addition, allow access to the metastore only from the HiveServer2 server, and then disable local access to the HiveServer2 server.

# Securing the Impala Web User Interface

The instructions in this section presume you are familiar with the <u>.htpasswd mechanism</u> commonly used to password-protect pages on web servers.

Password-protect the Impala web UI that listens on port 25000 by default. Set up a .htpasswd file in the \$IMPALA\_HOME directory, or start both the impalad and statestored daemons with the --webserver\_password\_file option to specify a different location (including the filename).

This file should only be readable by the Impala process and machine administrators, because it contains (hashed) versions of passwords. The username / password pairs are not derived from Unix usernames, Kerberos users, or any other system. The domain field in the password file must match the domain supplied to Impala by the new command-line option --webserver\_authentication\_domain. The default is mydomain.com.

Impala also supports using HTTPS for secure web traffic. To do so, set --webserver\_certificate\_file to refer to a valid .pem SSL certificate file. Impala will automatically start using HTTPS once the SSL certificate has been read and validated. A .pem file is basically a private key, followed by a signed SSL certificate; make sure to concatenate both parts when constructing the .pem file.

If Impala cannot find or parse the .pem file, it prints an error message and quits.

### Note:

If the private key is encrypted using a passphrase, Impala will ask for that passphrase on startup, which is not useful for a large cluster. In that case, remove the passphrase and make the .pem file readable only by Impala and administrators.

When you turn on SSL for the Impala web UI, the associated URLs change from http://prefixes to https://. Adjust any bookmarks or application code that refers to those URLs.

# Miscellaneous Topics

This section comprises miscellaneous security guide topics that you may find useful once you have secured your cluster with authentication, encryption and authorization techniques.

# Jsvc, Task Controller and Container Executor Programs

This section contains information about the following Hadoop security programs:

# MRv1 and YARN: The jsvc Program

The jsvc program is part of the bigtop-jsvc package and installed in either /usr/lib/bigtop-utils/jsvc or /usr/libexec/bigtop-utils/jsvc depending on the particular Linux flavor.

jsvc (more info) is used to start the DataNode listening on low port numbers. Its entry point is the SecureDataNodeStarter class, which implements the Daemon interface that jsvc expects. jsvc is run as root, and calls the SecureDataNodeStarter.init(...) method while running as root. Once the SecureDataNodeStarter class has finished initializing, jsvc sets the effective UID to be the hdfs user, and then calls SecureDataNodeStarter.start(...). SecureDataNodeStarter then calls the regular DataNode entry point, passing in a reference to the privileged resources it previously obtained.

## MRv1 Only: The Linux TaskController Program

A setuid binary called task-controller is part of the hadoop-0.20-mapreduce package and is installed in either /usr/lib/hadoop-0.20-mapreduce/sbin/Linux-amd64-64/task-controller or /usr/lib/hadoop-0.20-mapreduce/sbin/Linux-i386-32/task-controller.

This task-controller program, which is used on MRv1 only, allows the TaskTracker to run tasks under the Unix account of the user who submitted the job in the first place. It is a setuid binary that must have a very specific set of permissions and ownership in order to function correctly. In particular, it must:

- 1. Be owned by root
- 2. Be owned by a group that contains only the user running the MapReduce daemons
- 4. Be group readable and executable

This corresponds to the ownership root: mapred and the permissions 4754.

Here is the output of 1s on a correctly-configured Task-controller:

```
-rwsr-xr-- 1 root mapred 30888 Mar 18 13:03 task-controller
```

The TaskTracker will check for this configuration on start up, and fail to start if the Task-controller is not configured correctly.

## YARN Only: The Linux Container Executor Program

A setuid binary called container-executor is part of the hadoop-yarn package and is installed in /usr/lib/hadoop-yarn/bin/container-executor.

This container-executor program, which is used on YARN only and supported on GNU/Linux only, runs the containers as the user who submitted the application. It requires all user accounts to be created on the cluster nodes where the containers are launched. It uses a setuid executable that is included in the Hadoop distribution. The NodeManager uses this executable to launch and kill containers. The setuid executable switches to the user who has submitted the application and launches or kills the containers. For maximum security, this executor sets up restricted permissions and user/group ownership of local files and directories used by the containers

such as the shared objects, jars, intermediate files, log files, and so on. As a result, only the application owner and NodeManager can access any of the local files/directories including those localized as part of the distributed cache.

The container-executor program must have a very specific set of permissions and ownership in order to function correctly. In particular, it must:

- **1.** Be owned by root
- 2. Be owned by a group that contains only the user running the YARN daemons
- 4. Be group readable and executable

This corresponds to the ownership root: yarn and the permissions 6050.

--Sr-s--- 1 root yarn 91886 2012-04-01 19:54 container-executor

Important: Configuration changes to the Linux container executor could result in local NodeManager directories (such as usercache) being left with incorrect permissions. To avoid this, when making changes using either Cloudera Manager or the command line, first manually remove the existing NodeManager local directories from all configured local directories (yarn.nodemanager.local-dirs), and let the NodeManager recreate the directory structure.

### Task-controller and Container-executor Error Codes

When you set up a secure cluster for the first time and debug problems with it, the task-controller or container-executor may encounter errors. These programs communicate these errors to the TaskTracker or NodeManager daemon via numeric error codes which will appear in the TaskTracker or NodeManager logs respectively (/var/log/hadoop-mapreduce or /var/log/hadoop-yarn). The following sections list the possible numeric error codes with descriptions of what they mean:

- MRv1 ONLY: Task-controller Error Codes on page 309
- YARN ONLY: Container-executor Error Codes on page 311

### MRv1 ONLY: Task-controller Error Codes

The following table applies to the task-controller in MRv1.

Numeric Code	Name	Description
1	INVALID_ARGUMENT_NUMBER	<ul> <li>Incorrect number of arguments provided for the given task-controller command</li> <li>Failure to initialize the job localizer</li> </ul>
2	INVALID_USER_NAME	The user passed to the task-controller does not exist.
3	INVALID_COMMAND_PROVIDED	The task-controller does not recognize the command it was asked to execute.
4	SUPER_USER_NOT_ALLOWED_TO_RUN_TASKS	The user passed to the task-controller was the super user.
5	INVALID_TT_ROOT	The passed TaskTracker root does not match the configured TaskTracker root (mapred.local.dir), or does not exist.

# Miscellaneous Topics

Numeric Code	Name	Description
6	SETUID_OPER_FAILED	Either could not read the local groups database, or could not set UID or GID
7	UNABLE_TO_EXECUTE_TASK_SCRIPT	The task-controller could not execute the task launcher script.
8	UNABLE_TO_KILL_TASK	The task-controller could not kill the task it was passed.
9	INVALID_TASK_PID	The PID passed to the task-controller was negative or 0.
10	ERROR_RESOLVING_FILE_PATH	The task-controller couldn't resolve the path of the task launcher script file.
11	RELATIVE_PATH_COMPONENTS_IN_FILE_PATH	The path to the task launcher script file contains relative components (for example, "").
12	UNABLE_TO_STAT_FILE	The task-controller didn't have permission to stat a file it needed to check the ownership of.
13	FILE_NOT_OWNED_BY_TASKTRACKER	A file which the task-controller must change the ownership of has the wrong the ownership.
14	PREPARE_ATTEMPT_DIRECTORIES_FAILED	The mapred.local.dir is not configured, could not be read by the task-controller, or could not have its ownership secured.
15	INITIALIZE_JOB_FAILED	The task-controller couldn't get, stat, or secure the job directory or job working working directory.
16	PREPARE_TASK_LOGS_FAILED	The task-controller could not find or could not change the ownership of the task log directory to the passed user.
17	INVALID_TT_LOG_DIR	The hadoop.log.dir is not configured.
18	OUT_OF_MEMORY	The task-controller couldn't determine the job directory path or the task launcher script path.
19	INITIALIZE_DISTCACHEFILE_FAILED	Couldn't get a unique value for, stat, or the local distributed cache directory.
20	INITIALIZE_USER_FAILED	Couldn't get, stat, or secure the per-user task tracker directory.
21	UNABLE_TO_BUILD_PATH	The task-controller couldn't concatenate two paths, most likely because it ran out of memory.
22	INVALID_TASKCONTROLLER_PERMISSIONS	The task-controller binary does not have the correct permissions set. See Information about Other Hadoop Security Programs.
23	PREPARE_JOB_LOGS_FAILED	The task-controller could not find or could not change the ownership of the job log directory to the passed user.

Numeric Code	Name	Description
24	INVALID_CONFIG_FILE	The taskcontroller.cfg file is missing, malformed, or has incorrect permissions.
255	Unknown Error	There are several causes for this error. Some common causes are:  There are user accounts on your cluster that have a user ID less than the value specified for the min.user.id property in the taskcontroller.cfg file. The default value is 1000 which is appropriate on Ubuntu systems, but may not be valid for your operating system. For information about setting min.user.id in the taskcontroller.cfg file, see this step.  Jobs won't run and the TaskTracker is unable to create a Hadoop logs directory. For more information, see (MRv1 Only) Jobs won't run and TaskTracker is unable to create a Hadoop logs directory. on page 153.

# YARN ONLY: Container-executor Error Codes

The following table applies to the container-executor in YARN.

Numeric Code	Name	Description
1	INVALID_ARGUMENT_NUMBER	<ul> <li>Incorrect number of arguments provided for the given task-controller command</li> <li>Failure to initialize the container localizer</li> </ul>
2	INVALID_USER_NAME	The user passed to the task-controller does not exist.
3	INVALID_COMMAND_PROVIDED	The container-executor does not recognize the command it was asked to execute.
5	INVALID_NM_ROOT	The passed NodeManager root does not match the configured NodeManager root (yarn.nodemanager.local-dirs), or does not exist.
6	SETUID_OPER_FAILED	Either could not read the local groups database, or could not set UID or GID
7	UNABLE_TO_EXECUTE_CONTAINER_SCRIPT	The container-executor could not execute the container launcher script.
8	UNABLE_TO_SIGNAL_CONTAINER	The container-executor could not signal the container it was passed.

# Miscellaneous Topics

Numeric Code	Name	Description
9	INVALID_CONTAINER_PID	The PID passed to the container-executor was negative or 0.
18	OUT_OF_MEMORY	The container-executor couldn't allocate enough memory while reading the container-executor.cfg file, or while getting the paths for the container launcher script or credentials files.
20	INITIALIZE_USER_FAILED	Couldn't get, stat, or secure the per-user node manager directory.
21	UNABLE_TO_BUILD_PATH	The container-executor couldn't concatenate two paths, most likely because it ran out of memory.
22	INVALID_CONTAINER_EXEC_PERMISSIONS	The container-executor binary does not have the correct permissions set. See Appendix B - Information about Other Hadoop Security Programs.
24	INVALID_CONFIG_FILE	The container-executor.cfg file is missing, malformed, or has incorrect permissions.
25	SETSID_OPER_FAILED	Could not set the session ID of the forked container.
26	WRITE_PIDFILE_FAILED	Failed to write the value of the PID of the launched container to the PID file of the container.
255	Unknown Error	There are several causes for this error. Some common causes are:
		<ul> <li>There are user accounts on your cluster that have a user ID less than the value specified for the min.user.id property in the container-executor.cfg file. The default value is 1000 which is appropriate on Ubuntu systems, but may not be valid for your operating system. For information about setting min.user.id in the container-executor.cfg file, see this step.</li> <li>This error is often caused by previous errors; look earlier in the log file for possible causes.</li> </ul>

# Sqoop, Pig, and Whirr Security Support Status

Here is a summary of the status of security in the other CDH 5 components:

- Sqoop 1 and Pig support security with no configuration required.
- Whirr does not support security in CDH 5.

# Setting Up a Gateway Node to Restrict Cluster Access

Use the instructions that follow to set up and use a Hadoop cluster that is entirely firewalled off from outside access; the only exception will be one node which will act as a gateway. Client machines can access the cluster through the gateway via the REST API.

HttpFS will be used to allow REST access to HDFS, and Oozie will allow REST access for submitting and monitoring jobs.

# Installing and Configuring the Firewall and Gateway

Follow these steps:

- 1. Choose a cluster node to be the gateway machine
- 2. Install and configure the Oozie server by following the standard directions starting here: Installing Oozie
- 3. Install HttpFS.
- 4. Start the Oozie server:

```
$ sudo service oozie start
```

**5.** Start the HttpFS server:

```
$ sudo service hadoop-httpfs start
```

**6.** Configure firewalls.

Block all access from outside the cluster.

- The gateway node should have ports 11000 (oozie) and 14000 (hadoop-httpfs) open.
- Optionally, to maintain access to the Web Uls for the cluster's JobTrackers, NameNodes, etc., open their HTTP ports: see Ports Used by Components of CDH 5.
- 7. Optionally configure authentication in simple mode (default) or using Kerberos. See HttpFS Authentication on page 91 to configure Kerberos for HttpFS and Oozie Authentication on page 109 to configure Kerberos for
- 8. Optionally encrypt communication via HTTPS for Oozie by following these directions.

# **Accessing HDFS**

### With the Hadoop client:

All of the standard hadoop fs commands will work; just make sure to specify -fs webhdfs://HOSTNAME:14000. For example (where GATEWAYHOST is the hostname of the gateway machine):

```
$ hadoop fs -fs webhdfs://GATEWAYHOST:14000 -cat /user/me/myfile.txt
Hello World!
```

#### Without the Hadoop client:

You can run all of the standard hadoop fs commands by using the WebHDFS REST API and any program that can do GET, PUT, POST, and DELETE requests; for example:

```
$ curl "http://GATEWAYHOST:14000/webhdfs/v1/user/me/myfile.txt?op=OPEN&user.name=me"
Hello World!
```

• Important: Theuser.nameparameter is valid only if security is disabled. In a secure cluster, you must a initiate a valid Kerberos session.

### Miscellaneous Topics

In general, the command will look like this:

```
$ curl "http://GATEWAYHOST/webhdfs/v1/PATH?[user.name=USER&]op=..."
```

You can find a full explanation of the commands in the WebHDFS REST API documentation.

## Submitting and Monitoring Jobs

The Oozie REST API currently supports direct submission of MapReduce, Pig, and Hive jobs; Oozie will automatically create a workflow with a single action. For any other action types, or to execute anything more complicated than a single job, you will need to create an actual workflow. Any required files (e.g. JAR files, input data, etc.) must already exist on HDFS; if they don't, you can use HttpFS to upload the files.

#### With the Oozie client:

All of the standard Oozie commands will work. You can find a full explanation of the commands in the documentation for the <u>command-line utilities</u>.

#### Without the Oozie client:

You can run all of the standard Oozie commands by using the REST API and any program that can do GET, PUT, and POST requests. You can find a full explanation of the commands in the <u>Oozie Web Services API</u> documentation.

# Logging a Security Support Case

Before you log a support case, ensure you have either part or all of the following information to help Support investigate your case:

- If possible, provide a diagnostic data bundle following the instructions in <u>Collecting and Sending Diagnostic</u>
  Data to Cloudera.
- Provide details about the issue such as what was observed and what the impact was.
- Provide any error messages that were seen, using screen capture if necessary & attach to the case.
- If you were running a command or performing a series of steps, provide the commands and the results, captured to a file if possible.
- Specify whether the issue took place in a new install or a previously-working cluster.
- Mention any configuration changes made in the follow-up to the issue being seen.
- Specify the type of release environment the issue is taking place in, such as sandbox, development, or production.
- The severity of the impact and whether it is causing outage.

### Kerberos Issues

- For Kerberos issues, your krb5.conf and kdc.conf files are valuable for support to be able to understand your configuration.
- If you are having trouble with client access to the cluster, provide the output for klist -ef after kiniting as the user account on the client host in question. Additionally, confirm that your ticket is renewable by running kinit -R after successfully kiniting.
- Specify if you are authenticating (kiniting) with a user outside of the Hadoop cluster's realm (such as Active Directory, or another MIT Kerberos realm).
- If using AES-256 encryption, ensure you have the <u>Unlimited Strength JCE Policy Files</u> deployed on all cluster and client nodes.

### SSL/TLS Issues

- Specify whether you are using a private/commercial CA for your certificates, or if they are self-signed.
- Clarify what services you are attempting to setup SSL/TLS for in your description.

• When troubleshooting SSL/TLS trust issues, provide the output of the following openss1 command:

```
______,
openssl s_client -connect host.fqdn.name:port
```

### LDAP Issues

- Specify the LDAP service in use (Active Directory, OpenLDAP, one of Oracle Directory Server offerings, OpenDJ,
- Provide a screenshot of the LDAP configuration screen you are working with if you are troubleshooting setup
- Be prepared to troubleshoot using the ldapsearch command (requires the openIdap-clients package) on the host where LDAP authentication or authorization issues are being seen.