# IF2230 Virtual Memory

## Chapter 9: Virtual Memory

- Background
- Demand Paging
- Process Creation
- Page Replacement
- Allocation of Frames
- Thrashing
- Demand Segmentation
- Operating System Examples




#### Background

- Virtual memory separation of user logical memory from physical memory.
  - Only part of the program needs to be in memory for execution.
  - Logical address space can therefore be much larger than physical address space.
  - Allows address spaces to be shared by several processes.
  - Allows for more efficient process creation.
- Virtual memory can be implemented via:
  - Demand paging
  - Demand segmentation




# Virtual Memory That is Larger Than Physical Memory






#### Virtual-address Space

- Usually design logical address space for stack to start at Max logical address and grow "down" while heap grows "up"
  - Maximizes address space use
  - Unused address space between the two is hole
    - No physical memory needed until heap or stack grows to a given new page
- Enables sparse address spaces with holes left for growth, dynamically linked libraries, etc
- System libraries shared via mapping into virtual address space
- Shared memory by mapping pages readwrite into virtual address space
- Pages can be shared during fork(), speeding process creation





## Shared Library Using Virtual Memory






#### Demand Paging

- Bring a page into memory only when it is needed
  - Less I/O needed
  - Less memory needed
  - Faster response
  - More users
- ▶ Page is needed ⇒ reference to it
  - ▶ invalid reference ⇒ abort
  - ▶ not-in-memory  $\Rightarrow$  bring to memory



#### Transfer of a Paged Memory to Contiguous Disk Space





#### Valid-Invalid Bit


- With each page table entry a valid—invalid bit is associated ( $1 \Rightarrow$  in-memory,  $0 \Rightarrow$  not-in-memory)
- Initially valid—invalid but is set to 0 on all entries
- Example of a page table snapshot:

Frame #	valid-invalid b
	1
	1
	1
	0
:	
	0
	0
page table	<del></del> e

During address translation, if valid-invalid bit in page table entry is  $0 \Rightarrow$  page fault



#### Page Table When Some Pages Are Not in Main Memory






#### Page Fault

- If there is ever a reference to a page, first reference will trap to
   OS ⇒ page fault
- OS looks at another table to decide:
  - ▶ Invalid reference  $\Rightarrow$  abort.
  - Just not in memory.
- Get empty frame.
- Swap page into frame.
- Reset tables, validation bit = 1.
- Restart instruction: Least Recently Used



## Steps in Handling a Page Fault





#### What happens if there is no free frame?

- Page replacement find some page in memory, but not really in use, swap it out
  - algorithm
  - performance want an algorithm which will result in minimum number of page faults
- Same page may be brought into memory several times



#### Aspects of Demand Paging

- Extreme case start process with no pages in memory
  - OS sets instruction pointer to first instruction of process, non-memory-resident -> page fault
  - And for every other process pages on first access
  - Pure demand paging
- Actually, a given instruction could access multiple pages -> multiple page faults
  - Consider fetch and decode of instruction which adds 2 numbers from memory and stores result back to memory
  - Pain decreased because of locality of reference
- Hardware support needed for demand paging
  - Page table with valid / invalid bit
  - Secondary memory (swap device with swap space)
  - Instruction restart



## Performance of Demand Paging

- Stages in Demand Paging (worse case)
- 1. Trap to the operating system
- 2. Save the user registers and process state
- 3. Determine that the interrupt was a page fault
- 4. Check that the page reference was legal and determine the location of the page on the disk
- 5. Issue a read from the disk to a free frame:
  - Wait in a queue for this device until the read request is serviced
  - 2. Wait for the device seek and/or latency time
  - 3. Begin the transfer of the page to a free frame
- 6. While waiting, allocate the CPU to some other user
- 7. Receive an interrupt from the disk I/O subsystem (I/O completed)
- 8. Save the registers and process state for the other user
- 9. Determine that the interrupt was from the disk
- 10. Correct the page table and other tables to show page is now in memory
- 11. Wait for the CPU to be allocated to this process again
- 12. Restore the user registers, process state, and new page table, and then resume the interrupted instruction

#### Performance of Demand Paging

- ▶ Page Fault Rate  $0 \le p \le 1.0$ 
  - if p = 0 no page faults
  - $\triangleright$  if p = 1, every reference is a fault
- Effective Access Time (EAT)

```
EAT = (I - p) \times memory access
```

- + p (page fault overhead
- + [swap page out ]
- + swap page in
- + restart overhead)



#### Demand Paging Example

- Memory access time = 200 nanoseconds
- Average page-fault service time = 8 milliseconds
- ► EAT =  $(I p) \times 200 + p$  (8 milliseconds) =  $(I - p \times 200 + p \times 8,000,000$ =  $200 + p \times 7,999,800$
- If one access out of 1,000 causes a page fault, then EAT = 8.2 microseconds.

This is a slowdown by a factor of 40!!

- ▶ If want performance degradation < 10 percent
  - 220 > 200 + 7,999,800 x p 20 > 7,999,800 x p
  - P < .0000025
  - one page fault in every 400,000 memory accesses



#### Demand Paging Optimizations

- Swap space I/O faster than file system I/O even if on the same device
  - > Swap allocated in larger chunks, less management needed than file system
- Copy entire process image to swap space at process load time
  - Then page in and out of swap space
  - Used in older BSD Unix
- Demand page in from program binary on disk, but discard rather than paging out when freeing frame
  - Used in Solaris and current BSD
  - Still need to write to swap space
    - ▶ Pages not associated with a file (like stack and heap) anonymous memory
    - Pages modified in memory but not yet written back to the file system
- Mobile systems
  - Typically don't support swapping
  - Instead, demand page from file system and reclaim read-only pages (such as code)




#### Copy-on-Write

- Copy-on-Write (COW) allows both parent and child processes to initially share the same pages in memory
  - If either process modifies a shared page, only then is the page copied
- COW allows more efficient process creation as only modified pages are copied
- In general, free pages are allocated from a pool of zero-fill-on-demand pages
  - Pool should always have free frames for fast demand page execution
    - Don't want to have to free a frame as well as other processing on page fault
  - Why zero-out a page before allocating it?
- vfork() variation on fork() system call has parent suspend and child using copy-on-write address space of parent
  - Designed to have child call exec ()
  - Very efficient




#### Before Process 1 Modifies Page C





#### After Process 1 Modifies Page C





#### What Happens if There is no Free Frame?

- Used up by process pages
- ▶ Also in demand from the kernel, I/O buffers, etc
- How much to allocate to each?
- Page replacement find some page in memory, but not really in use, page it out
  - Algorithm terminate? swap out? replace the page?
  - Performance want an algorithm which will result in minimum number of page faults
- Same page may be brought into memory several times




## Page Replacement

- Prevent over-allocation of memory by modifying pagefault service routine to include page replacement
- Use modify (dirty) bit to reduce overhead of page transfers – only modified pages are written to disk
- Page replacement completes separation between logical memory and physical memory – large virtual memory can be provided on a smaller physical memory



## Need For Page Replacement






#### Basic Page Replacement

- I. Find the location of the desired page on disk
- 2. Find a free frame:
  - If there is a free frame, use it
  - If there is no free frame, use a page replacement algorithm to select a **victim** frame
- 3. Read the desired page into the (newly) free frame. Update the page and frame tables.
- 4. Restart the process



## Page Replacement






#### Page Replacement Algorithms

- Frame-allocation algorithm determines
  - How many frames to give each process
  - Which frames to replace
- Want lowest page-fault rate
- Evaluate algorithm by running it on a particular string of memory references (reference string) and computing the number of page faults on that string
- In all our examples, the reference string is I, 2, 3, 4, I, 2, 5, I, 2, 3, 4, 5



#### Graph of Page Faults Versus The Number of Frames





## First-In-First-Out (FIFO) Algorithm


- Reference string: 1, 2, 3, 4, 1, 2, 5, 1, 2, 3, 4, 5
- > 3 frames (3 pages can be in memory at a time per process)

4 frames

1	1	4	5	
2	2	1	3	9 page faults
3	3	2	4	


- ▶ FIFO Replacement Belady's Anomaly
  - ightharpoonup more frames  $\Rightarrow$  more page faults

#### FIFO Page Replacement





# FIFO Illustrating Belady's Anomaly





#### Optimal Algorithm


- Replace page that will not be used for longest period of time
- 4 frames example

1	4	
2		6 page faults
3		
4	5	

- How do you know this?
- Used for measuring how well your algorithm performs




#### Optimal Page Replacement





#### Least Recently Used (LRU) Algorithm

▶ Reference string: 1, 2, 3, 4, 1, 2, 5, 1, 2, 3, 4, 5




#### Counter implementation

- Every page entry has a counter; every time page is referenced through this entry, copy the clock into the counter
- When a page needs to be changed, look at the counters to determine which are to change



## LRU Page Replacement






#### LRU Algorithm (Cont.)

- Stack implementation keep a stack of page numbers in a double link form:
  - Page referenced:
    - move it to the top
    - requires 6 pointers to be changed
  - No search for replacement



#### Use Of A Stack to Record The Most Recent Page References





#### LRU Approximation Algorithms

#### Reference bit


- With each page associate a bit, initially = 0
- When page is referenced bit set to I
- Replace the one which is 0 (if one exists). We do not know the order, however.

#### Second chance

- Need reference bit
- Clock replacement
- If page to be replaced (in clock order) has reference bit = 1 then:
  - set reference bit 0
  - leave page in memory
  - replace next page (in clock order), subject to same rules



#### Second-Chance (clock) Page-Replacement Algorithm





# Counting Algorithms

- Keep a counter of the number of references that have been made to each page
- LFU Algorithm: replaces page with smallest count
- MFU Algorithm: based on the argument that the page with the smallest count was probably just brought in and has yet to be used



#### Allocation of Frames

- ▶ Each process needs *minimum* number of pages
- ► Example: IBM 370 6 pages to handle SS MOVE instruction:
  - instruction is 6 bytes, might span 2 pages
  - 2 pages to handle from
  - 2 pages to handle to
- Two major allocation schemes
  - fixed allocation
  - priority allocation



#### Fixed Allocation

- Equal allocation For example, if there are 100 frames and 5 processes, give each process 20 frames.
- Propositional allocate according to the size of process
  - -m = total number of frames

$$-a_i =$$
allocation for  $p_i = \frac{s_i}{S} \times m$ 

$$m = 64$$

$$s_i = 10$$

$$s_2 = 127$$

$$a_1 = \frac{10}{137} \times 64 \approx 5$$

$$a_2 = \frac{127}{137} \times 64 \approx 59$$



## **Priority Allocation**

- Use a proportional allocation scheme using priorities rather than size
- $\blacktriangleright$  If process  $P_i$  generates a page fault,
  - select for replacement one of its frames
  - select for replacement a frame from a process with lower priority number



#### Global vs. Local Allocation

- ▶ Global replacement process selects a replacement frame from the set of all frames; one process can take a frame from another
- ► Local replacement each process selects from only its own set of allocated frames




## Thrashing

- If a process does not have "enough" pages, the page-fault rate is very high. This leads to:
  - low CPU utilization
  - operating system thinks that it needs to increase the degree of multiprogramming
  - another process added to the system
- Thrashing ≡ a process is busy swapping pages in and out



# Thrashing (Cont.)






# Demand Paging and Thrashing

- Why does demand paging work? Locality model
  - Process migrates from one locality to another
  - Localities may overlap
- Why does thrashing occur?  $\Sigma$  size of locality > total memory size




#### Locality In A Memory-Reference Pattern



# Working-Set Model

- ▶  $\Delta$  = working-set window = a fixed number of page references Example: 10,000 instruction
- WSS<sub>i</sub> (working set of Process  $P_i$ ) = total number of pages referenced in the most recent  $\Delta$  (varies in time)
  - ightharpoonup if  $\Delta$  too small will not encompass entire locality
  - ightharpoonup if  $\Delta$  too large will encompass several localities
  - if  $\Delta = \infty \Rightarrow$  will encompass entire program
- ▶  $D = \sum WSS_i \equiv \text{total demand frames}$
- if  $D > m \Rightarrow Thrashing$
- Policy if D > m, then suspend one of the processes

# Working-set model






# Keeping Track of the Working Set

- Approximate with interval timer + a reference bit
- $\triangleright$  Example:  $\triangle = 10,000$ 
  - ▶ Timer interrupts after every 5000 time units
  - Keep in memory 2 bits for each page
  - Whenever a timer interrupts copy and sets the values of all reference bits to 0
  - If one of the bits in memory =  $I \Rightarrow page$  in working set
- Why is this not completely accurate?
- Improvement = 10 bits and interrupt every 1000 time units



## Page-Fault Frequency Scheme

- Establish "acceptable" page-fault rate
  - If actual rate too low, process loses frame
  - If actual rate too high, process gains frame






## Memory-Mapped Files

- Memory-mapped file I/O allows file I/O to be treated as routine memory access by mapping a disk block to a page in memory
- A file is initially read using demand paging. A page-sized portion of the file is read from the file system into a physical page. Subsequent reads/writes to/from the file are treated as ordinary memory accesses.
- Simplifies file access by treating file I/O through memory rather than read() write() system calls
- Also allows several processes to map the same file

# Memory Mapped Files





#### Memory-Mapped Files in Java

```
import java.io.*;
import java.nio.*;
import java.nio.channels.*;
public class MemoryMapReadOnly
   // Assume the page size is 4 KB
   public static final int PAGE SIZE = 4096;
   public static void main(String args∏) throws IOException {
           RandomAccessFile inFile = new RandomAccessFile(args[0],"r");
           FileChannel in = inFile.getChannel();
           MappedByteBuffer mappedBuffer =
            in.map(FileChannel.MapMode.READ ONLY, 0, in.size());
           long numPages = in.size() / (long)PAGE SIZE;
           if (in.size() % PAGE SIZE > 0)
                      ++numPages;
```



#### Memory-Mapped Files in Java (cont)

```
// we will "touch" the first byte of every page
       int position = 0;
       for (long i = 0; i < numPages; i++) {
              byte item = mappedBuffer.get(position);
              position += PAGE SIZE;
       in.close();
       inFile.close();
▶ The API for the map() method is as follows:
```

map(mode, position, size)

# Other Issues -- Prepaging

#### Prepaging

- To reduce the large number of page faults that occurs at process startup
- Prepage all or some of the pages a process will need, before they are referenced
- But if prepaged pages are unused, I/O and memory was wasted
- Assume s pages are prepaged and  $\alpha$  of the pages is used
  - Is cost of s \* α save pages faults > or < than the cost of prepaging s \* (I-α) unnecessary pages?</p>
  - $\triangleright \alpha$  near zero  $\Rightarrow$  prepaging loses



## Other Issues – Page Size

- Page size selection must take into consideration:
  - fragmentation
  - table size
  - ▶ I/O overhead
  - locality



#### Other Issues - TLB Reach

- TLB Reach The amount of memory accessible from the TLB
- ▶ TLB Reach = (TLB Size) X (Page Size)
- Ideally, the working set of each process is stored in the TLB. Otherwise there is a high degree of page faults.
- Increase the Page Size. This may lead to an increase in fragmentation as not all applications require a large page size
- Provide Multiple Page Sizes. This allows applications that require larger page sizes the opportunity to use them without an increase in fragmentation

## Other Issues – Program Structure

#### Program structure

- Int[128,128] data;
- Each row is stored in one page
- Program I

$$128 \times 128 = 16,384$$
 page faults

Program 2




# Other Issues – I/O interlock

- I/O Interlock Pages must sometimes be locked into memory
- Consider I/O. Pages that are used for copying a file from a device must be locked from being selected for eviction by a page replacement algorithm.



# Reason Why Frames Used For I/O Must Be In Memory





# Operating System Examples

Windows XP

Solaris



#### Windows XP


- Uses demand paging with clustering. Clustering brings in pages surrounding the faulting page.
- Processes are assigned working set minimum and working set maximum
- Working set minimum is the minimum number of pages the process is guaranteed to have in memory
- A process may be assigned as many pages up to its working set maximum
- When the amount of free memory in the system falls below a threshold, automatic working set trimming is performed to restore the amount of free memory
- Working set trimming removes pages from processes that
- have pages in excess of their working set minimum

#### Solaris

- Maintains a list of free pages to assign faulting processes
- Lotsfree threshold parameter (amount of free memory) to begin paging
- Desfree threshold parameter to increasing paging
- Minfree threshold parameter to being swapping
- Paging is performed by pageout process
- Pageout scans pages using modified clock algorithm
- Scanrate is the rate at which pages are scanned. This ranges from slowscan to fastscan
- Pageout is called more frequently depending upon the amount of free memory available



# Solaris 2 Page Scanner





End of Chapter 9