
# **Chapter 8: Main Memory**





# **Chapter 8: Memory Management**

- Background
- Swapping
- Contiguous Memory Allocation
- Segmentation
- Paging
- Structure of the Page Table
- Example: The Intel 32 and 64-bit Architectures
- Example: ARM Architecture





### **Objectives**

- To provide a detailed description of various ways of organizing memory hardware
- To discuss various memory-management techniques, including paging and segmentation
- To provide a detailed description of the Intel Pentium, which supports both pure segmentation and segmentation with paging




# **Background**

- Program must be brought (from disk) into memory and placed within a process for it to be run
- Main memory and registers are only storage CPU can access directly
- Memory unit only sees a stream of addresses + read requests, or address + data and write requests
- Register access in one CPU clock (or less)
- Main memory can take many cycles, causing a stall
- Cache sits between main memory and CPU registers
- Protection of memory required to ensure correct operation



#### **Base and Limit Registers**


- A pair of base and limit registers define the logical address space
- CPU must check every memory access generated in user mode to be sure it is between base and limit for that user







#### **Hardware Address Protection**







### **Address Binding**

- Programs on disk, ready to be brought into memory to execute form an **input queue** 
  - Without support, must be loaded into address 0000
- Inconvenient to have first user process physical address always at 0000
  - How can it not be?
- Further, addresses represented in different ways at different stages of a program's life
  - Source code addresses usually symbolic
  - Compiled code addresses **bind** to relocatable addresses
    - 4 i.e. "14 bytes from beginning of this module"
  - Linker or loader will bind relocatable addresses to absolute addresses
    - 4 i.e. 74014
  - Each binding maps one address space to another






#### **Binding of Instructions and Data to Memory**

- Address binding of instructions and data to memory addresses can happen at three different stages
  - Compile time: If memory location known a priori, absolute code can be generated; must recompile code if starting location changes
  - Load time: Must generate relocatable code if memory location is not known at compile time
  - **Execution time**: Binding delayed until run time if the process can be moved during its execution from one memory segment to another
    - 4 Need hardware support for address maps (e.g., base and limit registers)





#### **Multistep Processing of a User Program**





### Logical vs. Physical Address Space

- The concept of a logical address space that is bound to a separate physical address space is central to proper memory management
  - Logical address generated by the CPU; also referred to as virtual address
  - Physical address address seen by the memory unit
- Logical and physical addresses are the same in compile-time and load-time address-binding schemes; logical (virtual) and physical addresses differ in execution-time address-binding scheme
- Logical address space is the set of all logical addresses generated by a program
- Physical address space is the set of all physical addresses generated by a program





# Memory-Management Unit (MMU)


- Hardware device that at run time maps virtual to physical address
- Many methods possible, covered in the rest of this chapter
- To start, consider simple scheme where the value in the relocation register is added to every address generated by a user process at the time it is sent to memory
  - Base register now called relocation register
  - MS-DOS on Intel 80x86 used 4 relocation registers
- The user program deals with *logical* addresses; it never sees the *real* physical addresses
  - Execution-time binding occurs when reference is made to location in memory
  - Logical address bound to physical addresses






#### Dynamic relocation using a relocation register

- Routine is not loaded until it is called
- Better memory-space utilization; unused routine is never loaded
- All routines kept on disk in relocatable load format
- Useful when large amounts of code are needed to handle infrequently occurring cases
- No special support from the operating system is required
  - Implemented through program design
  - OS can help by providing libraries to implement dynamic loading








# **Dynamic Linking**

- Static linking system libraries and program code combined by the loader into the binary program image
- Dynamic linking –linking postponed until execution time
- Small piece of code, **stub**, used to locate the appropriate memory-resident library routine
- Stub replaces itself with the address of the routine, and executes the routine
- Operating system checks if routine is in processes' memory address
  - If not in address space, add to address space
- Dynamic linking is particularly useful for libraries
- System also known as shared libraries
- Consider applicability to patching system libraries
  - Versioning may be needed





# **Swapping**

- A process can be **swapped** temporarily out of memory to a backing store, and then brought back into memory for continued execution
  - Total physical memory space of processes can exceed physical memory
- Backing store fast disk large enough to accommodate copies of all memory images for all users; must provide direct access to these memory images
- Roll out, roll in swapping variant used for priority-based scheduling algorithms; lower-priority process is swapped out so higher-priority process can be loaded and executed
- Major part of swap time is transfer time; total transfer time is directly proportional to the amount of memory swapped
- System maintains a ready queue of ready-to-run processes which have memory images on disk






# **Swapping (Cont.)**

- Does the swapped out process need to swap back in to same physical addresses?
- Depends on address binding method
  - Plus consider pending I/O to / from process memory space
- Modified versions of swapping are found on many systems (i.e., UNIX, Linux, and Windows)
  - Swapping normally disabled
  - Started if more than threshold amount of memory allocated
  - Disabled again once memory demand reduced below threshold





# **Schematic View of Swapping**



main memory





#### **Context Switch Time including Swapping**

- If next processes to be put on CPU is not in memory, need to swap out a process and swap in target process
- Context switch time can then be very high
- 100MB process swapping to hard disk with transfer rate of 50MB/sec
  - Swap out time of 2000 ms
  - Plus swap in of same sized process
  - Total context switch swapping component time of 4000ms (4) seconds)
- Can reduce if reduce size of memory swapped by knowing how much memory really being used
  - System calls to inform OS of memory use via request memory() and release memory()





#### **Context Switch Time and Swapping (Cont.)**

- Other constraints as well on swapping
  - Pending I/O can't swap out as I/O would occur to wrong process
  - Or always transfer I/O to kernel space, then to I/O device
    - 4 Known as **double buffering**, adds overhead
- Standard swapping not used in modern operating systems
  - But modified version common
    - 4 Swap only when free memory extremely low





# **Swapping on Mobile Systems**

- Not typically supported
  - Flash memory based
    - 4 Small amount of space
    - 4 Limited number of write cycles
    - 4 Poor throughput between flash memory and CPU on mobile platform
- Instead use other methods to free memory if low
  - iOS asks apps to voluntarily relinquish allocated memory
    - 4 Read-only data thrown out and reloaded from flash if needed
    - 4 Failure to free can result in termination
  - Android terminates apps if low free memory, but first writes application state to flash for fast restart
  - Both OSes support paging as discussed below





### **Contiguous Allocation**

- Main memory must support both OS and user processes
- Limited resource, must allocate efficiently
- Contiguous allocation is one early method
- Main memory usually into two **partitions**:
  - Resident operating system, usually held in low memory with interrupt vector
  - User processes then held in high memory
  - Each process contained in single contiguous section of memory






# **Contiguous Allocation (Cont.)**

- Relocation registers used to protect user processes from each other, and from changing operating-system code and data
  - Base register contains value of smallest physical address
  - Limit register contains range of logical addresses each logical address must be less than the limit register
  - MMU maps logical address *dynamically*
  - Can then allow actions such as kernel code being **transient** and kernel changing size





#### **Hardware Support for Relocation and Limit Registers**








#### Multiple-partition allocation

- Multiple-partition allocation
  - Degree of multiprogramming limited by number of partitions
  - Variable-partition sizes for efficiency (sized to a given process' needs)
  - Hole block of available memory; holes of various size are scattered throughout memory
  - When a process arrives, it is allocated memory from a hole large enough to accommodate it
  - Process exiting frees its partition, adjacent free partitions combined
  - Operating system maintains information about:
     a) allocated partitions
     b) free partitions (hole)





# **Dynamic Storage-Allocation Problem**

How to satisfy a request of size *n* from a list of free holes?

- First-fit: Allocate the *first* hole that is big enough
- Best-fit: Allocate the *smallest* hole that is big enough; must search entire list, unless ordered by size
  - Produces the smallest leftover hole
- Worst-fit: Allocate the *largest* hole; must also search entire list
  - Produces the largest leftover hole

First-fit and best-fit better than worst-fit in terms of speed and storage utilization






#### **Fragmentation**

- External Fragmentation total memory space exists to satisfy a request, but it is not contiguous
- Internal Fragmentation allocated memory may be slightly larger than requested memory; this size difference is memory internal to a partition, but not being used
- First fit analysis reveals that given N blocks allocated, 0.5 N blocks lost to fragmentation
  - 1/3 may be unusable -> 50-percent rule





# **Fragmentation (Cont.)**

- Reduce external fragmentation by compaction
  - Shuffle memory contents to place all free memory together in one large block
  - Compaction is possible *only* if relocation is dynamic, and is done at execution time
  - I/O problem
    - 4 Latch job in memory while it is involved in I/O
    - 4 Do I/O only into OS buffers
- Now consider that backing store has same fragmentation problems





### **Segmentation**


- Memory-management scheme that supports user view of memory
- A program is a collection of segments
  - A segment is a logical unit such as:

```
main program
procedure
function
method
object
local variables, global variables
common block
stack
symbol table
arrays
```






# **User's View of a Program**








# **Logical View of Segmentation**



3

physical memory space





#### **Segmentation Architecture**

- Logical address consists of a two tuple:
   <segment-number, offset>,
- Segment table maps two-dimensional physical addresses; each table entry has:
  - base contains the starting physical address where the segments reside in memory
  - **limit** specifies the length of the segment
- Segment-table base register (STBR) points to the segment table's location in memory
- Segment-table length register (STLR) indicates number of segments used by a program;

segment number s is legal if s < STLR






# **Segmentation Architecture (Cont.)**

- Protection
  - With each entry in segment table associate:
    - 4 validation bit =  $0 \Rightarrow$  illegal segment
    - 4 read/write/execute privileges
- Protection bits associated with segments; code sharing occurs at segment level
- Since segments vary in length, memory allocation is a dynamic storage-allocation problem
- A segmentation example is shown in the following diagram





### **Segmentation Hardware**








# **Paging**

- Physical address space of a process can be noncontiguous; process is allocated physical memory whenever the latter is available
  - Avoids external fragmentation
  - Avoids problem of varying sized memory chunks
- Divide physical memory into fixed-sized blocks called frames
  - Size is power of 2, between 512 bytes and 16 Mbytes
- Divide logical memory into blocks of same size called pages
- Keep track of all free frames
- To run a program of size N pages, need to find N free frames and load program
- Set up a page table to translate logical to physical addresses
- Backing store likewise split into pages
- Still have Internal fragmentation





#### **Address Translation Scheme**


- Address generated by CPU is divided into:
  - Page number (p) used as an index into a page table which contains base address of each page in physical memory
  - Page offset (d) combined with base address to define the physical memory address that is sent to the memory unit

р	pag e	0	f
р	d		
<b>m</b> -	n		

For given logical address space  $2^m$  and page size  $2^n$ 




# **Paging Hardware**








#### Paging Model of Logical and Physical Memory






#### **Paging Example**



n=2 and m=4 32-byte memory and 4-byte pages




### Paging (Cont.)

- Calculating internal fragmentation
  - Page size = 2,048 bytes
  - Process size = 72,766 bytes
  - 35 pages + 1,086 bytes
  - Internal fragmentation of 2,048 1,086 = 962 bytes
  - Worst case fragmentation = 1 frame -1 byte
  - On average fragmentation = 1 / 2 frame size
  - So small frame sizes desirable?
  - But each page table entry takes memory to track
  - Page sizes growing over time
    - 4 Solaris supports two page sizes 8 KB and 4 MB
- Process view and physical memory now very different
- By implementation process can only access its own memory





#### **Free Frames**



Before allocation

After allocation





#### Implementation of Page Table

- Page table is kept in main memory
- Page-table base register (PTBR) points to the page table
- Page-table length register (PTLR) indicates size of the page table
- In this scheme every data/instruction access requires two memory accesses
  - One for the page table and one for the data / instruction
- The two memory access problem can be solved by the use of a special fast-lookup hardware cache called associative memory or translation look-aside buffers (TLBs)





### Implementation of Page Table (Cont.)

- Some TLBs store address-space identifiers (ASIDs) in each TLB entry – uniquely identifies each process to provide address-space protection for that process
  - Otherwise need to flush at every context switch
- TLBs typically small (64 to 1,024 entries)
- On a TLB miss, value is loaded into the TLB for faster access next time
  - Replacement policies must be considered
  - Some entries can be wired down for permanent fast access





#### **Associative Memory**


• Associative memory – parallel search

Page #	Frame #


- Address translation (p, d)
  - If p is in associative register, get frame # out
  - Otherwise get frame # from page table in memory



## **Paging Hardware With TLB**







#### **Effective Access Time**

- Associative Lookup =  $\varepsilon$  time unit
  - Can be < 10% of memory access time
- Hit ratio =  $\alpha$ 
  - Hit ratio percentage of times that a page number is found in the associative registers; ratio related to number of associative registers
- Consider  $\alpha = 80\%$ ,  $\epsilon = 20$ ns for TLB search, 100ns for memory access
- Effective Access Time (EAT)

EAT = 
$$(1 + \varepsilon) \alpha + (2 + \varepsilon)(1 - \alpha)$$
  
=  $2 + \varepsilon - \alpha$ 

- Consider  $\alpha = 80\%$ ,  $\varepsilon = 20$ ns for TLB search, 100ns for memory access
  - EAT =  $0.80 \times 100 + 0.20 \times 200 = 120 \text{ns}$
- Consider more realistic hit ratio ->  $\alpha = 99\%$ ,  $\epsilon = 20$ ns for TLB search, 100ns for memory access
  - EAT =  $0.99 \times 100 + 0.01 \times 200 = 101 \text{ns}$






### **Memory Protection**

- Memory protection implemented by associating protection bit with each frame to indicate if read-only or read-write access is allowed
  - Can also add more bits to indicate page execute-only, and so on
- Valid-invalid bit attached to each entry in the page table:
  - "valid" indicates that the associated page is in the process' logical address space, and is thus a legal page
  - "invalid" indicates that the page is not in the process' logical address space
  - Or use page-table length register (PTLR)
- Any violations result in a trap to the kernel





#### Valid (v) or Invalid (i) Bit In A Page Table







#### **Shared Pages**

#### Shared code

- One copy of read-only (reentrant) code shared among processes (i.e., text editors, compilers, window systems)
- Similar to multiple threads sharing the same process space
- Also useful for interprocess communication if sharing of read-write pages is allowed


#### Private code and data

- Each process keeps a separate copy of the code and data
- The pages for the private code and data can appear anywhere in the logical address space





#### **Shared Pages Example**





#### **Structure of the Page Table**

- Memory structures for paging can get huge using straight-forward methods
  - Consider a 32-bit logical address space as on modern computers
  - Page size of 4 KB (2<sup>12</sup>)
  - Page table would have 1 million entries  $(2^{32} / 2^{12})$
  - If each entry is 4 bytes -> 4 MB of physical address space / memory for page table alone
    - 4 That amount of memory used to cost a lot
    - 4 Don't want to allocate that contiguously in main memory
- Hierarchical Paging
- Hashed Page Tables
- Inverted Page Tables






#### **Hierarchical Page Tables**

- Break up the logical address space into multiple page tables
- A simple technique is a two-level page table
- We then page the page table





### **Two-Level Page-Table Scheme**







### **Two-Level Paging Example**

- A logical address (on 32-bit machine with 1K page size) is divided into:
  - a page number consisting of 22 bits
  - a page offset consisting of 10 bits
- Since the page table is paged, the page number is further divided into:
  - a 12-bit page number
  - a 10-bit page offset
- Thus, a logical address is as follows:


age nu	mber	page o
$\rho_1$	$\rho_2$	d
 12	10	10

- where  $p_1$  is an index into the outer page table, and  $p_2$  is the displacement within the page of the inner page table
- Known as forward-mapped page table






#### **Address-Translation Scheme**








### 64-bit Logical Address Space

- Even two-level paging scheme not sufficient
- If page size is  $4 \text{ KB} (2^{12})$ 
  - Then page table has 2<sup>52</sup> entries
  - If two level scheme, inner page tables could be  $2^{10}$  4-byte entries
  - Address would look like



- Outer page table has 2<sup>-2</sup> entries or 2<sup>-1</sup> bytes
- One solution is to add a 2<sup>nd</sup> outer page table
- But in the following example the  $2^{nd}$  outer page table is still  $2^{34}$  bytes in size
  - 4 And possibly 4 memory access to get to one physical memory location



## **Three-level Paging Scheme**

outer page	inner page	offset
$p_1$	$p_2$	d
42	10	12

2nd outer page	outer page	inner page	offset
$p_1$	$p_2$	$p_3$	d
32	10	10	12






### **Hashed Page Tables**


- Common in address spaces > 32 bits
- The virtual page number is hashed into a page table
  - This page table contains a chain of elements hashing to the same location
- Each element contains (1) the virtual page number (2) the value of the mapped page frame (3) a pointer to the next element
- Virtual page numbers are compared in this chain searching for a match
  - If a match is found, the corresponding physical frame is extracted
- Variation for 64-bit addresses is **clustered page tables** 
  - Similar to hashed but each entry refers to several pages (such as 16) rather than 1
  - Especially useful for **sparse** address spaces (where memory references are non-contiguous and scattered)





#### **Hashed Page Table**






### **Inverted Page Table**

- Rather than each process having a page table and keeping track of all possible logical pages, track all physical pages
- One entry for each real page of memory
- Entry consists of the virtual address of the page stored in that real memory location, with information about the process that owns that page
- Decreases memory needed to store each page table, but increases time needed to search the table when a page reference occurs
- Use hash table to limit the search to one or at most a few page-table entries
  - TLB can accelerate access
- But how to implement shared memory?
  - One mapping of a virtual address to the shared physical address





#### **Inverted Page Table Architecture**







#### **Oracle SPARC Solaris**

- Consider modern, 64-bit operating system example with tightly integrated HW
  - Goals are efficiency, low overhead
- Based on hashing, but more complex
- Two hash tables
  - One kernel and one for all user processes
  - Each maps memory addresses from virtual to physical memory
  - Each entry represents a contiguous area of mapped virtual memory,
    - 4 More efficient than having a separate hash-table entry for each page
  - Each entry has base address and span (indicating the number of pages the entry represents)





### **Oracle SPARC Solaris (Cont.)**


- TLB holds translation table entries (TTEs) for fast hardware lookups
  - A cache of TTEs reside in a translation storage buffer (TSB)
    - 4 Includes an entry per recently accessed page
- Virtual address reference causes TLB search
  - If miss, hardware walks the in-memory TSB looking for the TTE corresponding to the address
    - 4 If match found, the CPU copies the TSB entry into the TLB and translation completes
    - 4 If no match found, kernel interrupted to search the hash table
      - The kernel then creates a TTE from the appropriate hash table and stores it in the TSB, Interrupt handler returns control to the MMU, which completes the address translation.





#### **Example: The Intel 32 and 64-bit Architectures**


- Dominant industry chips
- Pentium CPUs are 32-bit and called IA-32 architecture
- Current Intel CPUs are 64-bit and called IA-64 architecture
- Many variations in the chips, cover the main ideas here



#### **Example: The Intel IA-32 Architecture**

- Supports both segmentation and segmentation with paging
  - Each segment can be 4 GB
  - Up to 16 K segments per process
  - Divided into two partitions
    - 4 First partition of up to 8 K segments are private to process (kept in local descriptor table (LDT))
    - 4 Second partition of up to 8K segments shared among all processes (kept in **global descriptor table (GDT)**)





#### **Example: The Intel IA-32 Architecture (Cont.)**

- CPU generates logical address
  - Selector given to segmentation unit
    - 4 Which produces linear addresses


S	g	p		
13	1	2		

- Linear address given to paging unit
  - Which generates physical address in main memory
  - 4 Paging units form equivalent of MMU
  - 4 Pages sizes can be 4 KB or 4 MB





#### **Logical to Physical Address Translation in IA-32**




page r	number	page offset
$p_1$	$p_2$	d
10	10	12






#### **Intel IA-32 Segmentation**








#### **Intel IA-32 Paging Architecture**








#### Intel IA-32 Page Address Extensions

- 32-bit address limits led Intel to create **page address extension** (**PAE**), allowing 32-bit apps access to more than 4GB of memory space
  - Paging went to a 3-level scheme
  - Top two bits refer to a page directory pointer table
  - Page-directory and page-table entries moved to 64-bits in size
  - Net effect is increasing address space to 36 bits 64GB of physical memory






#### Intel x86-64

- Current generation Intel x86 architecture
- 64 bits is ginormous (> 16 exabytes)
- In practice only implement 48 bit addressing
  - Page sizes of 4 KB, 2 MB, 1 GB
  - Four levels of paging hierarchy
- Can also use PAE so virtual addresses are 48 bits and physical addresses are 52 bits


		page map	page	directory		page		page			
unused		level 4	<sub> </sub> poir	ter table		directory		table		offset	
63	48 4	7 3	9 38	30	29		21 20		12 11		(





#### **Example: ARM Architecture**

- Dominant mobile platform chip (Apple iOS and Google Android devices for example)
- Modern, energy efficient, 32-bit CPU
- 4 KB and 16 KB pages
- 1 MB and 16 MB pages (termed sections)
- One-level paging for sections, two-level for smaller pages
- Two levels of TLBs
  - Outer level has two micro TLBs (one data, one instruction)
  - Inner is single main TLB
  - First inner is checked, on miss outers are checked, and on miss page table walk performed by CPU





# **End of Chapter 8**

