


Transport Layer: UDP + Reliable Data Transfer + TCP

Vivek Shah

Based on slides compiled by Marcos Vaz Salles

Internet Layering Model




Transport Layer

- Logical Communication between processes
 - Sender divides messages into segments.
 - Receiver re-assembles messages into segments.
- Principles underlying transport-layer services
 - (De)multiplexing
 - Detecting corruption
 - Optional: Reliable delivery, Flow control, Congestion control
- Transport-layer protocols in the Internet
 - User Datagram Protocol (UDP)
 - Simple (unreliable) message delivery
 - Transmission Control Protocol (TCP)
 - Reliable bidirectional stream of bytes



Socket Programming Using UDP





Source: Campbell


Socket Programming Using UDP

```
ssize_t recvfrom(int sockfd, void* buff,
 size_t nbytes, int flags, struct sockaddr* from,
 socklen_t *addrlen);
```



Two Basic Transport Features

• **Demultiplexing:** port numbers







User Datagram Protocol (UDP)

- Datagram messaging service
 - Demultiplexing of messages: port numbers
 - Detecting corrupted messages: checksum
- Lightweight communication between processes
 - Send messages to and receive them from a socket
 - Avoid overhead and delays of ordered, reliable delivery

SRC port	DST port		
checksum	length		
DATA			




Why Would Anyone Use UDP?

- Fine control over what data is sent and when
 - As soon as app process writes into socket
 - ... UDP will package data and send packet
- No delay for connection establishment
 - UDP blasts away without any formal preliminaries
 - ... avoids introducing unnecessary delays
- No connection state (no buffers, sequence #'s, etc.)
 - Can scale to more active clients at once
- Small packet header overhead (header only 8B long)



Popular Applications That C


- Simple query protocols like DNS
 - Overhead of connection establishment is overkill
 - Easier to have the application retransmit if needed



- Multimedia streaming (VoIP, video conferencing, ...)
 - Retransmitting lost/corrupted packets is not worthwhile
 - By time packet is retransmitted, it's too late



Reliable Data Transfer



Source: Kurose & Ross

- What can go wrong on the unreliable channel?
- How can you deal with it?
 - Suppose you want to transfer TCP segments, reliably and in order!



Challenges of Reliable Data Transfer

- Over a perfectly reliable channel: Done
- Over a channel with bit errors
 - Receiver detects errors and requests re-transmission
- Over a lossy channel with bit errors
 - Some data missing, others corrupted
 - Receiver cannot easily detect loss
- Over a channel that may reorder packets
 - Receiver cannot easily distinguish loss vs. out-of-order



An Analogy

- Alice and Bob are talking
 - What if Alice couldn't understand Bob?
 - Alice asks Bob to repeat what he said



- What if Bob hasn't heard Alice for a while?
 - Is Alice just being quiet? Has she lost reception?
 - How long should Bob just keep on talking?
 - Maybe Alice should periodically say "uh huh"
 - ... or Bob should ask "Can you hear me now?"



Take Aways from the Example

- Acknowledgments from receiver
 - Positive: "okay" or "uh huh" or "ACK"
 - Negative: "please repeat that" or "NACK"
- Retransmission by the sender
 - After not receiving an "ACK"
 - After receiving a "NACK"
- Timeout by the sender ("stop and wait")
 - Don't wait forever without some acknowledgment



TCP Support for Reliable Delivery

- Detect bit errors: checksum
 - Used to detect corrupted data at the receiver
 - ...leading the receiver to drop the packet
- Detect missing data: sequence number
 - Used to detect a gap in the stream of bytes
 - ... and for putting the data back in order
- Recover from lost data: retransmission
 - Sender re-transmits lost or corrupted data
 - Two main ways to detect lost packets




Transmission Control Protocol (TCP)

- Stream-of-bytes service: Send/recv streams, not msgs
- Reliable, in-order delivery
 - Checksums to detect corrupted data
 - Sequence numbers to detect losses and reorder data
 - Acknowledgments & retransmissions for reliable delivery
- Connection oriented: Explicit set-up and teardown
- Flow control: Prevent overload of receiver's buffer
- Congestion control: Adapt for greater good



TCP "Stream of Bytes" Service


Host A






... Emulated Using TCP "Segments"

Host A



TCP Segment


- IP packet
 - No bigger than Maximum Transmission Unit (MTU)
 - E.g., up to 1500 bytes on an Ethernet link
- TCP packet
 - IP packet with a TCP header and data inside
 - TCP header is typically 20 bytes long
- TCP segment
 - No more than Maximum Segment Size (MSS) bytes
 - E.g., up to 1460 consecutive bytes from the stream






TCP Acknowledgements

Host A




Automatic Repeat Request (ARQ)


- Receiver sends ACK when it receives packet
- Sender waits for ACK.
- If ACK not received within some timeout period, resend packet
- "stop and wait"
 - One packet at a time...






Reasons for Retransmission








How Long Should Sender Wait?

- Too short? Wasted re-transmissions
- Too long? Excessive delays when packet lost
- TCP sets timeout as function of Round Trip Time
 - ACK should arrive after RTT + fudge factor for queuing
- How does sender know RTT?
 - Can estimate RTT by watching the ACKs
 - Smooth estimate: Exponentially-weighted moving avg (EWMA)
 - EstimatedRTT = (1-a) * EstimatedRTT + a * SampleRTT
 - Typical value: a = 0.125



Example RTT Estimation

RTT: gaia.cs.umass.edu to fantasia.eurecom.fr



Source: Kurose & Ross

TCP Round Trip Time and Timeout

Setting the timeout

- EstimatedRTT plus "safety margin"
 - large variation in **EstimatedRTT** → larger safety margin
- first estimate of how much SampleRTT deviates from EstimatedRTT:

```
DevRTT = (1-\beta)*DevRTT + \beta*|SampleRTT-EstimatedRTT| (typically, \beta = 0.25)
```

Then set timeout interval:

TimeoutInterval = EstimatedRTT + 4*DevRTT



Source: Kurose &


A Flaw in This Approach

ACK acknowledges receipt to data, not transmission

- Consider a retransmission of a lost packet
 - If assume ACK with 1st transmission, SampleRTT too large
- Consider a duplicate packet
 - If assume ACK with 2nd transmission, SampleRTT too small
- Simple solution in the Karn/Partridge algorithm
 - Only collect samples for segments sent one single time
 - On retransmission, new_timeout = 2 * timeout




Well tuned timeouts help, but...



$$U_{\text{sender}} = \frac{L/R}{RTT + L/R} = \frac{.008}{30.008} = 0.00027$$



TCP Retransmission and Cumulative ACK



Source: Kurose & Ross (partial)

TCP Fast Retrasmit


- time-out period often relatively long:
 - long delay before resending lost packet
- detect lost segments via duplicate ACKs.
 - sender often sends many segments backto-back
 - if segment is lost, there will likely be many duplicate ACKs.

- if sender receives 3
 ACKs for the same
 data, it supposes
 that segment after
 ACKed data was
 lost:
 - <u>fast retransmit:</u>
 resend segment
 before timer expires



TCP Fast Retransmit

- Resending a segment after triple duplicate ACK
- Triple duplicate
 ACK works as a
 logical NACK





Source: Kurose & Ross (partial)


Effectiveness of Fast Retransmit

- When does Fast Retransmit work best?
 - Long transfers: High likelihood of many pkts in flight
 - Large window: High likelihood of many packets in flight
 - Low loss burstiness: Higher likelihood that later pkts arrive
- Implications for Web traffic
 - Most Web objects are short (e.g., 10 packets)
 - So, often aren't many packets in flight
 - ... making fast retransmit less likely to "kick in"
 - ... another reason for persistent connections!



Increasing TCP throughput

- Problem: Stop-and-wait + timeouts are inefficient
 - Only one TCP segment "in flight" at time
- Solution: Send multiple packets at once
- Problem: How many w/o overwhelming receiver?
- Solution: Determine "window size"




(a) a stop-and-wait protocol in operation

(b) a pipelined protocol in operation



Flow Control: Sliding Window

- Allow a larger amount of data "in flight"
 - Sender can get ahead of receiver, though not too far




Flow Control: Receiver Buffering

- Window size
 - Amount that can be sent w/o ACK, because receiver can buffer
- Receiver advertises window to sender
 - Tells amount of free space left (in bytes)

RcvWindow = RcvBuffer-[LastByteRcvd - LastByteRead]

Sender agrees not to exceed this amount


Window Size





Source: Freedman (partial)

Establishing a TCP Connection



Each host tells its ISN to other host

- Three-way handshake to establish connection
 - Host A sends a SYNchronize (open) to the host B
 - Host B returns a SYN ACKnowledgment (SYN ACK)
 - Host A sends an ACK to acknowledge the SYN ACK



Step 1: A's Initial SYN Packet

Flags: SYN

FIN

RST

PSH

URG

ACK

A's port			B's port	
A's Initial Sequence Number				
Acknowledgment				
20	0	Flags	Advertised window	
Checksum			Urgent pointer	
Options (variable)				

A tells B it wants to open a connection...



Step 2: B's SYN-ACK Packet

Flags: SYN

FIN

RST

PSH

URG

ACK

B's port		ort	A's port	
B's Initial Sequence Number				
A's ISN plus 1				
20	0	Flags	Advertised window	
Checksum			Urgent pointer	
Options (variable)				

B tells A it accepts, and is ready to hear the next byte..

... upon receiving this packet, A can start sending d



Step 3: A's ACK of the SYN-ACK

Flags: SYN

FIN

RST

PSH

URG

ACK

A's port			B's port
Sequence number			
B's ISN plus 1			
20	0	Flags	Advertised window
Checksum			Urgent pointer
Options (variable)			


A tells B it is okay to start sending...

... upon receiving this packet, B can start sending d



Source: Freedman

Tearing Down the Connection



Congestion Control

- Congestion in IP networks
 - Unavoidable due to best-effort service model
 - IP philosophy: decentralized control at end hosts
- Congestion control by the TCP senders
 - Infers congestion is occurring (e.g., from packet losses)
 - Slows down to alleviate congestion, for the greater good
- TCP congestion-control algorithm
 - Additive-increase, multiplicative-decrease
 - Slow start and slow-start restart



IP Best-Effort Design Philosophy


- Best-effort delivery
 - Let everybody send
 - Network tries to deliver what it can
 - ... and just drop the rest





Congestion is Unavoidable


- Two packets arrive at same time
 - Router can only transmit one: must buffer or drop other
- If many packets arrive in short period of time
 - Router cannot keep up with the arriving traffic
 - Buffer may eventually overflow





The Problem of Congestion

- What is congestion?
 - Load is higher than capacity
- What do IP routers do?
 - Drop the excess packets
- Why is this bad?
 - Wasted bandwidth for re-transmissions



Increase in load that results in a decrease in useful work done.


Source: Freedman


Ways to Deal With Congestion

- Ignore the problem
 - Many dropped (and retransmitted) packets
 - Can cause congestion collapse
- Reservations, like in circuit switching
 - Pre-arrange bandwidth allocations
 - Requires negotiation before sending packets
- Pricing
 - Don't drop packets for the high-bidders
 - Requires a payment model, and low-bidders still dropped
- Dynamic adjustment (TCP)
 - Every sender infers the level of congestion
 - Each adapts its sending rate "for the greater good"



Inferring From Implicit Feedback





- What does the end host see?
- What can the end host change?
- What if conditions change?

- TCP keeps congestion window, as in the graph
- Can you explain behavior?
 Why are there increases and drops?
- Why is there a "sawtooth"?



TCP Congestion Window

- Each TCP sender maintains a congestion window
 - Max number of bytes to have in transit (not yet ACK'd)
- Adapting the congestion window
 - Decrease upon losing a packet: backing off
 - Increase upon success: optimistically exploring
 - Always struggling to find right transfer rate
- Tradeoff
 - Pro: avoids needing explicit network feedback
 - Con: continually under- and over-shoots "right" rate




Additive Increase, Multiplicative Decrease (AIMD)

- How much to adapt?
 - Additive increase: On success of last window of data, increase window by 1 Max Segment Size (MSS)
 - Multiplicative decrease: On loss of packet, divide congestion window in half
- Much quicker to slow than speed up!
 - Over-sized windows (causing loss) are much worse than under-sized windows (causing lower throughput)
 - AIMD: A necessary condition for stability of TCP



Leads to TCP "Sawtooth"





Receiver Window vs. Congestion Window


- Flow control
 - Keep a fast sender from overwhelming a slow receiver
- Congestion control
 - Keep a *set of senders* from overloading the *network*
- Different concepts, but similar mechanisms
 - TCP flow control: receiver window
 - TCP congestion control: congestion window
 - Sender TCP window = min { congestion window, receiver window }



How Should a New Flow Start?

Start slow (a small CWND) to avoid overloading network





But, could take a long time to get started!




"Slow Start" Phase

- Start with a small congestion window
 - Initially, CWND is 1 MSS
 - So, initial sending rate is MSS / RTT
- Could be pretty wasteful
 - Might be much less than actual bandwidth
 - Linear increase takes a long time to accelerate
- Slow-start phase (really "fast start")
 - Sender starts at a slow rate (hence the name)
 - ... but increases rate exponentially until the first loss



Slow Start in Action


Double CWND per round-trip time





Slow Start and the TCP Sawtooth

Window



- So-called because TCP originally had no congestion control
 - Source would start by sending an entire receiver window
 - Led to congestion collapse!




Two Kinds of Loss in TCP

- Timeout
 - Packet n is lost and detected via a timeout
 - When? n is last packet in window, or all packets in flight lost
 - After timeout, blasting entire CWND would cause another burst
 - Better to start over with a low CWND
- Triple duplicate ACK
 - Packet n is lost, but packets n+1, n+2, etc. arrive
 - How detected? Multiple ACKs that receiver waiting for n
 - When? Later packets after n received
 - After triple duplicate ACK, sender quickly resends packet n
 - Do a multiplicative decrease and keep



Repeating Slow Start After Timeout



Slow-start restart: Go back to CWND of 1, but take advantage of knowing the previous value of CWND.




Repeating Slow Start After Idle Period

- Suppose a TCP connection goes idle for a while
- Eventually, the network conditions change
 - Maybe many more flows are traversing the link
- Dangerous to start transmitting at the old rate
 - Previously-idle TCP sender might blast network
 - ... causing excessive congestion and packet loss
- So, some TCP implementations repeat slow start
 - Slow-start restart after an idle period



TCP Achieves Some Notion of Fairness

- Effective utilization is not only goal
 - We also want to be fair to various flows
 - ... but what does *that* mean?
- Simple definition: equal shares of the bandwidth
 - N flows that each get 1/N of the bandwidth?
 - But, what if flows traverse different paths?
 - Result: bandwidth shared in proportion to RTT



Source: Freedman

What About Cheating?

- Some folks are more fair than others
 - Running multiple TCP connections in parallel (BitTorrent)
 - Modifying the TCP implementation in the OS
 - Some cloud services start TCP at > 1 MSS
 - Use the User Datagram Protocol
- What is the impact
 - Good guys slow down to make room for you
 - You get an unfair share of the bandwidth
- Possible solutions?
 - Routers detect cheating and drop excess packets?
 - Per user/customer failness?
 - Peer pressure?



Summary

- UDP
 - basic multiplexing, checksums
- TCP & reliable transfer
 - Segments, sequence numbers, automatic repeat requests
 - Timeout estimation
 - Pipelining, cumulative ACK, fast retransmit
 - Flow control: receiver window
 - Congestion control: congestion window, AIMD, slow start, slow start restart

