Microsoft TechNet

 $\underline{\text{TechNet Home}} > \underline{\text{Product \& Technologies}} > \underline{\text{SQL Server TechCenter Home}} > \underline{\text{Best Practices}}$

Predeployment I/O Best Practices

SQL Server Best Practices Article

Published: June 5, 2007

Writer: Mike Ruthruff

Contributors: Michael Thomassy, Prem Mehra

Technical Reviewers: Robert Dorr, Stuart Ozer, Juergen Thomas, Lindsey Allen, Burzin Patel, Bill Emmert, Bruce Worthington, Sanjay Mishra

Applies To: SQL Server 2005

Summary: The I/O system is important to the performance of SQL Server. When configuring a new server for SQL Server or when adding or modifying the disk configuration of an existing system, it is good practice to determine the capacity of the I/O subsystem prior to deploying SQL Server. This white paper discusses validating and determining the capacity of an I/O subsystem. A number of tools are available for performing this type of testing. This white paper focuses on the SQLIO.exe tool, but also compares all available tools. It also covers basic I/O configuration best practices for SQL Server 2005.

On This Page

- **♦** SQLIO

Overview

One of the key components that affect the performance of Microsoft® SQL Server $^{\text{TM}}$ is the I/O subsystem. When configuring a new server for SQL Server or when adding or modifying the disk configuration of an existing system it is good practice to determine the capacity of the I/O subsystem prior to deploying SQL Server.

This paper provides guidance for validating and determining the capacity of an I/O subsystem. A number of tools are available that can be used to perform this type of testing. The focus of this paper is on the SQLIO.exe tool. However, we will contrast and compare all of the available tools. Much of the information in this white paper is in the document that is included with the download of the SQLIO tool; however, this white paper includes updates to existing information and additional information, including basic I/O configuration best practices as related to SQL Server based on recent learnings.

Background

Using an I/O stress tool to validate performance and ensure that the system is tuned optimally for SQL Server before deployment helps identify hardware or I/O configuration related issues before the complexity of SQL Server is introduced. SQLIO.exe is a tool that can be used to determine the I/O capacity of a given hardware configuration. The purpose of SQLIO is *not* to simulate exactly the I/O patterns of SQL Server but rather to determine the capacity of an I/O subsystem for specific I/O types that are relevant to SQL Server deployments. Testing a variety of I/O types is necessary because performance problems can be specific to a certain type of I/O or pattern of I/O.

A number of tools are available to stress and validate the functionality of I/O subsystems. Some of these tools actually simulate SQL Server I/O patterns and others allow you to control the I/O patterns submitted to the subsystem. There are tools that confirm the functional validity of a configuration and others that are used purely to test performance capacity. The following table compares the most common tools currently used to test I/O subsystems in the context of SQL Server.

Table 1 Tools used to test I/O subsystems

Tool	Used to determine	I/O Patterns	Provided by
SQLIO.exe	Performance capacity	User defined— Single I/O type at a time	Microsoft
IOMeter	Performance capacity	User defined— Allows combinations of I/O types	Open Source
SQLIOSim	Functional correctness	Simulates SQL Server I/O patterns	Microsoft
SQLIOStress (deprecated – use SQLIOSim)	Functional correctness	Simulates SQL Server I/O patterns	Microsoft

SQLIOStress and SQLIOSim validate the basic functionality of an I/O subsystem under stress. They attempt to simulate actual SQL Server I/O patterns and check results for correctness. These tools are commonly used by the Microsoft SQL Server support organization to isolate hardware-related corruption problems.

For the purposes of this discussion, SQLIO and IOMeter are the most appropriate tools. SQLIO is a fairly rudimentary tool that can be used to issue a particular type of I/O against one or many test files to measure I/Os per second (IOPs), throughput (MB/s), and latency.

IOMeter is a bit more sophisticated; it enables you to define combinations of I/O patterns, which can be issued concurrently against one or more test files. While this can be advantageous for certain test scenarios, remember that the purpose of testing as described in this white paper is to measure performance and confirm that a particular I/O subsystem is configured correctly. It is misleading to assume that using a tool such as IOMeter allows you to simulate SQL Server I/O patterns just because with it you can define combinations of I/O types. This topic is discussed later in this paper.

With the growing variety of storage solutions in today's IT organizations, several items should be noted before continuing:

- While the information provided in this white paper can be used to performance test any disk subsystem, much of it is directed toward higher end storage arrays (such as those with significant amounts of cache, processing power, and so on). Keep this in mind if you are using or testing a more traditional disk subsystem.
- This paper focuses heavily on I/O subsystems with fiber channel connectivity. However, the same concepts can be applied to iSCSI or other traditional direct attach storage systems.
- ↑ Top of page

Determining I/O Capacity

This section covers best practices that should be applied when using any tool to determine the performance capacity of a given I/O configuration. Consider the following:

Test a variety of I/O types and sizes.

Test a combination of I/O sizes for read/write and sequential/random. For SQL-focused deployments, be sure to include I/O sizes of 8 KB, 64 KB, 128 KB, 256 KB & 1024 for sequential I/O. (Read-ahead can be up to 1024 KB when running SQL Server Enterprise Edition). For random I/O it is generally safe to focus only on 8-KB I/O.

There are differences when measuring the performance of sequential I/O versus measuring the performance of random I/O. The important unit of measurement for sequential I/O is throughput (MB/s) whereas for random I/O, the important unit of measure is the number of I/Os per second. If summarized at a high-level I/O, operations within SQL Server can be characterized as follows:

Online Transaction Processing (OLTP):

- OLTP processing is generally random in nature for both reads and writes issued against data files.
- Read activity (in most cases) is constant in nature.
- Write activity to the data files occurs during checkpoint operations (frequency is determined by recovery interval settings).
- Log writes are sequential in nature with a varying size, which is dependent on the nature of the workload (sector aligned up to 60 KB).
- Log reads are sequential in nature (sector aligned up to 120 KB).

Decision Support System (DSS):

- Reads and writes tend to be sequential in nature and are generally the result of table or index scans and bulk insert operations.
- I/O size varies but is generally larger than 8 KB. Read-ahead is any multiple of 8 KB up to 256 KB (1024 KB for Enterprise edition). Bulk load operations are any multiple of 8 KB up to 128 KB.

• Determine the saturation point of an I/O subsystem by gradually increasing the load.

Start with a small number of outstanding I/Os (-o) and gradually increase this until the path is saturated. Saturation occurs when latency increases and throughput stays the same. An example of disk saturation is shown in Figure 1.




Figure 1 Disk saturation for random reads

The performance monitor graph in Figure 1 shows three data points: Average Disk Queue Length, Disk Reads/sec and Avg. Disk sec/ Read (latency). The type of I/O issued here is random 8 KB reads. Using I/O of this type removes the impact of the array cache on the test because random reads will not benefit from the cache. As illustrated, as the number of outstanding I/Os is increased (Avg Disk Queue Length), the throughput increases until greater than 64 outstanding I/Os are issued. At this point, latency continues to increase; however, I/Os per second (Disk Reads/sec) stays constant—this is the point of disk saturation.

In addition to disk saturation, it is also possible to saturate the capacity of a Host Bus Adapter (HBA) before exhausting disk resources. Typical modern HBAs have a bandwidth of 2 Gb/s. This equates roughly into 200 MB/s. We have observed practical throughput in the range of 180–190 MB/s. The graph in Figure 2 illustrates the saturation of a single HBA.




Figure 2 HBA saturation

We know that the bandwidth of a single HBA is approximately 200 MB/s and in Figure 2 the maximum achieved throughput is almost exactly 200 MB/s. Based on the bandwidth of HBA and maximum achieved throughput, it is reasonable to conclude that the capacity of the HBA has been exhausted rather than the capacity of the underlying disks. This is largely based on the fact that the maximum throughput is attained with only two outstanding I/Os (Avg. Disk Queue Length) and a very low latency (Avg. Disk sec/Read).

• Use test files that are similar to your configuration.

Ideally, the size of your test files should be similar to the size of the database being deployed. Make sure that the total size of the test files used in each test is significantly larger than the amount of cache on the storage array (a minimum of two to four times the amount of any cache on the storage array). Using small test files can result in skewed results since the entire file may be cached on the array. In addition, small files could result in only a small portion of the disk being utilized, resulting in lower seek times (commonly referred to as *short stroking* the disk) and ultimately skewing the results.

One potential exception here is the strategy of using a very small test file to test the throughput of the channel. Using test files that remain memory resident on the array can be a technique that is used to determine the capacity of other components when there are no disk-based bottlenecks. By using this approach, you can quickly determine if you will be able to realize all of the theoretical bandwidth between array and host. The theoretical bandwidth is determined by things such as:

- The number of and bandwidth of HBAs installed in the host.
- The number of connections to and bandwidth of any switch ports being used.
- The number of and bandwidth of front end fiber channel ports on the array.

These are discussed more in the next point.

• Understand your particular hardware configuration.

Make sure that you understand your specific hardware configuration and the theoretical limits of the hardware. Be sure to consider specific details of your configuration that will impact throughput, including but not limited to:

- The number and bandwidth of HBAs installed on the host.
- The number and bandwidth of fiber channel switch ports as well as front-end fiber channel ports on the array.
- The number and rotational speed of physical disks/spindles backing each Logical Unit Volume (LUN). In addition, it is beneficial to understand specific implementation details about the array. (For example, is the access to LUNs load balanced across all service processors or are these statically assigned to a single service processor in the array? How is the cache configured at the LUN level?)
- Whether you are sharing physical spindles with other applications that use the storage array.
- The RAID level used by the configuration.
- Any multipath software used by the host and the mode in which the multipath software is running. Because this software can be run in both load balancing or failover only modes, it can affect the total throughput potential for multiple HBAs.
- The HBA configuration settings that are in place and the version of drivers/firmware that is being used. For example, increasing the queue depth setting on an HBA is commonly required to support the amount of outstanding I/Os needed for optimal SQL Server performance. Failure to adjust this properly may result in higher I/O
- Suboptimal cache settings on the storage array. If the storage array cache can be tuned manually, optimizing for writes is generally the best approach for the most common SQL Server workloads. SQL Server does not benefit as much from the read cache because it uses an internal read-ahead mechanism to prefetch pages during scans. It should be noted that when cache is mentioned, it is assumed that any cache on the array meets SQL Server core I/O requirements. Most higher-end modern arrays have cache that is battery backed and mirrored.

• Validate results against expected outcome.

If your test results are lower than expected, examine each component of the configuration to ensure optimal configuration. Common problems include:

- Suboptimal drivers or firmware used on the host HBAs or storage array.
- Improper queue depth settings on HBAs.
- $_{\bullet}\;$ Incorrectly configured multipath software and/or fiber switches.

Test each volume individually, and then test combinations of volumes. Assuming adequate disk resources, there should be a linear scale up of throughput (MB/s or I/Os per second) as additional volumes or paths (HBAs) are added to the test. This, of course, is dependent on hardware throughput limitations and the specific disk configuration backing each LUN.

• Ensure that test runs are long enough to be valid.

Short test runs (five to ten minutes) are okay for initial testing; however, if potential problem areas are discovered, longer tests should be run. Many of the larger storage systems utilize a self-tuning cache and may require that a workload be run for a period of time before an optimal cache performance is reached. It is not unreasonable to run tests of an hour or more and some vendors recommend even longer test durations to provide accurate results. This is specific to the characteristics of the array being tested and specifically the amount of cache on the array (large cache sizes tend to require longer runs). Discuss with your particular storage vendor how long they recommend running tests.

• Consider the potential impact of the array cache on test results.

Keep in mind for tests that issue writes, accurate disk-based performance will not be observed until the cache is saturated. If you are the only user of the array, allow some time in between each I/O type that you test to allow the I/O system to return to an idle state and run long enough so that you are actually observing disk-based I/O performance. Following a large amount of write activity, it may take some time to flush all pending write requests from cache to disk. If no wait time is included between tests, this could impact the results of subsequent tests. Waiting one minute between tests is acceptable for most systems; however, you should consult your storage vendor to determine what is acceptable on their specific hardware.

• Review performance with storage administrators and hardware vendors.

Store all of the benchmark data in order to compare it with the SQL Server I/O throughput numbers. Share this information with storage vendors and/or storage administrators to determine if your results are what would be expected for your particular storage configuration.

↑ Top of page

Disk Configuration Best Practices & Common Pitfalls

The SQL Server Best Practices site on Microsoft TechNet has a list of the top ten storage best practices with respect to SQL Server: see Storage Top 10 Best Practices.

In addition to the best practices on the Top 10 list, this section lists best practices when configuring the NTFS file system and other host-specific I/O settings.

Volume Alignment

Volume alignment, commonly referred to as sector alignment, should be performed on the file system (NTFS) whenever a volume is created on a RAID device. Failure to do so can lead to significant performance degradation; these are most commonly the result of partition misalignment with stripe unit boundaries. This can also lead to hardware cache misalignment, resulting in inefficient utilization of the array cache. For more information on this, see Disk performance may be slower than expected when you use multiple disks in Windows Server 2003, in Windows XP, and in Windows 2000.

Volume alignment on NTFS volumes can be performed by using diskpar.exe or DiskPart.exe. There is no advantage of using one over the other. However, DiskPart.exe is the preferred method since it is now included as part of Microsoft Windows® and the functionality will continue to be enhanced. Diskpar.exe is a Windows 2000 Resource Kit tool and is most commonly used in versions of Windows prior to Windows 2003 SP1. DiskPart.exe is a disk configuration utility that is built into Windows; in Windows 2003 version SP1 or greater DiskPart.exe contains an ALIGN option that can be used to align volumes.

When aligning the file system keep in mind the following:

- Ideally, the offset used to align the volume should be supplied by the OEM of your particular storage array.
- If the OEM does not provide an offset, the only way to determine the optimal offset is through testing
- A 64-KB offset (128 sectors) is a common value that works on many storage arrays and has been used with success in the SQL Server test labs (at the time of writing this
 paper). Vista™ and Windows Longhorn Server remove the need to manually establish correct alignment and use 1024 KB (2048 sectors) as a starting offset, which will
 probably work well for almost any array.
- Diskpar.exe works only on MBR partitions. DiskPart.exe supports both MBR and GPT partitions. Alignment of dynamic volumes is not currently supported as of Windows 2003 SP1.
- The value of the offset for diskpar.exe is expressed in sectors (512 bytes) and differs from the ALIGN option of DiskPart.exe, which uses a value defined in KB. For example "create partition primary align=64" creates a partition using a 64-KB offset.

To determine the current starting offset of a volume (or partition), you can either use Diskpar.exe with the —i option or WMI (as demonstrated in the following script) if Diskpar.exe is not available.

```
strComputer = "."
Set objWMIService = GetObject("winmgmts:\\" & strComputer & "\root\CIMV2")
Set colItems = objWMIService.ExecQuery( _
    "SELECT * FROM win32_DiskPartition",,48)
For Each objItem in colItems
    wscript.Echo "Disk: " & objItem.DiskIndex & " Partition: " & objItem.Index & " StartingOffset: " & objItem.StartingOffset/1024 & "KB"
    Wscript.Echo
Next
```

For more information on DiskPart.exe, see <u>DiskPart</u> on Microsoft TechNet, specifically the "create partition primary" section.

NTFS Allocation Unit Size

When formatting the partition that will be used for SQL Server data files, it is recommended that you use a 64-KB allocation unit size for data, logs, and tempdb. Be aware however, that using allocation unit sizes greater than 4 KB results in the inability to use NTFS compression on the volume. SQL Server, although it is not recommended that you use this, does support read-only data on compressed volumes.

HBA Queue Depth Settings

When configuring HBAs on the host, ensure that the Queue Depth is set to an optimal value. SQL Server applications are generally I/O-intensive, with many concurrent outstanding I/O requests. As a result, the default values for Queue Depth on HBAs are usually not high enough to support optimal performance. Currently the default value for the major HBA vendors is in the range of 8 to 32.

In our SQL Server testing, we have seen substantial gains in I/O performance when increasing this to 64 or even higher. It is worth noting that in these tests SQL Server was usually the only application using the storage array. It is important to discuss with your storage administrator the appropriate values for this setting, as the setting may affect other applications in sharing the same storage environment. When Queue Depth is set too low, a common symptom is increasing latency and less-than-expected throughput given the bandwidth between host/storage and the number of spindles in a particular configuration.

HBA Drivers

When choosing drivers for the HBAs that are installed on a host, ensure that you are using the recommended drivers for your particular storage array. The major HBA vendors have specific areas of their Web sites for downloading and installing the recommended drivers for a particular storage vendor.

For current Windows deployments, Storport is the preferred driver. In fact, on native x64 versions of Windows, Storport is the only supported driver for fiber channel HBAs. Be aware that there are also some significant differences between SCSIport and Storport drivers. When using Storport drivers, the number of maximum outstanding I/Os is 255 per LUN (vendor-specific parameters) as opposed to SCSIport, which only supports 255 per adapter (common parameter). This can have a significant impact on larger configurations, since the total amount of outstanding I/O can be more limited when using SCSIport. For more information, see Area Networks.

How Many LUNs Should I Have?

This is a common question raised in the design phase of a storage configuration for SQL Server. Unfortunately, there is no single answer to this question. Answering this question involves many considerations, which depend on the needs of the deployment and the implementation-specific details of the array being used. Be sure to consider the following when making this decision.

- Maintain a balanced storage design. The architecture of specific HBAs (Host Bus Adapters) and their settings influence performance and throughput. But in general, more LUNs result in more independent I/O queues and potentially more concurrent outstanding I/Os. Assuming that the Storage Area Network (SAN) has no bottlenecks, one can expect better scalability with multiple LUNs and multiple paths between server HBAs and the SAN.
- Look at the design from potential failure viewpoint
 - Keep in mind that a failed disk drive will impact the RAID group in which it participates and additionally the various LUNs that span that RAID group. To minimize the
 impact, ensure that failure exposure is limited.
 - In the event of having to run CHKDSK, the amount of time for CHKDSK to complete depends on the number of files/directories on the LUN. Large LUNs will not necessarily increase the outage time; however, it is not recommended that you use a large LUN and place a large number non-SQL related files on the volume. Keep the volume structure and number of files as small as is practical.
 - Any mount point volumes contained under a volume drive letter will be offline in the event of a CHKDSK against the root volume. It is recommended that you keep the root volume small and dedicated to providing access to the mount point volumes.
- Design for future growth. Data will undoubtedly grow over time and storage growth strategies should be factored into any storage design. Will you add more LUNs or increase the size of the LUNs when the need arises? Input from your storage vendor or administrator is very pertinent here—the administrator may have a policy that you must follow.
- Be aware of SQL Server implementation considerations. Ultimately the I/O performance of SQL Server is not tied to the number of underlying volumes (or LUNs). Rather, this is determined by the hardware capacity. A common misconception is that there is a one-to-one association between SQL Server threads and data files. This is not true. I/O operations are issued by any worker thread inside the SQL Server process. There are, however, two potential areas where the number of underlying LUNs affect SQL Server behavior. These are:
 - Backup and Restore. SQL Server will use one reader thread per volume and one writer thread per volume. If multiple volumes are mounted to a single drive letter using mount points, they still behave as separate volumes and use one thread per each volume.
 - File Initialization. Mainly a consideration on SQL Server 2000 and only for very large databases; SQL Server uses one thread per volume to initialize data files.

Ultimately, the storage design is a balance between performance, manageability, and availability. The previous list is not meant to be all inclusive but to bring up some of the common considerations to think about when designing storage for SQL Server. The optimal storage design varies from implementation to implementation.

↑ Top of page

SQLIO

SQLIO.exe is a tool provided by Microsoft that can be used to determine the I/O capacity of a given configuration. SQLIO is provided 'as is' and there is no support offered for any problems encountered when using the tool. Please see the EULA.doc for the license agreement for using this tool.

To download SQLIO, go to SQLIO Disk Subsystem Benchmark Tool on the Microsoft Download Center.

Specific Instructions for Using SQLIO.exe

This section provides instructions for using SQLIO to test the hardware capacity of a given configuration. For a complete set of the options available in SQLIO, see the readme.txt file or run 'SOLIO.exe -?' from a command line.

When using SQLIO to test a storage configuration, all of the volumes should be tested individually, and then volumes should be added until all volumes are tested at the same time. When testing a large number of volumes, there are potentially many combinations. In these cases, focus on scalability as the number of volumes included in the test is increased (1, 2, 4, 8, and so on). Testing the volumes in this manner enables you to determine if there are any problems with a given volume and if the cumulative throughput is expected, given the particular storage configuration.

Following is a sample of the syntax that could be used in a batch file to automate running SQLIO through a series of tests of varying I/O types and sizes. Table 2 has further explanations for suggested values when running tests. When running tests, make sure that you keep in mind the items outlined earlier in this document in Determining I/O <a href="Determi

One example of how this might be used would be the following. Keep in mind however that in order to gain a complete understanding of I/O subsystem performance, some of the parameters in the following example will need to be altered after each test run, specifically the number of outstanding I/Os issued during each test (discussed in more detail in Table 2, following this code):

```
::Test randmon IO's of 8k
call sqlio -kW -s600 -frandom -o32 -b8 -LS -Fparam.txt
call sqlio -kR -s600 -frandom -o32 -b8 -LS -Fparam.txt
::Test small sequential writes
call sqlio -kW -s60 -fsequential -o1 -b4 -LS -Fparam.txt
call sqlio -kW -s60 -fsequential -o1 -b8 -LS -Fparam.txt
call sqlio -kW -s60 -fsequential -o1 -b16 -LS -Fparam.txt
call sqlio -kW -s60 -fsequential -o1 -b16 -LS -Fparam.txt
call sqlio -kW -s60 -fsequential -o1 -b2 -LS -Fparam.txt
call sqlio -kW -s60 -fsequential -o1 -b64 -LS -Fparam.txt
call sqlio -kR -s60 -fsequential -o8 -b8 -LS -Fparam.txt
call sqlio -kR -s60 -fsequential -o8 -b128 -LS -Fparam.txt
call sqlio -kR -s60 -fsequential -o8 -b256 -LS -Fparam.txt
call sqlio -kW -s60 -fsequential -o8 -b256 -LS -Fparam.txt
call sqlio -kW -s60 -fsequential -o8 -b4 -LS -Fparam.txt
call sqlio -kW -s60 -fsequential -o8 -b4 -LS -Fparam.txt
call sqlio -kW -s60 -fsequential -o8 -b54 -LS -Fparam.txt
call sqlio -kW -s60 -fsequential -o8 -b54 -LS -Fparam.txt
call sqlio -kW -s60 -fsequential -o8 -b556 -LS -Fparam.txt
call sqlio -kW -s60 -fsequential -o8 -b556 -LS -Fparam.txt
call sqlio -kW -s60 -fsequential -o8 -b556 -LS -Fparam.txt
```

Some of the more commonly used parameters for SQLIO are discussed in the following table (again, see the readme.txt file or 'SQLIO.exe -?' for a complete list).

Table 2 Commonly used SQLIO.exe options

Option	Description
-o	Number of outstanding I/O requests per thread. When attempting to determine the capacity of a given volume or set of volumes, start with a reasonable number for this and increase until disk saturation is reached (that is, latency starts to increase without an additional increase in throughput or IOPs). Common values for this are 8, 16, 32, 64, and 128. Keep in mind that this setting is the number of outstanding I/Os per thread.
-LS	Instructs SQLIO to capture disk latency information. Capturing latency data is recommended when testing a system.
-k	Specify either R or W (read or write). Both reads and writes should be tested. Keep in mind that the storage array cache may absorb a good amount of write activity and potentially skew results. Ensure that the duration is long enough to saturate the cache in order to get a true measure of storage capacity.
-s	Duration of test (in seconds). For initial tests, running for 5-10 minutes per I/O size is recommended to get a good idea of I/O performance.
-b	Size of the I/O request in kbytes. For random I/O, 8 KB and 64 KB are as many values as are need to be tested. The most common random I/O size for SQL Server is 8 KB. For random I/O, pay close attention to the number of I/Os per second and latency. For sequential I/O, test a range of sizes (4, 8, 16, 32, 64, 128, 256) and pay attention to throughput and latency.
-f	Type of I/O to issue. Either 'random' or 'sequential'.
-F	Name of the file that will contain a list of the test file(s) used by SQLIO.

The sample syntax described in the previous code example and Table 2 will run a test against the drive or drives specified in the param.txt file. This file should reside in the same directory as SQLIO.exe. Here is an example param.txt that tests more than one volume at a time:

```
c:\sqlio_test.dat 4 0x0 100
d:\sqlio_test.dat 4 0x0 100
```

The options on each line of the param.txt file are as follows:

- <Path to test file> Full path and name of the test file to use.
- <Number of threads (per test file)> This has an effect on the amount of outstanding I/Os issued, since the -o parameter is per thread. We have found no significant difference between a single thread with the same number of cumulative I/Os as multiple threads. However, this may not be the case on very high-end storage systems and should be tested.
- «Mask » Set to 0x0
- <Size of test file in MB> Ideally, this should be large enough so that the test file is larger than any cache on the array. For the most accurate results, test files should be approximately the size of planned database files or ideally large enough to fill a significant portion of the underlying disks. Two to four times the size of the storage array controller cache can be used as a rule of thumb if no other better number exists.

Tests should be run multiple times with different parameter files (one for each individual volume and one for each combination of volumes). When testing combinations of volumes, add more volumes on each test until all volumes are used at one time. To comment out a specific test file path, prefix the line with #.

Note SQLIO currently has known issues when multiple threads are used to test many I/O paths at one time. The total number of threads is the cumulative total of threads used for all test files. If too many threads are used during a single test, the tool may experience random failures. Reducing the number of threads per target test file (in the parameter file) is a workaround for this problem.

Interpreting the Results of SQLIO

SQLIO will return and summarize certain performance data during the test run. When running the test you can redirect the output of SQLIO to a text file to capture the performance information. Using the options described in Table 2, SQLIO returns performance statistics for the total throughput (MB/sec), the average disk latency

(milliseconds), and the number of I/Os per second. In most cases this is enough information to get a basic understanding of the system's current I/O performance. If more detailed information is needed, Windows Performance Monitor and/or SAN specific monitoring tools can be used.

When interpreting the results from SQLIO keep in mind the following:

- SQLIO is generally not a CPU-intensive process. However, you should monitor during the run to ensure that there are no CPU bottlenecks, which would skew the results.
- Larger I/O sizes normally result in slightly higher latencies.
- For random I/O, focus on number of I/Os per second and latency. For sequential I/Os, focus mainly on throughput (MB/s) and latency.
- Ideally, you should see some increase in your throughput as you increase the number of volumes being tested at the same time. This is dependent on the underlying storage design and specifically impacted by any spindle sharing between LUNs. You may also see increased total throughput as the size of the I/O is increased. This is, however, dependent on the specifics of your particular configuration.
- When you no longer see increased throughput when increasing the number of outstanding I/Os you probably have saturated the disk, the bandwidth of the channel, or do not have the HBA queue depth setting high enough.
- Save all of the test results. It can be helpful to share the results from your SQLIO tests with your storage vendor since the vendor has detailed knowledge about how the equipment should perform for different I/O types, RAID levels, and so on. This data will also be valuable if troubleshooting I/O problems in the future.
- If you have multiple HBAs or multipathing software in use on the host, ensure that both paths are functionally working and, ideally, that the cumulative bandwidth of the HBAs can be exhausted. One test approach to exhaust bandwidth resources between the host and storage is to use very small test files (100 MB) for SQLIO so that they reside in the cache of the storage array (that is, 100 MB). Sequential I/O issued against these small test file(s) should saturate the bandwidth of the paths and allow one to determine if there are any issues related to bandwidth. When running a test such as this, look at the cumulative MB/s attainable and related this number to the number and bandwidth of HBAs. Ideally, you should be able to almost completely saturate the cumulative bandwidth of the number of HBAs in the host.
- If test results vary wildly, check to determine if you are sharing spindles with others on the array.
- Monitoring at host and on the array during tests is ideal for complete analysis. This provides more insight into actual limiting hardware resource (disk, fiber channel (FC) ports, service processors, and so on). Monitoring strategies using System Monitor are discussed in the next section.

↑ Top of page

Monitoring I/O Performance Using System Monitor

The Windows System Monitor tool can be used to get detailed information about I/O performance on a system. Table 3 contains detailed information specific to the I/O counters you should consider monitoring and how to interpret them. These counters can be captured by monitoring either Physical or Logical Disk counters. The choice of which object to use should be based on the specific storage configuration that is being tested.

Table 3 I/O related performance counters and their meanings

Disk Reads/sec & Disk Writes/sec Average Disk/sec Read & Average Disk/sec Write	Number of I/Os per second (IOPs) being issued against a particular disk or volume. This number varies based on the size of I/Os issued. Consult the hardware vendor for an estimation of the number of I/Os per second support per spindle on their particular hardware.	
Avorago Dick/soc Boad & Avorago Dick/soc Write	spiritule off their particular flatuware.	
Average Disk/sec Read & Average Disk/sec Wille	Measure of disk latency. Lower values are better but this can vary and is dependent on the size and nature of the I/Os being issued. Numbers also vary across different storage configurations (cache size/utilization can impact this greatly). On well-tuned I/O subsystems, ideal values would be: 1–5 ms for Log (ideally 1 ms on arrays with cache) 4–20 ms for Data on OLTP systems (ideally 10 ms or less) 30 ms or less on DSS (decision support system) type. Latencies here can vary significantly depending on the number of simultaneous queries being issued against the system. Sustained values of more than this when the total throughput is less than expected should be investigated. Consider these in combination with what is normal for your particular system. Make sure to monitor disk latencies for trend analysis. The number of I/Os and latency specific to SQL Server data files can be found by using the sys.dm_io_virtual_file_stats dynamic management view in SQL Server 2005.	
Average Disk Bytes/Read & Average Disk Bytes/Write	Size of I/Os being issued. This value may impact disk latency and larger I/Os may result in slightly higher latency. When used to monitor SQL Server, this will tell you the average size of the I/Os SQL Server is issuing.	
Average Disk Queue Length	Average number of outstanding I/O requests. The general rule of thumb is <=2 per spindle but this may be hard to measure due to storage virtualization, differences in RAID level between configurations, and so on. Focus on higher than average disk queue length in combination with higher than average disk latencies. This combination could indicate that the storage array cache is being over utilized or spindle sharing with other applications is impacting performance.	
Disk Read Bytes/sec & Disk Write Bytes/sec	Measure of the total bandwidth for a particular disk or LUN.	

It is important to note that while System Monitor provides a very accurate picture of your I/O subsystem's current performance, it may not provide enough information to successfully resolve all I/O performance issues in SAN environments. System Monitor can be used to diagnose I/O performance problems; however, resolution may lie in the storage array or in the HBA driver level, which can be more challenging to diagnose.

The ability and level of disk array monitoring varies from vendor to vendor but most, if not all storage vendors, offer some type of array-based monitoring. Longer test runs may be needed to capture performance information within the storage array. This is dependent on the frequency at which those tools capture data. It is advised that you familiarize yourself with the monitoring capabilities of your specific storage array. Some specific points of interest when monitoring storage arrays are FC port(s) utilization, write pending levels, % cache utilization, processor utilization for the internal controllers, LUN activity, and physical disk activity. All of these are potential bottlenecks for performance.

↑ Top of page

Conclusion

I/O performance is critical to any SQL Server deployment. Validating the performance of the underlying disk subsystem should be considered a best practice prior to deploying SQL Server applications. The time it takes to perform these tests will expose any issues prior to the deployment and avoid troubleshooting after the complexity of a SQL Server application is introduced. This practice is especially important for systems with large-scale I/O subsystems.

↑ Top of page

Resources

SQLIO Disk Subsystem Benchmark Tool (Microsoft Download Center)

 $\underline{\text{How to use the SQLIOSim utility to simulate SQL Server activity on a disk subsystem}}. (\textbf{Knowledge Base article})$

IOMeter (IOMeter site)

SQL ISV blog (Microsoft SQL ISV Program Management Team)

<u>SQL Server CAT Blog</u> (Microsoft SQL Server Development Customer Advisory Team)

SQL Server Best Practices (TechNet site)

SQL Server AlwaysOn Partner Program (Microsoft SQL Server site)

 $\underline{\mathsf{SQL}\;\mathsf{Server}\;\mathsf{Urban}\;\mathsf{Legends}}\;\mathsf{(Product\;\mathsf{Services}\;\mathsf{and}\;\mathsf{Support}\;\mathsf{(PSS)}\;\mathsf{Engineers}\;\mathsf{blog)}$

SQL Server 2000 I/O Basics white papers

- SQL Server 2000 I/O Basics
- SQL Server I/O Basics, Chapter 2

<u>Disk Subsystem Performance Analysis for Windows</u> (Windows Hardware Developer Center)

Storport in Windows Server 2003: Improving Manageability and Performance in Hardware RAID and Storage Area Networks. (Windows Storage Server white paper)

↑ Top of page

Manage Your Profile

© 2008 Microsoft Corporation. All rights reserved. Terms of Use | Trademarks | Privacy Statement

Microsoft