

C/C++ Program Design

CS205

Prof. Shiqi Yu (于仕琪)

yusq@sustech.edu.cn

http://faculty.sustech.edu.cn/yusq/





Integer Numbers



• int is the most frequently used integer type

```
int i; //declare a variable
int j = 10; //declare and initialize
int k;
k = 20; //assign a value
```

- Remember to initialize a variable!
- Will the compiler give an error?

```
int i;
cout << i; //what is i's value?
random value according to the architecture
```





Variable Initialization

init.cpp

```
#include <iostream>
using namespace std;
int main()
{
  int num1; //bad: uninitialized variable
  int num2; //bad: uninitialized variable
  cout << "num1 = " << num1 << endl;
  cout << "num2 = " << num2 << endl;
}</pre>
```

```
yushiqi: examples $ g++ init.cpp
yushiqi: examples $ file a.out
a.out: Mach-0 64-bit executable x86_64
yushiqi: examples $ ./a.out
num1 = 2
num2 = 84402213
```

```
yushiqi: examples $ g++ init.cpp
yushiqi: examples $ file a.out
a.out: Mach-O 64-bit executable arm64
yushiqi: examples $ ./a.out
num1 = 0
num2 = 0
```

- Uninitialized variables may have random values
- The behavior depends on the compiler, Clang (x86 64) and Clang (arm64) in the demo.
- Please initialize variables EXPLICITLY!



How to initialize

```
int num;
num = 10;//do not forget this line
int num = 10;
int num (10);
int num {10};
```





Overflow

overflow

3,224,990,521							
AC	⁺/-	%	÷				
7	8	9	×				
4	5	6	-				
1	2	3	+				
0			=				

```
int a = 56789;
int b = 56789;
int c = a * b;
cout << c << endl;</pre>
```

overflow.cpp

The output is a negative number!

-1069976775

Because 56789 is 0xDDD5, 16 bits

The correct result is 3,224,990,521 (0x CO 39 73 39).

The sign bit is 1!





signed and unsigned

The following code can give the correct answer.

```
unsigned int a = 56789;
unsigned int b = 56789;
unsigned int c = a * b;

31 30 29 28 27 26 25 24 23 22 21 20 19 18 17 16 15 14 13 12 11 10 9 8 7 6 5 4 3 2 1 0
signed int
unsigned int
```

- signed int can be shorten as int. Its range is [-2³¹, 2³¹-1] if it's 32-bit.
- unsigned int: Its range is [0, 2³²-1] if it's 32-bit.
- 32 bits for most modern systems, 16 for some old ones.





Different Data Types for Integer

- use long int for longer integers.
- use short int for shorter integers.
- and long long

But

C and C++ standards do not fix the widths of them



https://en.cppreference.com/w/cpp/language/types

						htt
Type specifier	Equivalent type	Width in bits by data model				
Type specifier	Equivalent type	C++ standard	LP32	ILP32	LLP64	LP64
short		at least 16	16	16	16	16
short int	short int					
signed short	SHOLC THE					
signed short int						
unsigned short	unsigned short int					
unsigned short int	unsigned short int					
int		at least 16	16	32	32	32
signed	int					
signed int						
unsigned	unsigned int					
unsigned int	unsigned int					
long		at least 32	32	32	32	64
long int	long int					
signed long	long int					
signed long int						
unsigned long	uncianed long int					
unsigned long int	unsigned long int					
long long		at least 64	64	64	64	64
long long int	long long int					
signed long long	(C++11)					
signed long long int						
unsigned long long	unsigned long long int					
<pre>unsigned long long int</pre>	(C++11)					
BY NC SA						

- Width in bits of different data models
- sizeof operator can return the width in bytes.



sizeof



It is an operator, not a function!

```
size.cpp
int i = 0;
short s = 0;
cout << "sizeof(int)=" << sizeof(int) << endl;
cout << "sizeof(i)=" << sizeof(i) << endl;
cout << "sizeof(short)=" << sizeof(s) << endl;
cout << "sizeof(long)=" << sizeof(long) << endl;
cout << "sizeof(size_t)=" << sizeof(size_t) << endl;</pre>
```





More Integer Types







- char: type for character, 8-bit integer indeed!
- signed char: signed 8-bit integer
- unsinged char: unsigned 8-bit integer
- char: either signed char or unsinged char





Integers and characters

- How we represent a character?
 - Use an 8-bit integer

```
char.cpp
char c1 = 'C';
char c2 = 80;
char c3 = 0x50;
```

+ Cl print integer

Chinese characters?

unicode

char32-t



bool

C股有 bool 数据类型

- A C++ keyword, but not a C keyword
- bool width: 1 byte (8 bits), NOT 1 bit!
- Value: true (1) or false (0)

What is the output?

```
bool.cpp
bool b = true;
int i = b;
cout << "i=" << i << endl;
cout << "b=" << b << endl;</pre>
```





bool

• Boolean data conversion

```
bool b = true;
int i = b; // the value of i is 1.
bool b = -256; // unrecommended conversion. the value of b is true
bool b = (-256 != 0); // better choice
```





Boolean in C

Use typedef to create a type

typedef char book #define true 1 #define false 0



• Defined in stdbool.h since C99

#include <stdbool.h>



SOUTHERN AND SECONDARY OF SCIENCE AND SECONDAR

size_t

- Computer memory keeps increasing
- 32-bit int was enough in the past to for data length
- But now it is not.

size t:

- Unsigned integer
- Type of the result of sizeof operator
- Can store the maximum size of a theoretically possible object of any type
- 32-bit, or 64-bit

Size-t

价为存内存大小





Fixed width integer types (since C++11)

Defined in <cstdint>

```
int8 t
int16 t
int32 t
int64 t
uint8 t
uint16 t
uint32 t
uint64 t
```

Some useful macros

```
INT8_MIN
INT16_MIN
INT32_MIN
INT64_MIN
INT8_MAX
INT16_MAX
INT32_MAX
INT32_MAX
INT64_MAX
```

intmax.cpp

```
#include <iostream>
#include <cstdint>
using namespace std;
int main()
{
    cout << "INT8_MAX=" << INT8_MAX << endl;
}</pre>
```





Choose appropriate integer types

- Wider integers consume more memory, and slower sometimes
- char(byte) is widely used for image pixels
- Choose a data type carefully, and consider all possibilities (short for wide dynamic range images)







Floating-point Numbers



SOUTHERN OLD SCIENCE WIND AS CONTOUNDED TO SCIENCE WIND AS CONTOUN

What's the output?

```
float.cpp
#include <iostream>
#include <iomanip>
using namespace std;
int main()
  float f1 = 1.2f;
  float f2 = f1 * 100000000000000; //1.0e15
  cout << std::fixed << std::setprecision(15) << f1 << endl;</pre>
  cout << std::fixed << std::setprecision(15) << f2 << endl;</pre>
  return 0;
```





• How many numbers in range [0, 1]?

Infinite!

12011年在第四实教

How many numbers can 32 bits represent?

2³²

3.2位表示在一次数

• You want 1.2, but float can only provide you 1.200000047683716...







Understanding Computing


- Are computers always accurate? 光流光光光光差
- Floating-point operations always bring some tiny errors.
- Those errors cannot be eliminated.
- What we can do: to manage them not to cause a problem.





Floating-point types

float: single precision floating-point type, 32 bits



- double: double precision floating-point type, 64 bits
- Ing double: extended precision floating-point type
 - > 128 bits if supported
 - 64 bits otherwise
- half precision floating-point, 16 bits (popular in deep learning, but not a C++ standard)





Floating-point VS integers

- Represent values between integers
- A much greater range of values
- Floating-point operations are slower than integer operations
- double operations is slower than float





Precision

Will f2 be greater than f1?

```
precision.cpp
float f1 = 2.34E + 10f;
float f2 = f1 + 10; // but f2 = f1
```

• Why?

 Can we use == operator to compare two floating point Jahs(fi-fs) L FLT EPSILON

numbers?



inf and nan

What will f1 and f2 be?

- \pm inf: infinity (Exponent=11111111, fraction=0)
- nan: not a number (Exponent=11111111, fraction!=0)





Arithmetic Operators





Constant numbers

```
95 // decimal
0137// octal
0x5F // hexadecimal
```

```
6.02e23 // 6.02 x 10^23
1.6e-19 // 1.6 x 10^-19
3.0 // 3.0
6.02e23L // long double
6.02e23f // float
```

3.14159 // 3.14159

```
95 // int
95u // unsigned int
951 // long
95ul // unsigned long
95lu // unsigned long
```

```
6.02e23 // double
```





const type qualifier

```
const float pi = 3.1415926f;
pi += 1; //error!
```

- If a variable/object is const-qualified, it cannot be modified.
- It must be initialized when you define it.





auto (since C++11)

auto is placeholder type specifier.

The type of the variable will be deduced from its initializer.

```
auto a = 2; // type of a is int
auto bc = 2.3; // type of b is double
auto c; //valid in C, error in C++
auto d = a * 1.2;
```

• Question:

```
auto a = 2; // type of a is int
// will a be converted to a
// double type variable?
a = 2.3;
```

No! 2.3 will be converted to a int 2, then assigned to a





Arithmetic operators

Operator name	Syntax
unary plus	+a
unary minus	- a
addition	a + b
subtraction	a - b
multiplication	a * b
division	a / b
modulo	a % b
bitwise NOT	~a
bitwise AND	a & b
bitwise OR	a b
bitwise XOR	a ^ b
bitwise left shift	a << b
bitwise right shift	a >> b

Operator Precedence
 If you cannot remember the precedence, use parentheses!

- > a++
- > ++a
- ***** /
- **>** + -
- > << >>



Other operators

Assignment Operators

Nooiginilent Operati

$$a += b$$

$$a *= b$$

$$a /= b$$

$$a \&= b$$

$$a ^= b$$

$$a >>= b$$

Increment/decrement

```
a++
```

```
int a = 3;
int b = a++; // What's the value of b?
int c = ++a; // What's the value of c?
```





Data type conversions

conversion.cpp

```
int num_int1 = 9; // initializing an int value to num_int1
int num_int2 = 'C'; // implicit conversion
int num_int3 = (int)'C'; // explicit conversion, C-style
int num_int4 = int('C'); // explicit conversion, function style
int num_int5 = 2.8; //implicit conversion
float num_float = 2.3; //implicit conversion from double to float
short num_short = 650000;
```


DANGER:

- The source code can be compiled successfully (even with warning messages) when the data types do not match.
- Please use explicit conversion if possible





Data loss



But

```
conversion.cpp
int num_int1 = 100000004;
```

float num_int_float = num_int1;
int num_int2 = (int)(num_int_float);

Will num_int2 be the same with num_int1?





Operator Associativity

- Left-to-right associativity or a right-to-left associativity
 - Ref: https://en.cppreference.com/book/operator_precedence
- The following two lines are equivalent.

```
int i = 17 / 5 * 5;
int i = (17 / 5) * 5;
```





Divisions

- Both operands are integers
 - Perform integer division
 - Any fractional part of the answer is discarded to make the result an integer float f = 17 / 5; // f will be 3.f, not 3.4f.
- One or both operands are floating-point numbers
 - Perform floating-point division float f = 17 / 5.f; // f will be 3.4f.





Distinct Operations for Different Types

- int, long, float, double: four kinds of operations
- If the operands are not the four types, automatic convert their types

```
unsigned char a = 255;
unsigned char b = 1;
int c = a + b; // c = ?
```

- The operands will be converted to one of the four types without losing data: int, long, float, double
 - Ref: https://en.cppreference.com/w/cpp/language/implicit_conversion





C/C++ Supposes

- You (the programmer) are smart enough!
- You know what exactly the source code means!

