Advanced Operating Systems

MS degree in Computer Engineering
University of Rome Tor Vergata

Lecturer: Francesco Quaglia


Trap/interrupt architecture

- 1. Architectural hints
- 2. Relations with software and its layering
- 3. Bindind to the Linux kernel internals


Single-core traditional concepts

- Traditional single-core machines only relied on
 - Traps (synchronous events wrt software execution)
 - ➤Interrupts from external devices (asynchronous events)
- The classical way of handling the event has been based on running operating system code on the **unique CPU-core** in the system (single core systems) upon event acceptance
- This has been enough (in terms of consistency) even for individual concurrent (multi-thread) applications given that the state of the hardware was time-shared across threads

Some more insights




An example with traps (e.g. syscalls)



from this point any time-shared thread sees the correct final state as determined by trap handling

Moving to multi-core systems



This thread does not see state B – what if the TLB on Core-1 caches the same page table (the same state portion) as the one of Core-0??

Core issues

- If the system state is distributed/replicated within in the hardware architecture we need mechanisms for allowing state changes by traps/interrupts to be propagated
- As an example, a trap on Core-0 needs to be propagated to Core-1 etc.
- In some cases this is addressed by pure firmware protocols (such as when the event **is bound to deterministic handling**)
- Otherwise we need mechanisms to propagate and handle the event at the operating system (software) level

The IPI (Inter Processor Interrupt) support

- IPI is a third type of event (beyond traps and classical interrupts) that <u>may trigger the execution of specific</u> operating system software on any CPU-core
- An IPI is a **synchronous event at the sender** CPU-core and an **asynchronous one at the recipient** CPU-core
- On the other hand, IPI is typically used to put in place cross CPU-core activities (e.g. request/reply protocols) allowing, e.g., a specific CPU-core to trigger a change in the state of another one
- Or to trigger a change on the hardware portion only observable by the other CPU-core


Priorities

- IPIs are generated via firmware support, but are finally processed at software level (it becomes an OS matter)
- Classically, at least two priority levels are admitted
 - ✓ High
 - ✓ Low
- High priority leads to immediate processing of the IPI at the recipient (a single IPI is accepted and stands out at any point in time)
- Low priority generally leads to queue the requests and process them via sequentialization

Actual support in x86 machines

- In x86 processors, the basic firmware support for interrupts is the so called APIC (Advanced Programmable Interrupt Controller)
- This offers a local instance to any CPU-core (called LAPIC Local APIC)
- As an example, LAPIC offers a "CPU-core local" programmable timer (for time tracking and time-sharing purposes) the LAPIC-T we already met
- It also offers pseudo-registers to be used for posting IPI requests in the system
- IPI requests travel along an ad-hoc APIC bus

The architectural scheme



The architectural scheme evolution

PIC Intel 8259		IRQ0 - IRQ7					
Two PIC Intel 8259		IRQ0 - IRQ15					
IO-APIC		Max 255 physical hardware IRQ, typical system only around 24 total hardware lines					
IRQ 0	System timer. Reserved for the system. Cannot be changed by a user.						
IRQ 1	Keyboard. Reserved for the system. Cannot be altered even if no keyboard is present or needed.						
IRQ 2	Second IRQ controller. See below for explanation.						
IRQ 3	COM 2(Default) COM 4(User)						
IRQ 4	COM 1(Default) COM 3(User)						
IRQ 5	Sound card (Sound Blaster Pro or later) or LPT2(User)						
IRQ 6	Floppy disk controller						
IRQ 7	LPT1(Parallel port) or sound card (8-bit Sound Blaster and compatibles)						
IRQ 8	Real time clock						
IRQ 9	ACPI SCI or ISA MPU-401						
IRQ 10	Free / Open interrupt / Available						
IRQ 11	Free / Open interrupt / Available						
IRQ 12	PS/2 connector Mouse / If no PS/2 connector mouse is used, this can be used for other peripherals						
IRQ 13	Math co-processor. Cannot be changed						
IRQ 14	Primary IDE. If no Primary IDE this can be changed						
IRO 15	Secondary IDE						

Nomenclature

- IRQ is the actual code associate with the interrupt request (depending on hardware configuration)
- INT in the "interrupt line" as seen by the OS-kernel software
- In the essence INT = F(IRQ)
- The evaluation of the function F is typically hardware specific
- As it will be clear in a few slides, on x86 processors INT = IRQ+32
- This means that the first 32 INT lines are reserved for something else these are the predefined traps of the hardware architecture

I/O APIC insights

- I/O APIC tracks how many CPUs are in the current chipset
- It can selectively direct interrupts to the different CPU-cores
- It uses so called local APIC-ID as an identifier of the core
- Fixed/physical operations
 - ✓ it sends interrupts from certain device to single, predefined core
- Logical/low priority operations
 - ✓ it can deliver interrupts from certain device to multiple cores in a round robin fashion
 - ✓ The destination group is of at most 8 elements (based on internal hardware constraints)

The Linux interface for APIC

- /proc/interrupt tells the actual accounting of the interrupt delivery to the different CPU-cores
- /proc/irq/<IRQ#>/smp_affinity tells what it the affinity of interrupts to CPU-cores in the logical/low priority operating mode
- The actual setup of the I/O APIC working mode is hardcoded into kernel boot rules and is generally observable via the dmesq buffer

Linux core data structures: the IDT

- It is a table of entries that are used to describe the entry point (the GATE) for the handling of any interrupt
- x86 machines have IDTs formed by 256 entries (the max amount of IRQ vectors we can generate with the I/O APIC architecture)
- The actual size and structure of the entries depends on the type of machine we are working on (say 32 vs 64 bit machines)
- Here is a high level view of the actual usage of the entries

Linux IDT bindings

Use

Back here in a while

0-19 (0x0-0x13)

Nonmaskable interrupts and exceptions

20-31 (0x14-0x1f)

Intel-reserved

32-127 (0x20-0x7f) - - - -

External interrupts (IRQs)

128 (0x80)

Programmed exception for system calls (segmented style)

129-238 (0x81-0xee)

External interrupts (IRQs)

239 (0xef)

Local APIC timer interrupt

240-250 (0xf0-0xfa)

Reserved by Linux for future use.

251-255 (0xfb-0xff)

Inter-processor interrupts

The mixture / changes with kernel releases (e.g. 255 is spurious)

What we already saw: idtr

- The **idtr** register (interrupt descriptor table register) keeps on each CPU-core
 - ✓ the IDT <u>virtual address (expressed as up to 6</u>


 <u>bytes 48bit linear address)</u>
 - ✓ The number of entries currently present in the IDT (expressed as 2 bytes up to 256)
- This is a packed structure that we can manipulate with the LIDT (Load IDT) and SIDT (Store IDT) x86 machine instructions

x86 protected mode

- The elements of the IDT are made up by 32-bit data structures
- •In more detail, the data stucture is of type struct desc_struct
- •It is defined in include/asm-i386/desc.h as

```
struct desc_struct {
  unsigned long a,b;
}
```

Structure of the x86 protected mode IDT entry



P Segment Present flag

Selector Segment Selector for destination code segment

D Size of gate: 1 = 32 bits; 0 = 16 bits

Reserved

IDT entry, Interrupt Gates

Name	Bit Full Name		Description					
Offset	4863	Offset 1631	Higher pa	igher part of the offset.				
Р	47	Present	can be set to 0 for unused interrupts or for Paging.					
DPL	45,46	Descriptor Privilege Level	Gate call protection. Specifies which privilege Level the calling Descriptor minimum should have. So hardware and CPU interrupts can be protected from beeing called out of userspace.					
S	44	Storage Segment	= 0 for interrupt gates.					
Туре	4043	Gate Type 03	Ob0101 Ob0110 Ob0111 Ob1110 Ob1111	0x5	5 6 7 14	80386 32 bit Task gate 80286 16-bit interrupt gate 80286 16-bit trap gate 80386 32-bit interrupt gate 80386 32-bit trap gate		
0	3239	Unused 07	Have to be 0.					
Selector	1631	Selector 015	Selector of the interrupt function (to make sense - the kernel's selector). The selector's descriptor's DPL field has to be 0 .					
Offset	015	Offset 015	Lower part of the interrupt function's offset address (also known as pointer).					


Recap on relations with the GDT

• The segment identifier/selector allows accessing the entry of the GDT where we can find the base value for the target segment

• NOTE:

- As we already know, there are 4 valid data/code segments, all mapped to base 0x0
- This is done in order to make <u>LINUX portable on</u> <u>architectures offering no segmentation support</u> (i.e. only offering paging)
- This is one reason why
 - ✓ Protection meta-data are also kept within page table entries
 - ✓ Setting up the offset for a GATE requires a <u>displacement</u> referring to 0x0, which can be denoted to the linker by the & operator

Long mode IDT entry structure




Accessing the gate address (long mode)

```
#define HML TO ADDR(h,m,l) \
   ((unsigned long) (l) | ((unsigned long) (m) << 16) | \
   ((unsigned long) (h) << 32))
gate desc *gate ptr;
gate ptr = .....;
HML TO ADDR (gate ptr->offset high, gate ptr->offset middle,
      gate ptr->offset low);
```

x86 long mode fully new concepts: IST

- The Interrupt Stack Table (IST) is available as an alternative to handle stack switch upon traps/interrupts
- This mechanism unconditionally switches stacks when it is enabled on each individual interrupt-vector basis using a field in the IDT entry
- This means that some interrupt vectors can selectively use the IST mechanism
- IST provides a method for specific interrupts (such as NMI, double-fault, and machine-check) to always execute on a known good stack
- The IST mechanism provides **up to seven IST pointers** in the TSS

A scheme



These are typically the primary stacks (possibly of different size) for processing a given trap/interrupts

Software will then switch to the classical kernel level stack of the running task if nothing prevents it (e.g. a double fault)

Macros for setting IDT entries (x86 protected mode)

Within the arch/i386/kernel/traps.c file we can find the declaration of the following macros that can be used for setting up one entry of the IDT

- > set trap gate(displacement, & symbol name)
- > set intr gate(displacement, & symbol name)
- > set_system_gate(displacement,&symbol_name)
- displacement indicates the target entry of the IDT
- &simbol_name identifies the segment displacement (starting from 0x0) which determines the address of the software module to be invoked for handling the trap or the interrupt

Main differences among the modules

- The set_trap_gate() function initializes one IDT entry such in away to define the value 0 as the privilege level admitted for accessing the GATE via software
- Therefore we cannot rely on the INT assembly instruction unless we are already executing in kernel mode
- The set_intr_gate() function looks similar, however the handler activation relies on interrupt masking
- set_system_gate() is similar to set_trap_gate() however it defines the value 3 as the level of privilege admitted for accessing the GATE

Variants for x86 long mode

CODE SNIPPET FROM desc.h

```
409 /*
410 * This routine sets up an interrupt gate at directory privilege level 3.
411 */
412 static inline void set_system_intr_gate(unsigned int n, void *addr)
413 {
414
        BUG_ON((unsigned)n > 0xFF);
        _set_gate(n, GATE_INTERRUPT, addr, 0x3, 0, __KERNEL_CS);
415
416 }
417
418 static inline void set system trap gate(unsigned int n, void *addr)
419 {
420
        BUG_ON((unsigned)n > 0xFF);
421
        _set_gate(n, GATE_TRAP, addr, 0x3, 0, __KERNEL_CS);
422 }
423
424 static inline void set_trap_gate(unsigned int n, void *addr)
425 {
426
        BUG_ON((unsigned)n > 0xFF);
427
        _set_gate(n, GATE_TRAP, addr, 0, 0, __KERNEL_CS);
428 }
```

i386/kernel-2.4 examples

Handler managing division errors set_trap_gate(0,÷_error)

Handler for non-maskable interrupts set_intr_gate(2,&nmi)

Handler used for dispatching system calls set_system_gate(SYSCALL_VECTOR,&system_call)


Reserved vs available IDT entries

- The entries from 0 to 31 are reserved for handlers that are used to manage specific (predefined) events/conditions (such as divide by 0 or page fault) or are already planned for future use ... these are mostly traps
- This is based on hardware design/requirements
- All the other entries are available for system programming purposes
- As an example, the entry at displacement 0x80 has been traditionally used for kernel level access via system calls
- We note that for some of the reserved entries, microcode tasks generate a so called error-code to be passed to the handler

Reserved vs available IDT entries

- If needed, the handler needs to be structured such in a way to be aware of the production of the error-code
- Particularly, beyond exploiting the error-code value, it needs to remove it from, e.g., the stack right before returning from trap/interrupt (IRET)
- Non-reserved entries area managed by the microcode with no generation of any error-code value

Actions of trap/interrupt handlers



kernel isolation on page tables

CPU snapshot generation on the stack? YES

Management of the presence/absence of error code? YES

Additional stack change? YES/NO

Control passage to a second level handler? Typically YES

Modular handler management: i386 case


- Trap/interrupt handlers are typically defined via ASM code within arch/i386/kernel/entry.S (this file also keeps the specification of the system call dispatcher, which is a trap handler)
- The handlers are managed via an additional dispatcher
- Initially, each handler logs a dummy-value into the stack in case no error-code is generated in relation to the specific trap/interrupt
- Then it logs into the stack the address of the actual handlerfunction (typically written in C)
- In more modern versions we log a VECTOR_INDEX for access to the vector of function pointers

Modular handler management: i386 case

- After, an assembly module, operating the dispatching, is activated
- This logs the CPU context and gives control to the handler via a conventional call
- Given that the input parameters are passed via the stack, the handlers will need to be compiled with asmlinkage directives (or more modern dotraplinkage)
- ... in more modern Linux kernel flavors (<u>e.g. x86 long</u> mode), the layering is a bit more articulated, but the basic concepts are the same
- One thing which is dealth with explicitly is IST and the stack frame redirection


The actual scheme

trap/interrupt



x86-64 early trap/interrupt stack layout details

Interrupt-Handler Stack



Coming from where?

Examples (dated)

```
No error code by firmware
ENTRY(overflow)
      pushl $0
      pushl $ SYMBOL_NAME(do_overflow)
      jmp error_code
ENTRY(general_protection)
      pushl $ SYMBOL_NAME(do_general_protection)
      jmp error_code
ENTRY(page_fault)
      pushl $ SYMBOL_NAME(do_page_fault)
      jmp error_code
```

Error code already posted firmware

The error_code block (still i386 case)

- The assembler code block called error_code is in charge of logging the CPU context into the stack
- This is done by aligning the stack content with the following data structure defined in include/asm-i386/ptrace.h

```
struct pt_regs {
   long ebx; long ecx;
   long edx; long esi;
   long edi; long ebp;
   long eax; int xds; int xes;
   long orig_eax; long eip; int xcs;
   long eflags; long esp; int xss;
}
```

• The actual handler can take as input a pt_regs* pointer and, if needed, an unsigned long representing the error-code

struct pt regs for x86 long mode

```
struct pt regs {
      unsigned long r15; ... unsigned long r12;
      unsigned long bp;
      unsigned long bx; /* arguments: non interrupts/non
tracing syscalls only save up to here*/
      unsigned long r11; ... unsigned long r8;
      unsigned long ax;
      unsigned long cx;
      unsigned long dx;
      unsigned long si;
      unsigned long di;
      unsigned long orig ax; /* end of arguments */ /* cpu
exception frame or undefined */
      unsigned long ip;
      unsigned long cs;
      unsigned long flags;
      unsigned long sp;
      unsigned long ss; /* top of stack page */
```

The page fault handler: main features

- The page fault handler is do_page_fault(struct pt_regs *regs, unsigned long error_code) and is defined in linux/arch/x86/mm/fault.c
- It takes as input the error-code determining the type of the occurred fault, which needs to be handled
- The fault type is specified via the three least significant bits of error code according to the following rules
 - > bit 0 == 0 means no page found, 1 means protection fault
 - bit 1 == 0 means read, 1 means write
 - bit 2 == 0 means kernel, 1 means user-mode

Back to IPI

- Immediate handling is allowed for the case in which there are no data structures that are shared across CPU-cores that need to be accessed for the handling (kind of stateless scenarios)
- An example is the system-halt (e.g. upon panic)
- Other classical usages of IPI are
 - ✓ Execution on a same function across all the CPU-cores (like the halt or the initialization of per-CPU variables)
 - ✓ Change of the state of hardware components across multiple CPU-cores in the system (e.g. the TLB state)
 - ✓ Ask some CPU to preempt the current thread

Actual IPI usage in Linux: a few examples

CALL_FUNCTION_VECTOR

Sent to all CPUs but the sender, forcing those CPUs to run a function passed by the sender. The corresponding interrupt handler is named call_function_interrupt(). Usually this interrupt is sent to all CPUs except the CPU executing the calling function by means of the smp_call_function() facility function.

RESCHEDULE_VECTOR

When a CPU receives this type of interrupt, the corresponding handler, named reschedule_interrupt(), limits itself to acknowledge the interrupt.

INVALIDATE_TLB_VECTOR

Sent to all CPUs but the sender, forcing them to invalidate their Translation Lookaside Buffers. The corresponding handler, named invalidate_interrupt()


Actual IPI API

```
send_IPI_all( )
      Sends an IPI to all CPUs (including the sender)
send IPI allbutself ( )
      Sends an IPI to all CPUs except the sender
send IPI_self( )
      Sends an IPI to the sender CPU
send IPI mask ( )
      Sends an IPI to a group of CPUs specified by a bit mask
```

Sequentialization of IPI management

- The sequentializing approach is used in case the IPI requires managing a shared data structure across the threads
- This is the typical case of an IPI that requires <u>specific</u> parameters for correct management
- These parameters are in fact <u>passed into predetermined</u> <u>memory locations</u> accessible to all the CPU-cores, whose position in memory is predetermined
- The classical case is the one of smp-call-function, whose function pointer and parameter are both passed into a global table

The scheme



```
207 int smp_call_function(void (*_func)(void *info), void *_info, int wait)
208 {
            Can deadlock when called with interrupts disabled */
215
                                                                         Beware this!!
       WARN_ON(irqs_disabled());
216
217
218
         spin_lock_bh(&call_lock);
         atomic set(&scf started, 0);
219
         atomic_set(&scf_finished, 0);
220
         func = func;
221
222
        info = info;
223
224
         for_each_online_cpu(i)
225
             os_write_file(cpu_data[i].ipi_pipe[1], "C", 1);
226
227
         while (atomic_read(&scf_started) != cpus)
228
             barrier();
229
230
        if (wait)
231
             while (atomic_read(&scf_finished) != cpus)
232
                  barrier();
233
234
         spin unlock bh(&call lock);
```

235

return 0;

IPI additional effects

- As noted before, one IPI used by Linux is the reschedule one
- This may lead to preemption of the task running on the CPU-core targeted by the IPI
- This may have effects on both
 - ✓ Correctness/consistency
 - ✓ Performance

Consistency aspects

- What about running a piece of code which is <u>CPU-specific</u> and preemption occur??
- One example

```
struct _the_struct v[NR_CPUS];
v[smp_processor_id()] = some_value; /* task
is preempted here... */ something =
v[smp_processor_id()];
```

We may be targeting different entries

Performance aspects

- smp_call_function() tipcally runs with interrupts allowed ... just remember the deadlock issue!!
- But we cannot risk to have some smp_call_function() runner getting context switched off the CPU
- Otherwise the release of the smp_call_function() resources (e.g. the spinlock) might be delayed
- and we might even deadlock anyhow!!

How to run with interrupts but no actual preemption

- We use per-CPU atomic counters (we already saw)
- If the counter is not zero then no preemption will take place (although we can be targeted by interrupts)
- The check in clearly done via software upon attempting to process the preemption interrupt
- Beware managing the preemption counter explicitly if required!!

Preemption enabling/disabling API recall

```
preempt_enable() // decrement the preempt counter
preempt_disable() // increment the preempt counter
preempt_enable_no_resched() decrement, but do not
immediately preempt

preempt_check_resched() // if needed, reschedule
preempt_count() return the preempt counter
put_cpu() /get_cpu() //decrase/increase the
counter (enable/disable preemption)
```

Variants of each other

Preemption vs SMP function calls

```
int smp call function(void (*func) (void *info), void *info, int
nonatomic, int wait) {
     cpumask t map;
     preempt disable();
     map = cpu online map;
     cpu clear(smp processor id(), map);
        smp call function map(func, info, nonatomic, wait,
                                 map);
     preempt enable();
     return 0;
                                   Internal structure with
```

preemption awareness

Be careful

- IPI is an extremely powerful technology
- However you need to consider scalability aspects
- This leads to conclude that IPI schemes involving large counts of CPU-cores need to be used only when mandatorily needed
- The classical example is when patching the kernel on line, e.g. upon mounting a module