# COMP 3331/9331: Computer Networks and Applications

Week 6
Congestion Control (Transport Layer)

Reading Guide: Chapter 3, Sections: 3.6-3.7

### Transport Layer: Outline


- 3.1 transport-layer services
- 3.2 multiplexing and demultiplexing
- 3.3 connectionless transport: UDP
- 3.4 principles of reliable data transfer

- 3.5 connection-oriented transport: TCP
  - segment structure
  - reliable data transfer
  - flow control
  - connection management
- 3.6 principles of congestion control
- 3.7 TCP congestion control

#### Connection Management

#### before exchanging data, sender/receiver "handshake":

- agree to establish connection (each knowing the other willing to establish connection)
- agree on connection parameters



```
Socket clientSocket =
  newSocket("hostname","port
  number");
```

```
connection state: ESTAB connection Variables:
    seq # client-to-server
        server-to-client
    rcvBuffer size
    at server,client

network
```


```
Socket connectionSocket =
  welcomeSocket.accept();
```


# Initial Sequence Number (ISN)

- Sequence number for the very first byte
- Why not just use ISN = 0?
- Practical issue
  - IP addresses and port #s uniquely identify a connection
  - Eventually, though, these port #s do get used again
  - ... small chance an old packet is still in flight
  - Easy to hijack a TCP connection (security threat)
- TCP therefore requires changing ISN
- Hosts exchange ISNs when they establish a connection

#### Agreeing to establish a connection

#### 2-way handshake:






- Q: will 2-way handshake always work in network?
- variable delays
- retransmitted messages
   (e.g. req\_conn(x)) due to
   message loss
- message reordering
- can't "see" other side

#### Agreeing to establish a connection

#### 2-way handshake failure scenarios:



**ESTAB** 

accept

server

**ESTAB** 


accept

data(x+1)


forgets x

data(x+1)


#### TCP 3-way handshake




# Step 1: A's Initial SYN Packet




## Step 2: B's SYN-ACK Packet



# Step 3: A's ACK of the SYN-ACK



#### TCP 3-way handshake: FSM



#### What if the SYN Packet Gets Lost?

- Suppose the SYN packet gets lost
  - Packet is lost inside the network, or:
  - Server discards the packet (e.g., it's too busy)
- Eventually, no SYN-ACK arrives
  - Sender sets a timer and waits for the SYN-ACK
  - ... and retransmits the SYN if needed
- How should the TCP sender set the timer?
  - Sender has no idea how far away the receiver is
  - Hard to guess a reasonable length of time to wait
  - SHOULD (RFCs 1122,2988) use default of 3 second,
     RFC 6298 use default of 1 second


#### SYN Loss and Web Downloads

- User clicks on a hypertext link
  - Browser creates a socket and does a "connect"
  - The "connect" triggers the OS to transmit a SYN
- If the SYN is lost...
  - 1-3 seconds of delay: can be very long
  - User may become impatient
  - ... and click the hyperlink again, or click "reload"
- User triggers an "abort" of the "connect"
  - Browser creates a new socket and another "connect"
  - Essentially, forces a faster send of a new SYN packet!
  - Sometimes very effective, and the page comes quickly

### TCP: closing a connection


- client, server each close their side of connection
  - send TCP segment with FIN bit = I
- respond to received FIN with ACK
  - on receiving FIN, ACK can be combined with own FIN
- simultaneous FIN exchanges can be handled

#### Normal Termination, One at a Time




TIMED\_WAIT: Can retransmit ACK if last ACK is lost


## Normal Termination, Both Together



#### Simultaneous Closure




## **Abrupt Termination**



- A sends a RESET (RST) to B
  - E.g., because application process on A crashed
- That's it
  - B does not ack the RST
  - Thus, RST is not delivered reliably
  - And: any data in flight is lost
  - But: if B sends anything more, will elicit another RST

#### TCP Finite State Machine



# TCP SYN Attack (SYN flooding)

- Miscreant creates a fake SYN packet
  - Destination is IP address of victim host (usually some server)
  - Source is some spoofed IP address
- Victim host on receiving creates a TCP connection state i.e allocates buffers, creates variables, etc and sends SYN ACK to the spoofed address (half-open connection)
- \* ACK never comes back
- After a timeout connection state is freed
- However for this duration the connection state is unnecessarily created
- Further miscreant sends large number of fake SYNs
  - Can easily overwhelm the victim
- Solutions:
  - Increase size of connection queue
  - Decrease timeout wait for the 3-way handshake
  - Firewalls: list of known bad source IP addresses
  - TCP SYN Cookies (explained on next slide)

#### TCP SYN Cookie

- On receipt of SYN, server does not create connection state
- It creates an initial sequence number (init\_seq) that is a hash of source & dest IP address and port number of SYN packet (secret key used for hash)
  - Replies back with SYN ACK containing init\_seq
  - Server does not need to store this sequence number
- If original SYN is genuine, an ACK will come back
  - Same hash function run on the same header fields to get the initial sequence number (init\_seq)
  - Checks if the ACK is equal to (init\_seq+1)
  - Only create connection state if above is true
- If fake SYN, no harm done since no state was created

http://etherealmind.com/tcp-syn-cookies-ddos-defence/

## Transport Layer: Outline

- 3.1 transport-layer services
- 3.2 multiplexing and demultiplexing
- 3.3 connectionless transport: UDP
- 3.4 principles of reliable data transfer


- 3.5 connection-oriented transport: TCP
  - segment structure
  - reliable data transfer
  - flow control
  - connection management
- 3.6 principles of congestion control
- 3.7 TCP congestion control

#### Principles of congestion control

#### congestion:


- informally: "too many sources sending too much data too fast for network to handle"
- different from flow control!
- manifestations:
  - lost packets (buffer overflow at routers)
  - long delays (queueing in router buffers)
- a top-10 problem!

## Congestion



Incoming rate is faster than outgoing link can support.

## Congestion



Incoming rate is faster than outgoing link can support.

#### Quiz: What's the worst that can happen?





A: This is no problem. Senders just keep transmitting, and it'll all work out.


B: There will be retransmissions, but the network will still perform without much trouble.


C: Retransmissions will become very frequent, causing a serious loss of efficiency


D: The network will become completely unusable













that has no hope of crossing link B.)

Congestion Control 31





#### Without congestion control


#### congestion:

- Increases delivery latency
- Increases loss rate
- Increases retransmissions, many unnecessary
- Wastes capacity of traffic that is never delivered
- Increases congestion, cycle continues ...

## Cost of Congestion

- Knee point after which
  - Throughput increases slowly
  - Delay increases fast

- Cliff point after which
  - Throughput starts to drop to zero (congestion collapse)
  - Delay approaches infinity



This happened to the Internet (then NSFnet) in 1986

- Rate dropped from a blazing 32 Kbps to 40bps
- This happened on and off for two years
- In 1988, Van Jacobson published "Congestion Avoidance and Control"
- The fix: senders voluntarily limit sending rate

### Approaches towards congestion control

two broad approaches towards congestion control:

#### end-end congestion control:

- no explicit feedback from network
- congestion inferred from end-system observed loss, delay
- approach taken by

#### network-assisted congestion control:

- routers provide feedback to end systems
  - single bit indicating congestion (SNA, DECbit, TCP/IP ECN, ATM)
  - explicit rate for sender to send at

### Transport Layer: Outline


- 3.1 transport-layer services
- 3.2 multiplexing and demultiplexing
- 3.3 connectionless transport: UDP
- 3.4 principles of reliable data transfer

- 3.5 connection-oriented transport: TCP
  - segment structure
  - reliable data transfer
  - flow control
  - connection management
- 3.6 principles of congestion control
- 3.7 TCP congestion control

## TCP's Approach in a Nutshell

- TCP connection has window
  - Controls number of packets in flight
- TCP sending rate:
  - roughly: send cwnd bytes, wait RTT for ACKS, then send more bytes

rate 
$$\approx \frac{\text{cwnd}}{\text{RTT}}$$
 bytes/sec



Vary window size to control sending rate

### All These Windows...

- Congestion Window: CWND
  - How many bytes can be sent without overflowing routers
  - Computed by the sender using congestion control algorithm
- Flow control window: Advertised / Receive Window (RWND)
  - How many bytes can be sent without overflowing receiver's buffers
  - Determined by the receiver and reported to the sender
- Sender-side window = minimum(CWND, RWND)
  - Assume for this lecture that RWND >> CWND



- This lecture will talk about CWND in units of MSS
  - (Recall MSS: Maximum Segment Size, the amount of payload data in a TCP packet)
  - This is only for pedagogical purposes

 Keep in mind that real implementations maintain CWND in bytes

## Two Basic Questions

\* How does the sender detect congestion?

How does the sender adjust its sending rate?



## Quiz: What is a "congestion event"

A: A segment loss (but how can the sender be sure of this?)

B: Increased delays

C: Receiving duplicate acknowledgement (s)

D: A retransmission timeout firing

E: Some subset of A, B, C & D (what is the subset?)



### Quiz: How should we set CWND?

A: We should keep raising it until a "congestion event" then back off slightly until we notice no more events.

B: We should raise it until a "congestion event", then go back to I and start raising it again


C: We should raise it until a "congestion event", then go back to median value and start raising it again.

D: We should sent as fast as possible at all times.

### Not All Losses the Same

- Duplicate ACKs: isolated loss
  - dup ACKs indicate network capable of delivering some segments
- Timeout: much more serious
  - Not enough dup ACKs
  - Must have suffered several losses
- Will adjust rate differently for each case

### RECAP: TCP fast retransmit



### Rate Adjustment


- Basic structure:
  - Upon receipt of ACK (of new data): increase rate
  - Upon detection of loss: decrease rate
- How we increase/decrease the rate depends on the phase of congestion control we're in:
  - Discovering available bottleneck bandwidth vs.
  - Adjusting to bandwidth variations

### Bandwidth Discovery with Slow Start (SS)

- Goal: estimate available bandwidth
  - start slow (for safety)
  - but ramp up quickly (for efficiency)
- Consider
  - RTT = 100ms, MSS=1000bytes
  - Window size to fill IMbps of BW = 12.5 packets
  - Window size to fill IGbps = 12,500 packets
  - Either is possible!

### TCP Slow Start

- when connection begins, increase rate exponentially until first loss event:
  - initially cwnd = I MSS
  - double cwnd every RTT
  - Simpler implementation achieved by incrementing cwnd for every ACK received
- summary: initial rate is slow but ramps up exponentially fast



## Adjusting to Varying Bandwidth


- Slow start gave an estimate of available bandwidth
- Now, want to track variations in this available bandwidth, oscillating around its current value
  - Repeated probing (rate increase) and backoff (rate decrease)
  - Known as Congestion Avoidance (CA)
- \* TCP uses: "Additive Increase Multiplicative Decrease" (AIMD)
  - We'll see why shortly...

## AIMD


- approach: sender increases transmission rate (window size), probing for usable bandwidth, until loss occurs
  - additive increase: increase cwnd by I MSS every RTT until loss detected
  - For each successful RTT, cwnd = cwnd +1
  - Simple implementation: for each ACK, cwnd = cwnd + 1/cwnd
  - multiplicative decrease: cut cwnd in half after loss

cwnd: TCP sender

AIMD saw tooth behavior: probing for bandwidth



## Leads to the TCP "Sawtooth"



### Slow-Start vs. AIMD

When does a sender stop Slow-Start and start Additive Increase?

- Introduce a "slow start threshold" (ssthresh)
  - Initialized to a large value
  - On timeout, ssthresh = CWND/2
- When CWND = ssthresh, sender switches from slow-start to AIMD-style increase

## **Implementation**

#### State at sender

- CWND (initialized to a small constant)
- ssthresh (initialized to a large constant)
- [Also dupACKcount and timer, as before]

#### Events

- ACK (new data)
- dupACK (duplicate ACK for old data)
- Timeout

## Event: ACK (new data)

If CWND < ssthresh</p> CWND packets per RTT ■ CWND += + Hence after one RTT with no drops: CWND = 2xCWND

## Event: ACK (new data)

- If CWND < ssthresh</p>
  - CWND += I

Slow start phase

- Else
  - CWND = CWND + I/CWND

"Congestion Avoidance" phase (additive increase)

- CWND packets per RTT
- Hence after one RTT with no drops:

CWND = CWND + I


## Event: dupACK

- dupACKcount ++
- If dupACKcount = 3 /\* fast retransmit \*/
  - ssthresh = CWND/2
  - CWND = CWND/2

### **Event: TimeOut**

- On Timeout
  - ssthresh ← CWND/2
  - CWND ← I

# Example



Slow-start restart: Go back to CWND = 1 MSS, but take advantage of knowing the previous value of CWND

## One Final Phase: Fast Recovery

The problem: congestion avoidance too slow in recovering from an isolated loss

### Example (window in units of MSS, not bytes)

- Consider a TCP connection with:
  - CWND=10 packets (of size MSS, which is 100 bytes)
  - Last ACK was for byte # 101
    - i.e., receiver expecting next packet to have seq. no. 101
- \* 10 packets [101, 201, 301,..., 1001] are in flight
  - Packet 101 is dropped
  - What ACKs do they generate?
  - And how does the sender respond?

### Timeline

- ACK 101 (due to 201) cwnd=10 dupACK#1 (no xmit)
- ACK 101 (due to 301) cwnd=10 dupACK#2 (no xmit)
- ACK 101 (due to 401) cwnd=10 dupACK#3 (no xmit)
- RETRANSMIT 101 ssthresh=5 cwnd= 5
- ACK 101 (due to 501) cwnd=5 + 1/5 (no xmit)
- ACK IOI (due to 601) cwnd=5 + 2/5 (no xmit)
- ACK 101 (due to 701) cwnd=5 + 3/5 (no xmit)
- ACK 101 (due to 801) cwnd=5 + 4/5 (no xmit)
- ACK 101 (due to 901) cwnd=5 + 5/5 (no xmit)
- ACK 101 (due to 1001) cwnd=6 + 1/5 (no xmit)
- ACK I 101 (due to 101) only now can we transmit new packets
- Plus no packets in flight so ACK "clocking" (to increase CWND) stalls for another RTT

## Solution: Fast Recovery

Idea: Grant the sender temporary "credit" for each dupACK so as to keep packets in flight

- ❖If dupACKcount = 3
  - ssthresh = cwnd/2
  - cwnd = ssthresh + 3
- While in fast recovery
  - cwnd = cwnd + I for each additional duplicate ACK
- Exit fast recovery after receiving new ACK
  - set cwnd = ssthresh

# Example

- Consider a TCP connection with:
  - CWND=10 packets (of size MSS = 100 bytes)
  - Last ACK was for byte # 101
    - i.e., receiver expecting next packet to have seq. no.
       101
- 10 packets [101, 201, 301,..., 1001] are in flight
  - Packet 101 is dropped

### **Timeline**

```
    ACK 101 (due to 201) cwnd=10 dup#1

❖ ACK 101 (due to 301) cwnd=10 dup#2
❖ ACK 101 (due to 401) cwnd=10 dup#3

❖ REXMIT IOI ssthresh=5 cwnd= 8 (5+3)

  ACK 101 (due to 501) cwnd= 9 (no xmit)
ACK 101 (due to 601) cwnd=10 (no xmit)
  ACK 101 (due to 701) cwnd=11 (xmit 1101)
  ACK 101 (due to 801) cwnd=12 (xmit 1201)


❖ ACK 101 (due to 901) cwnd=13 (xmit 1301)

* ACK 101 (due to 1001) cwnd=14 (xmit 1401)
♦ ACK 1101 (due to 101) cwnd = 5 (xmit 1501) ← exiting fast recovery


    Packets | | 101-140 | already in flight

❖ ACK 1201 (due to 1101) cwnd = 5 + 1/5 ← back in congestion avoidance
```

### Summary: TCP Congestion Control




### TCP Flavours



- \* TCP-Tahoe
  - cwnd = I on triple dup ACK & timeout
- \* TCP-Reno
  - cwnd = I on timeout
  - cwnd = cwnd/2 on triple dup ACK
- TCP-newReno
  - TCP-Reno + improved fast recovery
- \* TCP-SACK (NOT COVERED IN THE COURSE)
  - incorporates selective acknowledgements

### TCP/Reno: Big Picture



TD: Triple duplicate acknowledgements TO: Timeout

## Transport Layer: Summary

- principles behind transport layer services:
  - multiplexing, demultiplexing
  - reliable data transfer
  - flow control
  - congestion control
- instantiation, implementation in the Internet
  - UDP
  - TCP

#### next:

- leaving the network "edge" (application, transport layers)
- into the network "core"