




Measuring greenhouse gas fluxes from a salt marsh in Boundary Bay, Delta, BC using the eddy covariance approach. Photo: Tzu-Yi Lu


22 Eddy covariance

Lab visit, Monday March 25th



Science Biologique Pavillion, second floor (near the elevators), room SB-2210

141 Avenue du Président-Kennedy, Montreal Quebec
UQAM



Learning objectives

- Describe the eddy covariance approach & what observations are required to measure flux densities using this approach.
- Describe the equations used to calculate Q_H , Q_E and trace gas fluxes.
- Be able to interpret eddy covariance observations of Net Ecosystem Exchange (NEE).



Measurement of convective fluxes using the EC technique at a salt marsh in Boundary Bay, Delta, BC (Photo: Tzu-Yi Lu, UBC)

Convective transport

Turbulence and the ‘eddies’ transport not only momentum but also heat and mass. Turbulence is the most relevant vertical transport mechanism in the ABL.


Tower with eddy covariance instrumentation



Photo: Nick Lee

Evidence of convective transport in a time series


Simultaneous measurements at 6 heights on a tower of **wind vector** (arrows) and **temperature** (colors)






Test your knowledge (slido)

What temperature profile do those observations correspond to?




Potential temperature increases with height.

A




Potential temperature decreases with height.

B






Joint probability density - $w'T'$ – Day or night? (Slido)




(A) Day

(B) Night




Daytime joint probability density - $w'T'$




$$\overline{w'T'} > 0$$

sensible heat flux
transports energy away
from the surface




Potential temperature
decreases with height.

Fast trace of signals.




Nocturnal joint probability density - $w'T'$



$$\overline{w'T'} < 0$$

sensible heat flux transports energy towards the surface



Covariance and flux densities (1/2)

The vertical flux density of an entity s is defined as

flux density = air density × vertical velocity × concentration of s
(anything $\text{m}^{-2} \text{s}^{-1} = \text{kg m}^{-3} \times \text{m s}^{-1} \times \text{anything kg}^{-1}$)

For some entity s , its average flux density is hence

$$Q_S = \overline{\rho w s}$$

Applying **Reynold's decomposition**, and separate mean flow and turbulent fluctuations:

$$\rho = \bar{\rho} + \rho' \quad w = \bar{w} + w' \quad s = \bar{s} + s'$$

Covariance and flux densities (2/2)

Close to the surface, $\bar{w} \rightarrow 0$ and $\rho' \rightarrow 0$ hence

$$Q_S = \overline{\rho w'(\bar{s} + s')} = \overline{\rho(w' \bar{s} + w' s')}$$

$$Q_S = \overline{\rho(w' \bar{s} + w' s')} = (\overline{\rho w' \bar{s}} + \overline{\rho w' s'}) = \boxed{\rho \overline{w' s'}}$$

\downarrow

$$\frac{\overline{\rho w' \bar{s}}}{\text{since constant} \times w' \rightarrow 0 \text{ (see lecture 18)}} = 0$$


A flux density can be also expressed in terms of the correlation coefficient:

$$Q_S = \rho \overline{w' s'} = \rho r_{ws} \sigma_w \sigma_s$$

$$r_{uw} = \frac{\overrightarrow{u'w'}}{\sigma_u \sigma_w}$$

★ Standard deviation

The eddy-covariance approach (EC)



Source: <https://www.youtube.com/watch?v=CR4Anc8Mkas>

Measuring sensible heat flux density Q_H by EC

The instantaneous sensible heat flux density is (in W m^{-2}):

$$Q_H = C_a T' w'$$

Averaging:

$$\bar{Q}_H = \bar{C}_a \overline{T'w'} = \bar{C}_a \overline{w'T'}$$


Since $C_a = \rho c_p$ we can write:

$$\bar{Q}_H = \rho c_p \overline{w'T'} \quad \star$$

Where c_p is the specific heat of air at constant pressure.

Ultrasonic anemometers measures vertical wind fluctuation w' between 10 to 100 Hz

Thermocouples measures T'





Fine-wire
thermocouple
measures T'



Latent heat flux density Q_E

The instantaneous latent heat flux density is (in W m^{-2}):

$$Q_E = L_v w' \rho'_v$$

Averaging over a longer period results in the covariance ($L_v \sim \text{constant}$):

$$Q_E = L_v \overline{w' \rho'_v} \quad *$$

Here, L_v is the specific heat of vaporization (in J kg^{-1}) and ρ_v **partial density of water vapour** (=**absolute humidity**, in kg m^{-3}).





Vertical wind fluctuation
 w' at 20 Hz

Water vapour fluc-
tuations ρ_v' at 20 Hz

Eddy covariance in Boundary Bay, Delta, BC



https://youtu.be/qhWem_mXyX8

Knox / GEOG 321

Topic 22 - Eddy covariance

360 video of the Boundary Bay EC system

Check out this link:


<https://www.youtube.com/watch?v=63Ho07nCYjY>



Ultrasonic anemometer
measures vertical wind
fluctuations w'

Fast carbon dioxide
analyzer measures
**molar CO₂ density
fluctuations ρ_{CO_2}**
($\mu\text{mol m}^{-3}$)

Fast methane analyzer
measures
**molar CH₄ density
fluctuations ρ_{CH_4}**
($\mu\text{mol m}^{-3}$)



Measuring trace gas fluxes

If we equip an eddy covariance system with an analyzer that measures fast fluctuations of the molar density of any **trace gas ρ_c'** (e.g. $\mu\text{mol m}^{-3}$) we can directly determine the gas-exchange (molar flux) between a land surface and the atmosphere:



$$F_c = \overline{w' \rho'_c}^*$$

↑ ↑ ↓
Molar trace gas flux vertical wind molar density
 $(\mu\text{mol m}^{-2} \text{s}^{-1})$ (m s^{-1}) $(\mu\text{mol m}^{-3})$


To convert a molar trace gas flux to a mass flux, you multiply by the **molar mass \mathcal{M} (g mol $^{-1}$)** of the compound:

$$\text{Mass trace gas flux} \quad \rightarrow \quad F_{m,c} = \mathcal{M} F_c \quad \leftarrow \quad \text{Molar trace gas flux}$$
$$(g \text{ m}^{-2} \text{s}^{-1}) \qquad \qquad \qquad (\text{mol m}^{-2} \text{s}^{-1})$$


Measuring the ‘breathing’ of our biosphere



CARBONIQUE observations



FLUXNET – a global network of EC sites



Visualizing eddy covariance data (30 min avg data)

1. Go to: <https://288-gic-rshiny.geog.mcgill.ca/knox/carbonique/>
2. Plot CO₂ (CO₂ concentration) as the variable
 - What do you see?
3. Now change the variable to FC
 - What do you observe?
4. Create your own plot(s)

Take home points

- By simultaneously measuring vertical wind and a concentration, we can measure turbulent fluxes using the **eddy-covariance** technique.
- Eddy-covariance can be used to directly measure the **sensible heat flux density** using $Q_H = \rho c_p \overline{w' T'}$
- We can track the flux of water vapour and measure the **latent heat flux density** using $Q_E = L_v \overline{w' \rho_v'}$
- To measure **traces gas fluxes** we use the covariance between the molar density and the vertical wind ($w' \rho_c'$)
- Eddy covariance observations can help inform carbon cycle & climate science