Overloaded and Customized new/delete

Overloading operator new

GKxx

July 12, 2022



- 1 new Expressions and operator new
- 2 Overloading operator new
 - Standard Library Version
 - Overloading
- 3 Placement-new
 - Standard Library Versions
 - Customized Versions
- 4 new/delete in Modern C++
 - Sized-delete
 - Alignment-aware new/delete
 - Destroying-delete



new Expressions and operator new

000000

The execution of a new expression takes two steps:

- Allocate a block of memory.
- 2 Construct the object(s) on the allocated memory.

What we can control is the first step.

operator new

Memory allocation is done by a group of functions:

```
// Not inlined, not in any namespace
void *operator new(std::size_t size);
void *operator new[](std::size_t size);
```

- For new Type(args), the memory is allocated by calling operator new(sizeof(Type)) .
- For new Type[n]{initializers}, the memory is allocated by calling operator new[](sizeof(Type) * n).
- * C++17 alignment-aware allocation? Talk later.



new Expressions and operator new

000000

```
void *operator new(std::size_t size);
void *operator new[](std::size_t size);
```

- These two functions **do not know** the type of object(s) to be created.
- operator new[] does not know the number of objects to be created.

new Expressions and operator new

000000

The execution of a delete expression takes two steps:

- 1 Destroy the object. (Not executed by C++20 destroying-delete)
- 2 Deallocate the memory.

What we can control is the second step.

operator delete

Memory deallocation is done by a group of functions:

```
// Not inlined, not in any namespace
void operator delete(void *ptr) noexcept;
void operator delete[](void *ptr) noexcept;
```

- delete ptr deallocates the memory by calling operator delete(ptr).
- delete[] ptr deallocates the memory by calling
 operator delete[](ptr).
- * C++14 sized-deallocation? Talk later.



operator delete

Exceptions are not welcomed!

- All deallocation functions are noexcept, unless specified otherwise in the declaration.
- If a deallocation function terminates by throwing an exception, the behavior is undefined, even if it is declared with noexcept(false).
 - Such exception is not expected to be caught. Stack is possibly not unwound in this case.

new Expressions and operator new

Contents

- 1 new Expressions and operator new
- 2 Overloading operator new
 - Standard Library Version
 - Overloading
- 3 Placement-new
 - Standard Library Versions
 - Customized Versions
- 4 new/delete in Modern C++
 - Sized-delete
 - Alignment-aware new/delete
 - Destroying-delete



Standard operator new

The following functions are *replacable*:

```
void *operator new(std::size_t size);
void *operator new[](std::size_t size);
void operator delete(void *ptr) noexcept;
void operator delete[](void *ptr) noexcept;
```

- Standard versions (normal versions) are defined in standard library file <new>.
- But the compiler will choose the user-defined version if there exists one.
- In this case, they do not constitute redefinition.



Standard Library Version

new Expressions and operator new

Standard operator new

Difference between operator new and malloc?



Standard Library Version

Standard operator new

Difference between operator new and malloc? Basic:

- operator new allocates some memory when size == 1,
 while the behavior of malloc(0) is implementation-defined.
- On failure, operator new throws std::bad_alloc, while malloc returns null pointer.

Standard operator new

A simple operator new that uses malloc for allocation:

```
void *operator new(std::size_t size) {
  if (size == 0)
    size = 1;
  if (auto ptr = std::malloc(size))
    return ptr;
  throw std::bad_alloc{};
}
(Similar for operator new[]...)
```

Standard operator new

In fact, operator new keeps trying to allocate memory and, on failure, does some possible adjustment by calling a **new-handler**, until the allocation succeeds or no new-handler is available.

```
void *operator new(std::size_t size) {
  if (size == 0)
    size = 1;
  while (true) {
    if (auto ptr = std::malloc(size))
        return ptr;
    auto handler = std::get_new_handler();
    if (handler)
        handler();
    else
        throw std::bad_alloc{};
}
```



Standard Library Version

Standard operator delete

Possible implementation of operator delete that uses std::free to deallocate memory:

```
void operator delete(void *ptr) noexcept {
  std::free(ptr);
}
```

- Make sure it is safe to delete a null pointer.
- Similar for operator delete[].

Contents

new Expressions and operator new

- 2 Overloading operator new
 - Standard Library Version
 - Overloading
- - Standard Library Versions
 - Customized Versions
- - Sized-delete
 - Alignment-aware new/delete
 - Destroying-delete



Why Overload them?

Effective C++ Item 50 talks about the following most common reasons:

- To detect usage errors.
- To improve efficiency.
- To collect usage statistics.

Record Allocations

```
void *operator new(std::size_t size) {
  if (size == 0)
    size = 1:
  while (true) {
    if (auto ptr = std::malloc(size)) {
      recorder.add_record(ptr);
      return ptr;
    }
    auto handler = std::get_new_handler();
    if (handler)
      handler();
    else
      throw std::bad_alloc{};
```

Record Allocations

new Expressions and operator new

```
void operator delete(void *ptr) noexcept {
  if (!recorder.find(ptr))
    throw std::invalid_argument
        {"Invalid pointer passed to operator delete"};
  recorder.remove_record(ptr);
  std::free(ptr);
```

Class-specific Versions

```
struct Widget {
  static void *operator new(std::size_t size);
  static void *operator new[](std::size_t size);
  static void operator delete(void *ptr);
  static void operator delete[](void *ptr);
};
```

- When we use new/new[] to create class-type objects, the lookup for operator new/operator new[] begins in the class scope.
- If the new-expression uses the form ::new, the class-scope lookup is **bypassed** and the global version

```
::operator new / ::operator new[] will be called.
```



Class-specific Versions

```
struct Widget {
  static void *operator new(std::size_t size);
  static void *operator new[](std::size_t size);
  static void operator delete(void *ptr);
  static void operator delete[](void *ptr);
};
```

- The keyword static is optional: these functions are always static members.
- Deallocation functions are implicitly noexcept.



Example: Heap_tracked

new Expressions and operator new

This example is from *More Effective C++* Item 27: Requiring or prohibiting heap-based objects.

- dynamic_cast<const void *>(ptr) yields the beginning
 address of the object. (Casting it to void *,
 volatile void * or const volatile void * also work.)
- Track whether an object is heap-based by inheriting Heap_tracked in a mixin style.

•000000

new Expressions and operator new

Contents

- - Standard Library Version
 - Overloading
- 3 Placement-new
 - Standard Library Versions
 - Customized Versions
- - Sized-delete
 - Alignment-aware new/delete
 - Destroying-delete



0000000

new Expressions and operator new

new/delete with Extra Arguments

```
void *operator new(std::size_t size, const std::nothrow_t &) noexcept;
void *operator new[](std::size_t size, const std::nothrow_t &) noexcept;
void *operator new(std::size_t size, void *place) noexcept;
void *operator new[](std::size_t size, void *place) noexcept;

void operator delete(std::size_t size, const std::nothrow_t &) noexcept;
void operator delete[](std::size_t size, const std::nothrow_t &) noexcept;
void operator delete(std::size_t size, void *place) noexcept;
void operator delete[](std::size_t size, void *place) noexcept;
void operator delete[](std::size_t size, void *place) noexcept;
```

0000000

new Expressions and operator new

Standard Library Versions

Non-throwing operator new

```
auto ptr = new (std::nothrow) Type(args);
auto arr = new (std::nothrow) Type[n];
  std::nothrow is a tag of type std::nothrow_t defined in
    <new>.
    namespace std {
      struct nothrow_t {
        explicit nothrow_t() = default;
      };
      extern const nothrow_t nothrow;
    }
```

Standard Library Versions

new Expressions and operator new

Non-throwing operator new

```
auto ptr = new (std::nothrow) Type(args);
auto arr = new (std::nothrow) Type[n];
```

- new (std::nothrow) Type(args) calls operator new(sizeof(Type), std::nothrow) for memory allocation.
- new (std::nothrow) Type[n]{initializers} calls operator new[](sizeof(Type) * n, std::nothrow) for memory allocation.
- Returns null pointer on failure. No exception would be thrown.



0000000

new Expressions and operator new

Non-throwing operator new

Possible implementation:

```
void *operator new(std::size_t size,
                   const std::nothrow_t &) noexcept {
  void *ptr = nullptr;
  trv {
    ptr = ::operator new(size);
  } catch (...) {}
  return ptr;
```

0000000

Placement-new

new Expressions and operator new

```
The "real" placement-new:
```

```
Type *pos1 = somewhere();
new (pos1) Type(args);
Type *pos2 = somewhere_else();
new (pos2) Type [n] \{a, b, c, \ldots\};
```

- No allocation is performed.
- Placement-new is used for construct object(s) on given place.

new Expressions and operator new

Placement-new

Possible implementation:

```
void *operator new(std::size_t, void *place) noexcept {
  return place;
}
void *operator new[](std::size_t, void *place) noexcept {
  return place;
}
```

Notice

These two functions (as well as the corresponding operator deletes) **cannot** be replaced.



000000

new Expressions and operator new

Contents

- - Standard Library Version
 - Overloading
- 3 Placement-new
 - Standard Library Versions
 - Customized Versions
- - Sized-delete
 - Alignment-aware new/delete
 - Destroying-delete



000000

Customized Versions

Customized Arguments

Placement-delete

new Expressions and operator new

Recall the two steps for a new expression:

- Allocate enough memory.
- Construct the object(s).

For a new expression new (args...) Type(ctor_args...), if an exception is thrown during the **second** step:

- The corresponding operator delete is called with ptr, args... passed to it, where ptr is the beginning location of memory allocated in the first step.
- The operator delete deallocates the memory allocated by operator new to ensure memory-safety and exception-safety.



000000

Placement-delete

new Expressions and operator new

Possible implementation for non-throwing new:

```
void operator delete(void *ptr,
                     const std::nothrow_t &) noexcept {
  ::operator delete(ptr);
```

Placement-delete

new Expressions and operator new

Possible implementation for non-throwing new:

```
void operator delete(void *ptr,
                     const std::nothrow_t &) noexcept {
  ::operator delete(ptr);
```

Possible implementation of placement-delete for our customized placement-new:

```
void operator delete(void *ptr,
            long line, const char *file) noexcept {
  log_failure(ptr, line, file);
  ::operator delete(ptr);
```



Placement-delete

new Expressions and operator new

Possible implementation for the real "placement-new"?



Placement-delete

new Expressions and operator new

Possible implementation for the real "placement-new"?

```
void operator delete(void *, void *) noexcept {}
void operator delete[](void *, void *) noexcept {}
```

Placement-new

000000

Placement-delete

new Expressions and operator new

Possible implementation for the real "placement-new"?

```
void operator delete(void *, void *) noexcept {}
void operator delete[](void *, void *) noexcept {}
```

Notice

If no suitable placement-delete is found, no deallocation function would be called, which possibly results in memory leak.

Placement-new 00000

Placement-delete

new Expressions and operator new

```
Which operator delete is called?
auto ptr = new (std::nothrow) Type(args);
delete ptr;
```

Customized Versions

Placement-delete

```
Which operator delete is called?

auto ptr = new (std::nothrow) Type(args);

delete ptr;
```

Answer: **the normal version with no extra arguments.** A placement-**delete** is called only when constructors throw an exception.

Contents

new Expressions and operator new

- - Standard Library Version
 - Overloading
- - Standard Library Versions
 - Customized Versions
- 4 new/delete in Modern C++
 - Sized-delete
 - Alignment-aware new/delete
 - Destroying-delete



new Expressions and operator new

For some kinds of deallocation functions, it might be necessary to know the **size** of the block of memory to be deallocated.

A deallocation function which receives an extra std::size_t parameter is a sized-deallocation function.

Notice

Sized-deallocation function is a **usual** deallocation function. It is not a placement version.

Sized-delete

Before C++14, sized-delete could only be class-scoped static member:

```
struct Widget {
  int x:
  static void operator delete(void *p, std::size_t sz) {
    std::cout << "size == " << sz << '\n':
    ::operator delete(p);
 }
}:
auto ptr = new Widget;
delete ptr;
Output:
size == 4
```

new Expressions and operator new

Before C++14, sized-delete could only be class-scoped static member:

```
struct Widget {
  int x:
  static void operator delete[](void *p, std::size_t sz) {
    std::cout << "size == " << sz << '\n':
    ::operator delete[](p);
 }
}:
auto ptr = new Widget[100];
delete []ptr;
Possible output:
size == 408
```



new Expressions and operator new

If a sized-deallocation function is defined and its corresponding unsized version is not, the sized version is called for a delete-expression to deallocate the memory.

■ The std::size_t argument is passed by the compiler automatically.



new Expressions and operator new

If a sized-deallocation function is defined and its corresponding unsized version is not, the sized version is called for a delete-expression to deallocate the memory.

■ The std::size_t argument is passed by the compiler automatically.

Since C++14, global sized-deallocation functions are also allowed:

```
void operator delete(void *ptr, std::size_t size) noexcept;
void operator delete[](void *ptr, std::size_t size) noexcept;
```



new Expressions and operator new

The compiler may choose to call the sized version **or** the unsized one.

- Clang-14 calls the unsized version by default, even when the sized version is provided.
- Calls to one version must be effectively equivalent to the other version, otherwise the program has undefined behavior.
- The standard library implementations of sized-deallocation functions directly call the unsized versions.



Alignment-aware new/delete

Contents

- - Standard Library Version
 - Overloading
- - Standard Library Versions
 - Customized Versions
- 4 new/delete in Modern C++
 - Sized-delete
 - Alignment-aware new/delete
 - Destroying-delete



Alignment-aware new/delete

Alignment of Objects

Every object type has the **alignment requirement** property, representing the number of bytes between successive addresses at which objects of this type can be allocated.

- Alignment requirement of an object is an integer value of type std::size_t, and is always a power of 2.
- Alignment requirement could be queried with alignof or std::alignment_of.

Alignment of Objects

On 64-bit Ubuntu 20.04:

- alignof(int): 4
- alignof(long): 8
- alignof(char): 1

Alignment of Objects

```
On 64-bit Ubuntu 20.04:
```

```
alignof(int): 4
alignof(long): 8
alignof(char): 1
struct Widget {
  int x;
  char y;
};
```

alignof (Widget) is 4 because x must be placed at 4-byte boundaries.



Alignment of Objects

We may use alignas to set a special alignment requirement:

```
struct alignas(32) Widget {
 // ...
};
```

Alignment of Objects

We may use alignas to set a special alignment requirement:

```
struct alignas(32) Widget {
  // ...
};
```

Some types may have special alignment requirements: Intel intrinsic type __m256 is a 256-bit type and is aligned at 32-byte boundaries.

Alignment-aware Allocation

Since C++17, a group of alignment-aware allocation functions are introduced:

(Together with their deallocation functions and sized-deallocation functions.)

<cstdlib> also introduces std::aligned_alloc.



Alignment-aware Allocation

```
namespace std {
   enum class align_val_t : size_t {};
}
```

- Normal allocation functions allocate objects aligned at __STDCPP_DEFAULT_NEW_ALIGNMENT__ (might be 16).
- If alignof (Type) exceeds the default new alignment, the new-expression calls the alignment-aware operator new and passes alignof (Type) as the second argument. (Similar for array-new.)



Contents

- 1 new Expressions and operator new
- 2 Overloading operator new
 - Standard Library Version
 - Overloading
- 3 Placement-new
 - Standard Library Versions
 - Customized Versions
- 4 new/delete in Modern C++
 - Sized-delete
 - Alignment-aware new/delete
 - Destroying-delete



Destroying-delete

```
namespace std {
   struct destroying_delete_t {
      explicit destroying_delete_t() = default;
   };
   inline constexpr destroying_delete_t
      destroying_delete{}; // a tag
}
struct T {
   void operator delete(T *ptr, std::destroying_delete_t);
   // Together with its sized and alignment-aware versions.
};
```

Destroying-delete

Destroying-delete

If a destroying-delete is defined:

- delete-expressions do not execute the destructor before a call to operator delete.
- The destroying-delete is chosen in preference to the normal operator delete.
- It becomes the responsibility of the destroying-delete to destroy the object correctly.

Destroying-delete

new Expressions and operator new

If a destroying-delete is defined:

- delete-expressions do not execute the destructor before a call to operator delete.
- The destroying-delete is chosen in preference to the normal operator delete.
- It becomes the responsibility of the destroying-delete to destroy the object correctly.

What for? See https://open-std.org/JTC1/SC22/WG21/docs/papers/2017/p0722r1.html.

