CS100 Lecture 2

Variables and Arithmetic Types

Contents

- Variable declaration
- Arithmetic types
 - Bits and bytes
 - Integer types
 - Real floating types
 - Character types
 - Boolean type

Variable declaration

Type of a variable

Every variable in C has a type.

- The type is **fully deterministic** and **cannot be changed**.
- The type is known even when the program is not run.
 - $\circ \Leftrightarrow$ The type is known at **compile-time**.
 - $\circ \Leftrightarrow C$ is statically-typed. $\Leftrightarrow C$ has a static type system.
 - In contrast, Python is dynamically-typed.

*Note: The type of every variable is determined at compile-time except for variable-length arrays (since C99).

Statically-typed vs dynamically-typed

Python: dynamically typed

C: statically-typed

```
a = 42  # Type of a is int.
a = "hello" # Type of a becomes str.

int a = 42; // Type of a is int.
a = "hello"; // Error! Types mismatch!
```

The type of a variable

- can be changed, and
- is not necessarily known until we run the program.

The type of a variable

- is explicitly written on declaration, and
- is known at compile-time, and
- cannot be changed.

A type-related error in C is (usually) a compile error:

• It stops the compiler. The executable will not generated.

Declare a variable

To declare a variable, we need to specify its type and name.

```
Type name;
```

Example:

```
int x;  // Declares a variable named `x`, whose type is `int`.
double y; // Declares a variable named `y`, whose type is `double`.
```

We may declare multiple variables of a same type in one declaration statement, separated by ,:

```
int x, y; // Declares two variables `x` and `y`, both having type `int`.
```

Declare a variable

A variable declaration can be placed

- inside a function, which declares a local variable, or
- outside of any functions, which declares a **global variable**.

```
#include <stdio.h>

int x, y; // global variables

int main(void) {
    scanf("%d%d", &x, &y);
    printf("%d\n", x + y);
}

#include <stdio.h>

int main(void) {
    // local variables in `main`
    int x, y;
    scanf("%d%d", &x, &y);
    printf("%d\n", x + y);
}
```

Local variables vs global variables

Which one do you prefer?

```
#include <stdio.h>

int x, y; // global variables

int main(void) {
    scanf("%d%d", &x, &y);
    printf("%d\n", x + y);
}

#include <stdio.h>

int main(void) {
    // local variables in `main`
    int x, y;
    scanf("%d%d", &x, &y);
    printf("%d\n", x + y);
}
```

What are these variables used for?

```
#include <stdio.h>
// Other #includes
int x, y; // What are these two variables used for?
int moveSpaceShuttle(SpaceShuttle *shuttle, Coord to, Vehicle *by) {
 // 109 lines
int makePreparations(Environment *env, Task tasks[], Time time) {
  // 73 lines
LaunchResult launchSpaceShuttle(SpaceShuttle *shuttle, Task tasks[]) {
 // 35 lines
// Other 136 functions, 3325 lines in total
int main(void) {
  // 120 lines
```

Readability matters

[Best practice] Declare the variable when you first use it!

• If the declaration and use of the variable are too separated, it will become much more difficult to figure out what they are used for as the program goes longer.

[Best practice] Use meaningful names!

- The program would be a mess if polluted with names like a, b, c, d, x, y,
 cnt, cnt_2, flag1, flag2, flag3 everywhere.
- Use meaningful names: sumOfScore , student_cnt , open_success , ...

Readability is very important. Many students debug day and night simply because their programs are not human-readable.

Initialize a variable

A variable can be **initialized** on declaration.

This is syntactically **different** (though seems equivalent) to

```
int x; // Declares `x`, uninitialized.
x = 42; // Assigns 42 to `x`.
```

[Best practice] Initialize the variable if possible. Prefer initialization to later assignment.

⇒ More on initialization in later lectures.

Arithmetic types

Refer to this page for a complete, detailed and standard documentation.

Is intequivalent to \mathbb{Z} ?

• Is there a limitation on the numbers that int can represent?

Is intequivalent to \mathbb{Z} ?

• Is there a limitation on the numbers that int can represent?

Experiment:

```
#include <stdio.h>
int main(void) {
  int x = 1;
  while (1) {
    printf("%d\n", x);
    x *= 2;
    getchar();
  }
}
```

• On 64-bit Ubuntu 22.04 and compiled with GCC 13, after printing 1073741824 (2^{30}) , the output becomes negative, and then 0.

```
1073741824
-2147483648
0
```

Bits and bytes

Information is stored in computers in binary.

• $42_{\text{ten}} = 101010_{\text{two}}$.

A **bit** is either 0 or 1.

• The binary representation of 42 consists of 6 bits.

A **byte** is 8 bits 1 grouped together like 10001001.


- At least 1 byte is needed to store 42.
- ullet At least 3 bytes are needed to store $142857_{
 m ten}=100010111000001001_{
 m two}$

Bits and bytes

Suppose now we have n bits.

- How many different values can be represented?
- What is the largest integer that can be represented?
- How do we represent negative numbers? Non-integer values? ...

A 16-bit number: $45460_{\rm ten} = 1011000110010100_{\rm two}$.



Bits and bytes

Suppose now we have n bits.

- How many different values can be represented?
 - \circ 2^n .
- What is the largest integer that can be represented?

$$\circ \ 2^n - 1 = \underbrace{111 \dots 1}_{n}_{\text{two}}.$$

- How do we represent negative numbers? Non-integer values? ...
 - There are several different signed number representations, among which two's complement is widely used.
 - About floating-point numbers: IEEE754
 - Details are not covered in CS100.

An integer type in C is either **signed** or **unsigned**, and has a **width** denoting the number of bits that can be used to represent values.

Suppose we have an integer type of n bits in width.

- If the type is **signed** 2 , the range of values that can be represented is $\left[-2^{n-1},2^{n-1}-1\right]$.
- If the type is **unsigned**, the range of values that can be represented is $[0, 2^n 1]$.

```
(signed)
                                          unsigned
      short (int)
                                        short (int)
     signed / int /
                                      unsigned (int)
       signed int
  (signed) long (int)
                                    unsigned long (int)
(signed) long long (int)
                                 unsigned long long (int)
```

- The keyword int is optional in types other than int:
 - o e.g. short int and short name the same type.
 - e.g. unsigned int and unsigned name the same type.
- "Unsigned-ness" needs to be written explicitly: unsigned int, unsigned long, ...
- Types without the keyword unsigned are signed by default:
 - e.g. signed int and int name the same type.
 - e.g. signed long int , signed long , long int and long name the same type.

Width of integer types

| type | width (at least) | width (usually) |
|-----------|------------------|-----------------|
| short | 16 bits | 16 bits |
| int | 16 bits | 32 bits |
| long | 32 bits | 32 or 64 bits |
| long long | 64 bits | 64 bits |

- A signed type has the same width as its unsigned counterpart.
- It is also guaranteed that sizeof(short) \leqslant sizeof(int) \leqslant sizeof(long) \leqslant sizeof(long long).
 - sizeof(T) is the number of bytes that T holds.

Implementation-defined behaviors

The standard states that the exact width of the integer types is **implementation-defined**.


- Implementation: The compiler and the standard library.
- An implementation-defined behavior depends on the compiler and the standard library, and is often also related to the hosted environment (e.g. the operating system).

Which one should I use?

int is the most optimal integer type for the platform.

- Use int for integer arithmetic by default.
- Use long long if the range of int is not large enough.
- Use smaller types (short, or even unsigned char) for memory-saving or other special purposes.
- Use unsigned types for special purposes. We will see some in later lectures.

Which one is the real world, the integer types or \mathbb{Z} ?



Real floating types

"Floating-point": The number's radix point can "float" anywhere to the left, right, or between the significant digits of the number.

Real floating-point types can be used to represent some real values.

• Real floating-point types $\neq \mathbb{R}$.

Real floating types

C has three types for representing real floating-point values:

- float : single precision. Matches IEEE754 binary32 format if supported.
- double: double precision. Matches IEEE754 binary64 format if supported.
- long double: extended precision. A floating-point type whose precision and range are at least as good as those of double.

Details of IEEE754 formats are not required in CS100.

Range of values can be found in this table.

Which one should I use?

Use double for real floating-point arithmetic by default.

- In some cases the precision of float is not enough.
- Don't worry about efficiency! double arithmetic is not necessarily slower than float.

Do not use floating-point types for integer arithmetic!

scanf/printf

Refer to the table in this page.

| type | format specifier |
|-----------|------------------|
| short | %hd |
| int | %d |
| long | %ld |
| long long | %11d |

| type | format specifier |
|--------------------|------------------|
| unsigned short | %hu |
| unsigned | %u |
| unsigned long | %lu |
| unsigned long long | %llu |

• %f for float, %lf for double, and %Lf for long double.

Exercise

Write the "A+B" program for real numbers. Which type do you decide to use? How do you read and print the values?

Exercise

Write the "A+B" program for real numbers. Which type do you decide to use? How do you read and print the values?

```
#include <stdio.h>
int main(void) {
  double a, b;
  scanf("%lf%lf", &a, &b);
  printf("%lf\n", a + b);
  return 0;
}
```

Character types

The C standard provides three **different** character types: signed char, unsigned char and char.

```
Let T \in \{ \text{ signed char }, \text{ unsigned char }, \text{ char } \}. It is guaranteed that 1 == \text{sizeof}(T) <= \text{sizeof}(\text{short}) <= \text{sizeof}(\text{int}) <= \text{sizeof}(\text{long}) <= \text{sizeof}(\text{long}) long).
```

T takes exactly 1 byte.

Question: What is the valid range of signed char? unsigned char?

Character types

Question: What is the valid range of signed char? unsigned char?


- ullet signed char : [-128,127].
- ullet unsigned char : [0,255].

What? A character is an integer?

ASCII (American Standard Code for Information Interchange)

A Character is represented in computers as its ASCII code, which is a small integer.

• We only consider the so-called *ASCII characters* here.



A character is **nothing but** an integer! In C, there is no "conversion" between characters and ASCII code!

ASCII (American Standard Code for Information Interchange)

Important things to remember:

- ['0', '9'] = [48, 57].
- ['A', 'Z'] = [65, 90].
- ['a', 'z'] = [97, 122].

Example: Given a lowercase letter, return its uppercase form.

```
char to_uppercase(char x) {
  return x - 32;
}
```

[Best practice] Avoid magic numbers

What is the meaning of 32 here? \Rightarrow a magic number.

```
char to_uppercase(char x) {
  return x - 32;
}
```

Write it in a more human-readable way:

```
char to_uppercase(char x) {
  return x - ('a' - 'A');
}
```

Escape sequence

Some special characters are not directly representable: newline, tab, quote, ...

We use escape sequences, e.g.

| escape sequence | description |
|-----------------|--------------|
| \ | single quote |
| \" | double quote |
| | backslash |

| escape sequence | description |
|-----------------|-----------------|
| \n | newline |
| \r | carriage return |
| \t | horizontal tab |

Character types

char, signed char and unsigned char are three different types.

- Whether char is signed or unsigned is implementation-defined.
- If char is signed (unsigned), it represents the same set of values as the type signed char (unsigned char), but they are not the same type.
 - \circ In contrast, T and signed T are the same type for T \in { short, int, long, long long }.


Character types

For almost all cases, use char (or, sometimes int) to represent characters.

signed char and unsigned char are used for other purposes.

To read/print a char using scanf / printf, use %c.

Sad story: Handling non-ASCII letters? ...





Sad story: Handling non-ASCII letters? ...

Even though the standard provides wchar_t, char8_t (since C23), char16_t and char32_t to handle wide/UTF-8 characters, there are still a lot of problems.

C++23 has some improvement.

That's why Python people laugh at us ...





Boolean type: bool (since C99)

A type that represents true/false, 0/1, yes/no, ...

```
To access the name bool, true and false, <stdbool.h> is needed. (until C23)
```

Example: Define a function that accepts a character and returns whether that character is a lowercase letter.

Before C99, use int, 0 and 1: Since C99, using bool, false and true:

```
int is_lowercase(char c) {
  if (c >= 'a' && c <= 'z')
    return 1;
  else
    return 0;
}</pre>
bool is_lowercase(char c) {
  if (c >= 'a' && c <= 'z')
    return true;
  else
    return false;
}</pre>
```

Boolean type: bool (since C99)

Before C99, use int, 0 and 1:

Since C99, using bool, false and true:

```
int is_lowercase(char c) {
  if (c >= 'a' && c <= 'z')
    return 1;
  else
    return 0;
}</pre>
bool is_lowercase(char c) {
  if (c >= 'a' && c <= 'z')
    return true;
  else
    return false;
}</pre>
```

Both return values can be used as follows:

```
char c; scanf("%c", &c);
if (is_lowercase(c)) {
   // do something when c is lowercase ...
}
```

[Best practice] <u>Simplify your code</u>

Just return the result of the condition expression.

```
int is_lowercase(char c) {
  return c >= 'a' && c <= 'z';
}</pre>
bool is_lowercase(char c) {
  return c >= 'a' && c <= 'z';
}</pre>
```


We will introduce the operators (&& , <= , >=) involved here in later lectures.

Summary

- Variable declaration
 - Type + name
 - Multiple variables in one declaration statement
 - Global vs local
 - Initialization

Summary

Arithmetic types



Summary

- Arithmetic types
 - Width, signed-ness, valid range
 - Which type to choose
 - o Characters: ASCII code, escape sequence
 - Boolean

Notes

- ¹ A byte is 8 bits on most platforms, but we do have exceptions: 36-bit computing.
- ² There are several different signed number representations, but all popular machines and almost all compilers use **two's complement**. Before C23 and C++20, the C/C++ standards allow for all possible representations, so the minimal valid range for a n-bit integer is $\left[-2^{n-1}+1,2^{n-1}-1\right]$, which is the range for *one's complement* and *sign-and-magnitude*. Since C23 and C++20, the only representation allowed is two's complement, so the valid range is guaranteed to be $\left[-2^{n-1},2^{n-1}-1\right]$. In CS100 we still assume that two's complement is used, even though we are based on C17/C++17.