Design note

Project Summary


The Phase 2 of the simulator mainly focus on building these following parts

- The GUI
- The main simulator framework
- The memory
- Registers
- Instructions except trap, float point ops.
- Cache indicator
- Virtual keyboard
- Output box
- Logging box

Project structure


```
- LICENSE
1
   -- README.md
   ├─ document
     └─ project1_planning.md
   ├─ project
   | — simulator_GUI.py //The entrance of code, as well as the GUI codes
6
7
      └─ src
8
        ├─ IPL.txt
                         //the IPL file for loading program
9
         ├─ __init__.py
         10
11
   the project
12
         ├─ cpu.py
                         //Define the cpu Class, the main simulater
   logic happens here
        ├─ memory.py //Define the memeory class
13
                         //predifined mfr errors, to be used in phase3
         ├── mfr.py
14
         — op_code_list.py //a map of all op_codes
15
         ├─ register.py //Define the register class, used to initiate
16
   the registers
       └─ word.py
                         //Define the word Class, which is used to hold
17
   data in both memory and register
   ├── requirements.txt
19
   — setup.py
   └── tests
20
21
      ├─ IPL.txt
```

The GUI



- As can be seen above, main GUI contains all requiring parts of phase3.
- For the simulator part, I've done certain abstractions on the register indicators and the buttons.
 - Each line of register indicator is generated by the class RegisterGUI. This class also provides a method refresh_label allowing us to simply using binary string to refresh the indicator.
 - Each button is generated by class PressButton. This class also provides a method on_click to bind corresponding method calls.
 - When LD button is pressed, the value on the switch will be fetched and stored into the corresponding register. After this progress completes, the GUI will fetch result from the backend and refresh the indicator.
 - When LdFile button is pressed, the simulator will provoke a file selector for user to select the text. And then load the text into the memory start at the value of PC
 - All other button has the same logic: call corresponding backend function, and refresh the indicator upon finish.

0




• Abstraction of register indicators: The register indicators could be represented by the following python dictionary.


```
map_reg_location = {
1
2
       # name:
   x_location,y_location,reg_count,button_function,has_button
3
       "GPRO": [40, 70, 16, cpu_instance.gpr[0].set, True],
       "GPR1": [40, 110, 16, cpu_instance.gpr[1].set, True],
4
       "GPR2": [40, 150, 16, cpu_instance.gpr[2].set, True],
5
       "GPR3": [40, 190, 16, cpu_instance.gpr[3].set, True],
6
       "IXR1": [40, 280, 16, cpu_instance.ixr[1].set, True],
7
       "IXR2": [40, 320, 16, cpu_instance.ixr[2].set, True],
```

```
9
        "IXR3": [40, 360, 16, cpu_instance.ixr[3].set, True],
10
        "PC": [780, 70, 12, cpu_instance.pc.set, True],
11
        "MAR": [780, 110, 12, cpu_instance.mar.set, True],
        "MBR": [660, 150, 16, cpu_instance.mbr.set, True],
12
        "IR": [660, 190, 16, cpu_instance.ir.set, False],
13
14
        "MFR": [1020, 230, 4, cpu_instance.mfr.set, False],
        "CC": [1020, 270, 4, cpu_instance.cc.set, False],
15
16
   }
```

- For console log, it mainly used QTextEditLogger from Pyqt5 to serve as a python log handler. This log box will catch every log the simulator program generated.
- For Output box, it mainly used QTextEditLogger from Pyqt5 to serve as a simulator output. Only out command will output characters into this box.
- For cache indicator, it showed the 16 line of address and value of current cache. And will change color after cache hit/update/replace. Users can change the digit shown in the cache indicator into hexadecimal, binary or decimal by choosing in the ratio button.



• For Keyboard part, The keyboard allows the simulator to request input from user. The keyboard will only be effective when input indicator is on. After user hit a key, the program will continue to run.



The main simulator framework

• The main simulator framework is developed in cpu.py for class CPU.

• Table of data structure in class (CPU)

data	usage		
memory	the memory		
logger	python log stream used to output debug info		
output_log	python log stream used to send output into the output box in GUI		
рс	the pc register		
mar	the mar register		
mbr	the mbr register		
gpr[]	the gpr register in a list		
ixr[]	the ixr register in a list		
СС	the cc register place holder		
mfr	the mfr register		
ir	the ir register		
halt_signal	to indicate if halt or not		
input_signal	used to decide the register to fetch user's input		
run_mode	used to save the run_mode before hitting in command		
cache_display	used to decide the format of cache indicator(HEX/BIN/DEC)		

• Table of method in class CPU

method	usage
init	used to init cpu instance, assigning registers and memory to cpu.
run	used by run button in GUI, to run the program until halt_signal
run_single_cycle	used by SS button in GUI, to run a single instruction
store	used by store button in GUI, to store mbr into memory[mar]
store_plus	used by ST+ button in GUI, to store mbr and add 1 in mar
load	used by load button in GUI, to load memory[mar] to mbr
load_file	used by IdFile button in GUI, to load a text file into memory starting at PC.
get_all_reg	return all register status, used to refresh register indicators in GUI
init_program	reset memory, register, signals and reload program
_get_func_by_op	return specific method to be executed corresponding to the op_code
_get_effective_address	return the effective address according to ix, i, addr value
_hlt	the method to be executed in hlt op_code
_str	the method to be executed in str op_code
_lda	the method to be executed in Ida op_code
_ldx	the method to be executed in ldx op_code
_stx	the method to be executed in stx op_code
_ldr	the method to be executed in ldr op_code
_in	request input from keyboard
_chk	check input device(currently just pass through)
keyboard_input_action	the method for keyboard input, only triggers in input mode. Ignored in running mode
_out	output requested register to device, encoded with ascii

method	usage
_jz	the method to be executed in jz op_code
_jne	the method to be executed in jne op_code
_jcc	the method to be executed in jcc op_code
_jma	the method to be executed in jma op_code
_jsr	the method to be executed in jsr op_code
_rfs	the method to be executed in rfs op_code
_sob	the method to be executed in sob op_code
_jge	the method to be executed in jge op_code
_amr	the method to be executed in amr op_code
_smr	the method to be executed in smr op_code
_air	the method to be executed in air op_code
_sir	the method to be executed in sir op_code
_src	the method to be executed in src op_code
_rrc	the method to be executed in rrc op_code
_mlt	the method to be executed in mlt op_code
_dvd	the method to be executed in dvd op_code
_trr	the method to be executed in trr op_code
_and	the method to be executed in and op_code
_orr	the method to be executed in orr op_code
_not	the method to be executed in not op_code
_trap	the method to be executed in trap op

• The main loop(single step)

- mar = pc
- mbr = memory[mar]
- ir = mbr
- call _get_func_by_op() to get the specific function
- if halt_signal -> return
- if input
 - get input from keyboard
- pc.add(1)

memory

- Memory is implemented in memory.py for class Memory
 - Table of data structure in class Memory

data	usage		
memroy[]	used to contain data		
size	represent the size of memory		
logger	logger for debug info		
cache	cache array initiated with memory		
cache_map	map[address] -> cache_index, used to lookup address in cache		
cache_update_at	used to show which line is last updated		
cache_hit_at	che_hit_at used to show which line is last hit		
cache_replace_at used to show which line is last replaced			

• Table of method in class Memory

method	usage	
validate_addr	used to determine if the address is valid, will trigger MemReserveErr or MemOverflowErr if illegal	
reset	reset all memory to 0, used by pressing button init	
_store(address,value)	store value to address in memory, called by init_program and store_facade	
store_reserved(target,value)	store value to reserved locations	
_load(address)	return memory[address], only called by load_facade	
init_program(file_path)	read from file_path and preload the program into memory	
_malloc_cache_index	return an available slot in the cache, will trigger purge oldest if cache is full	
store_facade	Store value through cache. if cache hit, update cache. Else replace oldest cache.	
load_facade	Load value through cache, if cache hit, directly return. Else load cache and return	

register

- register is implemented in register.py for class Register
 - Table of data structure in class Register

data	usage
value	used to contain data
max	represent the max size of register, will raise a exception if value > max

• Table of method in class Register


method	usage		
init	initiate the register instance		
validate	check if the value has exceeded the max value of register		
set(value)	set the value of the register		
get	return the value of the register		
reset	set register to 0, used by pressing button init		
add(value)	add certain value to register, mainly used by self.pc.add(1) and self.mar.add(1)		
rotate(lr,al,count)	register rotation operation, currently just support logical rotate		
shift(lr,al,count)	register shift operation, currently just support logical shift		

Instructions Implemented


_hlt	the method to be executed in hlt op_code
_str	the method to be executed in str op_code
_lda	the method to be executed in lda op_code
_ldx	the method to be executed in ldx op_code
_stx	the method to be executed in stx op_code
_ldr	the method to be executed in ldr op_code
_in	request input from keyboard
_chk	check input device(currently just pass through)
_out	output requested register to device, encoded with ascii
_jz	the method to be executed in jz op_code
_jne	the method to be executed in jne op_code
_jcc	the method to be executed in jcc op_code
_jma	the method to be executed in jma op_code
_jsr	the method to be executed in jsr op_code
_rfs	the method to be executed in rfs op_code
_sob	the method to be executed in sob op_code
_jge	the method to be executed in jge op_code
_amr	the method to be executed in amr op_code
_smr	the method to be executed in smr op_code
_air	the method to be executed in air op_code
_sir	the method to be executed in sir op_code
_src	the method to be executed in src op_code
_rrc	the method to be executed in rrc op_code
_mlt	the method to be executed in mlt op_code
_dvd	the method to be executed in dvd op_code
_trr	the method to be executed in trr op_code
_and	the method to be executed in and op_code
_orr	the method to be executed in orr op_code
_not	the method to be executed in not op_code
_trap	the trap method

Program 1 Results

• The Program1 will take 20 number and a final input. And output the closest number to the final input in the 20 number. The program output will looks like this.



• As the example above, user has inputted 1 to 20 in the 20 numbers. And entered 5 in the final number(InputU). The program successfully found the closest number 5 and printed it out.



• This is another example during the test of only finding through 3 numbers. As can be seen, the closest number from 6543 is inputA -> 5432

Program1 with comments

```
# Program starts at 0x100
 1
2
    0100 0514 # Load R1 at 0x14
   0101 090C # STR R1 to 0xC
 3
   # ==== start taking number
 4
    0102 3037 # Print
 5
    0103 3038 # Input
 6
    0104 8493 # LDX I2 at 0x13
 7
    0105 050C # Load R1 at 0xC
8
9
    0106 1D01 # Sub 1 from R1
10
    0107 090C # STR R1 to 0xC
    0108 1901 # Add 1 to R1
11
12
   0109 3980 # SOB R1 IXR2 + 0000 -> 0102
    # ===== end 1
13
    010A 0511 # LDr R1, 0011[i] #start of numbers
14
15
    010B 1901 # Add R1,1
   010C 090C # str r1,000C(final address)
16
    010D 1901 # Add R1,1 # now pointing to next number
17
18
    010E 849B # ldx x2 -> loop start(001B)
19
    010F 0414 # Load R0 at 0x14
20 0110 1C01 # sub R0,1
    #=====start cal loop======
21
22
    0111 090F #str r1 to 000F(current address)
    0112 844F # ldx x1 from 000F(current address)
23
   0113 0640 # ldr r2,x1(current value)
24
    0114 0A0B # str r2,000B(save value)
25
26
    0115 162C # smr r2, 000C[i](diff with final)
    0116 0A0A # str r2 to 000A(save diff)
27
28 | 0117 1616 # smr r2, 0016()
29
   0118 0F00 # Add 0 to R3(pass)
30
   0119 298A # jcc: cc=1, x2,09
31
    011A 2C8E #jma #x2, 0E
32
   011B 060A # ldr r2,0,000A
    011C 0A16 # str r2,0,0016 #min_diff(0016) = 000A
33
34
    011D 060B # ldr r2,0,000B
    011E 0A15 # str r2,0,0015 # min_value(0015) = 000B
35
36 | 011F 1901 # Add R1,1
    0120 3880 # SOB RO x2()
37
   #end cal loop=======
38
39 | # reverse output
40 0121 0415 $ LDR RO at 0x15
41
   0122 3039 $ JSR RO at 0x19[i]
```

```
1 | # Subroutine to print "Plz input + sequence"
2
    0400 0B0E # Save R3 to 0x0E
3
   0401 0717 # Load R3 at 0x17 < -0400
   0402 1B07 # Add 7 to R3 <-0407
4
5
    0403 0B0D # Save R3 to 0x0D
    0404 848D # LDX I2 at 0x0D <-0407
6
7
    0405 0C09 # LDA RO with 9
8
   0406 0610 # LDR R2 at 0x10
9
   0407 0A0F # STR R2 to 0x0F
    0408 844F # LDX I1 at 0x0F
10
```

```
11 | 0409 0540 # LDR R1 with I1
    040A C901 # OUTPUT R1
12
    040B 1A01 # Add 1 to R2
13
    040C 3880 # SOB RO IXR2+0000 -< 0407
14
    040D 0512 # LDR r1,12
15
16
    040E 1114 # amr r1,0,14
17
    040F 150C # smr r1,0,0C
   0410 C901 # out put r1
18
    0411 0D0A # LDA r1,0
19
20
    0412 C901 # output r1
21 | 0413 070E # Load R3 at 0x0E
22 | 0414 3400 # Return
```

```
1 # Subroutine to take input
   0210 0B0E # Save R3 to 0x0E
   0211 0718 # Load R3 at 0x18
 3
   0212 1B09 # Add 9 to R3
4
5
   0213 0B0D # Save R3 to 0x0D
    0214 848D # LDX I2 at 0x0D
7
    0215 1B10 # Add 16 to R3
   0216 1B07 # Add 7 to R3
8
9
    0217 0B0F # Save R3 to 0x0F
    0218 84CF # LDX I3 at 0x0F
10
11
    0219 CC00 # CHK keyboard store to R0
    021A 2080 # JZ R0 IXR2
12
    021B C400 # IN Keyboard store to R0
13
    021C 1C0D # R0 -13
14
15
    021D 20C0 # JZ R0 IXR3
16 | 021E 180D # R0 +13
    021F C801 # OUT R0
17
    0220 0511 # LDR R1 at 0x11 # pointer to array
18
   0221 110C # ADD 0xC to R1 # add offset(0xC is the counter of loop)
19
20 | 0222 090B # STR R1 to 0xB
   0223 844B # LDR I1 at 0xB # I1 is the pointer to current number
21
22
    0224 0540 # LDR R1 I1 + 0000
23
   0225 0E0A # LDA R2 with 10
   0226 4180 # MLT # x 10
24
25
    0227 0A0A # STR R2 to 0xA
26
    0228 100A # Add 0xA to R0 # add to input
27
    0229 1COC # Sub 12 from RO
28
   022A 1COC # Sub 12 from RO
29
    022B 1COC # Sub 12 from RO
30
    022C 1COC # Sub 12 from RO #input -48 to value
31
    022D 0840 # Store RO to I1 #final result saved
    022E 2C80 # JMA IXR2
32
    0230 OCOA # LDA RO with \n
33
34
    0231 C801 # OUT R0
35 | 0232 070E # Load R3 at 0x0E
36 | 0233 3400 # Return
```

```
# Subroutine to print a number
2  0240 080F # Save R0 to 0xF
3  0241 0B0F # Save R3 to 0xF #??????
4  0242 0519 # LDR R1 at 0x19 # 240
```

```
5 | 0243 1911 # Add 0x11 to R1 # 251
     0244 090B # Save R1 to 0xB
 7
     0245 844B # LDR IXR1 at 0xB # 251
    0246 190F # Add F to R1 > 260
 8
 9
     0247 1900 # Add 0 to R1
10
     0248 090B # Save R1 to 0xB # 260 -> start of reverse output
     0249 1900 # Add 0 to R1
11
     024A 1900 # Add 0 to R1
12
     024B 0F0A # LDA R3
13
14
     024C CB01 # OUT R3 # output \n
15
     024D 0F00 # LDA R3
16
    024E CB01 # OUT R3 # output null???
     024F 0E0A # LDA R2 with 10
17
18
     0250 0712 # LDR R3 with addr 0012
19
     # ====start stack loop
    0251 0B0e # STR R3 0xe
20
    0252 87ce # LDX I3 0xe
21
22
    0253 4480 # DVD R0/R2
23
    0254 1918 # Add 24 to R1
    0255 1918 # Add 24 to R1
24
     #0256 C921 # OUT R1
25
26
    0256 09C0 # str r1 to addr(I3)
27
     0257 1B01 # air R3,1
    0258 2440 # JNE RO IXR1 # 251
28
29
     # ====endloop
30
     # ===== start output loop perpare=====
    0259 1F00 # sir R3,0
31
    025A 0B0E # str R3,0xe
32
    025B 060e # 1dr R2,0xe
33
34
    025C 1612 # smr R2, 12
     025D 844B # ldx x1,0xb <- start of output loop[260]
 35
36
    025E 1900 # Add 0 to R1
37
     025F 1900 # Add 0 to R1
38
     #=====start reverse output
39
     0260 1F01 # sir R3,1
    0261 0B0E # str R3,0xe
40
     0262 84CE # 1dx x3,0xe
41
42
     0263 04C0 # 1dr r0,x3
     0264 C821 # output r0
43
    0265 3A40 # sob r2,x1
44
     # ====end of output loop
45
46
    0266 070F # Load R3 at 0xF
    0267 3400 # Return
47
```


```
1 # String of "Plz input"
2
    0500 0050
 3
    0501 006C
4
    0502 007A
5
    0503 0020
    0504 0049
6
 7
    0505 006E
8
    0506 0070
9
    0507 0075
    0508 0074
10
11
    0509 000A
```

```
12 050A 0020
13
14 # variables
15 | 000A 0000 # var
16 000B 0000 # var
17 000c 0000 # var
18 | 000D 0000 # var
19 | 000E 0000 # var
20 | 000F 0000 # var
21 0010 0500 # pointer to string "Input"
22 | 0011 0600 # pointer to array list of 20 numbers[601-615]
23
24
25 | 0012 0041 # pointer to A
26
27 | 0013 0102 # pointer to IO loop
28 | 0014 0015 # loop 20 + 1 times
29
30 0015 0000 # var for nearest number
31 0016 FFFF # var for smallest difference
32
33 | 0017 0400 # pointer to print input subroutine
34 0018 0210 # pointer to read input subroutine
35 0019 0240 # pointer to print number subroutine
36 001A 0000
37 | 001B 0111 # start of cal loop
38 001C 010E
39 001D 011F
40 001E 011B
41 001F 011A
```

Program2 result

The program 2 will first need user to load a file into memory using the ldFile button in GUI.

After user set PC to 96 and hits run, the simulator will first output the file and ask user to input



After user input the word and hit enter for confirmation. The program continues to search for the word in the text.

```
when i woke up i was confused.
charlie was waiting up for me.
hepaused outside the door for an instant.
i tried to tell him everything was fine.
i tried again to make my voice clearer.
carlisle will give you something, it will stop.
Please Enter Word:
outside
outside 3 2
```

Like shown above, outside is the second word of the third sentence in the text.

Program2 IPL

```
1 0060 0c0a
2 0061 0e0a
 3 0062 4080
4 0063 0913
 5 0064 8453
6 0065 849e
7 0066 041f
8 0067 141e
9 0068 888b
10 0069 052b
11 006a 060b
12 006b c901
13 006c 1a01
14 006d 0a0b
15 006e 848b
16 006f 3845
17 0070 040c
18 0071 180d
19 0072 c801
20 0073 040c
21 0074 0b1c
22 0075 051c
23 0076 1914
24 0077 090d
25 0078 c400
26 0079 c801
27 007a 1c0d
28 007b 205d
```

```
29 007c 180d
  30
      007d 090b
  31
      007e 082b
  32
     007f 1901
  33
      0080 2c54
  34
      0081 1d01
  35
      0082 090e
  36
     0083 0513
      0084 191f
  37
  38
      0085 1919
  39
      0086 0913
  40 0087 8453
  41 0088 191f
  42
      0089 0913
  43
      008a 8493
  44 008b 1b14
  45
      008c 0b0d
  46 008d 84cd
  47
      008e 88cf
  48 008f 84de
  49
      0090 88d0
  50 0091 061c
  51 0092 051c
  52 0093 071c
  53
      0094 1a01
  54
     0095 1b01
      0096 041c
  55
  56 0097 181f
  57
      0098 1801
      0099 0811
  58
  59
      009a 180e
  60 009b 0812
  61
      009c 0430
  62
      009d 142f
  63
      009e 2482
  64
     009f 050f
  65
      00a0 150e
  66
      00a1 214d
  67
      00a2 050f
     00a3 1901
  68
  69
      00a4 090f
  70
      00a5 0510
  71
      00a6 1901
  72
      00a7 0910
  73
      00a8 2c40
  74
      00a9 040d
  75
      00aa 080f
  76
      00ab 052f
  77
      00ac c901
  78
      00ad 050f
  79
      00ae 1901
  80
      00af 040f
  81
      00b0 090f
  82
      00b1 140e
  83
      00b2 244f
```

```
84 00b3 0511
 85 00b4 c901
 86 00b5 1a1f
 87 00b6 1a11
 88 00b7 ca01
 89 00b8 c901
 90 00b9 1b1f
 91 | 00ba 1b11
 92 00bb cb01
93 00bc 2c9c
 94 00bd 040d
95 | 00be 080f
96 00bf 0430
97 00c0 1411
98 00c1 2097
99 00c2 1011
100 00c3 1412
101 00c4 2090
102 00c5 0410
103 00c6 1801
104 00c7 0810
105 00c8 0430
106 00c9 2440
107 | 00ca 2c9c
108 | 00cb 1a01
109 00cc 0410
110 00cd 1802
111 00ce 0810
112 00cf 071c
113 00d0 1b01
114 00d1 2c40
115 | 00d2 1b01
116 00d3 0410
117 00d4 1801
118 00d5 0810
119 00d6 2c40
```

Program2 instruction

```
1 LDA 0,0,10
 2 LDA 2,0,10
 3 MLT 0,2
 4 STR 1,0,19
5 LDX 1,19
6 LDX 2,30
7 LDR 0,0,31
8 SMR 0,0,30
9 STX 2,11
10 LDR 1,0,11,1
11 LDR 2,0,11
12 OUT 1,1
13 AIR 2,1
14 STR 2,0,11
15
   LDX 2,11
```

```
16 SOB 0,1,5
17
   LDR 0,0,12
18 AIR 0,13
19 OUT 0,1
20 LDR 0,0,12
21 STR 3,0,28
22 LDR 1,0,28
23 AIR 1,20
24 STR 1,0,13
25 IN 0,0
26 OUT 0,1
27 SIR 0,13
28 JZ 0,1,29
29 AIR 0,13
30 STR 1,0,11
31 STR 0,0,11,1
32 AIR 1,1
33 JMA 1,20
34 SIR 1,1
35 STR 1,0,14
36 LDR 1,0,19
37 AIR 1,31
38 AIR 1,25
39 STR 1,0,19
40 LDX 1,19
41 AIR 1,31
42 STR 1,0,19
43 LDX 2,19
44 AIR 3,20
45 STR 3,0,13
46 LDX 3,13
47 STX 3,15
48 LDX 3,30
49 STX 3,16
50 LDR 2,0,28
51 LDR 1,0,28
52 LDR 3,0,28
53 AIR 2,1
54 AIR 3,1
55 LDR 0,0,28
56 AIR 0,31
57 AIR 0,1
58 STR 0,0,17
59 AIR 0,14
60 STR 0,0,18
61 LDR 0,0,16,1
62 SMR 0,0,15,1
63 JNE 0,2,2
64 LDR 1,0,15
65 SMR 1,0,14
66 JZ 1,1,13
67 LDR 1,0,15
68
   AIR 1,1
69 STR 1,0,15
```

70

LDR 1,0,16

```
71 AIR 1,1
 72
    STR 1,0,16
 73
    JMA 1,0
74 LDR 0,0,13
 75
   STR 0,0,15
 76 LDR 1,0,15,1
 77 OUT 1,1
 78 LDR 1,0,15
 79 AIR 1,1
 80 LDR 0,0,15
 81 STR 1,0,15
 82 SMR 0,0,14
83 JNE 0,1,15
 84 LDR 1,0,17
 85 OUT 1,1
 86 AIR 2,31
87 AIR 2,17
 88 OUT 2,1
 89 OUT 1,1
90 AIR 3,31
91 AIR 3,17
92 OUT 3,1
93 JMA 2,28
94 LDR 0,0,13
95 STR 0,0,15
96 LDR 0,0,16,1
97 SMR 0,0,17
98 JZ 0,2,23
99 AMR 0,0,17
100 SMR 0,0,18
101 JZ 0,2,16
102 LDR 0,0,16
103 AIR 0,1
104 STR 0,0,16
105 LDR 0,0,16,1
106 JNE 0,1,0
107
    JNE 0,1,0
108 JMA 2,28
109 AIR 2,1
110 LDR 0,0,16
111 AIR 0,2
112 STR 0,0,16
113 LDR 3,0,28
114 AIR 3,1
115 JMA 1,0
116 AIR 3,1
117 LDR 0,0,16
118 AIR 0,1
119 STR 0,0,16
120 JMA 1,0
```