### **Virtual Memory: Concepts**

**Computer Systems** 

Nov. 1, 2017

Troels Henriksen


#### Based on slides by:

Randal E. Bryant and David R. O'Hallaron

# **Today**


- Address spaces
- VM as a tool for caching
- VM as a tool for memory management
- VM as a tool for memory protection
- Address translation

### A System Using Physical Addressing



Used in "simple" systems like embedded microcontrollers in devices like cars, elevators, and digital picture frames

# A System Using Virtual Addressing



- Used in all modern servers, laptops, and smart phones
- One of the great ideas in computer science

#### **Address Spaces**

Linear address space: Ordered set of contiguous non-negative integer addresses:

$$\{0, 1, 2, 3 \dots\}$$

- Virtual address space: Set of N = 2<sup>n</sup> virtual addresses {0, 1, 2, 3, ..., N-1}
- Physical address space: Set of M = 2<sup>m</sup> physical addresses {0, 1, 2, 3, ..., M-1}

### Why Virtual Memory (VM)?

- Uses main memory efficiently
  - Use DRAM as a cache for parts of a virtual address space
- Simplifies memory management
  - Each process gets the same uniform linear address space
- Isolates address spaces
  - One process can't interfere with another's memory
  - User program cannot access privileged kernel information and code

# **Today**

- Address spaces
- VM as a tool for caching
- VM as a tool for memory management
- VM as a tool for memory protection
- Address translation

#### **DRAM Cache Organization**


- DRAM cache organization driven by the enormous miss penalty
  - DRAM is about 10x slower than SRAM
  - Disk is about 10,000x slower than DRAM

#### Consequences

- Large page (block) size: typically 4 KB, sometimes 4 MB
- Fully associative
  - Any VP can be placed in any PP
  - Requires a "large" mapping function different from cache memories
- Highly sophisticated, expensive replacement algorithms
  - Too complicated and open-ended to be implemented in hardware
- Write-back rather than write-through


# **Enabling Data Structure: Page Table**

- A page table is an array of page table entries (PTEs) that maps virtual pages to physical pages.
  - Per-process kernel data structure in DRAM




#### Page Hit

Page hit: reference to VM word that is in physical memory (DRAM cache hit)




#### Page Fault


Page fault: reference to VM word that is not in physical memory (DRAM cache miss)




Page miss causes page fault (an exception)




- Page miss causes page fault (an exception)
- Page fault handler selects a victim to be evicted (here VP 4)



- Page miss causes page fault (an exception)
- Page fault handler selects a victim to be evicted (here VP 4)




- Page miss causes page fault (an exception)
- Page fault handler selects a victim to be evicted (here VP 4)
- Offending instruction is restarted: page hit!



#### **Allocating Pages**

Allocating a new page (VP 5) of virtual memory.



#### Locality to the Rescue Again!


- Virtual memory seems terribly inefficient, but it works because of locality.
- At any point in time, programs tend to access a set of active virtual pages called the working set
  - Programs with better temporal locality will have smaller working sets
- If (working set size < main memory size)</p>
  - Good performance for one process after compulsory misses
- If (SUM(working set sizes) > main memory size )
  - Thrashing: Performance meltdown where pages are swapped (copied) in and out continuously

# **Today**

- Address spaces
- VM as a tool for caching
- VM as a tool for memory management
- VM as a tool for memory protection
- Address translation


### VM as a Tool for Memory Management

- Key idea: each process has its own virtual address space
  - It can view memory as a simple linear array
  - Mapping function scatters addresses through physical memory
    - Well-chosen mappings can improve locality



#### VM as a Tool for Memory Management

- Simplifying memory allocation
  - Each virtual page can be mapped to any physical page
  - A virtual page can be stored in different physical pages at different times
- Sharing code and data among processes
  - Map virtual pages to the same physical page (here: PP 6)



Memory invisible to

user code

%rsp

(stack pointer)

# **Simplifying Linking and Loading**

#### Linking

- Each program has similar virtual address space
- Code, data, and heap always start at the same addresses.

#### Loading

- execve allocates virtual pages for .text and .data sections & creates PTEs marked as invalid
- The .text and .data sections are copied, page by page, on demand by the virtual memory system

brk **Run-time heap** (created by malloc) Loaded Read/write segment from (.data, .bss) the **Read-only segment** executable (.init,.text,.rodata) file 0x400000 Unused 0 21

**Kernel virtual memory** 

User stack (created at runtime)


Memory-mapped region for shared libraries

# **Today**

- Address spaces
- VM as a tool for caching
- VM as a tool for memory management
- VM as a tool for memory protection
- Address translation

#### VM as a Tool for Memory Protection

- Extend PTEs with permission bits
- MMU checks these bits on each access



# **Today**

- Address spaces
- VM as a tool for caching
- VM as a tool for memory management
- VM as a tool for memory protection
- Address translation

#### **VM Address Translation**

- Virtual Address Space
  - $V = \{0, 1, ..., N-1\}$
- Physical Address Space
  - $P = \{0, 1, ..., M-1\}$
- Address Translation

MAP: 
$$V \rightarrow P \cup \{\emptyset\}$$

- For virtual address a:
  - MAP(a) = a' if data at virtual address a is at physical address a' in P
  - MAP(a) = Ø if data at virtual address a is not in physical memory
    - Either invalid or stored on disk

# **Summary of Address Translation Symbols**

#### Basic Parameters

- **N** =  $2^n$ : Number of addresses in virtual address space
- M = 2<sup>m</sup>: Number of addresses in physical address space
- **P** = **2**<sup>p</sup> : Page size (bytes)


#### Components of the virtual address (VA)

- **TLBI**: TLB index
- TLBT: TLB tag
- VPO: Virtual page offset
- **VPN**: Virtual page number


#### Components of the physical address (PA)

- PPO: Physical page offset (same as VPO)
- **PPN:** Physical page number

#### Address Translation With a Page Table




#### **Address Translation: Page Hit**




- 1) Processor sends virtual address to MMU
- 2-3) MMU fetches PTE from page table in memory
- 4) MMU sends physical address to cache/memory
- 5) Cache/memory sends data word to processor

#### **Address Translation: Page Fault**



- 1) Processor sends virtual address to MMU
- 2-3) MMU fetches PTE from page table in memory
- 4) Valid bit is zero, so MMU triggers page fault exception
- 5) Handler identifies victim (and, if dirty, pages it out to disk)
- 6) Handler pages in new page and updates PTE in memory
- 7) Handler returns to original process, restarting faulting instruction

#### **Integrating VM and Cache**




VA: virtual address, PA: physical address, PTE: page table entry, PTEA = PTE address

### Speeding up Translation with a TLB


- Page table entries (PTEs) are cached in L1 like any other memory word
  - PTEs may be evicted by other data references
  - PTE hit still requires a small L1 delay
- Solution: Translation Lookaside Buffer (TLB)
  - Small set-associative hardware cache in MMU
  - Maps virtual page numbers to physical page numbers
  - Contains complete page table entries for small number of pages

#### Accessing the TLB

MMU uses the VPN portion of the virtual address to access the TLB:




#### **TLB Hit**



#### A TLB hit eliminates a memory access

#### **TLB Miss**




#### A TLB miss incurs an additional memory access (the PTE)

Fortunately, TLB misses are rare. Why?


Level 2

# **Multi-Level Page Tables**


- Suppose:
  - 4KB (2<sup>12</sup>) page size, 48-bit address space, 8-byte PTE
- Problem:
  - Would need a 512 GB page table!
    - $^{\bullet}$  2<sup>48</sup> \* 2<sup>-12</sup> \* 2<sup>3</sup> = 2<sup>39</sup> bytes
- Common solution: Multi-level page table
- Example: 2-level page table
  - Level 1 table: each PTE points to a page table (always memory resident)
  - Level 2 table: each PTE points to a page (paged in and out like any other data)



#### A Two-Level Page Table Hierarchy



# Translating with a k-level Page Table



#### **Summary**

- Programmer's view of virtual memory
  - Each process has its own private linear address space
  - Cannot be corrupted by other processes

#### System view of virtual memory

- Uses memory efficiently by caching virtual memory pages
  - Efficient only because of locality
- Simplifies memory management and programming
- Simplifies protection by providing a convenient interpositioning point to check permissions