<u>NS3</u>

1. Problem statement: Three nodes point – to – point network with duplex links between them. Set the queue size, vary the bandwidth and find the number of packets dropped.

Expected learning outcome: NS3 basic simulation basics, on-off application (CBR), reading traces through flow monitor and display the network performance

Algorithm:

- 2. Install internet stack on all nodes.
- 3. Assign IP4 addresses to netdevice containing two nodes at a time
- 4. Set network address for interfaces
- 5. Populate the global routing table between all nodes
- 6. Install a UDP socket instance on Node0 as sender that will connect to Node3 as receiver.
- 7. Start the UDP application at time 1.0 at rate Rate1
- 8. Use the ns-3 tracing mechanism to record the network performance.

```
// The output will consist of all the traced statistics collected at the network layer (by the flow monitor) and the application layer.
```

- $/\!/$ Finally, the number of packets dropped by the queuing discipline and
- // the number of packets dropped by the netdevice
- 9. vary the bandwidth of point-to-point link and observe the performance
- 10.Use gnuplot/matplotlib to visualise plots of bandwidth vs packet drop.
- 11. Conclude the performance from graph
- 12.Perform the above experiment for different topology conncetion.

Steps:

- 1. Open editor and write the program for the algorithm logic
- 2. Save in ns3.30/scratch directory
- 3. Compilation:

\$./waf --run scratch/filenameWithoutExtention

```
#include "ns3/core-module.h"
#include "ns3/internet-module.h"
#include "ns3/point-to-point-module.h"
#include "ns3/applications-module.h"
#include "ns3/traffic-control-module.h"
#include "ns3/flow-monitor-module.h"
using namespace ns3;
int main ()
{
    double simulationTime = 10: //seconds
```

```
std::string socketType="ns3::UdpSocketFactory";//"ns3::TcpSocketFactory";
NodeContainer nodes;
nodes.Create (3);
PointToPointHelper p2p;
p2p.SetDeviceAttribute ("DataRate", StringValue ("10Mbps"));
p2p.SetChannelAttribute ("Delay", StringValue ("2ms"));
p2p.SetQueue ("ns3::DropTailQueue", "MaxSize", StringValue ("1p"));
NetDeviceContainer dev01:
dev01 = p2p.Install (nodes.Get(0),nodes.Get(1));
NetDeviceContainer dev12;
dev12= p2p.Install (nodes.Get(1),nodes.Get(2));
InternetStackHelper stack;
stack.Install (nodes);
Ipv4AddressHelper address;
address.SetBase ("10.1.1.0", "255.255.255.0");
Ipv4InterfaceContainer interfaces01 = address.Assign (dev01);
address.SetBase ("10.1.2.0", "255.255.255.0");
Ipv4InterfaceContainer interfaces12 = address.Assign (dev12);
Ipv4GlobalRoutingHelper::PopulateRoutingTables ();
//Flow
uint16 t port = 7;
Address localAddress (InetSocketAddress (Ipv4Address::GetAny (), port));
PacketSinkHelper psh (socketType, localAddress);
ApplicationContainer sinkApp = psh.Install (nodes.Get (2));
sinkApp.Start (Seconds (0.0));
sinkApp.Stop (Seconds (simulationTime + 0.1));
OnOffHelper onoff (socketType, Ipv4Address::GetAny ());
onoff.SetAttribute ("OnTime", StringValue ("ns3::ConstantRandomVariable[Constant=1]"));
onoff.SetAttribute ("OffTime", StringValue ("ns3::ConstantRandomVariable[Constant=0]"));
onoff.SetAttribute ("DataRate", StringValue ("50Mbps")); //bit/s
ApplicationContainer apps;
InetSocketAddress rmt (interfaces12.GetAddress (1), port);
Address Value remote Address (rmt);
onoff.SetAttribute ("Remote", remoteAddress);
apps.Add (onoff.Install (nodes.Get (0)));
apps.Start (Seconds (1.0));
apps. Stop (Seconds (simulation Time +0.1));
FlowMonitorHelper flowmon;
Ptr<FlowMonitor> monitor = flowmon.InstallAll();
Simulator::Stop (Seconds (simulationTime + 5));
Simulator::Run();
```

```
Ptr<Ipv4FlowClassifier> classifier = DynamicCast<Ipv4FlowClassifier> (flowmon.GetClassifier ());
 std::map<FlowId, FlowMonitor::FlowStats> stats = monitor->GetFlowStats ();
 std::cout << std::endl << "*** Flow monitor statistics ***" << std::endl;
 for (std::map<FlowId, FlowMonitor::FlowStats>::const_iterator iter = stats.begin (); iter != stats.end
(); ++iter)
  {
   Ipv4FlowClassifier::FiveTuple t = classifier->FindFlow (iter->first);
   std::cout << "Flow ID: " << iter->first << " Src Addr " << t.sourceAddress << " Dst Addr " <<
t.destinationAddress<< std::endl;
   std::cout << "Tx Packets = " << iter->second.txPackets<< std::endl;
   std::cout << "Rx Packets = " << iter->second.rxPackets<< std::endl;
   std::cout << "Lost Packets = " << iter->second.lostPackets<< std::endl;</pre>
   std::cout << "Throughput" = " << iter->second.rxBytes * 8.0 / (iter-
>second.timeLastRxPacket.GetSeconds()-iter->second.timeFirstTxPacket.GetSeconds()) / 1000000
<< " Kbps"<< std::endl;
  }
 Simulator::Destroy ();
 return 0;
}
Usage of the existing examples: (Lab1.cc-→ example/traffic-control/traffic-control.cc)
*/
```

2. Simulate simple Extended Service Set with transmitting nodes in wireless LAN and determine the performance with respect to transmission of packets.

```
#include "ns3/core-module.h"
#include "ns3/point-to-point-module.h"
#include "ns3/network-module.h"
#include "ns3/applications-module.h"
#include "ns3/wifi-module.h"
#include "ns3/mobility-module.h"
#include "ns3/csma-module.h"
#include "ns3/internet-module.h"
#include "ns3/flow-monitor-module.h"
// Default Network Topology
// Number of wifi or csma nodes can be increased up to 250
//
          Rank 0 | Rank 1
// -----
// Wifi 10.1.3.0
//
     AP
// * * * *
// | | | 10.1.1.0
// n5 n6 n7 n0 ----- n1 n2 n3 n4
//
           point-to-point | | |
//
//
                     LAN 10.1.2.0
using namespace ns3;
NS_LOG_COMPONENT_DEFINE ("ThirdScriptExample");
int
main (int argc, char *argv[])
 uint32 t nCsma = 3;
 uint32 \text{ t nWifi} = 3;
 double simulationTime = 10; //seconds
 std::string socketType = "ns3::UdpSocketFactory";
 CommandLine cmd;
 cmd.Parse (argc,argv);
 // Check for valid number of csma or wifi nodes
 // 250 should be enough, otherwise IP addresses
 // soon become an issue
 if (nWifi > 250 || nCsma > 250)
   std::cout << "Too many wifi or csma nodes, no more than 250 each." << std::endl;
   return 1;
 NodeContainer p2pNodes;
 p2pNodes.Create (2);
```

```
PointToPointHelper pointToPoint;
pointToPoint.SetDeviceAttribute ("DataRate", StringValue ("5Mbps"));
pointToPoint.SetChannelAttribute ("Delay", StringValue ("2ms"));
NetDeviceContainer p2pDevices;
p2pDevices = pointToPoint.Install (p2pNodes);
NodeContainer csmaNodes;
csmaNodes.Add (p2pNodes.Get (1));
csmaNodes.Create (nCsma);
CsmaHelper csma;
csma.SetChannelAttribute ("DataRate", StringValue ("100Mbps"));
csma.SetChannelAttribute ("Delay", TimeValue (NanoSeconds (6560)));
NetDeviceContainer csmaDevices;
csmaDevices = csma.Install (csmaNodes);
NodeContainer wifiStaNodes;
wifiStaNodes.Create (nWifi);
NodeContainer wifiApNode = p2pNodes.Get (0);
YansWifiChannelHelper channel = YansWifiChannelHelper::Default ();
YansWifiPhyHelper phy = YansWifiPhyHelper::Default ();
phy.SetChannel (channel.Create ());
WifiHelper wifi;
wifi.SetRemoteStationManager ("ns3::AarfWifiManager");
WifiMacHelper mac;
Ssid ssid = Ssid ("ns-3-ssid");
mac.SetType ("ns3::StaWifiMac", "Ssid", SsidValue (ssid), "ActiveProbing", BooleanValue (false));
NetDeviceContainer staDevices;
staDevices = wifi.Install (phy, mac, wifiStaNodes);
mac.SetType ("ns3::ApWifiMac", "Ssid", SsidValue (ssid));
NetDeviceContainer apDevices;
apDevices = wifi.Install (phy, mac, wifiApNode);
MobilityHelper mobility;
mobility.SetPositionAllocator ("ns3::GridPositionAllocator",
                  "MinX", DoubleValue (0.0),
                  "MinY", DoubleValue (0.0),
                  "DeltaX", DoubleValue (5.0),
                  "DeltaY", DoubleValue (10.0),
                  "GridWidth", UintegerValue (3),
                  "LayoutType", StringValue ("RowFirst"));
mobility.SetMobilityModel ("ns3::RandomWalk2dMobilityModel",
                "Bounds", Rectangle Value (Rectangle (-50, 50, -50, 50)));
mobility.Install (wifiStaNodes);
```

```
mobility.SetMobilityModel ("ns3::ConstantPositionMobilityModel");
 mobility.Install (wifiApNode);
 InternetStackHelper stack;
 stack.Install (csmaNodes);
 stack.Install (wifiApNode);
 stack.Install (wifiStaNodes);
 Ipv4AddressHelper address;
 address.SetBase ("10.1.1.0", "255.255.255.0");
 Ipv4InterfaceContainer p2pInterfaces;
 p2pInterfaces = address.Assign (p2pDevices);
 address.SetBase ("10.1.2.0", "255.255.255.0");
 Ipv4InterfaceContainer csmaInterfaces;
 csmaInterfaces = address.Assign (csmaDevices);
 address.SetBase ("10.1.3.0", "255.255.255.0");
 address.Assign (staDevices);
 address.Assign (apDevices);
/* UdpEchoServerHelper echoServer (9);
 ApplicationContainer serverApps = echoServer.Install (csmaNodes.Get (nCsma));
 serverApps.Start (Seconds (1.0));
 serverApps.Stop (Seconds (10.0));
 UdpEchoClientHelper echoClient (csmaInterfaces.GetAddress (nCsma), 9);
 echoClient.SetAttribute ("MaxPackets", UintegerValue (1));
 echoClient.SetAttribute ("Interval", TimeValue (Seconds (1.0)));
 echoClient.SetAttribute ("PacketSize", UintegerValue (1024));
 ApplicationContainer clientApps =
  echoClient.Install (wifiStaNodes.Get (nWifi - 1));
 clientApps.Start (Seconds (2.0));
 clientApps.Stop (Seconds (10.0));
*/
//Flow
 uint16_t port = 7;
 Address localAddress (InetSocketAddress (Ipv4Address::GetAny (), port));
 PacketSinkHelper packetSinkHelper (socketType, localAddress);
 ApplicationContainer sinkApp = packetSinkHelper.Install (csmaNodes.Get (nCsma));
 sinkApp.Start (Seconds (0.0));
 sinkApp.Stop (Seconds (simulationTime + 0.1));
 uint32_t payloadSize = 1448;
 Config::SetDefault ("ns3::TcpSocket::SegmentSize", UintegerValue (payloadSize));
 OnOffHelper onoff (socketType, Ipv4Address::GetAny ());
 onoff.SetAttribute ("OnTime", StringValue ("ns3::ConstantRandomVariable[Constant=1]"));
 onoff.SetAttribute ("OffTime", StringValue ("ns3::ConstantRandomVariable[Constant=0]"));
 onoff.SetAttribute ("PacketSize", UintegerValue (payloadSize));
 onoff.SetAttribute ("DataRate", StringValue ("50Mbps")); //bit/s
 ApplicationContainer apps;
 Address Value remoteAddress (InetSocketAddress (csmaInterfaces.GetAddress (nCsma), port));
```

```
onoff.SetAttribute ("Remote", remoteAddress);
 apps.Add (onoff.Install (wifiStaNodes.Get (nWifi - 1)));
 apps.Start (Seconds (1.0));
 apps.Stop (Seconds (simulationTime + 0.1));
 Ipv4GlobalRoutingHelper::PopulateRoutingTables ();
 Simulator::Stop (Seconds (10.0));
 FlowMonitorHelper flowmon;
 Ptr<FlowMonitor> monitor = flowmon.InstallAll();
 Simulator::Run();
// Print per flow statistics
 monitor->CheckForLostPackets ();
 Ptr<Ipv4FlowClassifier> classifier = DynamicCast<Ipv4FlowClassifier> (flowmon.GetClassifier ());
 std::map<FlowId, FlowMonitor::FlowStats> stats = monitor->GetFlowStats ();
 for (std::map<FlowId, FlowMonitor::FlowStats>::const_iterator iter = stats.begin (); iter != stats.end
(); ++iter)
  {
 Ipv4FlowClassifier::FiveTuple t = classifier->FindFlow (iter->first);
   NS_LOG_UNCOND("Flow ID: " << iter->first << " Src Addr " << t.sourceAddress << " Dst
Addr " << t.destinationAddress);
   NS_LOG_UNCOND("Tx Packets = " << iter->second.txPackets);
   std::cout << "Rx Packets = " << iter->second.rxPackets<< std::endl;
   std::cout << "Lost Packets = " << iter->second.lostPackets<< std::endl;
   std::cout << "Throughput" = " << iter->second.rxBytes * 8.0 / (iter-
>second.timeLastRxPacket.GetSeconds()-iter->second.timeFirstTxPacket.GetSeconds()) / 1000000
<< " Kbps"<< std::endl;
 Simulator::Destroy ();
 return 0;
Usage of the existing examples: (Lab3.cc-→ example/third.cc)
```

3. Simulate a transmission of ping message over a network topology consisting of 6 nodes and find the number of packets dropped due to congestion.

```
// Network topology
//
//
     n0 n1 n2 n3 n4
                            n5
//
    //
// node n0,n1,n3,n4,n5 pings to node n2
// node n0 generates protocol 2 (IGMP) to node n3
#include <iostream>
#include <fstream>
#include <string>
#include <cassert>
#include "ns3/core-module.h"
#include "ns3/network-module.h"
#include "ns3/csma-module.h"
#include "ns3/applications-module.h"
#include "ns3/internet-apps-module.h"
#include "ns3/internet-module.h"
#include "ns3/flow-monitor-module.h"
//#include "ns3/netanim-module.h"
using namespace ns3;
NS_LOG_COMPONENT_DEFINE ("CsmaPingExample");
int
main (int argc, char *argv[])
 CommandLine cmd:
 cmd.Parse (argc, argv);
 Time interPacketInterval = Seconds (1.);
 // Here, we will explicitly create four nodes.
 NS_LOG_UNCOND ("Create nodes.");
 NodeContainer c;
 c.Create (6);
 // connect all our nodes to a shared channel.
 NS_LOG_UNCOND ("Build Topology.");
 CsmaHelper csma;
 csma.SetChannelAttribute ("DataRate", DataRateValue (DataRate (5000000)));
 csma.SetChannelAttribute ("Delay", TimeValue (MilliSeconds (2)));
 csma.SetDeviceAttribute ("EncapsulationMode", StringValue ("Llc"));
 NetDeviceContainer devs = csma.Install (c);
 // add an ip stack to all nodes.
 NS_LOG_UNCOND ("Add ip stack.");
 InternetStackHelper ipStack;
 ipStack.Install (c);
```

```
// assign ip addresses
 NS_LOG_UNCOND ("Assign ip addresses.");
 Ipv4AddressHelper ip;
 ip.SetBase ("192.168.1.0", "255.255.255.0");
 Ipv4InterfaceContainer addresses = ip.Assign (devs);
 NS_LOG_UNCOND ("Create Source");
 InetSocketAddress dst = InetSocketAddress (addresses.GetAddress (3));
 OnOffHelper onoff = OnOffHelper ("ns3::UdpSocketFactory", dst);
 onoff.SetAttribute ("OnTime", StringValue ("ns3::ConstantRandomVariable[Constant=1]"));
 onoff.SetAttribute ("OffTime", StringValue ("ns3::ConstantRandomVariable[Constant=0]"));
 onoff.SetAttribute ("PacketSize", UintegerValue (1100));
 onoff.SetAttribute ("DataRate", StringValue ("50Mbps"));
 ApplicationContainer apps = onoff.Install (c.Get (0));
 apps.Start (Seconds (1.0));
 apps.Stop (Seconds (10.0));
 NS LOG UNCOND ("Create Sink.");
 PacketSinkHelper sink = PacketSinkHelper ("ns3::UdpSocketFactory", dst);
 apps = sink.Install (c.Get (3));
 apps.Start (Seconds (0.0));
 apps.Stop (Seconds (11.0));
 NS LOG UNCOND ("Create pinger");
 V4PingHelper ping = V4PingHelper (addresses.GetAddress (0));
// ping.SetAttribute ("Interval", TimeValue (interPacketInterval));
ping.SetAttribute ("Interval", TimeValue (interPacketInterval));
 NodeContainer pingers;
 pingers.Add (c.Get (3));
 pingers.Add (c.Get (1));
 pingers.Add (c.Get (2));
 pingers.Add (c.Get (4));
 pingers.Add (c.Get (5));
 apps = ping.Install (pingers);
 apps.Start (Seconds (2.0));
 apps.Stop (Seconds (10.0));
//Enable Tracing using flowmonitor
 FlowMonitorHelper flowmon;
 Ptr<FlowMonitor> monitor = flowmon.InstallAll();
 Simulator::Stop (Seconds (10.0));
//Add visualization using Netanim
// AnimationInterface anim ("ex5.xml");
 NS_LOG_UNCOND ("Run Simulation.");
 Simulator::Run();
```

```
// Print per flow statistics
 monitor->CheckForLostPackets ();
 Ptr<Ipv4FlowClassifier> classifier = DynamicCast<Ipv4FlowClassifier> (flowmon.GetClassifier ());
 std::map<FlowId, FlowMonitor::FlowStats> stats = monitor->GetFlowStats ();
 for (std::map<FlowId, FlowMonitor::FlowStats>::const_iterator iter = stats.begin (); iter != stats.end
(); ++iter)
 Ipv4FlowClassifier::FiveTuple t = classifier->FindFlow (iter->first);
    NS_LOG_UNCOND("Flow ID: " << iter->first << " Src Addr " << t.sourceAddress << " Dst
Addr " << t.destinationAddress);
   NS_LOG_UNCOND("Tx Packets = " << iter->second.txPackets);
   NS_LOG_UNCOND("Rx Packets = " << iter->second.rxPackets);
   std::cout << "Lost Packets = " << iter->second.lostPackets<< std::endl;</pre>
   NS_LOG_UNCOND("Throughput: " << iter->second.rxBytes * 8.0 / (iter-
>second.timeLastRxPacket.GetSeconds()-iter->second.timeFirstTxPacket.GetSeconds()) / 1024 << "
Kbps");
  }
 Simulator::Destroy ();
 NS_LOG_UNCOND ("Done.");
Usage of the existing examples: (Lab5.cc-→ src/csma/examples/csma-ping.cc)
```