

# **PyREx Documentation**

Release 1.8.2

Ben Hokanson-Fasig

# **CONTENTS**

1	About PyREx					
	1.1 Installation	1				
	1.2 Quick Code Example	1				
	1.3 Units	2				
2	How to Use PyREx	3				
_	2.1 Working with Signal Objects	3				
	2.2 Antenna Class and Subclasses	12				
		18				
	2.4 Ice and Earth Models	23				
	2.5 Ray Tracing	24				
	2.6 Particle Generation	26				
	2.7 Full Simulation	27				
		29				
		33				
	2.9 More Examples	33				
3	Custom Sub-Package	34				
		35				
	3.2 ARIANNA Custom Module	36				
		36				
		36				
4	Example Code	40				
		40				
		42				
		43				
	4.4 Examine a Single Event	45				
5	Contributing to PyREx	48				
J		48				
		49				
		49				
		50				
	3.4 Releasing a frew version	50				
6	PyREx API	51				
	6.1 PyREx Package Imports	51				
	6.2 Individual Module APIs	72				
	6.3 Included Custom Sub-Packages	18				
7	Vandan III danna					
7		175				
	7.1 Version 1.8.2	. 13				

	7.2	Version 1.8.1	176
	7.3	Version 1.8.0	176
	7.4	Version 1.7.0	177
	7.5	Version 1.6.0	178
	7.6	Version 1.5.0	179
	7.7	Version 1.4.2	179
	7.8	Version 1.4.1	179
	7.9	Version 1.4.0	179
	7.10	Version 1.3.1	180
	7.11	Version 1.3.0	180
	7.12	Version 1.2.1	180
	7.13	Version 1.2.0	181
	7.14	Version 1.1.2	181
	7.15	Version 1.1.1	181
	7.16	Version 1.1.0	181
	7.17	Version 1.0.3	182
	7.18	Version 1.0.2	182
	7.19	Version 1.0.1	183
	7.20	Version 1.0.0	183
	7.21	Version 0.0.0	184
8	GitH	ub README	185
	8.1	PyREx - ( <b>Py</b> thon package for an IceCube <b>R</b> adio <b>Ex</b> tension)	185
Bi	bliogra	aphy	187
D.	than N	Module Index	188
ГУ	uioii I	vioune muex	100
In	dex		189

**CHAPTER** 

ONE

#### **ABOUT PYREX**

PyREx (**Py**thon package for an IceCube **R**adio **Ex**tension) is, as its name suggests, a Python package designed to simulate the measurement of Askaryan pulses via a radio antenna array around the IceCube South Pole Neutrino Observatory. The code is designed to be modular so that it can also be applied to other askaryan radio antennas (e.g. the ARA and ARIANNA collaborations).

#### 1.1 Installation

The easiest way to get the PyREx package is using pip as follows:

```
pip install git+https://github.com/bhokansonfasig/pyrex#egg=pyrex
```

PyREx requires python version 3.6+ as well as numpy version 1.13+, scipy version 0.19+, and h5py version 2.7+, which should be automatically installed when installing via pip.

Alternatively, you can download the code from https://github.com/bhokansonfasig/pyrex and then either include the pyrex directory (the one containing the python modules) in your PYTHON\_PATH, or just copy the pyrex directory into your working directory. PyREx is not currently available on PyPI, so a simple pip install pyrex will not have the intended effect.

## 1.2 Quick Code Example

The most basic simulation can be produced as follows:

First, import the package:

```
import pryex
```

Then, create a particle generator object that will produce random particles in a cylinder with radius and depth of 1 km and with a fixed energy of 100 PeV:

An array of antennas that represent the detector is also needed. The base Antenna class provides a basic antenna with a flat frequency response and no trigger condition. Here we make a single vertical "string" of four antennas with no noise:

```
antenna_array = []
for z in [-100, -150, -200, -250]:
   antenna_array.append(
        pyrex.Antenna(position=(0,0,z), noisy=False)
   )
```

Finally, we want to pass these into the *EventKernel* and produce an event:

Now the signals received by each antenna can be accessed by their waveforms parameter:

```
import matplotlib.pyplot as plt
for ant in kernel.ant_array:
    for wave in ant.waveforms:
        plt.figure()
        plt.plot(wave.times, wave.values)
        plt.show()
```

#### 1.3 Units

For ease of use, PyREx tries to use consistent units in all classes and functions. The units used are mostly SI with a few exceptions listed in bold below:

Metric	Unit
time	seconds (s)
frequency	hertz (Hz)
distance	meters (m)
density	grams per cubic centimeter (g/cm^3)
material thickness	grams per square centimeter (g/cm^2)
temperature	kelvin (K)
energy	gigaelectronvolts (GeV)
resistance	ohms $(\Omega)$
voltage	volts (V)
electric field	volts per meter (V/m)

1.3. Units 2

**CHAPTER** 

**TWO** 

#### **HOW TO USE PYREX**

This section describes in detail how to use a majority of the functions and classes included in the base PyREx package, along with short example code segments. The code in each section is designed to run sequentially, and the code examples all assume these imports:

```
import numpy as np
import matplotlib.pyplot as plt
import scipy.fftpack
import scipy.signal
import pyrex
```

All of the following examples can also be found (and easily run) in the Code Examples python notebook found in the examples directory.


#### 2.1 Working with Signal Objects

The base Signal class consists of an array of times and an array of corresponding signal values, and is instantiated with these two arrays. The times array is assumed to be in units of seconds, but there are no general units for the values array. It is worth noting that the Signal object stores shallow copies of the passed arrays, so changing the original arrays will not affect the Signal object.

```
time_array = np.linspace(0, 10)
value_array = np.sin(time_array)
my_signal = pyrex.Signal(times=time_array, values=value_array)
```

Plotting the Signal object is as simple as plotting the times vs the values:


```
plt.plot(my_signal.times, my_signal.values)
plt.show()
```



While there are no specified units for Signal.values, there is the option to specify the value\_type of the values. This is done using the Signal.Type enum. By default, a <code>Signal</code> object has value\_type=Type. unknown. However, if the signal represents a voltage, electric field, or power; value\_type can be set to Signal. Type.voltage, Signal.Type.field, or Signal.Type.power respectively:

Signal objects can be added as long as they have the same time array and value\_type. Signal objects can also be multiplied by numeric types, which will multiply the values attribute of the signal.


```
time_array = np.linspace(0, 10)
values1 = np.sin(time_array)
values2 = np.cos(time_array)
signal1 = pyrex.Signal(time_array, values1)
plt.plot(signal1.times, signal1.values,
         label="signal1 = sin(t)")
signal2 = pyrex.Signal(time_array, values2)
plt.plot(signal2.times, signal2.values,
         label="signal2 = cos(t)")
signal3 = signal1 + signal2
plt.plot(signal3.times, signal3.values,
         label="signal3 = sin(t) + cos(t)")
signal4 = 2 * signal3
plt.plot(signal4.times, signal4.values,
         label="signal4 = 2*(\sin(t)+\cos(t))")
all_signals = [signal1, signal2, signal3]
signal5 = sum(all_signals)
plt.plot(signal5.times, signal5.values, '--',
         label="signal5 = 2*(\sin(t)+\cos(t))")
plt.legend()
plt.show()
```



The Signal class provides many convenience attributes for dealing with signals:


The Signal class also provides functions for manipulating the signal. The Signal.resample() method will resample the times and values arrays to the given number of points (with the same endpoints):

```
my_signal.resample(1001)
len(my_signal.times) == len(my_signal.values) == 1001
my_signal.times[0] == 0
my_signal.times[-1] == 10
plt.plot(my_signal.times, my_signal.values)
plt.show()
```



The Signal.with\_times () method will interpolate/extrapolate the signal's values onto a new times array:

```
new_times = np.linspace(-5, 15)
new_signal = my_signal.with_times(new_times)
plt.plot(new_signal.times, new_signal.values, label="new signal")
plt.plot(my_signal.times, my_signal.values, label="original signal")
plt.legend()
plt.show()
```




The Signal.filter\_frequencies () method will apply a frequency-domain filter to the values array based on the passed frequency response function. In cases where the filter is designed for only positive frequencies (as below)

the filtered frequency may exhibit strange behavior, including potentially having an imaginary part. To resolve that issue, pass force\_real=True to the Signal.filter\_frequencies() method which will extrapolate the given filter to negative frequencies and ensure a real-valued filtered signal.

```
def lowpass_filter(frequency):
    if frequency < 1:
        return 1
    else:
        return 0


time_array = np.linspace(0, 10, 1001)
value_array = np.sin(0.1*2*np.pi*time_array) + np.sin(2*2*np.pi*time_array)
my_signal = pyrex.Signal(times=time_array, values=value_array)

plt.plot(my_signal.times, my_signal.values, label="original")
my_signal.filter_frequencies(lowpass_filter, force_real=True)
plt.plot(my_signal.times, my_signal.values, label="filtered")
plt.legend()
plt.show()</pre>
```




A number of classes which inherit from the Signal class are included in PyREx: EmptySignal, FunctionSignal, AskaryanSignal, and ThermalNoise. EmptySignal is simply a signal whose values are all zero:

```
time_array = np.linspace(0,10)
empty = pyrex.EmptySignal(times=time_array)
plt.plot(empty.times, empty.values)
plt.show()
```




FunctionSignal takes a function of time and creates a signal based on that function:

```
time_array = np.linspace(0, 10, num=101)
def square_wave(time):
    if int(time)%2==0:
        return 1
    else:
        return -1
square_signal = pyrex.FunctionSignal(times=time_array, function=square_wave)
plt.plot(square_signal.times, square_signal.values)
plt.show()
```




Additionally, FunctionSignal leverages its knowledge of the function to more accurately interpolate and extrapolate values for the Signal.with times () method:


```
new_times = np.linspace(0, 20, num=201)
long_square_signal = square_signal.with_times(new_times)
plt.plot(long_square_signal.times, long_square_signal.values, label="extrapolated")
plt.plot(square_signal.times, square_signal.values, label="original")
plt.legend()
plt.show()
```




AskaryanSignal produces an Askaryan pulse (in V/m) on a time array resulting from a given neutrino observed at a given angle from the shower axis and at a given distance from the shower vertex. For more about using the Particle class, see Particle Generation.



ThermalNoise produces Rayleigh noise (in V) at a given temperature and resistance which has been passed through a bandpass filter of the given frequency range:



Note that since *ThermalNoise* inherits from *FunctionSignal*, it can be extrapolated nicely to new times. It may be highly periodic outside of its original time range however, unless a larger number of frequencies is requested on initialization.



#### 2.2 Antenna Class and Subclasses

The base Antenna class provided by PyREx is designed to be subclassed in order to match the needs of each project. At its core, an Antenna object is initialized with a position, a temperature, and a frequency range, as well as optionally a resistance (for noise calculations) and a boolean dictating whether or not noise should be added to the antenna's signals (note that if noise is to be added, a resistance must be specified).

The basic properties of an Antenna object are is\_hit and waveforms. The is\_hit property specifies whether or not the antenna has been triggered by an event. waveforms is a list of all the waveforms which have triggered the antenna. The antenna also defines a signals attribute, which is a list of all signals the antenna has received, and all\_waveforms which is a list of all waveforms (signal plus noise) the antenna has received including those which didn't trigger. Finally, the antenna has an is\_hit\_mc property which is similar to is\_hit, but does not count triggers where noise alone would have triggered the antenna.

```
basic_antenna.is_hit == False
basic_antenna.waveforms == []
```


The Antenna class contains two attributes and three methods which represent characteristics of the antenna as they relate to signal processing. The attributes are efficiency and antenna\_factor, and the methods are Antenna.response(), Antenna.directional\_gain(), and Antenna.polarization\_gain(). The attributes are to be set and the methods overwritten in order to custmoize the way the antenna responds to incoming signals. efficiency is simply a scalar which multiplies the signal the antenna receives (default value is 1). antenna\_factor is a factor used in converting received electric fields into voltages (antenna\_factor = E/V; default value is 1). Antenna.response() takes a frequency or list of frequencies (in Hz) and returns the frequency response of the antenna at each frequency given (default always returns 1). Antenna.directional\_gain() takes angles theta and phi in the antenna's coordinates and returns the antenna's gain for a signal coming from that direction (default always returns 1). Antenna.directional\_gain() is dependent on the antenna's orientation, which is defined by its z\_axis and x\_axis attributes. To change the antenna's orientation, use the Antenna.set\_orientation() method which takes z\_axis and x\_axis arguments. Finally, Antenna.polarization\_gain() takes a polarization vector and returns the antenna's gain for a signal with that polarization (default always returns 1).


```
basic_antenna.efficiency == 1
basic_antenna.antenna_factor == 1
freqs = [1, 2, 3, 4, 5]
basic_antenna.response(freqs) == [1, 1, 1, 1, 1]
basic_antenna.directional_gain(theta=np.pi/2, phi=0) == 1
basic_antenna.polarization_gain([0,0,1]) == 1
```

The Antenna class defines an Antenna.trigger() method which is also expected to be overwritten. Antenna.trigger() takes a Signal object as an argument and returns a boolean of whether or not the antenna would trigger on that signal (default always returns True).

```
basic_antenna.trigger(pyrex.Signal([0],[0])) == True
```


The Antenna class also defines an Antenna.receive() method which takes a Signal object and processes the signal according to the antenna's attributes (efficiency, antenna\_factor, response, directional\_gain, and polarization\_gain as described above). To use the Antenna.receive() method, simply pass it the Signal object the antenna sees, and the Antenna class will handle the rest. You can also optionally specify the direction of travel of the signal (used in the Antenna.directional\_gain() calculation) and the polarization direction of the signal (used in the Antenna.polarization\_gain() calculation). If either of these is unspecified, the corresponding gain will simply be set to 1.





Beyond Antenna.waveforms, the *Antenna* object also provides methods for checking the waveform and trigger status for arbitrary times: Antenna.full\_waveform() and Antenna.is\_hit\_during(). Both of these methods take a time array as an argument and return either the waveform <code>Signal</code> object for those times or whether said waveform triggered the antenna, respectively.

```
total_waveform = basic_antenna.full_waveform(np.linspace(0,20))
plt.plot(total_waveform.times, total_waveform.values, label="Total Waveform")
plt.plot(incoming_signal_1.times, incoming_signal_1.values, label="Pure Signals")
plt.plot(incoming_signal_2.times, incoming_signal_2.values, color="C1")
plt.legend()
plt.show()
basic_antenna.is_hit_during(np.linspace(0, 200e-9)) == True
```




Finally, the Antenna class defines an Antenna . clear () method which will reset the antenna to a state of having received no signals:

```
basic_antenna.clear()
basic_antenna.is_hit == False
len(basic_antenna.waveforms) == 0
```

The Antenna.clear() method can also optionally reset the source of noise waveforms by passing reset\_noise=True so that if the same signals are given after the antenna is cleared, the noise waveforms will be different:

```
noise_before = basic_antenna.make_noise(np.linspace(0, 20))
plt.plot(noise_before.times, noise_before.values, label="Noise Before Clear")
basic_antenna.clear(reset_noise=True)
noise_after = basic_antenna.make_noise(np.linspace(0, 20))
plt.plot(noise_after.times, noise_after.values, label="Noise After Clear")
plt.legend()
plt.show()
```



To create a custom antenna, simply inherit from the Antenna class:

```
class NoiselessThresholdAntenna(pyrex.Antenna):
    def __init__(self, position, threshold):
        super().__init__(position=position, noisy=False)
        self.threshold = threshold


def trigger(self, signal):
    if max(np.abs(signal.values)) > self.threshold:
        return True
    else:
        return False
```

Our custom NoiselessThresholdAntenna should only trigger when the amplitude of a signal exceeds its threshold value:

(continues on next page)

(continued from previous page)

```
plt.figure()
plt.plot(wave.times, wave.values)
plt.show()
```



For more on customizing PyREx, see the Custom Sub-Package section.

PyREx also defines DipoleAntenna, a subclass of Antenna which provides a basic threshold trigger, a basic bandpass filter frequency response, a sine-function directional gain, and a typical dot-product polarization effect. A DipoleAntenna object can be created as follows:

# 2.3 AntennaSystem and Detector Classes

The AntennaSystem class is designed to bridge the gap between the basic antenna classes and realistic antenna systems including front-end processing of the antenna's signals. It is designed to be subclassed, but by default it takes as an argument the Antenna class or subclass it is extending, or an object of that class. It provides an interface nearly

identical to that of the Antenna class, but where an Antenna System. front\_end () method (which by default does nothing) is applied to the extended antenna's signals.

To extend an Antenna class or subclass into a full antenna system, inherit from the Antenna System class and define the AntennaSystem.front\_end() method. If the front end of the antenna system requires some time to equilibrate to noise signals, that can be specified in the AntennaSystem.lead\_in\_time attribute, adding that amount of time before any waveforms to be processed. A different trigger also optionally can be defined for the antenna system (by default it uses the antenna's trigger):

```
class PowerAntennaSystem(pyrex.AntennaSystem):
    """Antenna system whose signals and waveforms are powers instead of
   voltages."""
   def __init__(self, position, temperature, resistance, frequency_range):
       super().__init__(pyrex.Antenna)
        # The setup_antenna method simply passes all arguments on to the
       # antenna class passed to super.__init__() and stores the resulting
        # antenna to self.antenna
       self.setup_antenna(position=position, temperature=temperature,
                           resistance=resistance,
                           freq_range=frequency_range)
   def front_end(self, signal):
       return pyrex.Signal(signal.times, signal.values**2,
                            value_type=pyrex.Signal.Type.power)
```

Objects of this class can then, for the most part, be interacted with as though they were regular antenna objects:

```
position = (0, 0, -100) \# m
temperature = 300 \# K
resistance = 1e17 # ohm
frequency_range = (0, 5) \# Hz
basic_antenna_system = PowerAntennaSystem(position=position,
                                          temperature=temperature,
                                          resistance=resistance,
                                          frequency_range=frequency_range)
basic_antenna_system.trigger(pyrex.Signal([0],[0])) == True
incoming_signal_1 = pyrex.FunctionSignal(np.linspace(0,2*np.pi), np.sin,
                                         value_type=pyrex.Signal.Type.voltage)
incoming_signal_2 = pyrex.FunctionSignal(np.linspace(4*np.pi,6*np.pi), np.sin,
                                         value_type=pyrex.Signal.Type.voltage)
basic_antenna_system.receive(incoming_signal_1)
basic_antenna_system.receive(incoming_signal_2, direction=[0,0,1],
                             polarization=[1,0,0])
basic_antenna_system.is_hit == True
for waveform, pure_signal in zip(basic_antenna_system.waveforms,
                                 basic_antenna_system.signals):
   plt.figure()
   plt.plot(waveform.times, waveform.values, label="Waveform")
   plt.plot(pure_signal.times, pure_signal.values, label="Pure Signal")
   plt.legend()
   plt.show()
total_waveform = basic_antenna_system.full_waveform(np.linspace(0,20))
plt.plot(total_waveform.times, total_waveform.values, label="Total Waveform")
plt.plot(incoming_signal_1.times, incoming_signal_1.values, label="Pure Signals")
```


(continues on next page)


(continued from previous page)

```
plt.plot(incoming_signal_2.times, incoming_signal_2.values, color="C1")
plt.legend()
plt.show()

basic_antenna_system.is_hit_during(np.linspace(0, 200e-9)) == True

basic_antenna_system.clear()
basic_antenna_system.is_hit == False
len(basic_antenna_system.waveforms) == 0
```






The <code>Detector</code> class is another convenience class meant to be subclassed. It is useful for automatically generating many antennas (as would be used in a detector). Subclasses must define a <code>Detector.set\_positions()</code> method to assign vector positions to the self.antenna\_positions attribute. By default <code>Detector.set\_positions()</code> will raise a <code>NotImplementedError</code>. Additionally subclasses may extend the default <code>Detector.build\_antennas()</code> method which by default simply builds antennas of a passed antenna class using any keyword arguments passed to the method. In addition to simply generating many antennas at desired positions, another convenience of the <code>Detector</code> class is that once the <code>Detector.build\_antennas()</code> method is run, it can be iterated directly as though the object were a list of the antennas it generated. And finally, the <code>Detector.triggered()</code> method will check whether any of the antennas have been triggered, and can be overridden in subclasses to define a more complicated detector trigger. An example of subclassing the <code>Detector</code> class is shown below:


```
class AntennaGrid(pyrex.Detector):
    """A detector composed of a plane of antennas in a rectangular grid layout
    some distance below the ice."""
    def set_positions(self, number, separation=10, depth=-50):
        self.antenna_positions = []
        n_x = int(np.sqrt(number))
        n_y = int(number/n_x)
        dx = separation
        dy = separation
        for i in range(n_x):
            x = -dx*n_x/2 + dx/2 + dx*i
            for j in range(n_y):
                y = -dy*n_y/2 + dy/2 + dy*j
                self.antenna_positions.append((x, y, depth))
grid_detector = AntennaGrid(9)
# Build the antennas
temperature = 300 # K
resistance = 1e17 # ohm
frequency_range = (0, 5) # Hz
```

(continues on next page)

(continued from previous page)



Due to the parallels between Antenna and AntennaSystem, an antenna system may also be used in the custom detector class. Note however, that the antenna positions must be accessed as antenna.antenna.position since we didn't define a position attribute for the PowerAntennaSystem:



For convenience, objects derived from the <code>Detector</code> class can be added into a <code>CombinedDetector</code> object, which behaves similarly. The <code>CombinedDetector.build\_antennas()</code> method should work seamlessly if the subdetectors have the same <code>build\_antennas()</code> method, otherwise it will do its best to dispatch keyword arguments between the sub-detectors. Similarly the <code>CombinedDetector.triggered()</code> method will return <code>True</code> if either sub-detector was triggered, with arguments to the method dispatched to the proper sub-triggers.

#### 2.4 Ice and Earth Models

PyREx provides a class <code>IceMode1</code>, which is an alias for whichever south pole ice model class is preferred (currently <code>pyrex.ice\_mode1.AntarcticIce</code>). The <code>IceMode1</code> class provides class methods for calculating characteristics of the ice at different depths and frequencies outlined below:

```
depth = -1000 # m
pyrex.IceModel.temperature(depth)
pyrex.IceModel.index(depth)
pyrex.IceModel.gradient(depth)
frequency = 1e8 # Hz
pyrex.IceModel.attenuation_length(depth, frequency)
```

PyREx also provides two functions realted to its earth model: prem\_density() and slant\_depth(). prem\_density() calculates the density in grams per cubic centimeter of the earth at a given radius:

```
radius = 6360000 # m
pyrex.prem_density(radius)
```

slant\_depth() calculates the material thickness in grams per square centimeter of a chord cutting through the earth at a given nadir angle, starting from a given depth:

```
nadir_angle = 60 * np.pi/180 # radians
depth = 1000 # m
pyrex.slant_depth(nadir_angle, depth)
```

## 2.5 Ray Tracing

PyREx provides ray tracing in the RayTracer and RayTracePath classes. RayTracer takes a launch point and receiving point as arguments (and optionally an ice model and z-step), and will solve for the paths between the points (as RayTracePath objects).

```
start = (0, 0, -250) # m
finish = (100, 0, -100) # m
my_ray_tracer = pyrex.RayTracer(from_point=start, to_point=finish)
```

The two most useful properties of <code>RayTracer</code> are exists and solutions. The exists property is a boolean value of whether or not path solutions exist between the launch and receiving points. solutions is the list of (zero or two) <code>RayTracePath</code> objects which exist between the launch and receiving points. There are many other properties available in <code>RayTracer</code>, outlined in the <code>PyREx API</code> section, which are mostly used internally and maybe not interesting otherwise.

```
my_ray_tracer.exists
my_ray_tracer.solutions
```


The RayTracePath class contains the attributes of the paths between points. The most useful properties of RayTracePath are tof, path\_length, emitted\_direction, and received\_direction. These properties provide the time of flight, path length, and direction of rays at the launch and receiving points respectively.

```
my_path = my_ray_tracer.solutions[0]
my_path.tof
my_path.path_length
my_path.emitted_direction
my_path.received_direction
```

RayTracePath also provides a RayTracePath.attenuation() method which gives the attenuation of the signal at a given frequency (or frequencies), and a RayTracePath.coordinates property which gives the x, y, and z coordinates of the path (useful mostly for plotting, and are not guaranteed to be accurate for other purposes).

```
frequency = 500e6 # HZ
my_path.attenuation(100e6)
my_path.attenuation(np.linspace(1e8, 1e9, 11))
plt.plot(my_path.coordinates[0], my_path.coordinates[2])
plt.show()
```

2.5. Ray Tracing 24




Finally, RayTracePath.propagate() propagates a Signal object from the launch point to the receiving point of the path by applying the frequency-dependent attenuation from RayTracePath.attenuation(), and shifting the signal times by RayTracePath.tof. Note that it does not apply a 1/R effect based on the path length. If needed, this effect should be added in manually. RayTracePath.propagate() can also propagate the polarization vector of the signal, either independently or in the same function call.

```
time_array = np.linspace(0, 5e-9, 1001)
launch_signal = (
    pyrex.FunctionSignal(time_array, lambda t: np.sin(1e9*2*np.pi*t))
    + pyrex.FunctionSignal(time_array, lambda t: np.sin(1e10*2*np.pi*t))
)
plt.plot(launch_signal.times*1e9, launch_signal.values)
plt.show()
launch_pol = 1/np.sqrt(np.array([3, 3, 3]))

rec_signal, rec_pol = my_path.propagate(launch_signal, polarization=launch_pol)
plt.plot(rec_signal.times*1e9, rec_signal.values)
plt.show()
print(rec_pol)
```

2.5. Ray Tracing 25



#### 2.6 Particle Generation

PyREx includes the <code>Particle</code> class as a container for information about neutrinos which are generated to produce Askaryan pulses. A <code>Particle</code> contains an id, a vertex, a direction, an energy, an interaction, and a weight:

```
particle_type = pyrex.Particle.Type.electron_neutrino
initial_position = (0,0,0) # m
```

(continues on next page)

(continued from previous page)

The interaction attribute is an instance of an Interaction class (NeutrinoInteraction by default) which is a model for how the neutrino interacts in the ice. It has a kind denoting whether the interaction will be charged-current or neutral-current, an inelasticity, em\_frac and had\_frac describing the resulting particle shower(s), and cross\_section and interaction\_length in the ice at the energy of the parent Particle object:

```
type(particle.interaction)
particle.interaction.kind
particle.interaction.inelasticity
particle.interaction.em_frac
particle.interaction.had_frac
particle.interaction.cross_section
particle.interaction.interaction_length
```

PyREx also includes a number of classes for generating random neutrinos in various ice volumes. The <code>CylindricalGenerator</code> and <code>RectangularGenerator</code> classes generate neutrinos uniformly in cylindrical or rectangular volumes respectively. The <code>CylindricalShadowGenerator</code> and <code>RectangularShadowGenerator</code> classes are similar, but take into account Earth shadowing when generating particles. These generator classes take as arguments the necessary dimensions and an energy (which can be a scalar value or a function returning scalar values). A desired flavor ratio can also be given:

The create\_event() method of the generator returns an <code>Event</code> object, which contains a tree of <code>Particle</code> objects representing the event. Currently this tree will only contain a single neutrino, but could be expanded in the future in order to describe more exotic events. The neutrino is available as the only element in the list <code>Event.roots</code>. It can also be accessed by iterating the <code>Event</code> object.

Lastly, PyREx includes ListGenerator and FileGenerator classes which can be used to reproduce pregenerated events from either a list or from simulation output files, respectively. For example, to continuously re-throw our Particle object from above:

```
repetitive_generator = pyrex.ListGenerator([pyrex.Event(particle)])
repetitive_generator.create_event()
repetitive_generator.create_event()
```


#### 2.7 Full Simulation

PyREx provides the *EventKernel* class to control a basic simulation including the creation of neutrinos and their respective signals, the propagation of their pulses to the antennas, and the triggering of the antennas. The *EventKernel* is designed to be modular and can use a specific ice model, ray tracer, and signal times as specified in optional arguments (the defaults are explicitly specified below):

2.7. Full Simulation 27

```
particle_generator = pyrex.CylindricalShadowGenerator(dr=1000, dz=1000,
                                                      energy=1e8)
detector = []
for i, z in enumerate([-100, -150, -200, -250]):
   detector.append(
       pyrex.DipoleAntenna(name="antenna_"+str(i), position=(0, 0, z),
                            center_frequency=250e6, bandwidth=300e6,
                            resistance=0, effective_height=0.6,
                            trigger_threshold=1e-4, noisy=False)
   )
kernel = pyrex.EventKernel(generator=particle_generator,
                           antennas=detector,
                           ice_model=pyrex.IceModel,
                           ray_tracer=pyrex.RayTracer,
                           signal_times=np.linspace(-20e-9, 80e-9, 2000,
                                                    endpoint=False))
triggered = False
while not triggered:
   event = kernel.event()
   for antenna in detector:
        if antenna.is_hit:
           triggered = True
           break
particle = event.roots[0]
print("Particle type: ", particle.id)
print("Shower vertex: ", particle.vertex)
                      ", particle.direction)
print("Shower axis:
print("Particle energy: ", particle.energy)
print("Interaction type:", particle.interaction.kind)
print("Electromagnetic shower fraction:", particle.interaction.em_frac)
                                   ", particle.interaction.had_frac)
print("Hadronic shower fraction:
print("Event weight:", particle.weight)
for antenna in detector:
    for i, wave in enumerate(antenna.waveforms):
        plt.plot(wave.times * 1e9, wave.values)
        plt.xlabel("Time (ns)")
        plt.ylabel("Voltage (V)")
        plt.title(antenna.name + " - waveform "+str(i))
```

2.7. Full Simulation 28



### 2.8 Data File I/O

The File class controls the reading and writing of data files for simulation. At the most basic it takes a filename and mode in which to open the file, and if the file type is supported the object will be the appropriate file handler.

Like python's open () function, the File class works as a context manager and should preferrably be used in with statements. Currently the only data file type supported by PyREx is HDF5. Depending on whether an HDF5 file is being read or written there are additional keyword arguments that may be provided to File. HDF5 files support the following modes: 'r' for read-only, 'w' for write (overwrites existing file), 'a'/r+' for append (doesn't overwrite existing file), and 'x' for write (fails if file exists already).

If writing an HDF5 file, the optional arguments specify which event data to write. The available write options are write\_particles, write\_triggers, write\_antenna\_triggers, write\_rays, write\_noise, and write\_waveforms. Most of these are self-explanatory, but write\_antenna\_triggers will write triggering information for each antenna in the detector and write\_noise will write the frequency data required to replicate noise waveforms. The last optional argument is require\_trigger which specifies which data should only be written when the detector is triggered. If a boolean value, requires trigger or not for all data with the exception of particle and trigger data, which is always written. If a list of strings, the listed data will require triggers and any other data will always be written.

The most straightforward way to write data files is to pass a File object to the EventKernel object handling the simulation. In such a case, a global trigger condition should be passed to the EventKernel as well, either as a function which acts on a detector object, or as the "global" key in a dictionary of functions representing various trigger conditions:

```
particle_generator = pyrex.CylindricalShadowGenerator(dr=1000, dz=1000,
                                                       energy=1e8)
detector = []
for i, z in enumerate([-100, -150, -200, -250]):
   detector.append(
        pyrex.DipoleAntenna(name="antenna_"+str(i), position=(0, 0, z),
                            center_frequency=250e6, bandwidth=300e6,
                            resistance=0, effective_height=0.6,
                            trigger_threshold=1e-4, noisy=False)
def global_trigger_condition(det):
    for ant in det:
        if ant.is_hit:
            return True
    return False
def even_antenna_trigger(det):
    for i, ant in enumerate(det):
        if i%2==0 and ant.is_hit:
            return True
    return False
trigger_conditions = {
    "global": global_trigger_condition,
    "evens": even_antenna_trigger,
    "ant1": lambda det: det[1].is_hit
with pyrex.File('my_data_file.h5', 'x') as f:
    kernel = pyrex.EventKernel(generator=particle_generator,
                               antennas=detector,
                               event_writer=f,
                               triggers=trigger_conditions)
    for _ in range(10):
        event, triggered = kernel.event()
```

If you want to manually write the data file, then the File.set\_detector() and File.add() methods are necessary. File.set\_detector() associates the given antennas with the file object (and writes their data) and File.add() adds the data from the given event to the file. Here we also manually open and close the file object with File.open() and File.close(), and add some metadata to the file with File.add\_file\_metadata():

The <code>File</code> objects also support writing miscellaneous analysis data to the file. <code>File.create\_analysis\_dataset()</code> creates and returns a basic HDF5 dataset. <code>File.create\_analysis\_metadataset()</code> creates a joined set of tables for string and float data, which can be written to with <code>File.add\_analysis\_metadata()</code>. And finally, <code>File.add\_analysis\_indices()</code> allows for linking event indices to specific rows of analysis data.

If reading an HDF5 file, the slice\_range argument specifies the size of event slices to load into memory at once when iterating over events. In general, increasing the slice\_range will improve the speed of iteration at the cost of greater memory consumption.

```
with pyrex.File('my_data_file.h5', 'r', slice_range=100) as f:
    pass
```

When reading HDF5 files, there are a number of methods and attributes available to access the data. With the File

object alone, File.file\_metadata contains a dictionary of the file's metadata and File.antenna\_info contains a list of dictionaries with data for each antenna in the detector the file was run with. If waveform data is available, File.get\_waveforms() can be used to get all waveforms in the file or a specific subset based on event\_id, antenna\_id, and waveform\_type arguments. Finally, direct access to the contents of the HDF5 file is supported through either the proper paths or nicknames.

```
with pyrex.File('my_data_file.h5', 'r') as f:
   print(f.file_metadata)
   print(f.antenna_info[0])
    # No waveform data was stored above, so these will fail if run
    # All waveforms:
    # wfs = f.get_waveforms()
    # Waveforms from event 0
    # wfs = f.get_waveforms(event_id=0)
    # Waveforms in antenna 1 from all events
    # wfs = f.get_waveforms(antenna_id=1)
    # Direct waveform in antenna 4 from event 5
    # wf = f.get_waveforms(event_id=5, antenna_id=4, waveform_type=0)
    # Using full file path
   triggers = f['data/triggers']
    # Using dataset nickname
   particle_string_metadata = f['particles_meta_str']
    # Using analysis dataset nickname
   other = f['meaningless_data']
```

HDF5 files opened in read-only mode can also be iterated over, which allows access to the data for each event in turn. When iterating, the event objects have the following methods for accessing data. get\_particle\_info() and get\_rays\_info() return a list of dictionaries or attribute values for the event's particles or rays, respectively. The is\_neutrino, is\_nubar, and flavor attributes also contain the associated basic information about the base particle of the event. get\_waveforms() returns the waveforms for the event, or a specific subset based on antenna\_id and waveform\_type (as above). The triggered attribute contains whether the event triggered the detector and the get\_triggered\_components() method returns a list of the trigger conditions of the detector which were met (as specified when writing the file). And finally, if noise data is recorded for the event it is contained in the noise\_bases attribute. Iteration of the HDF5 files supports slicing as long as the step size is positive-valued, and individual events can also be reached by indexing the File object.

# 2.9 More Examples

For more code examples, see the *Example Code* section and the python notebooks in the examples directory.

2.9. More Examples 33

**CHAPTER** 

THREE

# **CUSTOM SUB-PACKAGE**

While the PyREx package provides a basis for simulation, the real benefits come in customizing the analysis for different purposes. To this end the custom sub-package allows for plug-in style modules to be distributed for different collaborations.

By default PyREx comes with custom modules for IREX (IceCube Radio Extension) and ARA (Askaryan Radio Array) accessible at pyrex.custom.irex and pyrex.custom.ara, respectively. More information about these modules can be found in their respective sections below.

Other institutions and research groups are encouraged to create their own custom modules to integrate with PyREx. These modules have full access to PyREx as if they were a native part of the package. When PyREx is loaded it automatically scans for these custom modules in certain parts of the filesystem and includes any modules that it can find. The first place searched is the custom directory in the PyREx package itself. Next, if a .pyrex-custom directory exists in the user's home directory (note the leading .), its subdirectories are searched for custom directories and any modules in these directories are included. Finally, if a pyrex-custom directory exists in the current working directory (this time without the leading .), its subdirectories are similarly scanned for modules inside custom directories. Note that if any name-clashing occurs, the first result found takes precedence (without warning). Additionally, none of these custom directories should contain an \_\_init\_\_.py file, or else the plug-in system may not work (For more information on the implementation, see PEP 420 and/or David Beazley's 2015 PyCon talk on Modules and Packages at https://youtu.be/0oTh1CXRaQ0?t=1h25m45s).

As an example, in the following filesystem layout (which is not meant to reflect the actual current modules available to PyREx) the available custom modules are pyrex.custom.pyspice, pyrex.custom.irex, pyrex.custom.ara, pyrex.custom.arianna, and pyrex.custom.my\_analysis. Additionally note that the name clash for the ARA module will result in the module included in PyREx being loaded and the ARA module in .pyrex-custom will be ignored.

```
/path/to/site-packages/pyrex/
|-- __init__.py
|-- signals.py
|-- antenna.py
|-- ...
|-- custom/
 |-- pyspice.py
  |-- irex/
     |-- __init__.py
   |-- antenna.py
   |-- ...
   |-- ara/
      |-- ___init___.py
   |-- antenna.py
   |-- ...
/path/to/home_dir/.pyrex-custom/
|-- ara/
  |-- custom/
   | |-- ara/
   | | |-- antenna.py
   | |-- ...
|-- arianna/
  |-- custom/
      |-- arianna/
          |-- __init__.py
      1
      |-- antenna.py
          |-- ...
      /path/to/cwd/pyrex-custom/
|-- my_analysis_module/
 |-- custom/
   | |-- my_analysis.py
```

# 3.1 ARA Custom Module

The ARA module contains classes for antennas and detectors as found or proposed for the ARA project.

The <code>HpolAntenna</code> and <code>VpolAntenna</code> classes are models of ARA Hpol and Vpol antennas using data lifted from AraSim. They use the antenna directional gains in <code>data/ARA\_dipoletestl\_output\_MY\_fixed.txt</code> and <code>data/ARA\_bicone6in\_output\_MY\_fixed.txt</code> respectively, and the electronics gains in <code>data/ARA\_Electronics\_TotalGain\_TwoFilters.txt</code>. The trigger condition of these antennas is based on a comparison of the maximum value of the tunnel-diode-convolved waveforms with the rms value of a tunnel-diode-convolved noise waveform.

The ARAString class creates a string of alternating HpolAntenna and VpolAntenna ojbects, as in a typical ARA station. The PhasedArrayString class implements a more densely-packed string of antennas which trigger based on a threshold trigger on the best beam-formed combination of the antenna waveforms. The RegularStation class creates a station at the given position with 4 (or another given number) strings spaced evenly around the station center. The AlbrechtStation class (proposed by Albrecht Karle) creates two phased array strings at the station center, one of VpolAntenna objects and the other of HpolAntenna objects, as well as 3 (or another given number) outrigger strings spaced evenly around the station center. The HexagonalGrid class creates a hexagonal grid of stations, spiralling outward from the center.

# 3.2 ARIANNA Custom Module

The ARIANNA module contains classes for antennas as found in the ARIANNA project.

The LPDA class is the model of the ARIANNA LPDA antenna based on data from NuRadioReco. It uses directional/polarization gain from data/createLPDA\_100MHz\_InfFirn.adl and data/createLPDA\_100MHz\_InfFirn.ral, and amplification gain from data/amp\_300\_gain.csv and data/amp\_300\_phase.csv. The trigger condition of the antenna requires the signal to reach above and below some threshold values within a trigger window.

### 3.3 IREX Custom Module

The IREX module contains classes for antennas and detectors which use waveform envelopes rather than raw waveforms. The detectors provided allow for testing of grid and station geometries.

The EvelopeHpol and EvelopeVpol classes wrap models of ARA Hpol and Vpol antennas with an additional front-end which uses a diode-bridge circuit to create waveform envelopes. The trigger condition for these antennas is a simple threshold trigger on the envelopes.

The IREXString class creates a string of EvelopeVpol antennas at a given position. The RegularStation class creates a station at a given position with 4 (or another given number) strings spaced evenly around the station center. The CoxeterStation class creates a station at a given position similar to the RegularStation, but with one string at the station center and the rest spaced evenly around the center. The StationGrid class creates a rectangular grid of stations (or strings, as specified by the station type). The dimensions of the grid in stations is Nx by Ny where N is the total number of stations, Nx=floor(sqrt(N)), and Ny=floor(N/Nx).

# 3.4 Build Your Own Custom Module

In the course of using PyREx you may wish to change some behavior of parts of the code. Due to the modularity of the code, many behavoirs should be customizable by substituting in your own classes inheriting from those already in PyREx. By adding these classes to your own custom module, your code can behave as though it was a native part of the PyREx package. Below the classes which can be easily substituted with your own version are listed, and descriptions of the behavior expected of the classes is outlined.

# 3.4.1 Askaryan Signal

The AskaryanSignal class is responsible for storing the time-domain signal of the Askaryan signal produced by a particle shower. The \_\_init\_\_() method of an AskaryanSignal-like class must accept the arguments listed below:

Attribute	Description	
times	A list-type (usually a numpy array) of time values at which to calculate the amplitude of the	
	Askaryan pulse.	
particle	A Particle object representing the neutrino that causes the event. Should have an energy,	
	vertex, id, and an interaction with an em_frac and had_frac.	
viewing_an	viewing_angle in radians measured from the shower axis.	
viewing_di	s Tane distance of the observation point from the shower vertex.	
ice	The ice model to be used for describing the medium's index of refraction.	
t0	The starting time of the Askaryan pulse / showers (default 0).	

The \_\_init\_\_() method should result in a Signal object with values being a numpy array of amplitudes corresponding to the given times and should have a proper value\_type. Additionally, all methods of the Signal class should be implemented (typically by just inheriting from Signal).

# 3.4.2 Antenna / Antenna System

The Antenna class is primarily responsible for receiving and triggering on Signal objects. The \_\_init\_\_() method of an Antenna-like class must accept a position argument, and any other arguments may be specified as desired. The \_\_init\_\_() method should set the position attribute to the given argument. If not inheriting from Antenna, the following methods and attributes must be implemented and may require the \_\_init\_\_() method to set some other attributes. AntennaSystem-like classes must expose the same required methods and attributes as Antenna-like classes, typically by passing calls down to an underlying Antenna-like object and applying some extra processing.

The <code>signals</code> attribute should contain a list of all pure <code>Signal</code> objects that the antenna has seen. This is different from the <code>all\_waveforms</code> attribute, which should contain a list of all waveform (pure signal + noise) <code>Signal</code> objects the antenna has seen. Yet again different from the <code>waveforms</code> attribute, which should contain only those waveforms which have triggered the antenna.

If using the default all\_waveforms and waveforms, a \_noises attribute and \_triggers attribute must be initialized to empty lists in \_\_init\_\_(). Additionally a make\_noise() method must be defined which takes a times array and returns a <code>Signal</code> object with noise amplitudes in the values attribute. If using the default make\_noise() method, a \_noise\_master attribute must be set in \_\_init\_\_() to either None or a <code>Signal</code> object that can generate noise waveforms (setting \_noise\_master to None and handling noise generation with the attributes <code>freq\_range</code> and <code>noise\_rms</code>, or <code>temperature</code> and <code>resistance</code>, is recommended).

A full\_waveform() method is required which will take a times array and return a <code>Signal</code> object of the waveform the antenna sees at those times. If using the default full\_waveform(), a noisy attribute is required which contains a boolean value of whether or not the antenna includes noise in its waveforms. If noisy is <code>True</code> then a <code>make\_noise()</code> method is also required, as described in the previous paragraph.

An is\_hit attribute is required which will be a boolean of whether or not the antenna has been triggered by any waveforms. Similarly an is\_hit\_during() method is required which will take a times array and return a boolean of whether the antenna is triggered during those times.

The trigger() method of the antenna should take a Signal object and return a boolean of whether or not that signal would trigger the antenna.

The clear() method should reset the antenna to a state of having received no signals (i.e. the state just after initialization), and should accept a boolean for reset\_noise which will force the noise waveforms to be recalculated. If using the default clear() method, the \_noises and \_triggers attributes must be lists.

A receive () method is required which will take a <code>Signal</code> object as <code>signal</code>, a 3-vector (list) as <code>direction</code>, and a 3-vector (list) as <code>polarization</code>. This function doesn't return anything, but instead processes the input signal and stores it to the <code>signals</code> list (and anything else needed for the antenna to have officially received the signal). This is the final required method, but if using the default <code>receive()</code> method, an <code>antenna\_factor</code> attribute is needed to define the conversion from electric field to voltage and an <code>efficiency</code> attribute is required, along with four more methods which must be defined:

The \_convert\_to\_antenna\_coordinates () method should take a point in cartesian coordinates and return the r, theta, and phi values of that point relative to the antenna. The directional\_gain () method should take theta and phi in radians and return a (complex) gain based on the directional response of the antenna. Similarly the polarization\_gain() method should take a polarization 3-vector (list) of an incoming signal and return a (complex) gain based on the polarization response of the antenna. Finally, the response() method should take a list of frequencies and return the (complex) gains of the frequency response of the antenna. This assumes that the directional and frequency responses are separable. If this is not the case then the gains may be better handled with a custom receive() method.

### 3.4.3 Detector

The preferred method of creating your own detector class is to inherit from the <code>Detector</code> class and then implement the <code>set\_positions()</code> method, the <code>triggered()</code> method, and potentially the <code>build\_antennas()</code> method. However the only requirement of a <code>Detector</code>-like object is that iterating over it will visit each antenna exactly once. This means that a simple list of antennas is an acceptable rudimentary detector. The advantages of using the <code>Detector</code> class are easy breaking into subsets (a detector could be made up of stations, which in turn are made up of strings) and the simpler <code>triggered()</code> method for trigger checks.

## 3.4.4 Ice Model

Ice model classes are responsible for describing the properties of the ice as functions of depth and frequency. While not explicitly required, all ice model classes in PyREx are defined only with static and class methods, so no \_\_init\_\_\_() method is actually necessary. The necessary methods, however, are as follows:

The index() method should take a depth (or numpy array of depths) and return the corresponding index of refraction. Conversely, the depth\_with\_index() method should take an index of refraction (or numpy array of indices) and return othe corresponding depths. In the case of degeneracy here (for example with uniform ice), the recommended behavior is to return the shallowest depth with the given index, though PyREx's behavior in cases of non-monotonic index functions is not well defined.

The temperature () method should take a depth (or numpy array of depths) and return the corresponding ice temperature in Kelvin.

Finally, the attenuation\_length() function should take a depth (or numpy array of depths) and a frequency (or numpy array of frequencies) and return the corresponding attenuation length. In the case of one scalar and one array argument, a simple 1D array should be returned. In the case of both arguments being arrays, the return value should be a 2D array where each row represents different frequencies at a single depth and each column represents different depths at a single frequency.

## 3.4.5 Ray Tracer / Ray Trace Path

The RayTracer and RayTracePath classes are responsible for handling ray tracing through the ice between shower vertices and antenna positions. The RayTracer class finds the paths between the two points and the RayTracePath calculates values along the path. Due to the potential for high calculation costs, the PyREx RayTracer and RayTracePath classess inherit from a LazyMutableClass which allows the use of a lazy\_property() decorator to cache results of attribute calculations. It is recommended that any other ray tracing classes consider doing this as well.

The \_\_init\_\_() method of a <code>RayTracer</code>-like class should take as arguments a 3-vector (list) from\_point, a 3-vector (list) to\_point, and an <code>IceModel</code>-like ice\_model. The only required features of the class are a boolean attribute <code>exists</code> recording whether or not paths exist between the given points, and an iterable attribute <code>solutions</code> which iterates over <code>RayTracePath</code>-like objects between the points.

A RayTracePath-like class will be initialized by a corresponding RayTracer-like object, so there are no requirements on its \_\_init\_\_() method. The path must have emitted\_direction and received\_direction attributes which are numpy arrays of the cartesian direction the ray is pointing at the from\_point and to\_point of the ray tracer, respectively. The path must also have attributes for the path\_length and tof (time of flight) alon the path.

The path class must have a propagate () method which takes a <code>Signal</code> object as its argument and propagates that signal by applying any attenuation and time of flight. This method does not have a return value. Additionally, note that any 1/R factor that the signal could have is not applied in this method, but externally by dividing the singal values by the <code>path\_length</code>. If using the default <code>propagate()</code> method, an <code>attenuation()</code> method is required which takes an array of frequencies <code>f</code> and returns the attenuation factors for a signal along the path at those frequencies.

Finally, though not required it is recommended that the path have a coordinates attribute which is a list of lists of the x, y, and z coordinates along the path (with some reasonable step size). This method is used for plotting purposes and does not need to have the accuracy necessary for calculations.

### 3.4.6 Interaction Model

The interaction model used for <code>Particle</code> interactions in ice handles the cross sections and interaction lengths of neutrinos, as well as the ratios of their interaction types and the resulting shower fractions. An interaction class should inherit from <code>Interaction</code> (preferrably keeping its <code>\_\_init\_\_()</code> method) and should implement the following methods:

The cross\_section property method should return the neutrino cross section for the Interaction. particle parent, specific to the Interaction.kind. Similarly the total\_cross\_section property method should return the neutrino cross section for the Interaction.particle parent, but this should be the total cross section for both charged-current and neutral-current interactions. The interaction\_length and total\_interaction\_length properties will convert these cross sections to interaction lengths automatically.

The choose\_interaction() method should return a value from Interaction. Type representing the interaction type based on a random choice. Similarly the choose\_inelasticity() method should return an inelasticity value based on a random choice, and the choose\_shower\_fractions() method return calculate electromagnetic and hadronic fractions based on the inelasticity attribute storing the inelasticity value from choose\_inelasticity(). The choose\_shower\_fractions() can be either chosen based on random processes like secondary generation or deterministic.

### 3.4.7 Particle Generator

The particle generator classes are quite flexible. The only requirement is that they possess an <code>create\_event()</code> method which returns a <code>Event</code> object consisting of at least one <code>Particle</code>. The <code>BaseGenerator</code> class provides a solid foundataion for basic uniform generators in a volume, requiring only implementation of the <code>get\_vertex()</code> and <code>get\_exit\_points()</code> methods for the specific volume at a minimum.

**CHAPTER** 

**FOUR** 

## **EXAMPLE CODE**

This section includes a number of more complete code examples for performing various tasks with PyREx. Each example includes a description of what it does, comments throughout describing the process, and a reference to the corresponding example script or notebook which can be run independent of one another. The examples are organized roughly from more basic to more complex.

# 4.1 Plot Detector Geometry

In this example we will make a few simple plots of the geometry of a detector object, handy for presentations or for visualizing your work. This code can be run from the Plot Detector notebook in the examples directory.

```
import numpy as np
import matplotlib.pyplot as plt
from mpl_toolkits.mplot3d import Axes3D
import pyrex
import pyrex.custom.irex as irex
# First we need to initialize the detector object and build its antennas.
# For this example we'll just use a basic station geometry. Since we won't be
# throwing any particles at it, the arguments of the antennas are largely
# unimportant, but we will set up the antennas to alternatingly be oriented
# vertically or horizontally.
detector = irex.StationGrid(stations=4, station_type=irex.RegularStation,
                            antennas_per_string=4, antenna_separation=10)
def alternating_orientation(index, antenna):
    if index%2==0:
        return ((0,0,1), (1,0,0))
    else:
        return ((1,0,0), (0,0,1))
detector.build_antennas(trigger_threshold=0,
                        orientation_scheme=alternating_orientation)
# Let's also define a function which will highlight certain antennas in red.
# This one will highlight all antennas which are oriented horizontally.
def highlight(antenna_system):
    # Since the antennas in our detector are technically AntennaSystems,
    # to access the orientation we need to get the antenna object
    # which is a member of the AntennaSystem
   return np.dot(antenna_system.antenna.z_axis, (0,0,1)) == 0
# For our first plot, let's make a 3-D image of the whole detector.
fig = plt.figure()
```

```
ax = fig.add_subplot(111, projection='3d')
# Plot the antennas which satisfy the highlight condition in red
xs = [ant.position[0] for ant in detector if highlight(ant)]
ys = [ant.position[1] for ant in detector if highlight(ant)]
zs = [ant.position[2] for ant in detector if highlight(ant)]
ax.scatter(xs, ys, zs, c="r")
# Plot the other antennas in black
xs = [ant.position[0] for ant in detector if not highlight(ant)]
ys = [ant.position[1] for ant in detector if not highlight(ant)]
zs = [ant.position[2] for ant in detector if not highlight(ant)]
ax.scatter(xs, ys, zs, c="k")
plt.show()
# Now let's plot the detector in a couple different 2-D angles.
# First, a top-down view of the entire detector.
plt.figure(figsize=(5, 5))
xs = [ant.position[0] for ant in detector if highlight(ant)]
ys = [ant.position[1] for ant in detector if highlight(ant)]
plt.scatter(xs, ys, c="r")
xs = [ant.position[0] for ant in detector if not highlight(ant)]
ys = [ant.position[1] for ant in detector if not highlight(ant)]
plt.scatter(xs, ys, c="k")
plt.title("Detector Geometry (Top View)")
plt.xlabel("x-position")
plt.ylabel("y-position")
plt.show()
# Next, let's take an x-z view of a single station. Let's also add in some
# string graphics by drawing lines from bottom antennas to the top of the ice.
plt.figure(figsize=(5, 5))
for station in detector.subsets:
   for string in station.subsets:
        lowest_antenna = sorted(string.subsets,
                                key=lambda ant: ant.position[2])[0]
        plt.plot([lowest_antenna.position[0], lowest_antenna.position[0]],
                 [lowest_antenna.position[2], 0], c="k", lw=1, zorder=-1)
xs = [ant.position[0] for ant in detector if highlight(ant)]
zs = [ant.position[2] for ant in detector if highlight(ant)]
plt.scatter(xs, zs, c="r", label="Horizontal")
xs = [ant.position[0] for ant in detector if not highlight(ant)]
zs = [ant.position[2] for ant in detector if not highlight(ant)]
plt.scatter(xs, zs, c="k", label="Vertical")
plt.xlim(200, 300)
plt.title("Single-Station Geometry (Side View)")
plt.xlabel("x-position")
plt.ylabel("z-position")
plt.legend()
```

plt.show()

# 4.2 Askaryan Frequency Content

In this example we explore how the frequency spectrum of an Askaryan pulse changes as a function of the off-cone angle (i.e. the angular distance between the Cherenkov angle and the observation angle). This code can be run from the Frequency Content notebook in the examples directory.

```
import numpy as np
import matplotlib.pyplot as plt
import pyrex
# First, set up a neutrino source and find the index of refraction at its depth.
# Then use that index of refraction to calculate the Cherenkov angle.
source = pyrex.Particle("nu_e", vertex=(0, 0, -1000), direction=(0, 0, -1),
                        energy=1e8)
n = pyrex.IceModel.index(source.vertex[2])
ch_angle = np.arccos(1/n)
# Now, for a range of dthetas, generate an Askaryan pulse dtheta away from the
# Chereknov angle and plot its frequency spectrum.
for dtheta in np.radians(np.logspace(-1, 1, 5)):
   n_pts = 10001
   pulse = pyrex.AskaryanSignal(times=np.linspace(-20e-9, 80e-9, n_pts),
                                 particle=source,
                                 viewing_angle=ch_angle-dtheta,
                                 viewing_distance=1000)
   plt.plot(pulse.frequencies[:int(n_pts/2)] * 1e-6, # Convert from Hz to MHz
             np.abs(pulse.spectrum)[:int(n_pts/2)])
   plt.title("Frequency Spectrum of Askaryan Pulse\n"+
              str(round(np.degrees(dtheta),2))+" Degrees Off-Cone")
   plt.xlabel("Frequency (MHz)")
   plt.xlim(0, 3000)
   plt.show()
# Actually, we probably really want to see the frequency content after the
# signal has propagated through the ice a bit. So first set up the ray tracer
# from our neutrino source to some other point where our antenna might be
# (and make sure a path between those two points exists).
rt = pyrex.RayTracer(from_point=source.vertex, to_point=(500, 0, -100))
if not rt.exists:
   raise ValueError ("Path to antenna doesn't exist!")
# Finally, plot the signal spectrum as it appears at the antenna position by
# propagating it along the (first solution) path.
path = rt.solutions[0]
for dtheta in np.radians(np.logspace(-1, 1, 5)):
   n_pts = 2048
    pulse = pyrex.AskaryanSignal(times=np.linspace(-20e-9, 80e-9, n_pts),
                                 particle=source,
                                 viewing_angle=ch_angle-dtheta,
                                 viewing_distance=path.path_length)
   path.propagate(pulse)
   plt.plot(pulse.frequencies[:int(n_pts/2)] * 1e-6, # Convert from Hz to MHz
```

# 4.3 Calculate Effective Area

In this example we will calculate the effective area of a detector over a range of energies. This code can be run from the Effective Area notebook in the examples directory.

**Warning:** In order to finish reasonably quickly, the number of events thrown in this example is low. This means that there are likely not enough events to accurately represent the effective area of the detector. For an accurate measurement, the number of events must be increased, but this will need much more time to run in that case.

```
import numpy as np
import matplotlib.pyplot as plt
import pyrex
import pyrex.custom.ara as ara
# First let's set the number of events that we will be throwing at each energy,
# and the energies we will be using. As stated in the warning, the number of
# events is set low to speed up the example, but that means the results are
# likely inaccurate. The energies are high to increase the chance of triggering.
n = vents = 100
energies = [1e9, 2e9, 5e9, 1e10] # GeV
# Next, set up the detector to be measured. Here we use a single standard
# ARA station.
detector = ara.HexagonalGrid(station_type=ara.RegularStation,
                             stations=1)
detector.build_antennas(power_threshold=-6.15)
# Now set up a neutrino generator for each energy. We'll use unrealistically
# small volumes to increase the chance of triggering.
generators = [pyrex.CylindricalShadowGenerator(dr=1000, dz=1000, energy=energy)
              for energy in energies]
# And then set up the event kernels for each energy. Let's use the ArasimIce
# class as our ice model since it calculates attenuations faster at the loss
# of some accuracy.
kernels = [pyrex.EventKernel(generator=gen, antennas=detector,
                             ice_model=pryex.ice_model.ArasimIce)
           for gen in generators]
# Now run each kernel and record the number of events from each that triggered
# the detector. In this case we'll set our trigger condition to 3/8 antennas
```

```
# triggering in a single polarization.
triggers = np.zeros(len(energies))
for i, kernel in enumerate(kernels):
    print("Running energy", energies[i])
    for j in range(n_events):
        print(j, "...", sep="", end="")
        detector.clear(reset_noise=True)
        particle = kernel.event()
        triggered = detector.triggered(station_requirement=1,
                                       polarized_antenna_requirement=3)
        if triggered:
            triggers[i] += 1
            print("y", end=" ")
            print("n", end=" ")
        if j%10==9:
            print (flush=True)
    print(triggers[i], "events triggered at", energies[i]/1e6, "PeV")
print("Done")
# Now that we have the trigger counts for each energy, we can calculate the
# effective volumes by scaling the trigger probability by the generation volume.
# Errors are calculated assuming poisson counting statistics.
generation_volumes = np.ones(4)*1000*1000*1000
effective_volumes = triggers / n_events * generation_volumes
volume_errors = np.sqrt(triggers) / n_events * generation_volumes
plt.errorbar(energies, effective_volumes, yerr=volume_errors,
             marker="o", markersize=5, linestyle=":", capsize=5)
ax = plt.gca()
ax.set_xscale("log")
ax.set_yscale("log")
plt.title("Detector Effective Volume")
plt.xlabel("Neutrino Energy (GeV)")
plt.ylabel("Effective Volume (km^3)")
plt.show()
# Then from the effecitve volumes, we can calculate the effective areas.
# The effective area is the probability interaction in the ice volume times the
# effective volume. The probability of interaction in the ice volume is given by
# the interaction cross section times the density of the ice. Calculate the
# cross section as an average of the neutrino and antineutrino cross sections.
cross_sections = np.zeros(len(energies))
for i, energy in enumerate(energies):
    nu = pyrex.Particle(particle_id="nu_e", vertex=(0, 0, 0),
                        direction=(0, 0, 1), energy=energy)
   nu_bar = pyrex.Particle(particle_id="nu_e_bar", vertex=(0, 0, 0),
                            direction=(0, 0, 1), energy=energy)
    cross_sections[i] = (nu.interaction.total_cross_section +
                         nu_bar.interaction.total_cross_section) / 2
ice_density = 0.92 \# g/cm^3
ice_density *= 1e15 # converted to q/km^3 = nucleons/km^3
effective_areas = 6.022e23 * ice_density * cross_sections * effective_volumes
effective_areas *= 1e-4 # converted from cm^2 to m^2
area_errors = 6.022e23 * ice_density * cross_sections * volume_errors * 1e-4
```

# 4.4 Examine a Single Event

In this example we will generate a single event with a given vertex, direction, and energy, and then we'll examine the event by plotting the waveforms. This is typically useful for auditing events from a larger simulation. This code can be run from the Examine Event notebook in the examples directory.

```
import numpy as np
import matplotlib.pyplot as plt
import pyrex
import pyrex.custom.ara as ara
# First let's rebuild our detector that was used in the simulation.
det = ara.HexagonalGrid(station_type=ara.RegularStation,
                        stations=1, lowest_antenna=-100)
det.build_antennas(power_threshold=-6.15)
# Then let's plot a couple views of it just to be sure everything looks right.
fig, ax = plt.subplots(1, 2, figsize=(12, 5))
ax[0].scatter([ant.position[0] for ant in det],
              [ant.position[1] for ant in det],
              c='k')
ax[0].set_title("Detector Top View")
ax[0].set_xlabel("x-position")
ax[0].set_ylabel("y-position")
ax[1].scatter([ant.position[0] for ant in det],
              [ant.position[2] for ant in det],
              c='k')
ax[1].set_title("Detector Side View")
ax[1].set_xlabel("x-position")
ax[1].set_ylabel("z-position")
plt.show()
# Now set up a particle generator that will just throw the one event we're
# interested in, and create an event kernel with our detector and our generator.
p = pyrex.Particle(particle_id=pyrex.Particle.Type.electron_neutrino,
                   vertex=[1002.65674195, -421.95118348, -586.0953201],
                   direction=[-0.90615395, -0.41800062, -0.06450191],
                   energy=1e9)
p.interaction.kind = p.interaction.Type.charged_current
p.interaction.em_frac = 1
p.interaction.had_frac = 0
gen = pyrex.ListGenerator(pyrex.Event(p))
kern = pyrex.EventKernel(antennas=det, generator=gen)
```

```
# Then make sure our detector is cleared out and throw the event!
# reset_noise will make sure we get new noise waveforms every time.
det.clear(reset_noise=True)
kern.event()
# Now let's take a look at the waveforms of the event. Since each event has a
# first and second ray, plot their waveforms side-by-side for each antenna.
for i, ant in enumerate(det):
   fig, ax = plt.subplots(1, 2, figsize=(12, 3))
    for j, wave in enumerate(ant.all_waveforms):
       ax[j].plot(wave.times*1e9, wave.values)
        ax[j].set_xlabel("Time (ns)")
        ax[j].set_ylabel("Amplitude (V)")
        ax[j].set_title("First Ray" if j%2==0 else "Second Ray")
   fig.suptitle("String "+str(int(i/4))+" "+ant.name)
   plt.show()
# From the plots it looks like the first ray is the one that triggered the
# detector. Let's calculate a signal-to-noise ratio of the first-ray waveform
# for each antenna.
print("Signal-to-noise ratios:")
for i, ant in enumerate(det):
   wave = ant.all_waveforms[0]
   signal_pp = np.max(wave.values) - np.min(wave.values)
   noise = ant.front_end(ant.antenna.make_noise(wave.times))
   noise_rms = np.sqrt(np.mean(noise.values**2))
   print(" String "+str(int(i/4))+" "+ant.name+":", signal_pp/(2*noise_rms))
# Let's also take a look at the trigger condition, which passes the waveform
# through a tunnel diode. Again we can plot the tunnel diode's integrated
# waveform for each ray side-by-side. The red lines indicate the trigger level.
# If the integrated waveform goes beyond those lines the antenna is triggered.
for i, ant in enumerate(det):
    fig, ax = plt.subplots(1, 2, figsize=(12, 3))
    for j, wave in enumerate(ant.all_waveforms):
       triggered = ant.trigger(wave)
       trigger_wave = ant.tunnel_diode(wave)
        # The first time ant.trigger is run for an antenna, the power mean and
        # rms are calculated which will determine the trigger condition.
        low_trigger = (ant._power_mean -
                      ant._power_rms*np.abs(ant.power_threshold))
        high_trigger = (ant._power_mean +
                        ant._power_rms*np.abs(ant.power_threshold))
        ax[j].plot(trigger_wave.times*1e9, trigger_wave.values)
        ax[j].axhline(low_trigger, color='r')
        ax[j].axhline(high_trigger, color='r')
        ax[j].set_title("Triggered" if triggered else "Missed")
        ax[j].set_xlabel("Time (ns)")
        ax[j].set_ylabel("Integrated Power (V^2)")
    fig.suptitle("String "+str(int(i/4))+" "+ant.name)
   plt.show()
# Finally, let's look at the relative trigger times to make sure they look
# reasonable. We could get the true relative trigger times from the waveforms
# by just taking the differences of their first times, but instead let's
# pretend we're doing an analysis and just use the times of the maxima.
trig_times = []
```

```
for ant in det:
   wave = ant.all_waveforms[0]
   trig_times.append(wave.times[np.argmax(np.abs(wave.values))])
# Then we can plot the progression of the event by coloring the antennas where
# red is the earliest time and blue/purple is the latest time.
fig, ax = plt.subplots(3, 1, figsize=(5, 16))
ax[0].scatter([ant.position[0] for ant in det],
              [ant.position[1] for ant in det],
              c=trig_times, cmap='rainbow_r')
ax[0].set_title("Detector Top View")
ax[0].set_xlabel("x-position")
ax[0].set_ylabel("y-position")
ax[1].scatter([ant.position[0] for ant in det],
              [ant.position[2] for ant in det],
              c=trig_times, cmap='rainbow_r')
ax[1].set_title("Detector Side View")
ax[1].set_xlabel("x-position")
ax[1].set_ylabel("z-position")
ax[2].scatter([ant.position[1] for ant in det],
              [ant.position[2] for ant in det],
              c=trig_times, cmap='rainbow_r')
ax[2].set_title("Detector Side View 2")
ax[2].set_xlabel("y-position")
ax[2].set_ylabel("z-position")
plt.show()
```

# **CONTRIBUTING TO PYREX**

PyREx is currently being maintained by Ben Hokanson-Fasig. Any direct contributions to the code base should be made through GitHub as described in the following sections, and will be reviewed by the maintainer or another approved reviewer. Note that contributions are also possible less formally through the creation of custom plug-ins, as described in *Custom Sub-Package*.

# 5.1 Branching Model

PyREx code contributions should follow a specific git branching model sometimes referred to as the Gitflow Workflow. In this model the master branch is reserved for release versions of the code, and most development takes place in feature branches which merge back to the develop branch.


The basic steps to add a feature are as follows:

- 1. From the develop branch, create a new feature branch.
- 2. In your feature branch, write the code.
- 3. Merge the feature branch back into the develop branch.
- 4. Delete the feature branch.

Then when it comes time for the next release, the maintainer will:

- 1. Create a release branch from the develop branch.
- 2. Document the changes for the new version.
- 3. Make any bug fixes necessary.
- 4. Merge the release branch into the master branch.
- 5. Tag the release with the version number.
- 6. Merge the release branch back into the develop branch.
- 7. Delete the release branch.

In order to make these processes easier, two shell scripts feature.sh and release.sh were created to automate the steps of the above processes respectively. The use of these scripts is defined in the following sections.



# 5.2 Contributing via Pull Request

The preferred method of contributing code to PyREx is to submit a pull request on GitHub. The general process for doing this is as follows:

First, if you haven't already you will need to fork the repository so that you have a copy of the code in which you can make your changes. This can be done by visiting https://github.com/bhokansonfasig/pyrex and clicking the Fork button in the upper-right.

Next you likely want to clone the repository onto your computer to edit the code. To do this, visit your fork on GitHub and click the Clone or download button and in your terminal run the git clone command with the copied link.

```
git clone https://github.com/YOUR-USERNAME/NAME-OF-FORKED-REPO
```

If you want your local clone to stay synced with the main PyREx repository, then you can set up an upstream remote.

Now before changing the code, you need to create a feature branch in which you can work. To do this, use the feature.sh script with the new action:

```
./feature.sh new feature-branch-name
```

This will create a new branch for you with the name you give it, and it will push the branch to GitHub. The name you use for your feature branch (in place of feature-branch-name above) should be a relatively short name, all lowercase with hyphens between words, and descriptive of the feature you are adding. If you would prefer that the branch not be pushed to GitHub immediately, you can use the private action in place of new in the command above.

Now that you have a feature branch set up, you can write the code for the new feature in this branch. One you've implemented (and tested!) the feature and you're ready for it to be added to PyREx, submit a pull request to the PyREx repository. To do this, go back to https://github.com/bhokansonfasig/pyrex and click the New pull request button. On the Compare changes page, click compare across forks. The base fork should be the main PyREx repository, the base branch should be develop, the head fork should be your fork of PyREx, and the compare branch should be your newly finished feature branch. Then after adding a title and description of your new feature, click Create pull request.

The last step is for the maintainer and other reviewers to review your code and either suggest changes or accept the pull request, at which point your code will be integrated for the next PyREx release!

# 5.3 Contributing with Direct Access

If you have direct access to the PyREx repository on GitHub, you can make changes without the need for a pull request. In this case the first step is to create a new feature branch with feature.sh as described above:

```
./feature.sh new feature-branch-name
```

Now in the feature branch, write and test your new code. Once that's finished you can merge the feature branch back using the merge action of feature.sh:

```
./feature.sh merge feature-branch-name
```

Note that (as long as the merge is successful) this also deletes the feature branch locally and on GitHub.

# 5.4 Releasing a New Version

If you are the maintainer of the code base (or were appointed by the maintainer to handle releases), then you will be responsible for creating and merging release branches to the master branch. This process is streamlined using the release.sh script. When it's time for a new release of the code, start by using the script to create a new release branch:

```
./release.sh new X.Y.Z
```

This creates a new branch named release-X.Y.Z where X.Y.Z is the release version number. Note that version numbers should follow Semantic Versioning, and if alpha, beta, release candidate, or other pre-release versions are necessary, lowercase letters may be added to the end of the version number. Additionally if creating a hotfix branch rather than a proper release, that can be specified at the end of the release.sh call:

```
./release.sh new X.Y.Z hotfix
```

Once the new release branch is created, the first commit to the branch should consist only of a change to the version number in the code so that it matches the release version number. This commit should have the message "Bumped version number to X.Y.Z".

The next step is to document all changes in the new release in the version history documentation. To help with this, release. sh prints out a list of all the commits since the last release. If you need to see this list again, you can use

```
git log master..release-X.Y.Z --oneline --no-merges
```

Once the documentation is up to date with all the changes (including updating any places in the usage or the examples which may have become outdated), do some bug testing and be sure that all code tests are passing. Then when you're sure the release is ready you can merge the release branch into the master and develop branches with

```
./release.sh merge X.Y.Z
```

This script will handle tagging the release and will delete the local release branch. If the release branch ended up pushed to GitHub at some point, it will need to be deleted there either through their interface or using

```
git push -d origin release-X.Y.Z
```

# **PYREX API**

The API documentation here is split into three sections. First, the *PyREx Package Imports* section documents all classes and functions that are imported by PyREx under a from pyrex import \* command. Next, the *Individual Module APIs* section is a full documentation of all the modules which make up the base PyREx package. And finally, the *Included Custom Sub-Packages* section documents the custom subpackages included with PyREx by default.

# 6.1 PyREx Package Imports

Signal(times, values[, value_type])	Base class for time-domain signals.	
<pre>EmptySignal(times[, value_type])</pre>	Class for signal with zero amplitude (all values = 0).	
FunctionSignal(times, function[, value_type])	Class for signals generated by a function.	
AskaryanSignal	alias of pyrex.signals.	
	ARVZAskaryanSignal	
ThermalNoise(times, f_band[, f_amplitude,])	Class for thermal Rayleigh noise signals.	
Antenna(position[, z_axis, x_axis,])	Base class for antennas.	
DipoleAntenna(name, position,[,])	Class for half-wave dipole antennas.	
AntennaSystem(antenna)	Base class for antenna system with front-end process-	
	ing.	
Detector(*args, **kwargs)	Base class for detectors for easily building up sets of	
	antennas.	
IceModel	<pre>alias of pyrex.ice_model.AntarcticIce</pre>	
<pre>prem_density(r)</pre>	Calculates the Earth's density at a given radius.	
slant_depth(angle, depth[, step])	Calculates the material thickness of a chord cutting	
	through Earth.	
NeutrinoInteraction	alias of pyrex.particle.CTWInteraction	
<pre>Particle(particle_id, vertex, direction, energy)</pre>	Class for storing particle attributes.	
Event(roots)	Class for storing a tree of Particle objects represent-	
	ing an event.	
CylindricalGenerator(dr, dz, energy[,])	Class to generate neutrino vertices in a cylindrical ice	
	volume.	
RectangularGenerator(dx, dy, dz, energy[,])	Class to generate neutrino vertices in a rectangular ice	
	volume.	
CylindricalShadowGenerator(dr, dz, energy[,	Class to generate neutrino vertices in a cylindrical ice	
])	volume.	
RectangularShadowGenerator(dx, dy, dz, en-	Class to generate neutrino vertices in a rectangular ice	
ergy)	volume.	
ListGenerator(events[, loop])	Class to generate neutrino events from a list.	
	Continued on next page	

Continued on next page

Table 1 – continued from previous page

FileGenerator(files[, slice_range,])	Class to	generate ne	utrino events from simulation
	file(s).		
RayTracer	alias	of	pyrex.ray_tracing.
	Special	LizedRayT	racer
RayTracePath	alias	of	pyrex.ray_tracing.
	Special	LizedRayT	racePath
<pre>EventKernel(generator, antennas[,])</pre>	High-leve	l kernel for co	ontrolling event simulation.
File	Class for 1	reading or wr	iting data files.

# 6.1.1 pyrex.Signal

class pyrex.Signal(times, values, value\_type=None)

Base class for time-domain signals.

Stores the time-domain information for signal values. Supports adding between signals with the same times array and value type.

### **Parameters**

times [array\_like] 1D array of times (s) for which the signal is defined.

**values** [array\_like] 1D array of values of the signal corresponding to the given *times*. Will be resized to the size of *times* by zero-padding or truncating as necessary.

value\_type Type of signal, representing the units of the values. Values should be from the Signal.Type enum, but integer or string values may work if carefully chosen. Signal. Type.undefined by default.

### **Attributes**

times, values [ndarray] 1D arrays of times (s) and corresponding values which define the signal.

value\_type [Signal.Type] Type of signal, representing the units of the values.

Type [Enum] Enum containing possible types (units) for signal values.

dt The time spacing of the times array, or None if invalid.

**frequencies** The FFT frequencies of the signal.

**spectrum** The FFT complex spectrum values of the signal.

**envelope** The envelope of the signal by Hilbert transform.

### **Methods**

Type	Enum containing possible types (units) for signal
	values.
filter_frequencies(freq_response[,	Apply the given frequency response function to the
force_real])	signal, in-place.
resample(n)	Resamples the signal into n points in the same time
	range, in-place.
with_times(new_times)	Returns a representation of this signal over a differ-
	ent times array.

# 6.1.2 pyrex.EmptySignal

**class** pyrex.**EmptySignal** (*times*, *value\_type=None*) Class for signal with zero amplitude (all values = 0).

### **Parameters**

times [array\_like] 1D array of times (s) for which the signal is defined.

value\_type Type of signal, representing the units of the values. Must be from the Signal.
Type Enum.

### See also:

**Signal** Base class for time-domain signals.

### Attributes

times, values [ndarray] 1D arrays of times (s) and corresponding values which define the signal.

value\_type [Signal.Type] Type of signal, representing the units of the values.

Type [Enum] Enum containing possible types (units) for signal values.

dt The time spacing of the times array, or None if invalid.

**frequencies** The FFT frequencies of the signal.

**spectrum** The FFT complex spectrum values of the signal.

**envelope** The envelope of the signal by Hilbert transform.

### **Methods**

Type	Enum containing possible types (units) for signal values.
filter_frequencies(freq_response[,	Apply the given frequency response function to the
force_real])	signal, in-place.
resample(n)	Resamples the signal into n points in the same time
	range, in-place.
with_times(new_times)	Returns a representation of this signal over a differ-
	ent times array.

# 6.1.3 pyrex.FunctionSignal

class pyrex.FunctionSignal(times, function, value\_type=None)

Class for signals generated by a function.

## **Parameters**

**times** [array\_like] 1D array of times (s) for which the signal is defined.

**function** [function] Function which evaluates the corresponding value(s) for a given time or array of times.

**value\_type** Type of signal, representing the units of the values. Must be from the Signal. Type Enum.

### See also:

**Signal** Base class for time-domain signals.

EmptySignal Class for signal with zero amplitude.

### **Attributes**

times, values [ndarray] 1D arrays of times (s) and corresponding values which define the signal.

value\_type [Signal.Type] Type of signal, representing the units of the values.

**Type** [Enum] Enum containing possible types (units) for signal values.

**function** [function] Function to evaluate the signal values at given time(s).

**dt** The time spacing of the *times* array, or None if invalid.

**frequencies** The FFT frequencies of the signal.

spectrum The FFT complex spectrum values of the signal.

**envelope** The envelope of the signal by Hilbert transform.

### **Methods**

Туре	Enum containing possible types (units) for signal values.
filter_frequencies(freq_response[,	Apply the given frequency response function to the
force_real])	signal, in-place.
resample(n)	Resamples the signal into n points in the same time
	range, in-place.
with_times(new_times)	Returns a representation of this signal over a differ-
	ent times array.

### 6.1.4 pyrex. Askaryan Signal

### pyrex.AskaryanSignal

alias of pyrex.signals.ARVZAskarvanSignal

### 6.1.5 pyrex.ThermalNoise

class pyrex. ThermalNoise (times, f\_band, f\_amplitude=None, rms\_voltage=None,  $ture=None, resistance=None, n_freqs=0$ )

Class for thermal Rayleigh noise signals.

The Rayleigh thermal noise is calculated in a given frequency band with flat or otherwise specified amplitude and random phase at some number of frequencies. Values are scaled to a provided or calculated RMS voltage.

### **Parameters**

times [array\_like] 1D array of times (s) for which the signal is defined.

**f\_band** [array\_like] Array of two elements denoting the frequency band (Hz) of the noise. The first element should be smaller than the second.

**f\_amplitude** [float or function, optional] The frequency-domain amplitude of the noise. If float, then all frequencies will have the same amplitude. If function, then the function is evaluated at each frequency to determine its amplitude. By default, uses Rayleigh-distributed amplitudes.

**rms\_voltage** [float, optional] The RMS voltage (V) of the noise. If specified, this value will be used instead of the RMS voltage calculated from the values of *temperature* and *resistance*.

**temperature** [float, optional] The thermal noise temperature (K). Used in combination with the value of *resistance* to calculate the RMS voltage of the noise.

**resistance** [float, optional] The resistance (ohm) for the noise. Used in combination with the value of *temperature* to calculate the RMS voltage of the noise.

n\_freqs [int, optional] The number of frequencies within the frequency band to use to calculate the noise signal. By default determines the number of frequencies based on the FFT bin size of *times*.

### Raises

**ValueError** If the RMS voltage cannot be calculated (i.e. *rms\_voltage* or both *temperature* and *resistance* are None).

**Warning:** Since this class inherits from FunctionSignal, its with\_times method will properly extrapolate noise outside of the provided times. Be warned however that outside of the original signal times the noise signal will be highly periodic. Since the default number of frequencies used is based on the FFT bin size of *times*, the period of the noise signal is actually the length of *times*. As a result if you are planning on extrapolating the noise signal, increasing the number of frequencies used is strongly recommended.

#### See also:

FunctionSignal Class for signals generated by a function.

### **Notes**

Calculation of the noise signal is based on the Rayleigh noise model used by ANITA [1]. Modifications have been made to the default to make the frequency-domain amplitudes Rayleigh-distributed, under the suggestion that this makes for more realistic noise traces.

### References

[1]

#### **Attributes**

times, values [ndarray] 1D arrays of times (s) and corresponding values which define the signal.

value\_type [Signal.Type.voltage] Type of signal, representing the units of the values.

**Type** [Enum] Enum containing possible types (units) for signal values.

**function** [function] Function to evaluate the signal values at given time(s).

f min [float] Minimum frequency of the noise frequency band.

**f\_max** [float] Maximum frequency of the noise frequency band.

**freqs, amps, phases** [ndarray] The frequencies used to define the noise signal and their corresponding amplitudes and phases.

rms [float] The RMS value of the noise signal.

dt The time spacing of the times array, or None if invalid.

**frequencies** The FFT frequencies of the signal.

**spectrum** The FFT complex spectrum values of the signal.

**envelope** The envelope of the signal by Hilbert transform.

#### **Methods**

Туре	Enum containing possible types (units) for signal
	values.
filter_frequencies(freq_response[,	Apply the given frequency response function to the
force_real])	signal, in-place.
resample(n)	Resamples the signal into n points in the same time
	range, in-place.
with_times(new_times)	Returns a representation of this signal over a differ-
	ent times array.

# 6.1.6 pyrex.Antenna

class pyrex.Antenna(position, z\_axis=(0, 0, 1), x\_axis=(1, 0, 0), antenna\_factor=1, efficiency=1, noisy=True, unique\_noise\_waveforms=10, freq\_range=None, temperature=None, resistance=None, noise\_rms=None)

Base class for antennas.

Stores the attributes of an antenna as well as handling receiving, processing, and storing signals and adding noise.

#### **Parameters**

**position** [array\_like] Vector position of the antenna.

**z\_axis** [array\_like, optional] Vector direction of the z-axis of the antenna.

**x\_axis** [array\_like, optional] Vector direction of the x-axis of the antenna.

**antenna\_factor** [float, optional] Antenna factor used for converting electric field values to voltages.

**efficiency** [float, optional] Antenna efficiency applied to incoming signal values.

**noisy** [boolean, optional] Whether or not the antenna should add noise to incoming signals.

**unique\_noise\_waveforms** [int, optional] The number of expected noise waveforms needed for each received signal to have its own noise.

**freq\_range** [array\_like, optional] The frequency band in which the antenna operates (used for noise production).

**temperature** [float, optional] The noise temperature (K) of the antenna. Used in combination with *resistance* to calculate the RMS voltage of the antenna noise.

**resistance** [float, optional] The noise resistance (ohm) of the antenna. Used in combination with *temperature* to calculate the RMS voltage of the antenna noise.

**noise\_rms** [float, optional] The RMS voltage (V) of the antenna noise. If specified, this value will be used instead of the RMS voltage calculated from the values of *temperature* and *resistance*.

### Attributes

**position** [array\_like] Vector position of the antenna.

**z\_axis** [ndarray] Vector direction of the z-axis of the antenna.

**x\_axis** [ndarray] Vector direction of the x-axis of the antenna.

antenna\_factor [float] Antenna factor used for converting electric field values to voltages.

**efficiency** [float] Antenna efficiency applied to incoming signal values.

**noisy** [boolean] Whether or not the antenna should add noise to incoming signals.

unique\_noises [int] The number of expected noise waveforms needed for each received signal to have its own noise.

**freq\_range** [array\_like] The frequency band in which the antenna operates (used for noise production).

**temperature** [float or None] The noise temperature (K) of the antenna. Used in combination with *resistance* to calculate the RMS voltage of the antenna noise.

**resistance** [float or None] The noise resistance (ohm) of the antenna. Used in combination with *temperature* to calculate the RMS voltage of the antenna noise.

**noise\_rms** [float or None] The RMS voltage (v) of the antenna noise. If not None, this value will be used instead of the RMS voltage calculated from the values of *temperature* and *resistance*.

signals [list of Signal] The signals which have been received by the antenna.

**is\_hit** Boolean of whether the antenna has been triggered.

waveforms Signal + noise (if noisy) for each triggered antenna hit.

all\_waveforms Signal + noise (if noisy) for all antenna hits.

### **Methods**

Reset the antenna to an empty state.
Calculate the (complex) directional gain of the an-
tenna.
Signal + noise (if noisy) for the given times.
Check if the antenna is triggered in a time range.
Creates a noise signal over the given times.
Calculate the (complex) polarization gain of the an-
tenna.
Process and store an incoming signal.
Calculate the (complex) frequency response of the
antenna.
Sets the orientation of the antenna.
Check if the antenna triggers on a given signal.

### 6.1.7 pyrex.DipoleAntenna

class pyrex.DipoleAntenna (name, position, center\_frequency, bandwidth, resistance, orientation=(0,0,1), trigger\_threshold=0, effective\_height=None, noisy=True, unique\_noise\_waveforms=10)

Class for half-wave dipole antennas.

Stores the attributes of an antenna as well as handling receiving, processing, and storing signals and adding noise. Uses a first-order butterworth filter for the frequency response. Includes a simple threshold trigger.

#### **Parameters**

name [str] Name of the antenna.

**position** [array\_like] Vector position of the antenna.

center\_frequency [float] Tuned frequency (Hz) of the dipole.

**bandwidth** [float] Bandwidth (Hz) of the antenna.

**resistance** [float] The noise resistance (ohm) of the antenna. Used to calculate the RMS voltage of the antenna noise.

**orientation** [array\_like, optional] Vector direction of the z-axis of the antenna.

trigger\_threshold [float, optional] Voltage threshold (V) above which signals will trigger.

**effective\_height** [float, optional] Effective length (m) of the antenna. By default calculated by the tuned *center\_frequency* of the dipole.

**noisy** [boolean, optional] Whether or not the antenna should add noise to incoming signals.

**unique\_noise\_waveforms** [int, optional] The number of expected noise waveforms needed for each received signal to have its own noise.

### See also:

Antenna Base class for antennas.

#### **Attributes**

name [str] Name of the antenna.

**position** [array\_like] Vector position of the antenna.

**z\_axis** [ndarray] Vector direction of the z-axis of the antenna.

**x\_axis** [ndarray] Vector direction of the x-axis of the antenna.

**antenna\_factor** [float] Antenna factor used for converting electric field values to voltages.

efficiency [float] Antenna efficiency applied to incoming signal values.

threshold [float, optional] Voltage threshold (V) above which signals will trigger.

**effective\_height** [float, optional] Effective length of the antenna. By default calculated by the tuned *center\_frequency* of the dipole.

**filter\_coeffs** [tuple of ndarray] Coefficients of the transfer function of the butterworth bandpass filter to be used for frequency response.

**noisy** [boolean] Whether or not the antenna should add noise to incoming signals.

**unique\_noises** [int] The number of expected noise waveforms needed for each received signal to have its own noise.

**freq\_range** [array\_like] The frequency band in which the antenna operates (used for noise production).

**temperature** [float or None] The noise temperature (K) of the antenna. Used in combination with *resistance* to calculate the RMS voltage of the antenna noise.

**resistance** [float or None] The noise resistance (ohm) of the antenna. Used in combination with *temperature* to calculate the RMS voltage of the antenna noise.

**noise\_rms** [float or None] The RMS voltage (V) of the antenna noise. If not None, this value will be used instead of the RMS voltage calculated from the values of *temperature* and resistance

signals [list of Signal] The signals which have been received by the antenna.

**is\_hit** Boolean of whether the antenna has been triggered.

waveforms Signal + noise (if noisy) for each triggered antenna hit.

all\_waveforms Signal + noise (if noisy) for all antenna hits.

### **Methods**

clear([reset_noise])	Reset the antenna to an empty state.	
directional_gain(theta, phi)	Calculate the (complex) directional gain of the an-	
	tenna.	
full_waveform(times)	Signal + noise (if noisy) for the given times.	
is_hit_during(times)	Check if the antenna is triggered in a time range.	
make_noise(times)	Creates a noise signal over the given times.	
polarization_gain(polarization)	Calculate the (complex) polarization gain of the an-	
	tenna.	
receive(signal[, direction, polarization,])	Process and store an incoming signal.	
response(frequencies)	Calculate the (complex) frequency response of the	
	antenna.	
set_orientation([z_axis, x_axis])	Sets the orientation of the antenna.	
trigger(signal)	Check if the antenna triggers on a given signal.	

# 6.1.8 pyrex.AntennaSystem

### class pyrex.AntennaSystem(antenna)

Base class for antenna system with front-end processing.

Behaves similarly to an antenna by passing some functionality downward to an antenna class, but additionally applies some front-end processing (e.g. an electronics chain) to the signals received.

### **Parameters**

antenna [Antenna] Antenna class or subclass to be extended with a front end. Can also accept an Antenna object directly.

#### See also:

pyrex. Antenna Base class for antennas.

### Attributes

antenna [Antenna] Antenna object extended by the front end.

**lead\_in\_time** [float] Lead-in time (s) required for the front end to equilibrate. Automatically added in before calculation of signals and waveforms.

**is** hit Boolean of whether the antenna system has been triggered.

**signals** The signals received by the antenna with front-end processing.

waveforms The antenna system signal + noise for each triggered hit.

**all\_waveforms** The antenna system signal + noise for all hits.

### **Methods**

clear([reset_noise])	Reset the antenna system to an empty state.
front_end(signal)	Apply front-end processes to a signal and return the
	output.
full_waveform(times)	Signal + noise for the antenna system for the given
	times.
is_hit_during(times)	Check if the antenna system is triggered in a time
	range.
make_noise(times)	Creates a noise signal over the given times.
receive(signal[, direction, polarization,])	Process and store an incoming signal.
set_orientation([z_axis, x_axis])	Sets the orientation of the antenna system.
setup_antenna(*args, **kwargs)	Setup the antenna by passing along its init argu-
	ments.
trigger(signal)	Check if the antenna system triggers on a given sig-
	nal.

# 6.1.9 pyrex.Detector

class pyrex.Detector(\*args, \*\*kwargs)

Base class for detectors for easily building up sets of antennas.

Designed for automatically generating antenna positions based on geometry parameters, then building all the antennas with some properties. Any parameters to the <u>\_\_init\_\_</u> method are automatically passed on to the set\_positions method. Once the antennas have been built, the object can be directly iterated over to iterate over the antennas (as if the object were just a list of the antennas).

#### Raises

**ValueError** If test\_antenna\_positions is True and an antenna is found to be above the ice surface.

### See also:

pyrex. Antenna Base class for antennas.

AntennaSystem Base class for antenna system with front-end processing.

#### **Notes**

When this class is subclassed, the \_\_init\_\_ method will mirror the signature of the set\_positions method so that parameters can be easily discovered.

The class is designed to be flexible in what defines a "detector". This should allow for easier modularization by defining detectors whose subsets are detectors themselves, and so on. For example, a string of antennas could be set up as a subclass of <code>Detector</code> which sets up some antennas in a vertical line. Then a station could be set up as a subclass of <code>Detector</code> which sets up multiple instances of the string class at different positions. Then a final overarching detector class can subclass <code>Detector</code> and set up multiple instances of the station class at different positions. In this example the <code>subsets</code> of the overarching detector class would be the station objects, the <code>subsets</code> of the station objects would be the string objects, and the <code>subsets</code> of the string objects would finally be the antenna objects. But the way the iteration of the <code>Detector</code> class is built, iterating over that overarching detector class would iterate directly over each antenna in each string in each station as a simple 1D list.

### **Attributes**

**antenna\_positions** [list] List (potentially with sub-lists) of the positions of the antennas generated by the set\_positions method.

subsets [list] List of the antenna or detector objects which make up the detector.

**test\_antenna\_positions** [boolean] Class attribute for whether or not an error should be raised if antenna positions are found above the surface of the ice (where simulation behavior is ill-defined). Defaults to True.

### Methods

build_antennas(*args, **kwargs)	Creates antenna objects at the set antenna positions.
clear([reset_noise])	Reset the detector to an empty state.
set_positions(*args, **kwargs)	Sets the positions of antennas in the detector.
triggered(*args[, require_mc_truth])	Check if the detector is triggered based on its current
	state.

# 6.1.10 pyrex.lceModel

### pyrex.IceModel

alias of pyrex.ice\_model.AntarcticIce

# 6.1.11 pyrex.prem density

### pyrex.prem\_density(r)

Calculates the Earth's density at a given radius.

Density from the Preliminary reference Earth Model (PREM). Supports passing an array of radii or a single radius.

#### **Parameters**

r [array\_like] Radius (m) at which to calculate density.

### Returns

array\_like Density (g/cm<sup>3</sup>) of the Earth at the given radii.

### **Notes**

The density calculation is based on the Preliminary reference Earth Model [1].

### References

[1]

# 6.1.12 pyrex.slant\_depth

pyrex.slant\_depth (angle, depth, step=500)

Calculates the material thickness of a chord cutting through Earth.

Integrates the Earth's density along the chord. Uses the PREM model for density.

#### **Parameters**

angle [float] Nadir angle (radians) of the chord's direction.

**depth** [float] (Positive-valued) depth (m) of the chord endpoint.

step [float, optional] Step size (m) for the integration.

#### Returns

**float** Material thickness (g/cm<sup>2</sup>) along the chord starting from *depth* and passing through the Earth at *angle*.

### See also:

**prem\_density** Calculates the Earth's density at a given radius.

# 6.1.13 pyrex.NeutrinoInteraction

pyrex.NeutrinoInteraction

alias of pyrex.particle.CTWInteraction

## 6.1.14 pyrex.Particle

### **Parameters**

particle\_id Identification value of the particle type. Values should be from the Particle.
Type enum, but integer or string values may work if carefully chosen. Particle. Type.
undefined by default.

**vertex** [array\_like] Vector position (m) of the particle.

**direction** [array\_like] Vector direction of the particle's velocity.

energy [float] Energy (GeV) of the particle.

**interaction\_model** [optional] Class to use to describe interactions of the particle. Should inherit from (or behave like) the base Interaction class.

interaction\_type [optional] Value of the interaction type. Values should be from the
 Interaction.Type enum, but integer or string values may work if carefully chosen.
 By default, the interaction\_model will choose an interaction type.

weight [float, optional] Total Monte Carlo weight of the particle. The calculation of this weight depends on the particle generation method, but this value should be the total weight representing the probability of this particle's event occurring.

### See also:

**Interaction** Base class for describing neutrino interaction attributes.

### **Attributes**

**id** [Particle.Type] Identification value of the particle type.

**vertex** [array\_like] Vector position (m) of the particle.

direction [array\_like] (Unit) vector direction of the particle's velocity.

energy [float] Energy (GeV) of the particle.

**interaction** [Interaction] Instance of the *interaction\_model* class to be used for calculations related to interactions of the particle.

weight [float] Total Monte Carlo weight of the particle

**survival\_weight** [float] Monte Carlo weight of the particle surviving to its vertex. Represents the probability that the particle does not interact along its path through the Earth.

**interaction\_weight** [float] Monte Carlo weight of the particle interacting at its vertex. Represents the probability that the particle interacts specifically at its given vertex.

#### **Methods**

Туре	Enum containing possible particle types.

# 6.1.15 pyrex.Event

class pyrex.Event(roots)

Class for storing a tree of Particle objects representing an event.

The event may be comprised of any number of root Particle objects specified at initialization. Each Particle in the tree may have any number of child Particle objects. Iterating the tree will return all Particle objects, but in no guaranteed order.

#### **Parameters**

roots [Particle or list of Particle] Root Particle objects for the event tree.

### See also:

Particle Class for storing particle attributes.

### Attributes

roots [Particle or list of Particle] Root Particle objects for the event tree.

### **Methods**

add_children(parent, children)	Add the given <i>children</i> to the <i>parent Particle</i> ob-
_ 4 , , ,	ject.
get_children(parent)	Get the children of the given parent Particle ob-
	ject.
get_from_level(level)	Get all Particle objects some level deep into the
	event tree.
get_parent(child)	Get the parent of the given <i>child</i> Particle object.

# 6.1.16 pyrex.CylindricalGenerator

class pyrex.CylindricalGenerator(dr, dz, energy, flavor\_ratio=(1, 1, 1), interaction\_model=<class 'pyrex.particle.CTWInteraction'>)
 Class to generate neutrino vertices in a cylindrical ice volume. Generates neutrinos in a cylinder with given radius and height.

#### **Parameters**

- dr [float] Radius of the ice volume. Neutrinos generated within (0, dr).
- **dz** [float] Height of the ice volume in the z-direction. Neutrinos generated within (-dz, 0).
- energy [float or function] Energy (GeV) of the neutrinos. If float, all neutrinos have the same constant energy. If function, neutrinos are generated with the energy returned by successive function calls.
- **flavor\_ratio** [array\_like, optional] Flavor ratio of neutrinos to be generated. Of the form [electron, muon, tau] neutrino fractions.
- **interaction\_model** [optional] Class to use to describe interactions of the generated particles. Should inherit from (or behave like) the base Interaction class.

### See also:

pyrex.particle.Interaction Base class for describing neutrino interaction attributes.

#### **Attributes**

- **count** [int] Number of neutrinos produced by the generator, including those not returned due to Earth shadowing or other effects.
- **dr** [float] Radius of the ice volume. Neutrinos generated within (0, dr).
- **dz** [float] Height of the ice volume in the z-direction. Neutrinos generated within (-dz, 0).
- **get\_energy** [function] Function returning energy (GeV) of the neutrinos by successive function calls.
- **ratio** [ndarary] (Normalized) flavor ratio of neutrinos to be generated. Of the form [electron, muon, tau] neutrino fractions.

**interaction\_model** [Interaction] Class to use to describe interactions of the generated particles.

### **Methods**

create_event()	Generate a neutrino event in the ice volume.
<pre>get_direction()</pre>	Get the direction of the next particle to be generated.
get_exit_points(particle)	Get the intersections of the particle path with the ice
	volume edges.
<pre>get_particle_type()</pre>	Get the particle type of the next particle to be gener-
	ated.
<pre>get_vertex()</pre>	Get the vertex of the next particle to be generated.
get_weights(particle)	Get the weighting factors to be applied to the parti-
	cle.

### 6.1.17 pyrex.RectangularGenerator

class pyrex.RectangularGenerator (dx, dy, dz, energy, flavor\_ratio=(1, 1, 1), interaction\_model=<class 'pyrex.particle.CTWInteraction'>)

Class to generate neutrino vertices in a rectangular ice volume.

Generates neutrinos in a box with given width, length, and height.

#### **Parameters**

- **dx** [float] Width of the ice volume in the x-direction. Neutrinos generated within (-dx / 2, dx / 2).
- **dy** [float] Length of the ice volume in the y-direction. Neutrinos generated within (-dy / 2, dy / 2).
- **dz** [float] Height of the ice volume in the z-direction. Neutrinos generated within (-dz, 0).
- **energy** [float or function] Energy (GeV) of the neutrinos. If float, all neutrinos have the same constant energy. If function, neutrinos are generated with the energy returned by successive function calls.
- **flavor\_ratio** [array\_like, optional] Flavor ratio of neutrinos to be generated. Of the form [electron, muon, tau] neutrino fractions.
- **interaction\_model** [optional] Class to use to describe interactions of the generated particles. Should inherit from (or behave like) the base Interaction class.

### See also:

pyrex.particle.Interaction Base class for describing neutrino interaction attributes.

### **Attributes**

- **count** [int] Number of neutrinos produced by the generator, including those not returned due to Earth shadowing or other effects.
- **dx** [float] Width of the ice volume in the x-direction. Neutrinos generated within (-dx / 2, dx / 2).
- **dy** [float] Length of the ice volume in the y-direction. Neutrinos generated within (-dy / 2, dy / 2).
- **dz** [float] Height of the ice volume in the z-direction. Neutrinos generated within (-dz, 0).
- **get\_energy** [function] Function returning energy (GeV) of the neutrinos by successive function calls.
- **ratio** [ndarary] (Normalized) flavor ratio of neutrinos to be generated. Of the form [electron, muon, tau] neutrino fractions.
- **interaction\_model** [Interaction] Class to use to describe interactions of the generated particles.

### **Methods**

create_event()	Generate a neutrino event in the ice volume.
<pre>get_direction()</pre>	Get the direction of the next particle to be generated.
<pre>get_exit_points(particle)</pre>	Get the intersections of the particle path with the ice
	volume edges.
<pre>get_particle_type()</pre>	Get the particle type of the next particle to be gener-
	ated.
<pre>get_vertex()</pre>	Get the vertex of the next particle to be generated.
get_weights(particle)	Get the weighting factors to be applied to the parti-
	cle.

# 6.1.18 pyrex.CylindricalShadowGenerator

 $\textbf{class} \ \, \texttt{pyrex.CylindricalShadowGenerator} (\textit{dr}, \textit{dz}, \textit{energy}, \textit{flavor\_ratio} = (1, 1, 1), \textit{interaction\_model} = < \textit{class} \\ \textit{'pyrex.particle.CTWInteraction'} > )$ 

Class to generate neutrino vertices in a cylindrical ice volume.

Generates neutrinos in a cylinder with given radius and height. Accounts for Earth shadowing by comparing the neutrino interaction length to the material thickness of the Earth along the neutrino path, and rejecting particles which would interact before reaching the vertex.

### **Parameters**

- dr [float] Radius of the ice volume. Neutrinos generated within (0, dr).
- **dz** [float] Height of the ice volume in the z-direction. Neutrinos generated within (-dz, 0).
- energy [float or function] Energy (GeV) of the neutrinos. If float, all neutrinos have the same constant energy. If function, neutrinos are generated with the energy returned by successive function calls.
- **flavor\_ratio** [array\_like, optional] Flavor ratio of neutrinos to be generated. Of the form [electron, muon, tau] neutrino fractions.
- interaction\_model [optional] Class to use to describe interactions of the generated particles.
  Should inherit from (or behave like) the base Interaction class.

### See also:

pyrex.particle.Interaction Base class for describing neutrino interaction attributes.

#### **Attributes**

- **count** [int] Number of neutrinos produced by the generator, including those not returned due to Earth shadowing or other effects.
- **dr** [float] Radius of the ice volume. Neutrinos generated within (0, dr).
- **dz** [float] Height of the ice volume in the z-direction. Neutrinos generated within (-dz, 0).
- **get\_energy** [function] Function returning energy (GeV) of the neutrinos by successive function calls.
- **ratio** [ndarary] (Normalized) flavor ratio of neutrinos to be generated. Of the form [electron, muon, tau] neutrino fractions.

interaction\_model [Interaction] Class to use to describe interactions of the generated particles.

### **Methods**

create_event()	Generate a neutrino event in the ice volume.
<pre>get_direction()</pre>	Get the direction of the next particle to be generated.
<pre>get_exit_points(particle)</pre>	Get the intersections of the particle path with the ice
	volume edges.
<pre>get_particle_type()</pre>	Get the particle type of the next particle to be gener-
	ated.
get_vertex()	Get the vertex of the next particle to be generated.

Continued on next page

### Table 14 – continued from previous page

get_weights(particle)	Get the weighting factors to be applied to the parti-
	cle.

# 6.1.19 pyrex.RectangularShadowGenerator

class pyrex.RectangularShadowGenerator (dx, dy, dz, energy,  $flavor\_ratio=(1, 1, 1)$ ,  $interaction\_model=<class 'pyrex.particle.CTWInteraction'>)$ 

Class to generate neutrino vertices in a rectangular ice volume.

Generates neutrinos in a box with given width, length, and height. Accounts for Earth shadowing by comparing the neutrino interaction length to the material thickness of the Earth along the neutrino path, and rejecting particles which would interact before reaching the vertex. Note the subtle difference in x and y ranges compared to the z range.

#### **Parameters**

- **dx** [float] Width of the ice volume in the x-direction. Neutrinos generated within (-dx / 2, dx / 2).
- **dy** [float] Length of the ice volume in the y-direction. Neutrinos generated within (-dy / 2, dy / 2).
- **dz** [float] Height of the ice volume in the z-direction. Neutrinos generated within (-dz, 0).
- **energy** [float or function] Energy (GeV) of the neutrinos. If float, all neutrinos have the same constant energy. If function, neutrinos are generated with the energy returned by successive function calls.
- **flavor\_ratio** [array\_like, optional] Flavor ratio of neutrinos to be generated. Of the form [electron, muon, tau] neutrino fractions.
- **interaction\_model** [optional] Class to use to describe interactions of the generated particles. Should inherit from (or behave like) the base Interaction class.

#### See also:

pyrex.particle.Interaction Base class for describing neutrino interaction attributes.

### Attributes

- **count** [int] Number of neutrinos produced by the generator, including those not returned due to Earth shadowing or other effects.
- **dx** [float] Width of the ice volume in the x-direction. Neutrinos generated within (-dx / 2, dx / 2).
- **dy** [float] Length of the ice volume in the y-direction. Neutrinos generated within (-dy / 2, dy / 2).
- **dz** [float] Height of the ice volume in the z-direction. Neutrinos generated within (-dz, 0).
- **get\_energy** [function] Function returning energy (GeV) of the neutrinos by successive function calls.
- **ratio** [ndarary] (Normalized) flavor ratio of neutrinos to be generated. Of the form [electron, muon, tau] neutrino fractions.

interaction\_model [Interaction] Class to use to describe interactions of the generated particles.

### **Methods**

create_event()	Generate a neutrino event in the ice volume.
<pre>get_direction()</pre>	Get the direction of the next particle to be generated.
<pre>get_exit_points(particle)</pre>	Get the intersections of the particle path with the ice
	volume edges.
<pre>get_particle_type()</pre>	Get the particle type of the next particle to be gener-
	ated.
get_vertex()	Get the vertex of the next particle to be generated.
get_weights(particle)	Get the weighting factors to be applied to the parti-
	cle.

# 6.1.20 pyrex.ListGenerator

class pyrex.ListGenerator(events, loop=True)

Class to generate neutrino events from a list.

Generates events by simply pulling them from a list of *Event* objects. By default returns to the start of the list once the end is reached, but can optionally fail after reaching the list's end.

### **Parameters**

**events** [Event, or list of Event] List of *Event* objects to draw from. If only a single *Event* object is given, creates a list of that event alone.

**loop** [boolean, optional] Whether or not to return to the start of the list after throwing the last *Event*. If False, raises an error if trying to throw after the last *Event*.

### See also:

pyrex. Event Class for storing a tree of Particle objects representing an event.

pyrex.Particle Class for storing particle attributes.

### **Attributes**

**count** [int] Number of neutrinos produced by the generator.

**events** [list of Event] List to draw *Event* objects from, sequentially.

**loop** [boolean] Whether or not to loop through the list more than once.

#### **Methods**

create_event()	Generate a neutrino event.

## 6.1.21 pyrex.FileGenerator

Class to generate neutrino events from simulation file(s).

Generates neutrinos by pulling their attributes from a (list of) simulation output file(s). Designed to make reproducing simulations easier.

### **Parameters**

**files** [str or list of str] List of file names containing neutrino event information. If only a single file name is provided, creates a list with that file alone.

**slice\_range** [int, optional] Number of events to load into memory at a time from the files. Increasing this value should result in an improvement in speed, while decreasing this value should result in an improvement in memory consumption.

**interaction model** [optional] Class used to describe the interactions of the stored particles.

**Warning:** This generator only supports *Event* objects containing a single level of *Particle* objects. Any dependencies among *Particle* objects will be ignored and they will all appear in the root level.

### See also:

```
pyrex.particle.Interaction Base class for describing neutrino interaction attributes.
pyrex.Event Class for storing a tree of Particle objects representing an event.
pyrex.Particle Class for storing particle attributes.
```

#### Attributes

**count** [int] Number of neutrinos produced by the generator.

files [list of str] List of file names containing neutrino information.

### Methods

create\_event()

Generate a neutrino.

# 6.1.22 pyrex.RayTracer

```
pyrex.RayTracer
alias of pyrex.ray_tracing.SpecializedRayTracer
```

# 6.1.23 pyrex.RayTracePath

```
pyrex.RayTracePath
    alias of pyrex.ray_tracing.SpecializedRayTracePath
```

# 6.1.24 pyrex.EventKernel

High-level kernel for controlling event simulation.

The kernel is responsible for handling the classes and objects which control the major simulation steps: particle creation, signal production, signal propagation, and antenna response. The modular kernel structure allows for easy switching of the classes or objects which handle any of the simulation steps.

### **Parameters**

**generator** A particle generator to create neutrino events.

antennas An iterable object consisting of antenna objects which can receive and store signals.

**ice\_model** [optional] An ice model describing the ice surrounding the *antennas*.

**ray\_tracer** [optional] A ray tracer capable of propagating signals from the neutrino vertex to the antenna positions.

**signal\_model** [optional] A signal class which generates signals based on the particle.

**signal\_times** [array\_like, optional] The array of times over which the neutrino signal should be generated.

**event\_writer** [File, optional] A file object to be used for writing data output.

**triggers** [function or dict, optional] A function or dictionary with function values representing trigger conditions of the detector. If a dictionary, must have a "global" key with its value representing the global detector trigger.

#### See also:

pyrex. Event Class for storing a tree of Particle objects representing an event.

pyrex.Particle Class for storing particle attributes.

pyrex. IceModel Class describing the ice at the south pole.

pyrex. RayTracer Class for calculating the ray-trace solutions between points.

pyrex. AskaryanSignal Class for generating Askaryan signals according to ARVZ parameterization.

pyrex.File Class for reading or writing data files.

# Notes

The kernel is designed to be modular so individual parts of the simulation chain can be exchanged. In order to interchange the pieces, their classes require the following at a minimum:

The particle generator generator must have a create\_event method which takes no arguments and returns a <code>Event</code> object consisting of <code>Particle</code> objects with <code>vertex</code>, <code>direction</code>, <code>energy</code>, and <code>weight</code> attributes.

The antenna iterable *antennas* must yield each antenna object once when iterating directly over *antennas*. Each antenna object must have a position attribute and a receive method which takes a signal object as its first argument, and ndarray objects as direction and polarization keyword arguments.

The ice\_model must have an index method returning the index of refraction given a (negative-valued) depth, and it must support anything required of it by the ray\_tracer.

The ray\_tracer must be initialized with the particle vertex and an antenna position as its first two arguments, and the <code>ice\_model</code> of the kernel as the <code>ice\_model</code> keyword argument. The ray tracer must also have <code>exists</code> and <code>solutions</code> attributes, the first of which denotes whether any paths exist between the given points and the second of which is an iterable revelaing each path between the points. These paths must have <code>emitted\_direction</code>, <code>received\_direction</code>, and <code>path\_length</code> attributes, as well as a <code>propagate</code> method which takes a signal object and applies the propagation effects of the path in-place to that object.

The signal\_model must be initialized with the signal\_times array, a Particle object from the Event, the viewing\_angle and viewing\_distance according to the ray\_tracer, and the ice\_model. The object created should be a Signal object with times and values attributes representing the time-domain Askaryan signal produced by the Particle.

### **Attributes**

gen The particle generator responsible for particle creation.

**antennas** The iterable of antennas responsible for handling applying their response and storing the resulting signals.

ice The ice model describing the ice containing the antennas.

ray\_tracer The ray tracer responsible for signal propagation through the ice.

signal\_model The signal class to use to generate signals based on the particle.

**signal\_times** The array of times over which the neutrino signal should be generated.

writer The file object to be used for writing data output.

**triggers** The trigger condition(s) of the detector.

# **Methods**

event()	Create a neutrino event and run it through the simu-
	lation chain.

# 6.1.25 pyrex.File

### class pyrex.File

Class for reading or writing data files.

Works as a context manager and allows for reading or writing simulation/real data or analysis-level data to the given file. Chooses the appropriate class for handling the given file type.

### **Parameters**

**filename** [str] File name to open in the given write mode.

**mode** [str, optional] Mode with which to open the file.

\*\*kwargs Keyword arguments passed on to the appropriate file handler.

### See also:

HDF5Reader Class for reading data from an hdf5 file.

HDF5Writer Class for writing data to an hdf5 file.

### **Attributes**

**readers** [dict] Dictionary with file extensions as keys and values with the corresponding classes used to handle reading of those file types.

writers [dict] Dictionary with file extensions as keys and values with the corresponding classes used to handle writing of those file types.

# 6.2 Individual Module APIs

# 6.2.1 Helper Functions (pyrex.internal\_functions)

Helper functions and classes for use in PyREx modules.

This module is intended as a container for functions, typically used in more than one PyREx module, which are not physics-motivated and are instead used mainly to clean up code. Functions and classes in this module may also be computer-science-motivated structures that python doesn't include naturally.

normalize(vector)	Normalize the given vector.
<pre>flatten(iterator[, dont_flatten])</pre>	Flattens an iterator to iterate over all elements individu-
	ally.
mirror_func(match_func, run_func[, self])	Mirror the attributes of one function onto another.
lazy_property(fn)	Decorator that makes a property lazily evaluated.
LazyMutableClass([static_attributes])	Class with lazy properties which may depend on other
	class attributes.

# pyrex.internal\_functions.normalize

```
pyrex.internal_functions.normalize(vector)
    Normalize the given vector.
```

### **Parameters**

vector [array like]

# Returns

ndarray Normalized form of vector.

# **Examples**

```
>>> normalize([5,0,0])
array([1., 0., 0.])
```

```
>>> v = np.array([1,0,1])
>>> normalize(v)
array([0.70710678, 0. , 0.70710678])
```

# pyrex.internal\_functions.flatten

```
pyrex.internal_functions.flatten(iterator, dont_flatten=())
```

Flattens an iterator to iterate over all elements individually.

Flattens all iterable elements in the given iterator recursively and yields the resulting flat iterator. Can optionally not flatten certain classes. Will not flatten strings or bytes to avoid recursion errors.

#### **Parameters**

**iterator** [iterable object] Iterable object to flatten.

dont\_flatten [tuple\_like, optional] Tuple (or similar) of classes which should not be flattened.

**Yields** 

**element** [any] Each element of *iterator* with sub-iterators expanded out.

### **Notes**

Since str and bytes objects are always considered iterable despite their length, these objects will not be flattened and will remain intact.

If a class is asked not to be flattened, any sub-iterators contained in an iterator of that class will not be flattened either (see examples).

# **Examples**

```
>>> list(flatten([1, 2, (3, 'four', [5, 6], 7), [8, 9]]))
[1, 2, 3, 'four', 5, 6, 7, 8, 9]
```

```
>>> list(flatten([1, 2, (3, 'four', [5, 6], 7), [8, 9]], dont_flatten=(tuple,)))
[1, 2, (3, 'four', [5, 6], 7), 8, 9]
```

```
>>> list(flatten([1, 2, [3, 'four', (5, 6), 7], [8, 9]], dont_flatten=(tuple,)))
[1, 2, 3, 'four', (5, 6), 7, 8, 9]
```

# pyrex.internal\_functions.mirror\_func

```
pyrex.internal_functions.mirror_func(match_func, run_func, self=None)
```

Mirror the attributes of one function onto another.

Creates a function which operates like one function, but has all the attributes of another. Works for functions or class methods.

#### **Parameters**

match\_func [function] Function with the attributes to be mirrored.

**run func** [function] Function with the desired behavior.

**self** [object or None, optional] If None, *run\_func* called as a regular function, otherwise *run\_func* is called as a class method (with *self* as its first argument).

# Returns

**function** Function with the behavior of run func, but the attributes of match func.

# **Examples**

```
>>> from inspect import signature
>>> def descriptive_add(a, b):
... """Function with a descriptive docstring."""
... pass
>>> def add_implementation(x, y):
... # Actually adds, but no docs or anything
... return x+y
>>> my_add = mirror_func(descriptive_add, add_implementation)
>>> my_add(2, 3)
```

(continues on next page)

(continued from previous page)

```
>>> my_add.__doc__
'Function with a descriptive docstring.'
>>> signature(my_add)
<Signature (a, b)>
```

```
>>> from inspect import signature
>>> class A:
        def __init__(self, value):
            self.value = value
        def mult(self, factor, power=1):
            """Multiplies value by factor and raises to power."""
            return (self.value*factor) **power
. . .
>>> class B(A):
        def __init__(self, value):
           self.value = value
            # Make the mult method look the same as for A, but with
            # different behavior
            self.mult = mirror_func(A.mult, B.different_mult, self=self)
. . .
        def different_mult(self, *args, **kwargs):
            """Different implementation of mult."""
. . .
            return (self.value*int(args[0]))**kwargs['power']
. . .
>>> b = B(5)
>>> b.mult(2.5, power=2)
>>> b.mult.__doc_
'Multiplies by factor and raises to power.'
>>> signature(b.mult)
<Signature (self, factor, power=1)>
```

### pyrex.internal\_functions.lazy\_property

```
pyrex.internal_functions.lazy_property(fn)
```

Decorator that makes a property lazily evaluated.

Acts like the standard python property decorator, but the first time the decorated property is accessed an attribute with the property's name prefixed by '\_lazy\_' will be created and the value of the property will be stored. Upon further access of the property, the stored value will be returned instead of recalculating it.

### **Parameters**

**fn** [function] Function returning class property which is to be decorated.

#### Returns

function Lazy-evaluation property function.

### See also:

LazyMutableClass Class for lazy properties dependent on attributes.

### **Notes**

Using the lazy\_property decorator instead of the simple python property decorator increases the time for property access (after the initial calculation) from ~0.5 microseconds to ~5 microseconds, so lazy\_property is only recommended for use on properties with calculation times >5 microseconds which are likely to be accessed more than once.

# **Examples**

```
>>> from time import sleep
>>> class A:
      def __init__(self, value):
           self.value = value
      @lazy_property
. . .
      def twice(self):
. . .
           sleep(5)
. . .
            return self.value*2
. . .
>>> a = A(1)
>>> "_lazy_twice" in a.__dict__
False
>>> a.twice
>>> "_lazy_twice" in a.__dict__
True
>>> a.twice
2.
```

### pyrex.internal\_functions.LazyMutableClass

**class** pyrex.internal\_functions.**LazyMutableClass** (*static\_attributes=None*) Class with lazy properties which may depend on other class attributes.

This class is intended as a base class for any class which desires lazy properties which depend on other attributes and thus may need to be recalculated when the class attributes change. Any lazy properties in this class will be lazily evaluated as usual until one of the given static attributes changes, at which point all lazy properties will be cleared and will be recalculated on their next call. By default the static attributes of the class will be set to all attributes present at the time of the LazyMutableClass. \_\_\_init\_\_\_call.

### **Parameters**

**static\_attributes** [None or sequence of str] Set of attribute names on which the lazy properties depend. If None then it will contain all members of \_\_dict\_\_ at the time of the call.

#### See also:

lazy\_property Decorator for lazily-evaluated properties.

# **Examples**

```
>>> from time import sleep
>>> class A(LazyMutableClass):
      def __init__(self, value):
           self.value = value
. . .
            super().__init__()
      @lazy_property
. . .
        def twice(self):
. . .
           sleep(5)
            return self.value*2
. . .
>>> a = A(1)
>>> "_lazy_twice" in a.__dict__
False
>>> a.twice
```

(continues on next page)

(continued from previous page)

```
2
>>> "_lazy_twice" in a.__dict__
True
>>> a.twice
2
>>> "_lazy_twice" in a.__dict__
False
>>> a.twice
10
>>> "_lazy_twice" in a.__dict__
True
>>> a.twice
10
```

# 6.2.2 Signal Processing (pyrex.signals)

Module containing classes for digital signal processing.

All classes in this module hold time-domain information about some signals, and have methods for manipulating this data as it relates to digital signal processing and general physics.

Signal(times, values[, value_type])	Base class for time-domain signals.
<pre>EmptySignal(times[, value_type])</pre>	Class for signal with zero amplitude (all values $= 0$ ).
FunctionSignal(times, function[, value_type])	Class for signals generated by a function.
ZHSAskaryanSignal(times, particle, view-	Class for generating Askaryan signals according to ZHS
ing_angle)	parameterization.
ARVZAskaryanSignal(times, particle,[,])	Class for generating Askaryan signals according to
	ARVZ parameterization.
AskaryanSignal	alias of pyrex.signals.
	ARVZAskaryanSignal
GaussianNoise(times, sigma)	Class for gaussian noise signals with standard deviation
	sigma.
ThermalNoise(times, f_band[, f_amplitude,])	Class for thermal Rayleigh noise signals.

### pyrex.signals.Signal

class pyrex.signals.Signal(times, values, value\_type=None)

Base class for time-domain signals.

Stores the time-domain information for signal values. Supports adding between signals with the same times array and value type.

### **Parameters**

**times** [array like] 1D array of times (s) for which the signal is defined.

**values** [array\_like] 1D array of values of the signal corresponding to the given *times*. Will be resized to the size of *times* by zero-padding or truncating as necessary.

value\_type Type of signal, representing the units of the values. Values should be from the Signal.Type enum, but integer or string values may work if carefully chosen. Signal. Type.undefined by default.

### **Attributes**

times, values [ndarray] 1D arrays of times (s) and corresponding values which define the signal.

value\_type [Signal.Type] Type of signal, representing the units of the values.

**Type** [Enum] Enum containing possible types (units) for signal values.

dt The time spacing of the times array, or None if invalid.

**frequencies** The FFT frequencies of the signal.

spectrum The FFT complex spectrum values of the signal.

**envelope** The envelope of the signal by Hilbert transform.

#### **Methods**

Type	Enum containing possible types (units) for signal
	values.
filter_frequencies(freq_response[,	Apply the given frequency response function to the
force_real])	signal, in-place.
resample(n)	Resamples the signal into n points in the same time
	range, in-place.
with_times(new_times)	Returns a representation of this signal over a differ-
	ent times array.

# pyrex.signals.EmptySignal

**class** pyrex.signals.**EmptySignal** (*times*, *value\_type=None*) Class for signal with zero amplitude (all values = 0).

### **Parameters**

**times** [array\_like] 1D array of times (s) for which the signal is defined.

value\_type Type of signal, representing the units of the values. Must be from the Signal.
Type Enum.

### See also:

**Signal** Base class for time-domain signals.

### Attributes

times, values [ndarray] 1D arrays of times (s) and corresponding values which define the signal.

value\_type [Signal.Type] Type of signal, representing the units of the values.

**Type** [Enum] Enum containing possible types (units) for signal values.

dt The time spacing of the times array, or None if invalid.

**frequencies** The FFT frequencies of the signal.

spectrum The FFT complex spectrum values of the signal.

**envelope** The envelope of the signal by Hilbert transform.

# **Methods**

Type	Enum containing possible types (units) for signal values.
filter_frequencies(freq_response[,	Apply the given frequency response function to the
force_real])	signal, in-place.
resample(n)	Resamples the signal into n points in the same time
	range, in-place.
with_times(new_times)	Returns a representation of this signal over a differ-
	ent times array.

# pyrex.signals.FunctionSignal

**class** pyrex.signals.**FunctionSignal**(*times*, *function*, *value\_type=None*)

Class for signals generated by a function.

### **Parameters**

times [array\_like] 1D array of times (s) for which the signal is defined.

**function** [function] Function which evaluates the corresponding value(s) for a given time or array of times.

value\_type Type of signal, representing the units of the values. Must be from the Signal.
Type Enum.

### See also:

**Signal** Base class for time-domain signals.

**EmptySignal** Class for signal with zero amplitude.

### **Attributes**

times, values [ndarray] 1D arrays of times (s) and corresponding values which define the signal.

value\_type [Signal.Type] Type of signal, representing the units of the values.

**Type** [Enum] Enum containing possible types (units) for signal values.

**function** [function] Function to evaluate the signal values at given time(s).

dt The time spacing of the times array, or None if invalid.

**frequencies** The FFT frequencies of the signal.

**spectrum** The FFT complex spectrum values of the signal.

**envelope** The envelope of the signal by Hilbert transform.

### **Methods**

Туре	Enum containing possible types (units) for signal
	values.
filter_frequencies(freq_response[,	Apply the given frequency response function to the
force_real])	signal, in-place.
	O a d'a sa dia a sa d

Continued on next page

Table 23 – continued from previous page

10010	20 Commaca nom providas page
resample(n)	Resamples the signal into n points in the same time
	range, in-place.
with_times(new_times)	Returns a representation of this signal over a differ-
	ent times array.

# pyrex.signals.ZHSAskaryanSignal

Class for generating Askaryan signals according to ZHS parameterization.

Stores the time-domain information for an Askaryan electric field (V/m) produced by the electromagnetic shower initiated by a neutrino.

#### **Parameters**

times [array\_like] 1D array of times (s) for which the signal is defined.

viewing\_angle [float] Observation angle (radians) measured relative to the shower axis.

**viewing\_distance** [float, optional] Distance (m) between the shower vertex and the observation point (along the ray path).

ice\_model [optional] The ice model to be used for describing the index of refraction of the medium.

**t0** [float, optional] Pulse offset time (s), i.e. time at which the shower takes place.

#### Raises

**ValueError** If the *particle* object is not a neutrino or antineutrino with a charged-current or neutral-current interaction.

# See also:

**Signal** Base class for time-domain signals.

pyrex.Particle Class for storing particle attributes.

### **Notes**

Calculates the Askaryan signal based on the ZHS parameterization [1]. Uses equations 20 and 21 to calculate the electric field close to the Chereknov angle.

### References

[1]

#### **Attributes**

times, values [ndarray] 1D arrays of times (s) and corresponding values which define the signal.

value\_type [Signal.Type.field] Type of signal, representing the units of the values.

**Type** [Enum] Enum containing possible types (units) for signal values.

energy [float] Energy (GeV) of the electromagnetic shower producing the pulse.

#### vector potential

dt The time spacing of the times array, or None if invalid.

**frequencies** The FFT frequencies of the signal.

spectrum The FFT complex spectrum values of the signal.

**envelope** The envelope of the signal by Hilbert transform.

### **Methods**

Туре	Enum containing possible types (units) for signal values.
filter_frequencies(freq_response[,	Apply the given frequency response function to the
force_real])	signal, in-place.
resample(n)	Resamples the signal into n points in the same time
	range, in-place.
with_times(new_times)	Returns a representation of this signal over a differ-
	ent times array.

# pyrex.signals.ARVZAskaryanSignal

Class for generating Askaryan signals according to ARVZ parameterization.

Stores the time-domain information for an Askaryan electric field (V/m) produced by the electromagnetic and hadronic showers initiated by a neutrino.

# **Parameters**

times [array\_like] 1D array of times (s) for which the signal is defined.

viewing\_angle [float] Observation angle (radians) measured relative to the shower axis.

**viewing\_distance** [float, optional] Distance (m) between the shower vertex and the observation point (along the ray path).

ice\_model [optional] The ice model to be used for describing the index of refraction of the medium.

**t0** [float, optional] Pulse offset time (s), i.e. time at which the showers take place.

### Raises

**ValueError** If the *particle* object is not a neutrino or antineutrino with a charged-current or neutral-current interaction.

### See also:

**Signal** Base class for time-domain signals.

pyrex.Particle Class for storing particle attributes.

### **Notes**

Calculates the Askaryan signal based on the ARVZ parameterization [1]. Uses a Heitler model for the electromagnetic shower profile [2] and a Gaisser-Hillas model for the hadronic shower profile [3]. Calculates the electric field from the vector potential using the convolution method outlined in section 4 of the ARVZ paper, which results in the most efficient calculation of the parameterization.

## References

### [1], [2], [3]

### **Attributes**

times, values [ndarray] 1D arrays of times (s) and corresponding values which define the signal.

value\_type [Signal.Type.field] Type of signal, representing the units of the values.

**Type** [Enum] Enum containing possible types (units) for signal values.

**em\_energy** [float] Energy (GeV) of the electromagnetic shower producing the pulse.

had\_energy [float] Energy (GeV) of the hadronic shower producing the pulse.

vector\_potential The vector potential of the signal.

dt The time spacing of the times array, or None if invalid.

**frequencies** The FFT frequencies of the signal.

**spectrum** The FFT complex spectrum values of the signal.

**envelope** The envelope of the signal by Hilbert transform.

# **Methods**

RAC(time, energy)	Calculates R*A_C at the given time and energy.
Type	Enum containing possible types (units) for signal
	values.
<pre>em_shower_profile(z, energy[, density,])</pre>	Calculates the electromagnetic shower longitudinal
	charge profile.
filter_frequencies(freq_response[,	Apply the given frequency response function to the
force_real])	signal, in-place.
had_shower_profile(z, energy[, density,])	Calculates the hadronic shower longitudinal charge
	profile.
<pre>max_length(energy[, density, crit_energy,])</pre>	Calculates the depth of a particle shower maximum.
resample(n)	Resamples the signal into n points in the same time
	range, in-place.
shower_signal(times, energy,)	Calculate the signal values for some shower type.
with_times(new_times)	Returns a representation of this signal over a differ-
	ent times array.

# pyrex.signals.AskaryanSignal

pyrex.signals.AskaryanSignal

alias of pyrex.signals.ARVZAskaryanSignal

### pyrex.signals.GaussianNoise

class pyrex.signals.GaussianNoise(times, sigma)

Class for gaussian noise signals with standard deviation sigma.

Calculates each time value independently from a normal distribution.

#### **Parameters**

**times** [array\_like] 1D array of times (s) for which the signal is defined.

**values** [array\_like] 1D array of values of the signal corresponding to the given *times*. Will be resized to the size of *times* by zero-padding or truncating.

**value\_type** Type of signal, representing the units of the values. Must be from the Signal. Type Enum.

### See also:

**Signal** Base class for time-domain signals.

#### Attributes

times, values [ndarray] 1D arrays of times (s) and corresponding values which define the signal.

value\_type [Signal.Type.voltage] Type of signal, representing the units of the values.

**Type** [Enum] Enum containing possible types (units) for signal values.

dt The time spacing of the times array, or None if invalid.

**frequencies** The FFT frequencies of the signal.

**spectrum** The FFT complex spectrum values of the signal.

**envelope** The envelope of the signal by Hilbert transform.

### **Methods**

Type	Enum containing possible types (units) for signal
	values.
filter_frequencies(freq_response[,	Apply the given frequency response function to the
force_real])	signal, in-place.
resample(n)	Resamples the signal into n points in the same time
	range, in-place.
with_times(new_times)	Returns a representation of this signal over a differ-
	ent times array.

### pyrex.signals.ThermalNoise

class pyrex.signals.ThermalNoise(times, f\_band, f\_amplitude=None, rms\_voltage=None, temperature=None, resistance=None, n\_freqs=0)

Class for thermal Rayleigh noise signals.

The Rayleigh thermal noise is calculated in a given frequency band with flat or otherwise specified amplitude and random phase at some number of frequencies. Values are scaled to a provided or calculated RMS voltage.

# **Parameters**

times [array\_like] 1D array of times (s) for which the signal is defined.

- **f\_band** [array\_like] Array of two elements denoting the frequency band (Hz) of the noise. The first element should be smaller than the second.
- **f\_amplitude** [float or function, optional] The frequency-domain amplitude of the noise. If float, then all frequencies will have the same amplitude. If function, then the function is evaluated at each frequency to determine its amplitude. By default, uses Rayleigh-distributed amplitudes.
- **rms\_voltage** [float, optional] The RMS voltage (V) of the noise. If specified, this value will be used instead of the RMS voltage calculated from the values of *temperature* and *resistance*.
- **temperature** [float, optional] The thermal noise temperature (K). Used in combination with the value of *resistance* to calculate the RMS voltage of the noise.
- **resistance** [float, optional] The resistance (ohm) for the noise. Used in combination with the value of *temperature* to calculate the RMS voltage of the noise.
- n\_freqs [int, optional] The number of frequencies within the frequency band to use to calculate the noise signal. By default determines the number of frequencies based on the FFT bin size of *times*.

### Raises

**ValueError** If the RMS voltage cannot be calculated (i.e. *rms\_voltage* or both *temperature* and *resistance* are None).

**Warning:** Since this class inherits from FunctionSignal, its with\_times method will properly extrapolate noise outside of the provided times. Be warned however that outside of the original signal times the noise signal will be highly periodic. Since the default number of frequencies used is based on the FFT bin size of *times*, the period of the noise signal is actually the length of *times*. As a result if you are planning on extrapolating the noise signal, increasing the number of frequencies used is strongly recommended.

### See also:

FunctionSignal Class for signals generated by a function.

# **Notes**

Calculation of the noise signal is based on the Rayleigh noise model used by ANITA [1]. Modifications have been made to the default to make the frequency-domain amplitudes Rayleigh-distributed, under the suggestion that this makes for more realistic noise traces.

### References

[1]

### Attributes

times, values [ndarray] 1D arrays of times (s) and corresponding values which define the signal.

**value\_type** [Signal.Type.voltage] Type of signal, representing the units of the values.

**Type** [Enum] Enum containing possible types (units) for signal values.

**function** [function] Function to evaluate the signal values at given time(s).

**f\_min** [float] Minimum frequency of the noise frequency band.

**f\_max** [float] Maximum frequency of the noise frequency band.

**freqs, amps, phases** [ndarray] The frequencies used to define the noise signal and their corresponding amplitudes and phases.

rms [float] The RMS value of the noise signal.

dt The time spacing of the times array, or None if invalid.

frequencies The FFT frequencies of the signal.

spectrum The FFT complex spectrum values of the signal.

**envelope** The envelope of the signal by Hilbert transform.

### **Methods**

Type	Enum containing possible types (units) for signal
	values.
filter_frequencies(freq_response[,	Apply the given frequency response function to the
force_real])	signal, in-place.
resample(n)	Resamples the signal into n points in the same time
	range, in-place.
with_times(new_times)	Returns a representation of this signal over a differ-
	ent times array.

# 6.2.3 Antennas (pyrex.antenna)

Module containing antenna classes responsible of receiving signals.

These classes are intended to model the properties of antennas including how signals are received as well as the production of noise. A number of attributes like directional gain, frequency response, and antenna factor may be necessary to calculate how signals are manipulated upon reception by an antenna.

Antenna(position[, z_axis, x_axis,])	Base class for antennas.
DipoleAntenna(name, position,[,])	Class for half-wave dipole antennas.

### pyrex.antenna.Antenna

```
class pyrex.antenna. Antenna (position, z_axis=(0, 0, 1), x_axis=(1, 0, 0), antenna_factor=1, efficiency=1, noisy=True, unique_noise_waveforms=10, freq_range=None, temperature=None, resistance=None, noise_rms=None)
```

Base class for antennas.

Stores the attributes of an antenna as well as handling receiving, processing, and storing signals and adding noise.

### **Parameters**

**position** [array\_like] Vector position of the antenna.

**z\_axis** [array\_like, optional] Vector direction of the z-axis of the antenna.

**x\_axis** [array\_like, optional] Vector direction of the x-axis of the antenna.

**antenna\_factor** [float, optional] Antenna factor used for converting electric field values to voltages.

efficiency [float, optional] Antenna efficiency applied to incoming signal values.

**noisy** [boolean, optional] Whether or not the antenna should add noise to incoming signals.

unique\_noise\_waveforms [int, optional] The number of expected noise waveforms needed for each received signal to have its own noise.

**freq\_range** [array\_like, optional] The frequency band in which the antenna operates (used for noise production).

**temperature** [float, optional] The noise temperature (K) of the antenna. Used in combination with *resistance* to calculate the RMS voltage of the antenna noise.

**resistance** [float, optional] The noise resistance (ohm) of the antenna. Used in combination with *temperature* to calculate the RMS voltage of the antenna noise.

**noise\_rms** [float, optional] The RMS voltage (V) of the antenna noise. If specified, this value will be used instead of the RMS voltage calculated from the values of *temperature* and *resistance*.

#### **Attributes**

**position** [array\_like] Vector position of the antenna.

**z\_axis** [ndarray] Vector direction of the z-axis of the antenna.

**x\_axis** [ndarray] Vector direction of the x-axis of the antenna.

antenna\_factor [float] Antenna factor used for converting electric field values to voltages.

efficiency [float] Antenna efficiency applied to incoming signal values.

**noisy** [boolean] Whether or not the antenna should add noise to incoming signals.

unique\_noises [int] The number of expected noise waveforms needed for each received signal to have its own noise.

**freq\_range** [array\_like] The frequency band in which the antenna operates (used for noise production).

**temperature** [float or None] The noise temperature (K) of the antenna. Used in combination with *resistance* to calculate the RMS voltage of the antenna noise.

**resistance** [float or None] The noise resistance (ohm) of the antenna. Used in combination with *temperature* to calculate the RMS voltage of the antenna noise.

**noise\_rms** [float or None] The RMS voltage (v) of the antenna noise. If not None, this value will be used instead of the RMS voltage calculated from the values of *temperature* and *resistance*.

signals [list of Signal] The signals which have been received by the antenna.

**is\_hit** Boolean of whether the antenna has been triggered.

waveforms Signal + noise (if noisy) for each triggered antenna hit.

all\_waveforms Signal + noise (if noisy) for all antenna hits.

#### Methods

<pre>clear([reset_noise])</pre>	Reset the antenna to an empty state.
directional_gain(theta, phi)	Calculate the (complex) directional gain of the an-
	tenna.
full_waveform(times)	Signal + noise (if noisy) for the given times.
is_hit_during(times)	Check if the antenna is triggered in a time range.
make_noise(times)	Creates a noise signal over the given times.
polarization_gain(polarization)	Calculate the (complex) polarization gain of the an-
	tenna.
receive(signal[, direction, polarization,])	Process and store an incoming signal.
response(frequencies)	Calculate the (complex) frequency response of the
	antenna.
set_orientation([z_axis, x_axis])	Sets the orientation of the antenna.
trigger(signal)	Check if the antenna triggers on a given signal.

### pyrex.antenna.DipoleAntenna

class pyrex.antenna. DipoleAntenna (name, position, center\_frequency, bandwidth, resistance, orientation=(0, 0, 1), trigger\_threshold=0, effective\_height=None, noisy=True, unique\_noise\_waveforms=10)

Class for half-wave dipole antennas.

Stores the attributes of an antenna as well as handling receiving, processing, and storing signals and adding noise. Uses a first-order butterworth filter for the frequency response. Includes a simple threshold trigger.

### **Parameters**

name [str] Name of the antenna.

**position** [array\_like] Vector position of the antenna.

center\_frequency [float] Tuned frequency (Hz) of the dipole.

**bandwidth** [float] Bandwidth (Hz) of the antenna.

**resistance** [float] The noise resistance (ohm) of the antenna. Used to calculate the RMS voltage of the antenna noise.

orientation [array\_like, optional] Vector direction of the z-axis of the antenna.

trigger\_threshold [float, optional] Voltage threshold (V) above which signals will trigger.

**effective\_height** [float, optional] Effective length (m) of the antenna. By default calculated by the tuned *center\_frequency* of the dipole.

**noisy** [boolean, optional] Whether or not the antenna should add noise to incoming signals.

**unique\_noise\_waveforms** [int, optional] The number of expected noise waveforms needed for each received signal to have its own noise.

### See also:

Antenna Base class for antennas.

### Attributes

name [str] Name of the antenna.

position [array\_like] Vector position of the antenna.

**z\_axis** [ndarray] Vector direction of the z-axis of the antenna.

**x\_axis** [ndarray] Vector direction of the x-axis of the antenna.

antenna\_factor [float] Antenna factor used for converting electric field values to voltages.

efficiency [float] Antenna efficiency applied to incoming signal values.

threshold [float, optional] Voltage threshold (V) above which signals will trigger.

**effective\_height** [float, optional] Effective length of the antenna. By default calculated by the tuned *center\_frequency* of the dipole.

**filter\_coeffs** [tuple of ndarray] Coefficients of the transfer function of the butterworth bandpass filter to be used for frequency response.

**noisy** [boolean] Whether or not the antenna should add noise to incoming signals.

**unique\_noises** [int] The number of expected noise waveforms needed for each received signal to have its own noise.

**freq\_range** [array\_like] The frequency band in which the antenna operates (used for noise production).

**temperature** [float or None] The noise temperature (K) of the antenna. Used in combination with *resistance* to calculate the RMS voltage of the antenna noise.

**resistance** [float or None] The noise resistance (ohm) of the antenna. Used in combination with *temperature* to calculate the RMS voltage of the antenna noise.

**noise\_rms** [float or None] The RMS voltage (V) of the antenna noise. If not None, this value will be used instead of the RMS voltage calculated from the values of *temperature* and *resistance*.

signals [list of Signal] The signals which have been received by the antenna.

**is\_hit** Boolean of whether the antenna has been triggered.

waveforms Signal + noise (if noisy) for each triggered antenna hit.

all\_waveforms Signal + noise (if noisy) for all antenna hits.

### **Methods**

clear([reset_noise])	Reset the antenna to an empty state.
directional_gain(theta, phi)	Calculate the (complex) directional gain of the an-
	tenna.
full_waveform(times)	Signal + noise (if noisy) for the given times.
is_hit_during(times)	Check if the antenna is triggered in a time range.
make_noise(times)	Creates a noise signal over the given times.
polarization_gain(polarization)	Calculate the (complex) polarization gain of the an-
	tenna.
receive(signal[, direction, polarization,])	Process and store an incoming signal.
response(frequencies)	Calculate the (complex) frequency response of the
	antenna.
set_orientation([z_axis, x_axis])	Sets the orientation of the antenna.
trigger(signal)	Check if the antenna triggers on a given signal.

# 6.2.4 High-level Detectors (pyrex.detector)

Module containing higher-level detector-related classes.

The classes in this module are responsible for higher-level operations of the antennas and detectors than in the antenna module. This includes functions like front-end electronics chains and trigger systems.

AntennaSystem(antenna)	Base class for antenna system with front-end process-
	ing.
Detector(*args, **kwargs)	Base class for detectors for easily building up sets of
	antennas.
CombinedDetector(*detectors)	Class for detectors which have been added together.

# pyrex.detector.AntennaSystem

# class pyrex.detector.AntennaSystem(antenna)

Base class for antenna system with front-end processing.

Behaves similarly to an antenna by passing some functionality downward to an antenna class, but additionally applies some front-end processing (e.g. an electronics chain) to the signals received.

### **Parameters**

**antenna** [Antenna] Antenna class or subclass to be extended with a front end. Can also accept an Antenna object directly.

### See also:

pyrex. Antenna Base class for antennas.

### **Attributes**

antenna [Antenna] Antenna object extended by the front end.

**lead\_in\_time** [float] Lead-in time (s) required for the front end to equilibrate. Automatically added in before calculation of signals and waveforms.

**is\_hit** Boolean of whether the antenna system has been triggered.

**signals** The signals received by the antenna with front-end processing.

waveforms The antenna system signal + noise for each triggered hit.

**all\_waveforms** The antenna system signal + noise for all hits.

### **Methods**

clear([reset_noise])	Reset the antenna system to an empty state.
front_end(signal)	Apply front-end processes to a signal and return the
	output.
full_waveform(times)	Signal + noise for the antenna system for the given
	times.
is_hit_during(times)	Check if the antenna system is triggered in a time
	range.
make_noise(times)	Creates a noise signal over the given times.
receive(signal[, direction, polarization,])	Process and store an incoming signal.
receive(signal[, direction, polarization,]) set_orientation([z_axis, x_axis])	Process and store an incoming signal.  Sets the orientation of the antenna system.
set_orientation([z_axis, x_axis])	Sets the orientation of the antenna system.

Continued on next page

## Table 32 – continued from previous page

trigger(signal)	Check if the antenna system triggers on a given sig-
	nal.

### pyrex.detector.Detector

class pyrex.detector.Detector(\*args, \*\*kwargs)

Base class for detectors for easily building up sets of antennas.

Designed for automatically generating antenna positions based on geometry parameters, then building all the antennas with some properties. Any parameters to the <u>\_\_init\_\_</u> method are automatically passed on to the set\_positions method. Once the antennas have been built, the object can be directly iterated over to iterate over the antennas (as if the object were just a list of the antennas).

#### Raises

**ValueError** If test\_antenna\_positions is True and an antenna is found to be above the ice surface.

### See also:

pyrex. Antenna Base class for antennas.

AntennaSystem Base class for antenna system with front-end processing.

#### **Notes**

When this class is subclassed, the \_\_init\_\_ method will mirror the signature of the set\_positions method so that parameters can be easily discovered.

The class is designed to be flexible in what defines a "detector". This should allow for easier modularization by defining detectors whose subsets are detectors themselves, and so on. For example, a string of antennas could be set up as a subclass of <code>Detector</code> which sets up some antennas in a vertical line. Then a station could be set up as a subclass of <code>Detector</code> which sets up multiple instances of the string class at different positions. Then a final overarching detector class can subclass <code>Detector</code> and set up multiple instances of the station class at different positions. In this example the <code>subsets</code> of the overarching detector class would be the station objects, the <code>subsets</code> of the station objects would be the string objects, and the <code>subsets</code> of the string objects would finally be the antenna objects. But the way the iteration of the <code>Detector</code> class is built, iterating over that overarching detector class would iterate directly over each antenna in each string in each station as a simple 1D list.

### **Attributes**

**antenna\_positions** [list] List (potentially with sub-lists) of the positions of the antennas generated by the set\_positions method.

**subsets** [list] List of the antenna or detector objects which make up the detector.

**test\_antenna\_positions** [boolean] Class attribute for whether or not an error should be raised if antenna positions are found above the surface of the ice (where simulation behavior is ill-defined). Defaults to True.

### **Methods**

build\_antennas(\*args, \*\*kwargs)

Creates antenna objects at the set antenna positions.

Continued on next page

Table 33 – continued from previous page

clear([reset_noise])	Reset the detector to an empty state.
set_positions(*args, **kwargs)	Sets the positions of antennas in the detector.
triggered(*args[, require_mc_truth])	Check if the detector is triggered based on its current
	state.

# pyrex.detector.CombinedDetector

class pyrex.detector.CombinedDetector(\*detectors)

Class for detectors which have been added together.

Designed to allow addition of Detector and Antenna-like objects which can still build all antennas and trigger by smartly passing down keyword arugments to the subsets. Maintains all other properties of the Detector objects.

#### Raises

**ValueError** If test\_antenna\_positions is True and an antenna is found to be above the ice surface.

### See also:

pyrex. Antenna Base class for antennas.

**AntennaSystem** Base class for antenna system with front-end processing.

**Detector** Base class for detectors for easily building up sets of antennas.

#### Attributes

**antenna\_positions** [list] List of the positions of the antennas in the detector.

subsets [list] List of the antenna or detector objects which make up the detector.

**test\_antenna\_positions** [boolean] Class attribute for whether or not an error should be raised if antenna positions are found above the surface of the ice (where simulation behavior is ill-defined). Defaults to True.

### **Methods**

build_antennas(*args, **kwargs)	Creates antenna objects at the set antenna positions.
clear([reset_noise])	Reset the detector to an empty state.
set_positions(*args, **kwargs)	Sets the positions of antennas in the detector.
triggered(*args[, require_mc_truth])	Check if the detector is triggered based on its current
	state.

# 6.2.5 Earth Model (pyrex.earth\_model)

Module containing earth model functions.

The earth model uses the Preliminary Earth Model (PREM) for density as a function of radius and a simple integrator for calculation of the slant depth along a straight path through the Earth.

prem density(r)	Calculates the Earth's density at a given radius.
	Continued on next page

## Table 35 – continued from previous page

	<u> </u>
<pre>slant_depth(angle, depth[, step])</pre>	Calculates the material thickness of a chord cutting
	through Earth.

# pyrex.earth\_model.prem\_density

```
pyrex.earth_model.prem_density(r)
```

Calculates the Earth's density at a given radius.

Density from the Preliminary reference Earth Model (PREM). Supports passing an array of radii or a single radius.

### **Parameters**

**r** [array\_like] Radius (m) at which to calculate density.

# Returns

array\_like Density (g/cm<sup>3</sup>) of the Earth at the given radii.

### **Notes**

The density calculation is based on the Preliminary reference Earth Model [1].

# References

[1]

# pyrex.earth\_model.slant\_depth

```
pyrex.earth_model.slant_depth (angle, depth, step=500)
```

Calculates the material thickness of a chord cutting through Earth.

Integrates the Earth's density along the chord. Uses the PREM model for density.

### **Parameters**

```
angle [float] Nadir angle (radians) of the chord's direction.
```

depth [float] (Positive-valued) depth (m) of the chord endpoint.

**step** [float, optional] Step size (m) for the integration.

### Returns

**float** Material thickness (g/cm<sup>2</sup>) along the chord starting from *depth* and passing through the Earth at *angle*.

# See also:

prem\_density Calculates the Earth's density at a given radius.

# 6.2.6 Ice Models (pyrex.ice\_model)

Module containing ice model classes.

The ice model classes contain static and class methods for convenience, and parameters of the ice model are set as class attributes.

AntarcticIce	Class describing the ice at the south pole.
NewcombIce	Class describing the ice at the south pole.
ArasimIce	Class describing the ice at the south pole.
IceModel	alias of pyrex.ice_model.AntarcticIce

### pyrex.ice model.Antarcticlce

# class pyrex.ice\_model.AntarcticIce

Class describing the ice at the south pole.

For convenience, consists of static methods and class methods, so creating an instance of the class may not be necessary. In all methods, the depth z should be given as a negative value if it is below the surface of the ice.

### **Notes**

Mostly based on ice characteristics outlined by Matt Newcomb.

### **Attributes**

**k**, **a**, **n0** [float] Parameters of the index of refraction of the ice.

thickness [float] Thickness of the ice sheet.

### **Methods**

$\verb  attenuation_length (z,f)$	Calculates attenuation lengths for given depths and frequencies.
depth_with_index(n)	Calculates the corresponding depth for a given index
	of refraction.
gradient(z)	Calculates the gradient of the index of refraction at a
	given depth.
index(z)	Calculates the index of refraction of the ice at a given
	depth.
temperature(z)	Calculates the temperature of the ice at a given depth.

# pyrex.ice\_model.Newcomblce

# class pyrex.ice\_model.Newcomblce

Class describing the ice at the south pole.

Uses an attenuation length based on Matt Newcomb's fit. For convenience, consists of static methods and class methods, so creating an instance of the class may not be necessary. In all methods, the depth z should be given as a negative value if it is below the surface of the ice.

**Warning:** The attenuation\_length method if this class does not currently work properly. This class should not be used until it is fixed.

### **Notes**

Mostly based on ice characteristics outlined by Matt Newcomb.

### **Attributes**

k, a, n0 [float] Parameters of the index of refraction of the ice.

thickness [float] Thickness of the ice sheet.

### **Methods**

${ t attenuation\_length}({ t z},{ t f})$	Calculates attenuation lengths for given depths and
	frequencies.
depth_with_index(n)	Calculates the corresponding depth for a given index
	of refraction.
gradient(z)	Calculates the gradient of the index of refraction at a
	given depth.
index(z)	Calculates the index of refraction of the ice at a given
	depth.
temperature(z)	Calculates the temperature of the ice at a given depth.

# pyrex.ice\_model.ArasimIce

### class pyrex.ice\_model.ArasimIce

Class describing the ice at the south pole.

Designed to match ice model used in AraSim. For convenience, consists of static methods and class methods, so creating an instance of the class may not be necessary. In all methods, the depth z should be given as a negative value if it is below the surface of the ice.

### **Attributes**

**k, a, n0** [float] Parameters of the index of refraction of the ice.

thickness [float] Thickness of the ice sheet.

**atten\_depths, atten\_lengths** [list] Depths and corresponding attenuation lengths to be interpolated in the attenuation\_length calculation.

### **Methods**

$attenuation\_length(z, f)$	Calculates attenuation lengths for given depths and
	frequencies.
depth_with_index(n)	Calculates the corresponding depth for a given index
	of refraction.
gradient(z)	Calculates the gradient of the index of refraction at a
	given depth.
	Continued on next page

Table 39 -	continued	from	previous page
Table 55 -	COLITION	11 0111	previous page

11	ontinued from previous page
index(z)	Calculates the index of refraction of the ice at a given
	depth.
temperature(z)	Calculates the temperature of the ice at a given depth.

### pyrex.ice\_model.lceModel

```
pyrex.ice_model.IceModel
    alias of pyrex.ice_model.AntarcticIce
```

# 6.2.7 Ray Tracers (pyrex.ray\_tracing)

Module containing classes for ray tracing through the ice.

Ray tracer classes correspond to ray trace path classes, where the ray tracer is responsible for calculating the existance and launch angle of paths between points, and the ray tracer path objects are responsible for returning information about propagation along their respective path.

BasicRayTracePath(parent_tracer,)	Class for representing a single ray-trace solution be-
	tween points.
SpecializedRayTracePath(parent_tracer,)	Class for representing a single ray-trace solution be-
	tween points.
BasicRayTracer(from_point, to_point[,])	Class for calculating the ray-trace solutions between
	points.
<pre>SpecializedRayTracer(from_point, to_point[,</pre>	Class for calculating the ray-trace solutions between
])	points.
RayTracer	alias of pyrex.ray_tracing.
	SpecializedRayTracer
RayTracePath	alias of pyrex.ray_tracing.
	SpecializedRayTracePath
<pre>PathFinder(ice_model, from_point, to_point)</pre>	Class for pseudo ray tracing.
ReflectedPathFinder(ice_model, from_point,	Class for pseudo ray tracing of a reflected ray.
)	
	-

# pyrex.ray\_tracing.BasicRayTracePath

**class** pyrex.ray\_tracing.**BasicRayTracePath** (parent\_tracer, launch\_angle, direct) Class for representing a single ray-trace solution between points.

Stores parameters of the ray path with calculations performed by integrating z-steps of size dz. Most properties are lazily evaluated to save on computation time. If any attributes of the class instance are changed, the lazily-evaluated properties will be cleared.

# **Parameters**

**parent\_tracer** [BasicRayTracer] Ray tracer for which this path is a solution.

launch\_angle [float] Launch angle (radians) of the ray path.

**direct** [boolean] Whether the ray path is direct. If True this means the path does not "turn over". If False then the path does "turn over" by either reflection or refraction after reaching some maximum depth.

See also:

pyrex.internal\_functions.LazyMutableClass Class with lazy properties which may depend on
 other class attributes.

BasicRayTracer Class for calculating the ray-trace solutions between points.

#### **Notes**

Even more attributes than those listed are available for the class, but are mainly for internal use. These attributes can be found by exploring the source code.

#### Attributes

**from\_point** [ndarray] The starting point of the ray path.

to\_point [ndarray] The ending point of the ray path.

**theta0** [float] The launch angle of the ray path at *from\_point*.

ice The ice model used for the ray tracer.

**dz** [float] The z-step (m) to be used for integration of the ray path attributes.

**direct** [boolean] Whether the ray path is direct. If True this means the path does not "turn over". If False then the path does "turn over" by either reflection or refraction after reaching some maximum depth.

emitted\_direction

received\_direction

path\_length

tof

coordinates

### **Methods**

attenuation(f)	Calculate the attenuation factor for signal frequen-
	cies.
propagate([signal, polarization])	Propagate the signal with optional polarization along
	the ray path.
theta(z)	Polar angle of the ray at the given depths.
z_integral(integrand)	Calculate the numerical integral of the given inte-
	grand.

### pyrex.ray\_tracing.SpecializedRayTracePath

**class** pyrex.ray\_tracing.**SpecializedRayTracePath** (*parent\_tracer*, *launch\_angle*, *direct*)

Class for representing a single ray-trace solution between points.

Stores parameters of the ray path with calculations performed analytically (with the exception of attenuation). These calculations require the index of refraction of the ice to be of the form n(z)=n0-k\*exp(a\*z). However this restriction allows for most of the integrations to be performed analytically. The attenuation is the only attribute which is still calculated by numerical integration with z-steps of size dz. Most properties are lazily evaluated to save on computation time. If any attributes of the class instance are changed, the lazily-evaluated properties will be cleared.

### **Parameters**

parent\_tracer [SpecializedRayTracer] Ray tracer for which this path is a solution.

launch\_angle [float] Launch angle (radians) of the ray path.

**direct** [boolean] Whether the ray path is direct. If True this means the path does not "turn over". If False then the path does "turn over" by either reflection or refraction after reaching some maximum depth.

#### See also:

pyrex.internal\_functions.LazyMutableClass Class with lazy properties which may depend on other class attributes.

SpecializedRayTracer Class for calculating the ray-trace solutions between points.

### **Notes**

Even more attributes than those listed are available for the class, but are mainly for internal use. These attributes can be found by exploring the source code.

The requirement that the ice model go as n(z)=n0-k\*exp(a\*z) is implemented by requiring the ice model to inherit from AntarcticIce. Obviously this is not fool-proof, but likely the ray tracing will obviously fail if the index follows a very different functional form.

#### **Attributes**

**from\_point** [ndarray] The starting point of the ray path.

**to\_point** [ndarray] The ending point of the ray path.

**theta0** [float] The launch angle of the ray path at from point.

ice The ice model used for the ray tracer.

dz [float] The z-step (m) to be used for integration of the ray path attributes.

**direct** [boolean] Whether the ray path is direct. If True this means the path does not "turn over". If False then the path does "turn over" by either reflection or refraction after reaching some maximum depth.

**uniformity\_factor** [float] Factor (<1) of the base index of refraction (n0 in the ice model) beyond which calculations start to break down numerically.

**beta\_tolerance** [float] beta value (near 0) below which calculations start to break down numerically.

emitted\_direction

received\_direction

path\_length

tof

coordinates

### **Methods**

attenuation(f)	Calculate the attenuation factor for signal frequencies.
	Continued on next page

Table 42 – continued from previous page

	1 1 0
propagate([signal, polarization])	Propagate the signal with optional polarization along
	the ray path.
theta(z)	Polar angle of the ray at the given depths.
z_integral(integrand[, numerical, x_func])	Calculate the integral of the given integrand.

# pyrex.ray\_tracing.BasicRayTracer

Class for calculating the ray-trace solutions between points.

Calculations performed by integrating z-steps of size dz. Most properties are lazily evaluated to save on computation time. If any attributes of the class instance are changed, the lazily-evaluated properties will be cleared.

### **Parameters**

**from\_point** [array\_like] Vector starting point of the ray path.

**to\_point** [array\_like] Vector ending point of the ray path.

ice\_model The ice model used for the ray tracer.

dz [float] The z-step (m) to be used for integration of the ray path attributes.

#### See also:

pyrex.internal\_functions.LazyMutableClass Class with lazy properties which may depend on
 other class attributes.

BasicRayTracePath Class for representing a single ray-trace solution between points.

### **Notes**

Even more attributes than those listed are available for the class, but are mainly for internal use. These attributes can be found by exploring the source code.

### Attributes

**from\_point** [ndarray] The starting point of the ray path.

**to\_point** [ndarray] The ending point of the ray path.

ice The ice model used for the ray tracer.

dz [float] The z-step (m) to be used for integration of the ray path attributes.

**solution\_class** Class for representing a single ray-trace solution between points.

exists

expected\_solutions

solutions

### Methods

) true_r.	angle_search(true_r,	r_function,	min_angle,	Calculates the angle where $r_function$ (angle) ==
	)			true_r.

Continued on next page

# Table 43 - continued from previous page

solution class

alias of BasicRayTracePath

### pyrex.ray\_tracing.SpecializedRayTracer

Class for calculating the ray-trace solutions between points.

Calculations in this class require the index of refraction of the ice to be of the form n(z)=n0-k\*exp(a\*z). However this restriction allows for most of the integrations to be performed analytically. Most properties are lazily evaluated to save on computation time. If any attributes of the class instance are changed, the lazily-evaluated properties will be cleared.

### **Parameters**

**from\_point** [array\_like] Vector starting point of the ray path.

**to\_point** [array\_like] Vector ending point of the ray path.

**ice\_model** The ice model used for the ray tracer.

dz [float] The z-step (m) to be used for integration of the ray path attributes.

### See also:

pyrex.internal\_functions.LazyMutableClass Class with lazy properties which may depend on other class attributes.

SpecializedRayTracePath Class for representing a single ray-trace solution between points.

#### Notes

Even more attributes than those listed are available for the class, but are mainly for internal use. These attributes can be found by exploring the source code.

The requirement that the ice model go as n(z)=n0-k\*exp(a\*z) is implemented by requiring the ice model to inherit from AntarcticIce. Obviously this is not fool-proof, but likely the ray tracing will obviously fail if the index follows a very different functional form.

### Attributes

**from point** [ndarray] The starting point of the ray path.

**to\_point** [ndarray] The ending point of the ray path.

ice The ice model used for the ray tracer.

**dz** [float] The z-step (m) to be used for integration of the ray path attributes.

**solution\_class** Class for representing a single ray-trace solution between points.

exists

expected\_solutions

solutions

### **Methods**

angle_search(true_r, $r_{-}$	_function,	min_angle,	Calculates the angle where $r_function$ (angle) ==
)			true_r.
solution_class			alias of SpecializedRayTracePath

# pyrex.ray\_tracing.RayTracer

```
pyrex.ray_tracing.RayTracer
    alias of pyrex.ray_tracing.SpecializedRayTracer
```

### pyrex.ray\_tracing.RayTracePath

```
pyrex.ray_tracing.RayTracePath
    alias of pyrex.ray_tracing.SpecializedRayTracePath
```

# pyrex.ray\_tracing.PathFinder

**class** pyrex.ray\_tracing.**PathFinder** (*ice\_model*, *from\_point*, *to\_point*) Class for pseudo ray tracing. Just uses straight-line paths.

### **Parameters**

ice\_model The ice model used for the ray tracer.

**from\_point** [array\_like] Vector starting point of the ray path.

to\_point [array\_like] Vector ending point of the ray path.

# **Attributes**

**from\_point** [ndarray] The starting point of the ray path.

**to\_point** [ndarray] The ending point of the ray path.

ice The ice model used for the ray tracer.

**exists** Boolean of whether the path exists between the endpoints.

emitted\_ray Direction in which the ray is emitted.

**received\_ray** Direction from which the ray is received.

path\_length Length (m) of the path.

tof Time of flight (s) for a particle along the path.

### **Methods**

attenuation(f[, n_steps])	Calculate the attenuation factor for signal frequencies.
propagate(signal)	Propagate the signal along the ray path, in-place.
time_of_flight([n_steps])	Time of flight (s) for a particle along the path.

# pyrex.ray\_tracing.ReflectedPathFinder

Class for pseudo ray tracing of a reflected ray. Uses straight-line paths.

### **Parameters**

ice\_model The ice model used for the ray tracer.

**from\_point** [array\_like] Vector starting point of the ray path.

to\_point [array\_like] Vector ending point of the ray path.

reflection\_depth [float, optional] (Negative-valued) depth (m) at which the ray reflects.

### Attributes

**from\_point** [ndarray] The starting point of the ray path.

**to\_point** [ndarray] The ending point of the ray path.

ice The ice model used for the ray tracer.

**bounce\_point** [ndarray] The point at which the ray path is reflected.

path\_1 [PathFinder] The path from from\_point to bounce\_point.

path\_2 [PathFinder] The path from bounce\_point to to\_point.

exists Boolean of whether the path exists between the endpoints.

emitted\_ray Direction in which the ray is emitted.

**received\_ray** Direction from which the ray is received.

path\_length Length of the path (m).

tof Time of flight (s) for a particle along the path.

### **Methods**

attenuation(f[, n_steps])	Calculate the attenuation factor for signal frequen-
	cies.
<pre>get_bounce_point([reflection_depth])</pre>	Calculates the point at which the ray is reflected.
propagate(signal)	Propagate the signal along the ray path, in-place.
time_of_flight([n_steps])	Time of flight (s) for a particle along the path.

# 6.2.8 Particles and Interaction Models (pyrex.particle)

Module for particles (neutrinos) and neutrino interactions in the ice.

Included in the module are the Particle class for storing particle/shower attributes and some Interaction classes which store models describing neutrino interactions.

Event(roots)	Class for storing a tree of Particle objects represent-
	ing an event.
Particle(particle_id, vertex, direction, energy)	Class for storing particle attributes.
Interaction(particle[, kind])	Base class for describing neutrino interaction attributes.
GQRSInteraction(particle[, kind])	Class for describing neutrino interaction attributes.
	O and the constraint of the co

Continued on next page

# Table 47 – continued from previous page

CTWInteraction(particle[, kind])	Class for describing neutrino interaction attributes.
NeutrinoInteraction	alias of pyrex.particle.CTWInteraction

# pyrex.particle.Event

class pyrex.particle.Event(roots)

Class for storing a tree of *Particle* objects representing an event.

The event may be comprised of any number of root <code>Particle</code> objects specified at initialization. Each <code>Particle</code> in the tree may have any number of child <code>Particle</code> objects. Iterating the tree will return all <code>Particle</code> objects, but in no guaranteed order.

#### **Parameters**

roots [Particle or list of Particle] Root Particle objects for the event tree.

### See also:

Particle Class for storing particle attributes.

#### Attributes

roots [Particle or list of Particle] Root Particle objects for the event tree.

### **Methods**

<pre>add_children(parent, children)</pre>	Add the given <i>children</i> to the <i>parent Particle</i> ob-
	ject.
get_children(parent)	Get the children of the given parent Particle ob-
	ject.
get_from_level(level)	Get all Particle objects some level deep into the
	event tree.
get_parent(child)	Get the parent of the given <i>child</i> Particle object.

### pyrex.particle.Particle

Class for storing particle attributes.

# **Parameters**

particle\_id Identification value of the particle type. Values should be from the Particle.
Type enum, but integer or string values may work if carefully chosen. Particle. Type.
undefined by default.

vertex [array\_like] Vector position (m) of the particle.

direction [array\_like] Vector direction of the particle's velocity.

**energy** [float] Energy (GeV) of the particle.

**interaction\_model** [optional] Class to use to describe interactions of the particle. Should inherit from (or behave like) the base Interaction class.

interaction\_type [optional] Value of the interaction type. Values should be from the
 Interaction.Type enum, but integer or string values may work if carefully chosen.
 By default, the interaction\_model will choose an interaction type.

weight [float, optional] Total Monte Carlo weight of the particle. The calculation of this weight depends on the particle generation method, but this value should be the total weight representing the probability of this particle's event occurring.

#### See also:

**Interaction** Base class for describing neutrino interaction attributes.

#### **Attributes**

id [Particle.Type] Identification value of the particle type.

vertex [array\_like] Vector position (m) of the particle.

direction [array\_like] (Unit) vector direction of the particle's velocity.

energy [float] Energy (GeV) of the particle.

**interaction** [Interaction] Instance of the *interaction\_model* class to be used for calculations related to interactions of the particle.

weight [float] Total Monte Carlo weight of the particle

**survival\_weight** [float] Monte Carlo weight of the particle surviving to its vertex. Represents the probability that the particle does not interact along its path through the Earth.

**interaction\_weight** [float] Monte Carlo weight of the particle interacting at its vertex. Represents the probability that the particle interacts specifically at its given vertex.

### **Methods**

Туре

Enum containing possible particle types.

### pyrex.particle.Interaction

class pyrex.particle.Interaction(particle, kind=None)

Base class for describing neutrino interaction attributes.

Defaults to values which will result in zero probability of interaction.

### **Parameters**

particle [Particle] Particle object for which the interaction is defined.

kind [optional] Value of the interaction type. Values should be from the Interaction.
Type enum, but integer or string values may work if carefully chosen. By default will be chosen by the choose\_interaction method.

### See also:

Particle Class for storing particle attributes.

### Attributes

particle [Particle] Particle object for which the interaction is defined.

**kind** [Interaction.Type] Value of the interaction type.

inelasticity [float] Inelasticity value from choose\_inelasticity distribution for the interaction.

**em\_frac** [float] Fraction of *particle* energy deposited into an electromagnetic shower.

**had\_frac** [float] Fraction of *particle* energy deposited into a hadronic shower.

total\_cross\_section The total neutrino cross section (cm^2) of the particle type.

total\_interaction\_length The neutrino interaction length (cmwe) of the particle type.

**cross\_section** The neutrino cross section (cm^2) of the particle interaction.

interaction\_length The neutrino interaction length (cmwe) of the particle interaction.

# **Methods**

Туре	Enum containing possible interaction types.
choose_inelasticity()	Choose an inelasticity for the particle attribute's
	shower.
choose_interaction()	Choose an interaction type for the particle at-
	tribute.
choose_shower_fractions()	Choose the electromagnetic and hadronic shower
	fractions.

# pyrex.particle.GQRSInteraction

class pyrex.particle.GQRSInteraction(particle, kind=None)

Class for describing neutrino interaction attributes.

Calculates values related to the interaction(s) of a given particle. Values based on GQRS 1998.

### **Parameters**

particle [Particle] Particle object for which the interaction is defined.

**kind** [optional] Value of the interaction type. Values should be from the Interaction. Type enum, but integer or string values may work if carefully chosen. By default will be chosen by the choose\_interaction method.

### See also:

**Interaction** Base class for describing neutrino interaction attributes.

Particle Class for storing particle attributes.

#### **Notes**

Neutrino intractions based on the GQRS Ultrahigh-Energy Neutrino Interactions paper [1].

# References

[1]

### **Attributes**

particle [Particle] Particle object for which the interaction is defined.

**kind** [Interaction.Type] Value of the interaction type.

**inelasticity** [float] Inelasticity value from choose\_inelasticity distribution for the interaction.

em\_frac [float] Fraction of particle energy deposited into an electromagnetic shower.

had\_frac [float] Fraction of particle energy deposited into a hadronic shower.

total\_cross\_section The total neutrino cross section (cm^2) of the particle type.

total\_interaction\_length The neutrino interaction length (cmwe) of the particle type.

**cross\_section** The neutrino cross section (cm^2) of the particle interaction.

interaction\_length The neutrino interaction length (cmwe) of the particle interaction.

### **Methods**

Туре	Enum containing possible interaction types.
choose_inelasticity()	Choose an inelasticity for the particle attribute's
	shower.
choose_interaction()	Choose an interaction type for the particle at-
	tribute.
choose_shower_fractions()	Choose the electromagnetic and hadronic shower
	fractions.

### pyrex.particle.CTWInteraction

class pyrex.particle.CTWInteraction(particle, kind=None)

Class for describing neutrino interaction attributes.

Calculates values related to the interaction(s) of a given particle. Values based on CTW 2011.

#### **Parameters**

particle [Particle] Particle object for which the interaction is defined.

kind [optional] Value of the interaction type. Values should be from the Interaction.
Type enum, but integer or string values may work if carefully chosen. By default will be chosen by the choose\_interaction method.

#### See also:

Interaction Base class for describing neutrino interaction attributes.

Particle Class for storing particle attributes.

# **Notes**

Neutrino intractions based on the CTW High Energy Neutrino-Nucleon Cross Sections paper [1]. Secondary generation method to determine shower fractions was pulled from AraSim, which is unchanged from icemc.

### References

[1]

### **Attributes**

particle [Particle] Particle object for which the interaction is defined.

**kind** [Interaction.Type] Value of the interaction type.

**inelasticity** [float] Inelasticity value from choose\_inelasticity distribution for the interaction.

em\_frac [float] Fraction of particle energy deposited into an electromagnetic shower.

had\_frac [float] Fraction of particle energy deposited into a hadronic shower.

total\_cross\_section The total neutrino cross section (cm^2) of the particle type.

total\_interaction\_length The neutrino interaction length (cmwe) of the particle type.

**cross\_section** The neutrino cross section (cm^2) of the particle interaction.

interaction\_length The neutrino interaction length (cmwe) of the particle interaction.

### **Methods**

Туре	Enum containing possible interaction types.
choose_inelasticity()	Choose an inelasticity for the particle attribute's
	shower.
choose_interaction()	Choose an interaction type for the particle at-
	tribute.
choose_shower_fractions()	Choose the electromagnetic and hadronic shower
	fractions.

# pyrex.particle.NeutrinoInteraction

pyrex.particle.NeutrinoInteraction
 alias of pyrex.particle.CTWInteraction

# 6.2.9 Event Generators (pyrex.generation)

Module for particle (neutrino) generators.

Generators are responsible for the input of events into the simulation.

Class to generate neutrino vertices in a cylindrical ice
volume.
Class to generate neutrino vertices in a rectangular ice
volume.
Class to generate neutrino vertices in a cylindrical ice
volume.

Continued on next page

Table 53 –	continued	from	previous	nage
iabic oo	COLITICICA	11 0111	providuo	page

RectangularShadowGenerator(dx, dy, dz, en-	Class to generate neutrino vertices in a rectangular ice
ergy)	volume.
ShadowGenerator(dx, dy, dz, energy[,])	

### **Methods**

ListGenerator(events[, loop])	Class to generate neutrino events from a list.
<pre>NumpyFileGenerator(files[, interaction_model])</pre>	Class to generate neutrino events from numpy file(s).
FileGenerator(files[, slice_range,])	Class to generate neutrino events from simulation
	file(s).

# pyrex.generation.BaseGenerator

class pyrex.generation.BaseGenerator(energy, flavor\_ratio=(1, 1, 1), interaction\_model=<class 'pyrex.particle.CTWInteraction'>)

Base class for neutrino generators.

Provides methods for generating neutrino attributes except for neutrino vertex, which should be provided by child classes to generate neutrinos in specific volumes.

#### **Parameters**

**energy** [float or function] Energy (GeV) of the neutrinos. If float, all neutrinos have the same constant energy. If function, neutrinos are generated with the energy returned by successive function calls.

**flavor\_ratio** [array\_like, optional] Flavor ratio of neutrinos to be generated. Of the form [electron, muon, tau] neutrino fractions.

**interaction\_model** [optional] Class to use to describe interactions of the generated particles. Should inherit from (or behave like) the base Interaction class.

### See also:

pyrex.particle.Interaction Base class for describing neutrino interaction attributes.

### **Attributes**

**count** [int] Number of neutrinos produced by the generator, including those not returned due to Earth shadowing or other effects.

**get\_energy** [function] Function returning energy (GeV) of the neutrinos by successive function calls.

**ratio** [ndarary] (Normalized) flavor ratio of neutrinos to be generated. Of the form [electron, muon, tau] neutrino fractions.

interaction\_model [Interaction] Class to use to describe interactions of the generated particles.

### **Methods**

create_event()	Generate a neutrino event in the ice volume.
get_direction()	Get the direction of the next particle to be generated.
	Continued on next page

T		•		
12010 6/1 -	CONTINUIOR	trom	nroviolic	naga
Table 54 –	COHIHIUCU	поп	DIEVIOUS	Dauc

<pre>get_exit_points(particle)</pre>	Get the intersections of the particle path with the ice
	volume edges.
<pre>get_particle_type()</pre>	Get the particle type of the next particle to be gener-
	ated.
get_vertex()	Get the vertex of the next particle to be generated.
get_weights(particle)	Get the weighting factors to be applied to the parti-
	cle.

# pyrex.generation.CylindricalGenerator

Class to generate neutrino vertices in a cylindrical ice volume.

Generates neutrinos in a cylinder with given radius and height.

#### **Parameters**

- **dr** [float] Radius of the ice volume. Neutrinos generated within (0, dr).
- **dz** [float] Height of the ice volume in the z-direction. Neutrinos generated within (-dz, 0).
- **energy** [float or function] Energy (GeV) of the neutrinos. If float, all neutrinos have the same constant energy. If function, neutrinos are generated with the energy returned by successive function calls.
- **flavor\_ratio** [array\_like, optional] Flavor ratio of neutrinos to be generated. Of the form [electron, muon, tau] neutrino fractions.
- **interaction\_model** [optional] Class to use to describe interactions of the generated particles. Should inherit from (or behave like) the base Interaction class.

### See also:

pyrex.particle.Interaction Base class for describing neutrino interaction attributes.

### Attributes

- **count** [int] Number of neutrinos produced by the generator, including those not returned due to Earth shadowing or other effects.
- **dr** [float] Radius of the ice volume. Neutrinos generated within (0, dr).
- **dz** [float] Height of the ice volume in the z-direction. Neutrinos generated within (-dz, 0).
- **get\_energy** [function] Function returning energy (GeV) of the neutrinos by successive function calls
- **ratio** [ndarary] (Normalized) flavor ratio of neutrinos to be generated. Of the form [electron, muon, tau] neutrino fractions.

**interaction\_model** [Interaction] Class to use to describe interactions of the generated particles.

### **Methods**

create_event()	Generate a neutrino event in the ice volume.
	Continued on next page

Table 55 -	continued	from	previous	page
14010 00	00111111000		piotioac	223

Get the direction of the next particle to be generated.
Get the intersections of the particle path with the ice
volume edges.
Get the particle type of the next particle to be gener-
ated.
Get the vertex of the next particle to be generated.
Get the weighting factors to be applied to the parti-
cle.

# pyrex.generation.RectangularGenerator

Class to generate neutrino vertices in a rectangular ice volume.

Generates neutrinos in a box with given width, length, and height.

#### **Parameters**

- **dx** [float] Width of the ice volume in the x-direction. Neutrinos generated within (-dx / 2, dx / 2).
- **dy** [float] Length of the ice volume in the y-direction. Neutrinos generated within (-dy / 2, dy / 2).
- **dz** [float] Height of the ice volume in the z-direction. Neutrinos generated within (-dz, 0).
- **energy** [float or function] Energy (GeV) of the neutrinos. If float, all neutrinos have the same constant energy. If function, neutrinos are generated with the energy returned by successive function calls.
- **flavor\_ratio** [array\_like, optional] Flavor ratio of neutrinos to be generated. Of the form [electron, muon, tau] neutrino fractions.
- **interaction\_model** [optional] Class to use to describe interactions of the generated particles. Should inherit from (or behave like) the base Interaction class.

# See also:

pyrex.particle.Interaction Base class for describing neutrino interaction attributes.

- **count** [int] Number of neutrinos produced by the generator, including those not returned due to Earth shadowing or other effects.
- **dx** [float] Width of the ice volume in the x-direction. Neutrinos generated within (-dx / 2, dx / 2).
- **dy** [float] Length of the ice volume in the y-direction. Neutrinos generated within (-dy / 2, dy / 2).
- **dz** [float] Height of the ice volume in the z-direction. Neutrinos generated within (-dz, 0).
- **get\_energy** [function] Function returning energy (GeV) of the neutrinos by successive function calls.
- **ratio** [ndarary] (Normalized) flavor ratio of neutrinos to be generated. Of the form [electron, muon, tau] neutrino fractions.

**interaction\_model** [Interaction] Class to use to describe interactions of the generated particles.

### **Methods**

create_event()	Generate a neutrino event in the ice volume.
<pre>get_direction()</pre>	Get the direction of the next particle to be generated.
<pre>get_exit_points(particle)</pre>	Get the intersections of the particle path with the ice
	volume edges.
<pre>get_particle_type()</pre>	Get the particle type of the next particle to be gener-
	ated.
get_vertex()	Get the vertex of the next particle to be generated.
get_weights(particle)	Get the weighting factors to be applied to the parti-
	cle.

# pyrex.generation.CylindricalShadowGenerator

Class to generate neutrino vertices in a cylindrical ice volume.

Generates neutrinos in a cylinder with given radius and height. Accounts for Earth shadowing by comparing the neutrino interaction length to the material thickness of the Earth along the neutrino path, and rejecting particles which would interact before reaching the vertex.

#### **Parameters**

- **dr** [float] Radius of the ice volume. Neutrinos generated within (0, dr).
- **dz** [float] Height of the ice volume in the z-direction. Neutrinos generated within (-dz, 0).
- energy [float or function] Energy (GeV) of the neutrinos. If float, all neutrinos have the same constant energy. If function, neutrinos are generated with the energy returned by successive function calls.
- **flavor\_ratio** [array\_like, optional] Flavor ratio of neutrinos to be generated. Of the form [electron, muon, tau] neutrino fractions.
- **interaction\_model** [optional] Class to use to describe interactions of the generated particles. Should inherit from (or behave like) the base Interaction class.

### See also:

pyrex.particle.Interaction Base class for describing neutrino interaction attributes.

- **count** [int] Number of neutrinos produced by the generator, including those not returned due to Earth shadowing or other effects.
- dr [float] Radius of the ice volume. Neutrinos generated within (0, dr).
- **dz** [float] Height of the ice volume in the z-direction. Neutrinos generated within (-dz, 0).
- **get\_energy** [function] Function returning energy (GeV) of the neutrinos by successive function calls.
- **ratio** [ndarary] (Normalized) flavor ratio of neutrinos to be generated. Of the form [electron, muon, tau] neutrino fractions.

**interaction\_model** [Interaction] Class to use to describe interactions of the generated particles.

### **Methods**

create_event()	Generate a neutrino event in the ice volume.
<pre>get_direction()</pre>	Get the direction of the next particle to be generated.
<pre>get_exit_points(particle)</pre>	Get the intersections of the particle path with the ice
	volume edges.
<pre>get_particle_type()</pre>	Get the particle type of the next particle to be gener-
	ated.
<pre>get_vertex()</pre>	Get the vertex of the next particle to be generated.
get_weights(particle)	Get the weighting factors to be applied to the parti-
	cle.

### pyrex.generation.RectangularShadowGenerator

Class to generate neutrino vertices in a rectangular ice volume.

Generates neutrinos in a box with given width, length, and height. Accounts for Earth shadowing by comparing the neutrino interaction length to the material thickness of the Earth along the neutrino path, and rejecting particles which would interact before reaching the vertex. Note the subtle difference in x and y ranges compared to the z range.

#### **Parameters**

- **dx** [float] Width of the ice volume in the x-direction. Neutrinos generated within (-dx / 2, dx / 2).
- **dy** [float] Length of the ice volume in the y-direction. Neutrinos generated within (-dy / 2, dy / 2).
- **dz** [float] Height of the ice volume in the z-direction. Neutrinos generated within (-dz, 0).
- **energy** [float or function] Energy (GeV) of the neutrinos. If float, all neutrinos have the same constant energy. If function, neutrinos are generated with the energy returned by successive function calls.
- **flavor\_ratio** [array\_like, optional] Flavor ratio of neutrinos to be generated. Of the form [electron, muon, tau] neutrino fractions.
- **interaction\_model** [optional] Class to use to describe interactions of the generated particles. Should inherit from (or behave like) the base Interaction class.

# See also:

pyrex.particle.Interaction Base class for describing neutrino interaction attributes.

- **count** [int] Number of neutrinos produced by the generator, including those not returned due to Earth shadowing or other effects.
- **dx** [float] Width of the ice volume in the x-direction. Neutrinos generated within (-dx / 2, dx / 2).

- **dy** [float] Length of the ice volume in the y-direction. Neutrinos generated within (-dy / 2, dy / 2).
- **dz** [float] Height of the ice volume in the z-direction. Neutrinos generated within (-dz, 0).
- **get\_energy** [function] Function returning energy (GeV) of the neutrinos by successive function calls.

**ratio** [ndarary] (Normalized) flavor ratio of neutrinos to be generated. Of the form [electron, muon, tau] neutrino fractions.

interaction\_model [Interaction] Class to use to describe interactions of the generated particles.

### **Methods**

create_event()	Generate a neutrino event in the ice volume.
<pre>get_direction()</pre>	Get the direction of the next particle to be generated.
get_exit_points(particle)	Get the intersections of the particle path with the ice
	volume edges.
<pre>get_particle_type()</pre>	Get the particle type of the next particle to be gener-
	ated.
get_vertex()	Get the vertex of the next particle to be generated.
get_weights(particle)	Get the weighting factors to be applied to the parti-
	cle.

# pyrex.generation.ShadowGenerator

class pyrex.generation.ShadowGenerator  $(dx, dy, dz, energy, flavor\_ratio=(1, 1, 1), interaction\_model=<class 'pyrex.particle.CTWInteraction'>)$ 

### **Methods**

create_event()	Generate a neutrino event in the ice volume.
<pre>get_direction()</pre>	Get the direction of the next particle to be generated.
<pre>get_exit_points(particle)</pre>	Get the intersections of the particle path with the ice
	volume edges.
<pre>get_particle_type()</pre>	Get the particle type of the next particle to be gener-
	ated.
<pre>get_vertex()</pre>	Get the vertex of the next particle to be generated.
get_weights(particle)	Get the weighting factors to be applied to the parti-
	cle.

# pyrex.generation.ListGenerator

class pyrex.generation.ListGenerator(events, loop=True)

Class to generate neutrino events from a list.

Generates events by simply pulling them from a list of Event objects. By default returns to the start of the list once the end is reached, but can optionally fail after reaching the list's end.

# Parameters

**events** [Event, or list of Event] List of Event objects to draw from. If only a single Event object is given, creates a list of that event alone.

**loop** [boolean, optional] Whether or not to return to the start of the list after throwing the last Event. If False, raises an error if trying to throw after the last Event.

### See also:

pyrex.Event Class for storing a tree of Particle objects representing an event.
pyrex.Particle Class for storing particle attributes.

#### **Attributes**

**count** [int] Number of neutrinos produced by the generator.

**events** [list of Event] List to draw Event objects from, sequentially.

**loop** [boolean] Whether or not to loop through the list more than once.

### **Methods**

create\_event()

Generate a neutrino event.

# pyrex.generation.NumpyFileGenerator

Generates neutrinos by pulling their attributes from a (list of) .npz file(s). Each file must have four to six arrays, containing the id values, vertices, directions, energies, and optional interaction types and weights respectively so the first particle will have properties given by the first elements of these arrays. Tries to smartly figure out which array is which based on their names, but if the arrays are unnamed, assumes they are in the order used above.

#### **Parameters**

**files** [str or list of str] List of file names containing neutrino information. If only a single file name is provided, creates a list with that file alone.

**interaction\_model** [optional] Class used to describe the interactions of the stored particles.

**Warning:** This generator only supports Event objects containing a single Particle object. There is currently no way to read from files where an Event contains mutliple Particle objects with some dependencies.

### See also:

pyrex.particle.Interaction Base class for describing neutrino interaction attributes.
pyrex.Event Class for storing a tree of Particle objects representing an event.
pyrex.Particle Class for storing particle attributes.

**files** [list of str] List of file names containing neutrino information.

ids [ndarray] Array of particle id values from the current file.

vertices [ndarray] Array of neutrino vertices from the current file.

directions [ndarray] Array of neutrino directions from the current file.

energies [ndarray] Array of neutrino energies from the current file.

**interactions** [ndarray] Array of interaction types from the current file.

weights [ndarray] Array of neutrino weights from the current file.

#### **Methods**

create\_event()

Generate a neutrino.

### pyrex.generation.FileGenerator

Class to generate neutrino events from simulation file(s).

Generates neutrinos by pulling their attributes from a (list of) simulation output file(s). Designed to make reproducing simulations easier.

#### **Parameters**

**files** [str or list of str] List of file names containing neutrino event information. If only a single file name is provided, creates a list with that file alone.

**slice\_range** [int, optional] Number of events to load into memory at a time from the files. Increasing this value should result in an improvement in speed, while decreasing this value should result in an improvement in memory consumption.

interaction\_model [optional] Class used to describe the interactions of the stored particles.

**Warning:** This generator only supports Event objects containing a single level of Particle objects. Any dependencies among Particle objects will be ignored and they will all appear in the root level.

### See also:

pyrex.particle.Interaction Base class for describing neutrino interaction attributes.

pyrex. Event Class for storing a tree of Particle objects representing an event.

pyrex.Particle Class for storing particle attributes.

#### **Attributes**

**count** [int] Number of neutrinos produced by the generator.

files [list of str] List of file names containing neutrino information.

# **Methods**

create\_event()

Generate a neutrino.

# 6.2.10 Simulation Kernel (pyrex.kernel)

Module for the simulation kernel.

The simulation kernel is responsible for running through the simulation chain by controlling classes and objects which will independently produce neutrinos, create corresponding signals, propagate the signals to antennas, and handle antenna processing of the signals.

EventKernel(generator, antennas[, ...])

High-level kernel for controlling event simulation.

# pyrex.kernel.EventKernel

High-level kernel for controlling event simulation.

The kernel is responsible for handling the classes and objects which control the major simulation steps: particle creation, signal production, signal propagation, and antenna response. The modular kernel structure allows for easy switching of the classes or objects which handle any of the simulation steps.

### **Parameters**

**generator** A particle generator to create neutrino events.

antennas An iterable object consisting of antenna objects which can receive and store signals.

**ice\_model** [optional] An ice model describing the ice surrounding the antennas.

**ray\_tracer** [optional] A ray tracer capable of propagating signals from the neutrino vertex to the antenna positions.

**signal\_model** [optional] A signal class which generates signals based on the particle.

**signal\_times** [array\_like, optional] The array of times over which the neutrino signal should be generated.

event\_writer [File, optional] A file object to be used for writing data output.

**triggers** [function or dict, optional] A function or dictionary with function values representing trigger conditions of the detector. If a dictionary, must have a "global" key with its value representing the global detector trigger.

### See also:

```
pyrex. Event Class for storing a tree of Particle objects representing an event.
```

pyrex.Particle Class for storing particle attributes.

pyrex. IceModel Class describing the ice at the south pole.

pyrex. RayTracer Class for calculating the ray-trace solutions between points.

pyrex. AskaryanSignal Class for generating Askaryan signals according to ARVZ parameterization.
pyrex. File Class for reading or writing data files.

#### **Notes**

The kernel is designed to be modular so individual parts of the simulation chain can be exchanged. In order to interchange the pieces, their classes require the following at a minimum:

The particle generator generator must have a create\_event method which takes no arguments and returns a *Event* object consisting of *Particle* objects with vertex, direction, energy, and weight attributes.

The antenna iterable *antennas* must yield each antenna object once when iterating directly over *antennas*. Each antenna object must have a position attribute and a receive method which takes a signal object as its first argument, and ndarray objects as direction and polarization keyword arguments.

The *ice\_model* must have an index method returning the index of refraction given a (negative-valued) depth, and it must support anything required of it by the *ray\_tracer*.

The ray\_tracer must be initialized with the particle vertex and an antenna position as its first two arguments, and the ice\_model of the kernel as the ice\_model keyword argument. The ray tracer must also have exists and solutions attributes, the first of which denotes whether any paths exist between the given points and the second of which is an iterable revelaing each path between the points. These paths must have emitted\_direction, received\_direction, and path\_length attributes, as well as a propagate method which takes a signal object and applies the propagation effects of the path in-place to that object.

The *signal\_model* must be initialized with the *signal\_times* array, a *Particle* object from the *Event*, the viewing\_angle and viewing\_distance according to the *ray\_tracer*, and the *ice\_model*. The object created should be a *Signal* object with times and values attributes representing the time-domain Askaryan signal produced by the *Particle*.

#### Attributes

gen The particle generator responsible for particle creation.

**antennas** The iterable of antennas responsible for handling applying their response and storing the resulting signals.

ice The ice model describing the ice containing the antennas.

**ray\_tracer** The ray tracer responsible for signal propagation through the *ice*.

**signal\_model** The signal class to use to generate signals based on the particle.

**signal\_times** The array of times over which the neutrino signal should be generated.

writer The file object to be used for writing data output.

**triggers** The trigger condition(s) of the detector.

### **Methods**

event()	Create a neutrino event and run it through the simu-
	lation chain.

# 6.2.11 Data File I/O (pyrex.io)

Module containing classes for reading and writing data files.

Includes reader and writer for hdf5 data files, as well as base reader and writer classes which can be extended to read and write other file formats.

File	Class for reading or writing data files.
HDF5Reader(filename[, slice_range])	Class for reading data from an hdf5 file.
<pre>HDF5Writer(filename[, mode,])</pre>	Class for writing data to an hdf5 file.

# pyrex.io.File

### class pyrex.io.File

Class for reading or writing data files.

Works as a context manager and allows for reading or writing simulation/real data or analysis-level data to the given file. Chooses the appropriate class for handling the given file type.

#### **Parameters**

**filename** [str] File name to open in the given write mode.

mode [str, optional] Mode with which to open the file.

\*\*kwargs Keyword arguments passed on to the appropriate file handler.

#### See also:

HDF5Reader Class for reading data from an hdf5 file.

HDF5Writer Class for writing data to an hdf5 file.

#### **Attributes**

**readers** [dict] Dictionary with file extensions as keys and values with the corresponding classes used to handle reading of those file types.

writers [dict] Dictionary with file extensions as keys and values with the corresponding classes used to handle writing of those file types.

## pyrex.io.HDF5Reader

class pyrex.io.HDF5Reader (filename, slice\_range=10)

Class for reading data from an hdf5 file.

Works as a context manager and allows for reading simulation/real data or analysis-level data from the given file.

#### **Parameters**

filename [str] File name to open in read mode.

**slice\_range** [int, optional] Number of events to include in each slice when iterating the file. Increasing this value should result in an improvement in speed, while decreasing this value should result in an improvement in memory consumption.

#### **Attributes**

**filename** [str] Name of the file (to be) opened.

is\_open Boolean of whether the file is currently open.

**antenna\_info** Antenna data from the file.

file metadata Metadata from the file's metadata datasets.

#### **Methods**

close()	Close the hdf5 file.
get_waveforms([event_id, antenna_id,])	Get waveform data from the file.
open()	Open the hdf5 file for reading.

# pyrex.io.HDF5Writer

class pyrex.io.HDF5Writer (filename, mode='x', write\_particles=True, write\_triggers=True, write\_antenna\_triggers=False, write\_rays=True, write\_noise=False, write waveforms=False, require trigger=True)

Class for writing data to an hdf5 file.

Works as a context manager and allows for writing simulation/real data or analysis-level data to the given file.

#### **Parameters**

**filename** [str] File name to open in the given write mode.

**mode** [str, optional] Mode with which to open the file. 'w' writes to the file, overwriting any existing data. 'x' writes to the file, failing if the file exists. 'a' appends to the file, creating if the file doesn't exist. 'r+' appends to the file, failing if the file doesn't exist.

write\_particles [bool, optional] Whether to write particle metadata when adding event data to the file.

write\_waveforms [bool, optional] Whether to write waveform data when adding event data to the file.

write\_triggers [bool, optional] Whether to write trigger data when adding event data to the file.

**require\_trigger** [bool or list of str, optional] Whether to write data only when the detector is triggered. If False all data will be written for every event. If True most data will be written only on a detector trigger (particle metadata and trigger data will still be written for every event). If a list of strings is provided, then the specified data types will be written only on a detector trigger and all other data types will be written for every event.

#### **Other Parameters**

write\_antenna\_triggers [bool, optional] Whether to write trigger data of individual antennas when adding event data to the file.

write\_rays [bool, optional] Whether to write ray metadata when adding event data to the file.

write\_noise [bool, optional] Whether to write noise-generation metadata when adding event data to the file.

#### **Attributes**

**filename** [str] Name of the file (to be) opened.

**is\_open** Boolean of whether the file is currently open.

**has\_detector** Boolean of whether the file has a linked detector.

### **Methods**

Add the data from an event to the file.
Write the given start and length indices to the event
indices dataset.
Writes the given <i>metadata</i> to the analysis metadata
group at name.
Writes the given <i>metadata</i> to the general file meta-
data group.
Close the hdf5 file.
Create the given analysis dataset in the file.
Create the given analysis group in the file.
Create the given analysis metadata group in the file.
Open the hdf5 file for writing.
Link the given <i>detector</i> to the file.

# 6.3 Included Custom Sub-Packages

# 6.3.1 Askaryan Radio Array (pyrex.custom.ara)

The ARA module contains classes for antennas and detectors as found or proposed for the ARA project.

The *HpolAntenna* and *VpolAntenna* classes are models of ARA Hpol and Vpol antennas using data lifted from AraSim. They use the antenna directional gains in data/ARA\_dipoletest1\_output\_MY\_fixed.txt and data/ARA\_bicone6in\_output\_MY\_fixed.txt respectively, and the electronics gains in data/ARA\_Electronics\_TotalGain\_TwoFilters.txt. The trigger condition of these antennas is based on a comparison of the maximum value of the tunnel-diode-convolved waveforms with the rms value of a tunnel-diode-convolved noise waveform.

The ARAString class creates a string of alternating HpolAntenna and VpolAntenna ojbects, as in a typical ARA station. The PhasedArrayString class implements a more densely-packed string of antennas which trigger based on a threshold trigger on the best beam-formed combination of the antenna waveforms. The RegularStation class creates a station at the given position with 4 (or another given number) strings spaced evenly around the station center. The AlbrechtStation class (proposed by Albrecht Karle) creates two phased array strings at the station center, one of VpolAntenna objects and the other of HpolAntenna objects, as well as 3 (or another given number) outrigger strings spaced evenly around the station center. The HexagonalGrid class creates a hexagonal grid of stations, spiralling outward from the center.

# **Default Package Imports**

<pre>HpolAntenna(name, position, power_threshold)</pre>	ARA Hpol ("quad-slot") antenna system with front-end
	processing.
VpolAntenna(name, position, power_threshold)	ARA Vpol ("bicone" or "birdcage") antenna system
	with front-end processing.
ARAString(x, y[, antennas_per_string,])	String of ARA Hpol and Vpol antennas.
PhasedArrayString $(x, y[,])$	Phased string of closely-packed antennas.
RegularStation(x, y[, strings_per_station,])	Station geometry with strings evenly spaced radially
	around the center.
	Continued on next page

# Table 68 – continued from previous page

AlbrechtStation(x, y[, station_diameter,])	Station geometry with center phased string and some outrigger strings.
HexagonalGrid([stations,])	Hexagonal grid of stations or strings.

# pyrex.custom.ara.HpolAntenna

ARA Hpol ("quad-slot") antenna system with front-end processing.

Applies as the front end a filter representing the full ARA electronics chain (including amplification) and signal clipping. Additionally provides a method for passing a signal through the tunnel diode.

#### **Parameters**

name [str] Name of the antenna.

**position** [array\_like] Vector position of the antenna.

power\_threshold [float] Power threshold for trigger condition. Antenna triggers if a signal passed through the tunnel diode exceeds this threshold times the noise RMS of the tunnel diode.

**amplification** [float, optional] Amplification to be applied to the signal pre-clipping. Note that the usual ARA electronics amplification is already applied without this.

**amplifier\_clipping** [float, optional] Voltage (V) above which the amplified signal is clipped (in positive and negative values).

**noisy** [boolean, optional] Whether or not the antenna should add noise to incoming signals.

unique\_noise\_waveforms [int, optional] The number of expected noise waveforms needed for each received signal to have its own noise.

### See also:

ARAAntennaSystem Antenna system extending base ARA antenna with front-end processing.

**HpolBase** Antenna class to be used for ARA Hpol antennas.

#### **Attributes**

antenna [Antenna] Antenna object extended by the front end.

**name** [str] Name of the antenna.

**position** [array\_like] Vector position of the antenna.

power\_threshold [float] Power threshold for trigger condition. Antenna triggers if a signal passed through the tunnel diode exceeds this threshold times the noise RMS of the tunnel diode.

**amplification** [float] Amplification to be applied to the signal pre-clipping. Note that the usual ARA electronics amplification is already applied without this.

**amplifier\_clipping** [float] Voltage (V) above which the amplified signal is clipped (in positive and negative values).

**is\_hit** Boolean of whether the antenna system has been triggered.

**signals** The signals received by the antenna with front-end processing.

waveforms The antenna system signal + noise for each triggered hit.

**all\_waveforms** The antenna system signal + noise for all hits.

### **Methods**

clear([reset_noise])	Reset the antenna system to an empty state.
front_end(signal)	Apply front-end processes to a signal and return the
	output.
full_waveform(times)	Signal + noise for the antenna system for the given
	times.
<pre>interpolate_filter(frequencies)</pre>	Generate interpolated filter values for given frequen-
	cies.
is_hit_during(times)	Check if the antenna system is triggered in a time
	range.
make_noise(times)	Creates a noise signal over the given times.
receive(signal[, direction, polarization,])	Process and store an incoming signal.
<pre>set_orientation([z_axis, x_axis])</pre>	Sets the orientation of the antenna system.
setup_antenna([center_frequency, bandwidth,	Setup the antenna by passing along its init argu-
])	ments.
trigger(signal)	Check if the antenna system triggers on a given sig-
	nal.
tunnel_diode(signal)	Calculate a signal as processed by the tunnel diode.

# pyrex.custom.ara.VpolAntenna

ARA Vpol ("bicone" or "birdcage") antenna system with front-end processing.

Applies as the front end a filter representing the full ARA electronics chain (including amplification) and signal clipping. Additionally provides a method for passing a signal through the tunnel diode.

# **Parameters**

name [str] Name of the antenna.

**position** [array like] Vector position of the antenna.

power\_threshold [float] Power threshold for trigger condition. Antenna triggers if a signal passed through the tunnel diode exceeds this threshold times the noise RMS of the tunnel diode.

**amplification** [float, optional] Amplification to be applied to the signal pre-clipping. Note that the usual ARA electronics amplification is already applied without this.

**amplifier\_clipping** [float, optional] Voltage (V) above which the amplified signal is clipped (in positive and negative values).

**noisy** [boolean, optional] Whether or not the antenna should add noise to incoming signals.

**unique\_noise\_waveforms** [int, optional] The number of expected noise waveforms needed for each received signal to have its own noise.

See also:

**ARAAntennaSystem** Antenna system extending base ARA antenna with front-end processing.

**VpolBase** Antenna class to be used for ARA Vpol antennas.

### **Attributes**

antenna [Antenna object extended by the front end.

name [str] Name of the antenna.

**position** [array\_like] Vector position of the antenna.

power\_threshold [float] Power threshold for trigger condition. Antenna triggers if a signal passed through the tunnel diode exceeds this threshold times the noise RMS of the tunnel diode.

**amplification** [float] Amplification to be applied to the signal pre-clipping. Note that the usual ARA electronics amplification is already applied without this.

**amplifier\_clipping** [float] Voltage (V) above which the amplified signal is clipped (in positive and negative values).

**is\_hit** Boolean of whether the antenna system has been triggered.

**signals** The signals received by the antenna with front-end processing.

waveforms The antenna system signal + noise for each triggered hit.

**all\_waveforms** The antenna system signal + noise for all hits.

### **Methods**

7 ([ , , ])	D +11 + + + + + + + + + + + + + + + + +
clear([reset_noise])	Reset the antenna system to an empty state.
front_end(signal)	Apply front-end processes to a signal and return the
	output.
full_waveform(times)	Signal + noise for the antenna system for the given
	times.
<pre>interpolate_filter(frequencies)</pre>	Generate interpolated filter values for given frequen-
	cies.
is_hit_during(times)	Check if the antenna system is triggered in a time
	range.
make_noise(times)	Creates a noise signal over the given times.
receive(signal[, direction, polarization,])	Process and store an incoming signal.
<pre>set_orientation([z_axis, x_axis])</pre>	Sets the orientation of the antenna system.
setup_antenna([center_frequency, bandwidth,	Setup the antenna by passing along its init argu-
])	ments.
trigger(signal)	Check if the antenna system triggers on a given sig-
	nal.
tunnel_diode(signal)	Calculate a signal as processed by the tunnel diode.

### pyrex.custom.ara.ARAString

String of ARA Hpol and Vpol antennas.

Sets the positions of antennas on string based on the parameters. Once the antennas have been built with build\_antennas, the object can be directly iterated over to iterate over the antennas (as if the object were

just a list of the antennas).

#### **Parameters**

- **x** [float] Cartesian x-position (m) of the string.
- y [float] Cartesian y-position (m) of the string.

antennas\_per\_string [float, optional] Total number of antennas to be placed on the string.

antenna\_separation [float or list of float, optional] The vertical separation (m) of antennas on the string. If float, all antennas are separated by the same constant value. If list, the separations in the list are the separations of neighboring antennas starting from the lowest up to the highest.

**lowest\_antenna** [float, optional] The Cartesian z-position (m) of the lowest antenna on the string.

#### Raises

**ValueError** If test\_antenna\_positions is True and an antenna is found to be above the ice surface.

#### See also:

pyrex.custom.ara.HpolAntenna ARA Hpol ("quad-slot") antenna system with front-end processing.
pyrex.custom.ara.VpolAntenna ARA Vpol ("bicone" or "birdcage") antenna system with front-end processing.

#### **Notes**

This class is designed to be the lowest subset level of a detector. It can (and should) be used for the subsets of some other Detector subclass to build up a full detector. Then when its "parent" is iterated, the instances of this class will be iterated as though they were all part of one flat list.

# Attributes

**antenna\_positions** [list] List (potentially with sub-lists) of the positions of the antennas generated by the set\_positions method.

subsets [list] List of the antenna or detector objects which make up the detector.

**test\_antenna\_positions** [boolean] Class attribute for whether or not an error should be raised if antenna positions are found above the surface of the ice (where simulation behavior is ill-defined). Defaults to True.

#### **Methods**

build_antennas(power_threshold[,])	Creates antenna objects at the set antenna positions.
<pre>clear([reset_noise])</pre>	Reset the detector to an empty state.
set_positions(x, y[, antennas_per_string,])	Generates antenna positions along the string.
triggered([antenna_requirement,])	Check if the string is triggered based on its current
	state.

### pyrex.custom.ara.PhasedArrayString

```
class pyrex.custom.ara.PhasedArrayString (x, y, antennas\_per\_string=10, antenna\_separation=1, lowest\_antenna=-100, antenna\_type=<class 'pyrex.custom.ara.antenna.VpolAntenna'>)
```

Phased string of closely-packed antennas.

Sets the positions of antennas on string based on the parameters. Once the antennas have been built with build\_antennas, the object can be directly iterated over to iterate over the antennas (as if the object were just a list of the antennas).

#### **Parameters**

- **x** [float] Cartesian x-position (m) of the string.
- y [float] Cartesian y-position (m) of the string.

antennas\_per\_string [float, optional] Total number of antennas to be placed on the string.

antenna\_separation [float or list of float, optional] The vertical separation (m) of antennas on the string. If float, all antennas are separated by the same constant value. If list, the separations in the list are the separations of neighboring antennas starting from the lowest up to the highest.

**lowest\_antenna** [float, optional] The Cartesian z-position (m) of the lowest antenna on the string.

antenna\_type [optional] The class to be used to create the antenna objects.

#### Raises

ValueError If test\_antenna\_positions is True and an antenna is found to be above the ice surface.

#### See also:

pyrex.custom.ara.HpolAntenna ARA Hpol ("quad-slot") antenna system with front-end processing.
pyrex.custom.ara.VpolAntenna ARA Vpol ("bicone" or "birdcage") antenna system with front-end processing.

### **Notes**

This class is designed to be the lowest subset level of a detector. It can (and should) be used for the subsets of some other Detector subclass to build up a full detector. Then when its "parent" is iterated, the instances of this class will be iterated as though they were all part of one flat list.

#### **Attributes**

antenna\_type The class to be used to create the antenna objects.

**antenna\_positions** [list] List (potentially with sub-lists) of the positions of the antennas generated by the set\_positions method.

**subsets** [list] List of the antenna or detector objects which make up the detector.

**test\_antenna\_positions** [boolean] Class attribute for whether or not an error should be raised if antenna positions are found above the surface of the ice (where simulation behavior is ill-defined). Defaults to True.

### **Methods**

build_antennas(power_threshold[,])	Creates antenna objects at the set antenna positions.
<pre>clear([reset_noise])</pre>	Reset the detector to an empty state.
set_positions(x, y[, antennas_per_string,])	Generates antenna positions along the string.
triggered(beam_threshold[, delays, angles,])	Check if the string is triggered based on its current
	state.

### pyrex.custom.ara.RegularStation

Station geometry with strings evenly spaced radially around the center.

Sets the positions of strings around the station based on the parameters. Supports any string type and passes extra keyword arguments on to the string class. Once the antennas have been built with build\_antennas, the object can be directly iterated over to iterate over the antennas (as if the object were just a list of the antennas).

#### **Parameters**

- **x** [float] Cartesian x-position (m) of the station.
- y [float] Cartesian y-position (m) of the station.

**strings\_per\_station** [float, optional] Number of strings to be placed evenly around the station.

station\_diameter [float, optional] Diameter (m) of the circle around which strings are placed.

**string\_type** [optional] Class to be used for creating string objects for *subsets*.

\*\*string\_kwargs Keyword arguments to be passed on to the \_\_init\_\_ methods of the string\_type class.

#### Raises

**ValueError** If test\_antenna\_positions is True and an antenna is found to be above the ice surface.

### See also:

pyrex.custom.ara.HpolAntenna ARA Hpol ("quad-slot") antenna system with front-end processing.
pyrex.custom.ara.VpolAntenna ARA Vpol ("bicone" or "birdcage") antenna system with front-end processing.

**ARAString** String of ARA Hpol and Vpol antennas.

#### **Notes**

This class is designed to have string-like objects (which are subclasses of Detector) as its *subsets*. Then whenver an object of this class is iterated, all the antennas of its strings will be yielded as in a 1D list.

# Attributes

**antenna\_positions** [list] List (potentially with sub-lists) of the positions of the antennas generated by the set\_positions method.

subsets [list] List of the antenna or detector objects which make up the detector.

**test\_antenna\_positions** [boolean] Class attribute for whether or not an error should be raised if antenna positions are found above the surface of the ice (where simulation behavior is ill-defined). Defaults to True.

#### **Methods**

build_antennas(*args, **kwargs)	Creates antenna objects at the set antenna positions.
clear([reset_noise])	Reset the detector to an empty state.
$set_positions(x, y[, strings_per_station,])$	Generates antenna positions around the station.
triggered([polarized_antenna_requirement,	Check if the station is triggered based on its current
])	state.

### pyrex.custom.ara.AlbrechtStation

```
class pyrex.custom.ara.AlbrechtStation (x, y, station\_diameter=40, hpol\_phased\_antennas=10, vpol\_phased\_antennas=10, hpol\_phased\_separation=1, vpol\_phased\_separation=1, hpol\_phased\_lowest=-49, vpol\_phased\_lowest=-69, outrigger\_strings\_per\_station=3, outrigger\_string\_type=<class 'pyrex.custom.ara.detector.ARAString'>, **outrigger\_string\_kwargs)
```

Station geometry with center phased string and some outrigger strings.

Station geometry proposed by Albrecht with a phased array string of each polarization at the station center, plus a number of outrigger strings evenly spaced radially around the station center. Sets the positions of strings around the station based on the parameters. Supports any string type and passes extra keyword arguments on to the string class. Once the antennas have been built with build\_antennas, the object can be directly iterated over to iterate over the antennas (as if the object were just a list of the antennas).

# Parameters

- **x** [float] Cartesian x-position (m) of the station.
- y [float] Cartesian y-position (m) of the station.
- **station\_diameter** [float, optional] Diameter (m) of the circle around which outrigger strings are placed.
- **hpol\_phased\_antennas** [float, optional] Number of Hpol phased antennas for the center string.
- **vpol\_phased\_antennas** [float, optional] Number of Vpol phased antennas for the center string.
- **hpol\_phased\_separation** [float or list of float, optional] Antenna separation (m) for the phased Hpol antennas.
- **vpol\_phased\_separation** [float or list of float, optional] Antenna separation (m) for the phased Vpol antennas.
- hpol\_phased\_lowest [float, optional] Cartesian z-position (m) of the lowest phased Hpol antenna.
- vpol\_phased\_lowest [float, optional] Cartesian z-position (m) of the lowest phased Vpol antenna.

**outrigger\_strings\_per\_station** [float, optional] Number of outrigger strings to be placed evenly around the station.

**outrigger\_string\_type** [optional] Class to be used for creating outrigger string objects for *sub-sets*.

\*\*outrigger\_string\_kwargs Keyword arguments to be passed on to the \_\_init\_\_ methods of the *outrigger\_string\_type* class. The default values for antennas\_per\_string, antenna\_separation, and lowest\_antenna are altered for this station geometry.

#### Raises

**ValueError** If test\_antenna\_positions is True and an antenna is found to be above the ice surface.

#### See also:

pyrex.custom.ara.HpolAntenna ARA Hpol ("quad-slot") antenna system with front-end processing.
pyrex.custom.ara.VpolAntenna ARA Vpol ("bicone" or "birdcage") antenna system with front-end processing.

**ARAString** String of ARA Hpol and Vpol antennas.

**PhasedArrayString** Phased string of closely-packed antennas.

#### **Notes**

This class is designed to have string-like objects (which are subclasses of Detector) as its *subsets*. Then whenver an object of this class is iterated, all the antennas of its strings will be yielded as in a 1D list.

### Attributes

**antenna\_positions** [list] List (potentially with sub-lists) of the positions of the antennas generated by the set\_positions method.

subsets [list] List of the antenna or detector objects which make up the detector.

**test\_antenna\_positions** [boolean] Class attribute for whether or not an error should be raised if antenna positions are found above the surface of the ice (where simulation behavior is ill-defined). Defaults to True.

### Methods

build_antennas(*args, **kwargs)	Creates antenna objects at the set antenna positions.
clear([reset_noise])	Reset the detector to an empty state.
set_positions(x, y[, station_diameter,])	Generates antenna positions around the station.
triggered(beam_threshold[,])	Check if the station is triggered based on its current
	state.

### pyrex.custom.ara.HexagonalGrid

Hexagonal grid of stations or strings.

Sets the positions of stations by spiralling outward in a hexagonal grid. Supports any station type (including

string types) and passes extra keyword arguments on to the station class. Once the antennas have been built with build\_antennas, the object can be directly iterated over to iterate over the antennas (as if the object were just a list of the antennas).

### **Parameters**

**stations** [float, optional] Number of stations to be placed.

**station\_separation** [float, optional] Distance (m) between adjacent stations.

station\_type [optional] Class to be used for creating station objects for subsets.

\*\*station\_kwargs Keyword arguments to be passed on to the \_\_init\_\_ methods of the station\_type class.

#### Raises

**ValueError** If test\_antenna\_positions is True and an antenna is found to be above the ice surface.

#### See also:

pyrex.custom.ara.HpolAntenna ARA Hpol ("quad-slot") antenna system with front-end processing.

pyrex.custom.ara.VpolAntenna ARA Vpol ("bicone" or "birdcage") antenna system with front-end processing.

**ARAString** String of ARA Hpol and Vpol antennas.

**RegularStation** Station geometry with strings evenly spaced radially around the center.

#### **Notes**

This class is designed to have station-like or string-like objects (which are subclasses of Detector) as its *subsets*. Then whenver an object of this class is iterated, all the antennas of its strings will be yielded as in a 1D list.

# Attributes

**antenna\_positions** [list] List (potentially with sub-lists) of the positions of the antennas generated by the set\_positions method.

subsets [list] List of the antenna or detector objects which make up the detector.

**test\_antenna\_positions** [boolean] Class attribute for whether or not an error should be raised if antenna positions are found above the surface of the ice (where simulation behavior is ill-defined). Defaults to True.

### **Methods**

build_antennas(*args, **kwargs)	Creates antenna objects at the set antenna positions.
clear([reset_noise])	Reset the detector to an empty state.
set_positions([stations,])	Generates antenna positions around the station.
triggered([station_requirement,])	Check if the detector is triggered based on its current
	state.

## **Individual Module APIs**

# Custom Antennas (pyrex.custom.ara.antenna)

Module containing customized antenna classes for ARA.

Many of the methods here mirror methods used in the antennas in AraSim, to ensure that AraSim results can be matched.

_read_directionality_data(filename)	Gather antenna directionality data from a data file.
_read_filter_data(filename)	Gather frequency-dependent filtering data from a data
	file.
ARAAntenna(position, center_frequency,)	Antenna class to be used for ARA antennas.
<pre>HpolBase(position, center_frequency,[,])</pre>	Antenna class to be used for ARA Hpol antennas.
VpolBase(position, center_frequency,[,])	Antenna class to be used for ARA Vpol antennas.
ARAAntennaSystem(base_antenna, name,[,	Antenna system extending base ARA antenna with
])	front-end processing.
HpolAntenna(name, position, power_threshold)	ARA Hpol ("quad-slot") antenna system with front-end
	processing.
VpolAntenna(name, position, power_threshold)	ARA Vpol ("bicone" or "birdcage") antenna system
	with front-end processing.
VpolBase(position, center_frequency,[,])  ARAAntennaSystem(base_antenna, name,[,])  HpolAntenna(name, position, power_threshold)	Antenna class to be used for ARA Vpol antennas.  Antenna system extending base ARA antenna with front-end processing.  ARA Hpol ("quad-slot") antenna system with front-end processing.  ARA Vpol ("bicone" or "birdcage") antenna system

# pyrex.custom.ara.antenna.\_read\_directionality\_data

pyrex.custom.ara.antenna.\_read\_directionality\_data (filename)

Gather antenna directionality data from a data file.

The data file should have columns for theta, phi, dB gain, non-dB gain, and phase (in degrees). This should be divided into sections for each frequency with a header line "freq: X MHz", optionally followed by a second line "trans: Y".

#### **Parameters**

filename [str] Name of the data file.

### Returns

dict Dictionary containing the data with keys (freq, theta, phi) and values (gain, phase).

set Set of unique frequencies appearing in the data keys.

# pyrex.custom.ara.antenna.\_read\_filter\_data

pyrex.custom.ara.antenna.\_read\_filter\_data(filename)

Gather frequency-dependent filtering data from a data file.

The data file should have columns for frequency, non-dB gain, and phase (in radians).

### **Parameters**

**filename** [str] Name of the data file.

### Returns

dict Dictionary containing the data with keys (freq) and values (gain, phase).

### pyrex.custom.ara.antenna.ARAAntenna

Antenna class to be used for ARA antennas.

Stores the attributes of an antenna as well as handling receiving, processing, and storing signals and adding noise.

#### **Parameters**

**position** [array\_like] Vector position of the antenna.

center\_frequency [float] Frequency (Hz) at the center of the antenna's frequency range.

bandwidth [float] Bandwidth (Hz) of the antenna.

**resistance** [float] The noise resistance (ohm) of the antenna. Used to calculate the RMS voltage of the antenna noise.

**orientation** [array\_like, optional] Vector direction of the z-axis of the antenna.

efficiency [float, optional] Antenna efficiency applied to incoming signal values.

**noisy** [boolean, optional] Whether or not the antenna should add noise to incoming signals.

**unique\_noise\_waveforms** [int, optional] The number of expected noise waveforms needed for each received signal to have its own noise.

**directionality\_data** [None or dict, optional] Dictionary containing data on the directionality of the antenna. If None, behavior is undefined.

**directionality\_freqs** [None or set, optional] Set of frequencies in the directionality data dict keys. If None, calculated automatically from *directionality\_data*.

### See also:

pyrex. Antenna Base class for antennas.

#### **Attributes**

**position** [array\_like] Vector position of the antenna.

**z\_axis** [ndarray] Vector direction of the z-axis of the antenna.

**x\_axis** [ndarray] Vector direction of the x-axis of the antenna.

antenna\_factor [float] Antenna factor used for converting fields to voltages.

efficiency [float] Antenna efficiency applied to incoming signal values.

**noisy** [boolean] Whether or not the antenna should add noise to incoming signals.

**unique\_noises** [int] The number of expected noise waveforms needed for each received signal to have its own noise.

**freq\_range** [array\_like] The frequency band in which the antenna operates (used for noise production).

**temperature** [float or None] The noise temperature (K) of the antenna. Used in combination with *resistance* to calculate the RMS voltage of the antenna noise.

**resistance** [float or None] The noise resistance (ohm) of the antenna. Used in combination with *temperature* to calculate the RMS voltage of the antenna noise.

**noise\_rms** [float or None] The RMS voltage (v) of the antenna noise. If not None, this value will be used instead of the RMS voltage calculated from the values of *temperature* and *resistance*.

signals [list of Signal] The signals which have been received by the antenna.

**is\_hit** Boolean of whether the antenna has been triggered.

waveforms Signal + noise (if noisy) for each triggered antenna hit.

**all\_waveforms** Signal + noise (if noisy) for all antenna hits.

#### **Methods**

clear([reset_noise])	Reset the antenna to an empty state.
directional_gain(theta, phi)	Calculate the (complex) directional gain of the an-
_5 \ \ \ \ \ \ \ \ \ \ \ \ \ \ \ \ \ \ \	tenna.
full_waveform(times)	Signal + noise (if noisy) for the given times.
generate_directionality_gains(theta,	Generate the (complex) frequency-dependent direc-
phi)	tional gains.
is_hit_during(times)	Check if the antenna is triggered in a time range.
make_noise(times)	Creates a noise signal over the given times.
polarization_gain(polarization, direction)	Calculate the (complex) polarization gain of the an-
	tenna.
receive(signal[, direction, polarization,])	Process and store an incoming signal.
response(frequencies)	Calculate the (complex) frequency response of the
	antenna.
set_orientation([z_axis, x_axis])	Sets the orientation of the antenna.
trigger(signal)	Check if the antenna triggers on a given signal.

### pyrex.custom.ara.antenna.HpolBase

class pyrex.custom.ara.antenna.HpolBase (position, center\_frequency, bandwidth, resistance, orientation=(0, 0, 1), efficiency=(0, 0, 1), efficiency=(0, 0, 1), orientation=(0, 0, 1), efficiency=(0, 0, 1), unique noise waveforms=(0, 0, 1)

Antenna class to be used for ARA Hpol antennas.

Stores the attributes of an antenna as well as handling receiving, processing, and storing signals and adding noise. Directionality data and antenna polarization gain specific to the Hpol ("quad-slot") antenna.

### **Parameters**

**position** [array\_like] Vector position of the antenna.

**center\_frequency** [float] Frequency (Hz) at the center of the antenna's frequency range.

**bandwidth** [float] Bandwidth (Hz) of the antenna.

**resistance** [float] The noise resistance (ohm) of the antenna. Used to calculate the RMS voltage of the antenna noise.

**orientation** [array\_like, optional] Vector direction of the z-axis of the antenna.

efficiency [float, optional] Antenna efficiency applied to incoming signal values.

**noisy** [boolean, optional] Whether or not the antenna should add noise to incoming signals.

**unique\_noise\_waveforms** [int, optional] The number of expected noise waveforms needed for each received signal to have its own noise.

#### See also:

**ARAAntenna** Antenna class to be used for ARA antennas.

#### **Attributes**

**position** [array\_like] Vector position of the antenna.

**z\_axis** [ndarray] Vector direction of the z-axis of the antenna.

**x\_axis** [ndarray] Vector direction of the x-axis of the antenna.

antenna\_factor [float] Antenna factor used for converting fields to voltages.

efficiency [float] Antenna efficiency applied to incoming signal values.

**noisy** [boolean] Whether or not the antenna should add noise to incoming signals.

unique\_noises [int] The number of expected noise waveforms needed for each received signal to have its own noise.

**freq\_range** [array\_like] The frequency band in which the antenna operates (used for noise production).

**temperature** [float or None] The noise temperature (K) of the antenna. Used in combination with *resistance* to calculate the RMS voltage of the antenna noise.

**resistance** [float or None] The noise resistance (ohm) of the antenna. Used in combination with *temperature* to calculate the RMS voltage of the antenna noise.

**noise\_rms** [float or None] The RMS voltage (v) of the antenna noise. If not None, this value will be used instead of the RMS voltage calculated from the values of *temperature* and *resistance*.

signals [list of Signal] The signals which have been received by the antenna.

is\_hit Boolean of whether the antenna has been triggered.

waveforms Signal + noise (if noisy) for each triggered antenna hit.

**all\_waveforms** Signal + noise (if noisy) for all antenna hits.

# **Methods**

clear([reset_noise])	Reset the antenna to an empty state.
directional_gain(theta, phi)	Calculate the (complex) directional gain of the an-
	tenna.
full_waveform(times)	Signal + noise (if noisy) for the given times.
generate_directionality_gains(theta,	Generate the (complex) frequency-dependent direc-
phi)	tional gains.
is_hit_during(times)	Check if the antenna is triggered in a time range.
make_noise(times)	Creates a noise signal over the given times.
polarization_gain(polarization, direction)	Calculate the (complex) polarization gain of the an-
	tenna.
receive(signal[, direction, polarization,])	Process and store an incoming signal.

Continued on next page

Table 78 – continued from previous page

response(frequencies)	Calculate the (complex) frequency response of the
	antenna.
set_orientation([z_axis, x_axis])	Sets the orientation of the antenna.
trigger(signal)	Check if the antenna triggers on a given signal.

# pyrex.custom.ara.antenna.VpolBase

class pyrex.custom.ara.antenna.VpolBase (position, center\_frequency, bandwidth, resistance, orientation=(0, 0, 1), efficiency=(0, 0, 1), efficiency=(0, 0, 1), unique noise waveforms=(0, 0, 1))

Antenna class to be used for ARA Vpol antennas.

Stores the attributes of an antenna as well as handling receiving, processing, and storing signals and adding noise. Directionality data and antenna polarization gain specific to the Vpol ("bicone" or "birdcage") antenna.

#### **Parameters**

**position** [array\_like] Vector position of the antenna.

**center\_frequency** [float] Frequency (Hz) at the center of the antenna's frequency range.

**bandwidth** [float] Bandwidth (Hz) of the antenna.

**resistance** [float] The noise resistance (ohm) of the antenna. Used to calculate the RMS voltage of the antenna noise.

orientation [array\_like, optional] Vector direction of the z-axis of the antenna.

efficiency [float, optional] Antenna efficiency applied to incoming signal values.

**noisy** [boolean, optional] Whether or not the antenna should add noise to incoming signals.

**unique\_noise\_waveforms** [int, optional] The number of expected noise waveforms needed for each received signal to have its own noise.

#### See also:

ARAAntenna Antenna class to be used for ARA antennas.

# Attributes

**position** [array\_like] Vector position of the antenna.

**z\_axis** [ndarray] Vector direction of the z-axis of the antenna.

**x\_axis** [ndarray] Vector direction of the x-axis of the antenna.

antenna\_factor [float] Antenna factor used for converting fields to voltages.

efficiency [float] Antenna efficiency applied to incoming signal values.

**noisy** [boolean] Whether or not the antenna should add noise to incoming signals.

unique\_noises [int] The number of expected noise waveforms needed for each received signal to have its own noise.

**freq\_range** [array\_like] The frequency band in which the antenna operates (used for noise production).

**temperature** [float or None] The noise temperature (K) of the antenna. Used in combination with *resistance* to calculate the RMS voltage of the antenna noise.

**resistance** [float or None] The noise resistance (ohm) of the antenna. Used in combination with *temperature* to calculate the RMS voltage of the antenna noise.

**noise\_rms** [float or None] The RMS voltage (v) of the antenna noise. If not None, this value will be used instead of the RMS voltage calculated from the values of *temperature* and *resistance*.

signals [list of Signal] The signals which have been received by the antenna.

**is\_hit** Boolean of whether the antenna has been triggered.

waveforms Signal + noise (if noisy) for each triggered antenna hit.

all\_waveforms Signal + noise (if noisy) for all antenna hits.

#### **Methods**

<pre>clear([reset_noise])</pre>	Reset the antenna to an empty state.
directional_gain(theta, phi)	Calculate the (complex) directional gain of the an-
	tenna.
full_waveform(times)	Signal + noise (if noisy) for the given times.
generate_directionality_gains(theta,	Generate the (complex) frequency-dependent direc-
phi)	tional gains.
is_hit_during(times)	Check if the antenna is triggered in a time range.
make_noise(times)	Creates a noise signal over the given times.
polarization_gain(polarization, direction)	Calculate the (complex) polarization gain of the an-
	tenna.
receive(signal[, direction, polarization,])	Process and store an incoming signal.
response(frequencies)	Calculate the (complex) frequency response of the
	antenna.
set_orientation([z_axis, x_axis])	Sets the orientation of the antenna.
trigger(signal)	Check if the antenna triggers on a given signal.

# pyrex.custom.ara.antenna.ARAAntennaSystem

```
class pyrex.custom.ara.antenna.ARAAntennaSystem (base_antenna, name, position, power_threshold, orientation=(0, 0, 1), amplification=1, amplifier_clipping=1, noisy=True, unique_noise_waveforms=10, **kwargs)
```

Antenna system extending base ARA antenna with front-end processing.

Applies as the front end a filter representing the full ARA electronics chain (including amplification) and signal clipping. Additionally provides a method for passing a signal through the tunnel diode.

#### **Parameters**

base\_antenna [Antenna] Antenna class or subclass to be extended with an ARA front end.

name [str] Name of the antenna.

**position** [array\_like] Vector position of the antenna.

power\_threshold [float] Power threshold for trigger condition. Antenna triggers if a signal passed through the tunnel diode exceeds this threshold times the noise RMS of the tunnel diode. **orientation** [array\_like, optional] Vector direction of the z-axis of the antenna.

**amplification** [float, optional] Amplification to be applied to the signal pre-clipping. Note that the usual ARA electronics amplification is already applied without this.

**amplifier\_clipping** [float, optional] Voltage (V) above which the amplified signal is clipped (in positive and negative values).

**noisy** [boolean, optional] Whether or not the antenna should add noise to incoming signals.

**unique\_noise\_waveforms** [int, optional] The number of expected noise waveforms needed for each received signal to have its own noise.

**directionality\_data** [dict, optional] Dictionary containing data on the directionality of the antenna. Should not be given if the *base\_antenna* class does not accept a *directionality\_data* argument.

**directionality\_freqs** [set, optional] Set of frequencies in the directionality data dict keys. Should not be given if the *base\_antenna* class does not accept a *directionality\_freqs* argument.

#### See also:

pyrex. AntennaSystem Base class for antenna system with front-end processing.

**ARAAntenna** Antenna class to be used for ARA antennas.

#### **Attributes**

antenna [Antenna] Antenna object extended by the front end.

name [str] Name of the antenna.

**position** [array\_like] Vector position of the antenna.

power\_threshold [float] Power threshold for trigger condition. Antenna triggers if a signal passed through the tunnel diode exceeds this threshold times the noise RMS of the tunnel diode.

**amplification** [float] Amplification to be applied to the signal pre-clipping. Note that the usual ARA electronics amplification is already applied without this.

**amplifier\_clipping** [float] Voltage (V) above which the amplified signal is clipped (in positive and negative values).

**lead\_in\_time** [float] Lead-in time (s) required for the front end to equilibrate. Automatically added in before calculation of signals and waveforms.

**is** hit Boolean of whether the antenna system has been triggered.

**signals** The signals received by the antenna with front-end processing.

waveforms The antenna system signal + noise for each triggered hit.

**all\_waveforms** The antenna system signal + noise for all hits.

#### **Methods**

clear([reset_noise])	Reset the antenna system to an empty state.
front_end(signal)	Apply front-end processes to a signal and return the
	output.
<u> </u>	Continued on next need

Continued on next page

Table 80 – continued from previous page	
full_waveform(times)	Signal + noise for the antenna system for the given
	times.
<pre>interpolate_filter(frequencies)</pre>	Generate interpolated filter values for given frequen-
	cies.
is_hit_during(times)	Check if the antenna system is triggered in a time
	range.
make_noise(times)	Creates a noise signal over the given times.
receive(signal[, direction, polarization,])	Process and store an incoming signal.
<pre>set_orientation([z_axis, x_axis])</pre>	Sets the orientation of the antenna system.
setup_antenna([center_frequency, bandwidth,	Setup the antenna by passing along its init argu-
])	ments.
trigger(signal)	Check if the antenna system triggers on a given sig-
	nal.
tunnel_diode(signal)	Calculate a signal as processed by the tunnel diode.

## pyrex.custom.ara.antenna.HpolAntenna

ARA Hpol ("quad-slot") antenna system with front-end processing.

Applies as the front end a filter representing the full ARA electronics chain (including amplification) and signal clipping. Additionally provides a method for passing a signal through the tunnel diode.

### **Parameters**

name [str] Name of the antenna.

position [array\_like] Vector position of the antenna.

power\_threshold [float] Power threshold for trigger condition. Antenna triggers if a signal passed through the tunnel diode exceeds this threshold times the noise RMS of the tunnel diode.

**amplification** [float, optional] Amplification to be applied to the signal pre-clipping. Note that the usual ARA electronics amplification is already applied without this.

**amplifier\_clipping** [float, optional] Voltage (V) above which the amplified signal is clipped (in positive and negative values).

**noisy** [boolean, optional] Whether or not the antenna should add noise to incoming signals.

**unique\_noise\_waveforms** [int, optional] The number of expected noise waveforms needed for each received signal to have its own noise.

#### See also:

**ARAAntennaSystem** Antenna system extending base ARA antenna with front-end processing.

**HpolBase** Antenna class to be used for ARA Hpol antennas.

### **Attributes**

antenna [Antenna] Antenna object extended by the front end.

**name** [str] Name of the antenna.

position [array\_like] Vector position of the antenna.

power\_threshold [float] Power threshold for trigger condition. Antenna triggers if a signal passed through the tunnel diode exceeds this threshold times the noise RMS of the tunnel diode.

**amplification** [float] Amplification to be applied to the signal pre-clipping. Note that the usual ARA electronics amplification is already applied without this.

**amplifier\_clipping** [float] Voltage (V) above which the amplified signal is clipped (in positive and negative values).

**is\_hit** Boolean of whether the antenna system has been triggered.

signals The signals received by the antenna with front-end processing.

waveforms The antenna system signal + noise for each triggered hit.

**all\_waveforms** The antenna system signal + noise for all hits.

#### **Methods**

<pre>clear([reset_noise])</pre>	Reset the antenna system to an empty state.
front_end(signal)	Apply front-end processes to a signal and return the
	output.
full_waveform(times)	Signal + noise for the antenna system for the given
	times.
interpolate_filter(frequencies)	Generate interpolated filter values for given frequen-
	cies.
is_hit_during(times)	Check if the antenna system is triggered in a time
	range.
make_noise(times)	Creates a noise signal over the given times.
receive(signal[, direction, polarization,])	Process and store an incoming signal.
set_orientation([z_axis, x_axis])	Sets the orientation of the antenna system.
setup_antenna([center_frequency, bandwidth,	Setup the antenna by passing along its init argu-
])	ments.
trigger(signal)	Check if the antenna system triggers on a given sig-
	nal.
tunnel_diode(signal)	Calculate a signal as processed by the tunnel diode.

# pyrex.custom.ara.antenna.VpolAntenna

class pyrex.custom.ara.antenna.VpolAntenna (name, position, power\_threshold, amplification=1, amplifier\_clipping=1, noisy=True, unique\_noise\_waveforms=10)

ARA Vpol ("bicone" or "birdcage") antenna system with front-end processing.

Applies as the front end a filter representing the full ARA electronics chain (including amplification) and signal clipping. Additionally provides a method for passing a signal through the tunnel diode.

#### **Parameters**

name [str] Name of the antenna.

**position** [array\_like] Vector position of the antenna.

power\_threshold [float] Power threshold for trigger condition. Antenna triggers if a signal passed through the tunnel diode exceeds this threshold times the noise RMS of the tunnel diode. **amplification** [float, optional] Amplification to be applied to the signal pre-clipping. Note that the usual ARA electronics amplification is already applied without this.

**amplifier\_clipping** [float, optional] Voltage (V) above which the amplified signal is clipped (in positive and negative values).

**noisy** [boolean, optional] Whether or not the antenna should add noise to incoming signals.

**unique\_noise\_waveforms** [int, optional] The number of expected noise waveforms needed for each received signal to have its own noise.

#### See also:

ARAAntennaSystem Antenna system extending base ARA antenna with front-end processing.

*VpolBase* Antenna class to be used for ARA Vpol antennas.

#### **Attributes**

antenna [Antenna] Antenna object extended by the front end.

name [str] Name of the antenna.

**position** [array\_like] Vector position of the antenna.

power\_threshold [float] Power threshold for trigger condition. Antenna triggers if a signal passed through the tunnel diode exceeds this threshold times the noise RMS of the tunnel diode.

**amplification** [float] Amplification to be applied to the signal pre-clipping. Note that the usual ARA electronics amplification is already applied without this.

**amplifier\_clipping** [float] Voltage (V) above which the amplified signal is clipped (in positive and negative values).

**is\_hit** Boolean of whether the antenna system has been triggered.

signals The signals received by the antenna with front-end processing.

waveforms The antenna system signal + noise for each triggered hit.

**all\_waveforms** The antenna system signal + noise for all hits.

### **Methods**

clear([reset_noise])	Reset the antenna system to an empty state.
front_end(signal)	Apply front-end processes to a signal and return the
	output.
full_waveform(times)	Signal + noise for the antenna system for the given
	times.
<pre>interpolate_filter(frequencies)</pre>	Generate interpolated filter values for given frequen-
	cies.
is_hit_during(times)	Check if the antenna system is triggered in a time
	range.
make_noise(times)	Creates a noise signal over the given times.
receive(signal[, direction, polarization,])	Process and store an incoming signal.
set_orientation([z_axis, x_axis])	Sets the orientation of the antenna system.
setup_antenna([center_frequency, bandwidth,	Setup the antenna by passing along its init argu-
])	ments.
	0 11 1 1

Continued on next page

Table 82 – continued from previous page

trigger(signal)	Check if the antenna system triggers on a given sig-
	nal.
tunnel_diode(signal)	Calculate a signal as processed by the tunnel diode.

# Custom Detectors (pyrex.custom.ara.detector)

Module containing customized detector geometry classes for ARA.

Designed to be flexible such that stations can be built up from any string types and the detector grid can be made up of stations or strings.

convert_hex_coords(hex_coords[, unit])	Convert from hexagonal coordinates to Cartesian.
ARAString(x, y[, antennas_per_string,])	String of ARA Hpol and Vpol antennas.
PhasedArrayString(x, y[,])	Phased string of closely-packed antennas.
RegularStation(x, y[, strings_per_station,])	Station geometry with strings evenly spaced radially around the center.
AlbrechtStation(x, y[, station_diameter,])	Station geometry with center phased string and some outrigger strings.
HexagonalGrid([stations,])	Hexagonal grid of stations or strings.

# pyrex.custom.ara.detector.convert hex coords

pyrex.custom.ara.detector.convert\_hex\_coords (hex\_coords, unit=1)
Convert from hexagonal coordinates to Cartesian.

# Parameters

**hex\_coords** [array\_like] Array with two elements representing the hexagonal coordinate.

unit [float, optional] Optional unit used to multiply the Cartesian coordinates.

#### Returns

- **x** [float] Cartesian x-position with the unit correction.
- y [float] Cartesian y-position with the unit correction.

#### **Notes**

Hexagonal coordinate system defined along non-perpendicular axes where the first axis is 30 degrees from the Cartesian x-axis and the second axis is parallel to the Cartesian y-axis. The conversion equations are therefore  $x=h_0-h_1/2$  and  $y=h_1*sqrt(3)/2$ .

#### pyrex.custom.ara.detector.ARAString

**class** pyrex.custom.ara.detector.**ARAString** (x, y,  $antennas\_per\_string=4$ ,  $antenna\_separation=10$ ,  $lowest\_antenna=-200$ )

String of ARA Hpol and Vpol antennas.

Sets the positions of antennas on string based on the parameters. Once the antennas have been built with build\_antennas, the object can be directly iterated over to iterate over the antennas (as if the object were just a list of the antennas).

### **Parameters**

- **x** [float] Cartesian x-position (m) of the string.
- y [float] Cartesian y-position (m) of the string.

antennas\_per\_string [float, optional] Total number of antennas to be placed on the string.

antenna\_separation [float or list of float, optional] The vertical separation (m) of antennas on the string. If float, all antennas are separated by the same constant value. If list, the separations in the list are the separations of neighboring antennas starting from the lowest up to the highest.

**lowest\_antenna** [float, optional] The Cartesian z-position (m) of the lowest antenna on the string.

#### Raises

**ValueError** If test\_antenna\_positions is True and an antenna is found to be above the ice surface.

#### See also:

pyrex.custom.ara.HpolAntenna ARA Hpol ("quad-slot") antenna system with front-end processing.
pyrex.custom.ara.VpolAntenna ARA Vpol ("bicone" or "birdcage") antenna system with front-end processing.

#### **Notes**

This class is designed to be the lowest subset level of a detector. It can (and should) be used for the subsets of some other Detector subclass to build up a full detector. Then when its "parent" is iterated, the instances of this class will be iterated as though they were all part of one flat list.

#### Attributes

**antenna\_positions** [list] List (potentially with sub-lists) of the positions of the antennas generated by the set\_positions method.

**subsets** [list] List of the antenna or detector objects which make up the detector.

**test\_antenna\_positions** [boolean] Class attribute for whether or not an error should be raised if antenna positions are found above the surface of the ice (where simulation behavior is ill-defined). Defaults to True.

### **Methods**

$\verb build_antennas (power_threshold[, \dots]) $	Creates antenna objects at the set antenna positions.
clear([reset_noise])	Reset the detector to an empty state.
set_positions(x, y[, antennas_per_string,])	Generates antenna positions along the string.
triggered([antenna_requirement,])	Check if the string is triggered based on its current
	state.

### pyrex.custom.ara.detector.PhasedArrayString

Phased string of closely-packed antennas.

Sets the positions of antennas on string based on the parameters. Once the antennas have been built with build\_antennas, the object can be directly iterated over to iterate over the antennas (as if the object were just a list of the antennas).

#### **Parameters**

- x [float] Cartesian x-position (m) of the string.
- y [float] Cartesian y-position (m) of the string.

antennas\_per\_string [float, optional] Total number of antennas to be placed on the string.

antenna\_separation [float or list of float, optional] The vertical separation (m) of antennas on the string. If float, all antennas are separated by the same constant value. If list, the separations in the list are the separations of neighboring antennas starting from the lowest up to the highest.

**lowest\_antenna** [float, optional] The Cartesian z-position (m) of the lowest antenna on the string.

antenna\_type [optional] The class to be used to create the antenna objects.

### Raises

**ValueError** If test\_antenna\_positions is True and an antenna is found to be above the ice surface.

# See also:

pyrex.custom.ara.HpolAntenna ARA Hpol ("quad-slot") antenna system with front-end processing.
pyrex.custom.ara.VpolAntenna ARA Vpol ("bicone" or "birdcage") antenna system with front-end processing.

#### **Notes**

This class is designed to be the lowest subset level of a detector. It can (and should) be used for the subsets of some other Detector subclass to build up a full detector. Then when its "parent" is iterated, the instances of this class will be iterated as though they were all part of one flat list.

#### **Attributes**

antenna\_type The class to be used to create the antenna objects.

**antenna\_positions** [list] List (potentially with sub-lists) of the positions of the antennas generated by the set\_positions method.

**subsets** [list] List of the antenna or detector objects which make up the detector.

**test\_antenna\_positions** [boolean] Class attribute for whether or not an error should be raised if antenna positions are found above the surface of the ice (where simulation behavior is ill-defined). Defaults to True.

### **Methods**

build_antennas(power_threshold[,])	Creates antenna objects at the set antenna positions.
clear([reset_noise])	Reset the detector to an empty state.
set_positions(x, y[, antennas_per_string,])	Generates antenna positions along the string.
triggered(beam_threshold[, delays, angles,])	Check if the string is triggered based on its current
	state.

### pyrex.custom.ara.detector.RegularStation

Station geometry with strings evenly spaced radially around the center.

Sets the positions of strings around the station based on the parameters. Supports any string type and passes extra keyword arguments on to the string class. Once the antennas have been built with build\_antennas, the object can be directly iterated over to iterate over the antennas (as if the object were just a list of the antennas).

#### **Parameters**

- **x** [float] Cartesian x-position (m) of the station.
- y [float] Cartesian y-position (m) of the station.

strings\_per\_station [float, optional] Number of strings to be placed evenly around the station.

station\_diameter [float, optional] Diameter (m) of the circle around which strings are placed.

**string\_type** [optional] Class to be used for creating string objects for *subsets*.

\*\*string\_kwargs Keyword arguments to be passed on to the \_\_init\_\_ methods of the string\_type class.

#### Raises

**ValueError** If test\_antenna\_positions is True and an antenna is found to be above the ice surface.

### See also:

pyrex.custom.ara.HpolAntenna ARA Hpol ("quad-slot") antenna system with front-end processing.
pyrex.custom.ara.VpolAntenna ARA Vpol ("bicone" or "birdcage") antenna system with front-end processing.

**ARAString** String of ARA Hpol and Vpol antennas.

#### **Notes**

This class is designed to have string-like objects (which are subclasses of Detector) as its *subsets*. Then whenver an object of this class is iterated, all the antennas of its strings will be yielded as in a 1D list.

# Attributes

**antenna\_positions** [list] List (potentially with sub-lists) of the positions of the antennas generated by the set\_positions method.

subsets [list] List of the antenna or detector objects which make up the detector.

**test\_antenna\_positions** [boolean] Class attribute for whether or not an error should be raised if antenna positions are found above the surface of the ice (where simulation behavior is ill-defined). Defaults to True.

### **Methods**

build_antennas(*args, **kwargs)	Creates antenna objects at the set antenna positions.
clear([reset_noise])	Reset the detector to an empty state.
$set_positions(x, y[, strings_per_station,])$	Generates antenna positions around the station.
triggered([polarized_antenna_requirement,	Check if the station is triggered based on its current
])	state.

## pyrex.custom.ara.detector.AlbrechtStation

Station geometry with center phased string and some outrigger strings.

Station geometry proposed by Albrecht with a phased array string of each polarization at the station center, plus a number of outrigger strings evenly spaced radially around the station center. Sets the positions of strings around the station based on the parameters. Supports any string type and passes extra keyword arguments on to the string class. Once the antennas have been built with build\_antennas, the object can be directly iterated over to iterate over the antennas (as if the object were just a list of the antennas).

## **Parameters**

- **x** [float] Cartesian x-position (m) of the station.
- y [float] Cartesian y-position (m) of the station.
- **station\_diameter** [float, optional] Diameter (m) of the circle around which outrigger strings are placed.
- **hpol\_phased\_antennas** [float, optional] Number of Hpol phased antennas for the center string.
- vpol\_phased\_antennas [float, optional] Number of Vpol phased antennas for the center string.
- **hpol\_phased\_separation** [float or list of float, optional] Antenna separation (m) for the phased Hpol antennas.
- **vpol\_phased\_separation** [float or list of float, optional] Antenna separation (m) for the phased Vpol antennas.
- **hpol\_phased\_lowest** [float, optional] Cartesian z-position (m) of the lowest phased Hpol antenna.
- vpol\_phased\_lowest [float, optional] Cartesian z-position (m) of the lowest phased Vpol antenna.

**outrigger\_strings\_per\_station** [float, optional] Number of outrigger strings to be placed evenly around the station.

**outrigger\_string\_type** [optional] Class to be used for creating outrigger string objects for *sub-sets*.

\*\*outrigger\_string\_kwargs Keyword arguments to be passed on to the \_\_init\_\_ methods of the *outrigger\_string\_type* class. The default values for antennas\_per\_string, antenna\_separation, and lowest\_antenna are altered for this station geometry.

### Raises

**ValueError** If test\_antenna\_positions is True and an antenna is found to be above the ice surface.

#### See also:

pyrex.custom.ara.HpolAntenna ARA Hpol ("quad-slot") antenna system with front-end processing.
pyrex.custom.ara.VpolAntenna ARA Vpol ("bicone" or "birdcage") antenna system with front-end processing.

**ARAString** String of ARA Hpol and Vpol antennas.

**PhasedArrayString** Phased string of closely-packed antennas.

#### **Notes**

This class is designed to have string-like objects (which are subclasses of Detector) as its *subsets*. Then whenver an object of this class is iterated, all the antennas of its strings will be yielded as in a 1D list.

### Attributes

**antenna\_positions** [list] List (potentially with sub-lists) of the positions of the antennas generated by the set\_positions method.

subsets [list] List of the antenna or detector objects which make up the detector.

**test\_antenna\_positions** [boolean] Class attribute for whether or not an error should be raised if antenna positions are found above the surface of the ice (where simulation behavior is ill-defined). Defaults to True.

### Methods

build_antennas(*args, **kwargs)	Creates antenna objects at the set antenna positions.
clear([reset_noise])	Reset the detector to an empty state.
set_positions(x, y[, station_diameter,])	Generates antenna positions around the station.
triggered(beam_threshold[,])	Check if the station is triggered based on its current
	state.

## pyrex.custom.ara.detector.HexagonalGrid

Hexagonal grid of stations or strings.

Sets the positions of stations by spiralling outward in a hexagonal grid. Supports any station type (including string types) and passes extra keyword arguments on to the station class. Once the antennas have been built with build\_antennas, the object can be directly iterated over to iterate over the antennas (as if the object were just a list of the antennas).

#### **Parameters**

**stations** [float, optional] Number of stations to be placed.

**station separation** [float, optional] Distance (m) between adjacent stations.

station\_type [optional] Class to be used for creating station objects for subsets.

\*\*station\_kwargs Keyword arguments to be passed on to the \_\_init\_\_ methods of the station type class.

#### Raises

**ValueError** If test\_antenna\_positions is True and an antenna is found to be above the ice surface.

### See also:

pyrex.custom.ara.HpolAntenna ARA Hpol ("quad-slot") antenna system with front-end processing.

pyrex.custom.ara.VpolAntenna ARA Vpol ("bicone" or "birdcage") antenna system with front-end processing.

**ARAString** String of ARA Hpol and Vpol antennas.

**RegularStation** Station geometry with strings evenly spaced radially around the center.

#### **Notes**

This class is designed to have station-like or string-like objects (which are subclasses of Detector) as its *subsets*. Then whenver an object of this class is iterated, all the antennas of its strings will be yielded as in a 1D list.

## Attributes

**antenna\_positions** [list] List (potentially with sub-lists) of the positions of the antennas generated by the set\_positions method.

subsets [list] List of the antenna or detector objects which make up the detector.

**test\_antenna\_positions** [boolean] Class attribute for whether or not an error should be raised if antenna positions are found above the surface of the ice (where simulation behavior is ill-defined). Defaults to True.

### **Methods**

build_antennas(*args, **kwargs)	Creates antenna objects at the set antenna positions.
clear([reset_noise])	Reset the detector to an empty state.
set_positions([stations,])	Generates antenna positions around the station.
triggered([station_requirement,])	Check if the detector is triggered based on its current
	state.

# 6.3.2 Antarctic Ross Ice-Shelf Antenna Neutrino Array (pyrex.custom.arianna)

The ARIANNA module contains classes for antennas as found in the ARIANNA project.

The LPDA class is the model of the ARIANNA LPDA antenna based on data from NuRadioReco. It uses directional/polarization gain from data/createLPDA\_100MHz\_InfFirn.adl and data/createLPDA\_100MHz\_InfFirn.ral, and amplification gain from data/amp\_300\_gain.csv and data/amp\_300\_phase.csv. The trigger condition of the antenna requires the signal to reach above and below some threshold values within a trigger window.

## **Default Package Imports**

LPDA(name, position, threshold[, ...])

ARIANNA LPDA antenna system.

## pyrex.custom.arianna.LPDA

class pyrex.custom.arianna.LPDA (name, position, threshold, trigger\_window=5e-09,  $z_axis=(0, 0, 1)$ ,  $x_axis=(1, 0, 0)$ , amplification=1, amplifier\_clipping=1, noisy=True, unique\_noise\_waveforms=10)

ARIANNA LPDA antenna system.

Applies as the front end a filter representing the ARIANNA amplifier and signal clipping.

### **Parameters**

name [str] Name of the antenna.

**position** [array\_like] Vector position of the antenna.

threshold [float] Voltage sigma threshold for the trigger condition.

trigger window [float] Time window (ns) for the trigger condition.

z axis [array like, optional] Vector direction of the z-axis of the antenna.

**x\_axis** [array\_like, optional] Vector direction of the x-axis of the antenna.

**amplification** [float, optional] Amplification to be applied to the signal pre-clipping.

**amplifier\_clipping** [float, optional] Voltage (V) above which the amplified signal is clipped (in positive and negative values).

**noisy** [boolean, optional] Whether or not the antenna should add noise to incoming signals.

unique\_noise\_waveforms [int, optional] The number of expected noise waveforms needed for each received signal to have its own noise.

### See also:

**ARIANNAAntennaSystem** Antenna system extending base ARIANNA antenna with front-end processing. **ARIANNAAntenna** Antenna class to be used for ARIANNA antennas.

### **Attributes**

antenna [Antenna] Antenna object extended by the front end.

name [str] Name of the antenna.

**position** [array\_like] Vector position of the antenna.

**threshold** [float] Voltage sigma threshold for the trigger condition.

trigger\_window [float] Time window (ns) for the trigger condition.

**amplification** [float] Amplification to be applied to the signal pre-clipping. Note that the usual ARA electronics amplification is already applied without this.

**amplifier\_clipping** [float] Voltage (V) above which the amplified signal is clipped (in positive and negative values).

is\_hit Boolean of whether the antenna system has been triggered.

**signals** The signals received by the antenna with front-end processing.

waveforms The antenna system signal + noise for each triggered hit.

**all\_waveforms** The antenna system signal + noise for all hits.

## **Methods**

clear([reset_noise])	Reset the antenna system to an empty state.
front_end(signal)	Apply front-end processes to a signal and return the
	output.
full_waveform(times)	Signal + noise for the antenna system for the given
	times.
<pre>interpolate_filter(frequencies)</pre>	Generate interpolated filter values for given frequen-
	cies.
is_hit_during(times)	Check if the antenna system is triggered in a time
	range.
make_noise(times)	Creates a noise signal over the given times.
receive(signal[, direction, polarization,])	Process and store an incoming signal.
<pre>set_orientation([z_axis, x_axis])</pre>	Sets the orientation of the antenna system.
setup_antenna([center_frequency, bandwidth,	Setup the antenna by passing along its init argu-
])	ments.
trigger(signal)	Check if the antenna system triggers on a given sig-
	nal.

## **Individual Module APIs**

## Custom Antennas (pyrex.custom.arianna.antenna)

Module containing customized antenna classes for ARIANNA.

Based primarily on the LPDA implementation (and data) in NuRadioReco.

_read_response_data(filename)	Gather antenna directionality/polarization data from a WIPLD data file.
_read_amplifier_data(gain_filename,[,	Gather frequency-dependent amplifier data from data
])	files.
ARIANNAAntenna(position, center_frequency,)	Antenna class to be used for ARIANNA antennas.
ARIANNAAntennaSystem(name, position, thresh-	Antenna system extending base ARIANNA antenna
old)	with front-end processing.
LPDA(name, position, threshold[,])	ARIANNA LPDA antenna system.

## pyrex.custom.arianna.antenna.\_read\_response\_data

```
pyrex.custom.arianna.antenna._read_response_data (filename)
Gather antenna directionality/polarization data from a WIPLD data file.
```

Data files should exist with names *filename*.ra1 and *filename*.ad1. The .ad1 file should contain frequencies in the first column, real and imaginary parts of the impedance in the sixth and seventh columns, and S-parameter data in the eigth and ninth columns. The .ra1 file should contain phi and theta in the first two columns, the real and imaginary parts of the phi field in the next two columns, and the real and imaginary parts of the theta field in the next two columns. This should be divided into sections for each frequency with a header line "> Gen. no. 1 X GHz 73 91 Gain" where "X" is the frequency in GHz.

### **Parameters**

**filename** [str] Name of the data files without extension. Extensions .ral and .adl will be added automatically.

### Returns

**dict** Dictionary containing the data with keys (freq, theta, phi) and values (theta E-field, phi E-field).

set Set of unique frequencies appearing in the data keys.

**ndarray** Array of S-parameter values corresponding to the frequencies.

### Raises

ValueError If the frequency values of the .ral and .adl files don't match.

## pyrex.custom.arianna.antenna. read amplifier data

```
pyrex.custom.arianna.antenna._read_amplifier_data(gain_filename, gain offset=0)
phase_filename,
```

Gather frequency-dependent amplifier data from data files.

Each data file should have columns for frequency, gain or phase data, and a third empty column. The gain should be in dB and the phase should be in degrees.

### **Parameters**

```
gain_filename [str] Name of the data file containing gains (in dB).phase_filename [str] Name of the data file containing phases (in degrees).gain_offset [float] Offset to apply to the gain values (in dB).
```

## Returns

dict Dictionary containing the data with keys (freq) and values (gain, phase).

### pyrex.custom.arianna.antenna.ARIANNAAntenna

class pyrex.custom.arianna.antenna.ARIANNAAntenna (position, center\_frequency, bandwidth, resistance,  $z\_axis=(0, 0, 1), x\_axis=(1, 0, 0), ef$ ficiency=1, noisy=True, unique\_noise\_waveforms=10, response\_data=None, response\_freqs=None)

Antenna class to be used for ARIANNA antennas.

Stores the attributes of an antenna as well as handling receiving, processing, and storing signals and adding noise.

### **Parameters**

**position** [array\_like] Vector position of the antenna.

**center\_frequency** [float] Frequency (Hz) at the center of the antenna's frequency range.

bandwidth [float] Bandwidth (Hz) of the antenna.

**resistance** [float] The noise resistance (ohm) of the antenna. Used to calculate the RMS voltage of the antenna noise.

**z\_axis** [array\_like, optional] Vector direction of the z-axis of the antenna.

**x\_axis** [array\_like, optional] Vector direction of the x-axis of the antenna.

efficiency [float, optional] Antenna efficiency applied to incoming signal values.

**noisy** [boolean, optional] Whether or not the antenna should add noise to incoming signals.

**unique\_noise\_waveforms** [int, optional] The number of expected noise waveforms needed for each received signal to have its own noise.

**response\_data** [None or dict, optional] Dictionary containing data on the response of the antenna. If None, behavior is undefined.

**response\_freqs** [None or set, optional] Set of frequencies in the response data dict keys. If None, calculated automatically from *response\_data*.

### See also:

pyrex. Antenna Base class for antennas.

### Attributes

**position** [array\_like] Vector position of the antenna.

**z\_axis** [ndarray] Vector direction of the z-axis of the antenna.

**x axis** [ndarray] Vector direction of the x-axis of the antenna.

antenna\_factor [float] Antenna factor used for converting fields to voltages.

efficiency [float] Antenna efficiency applied to incoming signal values.

noisy [boolean] Whether or not the antenna should add noise to incoming signals.

unique\_noises [int] The number of expected noise waveforms needed for each received signal to have its own noise.

**freq\_range** [array\_like] The frequency band in which the antenna operates (used for noise production).

**temperature** [float or None] The noise temperature (K) of the antenna. Used in combination with *resistance* to calculate the RMS voltage of the antenna noise.

**resistance** [float or None] The noise resistance (ohm) of the antenna. Used in combination with *temperature* to calculate the RMS voltage of the antenna noise.

**noise\_rms** [float or None] The RMS voltage (v) of the antenna noise. If not None, this value will be used instead of the RMS voltage calculated from the values of *temperature* and *resistance*.

signals [list of Signal] The signals which have been received by the antenna.

**is\_hit** Boolean of whether the antenna has been triggered.

waveforms Signal + noise (if noisy) for each triggered antenna hit.

**all\_waveforms** Signal + noise (if noisy) for all antenna hits.

# **Methods**

Reset the antenna to an empty state.
Calculate the (complex) directional gain of the an-
tenna.
Signal + noise (if noisy) for the given times.
Generate the (complex) frequency-dependent re-
sponse gains.
Check if the antenna is triggered in a time range.
Creates a noise signal over the given times.
Calculate the (complex) polarization gain of the an-
tenna.
Process and store an incoming signal.
Calculate the (complex) frequency response of the
antenna.
Sets the orientation of the antenna.
Check if the antenna triggers on a given signal.

### pyrex.custom.arianna.antenna.ARIANNAAntennaSystem

class pyrex.custom.arianna.antenna.ARIANNAAntennaSystem(name, position, threshold,

trigger\_window=5e-09, z\_axis=(0, 0, 1), x\_axis=(1, 0, 0), amplification=1, amplifier\_clipping=1, noisy=True, unique\_noise\_waveforms=10, response\_data=None, response\_freqs=None, \*\*kwargs)

Antenna system extending base ARIANNA antenna with front-end processing.

Applies as the front end a filter representing the ARIANNA amplifier and signal clipping.

## **Parameters**

name [str] Name of the antenna.

**position** [array\_like] Vector position of the antenna.

threshold [float] Voltage sigma threshold for the trigger condition.

trigger\_window [float] Time window (ns) for the trigger condition.

**z\_axis** [array\_like, optional] Vector direction of the z-axis of the antenna.

**x\_axis** [array\_like, optional] Vector direction of the x-axis of the antenna.

**amplification** [float, optional] Amplification to be applied to the signal pre-clipping.

**amplifier\_clipping** [float, optional] Voltage (V) above which the amplified signal is clipped (in positive and negative values).

**noisy** [boolean, optional] Whether or not the antenna should add noise to incoming signals.

**unique\_noise\_waveforms** [int, optional] The number of expected noise waveforms needed for each received signal to have its own noise.

**response\_data** [None or dict, optional] Dictionary containing data on the response of the antenna. If None, behavior is undefined.

**response\_freqs** [None or set, optional] Set of frequencies in the response data dict keys. If None, calculated automatically from *response\_data*.

## See also:

pyrex. AntennaSystem Base class for antenna system with front-end processing.

**ARIANNA** Antenna class to be used for ARIANNA antennas.

#### **Attributes**

antenna [Antenna] Antenna object extended by the front end.

name [str] Name of the antenna.

**position** [array\_like] Vector position of the antenna.

threshold [float] Voltage sigma threshold for the trigger condition.

**trigger\_window** [float] Time window (s) for the trigger condition.

**amplification** [float] Amplification to be applied to the signal pre-clipping. Note that the usual ARA electronics amplification is already applied without this.

**amplifier\_clipping** [float] Voltage (V) above which the amplified signal is clipped (in positive and negative values).

**lead\_in\_time** [float] Lead-in time (s) required for the front end to equilibrate. Automatically added in before calculation of signals and waveforms.

**is\_hit** Boolean of whether the antenna system has been triggered.

**signals** The signals received by the antenna with front-end processing.

waveforms The antenna system signal + noise for each triggered hit.

**all\_waveforms** The antenna system signal + noise for all hits.

### Methods

clear([reset_noise])	Reset the antenna system to an empty state.
front_end(signal)	Apply front-end processes to a signal and return the
-	output.
full_waveform(times)	Signal + noise for the antenna system for the given
	times.
<pre>interpolate_filter(frequencies)</pre>	Generate interpolated filter values for given frequen-
	cies.
is_hit_during(times)	Check if the antenna system is triggered in a time
	range.
make_noise(times)	Creates a noise signal over the given times.
receive(signal[, direction, polarization,])	Process and store an incoming signal.
<pre>set_orientation([z_axis, x_axis])</pre>	Sets the orientation of the antenna system.
setup_antenna([center_frequency, bandwidth,	Setup the antenna by passing along its init argu-
])	ments.
trigger(signal)	Check if the antenna system triggers on a given sig-
	nal.

## pyrex.custom.arianna.antenna.LPDA

class pyrex.custom.arianna.antenna.LPDA (name, position, threshold, trigger\_window=5e-09,  $z\_axis=(0, 0, 1)$ ,  $x\_axis=(1, 0, 0)$ , amplification=1,  $amplifier\_clipping=1$ , noisy=True,  $unique\_noise\_waveforms=10$ )

ARIANNA LPDA antenna system.

Applies as the front end a filter representing the ARIANNA amplifier and signal clipping.

## **Parameters**

name [str] Name of the antenna.

**position** [array\_like] Vector position of the antenna.

threshold [float] Voltage sigma threshold for the trigger condition.

**trigger\_window** [float] Time window (ns) for the trigger condition.

**z\_axis** [array\_like, optional] Vector direction of the z-axis of the antenna.

**x\_axis** [array\_like, optional] Vector direction of the x-axis of the antenna.

**amplification** [float, optional] Amplification to be applied to the signal pre-clipping.

**amplifier\_clipping** [float, optional] Voltage (V) above which the amplified signal is clipped (in positive and negative values).

**noisy** [boolean, optional] Whether or not the antenna should add noise to incoming signals.

**unique\_noise\_waveforms** [int, optional] The number of expected noise waveforms needed for each received signal to have its own noise.

### See also:

**ARIANNAAntennaSystem** Antenna system extending base ARIANNA antenna with front-end processing. **ARIANNAAntenna** Antenna class to be used for ARIANNA antennas.

### Attributes

antenna [Antenna] Antenna object extended by the front end.

**name** [str] Name of the antenna.

position [array\_like] Vector position of the antenna.

threshold [float] Voltage sigma threshold for the trigger condition.

trigger\_window [float] Time window (ns) for the trigger condition.

**amplification** [float] Amplification to be applied to the signal pre-clipping. Note that the usual ARA electronics amplification is already applied without this.

**amplifier\_clipping** [float] Voltage (V) above which the amplified signal is clipped (in positive and negative values).

**is\_hit** Boolean of whether the antenna system has been triggered.

**signals** The signals received by the antenna with front-end processing.

waveforms The antenna system signal + noise for each triggered hit.

all\_waveforms The antenna system signal + noise for all hits.

### **Methods**

clear([reset_noise])	Reset the antenna system to an empty state.
front_end(signal)	Apply front-end processes to a signal and return the
_ , ,	output.
full_waveform(times)	Signal + noise for the antenna system for the given
	times.
<pre>interpolate_filter(frequencies)</pre>	Generate interpolated filter values for given frequen-
	cies.
is_hit_during(times)	Check if the antenna system is triggered in a time
	range.
make_noise(times)	Creates a noise signal over the given times.
receive(signal[, direction, polarization,])	Process and store an incoming signal.
set_orientation([z_axis, x_axis])	Sets the orientation of the antenna system.
setup_antenna([center_frequency, bandwidth,	Setup the antenna by passing along its init argu-
])	ments.
trigger(signal)	Check if the antenna system triggers on a given sig-
	nal.

# 6.3.3 IceCube Radio Extension (pyrex.custom.irex)

The IREX module contains classes for antennas and detectors which use waveform envelopes rather than raw waveforms. The detectors provided allow for testing of grid and station geometries.

The EvelopeHpol and EvelopeVpol classes wrap models of ARA Hpol and Vpol antennas with an additional front-end which uses a diode-bridge circuit to create waveform envelopes. The trigger condition for these antennas is a simple threshold trigger on the envelopes.

The IREXString class creates a string of EvelopeVpol antennas at a given position. The RegularStation class creates a station at a given position with 4 (or another given number) strings spaced evenly around the station center. The CoxeterStation class creates a station at a given position similar to the RegularStation, but with one string at the station center and the rest spaced evenly around the center. The StationGrid class creates a rectangular grid of stations (or strings, as specified by the station type). The dimensions of the grid in stations is Nx by Ny where N is the total number of stations, Nx=floor(sqrt(N)), and Ny=floor(N/Nx).

## **Default Package Imports**

EnvelopeHpol(name, position, trigger_threshold)	ARA Hpol ("quad-slot") antenna system with front-end
	processing.
EnvelopeVpol(name, position, trigger_threshold)	ARA Vpol ("bicone" or "birdcage") antenna system
	with front-end processing.
<pre>IREXString(x, y[, antennas_per_string,])</pre>	String of IREX Vpol antennas.
RegularStation(x, y[, strings_per_station,])	Station geometry with strings evenly spaced radially
	around the center.
CoxeterStation(x, y[, strings_per_station,])	Station geometry with center string and the rest evenly
	spaced radially.
StationGrid([stations, station_separation,])	Rectangular grid of stations or strings.

## pyrex.custom.irex.EnvelopeHpol

```
class pyrex.custom.irex.EnvelopeHpol (name, position, trigger_threshold, time_over_threshold=0, orientation=(0, 0, 1), amplification=1, amplifier_clipping=1, envelope_amplification=1, envelope_method='analytic', noisy=True, unique_noise_waveforms=10)
```

ARA Hpol ("quad-slot") antenna system with front-end processing.

Consists of an ARA Hpol antenna with typical responses, front-end electronics, and amplifier clipping, but with an additional amplification and envelope circuit applied after all other front-end processing.

#### **Parameters**

name [str] Name of the antenna.

**position** [array\_like] Vector position of the antenna.

**trigger\_threshold** [float] Threshold (V) for trigger condition. Antenna triggers if the voltage value of the waveform exceeds this value.

**time\_over\_threshold** [float, optional] Time (s) that the voltage waveform must exceed *trig-ger threshold* for the antenna to trigger.

**orientation** [array like, optional] Vector direction of the z-axis of the antenna.

**amplification** [float, optional] Amplification to be applied to the signal pre-clipping. Note that the usual ARA electronics amplification is already applied without this.

**amplifier\_clipping** [float, optional] Voltage (V) above which the amplified signal is clipped (in positive and negative values).

**envelope\_amplification** [float, optional] Amplification to be applied to the signal after the typical ARA front end, before the envelope circuit.

envelope\_method [{('hilbert', 'analytic', 'spice') + ('basic', 'biased', 'doubler', 'bridge', 'log amp')}, optional] String describing the circuit (and calculation method) to be used for envelope calculation. If the string contains "hilbert", the hilbert envelope is used. If the string contains "analytic", an analytic form is used to calculate the circuit output. If the string contains "spice", ngspice is used to calculate the circuit output. The default value "analytic" uses an analytic diode bridge circuit.

**noisy** [boolean, optional] Whether or not the antenna should add noise to incoming signals.

unique\_noise\_waveforms [int, optional] The number of expected noise waveforms needed for each received signal to have its own noise.

### **Attributes**

antenna [Antenna] Antenna object extended by the front end.

name [str] Name of the antenna.

position [array\_like] Vector position of the antenna.

**trigger\_threshold** [float] Threshold (V) for trigger condition. Antenna triggers if the voltage value of the waveform exceeds this value.

**time\_over\_threshold** [float] Time (s) that the voltage waveform must exceed *trigger\_threshold* for the antenna to trigger.

**envelope\_amplification** [float] Amplification to be applied to the signal pre-clipping. Note that the usual ARA electronics amplification is already applied without this.

**envelope\_method** [str] String describing the circuit (and calculation method) to be used for envelope calculation.

is\_hit Boolean of whether the antenna system has been triggered.

signals The signals received by the antenna with front-end processing.

waveforms The antenna system signal + noise for each triggered hit.

**all\_waveforms** The antenna system signal + noise for all hits.

### **Methods**

front-end processes to a signal and return the t. front-end processes to a signal and return the t.
front-end processes to a signal and return the t.
t.
l + noise for the antenna system for the given
ate interpolated filter values for given frequen-
if the antenna system is triggered in a time
n the signal envelope based on the antenna's
lope_method.
es a noise signal over the given times.
ss and store an incoming signal.
ne orientation of the antenna system.
the antenna by passing along its init argu-
if the antenna triggers on a given signal.
late a signal as processed by the tunnel diode.

## pyrex.custom.irex.EnvelopeVpol

```
class pyrex.custom.irex.EnvelopeVpol (name, position, trigger_threshold, time_over_threshold=0, orientation=(0, 0, 1), amplification=(0, 0, 1), amplification=(0, 0, 1), envelope_amplification=(0, 0, 1), noisy=True, unique_noise_waveforms=(0, 0, 1), noisy=(0, 0, 1), n
```

ARA Vpol ("bicone" or "birdcage") antenna system with front-end processing.

Consists of an ARA Vpol antenna with typical responses, front-end electronics, and amplifier clipping, but with an additional amplification and envelope circuit applied after all other front-end processing.

#### **Parameters**

name [str] Name of the antenna.

position [array\_like] Vector position of the antenna.

**trigger\_threshold** [float] Threshold (V) for trigger condition. Antenna triggers if the voltage value of the waveform exceeds this value.

**time\_over\_threshold** [float, optional] Time (s) that the voltage waveform must exceed *trig-ger\_threshold* for the antenna to trigger.

orientation [array\_like, optional] Vector direction of the z-axis of the antenna.

**amplification** [float, optional] Amplification to be applied to the signal pre-clipping. Note that the usual ARA electronics amplification is already applied without this.

**amplifier\_clipping** [float, optional] Voltage (V) above which the amplified signal is clipped (in positive and negative values).

**envelope\_amplification** [float, optional] Amplification to be applied to the signal after the typical ARA front end, before the envelope circuit.

envelope\_method [{('hilbert', 'analytic', 'spice') + ('basic', 'biased', 'doubler', 'bridge', 'log amp')}, optional] String describing the circuit (and calculation method) to be used for envelope calculation. If the string contains "hilbert", the hilbert envelope is uesd. If the string contains "analytic", an analytic form is used to calculate the circuit output. If the string contains "spice", ngspice is used to calculate the circuit output. The default value "analytic" uses an analytic diode bridge circuit.

**noisy** [boolean, optional] Whether or not the antenna should add noise to incoming signals.

**unique\_noise\_waveforms** [int, optional] The number of expected noise waveforms needed for each received signal to have its own noise.

## Attributes

antenna [Antenna] Antenna object extended by the front end.

name [str] Name of the antenna.

**position** [array like] Vector position of the antenna.

**trigger\_threshold** [float] Threshold (V) for trigger condition. Antenna triggers if the voltage value of the waveform exceeds this value.

**time\_over\_threshold** [float] Time (s) that the voltage waveform must exceed *trigger\_threshold* for the antenna to trigger.

**envelope\_amplification** [float] Amplification to be applied to the signal pre-clipping. Note that the usual ARA electronics amplification is already applied without this.

**envelope\_method** [str] String describing the circuit (and calculation method) to be used for envelope calculation.

**is\_hit** Boolean of whether the antenna system has been triggered.

**signals** The signals received by the antenna with front-end processing.

waveforms The antenna system signal + noise for each triggered hit.

**all\_waveforms** The antenna system signal + noise for all hits.

## **Methods**

clear([reset_noise])	Reset the antenna system to an empty state.
envelopeless_front_end(signal)	Apply front-end processes to a signal and return the
	output.
front_end(signal)	Apply front-end processes to a signal and return the
	output.
full_waveform(times)	Signal + noise for the antenna system for the given
	times.
interpolate_filter(frequencies)	Generate interpolated filter values for given frequen-
	cies.
is_hit_during(times)	Check if the antenna system is triggered in a time
	range.
make_envelope(signal)	Return the signal envelope based on the antenna's
	envelope_method.
make_noise(times)	Creates a noise signal over the given times.
receive(signal[, direction, polarization,])	Process and store an incoming signal.
set_orientation([z_axis, x_axis])	Sets the orientation of the antenna system.
setup_antenna([center_frequency, bandwidth,	Setup the antenna by passing along its init argu-
])	ments.
trigger(signal)	Check if the antenna triggers on a given signal.
tunnel_diode(signal)	Calculate a signal as processed by the tunnel diode.

## pyrex.custom.irex.IREXString

class pyrex.custom.irex.IREXString(x, y, antennas\_per\_string=2, antenna\_separation=50, lowest\_antenna=-100)

String of IREX Vpol antennas.

Sets the positions of antennas on string based on the parameters. Once the antennas have been built with build\_antennas, the object can be directly iterated over to iterate over the antennas (as if the object were just a list of the antennas).

## **Parameters**

- **x** [float] Cartesian x-position (m) of the string.
- y [float] Cartesian y-position (m) of the string.

antennas\_per\_string [float, optional] Total number of antennas to be placed on the string.

antenna\_separation [float or list of float, optional] The vertical separation (m) of antennas on the string. If float, all antennas are separated by the same constant value. If list, the separations in the list are the separations of neighboring antennas starting from the lowest up to the highest.

**lowest\_antenna** [float, optional] The Cartesian z-position (m) of the lowest antenna on the string.

#### Raises

**ValueError** If test\_antenna\_positions is True and an antenna is found to be above the ice surface.

#### See also:

pyrex.custom.irex.EnvelopeHpo1 ARA Hpol ("quad-slot") antenna system with front-end processing.

pyrex.custom.irex.EnvelopeVpol ARA Vpol ("bicone" or "birdcage") antenna system with frontend processing.

### **Notes**

This class is designed to be the lowest subset level of a detector. It can (and should) be used for the subsets of some other Detector subclass to build up a full detector. Then when its "parent" is iterated, the instances of this class will be iterated as though they were all part of one flat list.

#### **Attributes**

**antenna\_positions** [list] List (potentially with sub-lists) of the positions of the antennas generated by the set\_positions method.

subsets [list] List of the antenna or detector objects which make up the detector.

**test\_antenna\_positions** [boolean] Class attribute for whether or not an error should be raised if antenna positions are found above the surface of the ice (where simulation behavior is ill-defined). Defaults to True.

## **Methods**

build_antennas(trigger_threshold[,])	Creates antenna objects at the set antenna positions.
clear([reset_noise])	Reset the detector to an empty state.
set_positions(x, y[, antennas_per_string,])	Generates antenna positions along the string.
triggered([antenna_requirement,])	Check if the string is triggered based on its current
	state.

### pyrex.custom.irex.RegularStation

Station geometry with strings evenly spaced radially around the center.

Sets the positions of strings around the station based on the parameters. Supports any string type and passes extra keyword arguments on to the string class. Once the antennas have been built with build\_antennas, the object can be directly iterated over to iterate over the antennas (as if the object were just a list of the antennas).

### **Parameters**

**x** [float] Cartesian x-position (m) of the station.

y [float] Cartesian y-position (m) of the station.

**strings\_per\_station** [float, optional] Number of strings to be placed evenly around the station.

station\_diameter [float, optional] Diameter (m) of the circle around which strings are placed.

string\_type [optional] Class to be used for creating string objects for subsets.

\*\*string\_kwargs Keyword arguments to be passed on to the \_\_init\_\_ methods of the string\_type class.

### Raises

**ValueError** If test\_antenna\_positions is True and an antenna is found to be above the ice surface.

#### See also:

pyrex.custom.irex.EnvelopeHpol ARA Hpol ("quad-slot") antenna system with front-end processing.

pyrex.custom.irex.EnvelopeVpo1 ARA Vpol ("bicone" or "birdcage") antenna system with frontend processing.

**IREXString** String of IREX Vpol antennas.

### **Notes**

This class is designed to have string-like objects (which are subclasses of Detector) as its *subsets*. Then whenver an object of this class is iterated, all the antennas of its strings will be yielded as in a 1D list.

### Attributes

**antenna\_positions** [list] List (potentially with sub-lists) of the positions of the antennas generated by the set\_positions method.

**subsets** [list] List of the antenna or detector objects which make up the detector.

**test\_antenna\_positions** [boolean] Class attribute for whether or not an error should be raised if antenna positions are found above the surface of the ice (where simulation behavior is ill-defined). Defaults to True.

## **Methods**

<pre>build_antennas(*args, **kwargs)</pre>	Creates antenna objects at the set antenna positions.
clear([reset_noise])	Reset the detector to an empty state.
set_positions(x, y[, strings_per_station,])	Generates antenna positions around the station.
triggered([antenna_requirement,])	Check if the station is triggered based on its current
	state.

## pyrex.custom.irex.CoxeterStation

Station geometry with center string and the rest evenly spaced radially.

Sets the positions of strings around the station based on the parameters. Supports any string type and passes extra keyword arguments on to the string class. Once the antennas have been built with build\_antennas, the object can be directly iterated over to iterate over the antennas (as if the object were just a list of the antennas).

### **Parameters**

- **x** [float] Cartesian x-position (m) of the station.
- y [float] Cartesian y-position (m) of the station.
- **strings\_per\_station** [float, optional] Number of strings to be placed around the station. Note that the first string is always placed at the center and the rest of the strings are placed evenly around that center string.
- station\_diameter [float, optional] Diameter (m) of the circle around which strings are placed.
- **string\_type** [optional] Class to be used for creating string objects for *subsets*.
- \*\*string\_kwargs Keyword arguments to be passed on to the \_\_init\_\_ methods of the string\_type class.

## Raises

**ValueError** If test\_antenna\_positions is True and an antenna is found to be above the ice surface.

#### See also:

pyrex.custom.irex.EnvelopeHpo1 ARA Hpol ("quad-slot") antenna system with front-end processing.

pyrex.custom.irex.EnvelopeVpol ARA Vpol ("bicone" or "birdcage") antenna system with frontend processing.

**IREXString** String of IREX Vpol antennas.

## **Notes**

This class is designed to have string-like objects (which are subclasses of Detector) as its *subsets*. Then whenver an object of this class is iterated, all the antennas of its strings will be yielded as in a 1D list.

### **Attributes**

**antenna\_positions** [list] List (potentially with sub-lists) of the positions of the antennas generated by the set\_positions method.

subsets [list] List of the antenna or detector objects which make up the detector.

**test\_antenna\_positions** [boolean] Class attribute for whether or not an error should be raised if antenna positions are found above the surface of the ice (where simulation behavior is ill-defined). Defaults to True.

### **Methods**

<pre>build_antennas(*args, **kwargs)</pre>	Creates antenna objects at the set antenna positions.
clear([reset_noise])	Reset the detector to an empty state.
$set_positions(x, y[, strings_per_station,])$	Generates antenna positions around the station.
triggered([antenna_requirement,])	Check if the station is triggered based on its current
	state.

### pyrex.custom.irex.StationGrid

Rectangular grid of stations or strings.

Sets the positions of stations in a square layout if possible, otherwise in a rectangular layout (drops any extra stations). Supports any station type (including string types) and passes extra keyword arguments on to the station class. Once the antennas have been built with build\_antennas, the object can be directly iterated over to iterate over the antennas (as if the object were just a list of the antennas).

#### **Parameters**

stations [float, optional] Number of stations to be placed.

station\_separation [float, optional] Distance (m) between adjacent stations.

station\_type [optional] Class to be used for creating station objects for subsets.

\*\*station\_kwargs Keyword arguments to be passed on to the \_\_init\_\_ methods of the station\_type class.

#### Raises

**ValueError** If test\_antenna\_positions is True and an antenna is found to be above the ice surface.

**Warning:** If the number of *stations* provided does not divide nicely into a rectangle, extra stations may be dropped without warning. For example, if *stations* is 5, then a 2x2 grid will be created and the last station will be silently dropped.

#### See also:

**IREXString** String of IREX Vpol antennas.

**RegularStation** Station geometry with strings evenly spaced radially around the center.

**CoxeterStation** Station geometry with center string and the rest evenly spaced radially.

## **Notes**

This class is designed to have station-like or string-like objects (which are subclasses of Detector) as its *subsets*. Then whenver an object of this class is iterated, all the antennas of its strings will be yielded as in a 1D list.

### **Attributes**

**antenna\_positions** [list] List (potentially with sub-lists) of the positions of the antennas generated by the set\_positions method.

subsets [list] List of the antenna or detector objects which make up the detector.

**test\_antenna\_positions** [boolean] Class attribute for whether or not an error should be raised if antenna positions are found above the surface of the ice (where simulation behavior is ill-defined). Defaults to True.

## **Methods**

build_antennas(*args, **kwargs)	Creates antenna objects at the set antenna positions.
clear([reset_noise])	Reset the detector to an empty state.
set_positions([stations,])	Generates antenna positions around the station.
triggered([station_requirement,])	Check if the detector is triggered based on its current
	state.

### **Individual Module APIs**

## Custom Front-ends (pyrex.custom.irex.frontends)

Module containing IREX front-end circuit models.

Contains wrappers for PySpice circuits as well as analytical forms for some envelope circuits.

basic_envelope_model(signal[, cap, res])	Model of a basic diode-capacitor-resistor envelope circuit.
bridge_rectifier_envelope_model(signal[,	Model of a diode bridge rectifier envelope circuit.
])	

## pyrex.custom.irex.frontends.basic envelope model

```
pyrex.custom.irex.frontends.basic_envelope_model (signal, cap=2e-11, res=500) Model of a basic diode-capacitor-resistor envelope circuit.
```

Passes the input signal through a basic envelope circuit consisting of a diode, a capacitor, and a resistor. The diode used is modeled after an HSMS 2852 diode.

## **Parameters**

signal [Signal] Signal object used as input to the circuit.

cap [float, optional] Capacitance (F) of the circuit's capacitor C1.

res [float, optional] Resistance (ohm) of the circuit's resistor R1.

### Returns

**Signal** Output of the envelope circuit for the given input.

## **Notes**

Ascii depiction of the basic envelope circuit:

## pyrex.custom.irex.frontends.bridge rectifier envelope model

```
pyrex.custom.irex.frontends.bridge_rectifier_envelope_model(signal, cap=2e-11, res=500)
```

Model of a diode bridge rectifier envelope circuit.

Passes the input signal through a diode bridge rectifier envelope circuit consisting of four diodes in a diode bridge, a capacitor, and a resistor. The diode used is modeled after an HSMS 2852 diode.

## **Parameters**

signal [Signal] Signal object used as input to the circuit.

cap [float, optional] Capacitance (F) of the circuit's capacitor C1.


res [float, optional] Resistance (ohm) of the circuit's resistor R1.

## Returns

**Signal** Output of the envelope circuit for the given input.

## **Notes**

Ascii depiction of the diode bridge rectifier envelope circuit:



## Custom Antennas (pyrex.custom.irex.antenna)

Module containing customized antenna classes for IREX.

The IREX antennas are based around existing ARA antennas with an extra envelope circuit applied in the front-end, designed to reduce power consumption and the amount of digitized information.

DipoleTester(position, center_frequency,)	Dipole antenna for IREX testing.
EnvelopeSystem(base_antenna, name, position,	Antenna system extending ARA antennas with an enve-
)	lope circuit.
EnvelopeHpol(name, position, trigger_threshold)	ARA Hpol ("quad-slot") antenna system with front-end
	processing.
EnvelopeVpol(name, position, trigger_threshold)	ARA Vpol ("bicone" or "birdcage") antenna system
	with front-end processing.

## pyrex.custom.irex.antenna.DipoleTester

```
class pyrex.custom.irex.antenna.DipoleTester(position, center_frequency, bandwidth, resistance, orientation=(0, 0, 1), effective_height=None, noisy=True, unique_noise_waveforms=(0, 0, 1)
```

Dipole antenna for IREX testing.

Stores the attributes of an antenna as well as handling receiving, processing, and storing signals and adding noise. Uses a first-order butterworth filter for the frequency response.

### **Parameters**

**position** [array\_like] Vector position of the antenna.

**center\_frequency** [float] Tuned frequency (Hz) of the dipole.

**bandwidth** [float] Bandwidth (Hz) of the antenna.

**resistance** [float] The noise resistance (ohm) of the antenna. Used to calculate the RMS voltage of the antenna noise.

orientation [array\_like, optional] Vector direction of the z-axis of the antenna.

**effective\_height** [float, optional] Effective length (m) of the antenna. By default calculated by the tuned *center\_frequency* of the dipole.

**noisy** [boolean, optional] Whether or not the antenna should add noise to incoming signals.

**unique\_noise\_waveforms** [int, optional] The number of expected noise waveforms needed for each received signal to have its own noise.

### **Attributes**

name [str] Name of the antenna.

position [array\_like] Vector position of the antenna.

**z\_axis** [ndarray] Vector direction of the z-axis of the antenna.

**x\_axis** [ndarray] Vector direction of the x-axis of the antenna.

antenna\_factor [float] Antenna factor used for converting fields to voltages.

efficiency [float] Antenna efficiency applied to incoming signal values.

threshold [float, optional] Voltage threshold (V) above which signals will trigger.

**effective\_height** [float, optional] Effective length of the antenna. By default calculated by the tuned *center\_frequency* of the dipole.

**filter\_coeffs** [tuple of ndarray] Coefficients of transfer function for butterworth bandpass filter to be used for frequency response.

**noisy** [boolean] Whether or not the antenna should add noise to incoming signals.

**unique\_noises** [int] The number of expected noise waveforms needed for each received signal to have its own noise.

**freq\_range** [array\_like] The frequency band in which the antenna operates (used for noise production).

**temperature** [float or None] The noise temperature (K) of the antenna. Used in combination with *resistance* to calculate the RMS voltage of the antenna noise.

**resistance** [float or None] The noise resistance (ohm) of the antenna. Used in combination with *temperature* to calculate the RMS voltage of the antenna noise.

**noise\_rms** [float or None] The RMS voltage (V) of the antenna noise. If not None, this value will be used instead of the RMS voltage calculated from the values of *temperature* and *resistance*.

signals [list of Signal] The signals which have been received by the antenna.

is hit Boolean of whether the antenna has been triggered.

waveforms Signal + noise (if noisy) for each triggered antenna hit.

all\_waveforms Signal + noise (if noisy) for all antenna hits.

### **Methods**

clear([reset_noise])	Reset the antenna to an empty state.
	Calculate the (complex) directional gain of the an-
directional_gain(theta, phi)	, 1
	tenna.
full_waveform(times)	Signal + noise (if noisy) for the given times.
is_hit_during(times)	Check if the antenna is triggered in a time range.
make_noise(times)	Creates a noise signal over the given times.
polarization_gain(polarization)	Calculate the (complex) polarization gain of the an-
	tenna.
receive(signal[, direction, polarization,])	Process and store an incoming signal.
response(frequencies)	Calculate the (complex) frequency response of the
	antenna.
set_orientation([z_axis, x_axis])	Sets the orientation of the antenna.
trigger(signal)	Check if the antenna triggers on a given signal.

## pyrex.custom.irex.antenna.EnvelopeSystem

```
class pyrex.custom.irex.antenna.EnvelopeSystem(base\_antenna, name, position, trig-ger\_threshold, time\_over\_threshold=0, orientation=(0, 0, 1), amplification=1, amplifier\_clipping=1, envelope\_amplification=1, envelope\_amplification=1, envelope\_method='analytic', noisy=True, unique noise waveforms=10)
```

Antenna system extending ARA antennas with an envelope circuit.

Consists of an ARA antenna with typical responses, front-end electronics, and amplifier clipping, but with an additional amplification and envelope circuit applied after all other front-end processing.

#### **Parameters**

base\_antenna [Antenna] Antenna class or subclass to be extended with an ARA front end.

name [str] Name of the antenna.

**position** [array\_like] Vector position of the antenna.

**trigger\_threshold** [float] Threshold (V) for trigger condition. Antenna triggers if the voltage value of the waveform exceeds this value.

**time\_over\_threshold** [float, optional] Time (s) that the voltage waveform must exceed *trig-ger\_threshold* for the antenna to trigger.

- **orientation** [array\_like, optional] Vector direction of the z-axis of the antenna.
- **amplification** [float, optional] Amplification to be applied to the signal pre-clipping. Note that the usual ARA electronics amplification is already applied without this.
- **amplifier\_clipping** [float, optional] Voltage (V) above which the amplified signal is clipped (in positive and negative values).
- **envelope\_amplification** [float, optional] Amplification to be applied to the signal after the typical ARA front end, before the envelope circuit.
- envelope\_method [{('hilbert', 'analytic', 'spice') + ('basic', 'biased', 'doubler', 'bridge', 'log amp')}, optional] String describing the circuit (and calculation method) to be used for envelope calculation. If the string contains "hilbert", the hilbert envelope is uesd. If the string contains "analytic", an analytic form is used to calculate the circuit output. If the string contains "spice", ngspice is used to calculate the circuit output. The default value "analytic" uses an analytic diode bridge circuit.
- **noisy** [boolean, optional] Whether or not the antenna should add noise to incoming signals.
- unique\_noise\_waveforms [int, optional] The number of expected noise waveforms needed for each received signal to have its own noise.

#### See also:

pyrex.custom.ara.antenna.ARAAntennaSystem Antenna system extending base ARA antenna with front-end processing.

pyrex. custom. ara. antenna. ARAAntenna Antenna class to be used for ARA antennas.

### **Attributes**

antenna [Antenna] Antenna object extended by the front end.

name [str] Name of the antenna.

**position** [array\_like] Vector position of the antenna.

- **trigger\_threshold** [float] Threshold (V) for trigger condition. Antenna triggers if the voltage value of the waveform exceeds this value.
- **time\_over\_threshold** [float] Time (s) that the voltage waveform must exceed *trigger\_threshold* for the antenna to trigger.
- **envelope\_amplification** [float] Amplification to be applied to the signal pre-clipping. Note that the usual ARA electronics amplification is already applied without this.
- envelope\_method [str] String describing the circuit (and calculation method) to be used for envelope calculation.
- **lead\_in\_time** [float] Lead-in time (s) required for the front end to equilibrate. Automatically added in before calculation of signals and waveforms.
- **is\_hit** Boolean of whether the antenna system has been triggered.
- **signals** The signals received by the antenna with front-end processing.
- waveforms The antenna system signal + noise for each triggered hit.
- **all\_waveforms** The antenna system signal + noise for all hits.

## **Methods**

Reset the antenna system to an empty state.
Apply front-end processes to a signal and return the
output.
Apply front-end processes to a signal and return the
output.
Signal + noise for the antenna system for the given
times.
Generate interpolated filter values for given frequen-
cies.
Check if the antenna system is triggered in a time
range.
Return the signal envelope based on the antenna's
envelope_method.
Creates a noise signal over the given times.
Process and store an incoming signal.
Sets the orientation of the antenna system.
Setup the antenna by passing along its init argu-
ments.
Check if the antenna triggers on a given signal.
Calculate a signal as processed by the tunnel diode.

## pyrex.custom.irex.antenna.EnvelopeHpol

ARA Hpol ("quad-slot") antenna system with front-end processing.

Consists of an ARA Hpol antenna with typical responses, front-end electronics, and amplifier clipping, but with an additional amplification and envelope circuit applied after all other front-end processing.

### **Parameters**

**name** [str] Name of the antenna.

**position** [array\_like] Vector position of the antenna.

**trigger\_threshold** [float] Threshold (V) for trigger condition. Antenna triggers if the voltage value of the waveform exceeds this value.

**time\_over\_threshold** [float, optional] Time (s) that the voltage waveform must exceed *trig-ger\_threshold* for the antenna to trigger.

**orientation** [array\_like, optional] Vector direction of the z-axis of the antenna.

**amplification** [float, optional] Amplification to be applied to the signal pre-clipping. Note that the usual ARA electronics amplification is already applied without this.

**amplifier\_clipping** [float, optional] Voltage (V) above which the amplified signal is clipped (in positive and negative values).

**envelope\_amplification** [float, optional] Amplification to be applied to the signal after the typical ARA front end, before the envelope circuit.

envelope\_method [{('hilbert', 'analytic', 'spice') + ('basic', 'biased', 'doubler', 'bridge', 'log amp')}, optional] String describing the circuit (and calculation method) to be used for envelope calculation. If the string contains "hilbert", the hilbert envelope is uesd. If the string contains "analytic", an analytic form is used to calculate the circuit output. If the string contains "spice", ngspice is used to calculate the circuit output. The default value "analytic" uses an analytic diode bridge circuit.

**noisy** [boolean, optional] Whether or not the antenna should add noise to incoming signals.

**unique\_noise\_waveforms** [int, optional] The number of expected noise waveforms needed for each received signal to have its own noise.

#### **Attributes**

antenna [Antenna] Antenna object extended by the front end.

name [str] Name of the antenna.

position [array\_like] Vector position of the antenna.

**trigger\_threshold** [float] Threshold (V) for trigger condition. Antenna triggers if the voltage value of the waveform exceeds this value.

**time\_over\_threshold** [float] Time (s) that the voltage waveform must exceed *trigger\_threshold* for the antenna to trigger.

**envelope\_amplification** [float] Amplification to be applied to the signal pre-clipping. Note that the usual ARA electronics amplification is already applied without this.

**envelope\_method** [str] String describing the circuit (and calculation method) to be used for envelope calculation.

is\_hit Boolean of whether the antenna system has been triggered.

**signals** The signals received by the antenna with front-end processing.

waveforms The antenna system signal + noise for each triggered hit.

**all\_waveforms** The antenna system signal + noise for all hits.

## **Methods**

<pre>clear([reset_noise])</pre>	Reset the antenna system to an empty state.
envelopeless_front_end(signal)	Apply front-end processes to a signal and return the
	output.
front_end(signal)	Apply front-end processes to a signal and return the
	output.
full_waveform(times)	Signal + noise for the antenna system for the given
	times.
<pre>interpolate_filter(frequencies)</pre>	Generate interpolated filter values for given frequen-
	cies.
is_hit_during(times)	Check if the antenna system is triggered in a time
	range.
make_envelope(signal)	Return the signal envelope based on the antenna's
	envelope_method.
make_noise(times)	Creates a noise signal over the given times.
	0

Continued on next page

Table	106 -	continued	from	previous	page

receive(signal[, direction, polarization,])	Process and store an incoming signal.
set_orientation([z_axis, x_axis])	Sets the orientation of the antenna system.
setup_antenna([center_frequency, bandwidth,	Setup the antenna by passing along its init argu-
])	ments.
trigger(signal)	Check if the antenna triggers on a given signal.
tunnel_diode(signal)	Calculate a signal as processed by the tunnel diode.

## pyrex.custom.irex.antenna.EnvelopeVpol

class pyrex.custom.irex.antenna.EnvelopeVpol (name, position, trigger\_threshold, time\_over\_threshold=0, orientation=(0, 0, 1), amplification=(0, 0, 1),

ARA Vpol ("bicone" or "birdcage") antenna system with front-end processing.

Consists of an ARA Vpol antenna with typical responses, front-end electronics, and amplifier clipping, but with an additional amplification and envelope circuit applied after all other front-end processing.

#### **Parameters**

name [str] Name of the antenna.

**position** [array\_like] Vector position of the antenna.

**trigger\_threshold** [float] Threshold (V) for trigger condition. Antenna triggers if the voltage value of the waveform exceeds this value.

**time\_over\_threshold** [float, optional] Time (s) that the voltage waveform must exceed *trig-ger\_threshold* for the antenna to trigger.

**orientation** [array\_like, optional] Vector direction of the z-axis of the antenna.

**amplification** [float, optional] Amplification to be applied to the signal pre-clipping. Note that the usual ARA electronics amplification is already applied without this.

**amplifier\_clipping** [float, optional] Voltage (V) above which the amplified signal is clipped (in positive and negative values).

**envelope\_amplification** [float, optional] Amplification to be applied to the signal after the typical ARA front end, before the envelope circuit.

envelope\_method [{('hilbert', 'analytic', 'spice') + ('basic', 'biased', 'doubler', 'bridge', 'log amp')}, optional] String describing the circuit (and calculation method) to be used for envelope calculation. If the string contains "hilbert", the hilbert envelope is uesd. If the string contains "analytic", an analytic form is used to calculate the circuit output. If the string contains "spice", ngspice is used to calculate the circuit output. The default value "analytic" uses an analytic diode bridge circuit.

noisy [boolean, optional] Whether or not the antenna should add noise to incoming signals.

unique\_noise\_waveforms [int, optional] The number of expected noise waveforms needed for each received signal to have its own noise.

## **Attributes**

antenna [Antenna] Antenna object extended by the front end.

**name** [str] Name of the antenna.

**position** [array\_like] Vector position of the antenna.

**trigger\_threshold** [float] Threshold (V) for trigger condition. Antenna triggers if the voltage value of the waveform exceeds this value.

**time\_over\_threshold** [float] Time (s) that the voltage waveform must exceed *trigger\_threshold* for the antenna to trigger.

**envelope\_amplification** [float] Amplification to be applied to the signal pre-clipping. Note that the usual ARA electronics amplification is already applied without this.

**envelope\_method** [str] String describing the circuit (and calculation method) to be used for envelope calculation.

**is\_hit** Boolean of whether the antenna system has been triggered.

**signals** The signals received by the antenna with front-end processing.

waveforms The antenna system signal + noise for each triggered hit.

**all\_waveforms** The antenna system signal + noise for all hits.

### Methods

Reset the antenna system to an empty state.
Apply front-end processes to a signal and return the
output.
Apply front-end processes to a signal and return the
output.
Signal + noise for the antenna system for the given
times.
Generate interpolated filter values for given frequen-
cies.
Check if the antenna system is triggered in a time
range.
Return the signal envelope based on the antenna's
envelope_method.
Creates a noise signal over the given times.
Process and store an incoming signal.
Sets the orientation of the antenna system.
Setup the antenna by passing along its init argu-
ments.
Check if the antenna triggers on a given signal.
Calculate a signal as processed by the tunnel diode.

## Custom Detectors (pyrex.custom.irex.detector)

Module containing customized detector geometry classes for IREX.

Designed to be flexible such that stations can be built up from any string types and the detector grid can be made up of stations or strings.

<pre>IREXString(x, y[, antennas_per_string,])</pre>	String of IREX Vpol antennas.
RegularStation(x, y[, strings_per_station,])	Station geometry with strings evenly spaced radially around the center.
	Continued on next page

## Table 108 – continued from previous page

CoxeterStation(x, y[, strings_per_station,])	Station geometry with center string and the rest evenly spaced radially.
StationGrid([stations, station_separation,])	Rectangular grid of stations or strings.

## pyrex.custom.irex.detector.IREXString

String of IREX Vpol antennas.

Sets the positions of antennas on string based on the parameters. Once the antennas have been built with build\_antennas, the object can be directly iterated over to iterate over the antennas (as if the object were just a list of the antennas).

### **Parameters**

- **x** [float] Cartesian x-position (m) of the string.
- **y** [float] Cartesian y-position (m) of the string.

antennas\_per\_string [float, optional] Total number of antennas to be placed on the string.

antenna\_separation [float or list of float, optional] The vertical separation (m) of antennas on the string. If float, all antennas are separated by the same constant value. If list, the separations in the list are the separations of neighboring antennas starting from the lowest up to the highest.

**lowest\_antenna** [float, optional] The Cartesian z-position (m) of the lowest antenna on the string.

### Raises

**ValueError** If test\_antenna\_positions is True and an antenna is found to be above the ice surface.

## See also:

pyrex.custom.irex.EnvelopeHpol ARA Hpol ("quad-slot") antenna system with front-end processing.

pyrex.custom.irex.EnvelopeVpol ARA Vpol ("bicone" or "birdcage") antenna system with frontend processing.

### **Notes**

This class is designed to be the lowest subset level of a detector. It can (and should) be used for the subsets of some other Detector subclass to build up a full detector. Then when its "parent" is iterated, the instances of this class will be iterated as though they were all part of one flat list.

## Attributes

**antenna\_positions** [list] List (potentially with sub-lists) of the positions of the antennas generated by the set\_positions method.

subsets [list] List of the antenna or detector objects which make up the detector.

**test\_antenna\_positions** [boolean] Class attribute for whether or not an error should be raised if antenna positions are found above the surface of the ice (where simulation behavior is ill-defined). Defaults to True.

### Methods

build_antennas(trigger_threshold[,])	Creates antenna objects at the set antenna positions.
clear([reset_noise])	Reset the detector to an empty state.
set_positions(x, y[, antennas_per_string,])	Generates antenna positions along the string.
triggered([antenna_requirement,])	Check if the string is triggered based on its current
	state.

## pyrex.custom.irex.detector.RegularStation

Station geometry with strings evenly spaced radially around the center.

Sets the positions of strings around the station based on the parameters. Supports any string type and passes extra keyword arguments on to the string class. Once the antennas have been built with build\_antennas, the object can be directly iterated over to iterate over the antennas (as if the object were just a list of the antennas).

#### **Parameters**

- **x** [float] Cartesian x-position (m) of the station.
- y [float] Cartesian y-position (m) of the station.

strings\_per\_station [float, optional] Number of strings to be placed evenly around the station.

station\_diameter [float, optional] Diameter (m) of the circle around which strings are placed.

**string\_type** [optional] Class to be used for creating string objects for *subsets*.

\*\*string\_kwargs Keyword arguments to be passed on to the \_\_init\_\_ methods of the string\_type class.

## Raises

**ValueError** If test\_antenna\_positions is True and an antenna is found to be above the ice surface.

### See also:

pyrex.custom.irex.EnvelopeHpol ARA Hpol ("quad-slot") antenna system with front-end processing.

pyrex.custom.irex.EnvelopeVpo1 ARA Vpol ("bicone" or "birdcage") antenna system with frontend processing.

**IREXString** String of IREX Vpol antennas.

### **Notes**

This class is designed to have string-like objects (which are subclasses of Detector) as its *subsets*. Then whenver an object of this class is iterated, all the antennas of its strings will be yielded as in a 1D list.

### **Attributes**

**antenna\_positions** [list] List (potentially with sub-lists) of the positions of the antennas generated by the set\_positions method.

subsets [list] List of the antenna or detector objects which make up the detector.

**test\_antenna\_positions** [boolean] Class attribute for whether or not an error should be raised if antenna positions are found above the surface of the ice (where simulation behavior is ill-defined). Defaults to True.

### **Methods**

build_antennas(*args, **kwargs)	Creates antenna objects at the set antenna positions.
clear([reset_noise])	Reset the detector to an empty state.
set_positions(x, y[, strings_per_station,])	Generates antenna positions around the station.
triggered([antenna_requirement,])	Check if the station is triggered based on its current
	state.

## pyrex.custom.irex.detector.CoxeterStation

Station geometry with center string and the rest evenly spaced radially.

Sets the positions of strings around the station based on the parameters. Supports any string type and passes extra keyword arguments on to the string class. Once the antennas have been built with build\_antennas, the object can be directly iterated over to iterate over the antennas (as if the object were just a list of the antennas).

### **Parameters**

- x [float] Cartesian x-position (m) of the station.
- y [float] Cartesian y-position (m) of the station.
- **strings\_per\_station** [float, optional] Number of strings to be placed around the station. Note that the first string is always placed at the center and the rest of the strings are placed evenly around that center string.

**station\_diameter** [float, optional] Diameter (m) of the circle around which strings are placed.

**string type** [optional] Class to be used for creating string objects for *subsets*.

\*\*string\_kwargs Keyword arguments to be passed on to the \_\_init\_\_ methods of the string\_type class.

### Raises

**ValueError** If test\_antenna\_positions is True and an antenna is found to be above the ice surface.

## See also:

pyrex.custom.irex.EnvelopeHpol ARA Hpol ("quad-slot") antenna system with front-end processing. pyrex.custom.irex.EnvelopeVpo1 ARA Vpol ("bicone" or "birdcage") antenna system with frontend processing.

**IREXString** String of IREX Vpol antennas.

#### **Notes**

This class is designed to have string-like objects (which are subclasses of Detector) as its *subsets*. Then whenver an object of this class is iterated, all the antennas of its strings will be yielded as in a 1D list.

#### Attributes

**antenna\_positions** [list] List (potentially with sub-lists) of the positions of the antennas generated by the set\_positions method.

subsets [list] List of the antenna or detector objects which make up the detector.

**test\_antenna\_positions** [boolean] Class attribute for whether or not an error should be raised if antenna positions are found above the surface of the ice (where simulation behavior is ill-defined). Defaults to True.

### **Methods**

build_antennas(*args, **kwargs)	Creates antenna objects at the set antenna positions.
clear([reset_noise])	Reset the detector to an empty state.
set_positions(x, y[, strings_per_station,])	Generates antenna positions around the station.
triggered([antenna_requirement,])	Check if the station is triggered based on its current
	state.

## pyrex.custom.irex.detector.StationGrid

Rectangular grid of stations or strings.

Sets the positions of stations in a square layout if possible, otherwise in a rectangular layout (drops any extra stations). Supports any station type (including string types) and passes extra keyword arguments on to the station class. Once the antennas have been built with build\_antennas, the object can be directly iterated over to iterate over the antennas (as if the object were just a list of the antennas).

## **Parameters**

**stations** [float, optional] Number of stations to be placed.

station\_separation [float, optional] Distance (m) between adjacent stations.

**station type** [optional] Class to be used for creating station objects for *subsets*.

\*\*station\_kwargs Keyword arguments to be passed on to the \_\_init\_\_ methods of the station\_type class.

### Raises

**ValueError** If test\_antenna\_positions is True and an antenna is found to be above the ice surface.

**Warning:** If the number of *stations* provided does not divide nicely into a rectangle, extra stations may be dropped without warning. For example, if *stations* is 5, then a 2x2 grid will be created and the last station will be silently dropped.

### See also:

IREXString String of IREX Vpol antennas.

**RegularStation** Station geometry with strings evenly spaced radially around the center.

CoxeterStation Station geometry with center string and the rest evenly spaced radially.

#### **Notes**

This class is designed to have station-like or string-like objects (which are subclasses of Detector) as its *subsets*. Then whenver an object of this class is iterated, all the antennas of its strings will be yielded as in a 1D list

#### Attributes

**antenna\_positions** [list] List (potentially with sub-lists) of the positions of the antennas generated by the set\_positions method.

subsets [list] List of the antenna or detector objects which make up the detector.

**test\_antenna\_positions** [boolean] Class attribute for whether or not an error should be raised if antenna positions are found above the surface of the ice (where simulation behavior is ill-defined). Defaults to True.

### **Methods**

build_antennas(*args, **kwargs)	Creates antenna objects at the set antenna positions.
clear([reset_noise])	Reset the detector to an empty state.
set_positions([stations,])	Generates antenna positions around the station.
triggered([station_requirement,])	Check if the detector is triggered based on its current
	state.

# **VERSION HISTORY**

# 7.1 Version 1.8.2

### **New Features**

- Added CylindricalGenerator, RectangularGenerator, CylindricalShadowGenerator, and RectangularShadowGenerator classes to provide options for generation volumes and how to account for shadowing by the Earth. RectangularShadowGenerator has the same behavior as the existing ShadowGenerator, so ShadowGenerator is being deprecated.
- Added ability to add Detector (and Antenna or AntennaSystem) objects into a CombinedDetector for ease of use.
- Added ability to multiply (and divide) Signal objects by numeric types.
- Added support for total events thrown in simulation, accessed by the File.total\_events\_thrown attribute of file readers.

## **Changes**

- Separated Particle.weight into Particle.survival\_weight and Particle. interaction\_weight. Now Particle.weight serves as a convenience attribute which gives the product of the two weights.
- Changed FileGenerator to read from simulation output files rather than numpy files. For the time being numpy files can be read with NumpyFileGenerator.
- All generator classes now have a count attribute for keeping track of the total number of events thrown.

# **Bug Fixes**

- Fixed error in ARAAntenna signal amplitudes introduced in version 1.8.1.
- Fixed minor bugs in File interfaces.

## **Performance Improvements**

• Changed AskaryanSignal charge profile and RAC calculations to accept numpy arrays. Should result in marginal improvements in signal calculation speed.

# 7.2 Version 1.8.1

### **New Features**

- Added ability to write (and subsequently read) simulation data files using File objects.
- File I/O supports HDF5 files, but should be considered to be in a public-beta state until the release of version 1.9.0.
- EventKernel now accepts event\_writer and triggers arguments for writing simulation data to output files.

## **Changes**

- ThermalNoise now uses Rayleigh-distributed amplitudes in frequency space by default.
- Handling of signal polarizations has been more closely integrated with the ray tracer; RayTracer. propagate() now propagating the polarization vector as well as the signal.
- 3 dB splitter effect moved from ARAAntenna.response() to ARAAntennaSystem.front\_end() for a more logical separation of antenna and front-end.
- Adjusted default noise rms of ARIANNAAntennaSystem to the expected value in ARIANNA.

## **Bug Fixes**

- Corrected signal polarization calculation.
- Fixed calculation of fresnel factors in surface reflection.
- Fixed bug in antenna gains of asymmetric antennas for theta angles near 180 degrees.
- Corrected effective height of antennas modeled by WIPL-D (i.e. LPDA).

## 7.3 Version 1.8.0

## **New Features**

- Added model of the ARIANNA LPDA based primarily on the implementation in NuRadioReco.
- Added Antenna.is\_hit\_mc and AntennaSystem.is\_hit\_mc which test noise-only triggers to determine whether a triggered antenna as truly triggered by signal or not.
- Added require\_mc\_truth argument to Detector.triggered() to toggle whether a true Monte Carlo signal trigger (described above with Antenna.is\_hit\_mc) is required for a detector trigger.
- Added AntennaSystem.lead\_in\_time which allows front-end systems time to equilibrate before waveforms are recorded.

## **Changes**

• Antenna.waveforms and Antenna.all\_waveforms now include all relevant signals in the waveform during that time, similar to Antenna.full\_waveform().

7.2. Version 1.8.1 176

• ARAAntenna.interpolate\_filter() moved to ARAAntennaSystem. interpolate\_filter(), since this better matches the logical location of the front-end electronics.

## **Bug Fixes**

- Fixed error in calculation of ARA Hpol polarization gain.
- Corrected amplification of ARAAntennaSystem (previously was silently ignored).
- Corrected tunnel diode and other triggers to use standard deviation from mean rather than rms.
- Fixed accidental duplication of antennas when Detector.build\_antennas() is called more than once.
- Fixed numerical issue when checking that antenna axes are perpendicular.

# 7.4 Version 1.7.0

### **New Features**

- Moved pyrex.custom.ara module into main PyREx package instead of being a plug-in.
- All docstrings now follow numpy docstring style.
- Added particle types and interaction information to Particle class.
- Added Interaction classes GQRSInteraction and CTWInteraction for defining different neutrino interaction models. Preferred model (CTWInteraction) aliased to NeutrinoInteraction.
- Added ShadowGenerator.get\_vertex(), ShadowGenerator.get\_direction(),
   ShadowGenerator.get\_particle\_type(), ShadowGenerator.get\_exit\_points(),
   and ShadowGenerator.get\_weight() methods for generating neutrinos more modularly.
- Added *Event* class for holding a tree of *Particle* objects. *Event* objects are now returned by generators and the *EventKernel*.
- Added ZHSAskaryanSignal class for the Zas, Halzen, Stanev parameterization of Askaryan pulses. Mostly for comparison purposes.

## **Changes**

- ShadowGenerator.create\_particle() changed to ShadowGenerator.create\_event() and now returns an *Event* object.
- Generator classes moved to pyrex.generation module.
- Signal.ValueTypes changed to Signal.Type to match Particle.Type and Interaction. Type.
- FastAskaryanSignal changed to ARVZAskaryanSignal. This class is still the preferred parameterization aliased to AskaryanSignal.
- Arguments of *AskaryanSignal* changed to take a *Particle* object rather than taking its parameters individually.
- Removed unused SlowAskaryanSignal.
- Now that AskaryanSignal can handle different particle and shower types, secondary particle generation was added to determine shower fractions: NeutrinoInteraction.em\_frac and NeutrinoInteraction.had\_frac.

7.4. Version 1.7.0

• Changed IREX envelope antennas to be an envelope front-end on top of an ARA antenna. Results in IREXAntennaSystem becoming EnvelopeHpol and EnvelopeVpol.

# 7.5 Version 1.6.0

#### **New Features**

- EventKernel can now take arguments to specify the ray tracer to be used and the times array to be used in signal generation.
- Added shell scripts to more easily work with git branching model.

#### **Changes**

- ShadowGenerator energy\_generator argument changed to energy and can now take a function or a scalar value, in which case all particles will have that scalar value for their energy.
- EventKernel now uses pyrex. IceModel as its ice model by default.
- Antenna.receive() method (and receive() method of all inheriting antennas) now uses direction argument instead of origin argument to calculate directional gain.
- Antenna.clear() and Detector.clear() functions can now optionally reset the noise calculation by using the reset\_noise argument.
- Antenna classes can now set the unique\_noise\_waveforms argument to specify the expected number of unique noise waveforms needed.
- ArasimIce.attenuation\_length() changed to more closely match AraSim.
- IceModel reverted to AntarcticIce with new index of refraction coefficients matching those of ArasimIce.
- prem\_density() can now be calculated for an array of radii.

#### **Performance Improvements**

- Improved performance of slant\_depth() calculation.
- Improved performance of IceModel.attenuation\_length() calculation.
- Using the Antenna unique\_noise\_waveforms argument can improve noise waveform calculation speed (previously assumed 100 unique waveforms were necessary).

#### **Bug Fixes**

- Fixed received direction bug in EventKernel, which had still been assuming a straight-ray path.
- Lists in function keyword arguments were changed to tuples to prevent unexpected mutability issues.
- Fixed potential errors in BasicRayTracer and BasicRayTracePath.

7.5. Version 1.6.0 178

# 7.6 Version 1.5.0

### **Changes**

- Changed structure of Detector class so a detector can be built up from strings to stations to the full detector.
- Detector.antennas attribute changed to Detector.subsets, which contains the pieces which make up the detector (e.g. antennas on a string, strings in a station).
- Iterating the Detector class directly retains its effect of iterating each antenna in the detector directly.

#### **New Features**

- Added:meth'Detector.triggered' and Detector.clear() methods.
- Added two new neutrino generators ListGenerator and FileGenerator designed to pull pre-generated Particle objects.

### **Bug Fixes**

• Preserve value\_type of Signal objects passed to IREXAntennaSystem.front\_end().

# 7.7 Version 1.4.2

#### **Performance Improvements**

• Improved performance of FastAskaryanSignal by reducing the size of the convolution.

#### **Changes**

Adjusted time step of signals generated by kernel slightly (2000 steps instead of 2048).

# 7.8 Version 1.4.1

#### **Changes**

- Improved ray tracing and defaulted to the almost completely analytical SpecializedRayTracer and SpecializedRayTracePath classes as RayTracer and RayTracePath.
- Added ray tracer into EventKernel to replace PathFinder completely.

# 7.9 Version 1.4.0

#### **New Features**

• Implemented full ray tracing in the RayTracer and RayTracePath classes.

7.6. Version 1.5.0 179

# 7.10 Version 1.3.1

#### **New Features**

- Added diode bridge rectifier envelope circuit analytic model to irex.frontends and made it the default analytic envelope model in :classs:'IREXAntennaSystem'.
- Added allow\_reflection attribute to EventKernel class to determine whether ReflectedPathFinder solutions should be allowed.

### **Changes**

• Changed neutrino interaction model to include all neutrino and anti-neutrino interactions rather than only charged-current neutrino (relevant for ShadowGenerator class).

# 7.11 Version 1.3.0

#### **New Features**

• Added and implemented ReflectedPathFinder class for rays which undergo total internal reflection and subsequently reach an antenna.

## **Changes**

• Change AksaryanSignal angle to always be positive and remove < 90 degree restriction (Alvarez-Muniz, Romero-Wolf, & Zas paper suggests the algorithm should work for all angles).

#### **Performance Improvements**

• Improve performance of ice index calculated at many depths.

## 7.12 Version 1.2.1

#### **New Features**

• Added Antenna.set\_orientation() method for setting the z\_axis and x\_axis attributes appropriately.

### **Bug Fixes**

• Fixed bug where Antenna.\_convert\_to\_antenna\_coordinates() function was returning coordinates relative to (0,0,0) rather than the antenna's position.

7.10. Version 1.3.1 180

# 7.13 Version 1.2.0

### **Changes**

- Changed custom module to a package containing irex module.
- custom package leverages "Implicit Namespace Package" structure to allow plug-in style additions to the package in either the user's ~/.pyrex-custom/directory or the ./pyrex-custom directory.

## 7.14 Version 1.1.2

#### **New Features**

- Added Signal.with\_times() method for interpolation/extrapolation of signals to different times.
- Added Antenna.full\_waveform() and Antenna.is\_hit\_during() methods for calculation of waveform over arbitrary time array and whether said waveform triggers the antenna, respectively.
- Added IREXAntenna.front\_end\_processing() method for processing envelope, amplifying signal, and downsampling result (downsampling currently inactive).

### **Changes**

- Change Antenna.make\_noise() to use a single master noise object and use ThermalNoise. with\_times() to calculate noise at different times.
  - To ensure noise is not obviously periodic (for <100 signals), uses 100 times the recommended number of frequencies, which results in longer computation time for noise waveforms.

### 7.15 Version 1.1.1

### **Changes**

- Moved ValueTypes inside Signal class. Now access as Signal.ValueTypes.voltage, etc.
- Changed signal envelope calculation in custom IREXAntenna from hilbert transform to a basic model. Spice
  model also available, but slower.

### 7.16 Version 1.1.0

#### **New Features**

- Added Antenna.directional\_gain() and Antenna.polarization\_gain() methods to base Antenna.
  - Antenna.receive() method should no longer be overwritten in most cases.
  - Antenna now has orientation defined by z\_axis and x\_axis.
  - antenna\_factor and efficiency attributes added to Antenna for more flexibility.

7.13. Version 1.2.0 181

- Added value\_type attribute to Signal class and derived classes.
  - Current value types are ValueTypes.undefined, ValueTypes.voltage, ValueTypes. field, and ValueTypes.power.
  - Signal objects now must have the same value\_type to be added (though those with ValueTypes. undefined can be coerced).

### **Changes**

- Made units consistent across PyREx.
- Added ability to define Antenna noise by RMS voltage rather than temperature and resistance if desired.
- Allow DipoleAntenna to guess at effective\_height if not specified.

### **Performance Improvements**

• Increase speed of IceModel.\_\_atten\_coeffs() method, resulting in increased speed of attenuation length calculations.

# 7.17 Version 1.0.3

#### **New Features**

Added custom module to contain classes and functions specific to the IREX project.

# 7.18 Version 1.0.2

### **New Features**

• Added Antenna.make\_noise() method so custom antennas can use their own noise functions.

#### **Changes**

- Allow passing of numpy arrays of depths and frequencies into most IceModel methods.
  - IceModel.gradient() must still be calculated at individual depths.
- Added ability to specify RMS voltage of ThermalNoise without providing temperature and resistance.
- Removed (deprecated) Antenna.isHit().

#### **Performance Improvements**

- Allowing for IceModel to calculate many attenuation lengths at once improves speed of PathFinder.
  propagate().
- Improved speed of PathFinder.time\_of\_flight() and PathFinder.attenuation() (and improved accuracy to boot).

7.17. Version 1.0.3

# 7.19 Version 1.0.1

### **Changes**

• Changed Antenna to not require a temperature and frequency range if no noise is produced.

#### **Bug Fixes**

- Fixed bugs in AskaryanSignal that caused the convolution to fail.
- Fixed bugs resulting from converting IceModel.temperature() from Celsius to Kelvin.

# 7.20 Version 1.0.0

- Created PyREx package based on original notebook.
- Added all signal classes to produce full-waveform Askaryan pulses and thermal noise.
- Changed Antenna class to DipoleAntenna to allow Antenna to be a base class.
- Changed Antenna.isHit() method to Antenna.is\_hit property.
- Introduced IceModel alias for AntarcticIce (or any future preferred ice model).
- Moved AntarcticIce.attenuationLengthMN() to its own NewcombIce class inheriting from AntarcticIce.
- Added PathFinder.propagate() to propagate a Signal object in a customizable way.
- Changed naming conventions to be more consistent, verbose, and "pythonic":
  - AntarcticIce.attenuationLength() becomes AntarcticIce.
    attenuation\_length().
  - In pyrex.earth\_model, RE becomes EARTH\_RADIUS.
  - In pyrex.particle, neutrino\_interaction becomes NeutrinoInteraction.
  - In pyrex.particle, NA becomes AVOGADRO\_NUMBER.
  - particle class becomes Particle namedtuple.
  - Particle.vtx becomes Particle.vertex.
  - Particle.dir becomes Particle.direction.
  - Particle. E becomes Particle. energy.
  - In pyrex.particle, next\_direction() becomes random\_direction().
  - ${\sf shadow\_generator}$  ShadowGenerator.
  - PathFinder.exists() method becomes PathFinder.exists property.
  - PathFinder.getEmittedRay() method becomes PathFinder.emitted\_ray property.
  - PathFinder.getPathLength() method becomes PathFinder.path\_length property.
  - PathFinder.propagateRay() split into PathFinder.time\_of\_flight() (with corresponding PathFinder.tof property) and PathFinder.attenuation().

7.19. Version 1.0.1

# 7.21 Version 0.0.0

Original PyREx python notebook written by Kael Hanson:

https://gist.github.com/physkael/898a64e6fbf5f0917584c6d31edf7940

7.21. Version 0.0.0 184

**CHAPTER** 

**EIGHT** 

# **GITHUB README**

# 8.1 PyREx - (Python package for an IceCube Radio Extension)

PyREx (**Py**thon package for an IceCube **R**adio **Ex**tension) is, as its name suggests, a Python package designed to simulate the measurement of Askaryan pulses via a radio antenna array around the IceCube South Pole Neutrino Observatory. The code is designed to be modular so that it can also be applied to other askaryan radio antennas (e.g. the ARA and ARIANNA collaborations).

### 8.1.1 Useful Links

- Source (GitHub): https://github.com/bhokansonfasig/pyrex
- · Documentation: https://bhokansonfasig.github.io/pyrex/
- Release notes: https://bhokansonfasig.github.io/pyrex/build/html/versions.html

## 8.1.2 Getting Started

### Requirements

PyREx requires python version 3.6+ as well as numpy version 1.13+, scipy version 0.19+, and h5py version 2.7+. After installing python from https://www.python.org/downloads/, the required packages can be installed with pip as follows, or they will be installed automatically by simply installing pyrex as specified in the next section.

```
pip install numpy>=1.13
pip install scipy>=0.19
pip install h5py>=2.7
```

### Installing

The easiest way to get the PyREx package is using pip as follows

```
pip install git+https://github.com/bhokansonfasig/pyrex#egg=pyrex
```

Note that since PyREx is not currently available on PyPI, a simple pip install pyrex will not have the intended effect.

### **Optional Dependencies**

The following packages are not required for running PyREx by default, but may be useful or required for running some specific parts of the code:

### matplotlib

Recommended version: 2.1+

Used for creating plots in example code and auxilliary scripts.

### **PySpice**

Recommended version: 1.1

Used by IREX sub-package for some complex front-end circuits. Not needed for default front-ends.

## 8.1.3 Examples

For examples of how to use PyREx, see the usage page and the examples page in the documentation, or the python notebooks in the examples directory.

# 8.1.4 Contributing

Contributions to the code base are mostly handled through pull requests. Before contributing, for more information please read the contribution page in the documentation.

#### 8.1.5 Authors

• Ben Hokanson-Fasig

#### 8.1.6 License

MIT License

Copyright (c) 2018 Ben Hokanson-Fasig

# **BIBLIOGRAPHY**

- [1] A. Connolly et al, ANITA Note #76, "Thermal Noise Studies: Toward A Time-Domain Model of the ANITA Trigger." https://www.phys.hawaii.edu/elog/anita\_notes/060228\_110754/noise\_simulation.ps
- [1] Dziewonski, Adam M.; Anderson, Don L. (June 1981), "Preliminary reference Earth model." Physics of the Earth and Planetary Interiors. **25** (4), 297–356 (1981).
- [1] E. Zas, F. Halzen, T. Stanev, "Electromagnetic pulses from high-energy showers: implications for neutrino detection", Physical Review D **45**, 362-376 (1992).
- [1] J. Alvarez-Muniz et al, "Practical and accurate calculations of Askaryan radiation." Physical Review D **84**, 103003 (2011).
- [2] K.D. de Vries et al, "On the feasibility of RADAR detection of high-energy neutrino-induced showers in ice." Astropart. Phys. **60**, 25-31 (2015).
- [3] J. Alvarez-Muniz & E. Zas, "EeV Hadronic Showers in Ice: The LPM effect." ICRC proceedings, 17-25 (1999).
- [1] A. Connolly et al, ANITA Note #76, "Thermal Noise Studies: Toward A Time-Domain Model of the ANITA Trigger." https://www.phys.hawaii.edu/elog/anita\_notes/060228\_110754/noise\_simulation.ps
- [1] Dziewonski, Adam M.; Anderson, Don L. (June 1981), "Preliminary reference Earth model." Physics of the Earth and Planetary Interiors. **25** (4), 297–356 (1981).
- [1] R. Gandhi et al, "Ultrahigh-Energy Neutrino Interactions." Physical Review D 58, 093009 (1998).
- [1] A. Connolly et al, "Calculation of High Energy Neutrino-Nucleon Cross Sections and Uncertainties Using the MSTW Parton Distribution Functions and Implications for Future Experiments." Physical Review D 83, 113009 (2011).

# **PYTHON MODULE INDEX**

# р

```
pyrex.antenna, 84
pyrex.custom.ara.antenna, 128
pyrex.custom.ara.detector, 138
pyrex.custom.arianna.antenna, 146
pyrex.custom.irex.antenna, 162
pyrex.custom.irex.detector, 169
pyrex.custom.irex.frontends, 161
pyrex.detector, 87
pyrex.earth_model, 90
pyrex.generation, 105
pyrex.ice_model, 92
pyrex.internal_functions,72
pyrex.io, 115
pyrex.kernel, 114
pyrex.particle, 100
pyrex.ray_tracing,94
pyrex.signals, 76
```

# **INDEX**

Symbols	С
_read_amplifier_data() (in module	CombinedDetector (class in pyrex.detector), 90
pyrex.custom.arianna.antenna), 147	convert_hex_coords() (in module
_read_directionality_data() (in module	pyrex.custom.ara.detector), 138
pyrex.custom.ara.antenna), 128	CoxeterStation (class in pyrex.custom.irex), 158
_read_filter_data() (in module	CoxeterStation (class in
pyrex.custom.ara.antenna), 128	pyrex.custom.irex.detector), 172
_read_response_data() (in module	CTWInteraction (class in pyrex.particle), 104
pyrex.custom.arianna.antenna), 147	CylindricalGenerator (class in pyrex), 63 CylindricalGenerator (class in pyrex.generation),
A	107
AlbrechtStation (class in pyrex.custom.ara), 125	CylindricalShadowGenerator (class in pyrex),
AlbrechtStation (class in pyrex.custom.ara), 125  AlbrechtStation (class in	66
pyrex.custom.ara.detector), 142	CylindricalShadowGenerator (class in
AntarcticIce (class in pyrex.ice_model), 92	pyrex.generation), 109
Antenna (class in pyrex), 56	D.
Antenna (class in pyrex.antenna), 84	D
AntennaSystem (class in pyrex), 59	Detector (class in pyrex), 60
AntennaSystem (class in pyrex.detector), 88	Detector (class in pyrex.detector), 89
ARAAntenna (class in pyrex.custom.ara.antenna), 129	DipoleAntenna (class in pyrex), 57
ARAAntennaSystem (class in	DipoleAntenna (class in pyrex.antenna), 86
pyrex.custom.ara.antenna), 133	DipoleTester (class in pyrex.custom.irex.antenna),
ArasimIce (class in pyrex.ice_model), 93	163
ARAString (class in pyrex.custom.ara), 121	E
ARAString (class in pyrex.custom.ara.detector), 138 ARIANNAAntenna (class in	<del>_</del>
ARIANNAAntenna (class in pyrex.custom.arianna.antenna), 148	EmptySignal (class in pyrex), 53 EmptySignal (class in pyrex.signals), 77
ARIANNAAntennaSystem (class in	EnvelopeHpol (class in pyrex.custom.irex), 153
pyrex.custom.arianna.antenna), 149	EnvelopeHpol (class in pyrex.custom.irex.antenna),
ARVZAskaryanSignal (class in pyrex.signals), 80	166
AskaryanSignal (in module pyrex), 54	EnvelopeSystem (class in
AskaryanSignal (in module pyrex.signals), 81	pyrex.custom.irex.antenna), 164
D	EnvelopeVpol (class in pyrex.custom.irex), 155
В	EnvelopeVpol (class in pyrex.custom.irex.antenna),
BaseGenerator (class in pyrex.generation), 106	168
<pre>basic_envelope_model() (in module</pre>	Event (class in pyrex), 63
pyrex.custom.irex.frontends), 161	Event (class in pyrex.particle), 101
BasicRayTracePath (class in pyrex.ray_tracing), 94	EventKernel (class in pyrex), 69
BasicRayTracer (class in pyrex.ray_tracing), 97	EventKernel (class in pyrex.kernel), 114
bridge_rectifier_envelope_model() (in	F
module pyrex.custom.irex.frontends), 162	
	File (class in pyrex), 71

File (class in pyrex.io), 116 FileGenerator (class in pyrex), 68 FileGenerator (class in pyrex.generation), 113 flatten() (in module pyrex.internal_functions), 72 FunctionSignal (class in pyrex), 53 FunctionSignal (class in pyrex.signals), 78	Particle (class in pyrex.particle), 101 PathFinder (class in pyrex.ray_tracing), 99 PhasedArrayString (class in pyrex.custom.ara), 123 PhasedArrayString (class in pyrex.custom.ara.detector), 140
G	prem_density() (in module pyrex), 61
	<pre>prem_density() (in module pyrex.earth_model), 91 pyrex.antenna (module), 84</pre>
GaussianNoise ( <i>class in pyrex.signals</i> ), 82 GQRSInteraction ( <i>class in pyrex.particle</i> ), 103	pyrex.custom.ara.antenna (module), 128
	pyrex.custom.ara.detector(module), 138
H	pyrex.custom.arianna.antenna (module), 146
HDF5Reader (class in pyrex.io), 116	pyrex.custom.irex.antenna(module), 162
HDF5Writer (class in pyrex.io), 117	pyrex.custom.irex.detector(module), 169
HexagonalGrid (class in pyrex.custom.ara), 126	pyrex.custom.irex.frontends (module), 161
HexagonalGrid (class in pyrex.custom.ara.detector),	pyrex.detector (module), 87 pyrex.earth_model (module), 90
143	pyrex.generation (module), 105
HpolAntenna (class in pyrex.custom.ara), 119	pyrex.ice_model (module), 92
HpolAntenna (class in pyrex.custom.ara.antenna), 135 HpolBase (class in pyrex.custom.ara.antenna), 130	pyrex.internal_functions (module), 72
npolbase (class in pyrex.custom.ara.amemia), 130	pyrex.io (module), 115
	pyrex.kernel (module), 114
IceModel (in module pyrex), 61	pyrex.particle (module), 100
IceModel (in module pyrex.ice_model), 94	pyrex.ray_tracing (module), 94
Interaction (class in pyrex.particle), 102	pyrex.signals(module),76
IREXString (class in pyrex.custom.irex), 156	R
IREXString (class in pyrex.custom.irex.detector), 170	RayTracePath (in module pyrex), 69
1	RayTracePath (in module pyrex.ray_tracing), 99
L	RayTracer (in module pyrex), 69
lazy_property() (in module	RayTracer (in module pyrex.ray_tracing), 99
pyrex.internal_functions), 74	RectangularGenerator (class in pyrex), 64
LazyMutableClass (class in pyrex.internal_functions), 75	RectangularGenerator (class in pyrex.generation), 108
ListGenerator (class in pyrex), 68 ListGenerator (class in pyrex.generation), 111	RectangularShadowGenerator (class in pyrex), 67
LPDA (class in pyrex.custom.arianna), 145 LPDA (class in pyrex.custom.arianna.antenna), 151	RectangularShadowGenerator (class in pyrex.generation), 110
M	ReflectedPathFinder (class in pyrex.ray_tracing), 100
mirror_func() (in module pyrex.internal_functions), 73	RegularStation (class in pyrex.custom.ara), 124 RegularStation (class in pyrex.custom.ara)
N	pyrex.custom.ara.detector), 141
NeutrinoInteraction (in module pyrex), 62	Regular Station (class in pyrex.custom.irex), 157
NeutrinoInteraction (in module pyrex, 02) NeutrinoInteraction (in module pyrex.particle),	RegularStation (class in pyrex.custom.irex.detector), 171
105	
Newcombice (class in pyrex.ice_model), 92	S
normalize() (in module pyrex.internal_functions), 72 NumpyFileGenerator (class in pyrex.generation),	ShadowGenerator (class in pyrex.generation), 111
112	Signal (class in pyrex), 52
	Signal (class in pyrex.signals), 76
P	<pre>slant_depth() (in module pyrex), 61 slant_depth() (in module pyrex.earth_model), 91</pre>
Particle (class in nyrer) 62	5 Larie_acper() (in mounte pyrex.eurin_mouet), 91

Index 190

```
SpecializedRayTracePath (class in pyrex.ray_tracing), 95
SpecializedRayTracer (class in pyrex.ray_tracing), 98
StationGrid (class in pyrex.custom.irex), 160
StationGrid (class in pyrex.custom.irex.detector), 173
```

# Τ

ThermalNoise (class in pyrex), 54
ThermalNoise (class in pyrex.signals), 82

## V

VpolAntenna (class in pyrex.custom.ara), 120 VpolAntenna (class in pyrex.custom.ara.antenna), 136 VpolBase (class in pyrex.custom.ara.antenna), 132

# Ζ

ZHSAskaryanSignal (class in pyrex.signals), 79

Index 191