


GEO GATEWAY



USER GUIDE

VERSION 2.2



GeoGateway

Tools for Analysis,
Modeling, and
Response Using
Geodetic Imaging
and Global
Positioning System
Products.



Copyright © 2021

Government Sponsorship Acknowledgement

Table of Contents

Overview	1-2
Map Tools	3-7
UAVSAR	8-14
Global Navigation Satellite System (GNSS)	15-24
Seismicity	25-27
Nowcast	28-33
Magnitude	34-36
Disloc	37-43
Studies	44-47
3D Imaging	48-50
Feedback	51
References	52-53

Acknowledgments

The User Guide was developed primarily by:

Megan Ani Mirkhanian (mmirkhan@uci.edu), University of California, Irvine
Lisa Grant Ludwig (lgrant@uci.edu), University of California, Irvine

With assistance from other GeoGateway team members:

Andrea Donnellan (andrea.donnellan@jpl.nasa.gov), Jet Propulsion Laboratory
Jay Parker (jay.w.parker@jpl.nasa.gov), Jet Propulsion Laboratory

Other GeoGateway contributing members include:

John Rundle (jbrundle@ucdavis.edu), University of California, Davis
Jun Wang (wang208@iu.edu), Indiana University
Marlon Pierce (marpierc@iu.edu), Indiana University
Yu (Marie) Ma (yuma@iu.edu), Indiana University
Nicholas Mowery (nbmowery@iu.edu), Indiana University
Robert A Granat (granat@gmail.com), State University of New York
Michael B Heflin (michael.b.heflin@jpl.nasa.gov), Jet Propulsion Laboratory
Margaret T Glasscoe (margaret.t.glasscoe@jpl.nasa.gov), Jet Propulsion Laboratory
Nathan Pulver (nathan.pulver@jpl.nasa.gov), Jet Propulsion Laboratory
Gregory Lyzenga (lyzenga@hmc.edu), Harvey Mudd College

Overview

GeoGateway is a data product search and analysis gateway for scientific discovery, field use, and disaster response.

GeoGateway consists of NASA's geodetic imaging products including InSAR (interferometric synthetic aperture radar) and GNSS (Global Navigation Satellite System), integrated with earthquake faults datasets, seismicity, and models.



Figure 1: UAVSAR Science Aircraft. (Figure adapted from Jet Propulsion Laboratory (JPL))

Goals

- Bridge the gap between production and end-use of data products
- Simplify discovery of geodetic imaging and GPS data products
- Enable researchers to explore and integrate data products
- Allow researchers to easily share, publish, and collaborate



The purpose of GeoGateway is to increase the value of existing geodetic imaging products from NASA as well as GNSS products from USGS to enable researchers to explore and integrate these data products.



Figure 2: UAVSAR Science Aircraft. (Figure adapted from Jet Propulsion Laboratory (JPL))

The screenshot shows the GeoGateway homepage. At the top left is the URL "geo-gateway.org". Below it is the "GEO GATEWAY" logo with the tagline "Tools for Analysis, Modeling, and Response Using Geodetic Imaging Products". A large "Welcome to GEO GATEWAY" banner is centered. To the right is a world map highlighting North America and South America. In the center, there is descriptive text about GeoGateway and its access information. On the left, there is a sidebar with navigation links and a map of the United States.

geo-gateway.org

GEO GATEWAY Tools for Analysis, Modeling, and Response Using Geodetic Imaging Products

Welcome to **GEO GATEWAY**

GeoGateway is a web map-based science gateway supported by NASA's AIST program.

To access GeoGateway click on the provided link (<https://geo-gateway.org>).

Tools display option

Zoom In

Zoom Out

Maptools UAVSAR GNSS Seismicity
Nowcast Magnitude Disloc Studies
3D Imaging Feedback Help

GeoGateway includes 11 tabs

1. Map Tools
2. UAVSAR
3. GNSS
4. Seismicity
5. Nowcast
6. Magnitude
7. Disloc
8. Studies
9. 3D Imaging
10. Feedback
11. Help

Pacific Ocean

Map data: © Esri


Figure 3: Overview of GeoGateway's tabs

Maptools

UCERF3 Faults

(Uniform California Earthquake Rupture Forecast, version 3)

The U.S. Geological Survey ([USGS](https://pubs.usgs.gov/of/2013/1165/)) UCERF3 faults (<https://pubs.usgs.gov/of/2013/1165/>) can be plotted with 4 color options for user preference. To insert the fault lines, check the box next to “UCERF3 Faults.” Users are given the option to choose from either black, yellow, red, or grey faults. To obtain more information regarding a particular fault, click on the fault and a popup with information pertaining to the selected fault will appear.



Quaternary Faults

Quaternary faults demonstrate geologic evidence of coseismic surface deformation in the Quaternary (the past 1.6 million years). As shown in *figure 2*, different age Quaternary faults are labeled and colored according to when they last ruptured. Class B faults are either those faults that might not extend deep enough to be considered a possible source for causing earthquakes or there is insufficient geological evidence to be classified in another class. Users may select the Quaternary fault(s) of choice by checking and unchecking the boxes shown under “USGS Faults Database.” (Data source: <https://doi.org/10.5066/F7S75FJM>)




Figure 2: Quaternary faults within Maptools tab.



KML Uploader

KML (Keyhole Markup Language) is a file format used to display geographic data.

For *example*, visiting the USGS website below,

<https://earthquake.usgs.gov/earthquakes/search/>

allows for users to search through an earthquake catalog in which the selected earthquake data can be downloaded as a KML file and uploaded into GeoGateway as shown in *figure 3*.

Once uploaded into GeoGateway, the KML file(s) are displayed.

By clicking the box next to the uploaded KML file, the file will be displayed on the map.

In this case, the KML file named “USGS_Earthquakes” is displayed on the map.




Figure 3: USGS earthquakes catalog output options





Figure 4: Downloaded KML file from USGS displayed on the map



Show State Boundaries

To display state boundaries within the United States, check the box next to “Show State Boundaries.”




Figure 5: Maptools, United States boundary layer

Show Coastlines

To display coastlines, check the box next to “Show Coastlines.”



Figure 6: Maptools, global coastlines layer



Show Current Location

By clicking on “Show Current Location” users are able to view their current location on the map.




Figure 7: Maptools, show current location option

View map in different modes

By toggling over to right corner, choose either “ArcGIS Topo Map,” “ArcGIS Light Map,” “ArcGIS Dark Map.”




Figure 8: Maptools, different map coloring options



UAVSAR

UAVSAR (Uninhabited Aerial Vehicle Synthetic Aperture Radar), is an airborne, L-band, fully polarimetric radar, housed in a pod that is mounted to the belly of a piloted Gulfstream III aircraft. Interferometric radar images, or interferograms, are generated from repeat passes flown over a site of interest. Interferometric radar observations are made from the swaths received, which are approximately 22 km wide and typically between 100 and 300 km long (Donnellan et al., 2014).




Figure 1: Demonstration of the uninhabited aerial vehicle flight path and how the swath path is determined. (Figure adapted from (Christian Wolff, 2008))

The wide swath of the UAVSAR instrument results in a large incidence angle variation across the swath. Near range incidence angles are approximately 25° whereas far range incidence angles are approximately 65° resulting in a 40° incidence angle variation across the swath.

Since repeat pass radar interferometric measurements only capture the component of surface motion along the line-of-sight vector, it is important to account for imaging geometry variations. Thus, a constant vertical displacement will exhibit a line-of-sight displacement that varies as the cosine of the look angle (angle between aircraft nadir vector and line of sight) and a constant cross-track displacement will exhibit a line-of-sight displacement that varies as the sine of the look angle.

Different fault geometries and types of slip produce different surface motions and project differently onto a line-of-sight change between points on the ground and instrument.

Interpreting line-of-sight changes for fault motions requires assumptions for the style of faulting. Slip of a certain orientation, corresponding to fault slip, can be projected onto line-of-sight between the ground and instrument using the following parameters (Donnellan et al., 2014).




Figure 2: UAVSAR Parameters and Fault Parameters. (Figure adapted from (Donnellan et al., 2014))




To the right, we see two different radar images creating the interferogram (shows the change or difference from each radar image).



Figure 3: Demonstration the difference between two swaths in the same location on two different dates, which results in an interferogram. (Figure adapted from (Jet Propulsion Laboratory, 2014))



Example UAVSAR uses:



To upload UAVSAR interferograms, follow either method (1) or (2)

1. The “flight name/path” directly finds the flight name and path wanted
2. The “latitude, longitude” option returns all flight swaths crossing paths with those coordinates.



*Note options to draw an area or drop a pin can assist users to finding an interferogram




Figure 4: Demonstrates option 1 (inputting flight name/path)




Figure 5: Demonstrates option 2 (inputting a latitude and longitude)

As shown in figure 5 the option is given to filter by date by inputting (mm/dd/yyy), narrowing the selection.

To further look into the surface fracturing, click on “Show Alternate Coloring” below the “Filter by Date” option. Notice the units of displacement change to “cm.”
 *Note to set the swath opacity, move the blue dot to the left (less visibility) or right (more visibility).




Figure 6: Demonstrates the change from the original unwrapped phase from figure 5, to displacement.



To look closer into the UAVSAR swaths,

1. Search for a flight path.
2. Select the flight path by clicking on it (flight path selection should be a darker color from the unselected paths).
3. Click on the UAVSAR flight path that is shown on the map, allowing the Line-of-Sight (LOS) tool to appear.




Figure 7: Line-of-Sight tool

Place the two markers on any location along the UAVSAR swath, to look at different ground range change.

The LOS tool allows users to study ground range change (cm), along a distance (km).




Figure 8: Line-of-Sight tool set to specific distance

Users are able to choose a distance of focus by moving as shown in figure 8.



GNSS

Global Navigation Satellite System (GNSS) is any satellite constellation which provides positioning, navigation, and timing (PNT) services on a global or regional basis (*Other Global Navigation Satellite Systems (GNSS)*, 2020). One of the systems GNSS includes is the United States-owned Global Positioning System (GPS).

GNSS operates via satellites sending information on two radio-frequency carriers to the receivers on earth as shown on *figure 1*. The GNSS receivers have both an antenna and processing unit. The antenna receives the satellite signals, and the receiver processes the information and turns it into measurements.




Figure 1: Network of the Americas (NOTA) GNSS station portraying the primary components of the platform. (Figure adapted from (UNAVCO, 2020))




Figure 2: Demonstrates how GNSS data detects fault movement along the San Andreas Fault. (Figure adapted from (USGS, n.d.))

GeoGateway's GNSS tool can be used to measure plate motion and strain accumulation across faults. *Figure 2* demonstrates how fault motion is measured along a segment of the San Andreas Fault. The top of the figure (square shape) demonstrates the initial state of the fault at the date of observation, while the bottom of figure (parallelogram) shows how at a later date of observation, the fault has moved.




Figure 3: GeoGateway's GNSS tab, which includes five options of analysis; Velocities, Coseismic, Postseismic, Displacement, and Model.

GeoGateway offers five tools for analyzing GNSS data as shown in figure 3. Note the parameters in bold are required and the remaining parameters that are not in bold use default values set by GeoGateway which will be discussed within this section.

Parameters




Figure 4: Overview of the geographic coordinate system (Figure adapted from (Britannica, n.d.))

Center Latitude (see *figure 4*) in decimal degrees
Center Longitude (see *figure 4*) in decimal degrees

*Positive latitude is above the equator (N), and negative latitude is below the equator (S). Positive longitude is east of the prime meridian, while negative longitude is west of the prime meridian.

Longitude Span and **Latitude Span** are measured in degrees, allowing the user to create a specified parameter.

Ref. Site is the GNSS station site that the velocity vector data will be referenced to. A map with the sites can be located through the website listed below, or users may access the list of sites by clicking on “**Stations**” in the Ref. Site section of the GNSS tab. Once a location is chosen, type the 4-letter code in the box.

<https://sideshow.jpl.nasa.gov/post/series.html>

Scale allows the user to control the velocity vector length scaling.
 Recommend setting to **320** mm/yr/deg.


Output Prefix allows users to name the dataset output.



- Minimize Marker Size
- Display absolute verticals
- Include error ellipses

“Minimize marker size”  allows users to make GNSS site markers smaller as shown in the image below.


“Display absolute verticals”



Error bars are graphical tools used to illustrate the pair-wise correlation that exists between computed values (Error Ellipses). By checking the box “**Include error ellipses**,” a black ellipse at the tip of the velocity vector, representing error is displayed, as shown in the image below.



Once data is inputted, click on “Run”. There is an option to download the velocity text table and the horizontal and vertical KML files as shown in the image on the right.



By selecting the “Velocities” option, the velocities of different GNSS stations are seen relative to the reference frame.

As shown in *figure 5* below “CCCC” is set as the reference point.




Figure 5: Velocities Analysis

Each vector shows the velocity of a single GNSS station as the Earth moves.

The tail of the vector is pinned at the GNSS station, and the length of the vector shows how fast the GNSS station is moving. The other end of the line, away from the marker, is the direction the GNSS station is moving.

Vertical displacements are shown by red (uplift) or blue (subsidence) circles. The larger the circle, the more displacement.



By clicking on a GNSS station, three time series graphs appear.




Figure 6: Time Series for WNRA station




Figure 7: Time series tables, including latitude, longitude, and height



The time series shows how far the station has moved. The top graph shows latitude (cm) versus time (years). The black dots are the data points and the red line is the best fit line to the entire dataset. In this example, we see as time progresses the station moves closer to the North. For the longitude versus time graph (middle graph) we see that the GNSS station is moving to the West. The bottom graph shows the vertical height versus time which is decreasing. The green lines that intersect vertically on the graph are locations where there are jumps in the data.

Coseismic and postseismic data can be selected by specifying a time period during or after an earthquake which a user wants to focus on.




Figure 8: Crustal deformation is spatially and temporally non-uniform as strain accumulates over prolonged time scales, where its later rapidly released as earthquakes, and readjusts post-seismically. Numerous types of data from different sections of the earthquake cycle (as shown in the figure above) are required for analysis.

Figure 8 illustrates the earthquake cycle, and typical rates of deformation in the coseismic and postseismic periods.



GNSS Data Analysis

Select GNSS data models

Coseismic

Center Latitude		
Center Longitude		
Longitude Span	in degree	
Latitude Span	in degree	
Epoch	YYYY-MM-DD	
Ref. Site	4-letter code	<input type="button" value="Stations"/>
Scale	320 mm/yr/deg	
Coseismic Win.	0.1 years	
Output Prefix		
<input type="checkbox"/> Minimize Marker Size <input type="checkbox"/> Display absolute verticals <input type="checkbox"/> Include error ellipses		
<input type="button" value="Run"/>		
Data source: <u>GNSS Time Series</u>		

Figure 9: Coseismic offset refers to the time during an earthquake until a rupture ends.

GNSS Data Analysis

Select GNSS data models

Postseismic

Center Latitude		
Center Longitude		
Longitude Span	in degree	
Latitude Span	in degree	
Epoch	YYYY-MM-DD	
Ref. Site	4-letter code	<input type="button" value="Stations"/>
Scale	320 mm/yr/deg	
Coseismic Win.	0.1 years	
Postseismic Win.	2 years	
Output Prefix		
<input type="checkbox"/> Minimize Marker Size <input type="checkbox"/> Display absolute verticals <input type="checkbox"/> Include error ellipses		
<input type="button" value="Run"/>		
Data source: <u>GNSS Time Series</u>		

Figure 10: Postseismic deformation refers to the time after a large earthquake when deformation occurs.

To generate coseismic and postseismic displacements, the user must consider “Epoch” and “Coseismic Window” and “Postseismic Window.” The Epoch is the time of the event and the window is any time period of choice.



The displacement tool avoids use of any fit parameters and instead uses daily time series data to directly compute displacements between any two times which have measurements (Heflin et al., 2020).

GNSS Data Analysis
Select GNSS data models

Displacement

Draw an area on map Clear GNSS Layers

Center Latitude		
Center Longitude		
Longitude Span	in degree	
Latitude Span	in degree	
Epoch 1	YYYY-MM-DD	
Epoch 2	YYYY-MM-DD	
Ref. Site	4-letter code	<u>Stations</u>
Scale	320 mm/yr/deg	
Av. Win. 1	10 days	
Av. Win. 2	10 days	
Output Prefix		
<input type="checkbox"/> Use NGL data <input type="checkbox"/> Minimize Marker Size <input type="checkbox"/> Display absolute verticals <input type="checkbox"/> Include error ellipses		
Run		
Data source: <u>GNSS Time Series</u>		

Figure 11: Displacement Analysis



GNSS Data Analysis

Select GNSS data models

Model ▼

Draw an area on map Clear GNSS Layers

Center Latitude	
Center Longitude	
Longitude Span	in degree
Latitude Span	in degree
Epoch 1	YYYY-MM-DD
Epoch 2	YYYY-MM-DD
Ref. Site	4-letter code
Scale	320 mm/yr/deg
Output Prefix	

Minimize Marker Size

Display absolute verticals

Include error ellipses

Run

Data source:
[GNSS Time Series](#)

Figure 12: Model Analysis

The model tool uses all fit parameters to compute a displacement between two user specified times (Heflin et al., 2020).



Seismicity

The seismicity tab allows users to display earthquakes in a region over a specified period. *Figure 1* displays GeoGateway’s Seismicity tab. The tab is split into two sections, “Recent Earthquakes from USGS” and “Search Earthquake Catalog.”




Figure 1: GeoGateway’s Seismicity tab



The tab allows users to view recent earthquakes from USGS data. The USGS data can also be found on the USGS website earthquake.usgs.gov/earthquakes/map/. As shown in *figure 2*, the displayed earthquake events are color coded with the hotter colors representing recent events and the cooler colors representing less recent events.




Figure 2: GeoGateway's Seismicity tab - displaying seismic events greater than magnitude 2.5 in the last week.

Filters, such as **M > 1.0, Last Day**, **M > 2.5, Last week**, and **M > 4.5, Last Month** can be selected as shown in *figure 2*. As shown below, additional filters may be applied to generate recent earthquakes.



To search for a particular earthquake event, input specific parameters pertaining to the event in the **Search Earthquake Catalog** section.

Box 1-4 require users to input the latitudes and longitudes of the specified region. Users have the option to use the “Draw an area on map” feature to generate earthquake events onto the map based on the region drawn by the user.




Figure 3: Draw an area on map option

Box 5-8 require data regarding the range of date and time of interest.

Box 9-10 require the range of chosen magnitude.

Box 11 requires the user to scale the size of the icon of the earthquake event, by inputting a number (larger number = larger icon).

By clicking on **Search Catalog** earthquake events based on the given parameters inputted by the user are shown on the map.

To clear the inputted USGS data, click on **Clear USGS Layers** right below to **Draw an area on map** option.

Moreover, users are given the option to download “USGS KML” and “GeoJSON.”

Ending Time	UU:UU:UU
Minimum Magnitude	3.0
Maximum Magnitude	10.0
Icon Display Scale	1
Search Catalog	
Download USGS KML Download USGS GeoJSON	

Figure 4: Download USGS KML and GeoJSON.



Nowcast

GeoGateway's Nowcast tab consists of useful tools to evaluate earthquake hazard and risk generated by the [Open Hazards Group](#).

Users have the option to choose from

- Global Forecast
 - Heat Map (M>6.5, 1 Year)
 - Warm colors represent high risk and cool colors represent low risk
- California Forecast
 - Heat Map (M>5, 1 Year)
 - Warm colors represent high risk and cool colors represent low risk
- Display California faults
- Display Global Disaster Alerting Coordination System (GDACS) Data
- Generate Nowcast Plots, resulting in earthquake potential scores





Figure 1: Nowcast tab

By clicking on the “Global Forecast” option, users are able generate a heat map which forecasts magnitudes greater than 6.5 in a year. *Figure 2* displays the risk associated for such forecasts along portions of the coast of Alaska, Canada and northern United States. High risk is represented through warm colors and low risk is represented as cool colors. By clicking on any part of the layer, users are able to see the risk associated with the location of interest.






Figure 2: Display of global forecast heat map along the coast of parts of Alaska, Canada, and Northern United States

By clicking on the “California Forecast” option, users are able generate a heat map which forecasts magnitudes greater than 5 in a year. *Figure 3* displays the risk associated for such forest within California and parts of Nevada.




Figure 3: Display of California forecast heat map within California and parts of Nevada



By clicking on “show GDACS Data ($\geq 5.5M$)” option, Global Disaster Alerting Coordination System (GDACS) data for earthquakes greater than or equal to 5.5 is displayed. *Figure 4* displays GDACS data off the coast of Fiji.




Figure 4: Global Disaster Altering Coordination System data off the coast of Fiji

The second section of the tab allows for users to generate Nowcast Plots pertaining to the potential score that characterizes the current state of progress of a defined geographic region through its normal earthquake “cycle.” Nowcasting is the prediction of the present, the very future and the very recent past, and it uses proxy data to estimate the current dynamical state of a driven complex system such as earthquakes, neural networks, or the financial markets (Donnellan et al., 2021).

Seismic nowcasting uses counts of small earthquakes as proxy data to determine the natural time. The count of small earthquakes since the last large earthquake is the natural time that has elapsed in the last large earthquake. The proxy data allows for an estimate of the current dynamical state of an earthquake fault system.






Figure 5: Nowcast plots for LocationA





Figure 6: Earthquake Potential Score for LocationA (Pasadena, CA)



The Earthquake Potential Score (EPS) data for the chosen location, in this case "LocationA" can be viewed.

$$\text{EPS} = P\{n \leq n(t)\}$$

P = Cumulative Distribution Function (CDF) of small earthquakes occurring between large earthquakes

$n(t)$ = the number of small earthquakes since the last large earthquake
 n = small earthquakes since the last large earthquake.

EPS values for *figure 6* portray magnitudes greater than $M = 6$, 100 km within the specified region.

The figure portrays that the small earthquakes count for today is 32 and the EPS Value is 80.0%.

Figure 7's data displays “Number-Magnitude” statistics. The blue squares represent all the earthquakes ≥ 3 and the lower green circles show earthquakes $3 \leq X < 6.5$.




Figure 7: Number-Magnitude for Earthquakes near LocationA (Pasadena, CA)

The last figure located on the far right displays a map of earthquakes with a magnitude ≥ 6.0 near San Bernardino as of 1970 to 2018. The blue circle centered on San Bernardino has a radius equal to 100 km.




Figure 8: Earthquakes greater than Magnitude 6.0 near LocationA (Pasadena, CA) from 1970/06/24 to 2018/10/22



Magnitude

Magnitude is the physical size of an earthquake. In *figure 1*, notice the magnitude scale in correspondence to the earthquake's energy equivalence.




Figure 1: Seismic wave energy in earthquakes and energy equivalents. (Figure adapted from (Incorporated Research Institutes for Seismology, IRIS))

Both seismic moment and moment magnitude (M_w) can be calculated using GeoGateway's moment magnitude calculator. As shown in *figure 2*, **seismic moment** equates to the product of the shear modulus (μ), displacement (D), and rupture area (A), and **moment magnitude** equates to the product of two-thirds the log base of seismic moment, subtracted by 10.73.




Figure 2: Represents the seismic moment and moment magnitude equations. (Figure adapted from (Vista Heights Middle School))

The shear modulus (μ) is

3.2×10^{11} dynes/cm² in the crust
 7.5×10^{11} dynes/cm² in the mantle

The area (km²) as shown in *figure 2* can be found by using the length (L) and width (W), of the rupture. The slip (meters) is the average displacement (D) of the rupture.

Step 1: To begin calculations,
click on the “Magnitude” tab

Step 2: Once the tab is open, input the
fault length that ruptured in kilometers


Step 3: Input the fault width that ruptured, in
units of kilometers

Step 4: Input the distance the fault moved (slip),
in units of meters

Step 5: Input the shear modulus in units of $\frac{10^{11} \text{ dyne}}{\text{cm}^2}$

Step 6: Click on Calculate





GeoGateway has set the moment magnitude 6.0 Napa, CA earthquake as default. The results indicate a seismic moment of 1.7×10^{25} dyne*cm and a moment magnitude of 6.1.



Disloc

Elastic dislocation models are commonly used to analyze inversion on faults following the event of an earthquake (Chen et al., 2020). In 1985, Yoshimitsu Okada (Ph.D.) proposed a formula which calculated displacement in an isotropic, uniform elastic half space. The formula can calculate coseismic deformation caused by any fault within the elastic half space (Okada, 1985). Okada's dislocation theory, which is the most commonly used dislocation theory, is often used with InSAR. InSAR monitors the surface coseismic deformation field, and subsequently, Okada's theory is used to conduct fault slip inversion, calculating the coseismic strain stress field (Chen et al., 2020). Elastic dislocation models generated by Disloc can be used to geodetically measure deformation of an elastic medium due to slip from active faults (Avouac, n.d.).




Figure 1: Example of Okada's dislocation in an elastic half space (figure adapted from NASA's GeoGateway team).




Figure 2: Elastic Dislocation Fault Parameters (figure adapted from Harvey Mudd College)

In figure 2, the ***location*** of the fault is defined as the surface projection of the lower-left corner of the fault plane. The ***depth*** is represented as the z-coordinate of the fault's bottom edge. The depth is the absolute value of the z-coordinate. The ***dip*** angle is measured from horizontal (Harvey Mudd College, n.d.).

The **strike** angle is the orientation (measured clockwise from north) of the surface projection of the fault's horizontal edges. The **length** and **width** are the dimensions of the rectangular fault (Harvey Mudd College, n.d.).


U_1 is the strike slip component of fault slip (strike-slip dislocation U_1 greater than 0 identifies a right lateral motion).

U_2 is the dip slip component of fault slip (dip-slip dislocation U_2 greater than 0 identifies a reverse motion).


U_3 is the tensile component of fault slip (tensile dislocation U_3 greater than 0 identifies a tensile opening).


To run Disloc, visit the Disloc tab on GeoGateway and follow the following steps.

Step 1: Create an account on GeoGateway by visiting
<https://geo-gateway.org/auth/create-account>

Step 2: Log into GeoGateway by clicking on the “” button on the left corner found on GeoGateway’s homepage.

Step 3: On the upper right corner on GeoGateway’s homepage, click on “GeoGateway Develop,” and then click on “Workspace.”





Step 5: Users must upload their Disloc files into the area shown in the red box. Users have the option to change the experiment name and add a description by clicking on “Add a description.” Users may also change the “elevation,” “azimuth,” and “radar frequency,” of their choice as shown in the image to the right. Lastly, click on the green button, “Save and Launch.” Note the data might take a couple of minutes to load.

Experiment Name: Disloc on May 13, 2021 11:03 AM

Add a description

Project: Default Project

Application Configuration

Disloc Input File: Select file from storage OR Drop files here or browse (Max file upload size is 64 MB)

Elevation: 60

Azimuth: 0

Radar Frequency: 1.26


Allocation: Geo Default

Compute Resource: geogateway-vc-jetstream-cloud.org

Settings for queue cloud: 1 NODE COUNT, 0 CORE COUNT, 10 minutes TIME LIMIT

Save and Launch

To find the output files, click on the Erlenmeyer flask found on the left side of the page. There the output file name will be displayed. To view the output files, click on the experiment of interest.



Browse Experiments


Search Experiments Select an attribute to search by Select an experiment status to filter by Reset Search

Select a date range to filter by

Name	Application	Creation Time	Status	Actions
Disloc on May 12, 2021 11:49 AM	Disloc	a day ago	COMPLETED	Clone
Disloc on May 12, 2021 10:23 AM	Disloc	a day ago	COMPLETED	Clone
Disloc on May 12, 2021 9:57 AM	Disloc	mmirkhan	a day ago	COMPLETED Clone

Showing 1 - 3

In the image below, the experiment summary and output files are displayed. Now, users may download each of these files.



Geo Gateway

Experiment Summary Share 2 Clone

- Disloc Output
- [output.csv](#)
- Disloc-Standard-Error
- [Disloc.stderr](#)
- Disloc-Standard-Out
- [Disloc.stdout](#)
- KMZ Output File
- [output.csv.insar.kmz](#)

User Input Copy

- [4fault.txt](#)
- [input.txt](#)

	A	B	C
1	201 101 32.705002 -115.911331		
2	69.11097717285156 -60.93335342407227 -5		
3	14 45 1 1 -450 -600 0 33.14		
4	x y ux uy uz exx exy eyy		
5	-100.000002 -10.000000 -2.311e+00 6.078e-01 -3.776e-01 -2.695e-02 6.8		
6	-99.000002 -10.000000 -2.338e+00 6.166e-01 -3.813e-01 -2.741e-02 6.99		
7	-98.000000 -10.000000 -2.366e+00 6.256e-01 -3.850e-01 -2.787e-02 7.17		
8	-97.000000 -10.000000 -2.394e+00 6.348e-01 -3.887e-01 -2.835e-02 7.36		
9	-96.000002 -10.000000 -2.422e+00 6.442e-01 -3.925e-01 -2.884e-02 7.55		
10	-95.000002 -10.000000 -2.451e+00 6.538e-01 -3.963e-01 -2.933e-02 7.74		
11	-94.000002 -10.000000 -2.481e+00 6.635e-01 -4.002e-01 -2.984e-02 7.94		
12	-93.000000 -10.000000 -2.511e+00 6.735e-01 -4.041e-01 -3.036e-02 8.15		
13	-92.000002 -10.000000 -2.542e+00 6.837e-01 -4.081e-01 -3.089e-02 8.37		
14	-91.000000 -10.000000 -2.573e+00 6.939e-01 -4.120e-01 -3.142e-02 8.59		
15	-90.000000 -10.000000 -2.605e+00 7.048e-01 -4.162e-01 -3.199e-02 8.82		

Figure 3: output.csv

Figure 3 displays the output.csv file which shows the x, y, U₁, U₂, and U₃ (refer to figure 2), and exx, exy, and eyy (components of the surface strain) factors. For more information regarding the parameters used please refer to (Okada, 1985).



Referring to Step 5, users must upload a text file. The figure below shows what the text file must include.

Line 1: Latitude Longitude # (The latitude and longitude are the model origin location, corresponding to $x = 0, y = 0$. The $\#$ represents the generation parameter. This tells how you will specify the points at which you want calculated displacements. If it is 0, this means you will be giving it a list of arbitrary x, y points (good for irregularly distributed sites). If it is 1, this means you are asking for output at regularly spaced points on a rectangular grid)

[Example of line 1:](#) 32.705000 -115.911333 1

Line 2: $x_0 \ x_d \ x_e \ y_0 \ y_d \ y_e$ (Represents the grid: This consists of starting x -coordinate (km), increment in x -direction (km), number of steps in x -direction, starting y -coordinate (km), increment in y -direction (km), number of steps in y -direction).

[Example of line 2:](#) -100 1 201 -10 1 101

Line 3: x, y (km) from origin and strike (degrees) (x coordinate and y coordinate of the first fault and the strike angle of the fault, measured clockwise from north)

[Example of line 3:](#) 69.110979 -60.933355 -5

Line 4: fault type 0 for point dislocation and 1 for rectangular plane dislocation, depth, dip (degrees), lambda (λ), mu (μ), U_1 , U_2 , U_3 , length (km), width (km)

(Provide the vertical depth to the *bottom* of the fault, followed by the dip angle in degrees (zero for horizontal; 90° for vertical). The λ and μ are the Lamé elastic parameters, their absolute values are not important, only their ratio. For both lambda and mu, units are nominally Pascals (Pa), but in disloc, only their ratio is used, therefore the units cancel out. It is practical to set both to the value "1". Disloc then models the earth as an isotropic elastic solid with a Poisson Ratio of 0.25. $\lambda=\mu$ is the most common assumption for typical rocks. U_1 , U_2 , and U_3 are the amounts of relative slip to apply to the fault surface in the strike-slip, dip-slip, and tensile directions, respectively. Positive U_1 corresponds to *left-lateral motion* (opposite in sense to the San Andreas fault for example). Positive U_2 corresponds to *thrusting motion* with the hanging wall riding up over the foot wall (like the San Gabriel mountains for example). U_3 will not normally be used since ordinary earthquake faults involve motion only tangential to the fault plane. Finally, the length and width of the rectangular fault surface.)

[Example of line 4:](#) 1 14 45 1 1 -450 -600 0 33 14

Repeat the formatting from line 3 and line 4 for each additional fault.

[Example of line 5 \(same format as line 3\):](#) 56.877979 -45.030355 -48

[Example of line 6 \(same format as line 4\):](#) 1 15 75 1 1 -830 0 0 51 15

[Example of line 7 \(same format as line 3\):](#) 46.475979 -56.538355 132

[Example of line 8 \(same format as line 4\):](#) 1 14 60 1 1 -830 0 0 60 14

[Example of line 9 \(same format as line 3\):](#) 25.940979 -9.411355 -25

[Example of line 10 \(same format as line 4\):](#) 1 12 50 1 1 -100 0 0 18 12

Figure 4: Dislocation input data

To allow the output file to be shown on GeoGateway, return to the Disloc tab on the GeoGateway website and click on “Load Experiments” as shown in the image below. Once the experiments appear, click on the green highlighted text






Figure 5: Dislocation output data displayed on map on GeoGateway. The image is in correspondence to lines 1-4 from figure 4.




Figure 6: Dislocation output data displayed on map on GeoGateway. The image is in correspondence to lines 1-10 from figure 4.



Special Studies

GeoGateway's Special Studies tab lists products for demonstration purposes. The study includes wildfire burn areas and debris flows imaged with UAVSAR following the Southern California 2018 Woolsey Fire shown in figure (2) below; and the 2017 Montecito, California fire, in figure (4) below. See *Donnellan et al. 2018* for more information on the Montecito, CA fire.



from the Los Angeles Times)





Figure 1(a): Woolsey Fire and Hill fire perimeter






Figure 2(b): UAVSAR correlation image (1) of Woolsey fire. UAVSAR can see through smoke, clouds, and the dark of night.




Figure 2(c): UAVSAR correlation image (2) of Woolsey fire.





Figure 3: Debris flow on Highway 101 following the Thomas Fire in Montecito (figure adapted from courtesy of Trevor Hughes, USA TODAY)




Figure 4(a): The image displays UAVSAR high-resolution interferogram that has been despeckled, converted to four colors and contrast increased. Orange represents the disturbed areas, and debris flows can be seen extending from the fire scar south of the outline.






Figure 4(b): The image displays UAVSAR high-resolution correlation image that has been despeckled, converted to two colors and contrast increased. Purple represents the disturbed areas and are decorrelated, and debris flows can be seen extending from the fire scar.




Figure 4(c): Montecito debris flow optical image.



3D Imaging

Users can locate postseismic products of the Ridgecrest Earthquake (M6.4 (July 4, 2019) and M7.1 (July 5, 2019)) by navigating to the “3D Imaging” tab and clicking on the box labeled “Postseismic Products of Ridgecrest Earthquake.”

The data was collected by Andrea Donnellan and Gregory Lyzenga.



Figure 1: Earthquake Damage on California Hwy 178
figure adapted by (Ben Brooks, USGS)

More information regarding the data can be obtained by clicking on the citation below

[Andrea Donnellan, Gregory Lyzenga, Adnan Ansar, Christine Goulet, Jun Wang, Marlon Pierce; Targeted High-Resolution Structure from Motion Observations over the M_wMw 6.4 and 7.1 Ruptures of the Ridgecrest Earthquake Sequence. Seismological Research Letters doi: <https://doi.org/10.1785/0220190274>](https://doi.org/10.1785/0220190274)




Figure 2: Figures from 2019 Ridgecrest earthquake

2(a) Boxed location shows location of the Ridgecrest earthquakes. Picture adapted from (Jobe et al., 2020)

2(b) Shaking intensity levels associated with each contour color shown for Mw 7.1 earthquake event. Warm colors represent higher intensity and color colors represent lower intensity. Picture adapted from (USGS, 2020).

2(c) Shaking intensity levels associated with each contour color shown for Mw 6.4 earthquake event. Warm colors represent higher intensity and color colors represent lower intensity. Picture adapted from (USGS, 2020).

2(d) Road offset on the road at Naval Air Weapons Station China Lake (NAWSCL) from the M7.1 rupture (Ben Brooks, USGS).



The products included in the 3D Imaging tab comprise of,

1. **Inferred rupture traces and orthomosaic images** for the M6.4 earthquake and M7.1 earthquake, which can be selected by clicking on the corresponding box. The inferred rupture traces can be downloaded as a KML.
2. **Six point cloud** (in LAZ format), which can be downloaded for each earthquake by clicking on “Point Cloud” across the listed dates which range from 2019/07/09 to 2019/09/27. Further, clicking on the “2cm DSM” option will download a 2 cm Digital Surface Model (in LAZ format). A quality report can be accessed by clicking on “Report.”
3. **Digital Surface Model (DSM) and orthomosaic image**, which can be downloaded as a KMZ by clicking on “Products overview (kmz).”
4. **Data from Potee**, a viewer for large point cloud/LIDAR data sets, which can be accessed and viewed by clicking on "View Point Clouds." Potee allows for users to adjust the appearance, clip, measure, export, and complete several other actions to the orthomosaic images.
5. An **animated GIF** of the M7.1 earthquake, which can be accessed by clicking on the “Animated Gif” button under M7.1 products.

	Point Cloud	2cm DSM	Report
2019/07/09	Point Cloud	2cm DSM	Report
2019/07/11	Point Cloud	2cm DSM	Report
2019/07/15	Point Cloud	2cm DSM	Report
2019/07/22	Point Cloud	2cm DSM	Report
2019/08/08	Point Cloud	2cm DSM	Report
2019/09/27	Point Cloud	2cm DSM	Report
Products overview (kmz)		View Point Clouds	

	Point Cloud	2cm DSM	Report
2019/07/09	Point Cloud	2cm DSM	Report
2019/07/11	Point Cloud	2cm DSM	Report
2019/07/15	Point Cloud	2cm DSM	Report
2019/07/22	Point Cloud	2cm DSM	Report
2019/08/08	Point Cloud	2cm DSM	Report
2019/09/27	Point Cloud	2cm DSM	Report
Products overview (kmz)		View Point Clouds	

Figure 3: 3D Imaging tab content



The figure illustrates the GeoGateway 3D Imaging interface, showing a central map view with several arrows pointing to different components:

- Top Left:** A 3D point cloud visualization showing inferred rupture traces in orange on a terrain surface.
- Top Right:** A 3D point cloud visualization showing a large rectangular area with internal features.
- Bottom Left:** A 3D point cloud visualization showing inferred rupture traces in orange on a terrain surface.
- Bottom Right:** A 3D point cloud visualization showing a large rectangular area with internal features.
- Central Map View:** The main map shows the location of the ruptures in Salt Wells Valley, California. It includes labels for "SALT WELLS VALLEY", "Skytop", "2300 R", "7000 R", "E. Braman Rd.", and "118". Arrows point from the top-left and top-right 3D views to specific locations on the map. Arrows also point from the bottom-left and bottom-right 3D views to other locations on the map.
- Left Sidebar:** A detailed product overview page for the Ridgecrest Earthquake sequence.
 - Section Headers:** Postseismic Products of Ridgecrest Earthquake, 3D Imaging, Feedback, Help.
 - Checklist:**
 - Inferred Rupture Traces M6.4
 - Overview of orthomosaic image M6.4
 - Inferred Rupture Traces M7.1
 - Overview of orthomosaic image M7.1
 - M 6.4 products:**

Date	Type	Resolution	Action
2019/07/09	Point Cloud	2cm DSM	Report
2019/07/11	Point Cloud	2cm DSM	Report
2019/07/15	Point Cloud	2cm DSM	Report
2019/07/22	Point Cloud	2cm DSM	Report
2019/08/08	Point Cloud	2cm DSM	Report
2019/09/27	Point Cloud	2cm DSM	Report

[View Point Clouds](#)
 - M 7.1 products:**

Date	Type	Resolution	Action
2019/07/09	Point Cloud	2cm DSM	Report
2019/07/11	Point Cloud	2cm DSM	Report
2019/07/15	Point Cloud	2cm DSM	Report
2019/07/22	Point Cloud	2cm DSM	Report
2019/08/08	Point Cloud	2cm DSM	Report
2019/09/27	Point Cloud	2cm DSM	Report

[View Point Clouds](#)
 - [View Animated Gif](#)



Feedback

GeoGateway's feedback tab is designed for users to submit reports on a bug or feature, provide enhancement ideas or any suggestions, or report any other concerns pertaining to GeoGateway.

The screenshot shows the 'Feedback' tab of the GeoGateway interface. At the top, there is a navigation bar with tabs: Maptools, UAVSAR, GNSS, Seismicity, Nowcast, Magnitude, Disloc, Studies, 3D Imaging, Feedback (which is highlighted in black), and Help. Below the navigation bar is a 'Bug Report Form' section. It includes an 'Email (Optional)' input field, a 'Report Type' dropdown menu with options: Bug, Feature, Enhancement, and Other, and a 'Related Tool' dropdown menu with options: Map Tools, UAVSAR, GNSS, Seismicity, Nowcast, Magnitude, Disloc, Help, and Other. There is also a 'Description' input field and a 'Screenshots' section with a note: 'Use screenshots of related tool to help us solve the problem'. A file upload area says 'Drop files or click here to upload' with a blue arrow button. At the bottom, it says 'Powered by Qualtrics'.

Navigate to the “Feedback” tab.

Input email (optional).

Choose the report type. Users may also provide recommendations for the GeoGateway team by selecting “other.”

Choose the tool or tab to file the report on

Users should include a description on what they want to report.

Include screenshots if need be.

Left click on the blue box with the arrow to send in the report.



References:

- Avouac, J.-P. (n.d.). Appendix: On the use of the ‘Elastic Dislocations.’
[ftp://ftp.gps.caltech.edu/pub/avouac/Ge177/Presentations-old/\(10\) Appendix_Elastic_Dislocation.ppt](ftp://ftp.gps.caltech.edu/pub/avouac/Ge177/Presentations-old/(10) Appendix_Elastic_Dislocation.ppt)
- Britannica. (n.d.). Longitude geography.
<https://www.britannica.com/science/longitude>
- Chen, J., Tang, H., & Chen, W. (2020). Deep learning of the aftershock hysteresis effect based on the elastic dislocation theory. *Natural Hazards and Earth System Sciences*, 20(11), 3117–3134. <https://doi.org/10.5194/nhess-20-3117-2020>
- Donnellan, A., Parker, J., Heflin, M., Glasscoe, M., Lyzenga, G., Pierce, M., Wang, J., Rundle, J., Ludwig, L. G., Granat, R., Mirkhanian, M., & Pulver, N. (2021). Improving access to geodetic imaging crustal deformation data using GeoGateway. *Earth Science Informatics*. <https://doi.org/10.1007/s12145-020-00561-7>
- Donnellan, A., Parker, J., Hensley, S., Pierce, M., Wang, J., & Rundle, J. (2014). UAVSAR observations of triggered slip on the Imperial, Superstition Hills, and East Elmore Ranch Faults associated with the 2010 M 7.2 El Mayor-Cucapah earthquake. *AGU: Geochemistry, Geophysics, Geosystems*, 815–829. <https://doi.org/10.1002/2013GC005120>
- Donnellan, A., Parker, J., Milliner, C., Farr, T. G., Glasscoe, M., Lou, Y., Zheng, Y., & Hawkins, B. (2018). UAVSAR and Optical Analysis of the Thomas Fire Scar and Montecito Debris Flows: Case Study of Methods for Disaster Response Using Remote Sensing Products. *Earth and Space Science*, 5(7), 339–347. <https://doi.org/10.1029/2018EA000398>
- Harvey Mudd College. (n.d.). Elastic Dislocation Fault Parameters. 1–2.
<http://www.physics.hmc.edu/GL/misc/disloc.pdf>
- Heflin, M., Donnellan, A., Parker, J., Lyzenga, G., Moore, A., Ludwig, L. G., et al. (2020). Automated estimation and tools to extract positions, velocities, breaks, and seasonal terms from daily GNSS measurements: illuminating nonlinear Salton Trough deformation. *Earth and Space Science*, 7, e2019EA000644. <https://doi.org/10.1029/2019EA000644>
- Incorporated Research Institutions for Seismology (IRIS). (n.d.) How Often Do Earthquakes Occur? IRIS - Education and Outreach Series, 3. https://www.iris.edu/hq/inclass/fact-sheet/how_often_do_earthquakes_occur
- Jet Propulsion Laboratory. (2014). What is UAVSAR?
<https://uavstar.jpl.nasa.gov/education/what-is-uavstar.html>



- Jobe, J. A. T., Philibosian, B., Chupik, C., Dawson, T., Bennett, S. E. K., Gold, R., DuRoss, C., Ladinsky, T., Kendrick, K., Haddon, E., Pierce, I., Swanson, B., & Seitz, G. (2020). Evidence of Previous Faulting along the 2019 Ridgecrest, California, Earthquake Ruptures. *Bulletin of the Seismological Society of America*.
<https://doi.org/https://doi.org/10.1785/0120200041>
- Okada, Y. (1985). Internal deformation due to shear and tensile faults in a half-space. *Bulletin – Seismological Society of America*, 82(2), 1018–1040.
https://watermark.silverchair.com/BSSA0750041135.pdf?token=AQECAHi208BE49Ooa n9khhW_Ercy7Dm3ZL_9Cf3qfKAc485ysgAAAvowggL2BgkqhkiG9w0BBwagggLnMI IC4wIBADCCAtwGCSqGSIB3DQEHAeBglghkgBZQMEAS4wEQQM0wXyjLzqC9 G7ZjvwAgEQgIICrT9Ww8cdmlGOvsTkX_vITtpWyJGHuXAYQkjyJqRA
- Other Global Navigation Satellite Systems (GNSS). (2020). The Global Positioning System.
<https://www.gps.gov/systems/gnss/>
- Parker, J., Donnellan, A. and Glasscoe, M.T. (2021). Survey of Transverse Range Fire Scars in Ten Years of UAVSAR Polarimetry. *Earth and Space Science*, 8, e2021EA001644.
<https://doi.org/10.1029/2021EA001644>.
- UNAVCO. (2020). Network of the Americas (NOTA). <https://www.unavco.org/projects/major-projects/nota/nota.html>
- USGS. (n.d.). About GPS. <https://earthquake.usgs.gov/monitoring/gps/about.php>
- USGS. (2021). USGS Magnitude 2.5+ Earthquakes, Past Day.
<https://earthquake.usgs.gov/earthquakes/map/?extent=23.64452,-125.46387&extent=50.6808,-64.51172>
- Vista Heights Middle School. (n.d.). Modeling the Calculation of an Earthquakes Seismic Moment. <https://vhmsscience.weebly.com/seismic-moment-model.html>

