Table of Contents

- APEX Websocket Notification Bundle
 - Demo
 - Preview
 - Changelog
 - Installation and Configuration
 - o Installation Node.js Server
 - Install Node.js
 - Install Notification Package
 - Configure Notification Package
 - Installation Database
 - Database ACL
 - Oracle SSL Wallet
 - Compile the PL/SQL package
 - Installation APEX
 - Install Plugins
 - Usage
 - Node.js Server
 - REST-Service
 - ∘ PL/SQL API
 - List of global package variables
 - List of all procedures with all parameters
 - APEX
 - Init Websocket Notify Connection
 - Send Websocket Notify
 - Show Websocket Notify
 - ∘ <u>License</u>

APEX Websocket Notification Bundle

Purpose of this software bundle was to enable all APEX developers to use modern and state of the art web features like Node, Websockets and nice looking notifications in their applications.

This bundle includes all these features and simultaneously is designed to use all of them out of the box. This means:

- Ready to go Node.js websocket server especially for notifications using socket.io
- A native PL/SQL package to send all kinds of different messages/notifications using APEX_WEB_SERVICE
- APEX plugins for all kind of events that are needed by the notification system:
 - Initialize websocket connection to server
 - Send messages and notifications to users

Show different styled notifications on client side

Developers don't need to be experts in Javascript or JQuery and stuff like that (But as always, it's not a bad skill!;)). APEX & PL/SQL Know-How and a good knowledge of using Dynamic Actions should be enough to implement this notification bundle in your applications...

Infrastructure Diagram



Demo

A demo application is available under https://apex.danielh.de/ords/f?p=WSNOTIFY

And of course you find a APEX export (demo_app.sql) of it in <u>../apex/</u> folder. To use it just import the app and then go through the installation steps below. Under Shared Components --> Edit Application Definition --> Substitutions Strings, set

- G_WS_SERVER_HOST to the hostname or ip address of your node notification server
- G_WS_SERVER_PORT to the port of your node notification server
- **G_WS_SERVER_AUTHTOKEN** to your secure and random authToken of your node notification server (read further for more informations)

The demo includes all plugins and shows the most common preferences and possibilities.

Preview



Changelog

1.1.0 - Updated Javascript Libs (socket.io 1.5.1 & Alertify 1.8.0) / Send Websocket Notify Plugin enhancements

1.0.0 - Initial Release

Installation and Configuration

Installation Node.js Server

Install Node.js

It is required to have a up and running Node.js installation on your server. Either install it using a package manager, or download the latest version from <u>Nodejs homepage</u>...for example: - Ubuntu:

• Mac OS X (Homebrew):

```
brew install nodejs
```

• Windows: Download and install it from Nodejs homepage

npm is the package manager for Node applications. npm is used to install all required packages by the Node Websocket Notification Server...

Install Notification Package

- Copy the complete folder .../node/node-notify-server to your server
- change to this directory via command line:

```
cd /path/to/node-notify-server
```

• Install all dependencies

```
npm install
```

Start server

```
npm start
```

This should be everything to have the Notification Server up und running. To check that, you can point your web browser to http://[host-ip-of-server]:8080

There you should get a overview of all supported services by the Notification Server.

This helper pages are supported by the server:

- Overview Services: http://[host-ip-of-server]:8080
- Server Status Page: http://[host-ip-of-server]:8080/status
- Websocket Test Client: http://[host-ip-of-server]:8080/testclient

Configure Notification Package

You can change the default behavior of the server by editing the JSON config file ../node/node-notify-server/prefs.json

```
{
    "server": {
        "ip": "0.0.0.0", // listener ip address 0.0.0.0 for all interfaces
        "port": "8080", // listener port
        "authUser": "", // User for HTTP basic auth, empty means no user auth (only
REST-Interface)
```

```
"authPwd": "", // Password for HTTP basic auth, empty means no user auth
(only REST-Interface)
    "sslKeyPath": "", // FOR SSL: path to ssl key file (./certs/key.pem), empty
means no SSL/HTTPS
    "sslCertPath": "", // FOR SSL: path to ssl certificate file
(./certs/cert.pem), empty means no SSL/HTTPS
    "logging": true // logging to console on or off, for prod disable logging
},
    "socket": {
        "private": true, // activate private websocket room/namespace of server
        "public": true, // activate public websocket room/namespace of server
        "authToken": "please-change-me" // authentication token, client should have
the same to connect with websocket, please change it to some random string
}
```

After changing one of these settings, please restart the Node Notification Server.

SSL Support: - For test environments you can use the script ../node/node-notify-server/certs/create_cert.sh to create a self signed certificate - For production environments please get a officially signed certificate and place key.pem and cert.pem into the certs folder

Installation Database

Database ACL

All notifications are sent through web service requests. Therefore a ACL is needed, so you are allowed to connect to this host. Here is a example script, configure it to reflect your environment...

Oracle SSL Wallet

If you configured the Node Notification Server with SSL/HTTPS support, a Oracle SSL Wallet is needed by the database to communicate with the REST-Interface for sending notifications.

To manually create a wallet, either use Oracle Wallet Manager or create the wallet with openssl utils like: - Grab the certificate from your server <u>node-notify-server/certs</u> - Create the wallet on command line

```
openssl pkcs12 -export -in cert.pem -out ewallet.p12 -nokeys
```

- Place the wallet file on your database server
- Change the wallet path and password in <u>package specification</u> under "Websocket REST Call defaults / security defaults"
 - g_ssl_wallet_path: Path of Oracle SSL wallet
 - g_ssl_wallet_pwd: Password of Oracle SSL wallet

Compile PL/SQL package

- Change the global variables in the <u>package specification</u> under "Websocket REST Call defaults" to reflect your environment
 - g_ws_rest_host: Hostname or IP of Node Server
 - g_ws_rest_port: Port of Node Server
 - **g_ws_rest_proto:** Protocol of Node Server (http or https) if https, then "g_ssl_wallet_path" and "g_ssl_wallet_pwd" are required
 - g_ws_basic_auth_user: HTTP Basic Auth username of Node Server (REST-Interface)
 - g_ws_basic_auth_pwd: HTTP Basic Auth password of Node Server (REST-Interface)
- Connect to your database and compile the package spec and body (ws_notify_api.pks & ws_notify_api.pkb) from <u>../plsql</u> folder

Installation APEX

Install Plugins

The APEX part contains 3 plugins, you can find it in <u>../apex/plugins</u> folder. Just import these 3 files to your application and you are ready to go.

- Init Websocket Notify Connection dynamic_action_plugin_de_danielh_initwsnotifyconnection.sql
- Send Websocket Notify dynamic_action_plugin_de_danielh_sendwsnotify.sql
- Show Websocket Notify dynamic_action_plugin_de_danielh_showwsnotify.sql

For a detailed description of the plugins, read further under "Usage Section" or import the demo app sql file to your workspace.

Usage

Node.js Server

As mentioned in the installation steps, the node notification server component consists of 3 areas:

• REST-Interface

Sending messages and notifications to users which are connected to the websocket interface.

Websocket-Interface

Connecting and authenticating users against the node server and still more to receive live messages on client browser from server part. There exists 2 rooms/namespaces which users can subscribe to:

- **private** For single user messages to all instances of one user (e.g. one user is logged in with 3 browsers)
- **public** For single user messages to all instances of one user *AND* broadcasting messages to all connected clients
 - Helper pages

Helper pages to get informations about services, status of server and a test client page to test some websocket interactions.

- Overview Services: http://[host-ip-of-server]:8080
- Server Status Page: http://[host-ip-of-server]:8080/status
- Websocket Test Client: http://[host-ip-of-server]:8080/testclient

General settings of the node server like IP, port, authentication, SSL support and active websocket rooms can be configured with <u>../node/node-notify-server/prefs.json</u> file as mentioned above.

REST-Service

The REST-Service is designed to send messages to connected websocket users. Base-URL scheme looks like this:

Type: GET
http://[host-ip-of-server]:[port]/notifyuser

URL-Parameter

- userid (required) User-ID of connected user, in APEX APP_USER is used
- room (required) Websocket room valid values: private, public
- **type** (required) Notification type *valid values: info, success, warn, error*
- optparam (optional) Optional Parameter string to send any kind of information to the websocket client

HTTP Header-Variables

- o notify-title (required) Title of notification
- notify-message (required) Message content of notification

A demo call using curl looks like this:

```
curl -H "notify-title: Test Title Text" -H "notify-message: Test Message Text"
"http://[host-ip-of-server]:[port]/notifyuser?userid=daniel&room=private&type=info&
optparam=myoptionalinfo123"
```

PL/SQL API

The PL/SQL API consists of one package **ws_notify_api** and includes many procedures to send any kind of possible notifications over the REST-Interface. It can be used to send notifications to users via PL/SQL or inside of APEX. All web service requests are based on APEX package APEX_WEB_SERVICE.

List of global package variables

- g_ws_rest_host Node Notification Server Hostname or IP
- g_ws_rest_port Node Notification Server Port
- g_ws_rest_path Node Notification Server REST-Service Base Path
- g_ws_rest_proto Node Notification Server Protocol (http or https)
- g_ws_rest_base_url Combines Protocol, Host, Port and Path
- g_ws_basic_auth_user HTTP Basic Auth username of Node Server (REST-Interface)
- g_ws_basic_auth_pwd HTTP Basic Auth password of Node Server (REST-Interface)
- g_ssl_wallet_path If https, path to oracle wallet
- g_ssl_wallet_pwd If https, password of oracle wallet

List of all procedures with all parameters

Procedure: do_rest_notify_user

Purpose: Send Websocket Notifications over REST to connected users (General sending procedure with all parameters)

Parameter: - i_userid (required) - i_room (required) - ("private" or "public") - i_type (required) - (info, success, warn, error) - i_title (required) - i_message (required) - i_optparam (optional) - (Optional Parameter String)

Procedure: do_notify_user_private_info

Purpose: Send Websocket Notification to User / Room: Private / Type: Info

Parameter: - i_userid (required) - i_title (required) - i_message (required) - i_optparam (optional) -

(Optional Parameter String)

Procedure: do_notify_user_private_success

Purpose: Send Websocket Notification to User / Room: Private / Type: Success

Parameter: - i_userid (required) - i_title (required) - i_message (required) - i_optparam (optional) -

(Optional Parameter String)

Procedure: do_notify_user_private_warn

Purpose: Send Websocket Notification to User / Room: Private / Type: Warn

Parameter: - i_userid (required) - i_title (required) - i_message (required) - i_optparam (optional) -

(Optional Parameter String)

Procedure: do_notify_user_private_error

Purpose: Send Websocket Notification to User / Room: Private / Type: Error

Parameter: - i_userid (required) - i_title (required) - i_message (required) - i_optparam (optional) -

(Optional Parameter String)

Procedure: do_notify_user_public_info

Purpose: Send Websocket Notification to User / Room: Public / Type: Info

Parameter: - i_userid (required) - i_title (required) - i_message (required) - i_optparam (optional) -

(Optional Parameter String)

Procedure: do_notify_user_public_success

Purpose: Send Websocket Notification to User / Room: Public / Type: Success

Parameter: - i_userid (required) - i_title (required) - i_message (required) - i_optparam (optional) - (Optional Parameter String)

Procedure: do_notify_user_public_warn

Purpose: Send Websocket Notification to User / Room: Public / Type: Warn

Parameter: - i_userid (required) - i_title (required) - i_message (required) - i_optparam (optional) -

(Optional Parameter String)

Procedure: do_notify_user_public_error

Purpose: Send Websocket Notification to User / Room: Public / Type: Error

Parameter: - i_userid (required) - i_title (required) - i_message (required) - i_optparam (optional) -

(Optional Parameter String)

Procedure: do_notify_all_public_info

Purpose: Send Websocket Notification to all Users / Room: Public / Type: Info

Parameter: - i_title (required) - i_message (required) - i_optparam (optional) - (Optional Parameter

String)

Procedure: do_notify_all_public_success

Purpose: Send Websocket Notification to all Users / Room: Public / Type: Success

Parameter: - i_title (required) - i_message (required) - i_optparam (optional) - (Optional Parameter

String)

Procedure: do_notify_all_public_warn

Purpose: Send Websocket Notification to all Users / Room: Public / Type: Warn

Parameter: - i_title (required) - i_message (required) - i_optparam (optional) - (Optional Parameter

String)

Procedure: do_notify_all_public_error

Purpose: Send Websocket Notification to all Users / Room: Public / Type: Error

Parameter: - i_title (required) - i_message (required) - i_optparam (optional) - (Optional Parameter

String)

A demo call could look like this:

APEX

As already mentioned above, the APEX part contains 3 plugins to cover all functionalities from initialization of a websocket connection, sending notifications to other connected users to show incoming notifications. All 3 plugin files are located under ../apex/plugins folder.

Init Websocket Notify Connection

- Plugin File: dynamic_action_plugin_de_danielh_initwsnotifyconnection.sql
- **Purpose:** Initialize a connection to the websocket server, for general usage over all pages of your APEX application this plugin should be located on Global Page 0 (Zero)
- Plugin Attributes:
 - Use SSL Choose if the connection to the websocket server is secure (HTTPS) or plain (HTTP)
 - Server Hostname or IP The hostname or ip address of the websocket server
 - Server Port The port of the websocket server
 - Websocket Type or Room The type/room of the websocket server. There are 2 possible connections: private, public
 - Websocket Auth User-ID User-ID which connects / authenticates against the websocket server. Is used to identify a user. Default: APEX APP_USER
 - Websocket Auth-Token Auth-Token of the Node Notify Websocket Server. This is to increase security.
 - Logging Whether to log events in the console
- Plugin Events:
 - Private Websocket Connection success Successfully connected to private room
 - Private Websocket Connection error Error connecting to private room

- Private Websocket Disconnected Websocket connection is disconnected for private room
- Public Websocket Connection success Successfully connected to public room
- Public Websocket Connection error Error connecting to public room
- Public Websocket Disconnected Websocket connection is disconnected for public room
- Receive Private Message Receiving an incoming private message
- Receive Public Message Receiving an incoming public message

Send Websocket Notify

- Plugin File: dynamic_action_plugin_de_danielh_sendwsnotify.sql
- Purpose: Send websocket notifications to other connected users or to all connected users
- Plugin Attributes:
 - Source Source of all Notification relevant informations (Values: Items / SQL Query)
 - To User (User-ID) Item which holds informations about the User-ID or Username of the user who get's the notification
 - Websocket Room Item which holds informations about the websocket room Valid values:
 "private" or "public"
 - **Notification Type** Item which holds informations about the type of the notification Valid values: info, success, warn, error
 - Notification Title Item which holds informations about the title of the notification
 - Notification Message Item which holds informations about the message content of the notification
 - Optional Parameter Item which holds informations about a optional parameter This could be any kind of string or number combination. This information can be processed on the client side
 - SQL Query SQL Query which returns all relevant informations for sending a notification. The Query should only return one row!
 - Show Wait Spinner Show / Hide wait spinner for AJAX call
 - Escape HTML Whether to escape special chars (HTML) or not
 - Logging Whether to log events in the console
- Plugin Events:
 - Send Notification success Sending a notification was successfull
 - Send Notification error Error sending a notification
 - Send Notification missing values Missing required parameters for sending a notification
- Example SQL Source Query: SELECT 'MYUSER' AS user id,

```
'private' AS room, -- private, public
'info' AS notify_type, -- info, success, warn, error
'Test Title' AS title,
'My Test Message Content...' AS message,
'123:abc' AS optional_parameter
FROM dual
```

Show Websocket Notify

- Plugin File: dynamic_action_plugin_de_danielh_showwsnotify.sql
- **Purpose:** Show notifications for incoming websocket message events. Notifications UI based on <u>AlertifyJS</u>
- Plugin Attributes:
 - Notification Icon CSS Class Icon CSS class for the incoming notification Default: fa-bell
 - Notification Wait Time Time (in seconds) to wait before the notification is dismissed, a value of 0 means keep open till clicked.
 - Notification Position Position of the notification message on screen
 - Logging Whether to log events in the console

All other parameters of an notification object (title, message, type (info, success, warn, error), etc.) are automatically fetched from the websocket message event.

- Plugin Events:
 - Private Notification clicked Clicked on a private notification object
 - Public Notification clicked Clicked on a public notification object

License

This software is under **MIT License**.