OpenFOAM Tutorials

2 Add temperature to solvers

2.1 Add the heat transport equation to the icoFoam solver, in order to calculate how the flow can affect the heat transfer between two heated walls. The heat transport equation is

$$\frac{\partial T}{\partial t} + (\boldsymbol{\nabla} \cdot \boldsymbol{V})T = \alpha \nabla^2 T$$

where α is the themal diffusivity.

Copy the icoFoam solver to your OpenFOAM project directory, inside a folder named applications, where you can store all your modified OpenFOAM solvers. If you haven't already created such directory, either do it manually, or follow the commands

```
$ mkdir -p $WM_PROJECT_USER_DIR/applications
$ cp -r $FOAM_SOLVERS/incompressible/icoFoam $WM_PROJECT_USER_DIR/applications/myIcoFoam
$ cd $WM_PROJECT_USER_DIR/applications/solvers/myIcoFoam
```

Rename the icoFoam.C file to myIcoFoam.C. Now go into the Make subdirectory and open the 'files' file with a text editor. Change it to read:

```
myIcoFoam.C

EXE = $(FOAM_USER_APPBIN)/myIcoFoam
```

You can delete old binaries, if they exist, using the command

\$ wclean

To compile the new solver, run the command

\$ wmake

If everything worked correctly, your new solver binary should be present in the FOAM_USER_APPBIN directory. Check this with:

\$ ls \$FOAM_USER_APPBIN

This will show the steps to add another field variable to a solver. Open the myIcoFoam.C with a text editor. Following the flow of the myIcoFoam program, one notices that the header file createFields.H is called prior to the solution loop. This file was copied with the solver and has the specific information pertaining to what variables will be solved. Inside the createFields.H file, the first items loaded is the kinematic viscosity from the transportProperties dictionary file. We will add a new transport property related to the thermal diffusivity which will be denoted as alpha. Make the following edits:

```
//Add here...
dimensionedScalar alpha
(
   transportProperties.lookup("alpha")
);
//Done for now...
```

Later on, we will need to edit the transportProperties dictionary file to reflect this change. Moreover, in the same file, add a volScalarField, similar to the pressure field, that represents the temperature.

```
Info<< "Reading field T\n" <<endl;

volScalarField T
(
    IOobject
    (
        "T",
        runTime.timeName(),
        mesh,
        IOobject::MUST_READ,
        IOobject::AUTO_WRITE
    ),
    mesh
);</pre>
```

Save these changes. You've completed adding a new scalar field variable 'T' and a new constant 'alpha'. The next step is to add a new equation describing the transport of the temperature. Return to editing the mylcoFoam.C file. Because the temperature transport depends on the velocity field, we will add the equation after the momentum equation is solved (after the PISO loop), but before the time step is written. Edit your file so it looks like this:

```
#include "continuityErrs.H"

U -= rUA*fvc::grad(p);
U.correctBoundaryConditions();
}

//add these lines...
fvScalarMatrix TEqn
(
    fvm::ddt(T)
    + fvm::div(phi, T)
    - fvm::laplacian(alpha, T)
);

TEqn.solve();
//done adding lines...
runTime.write();
```

These lines add a new equation for the temperature and make use of the face flux variable, phi, which is already used in the momentum equation solution.

Save your changes and run wmake to compile the solver:

\$ wmake

2.2 The next step in this process is to test the new solver. This will first be accomplished by modifying the existing cavity tutorial. Copy a cavity case from the tutorials folder into your OpenFOAM directory. Open the transportProperties dictionary in your favorite editor and add the following line under the definition of nu:

```
alpha alpha [0 2 -1 0 0 0 0] 0.002;
```

In the ./O/ folder, create a file for the initial and boundary conditions of temperature:

```
FoamFile
  version
                2.0;
                ascii;
  format
  class
                volScalarField;
  object
                Τ;
//***************************//
                      [0 0 0 1 0 0 0];
dimensions
internalField
                     uniform 300;
boundaryField
  movingWall
                      fixedValue;
     type
     value
                      uniform 350;
  fixedWalls
     type
                      fixedValue;
     value
                     uniform 300;
  frontAndBack
     type
                      empty;
}
```


The next thing tha must be done is to choose discretization scemes and solution algorithms for the extra energy equation. By adding a new equation to solve, we need to tell OpenFOAM what discretization schemes to apply to the equations. This is done in the fvSchemes dictionary. Open the 'fvSchemes' dictionary. Now, there are two main items added in the thermal transport equation above: a divergence term and a laplacian. Under each of these sections in the dictionary, we need to add terms which match what was added in the solver source code. Edit your file so it includes the following:

```
divSchemes
{
  default
                          none;
  div(phi,U)
                          Gauss linear;
  div(phi,T)
                          Gauss upwind;
laplacianSchemes
  default
                          none:
  laplacian(nu,U)
                          Gauss linear corrected;
  laplacian((1|A(U)),p) Gauss linear corrected;
  laplacian(alpha,T)
                          Gauss linear corrected;
}
```

Alternatively, a scheme can be added to the 'default' field instead of adding specific ones below. Next, open the fvSolution dictionary. It should look like this:


```
solvers
{
  p
   {
                         PCG;
      solver
      preconditioner
                         DIC;
      tolerance
                         1e-06;
      relTol
                         0.05;
  pFinal
      $p;
                         0;
      relTol
  U
                         smoothSolver;
      solver
                         symGaussSeidel;
      smoother
                         1e-05;
      tolerance
      relTol
   //add this...
   Т
   {
                         BICCG;
      solver
      {\tt preconditioner}
                         DILU;
      tolerance
                         1e-7;
      relTol
                         0;
   //done editing...
```

After successfully running the case, the temperature field should look similar to the following picture



2.3 Simulate the thermal laminar 3D pipe flow of the previous tutorial, by adding a temperature field, similarly with the previous step. Define two opposite walls with temperatures 300 K and 350 K respectively, while the other two will be fully insulated.

2.4 Create a new solver, called laplaceFoam that solves the Laplace equation in a rectangular flat plate, with boundary and initial conditions as shown in the next figure. Use the quantities $T_w = 100 \ K$, $L = 2 \ m$ and $H = 1 \ m$.



For the creation of the new solver, copy the existing solver electrostaticFoam into the applications directory, in your Home folder, and change the name in all the appropriate files, as described in Step 2.

Modify the laplaceFoam.C and the createFields.H files, in order to only solve the Laplace equation for the volScalarField T. Delete any unnecessary commands, equations and variables inside the solver and compile the solver.

Create the case and test the validity of your results.