
Chapter 6 Transport Layer

A note on the use of these Powerpoint slides:

The notes used in this course are substantially based on Powerpoint slides developed and copyrighted by J.F. Kurose and K.W. Ross, 1996-2016



Computer Networking: A Top Down Approach

7th edition
Jim Kurose, Keith Ross
Pearson/Addison Wesley
April 2016

Chapter 6: Transport Layer

our goals:

- understand principles behind transport layer services:
 - multiplexing, demultiplexing
 - reliable data transfer
 - flow control
 - congestion control

- learn about Internet transport layer protocols:
 - UDP: connectionless transport
 - TCP: connection-oriented reliable transport
 - TCP congestion control


Chapter 6 outline

- 6.1 transport-layer services
- 6.2 multiplexing and demultiplexing
- 6.3 connectionless transport: UDP
- 6.4 principles of reliable data transfer

- 6.5 connection-oriented transport: TCP
 - segment structure
 - reliable data transfer
 - flow control
 - connection management
- 6.6 principles of congestion control
- 6.7 TCP congestion control

Transport services and protocols

- provide logical communication between app processes running on different hosts
- transport protocols run in end systems
 - send side: breaks app messages into segments, passes to network layer
 - rcv side: reassembles segments into messages, passes to app layer
- more than one transport protocol available to apps
 - Internet: TCP and UDP



Transport vs. network layer


- network layer: logical communication between hosts
- transport layer: logical communication between processes
 - relies on, enhances, network layer services

household analogy:

- 12 kids in Ann's house sending letters to 12 kids in Bill's house:
- hosts = houses
- processes = kids
- app messages = letters in envelopes
- transport protocol = Ann and Bill who demux to inhouse siblings
- network-layer protocol = postal service

Internet transport-layer protocols

- reliable, in-order delivery (TCP)
 - congestion control
 - flow control
 - connection setup
- unreliable, unordered delivery: UDP
 - no-frills extension of "best-effort" IP
- services not available:
 - delay guarantees
 - bandwidth guarantees




Chapter 6 outline

- 6.1 transport-layer services
- 6.2 multiplexing and demultiplexing
- 6.3 connectionless transport: UDP
- 6.4 principles of reliable data transfer


- 6.5 connection-oriented transport: TCP
 - segment structure
 - reliable data transfer
 - flow control
 - connection management
- 6.6 principles of congestion control
- 6.7 TCP congestion control

Multiplexing/demultiplexing



How demultiplexing works

- host receives IP datagrams
 - each datagram has source IP address, destination IP address
 - each datagram carries one transport-layer segment
 - each segment has source, destination port number
- host uses IP addresses & port numbers to direct segment to appropriate socket



TCP/UDP segment format

Connectionless demultiplexing

recall: created socket has host-local port #:


```
clientSocket =
socket(AF_INET, SOCK_DGRAM)
clientSocket.bind(('',
10000))
```

- recall: when creating datagram to send into UDP socket, must specify
 - destination IP address

IP datagrams with same


destination port #

- when host receives UDP segment:
 - checks destination port # in segment
 - directs UDP segment to socket with that port #



to same socket at dest

Connectionless demux: example




Connection-oriented demux

- TCP socket identified by 4-tuple:
 - source IP address
 - source port number
 - dest IP address
 - dest port number
- demux: receiver uses all four values to direct segment to appropriate socket


- server host may support many simultaneous TCP sockets:
 - each socket identified by its own 4-tuple
- web servers have different sockets for each connecting client
 - non-persistent HTTP will have different socket for each request

Connection-oriented demux: example



three segments, all destined to IP address: B, dest port: 80 are demultiplexed to *different* sockets

Connection-oriented demux: example




Chapter 6 outline

- 6.1 transport-layer services
- 6.2 multiplexing and demultiplexing
- 6.3 connectionless transport: UDP
- 6.4 principles of reliable data transfer

- 6.5 connection-oriented transport: TCP
 - segment structure
 - reliable data transfer
 - flow control
 - connection management
- 6.6 principles of congestion control
- 6.7 TCP congestion control

UDP: User Datagram Protocol [RFC 768]

- "no frills," "bare bones" Internet transport protocol
- "best effort" service, UDP segments may be:
 - lost
 - delivered out-of-order to app
- connectionless:
 - no handshaking between UDP sender, receiver
 - each UDP segment handled independently of others



UDP segment format

UDP: User Datagram Protocol [RFC 768]

why is there a UDP?

- no connection establishment (which can add delay)
- simple: no connection state at sender, receiver
- small header size
- no congestion control:
 UDP can blast away as fast as desired

UDP use:

- streaming multimedia apps (loss tolerant, rate sensitive)
- DNS
- SNMP
- reliable transfer over UDP:
 - add reliability at application layer
 - application-specific error recovery!

UDP checksum

Goal: detect "errors" (e.g., flipped bits) in transmitted segment

sender:

- treat segment contents, including header fields, as sequence of 16-bit integers
- checksum: One's (Is) complement of the sum of segment contents
- sender puts checksum value into UDP checksum field


receiver:

- compute checksum of received segment
- check if computed checksum equals checksum field value:
 - NO error detected
 - YES no error detected.
 But maybe errors
 nonetheless? More later

• • • •

Internet checksum: example

example: add two 16-bit integers



Note: when adding numbers, a carryout from the most significant bit needs to be added to the result

^{*} Check out the online interactive exercises for more examples: http://gaia.cs.umass.edu/kurose_ross/interactive/

Exercise

- a. Suppose you have the following 2 bytes: 01011100 and 01100101. What is the 1s complement of the sum of these 2 bytes?
- b. Suppose you have the following 2 bytes: 11011010 and 01100101. What is the 1s complement of the sum of these 2 bytes?
- c. For the bytes in part (a), give an example where one bit is flipped in each of the 2 bytes and yet the 1s complement doesn't change.

Chapter 6 outline

- 6.1 transport-layer services
- 6.2 multiplexing and demultiplexing
- 6.3 connectionless transport: UDP
- 6.4 principles of reliable data transfer

- 6.5 connection-oriented transport: TCP
 - segment structure
 - reliable data transfer
 - flow control
 - connection management
- 6.6 principles of congestion control
- 6.7 TCP congestion control

Chapter 6 outline

- 6.1 transport-layer services
- 6.2 multiplexing and demultiplexing
- 6.3 connectionless transport: UDP
- 6.4 principles of reliable data transfer

- 6.5 connection-oriented transport: TCP
 - segment structure
 - reliable data transfer
 - flow control
 - connection management
- 6.6 principles of congestion control
- 6.7 TCP congestion control

TCP: Overview RFCs: 793,1122,1323, 2018, 2581

- point-to-point:
 - one sender, one receiver
- reliable, in-order byte stream:
 - no "message boundaries"
- pipelined:
 - TCP congestion and flow control set window size

full duplex data:

- bi-directional data flow in same connection
- MSS: maximum segment size
- connection-oriented:
 - handshaking (exchange of control msgs) inits sender, receiver state before data exchange
- flow controlled:
 - sender will not overwhelm receiver

TCP segment structure


URG: urgent data (generally not used)

ACK: ACK # valid

PSH: push data now (generally not used)

RST, SYN, FIN: connection estab (setup, teardown commands)

Internet checksum (as in UDP)




by bytes of data (not segments!)

> # bytes rcvr willing to accept

TCP seq. numbers

sequence numbers:

- byte stream "number" of first byte in segment's data
 - E.g., Suppose that a process in Host A wants to send a stream of data (a file of 500,000 bytes) to a process in Host B over a TCP connection. MSS is 1,000 bytes, and the Ist byte is numbered 0.



- Seq # of the 1st segment: 0; Seq # of the 2nd segment: 1000;
- Seq # of the 3rd segment: ?

TCP ACKs

acknowledgments:


- seq # of next byte expected from other side
 - Suppose that Host A has received all bytes numbered 0 through 535 from B and suppose that it is about to send a segment to Host B
 - Host A is waiting for byte 536 and all the subsequent bytes
 - So Host A puts 536 in the acknowledgment number field

cumulative ACK

- Suppose that Host A has received one segment from Host B containing bytes 0 ~ 535, and another segment containing bytes 900 ~ 1,000
- For some reason Host A has not yet received bytes 536 ~ 899
- Host A is still waiting for byte 536 (and beyond)
- A's next segment to B will contain 536 in the acknowledgment number field


TCP seq. numbers, ACKs

outgoing segment from sender



- Q: how receiver handles out-of-order segments
 - A: TCP spec doesn't say,
 - up to implementor

TCP seq. numbers, ACKs



simple telnet scenario

TCP round trip time, timeout


- Q: how to set TCP timeout value?
- longer than RTT
 - but RTT varies
- too short: premature timeout, unnecessary retransmissions
- too long: slow reaction to segment loss

- Q: how to estimate RTT?
- SampleRTT: measured time from segment transmission until ACK receipt
 - ignore retransmissions
- SampleRTT will vary, want estimated RTT "smoother"
 - average several recent measurements, not just current SampleRTT

TCP round trip time, timeout

EstimatedRTT = $(1-\alpha)$ *EstimatedRTT + α *SampleRTT

- exponential weighted moving average
- influence of past sample decreases exponentially fast
- typical value: $\alpha = 0.125$



TCP round trip time, timeout

- timeout interval: EstimatedRTT plus "safety margin"
 - large variation in **EstimatedRTT** -> larger safety margin
- estimate SampleRTT deviation from EstimatedRTT:

```
DevRTT = (1-\beta)*DevRTT + \beta*|SampleRTT-EstimatedRTT| (typically, \beta = 0.25)
```

TimeoutInterval = EstimatedRTT + 4*DevRTT



estimated RTT

safety margin"

^{*} Check out the online interactive exercises for more examples: http://gaia.cs.umass.edu/kurose_ross/interactive/

Chapter 6 outline

- 6.1 transport-layer services
- 6.2 multiplexing and demultiplexing
- 6.3 connectionless transport: UDP
- 6.4 principles of reliable data transfer

- 6.5 connection-oriented transport: TCP
 - segment structure
 - reliable data transfer
 - flow control
 - connection management
- 6.6 principles of congestion control
- 6.7 TCP congestion control

TCP reliable data transfer

- TCP creates rdt service on top of IP's unreliable service
 - pipelined segments
 - cumulative acks
 - single retransmission timer
- retransmissions triggered by:
 - timeout events
 - duplicate acks

let's initially consider simplified TCP sender:

- ignore duplicate acks
- ignore flow control, congestion control

TCP sender events:

data rcvd from app:

- create segment with seq #
- seq # is byte-stream number of first data byte in segment
- start timer if not already running
 - think of timer as for oldest unacked segment
 - expiration interval:TimeOutInterval

timeout:

- retransmit segment that caused timeout
- restart timer

ack rcvd:


- if ack acknowledges previously unacked segments
 - update what is known to be ACKed
 - start timer if there are still unacked segments

TCP sender (simplified)


/* SendBase—1: last cumulatively ACKed byte */
if (there are currently not-yet-acked segments)

start timer


else stop timer



TCP: retransmission scenarios



TCP: retransmission scenarios



cumulative ACK

TCP ACK generation [RFC 1122, RFC 5681]

event at receiver	TCP receiver action
arrival of in-order segment with expected seq #. All data up to expected seq # already ACKed	delayed ACK. Wait up to 500ms for next segment. If no next segment, send ACK
arrival of in-order segment with expected seq #. One other segment has ACK pending	immediately send single cumulative ACK, ACKing both in-order segments
arrival of out-of-order segment higher-than-expect seq. # . Gap detected	immediately send duplicate ACK, indicating seq. # of next expected byte
arrival of segment that partially or completely fills gap	immediate send ACK, provided that segment starts at lower end of gap

TCP fast retransmit

- time-out period often relatively long:
 - long delay before resending lost packet
- detect lost segments via duplicate ACKs.
 - sender often sends many segments backto-back
 - if segment is lost, there will likely be many duplicate ACKs.


TCP fast retransmit

if sender receives

"triple duplicate
ACKs" for same data,
resend unacked
segment with smallest
seq #

 likely that unacked segment lost, so don't wait for timeout

TCP fast retransmit



Chapter 6 outline

- 6.1 transport-layer services
- 6.2 multiplexing and demultiplexing
- 6.3 connectionless transport: UDP
- 6.4 principles of reliable data transfer

- 6.5 connection-oriented transport: TCP
 - segment structure
 - reliable data transfer
 - flow control
 - connection management
- 6.6 principles of congestion control
- 6.7 TCP congestion control

TCP flow control

application may remove data from TCP socket buffers

... slower than TCP receiver is delivering (sender is sending)

application process application OS TCP socket receiver buffers TCP code ĬΡ code from sender


receiver protocol stack

flow control

receiver controls sender, so sender won't overflow receiver's buffer by transmitting too much, too fast

TCP flow control

- receiver "advertises" free buffer space by including rwnd value in TCP header of receiver-to-sender segments
 - RcvBuffer size set via socket options (typical default is 4096 bytes)
 - many operating systems autoadjust RcvBuffer
- sender limits amount of unacked ("in-flight") data to receiver's rwnd value
- guarantees receive buffer will not overflow



receiver-side buffering

Chapter 3 outline


- 3.1 transport-layer services
- 3.2 multiplexing and demultiplexing
- 3.3 connectionless transport: UDP
- 3.4 principles of reliable data transfer

- 3.5 connection-oriented transport: TCP
 - segment structure
 - reliable data transfer
 - flow control
 - connection management
- 3.6 principles of congestion control
- 3.7 TCP congestion control

Connection Management

before exchanging data, sender/receiver "handshake":

- agree to establish connection (each knowing the other willing to establish connection)
- agree on connection parameters





```
Socket clientSocket =
  newSocket("hostname","port
  number");
```

```
Socket connectionSocket =
  welcomeSocket.accept();
```

Agreeing to establish a connection

2-way handshake:







- Q: will 2-way handshake always work in network?
- variable delays
- retransmitted messages (e.g. req_conn(x)) due to message loss
- message reordering
- can't "see" other side


Agreeing to establish a connection

2-way handshake failure scenarios:






TCP 3-way handshake




TCP 3-way handshake: FSM



TCP: closing a connection

- client, server each close their side of connection
 - send TCP segment with FIN bit = I
- respond to received FIN with ACK
 - on receiving FIN, ACK can be combined with own FIN
- simultaneous FIN exchanges can be handled


TCP: closing a connection



Sequences of TCP states

TCP Client Lifecycle

TCP Server Lifecycle



Chapter 6 outline


- 6.1 transport-layer services
- 6.2 multiplexing and demultiplexing
- 6.3 connectionless transport: UDP
- 6.4 principles of reliable data transfer

- 6.5 connection-oriented transport: TCP
 - segment structure
 - reliable data transfer
 - flow control
 - connection management
- 6.6 principles of congestion control
- 6.7 TCP congestion control

Principles of congestion control


congestion:

- informally: "too many sources sending too much data too fast for network to handle"
- different from flow control!
- manifestations:
 - lost packets (buffer overflow at routers)
 - long delays (queueing in router buffers)
- a top-10 problem!




Transport Layer 6-55


- one router, finite buffers
- sender retransmission of timed-out packet
 - transport-layer input includes retransmissions : $\lambda_{in} \ge \lambda_{in}$



idealization: perfect knowledge

sender sends only when router buffers available






Idealization: known loss

packets can be lost, dropped at router due to full buffers


 sender only resends if packet known to be lost




packets can be lost,

dropped at router due to full buffers


 sender only resends if packet known to be lost







Realistic: duplicates

- packets can be lost, dropped at router due to full buffers
- sender times out prematurely, sending two copies, both of which are delivered








"costs" of congestion:


- queuing delays
- more work (retrans) to compensate for lost packets
- unneeded retransmissions: link carries multiple copies of pkt
 - decreasing goodput


- four senders
- multihop paths
- timeout/retransmit

Q: what happens as λ_{in} and λ_{in} increase?

A: as red λ_{in} increases, all arriving blue pkts at upper queue are dropped, blue throughput $\rightarrow 0$







another "cost" of congestion:

when packet dropped, any "upstream transmission capacity used for that packet was wasted!

Chapter 6 outline

- 6.1 transport-layer services
- 6.2 multiplexing and demultiplexing
- 6.3 connectionless transport: UDP
- 6.4 principles of reliable data transfer


- 6.5 connection-oriented transport: TCP
 - segment structure
 - reliable data transfer
 - flow control
 - connection management
- 6.6 principles of congestion control
- 6.7 TCP congestion control

TCP congestion control: additive increase multiplicative decrease


- approach: sender increases transmission rate (window size), probing for usable bandwidth, until loss occurs
 - additive increase: increase cwnd by I MSS every RTT until loss detected
 - multiplicative decrease: cut cwnd in half after loss

AIMD saw tooth behavior: probing for bandwidth

cwnd: TCP sender



TCP Congestion Control: details



sender limits transmission:

$$\begin{array}{ccc} \text{LastByteSent-} & \leq & \text{cwnd} \\ \text{LastByteAcked} & \end{array}$$

 cwnd is dynamic, function of perceived network congestion


TCP sending rate:

 roughly: send cwnd bytes, wait RTT for ACKS, then send more bytes

rate
$$\approx \frac{\text{cwnd}}{\text{RTT}}$$
 bytes/sec

TCP Slow Start

- when connection begins, increase rate exponentially until first loss event:
 - initially cwnd = I MSS
 - double cwnd every RTT
 - done by incrementing cwnd for every ACK received
- summary: initial rate is slow but ramps up exponentially fast



TCP: detecting, reacting to loss

- loss indicated by timeout:
 - cwnd set to I MSS;
 - window then grows exponentially (as in slow start) to threshold, then grows linearly
- loss indicated by 3 duplicate ACKs: TCP RENO
 - dup ACKs indicate network capable of delivering some segments
 - cwnd is cut in half window then grows linearly
- TCP Tahoe always sets cwnd to I (timeout or 3 duplicate acks)

TCP: switching from slow start to CA


Q: when should the exponential increase switch to linear?

A: when **cwnd** gets to 1/2 of its value before timeout.

Implementation:


- variable ssthresh
- on loss event, ssthresh is set to 1/2 of cwnd just before loss event

(congestion avoidance)



^{*} Check out the online interactive exercises for more examples: http://gaia.cs.umass.edu/kurose_ross/interactive/


Summary: TCP Congestion Control



TCP throughput

- avg. TCP thruput as function of window size, RTT?
 - ignore slow start, assume always data to send
- W: window size (measured in bytes) where loss occurs
 - avg. window size (# in-flight bytes) is 3/4 W
 - avg. thruput is 3/4W per RTT

avg TCP throuput =
$$\frac{3}{4} \frac{W}{RTT}$$
 bytes/sec



TCP Futures: TCP over "long, fat pipes"


- example: I500 byte segments, I00ms RTT, wantI0 Gbps throughput
- requires \overline{W} = 83,333 in-flight segments
- throughput in terms of segment loss probability, L [Mathis 1997]:

TCP throughput =
$$\frac{1.22 \cdot MSS}{RTT \sqrt{L}}$$

- ⇒ to achieve 10 Gbps throughput, need a loss rate of L = $2 \cdot 10^{-10}$ a very small loss rate!
- new versions of TCP for high-speed

TCP Fairness


fairness goal: if K TCP sessions share same bottleneck link of bandwidth R, each should have average rate of R/K



Why is TCP fair?

two competing sessions:

- additive increase gives slope of I, as throughout increases
- multiplicative decrease decreases throughput proportionally



Fairness (more)

Fairness and UDP

- multimedia apps often do not use TCP
 - do not want rate throttled by congestion control
- instead use UDP:
 - send audio/video at constant rate, tolerate packet loss


Fairness, parallel TCP connections

- application can open multiple parallel connections between two hosts
- web browsers do this
- e.g., link of rate R with 9 existing connections:
 - new app asks for I TCP, gets rate R/I0
 - new app asks for 11 TCPs, gets R/2

Explicit Congestion Notification (ECN)

network-assisted congestion control:

- two bits in IP datagram header (ToS field) marked by network router to indicate congestion
- congestion indication carried to receiving host
- receiver (seeing congestion indication in IP datagram) sets ECE (ECN Echo) bit on receiver-to-sender ACK segment to notify sender of congestion



Chapter 6: summary

- principles behind transport layer services:
 - multiplexing, demultiplexing
 - reliable data transfer
 - flow control
 - congestion control
- instantiation, implementation in the Internet
 - UDP
 - TCP