# TCC Useful Functions for TTCN-3 Toolset with TITAN, Description

Gábor Szalai

Version 1551-CNL 113 472, Rev. AJ, 2018-05-29

# **Table of Contents**

How to Read This Document	. 1
Presumed Knowledge	. 1
Functionality	. 1
Implemented Protocols	. 1
Supported Standards	. 1
Routing Functionality	. 1
Modified and Non-Implemented Protocol Elements	. 1
Backward Incompatibilities	. 1
R35A	. 1
System Requirements	. 3
Installation	. 3
Functions	. 3
Message Encoding Functions	. 3
Overview	. 3
Function Definitions	. 3
Error Messages	. 5
Warning Messages	. 5
Examples	. 5
Test Environment Handling Functions	. 7
Overview	. 7
Function Definitions	. 7
Error Messages	. 7
Warning Messages	. 7
Examples	. 7
Network Interface Functions	. 8
Overview	. 8
Function Definitions	. 8
Error Messages	11
Warning Messages	12
Examples	12
Makefile	13
File I/O Functions	13
Overview	14
Function Definitions	14
Error Messages	17
Warning Messages	17
Examples	18
Assertion Functions	20

Overview	20
Function Definitions	20
Error Messages	20
Warning Messages	20
Examples	20
Conversion Functions	20
Overview	21
Function Definitions	21
Error Messages	24
Warning Messages	24
Examples	24
Makefile	24
Date and Time Functions	24
Overview	24
Function Definitions	25
Error Messages.	27
Warning Messages	27
Examples	27
Maths Functions	29
Overview	29
Function Definitions	29
Error Messages	33
Warning Messages	33
Examples	33
Security Functions	35
Overview	35
Function Definitions	35
Error Messages	38
Warning Messages	38
Examples	38
Message Handling Functions	41
Overview	41
Function Definitions	41
Error Messages	42
Warning Messages	42
Examples	42
Permutated Parameters Handling	42
Overview	43
Function Definitions	43
Error Messages	45
Warning Messages	45

Examples	. 45
Titan Metadata Functions	. 45
Overview	. 45
Function Definitions	. 45
Error Messages	. 45
Warning Messages	. 46
Examples	. 46
Text Template Substitution Functions	. 46
Overview	. 47
Function Definitions	. 47
Error Messages	. 47
Warning Messages	. 47
Examples	. 47
IPsec Functions	. 48
Overview	. 48
PF_KEY API	. 48
Netlink XFRM API	. 48
Function Definitions	. 49
Security Parameter Index Query Function	. 49
Security Association Database Handling Functions	. 49
Security Policy Database Handling Functions	. 51
Error Messages	. 52
Warning Messages	. 53
Examples	. 53
XPath Support Functions	. 54
Overview	. 55
Function Definitions	. 55
Building the TinyXPath External Library	. 56
Preparing your TTCN-3 Environment for Using TinyXPath	. 57
Modification of the TTCN-3 Files in your Project	. 57
Modification of the Makefile of Your Project	. 57
Error Messages	. 58
Warning Messages	. 58
Examples	. 58
System Functions	. 58
Overview	. 58
Function definitions	. 59
Error Messages	. 59
Warning Messages	. 59
Examples	. 59
FileSystem Functions	. 59

Overview	39
Function Definitions	39
Error Messages	60
Warning Messages	30
Examples	
egexp functions	31
Overview	31
Function Definitions	
Error Messages	
Warning Messages	
Examples	
erminology	3
Abbreviations	3
eferences	33

### How to Read This Document

This is the Function Specification for the TCC Useful Functions. The modules are developed for the TTCN-3 Toolset with TITAN.

# **Presumed Knowledge**

The knowledge of the TITAN TTCN-3 Test Executor [3] and the TTCN-3 language [1] is essential. Other documents that the reader should be familiar with are referenced in the consecutive section of each function.

# **Functionality**

The functions described in this document are TTCN-3 or external TTCN-3 functions. TTCN-3 functions are implemented in TTCN-3 language; external TTCN-3 functions are implemented in C++.

# **Implemented Protocols**

None.

# **Supported Standards**

None.

# **Routing Functionality**

Routing functionality is not performed.

# Modified and Non-Implemented Protocol Elements

None.

# **Backward Incompatibilities**

#### **R35A**

The non-open source TCCSecurity\_Functions are moved to a separate product.

The TCC Security Functions CNL 113 874 should be added to the project if the moved functions are used.

If the non-moved functions are used in the project the TCCOpenSecurity\_Functions should be imported instead of TCCSecurity\_Functions

- Moved files:
  - TCCSecurity.cc
  - TCCSecurity\_Functions.ttcn
  - aka\_algorythm\_set.c
  - aka\_algorythm\_set.h
  - snow3g.c
  - snow3g.h
  - zuc.c
  - zuc.h
- Moved functions:
  - . f\_TCCSecurity\_hex2char
  - o f\_IMSAKA\_f1
  - 。f\_IMSAKA\_f1\_opc
  - o f\_IMSAKA\_f2
  - o f\_IMSAKA\_f2\_opc
  - o f\_IMSAKA\_f3
  - o f\_IMSAKA\_f3\_opc
  - f\_IMSAKA\_f4
  - o f\_IMSAKA\_f4\_opc
  - o f\_IMSAKA\_f2345
  - 。f\_IMSAKA\_f2345\_opc
  - o f\_IMSAKA\_f5
  - o f\_IMSAKA\_f5\_opc
  - o f\_IMSAKA\_f1star
  - . f\_IMSAKA\_f1star\_opc
  - o f\_IMSAKA\_f5star
  - o f\_IMSAKA\_f5star\_opc
  - o f\_EAPSIM\_A3A8
  - . f\_IMSAKA\_calculateAUTN
  - . f\_calculate128\_EEA3
  - . f\_calculate128\_EIA3
  - o f\_calculate128\_EEA1
  - o f\_calculate128\_EIA1
  - . f\_calculate128\_EIA2
  - o f\_calculate128\_EEA2

# **System Requirements**

In order to operate any of the Useful Functions the following system requirements must be satisfied:

• TITAN TTCN-3 Test Executor version 6.3.pl0 (CRL 113 200/6 R3A) or higher installed. For installation guide see [2].

Further system requirements, if any, are listed in the consecutive section of each function.

### **Installation**

Since the Useful Functions are used as a part of the TTCN-3 test environment this requires TTCN-3 Test Executor to be installed before any operation of these functions. For more details on the installation of TTCN-3 Test Executor see the relevant section of [2].

If not otherwise noted in the respective sections, the following are needed to use the Useful Functions:

Copy the files listed in the section related to the specific functions to the directory of the test suite or create symbolic links to them.

- Import the TTCN-3 module containing the declaration of the functions to the modules that will use them.
- Create Makefile or modify the existing one. For more detail see the relevant section of [3].

## **Functions**

# **Message Encoding Functions**

### Overview

Encoding functions can be used to encode data to a specific format or decode encoded data.

Encoding functions are implemented in the following files:

- TCCEncoding\_Functions.ttcn: external TTCN-3 function declarations
- TCCEncoding.cc: source file of the functions

### **Function Definitions**

The following functions are defined in Encoding Functions:

external function enc\_MIME\_Base64(in octetstring p\_msg) return charstring;

Encodes the octetstring parameter msq to MIME Base64 format according to [3].

- external function dec\_MIME\_Base64(in charstring p\_b64) return octetstring;
   Decodes a MIME Base64 encoded character string to octetstring.
- external function enc\_LDIF\_Base64(in octetstring p\_msg) return charstring;
   Encodes the parameter msg to LDIF Base64 format according to [5].
- external function dec\_LDIF\_Base64(in charstring p\_b64) return octetstring;
   Decodes an LDIF Base64 encoded character string to octetstring.
- $\bullet \ \ \text{function} \ \ f\_\text{encGSM7bit} (\text{in universal charstring pl\_str}) \ \ \text{return octetstring} \\$

Encodes the parameter pl\_str (containing characters of the default alphabet) to octetstring containing USSD packing [12].

The Greek capital letters and the euro sign have to be represented in the "quadruple" notation (for example, the Greek capital letter delta is char(0, 0, 3, 148))

 $\bullet \ \ \text{function} \ \ f\_decGSM7bit (in \ octetstring \ pl\_gsm7bit) \ \ return \ universal \ \ charstring \\$ 

Decodes a USSD packed encoded octetstring to characters of the default alphabet [12].

NOTE Non-ASCII characters will be decoded into the quadruple notation. For example the Japanese yen symbol will be decoded to char(0, 0, 0, 165).

function f\_is\_TBCD(in charstring pl\_number) return boolean;

Returns true if the pl\_number contains only valid TBCD characters, otherwise returns false. The valid TBCD characters are 0-9, \*,#,a,b,c.

external function f enc TBCD(in charstring pl char) return octetstring;

Encodes the parameter pl\_char (charstring containing valid TBCD characters) to octetstring using TBCD encoding [13]. Valid TBCD characters are 0-9, \*,#,a,b,c. If the encoding of an invalid character is attempted, an empty octetstring is returned with a warning.

external function f\_dec\_TBCD(in octetstring pl\_oct) return charstring;

Decodes a valid TBCD encoded octetstring to charstring format [13]. If the encoding is incorrect then an empty charstring is returned with a warning.

• function f\_encode\_ISUP\_Called\_Party\_Number(in pl\_ISUP\_Called\_Party\_Number) return octetstring

Encodes <ISUP\_Called\_Party\_Number> type to octetstring format. (Encoding defined in ISUP protocol [14], section 3.9)

• function f\_encode\_ISUP\_Calling\_Party\_Number(in pl\_ISUP\_Calling\_Party\_Number) return octetstring

Encodes <ISUP\_Calling\_Party\_Number> type to octetstring format. (Encoding defined in ISUP protocol [14], section 3.10)

• function f\_encode\_MobileL3\_CalledPartyBCDNumber(in pl\_MobileL3\_CalledPartyBCDNumber) return octetstring

MobileL3\_CalledPartyBCDNumber)

Encodes <MobileL3\_CalledPartyBCDNumber> type to octetstring format. (Encoding defined in Mobile L3 protocol [15], section 10.5.4.7)

• public function f\_enc\_TBCD\_hex(in hexstring pl\_hex) return octetstring

The function converts a hexstring into TBCD-String format.

## **Error Messages**

None.

# **Warning Messages**

Warning: Invalid character in Base64 encoded data: ...

This warning message is only printed by the function dec\_LDIF\_Base64, if the Base64 encoded data passed as a parameter contains one or more characters that are not defined in Base64 (i.e. a character other than [A-Z][a-z][0-9]/+). The decoded data may still be valid.

Warning: Invalid character <character> will be encoded as space!

Only characters contained in Section 6.2.1 of [12] can be correctly encoded with f\_encGSM7bit. Other characters will be encoded as space.

Warning: Unknown extension character <extension code> will be decoded as space!

Only extensions contained in section 6.2.1.1 of [12] can be correctly decoded with f\_decGSM7bit. Other extension characters will be decoded as space.

Warning: Filler digit at invalid location!

f\_dec\_TBCD returns an empty charstring and gives this warning if there is a filler digit at a location other than the msb side of the last octet.

Warning: Invalid TBCD digit!

f\_enc\_TBCD returns an empty octetstring and gives this warning if the encoding of an invalid TBCD character is attempted.

# **Examples**

```
module TCCEncoding_Example {
import from TCCEncoding_Functions all;
```

```
type component test_CT {
  var charstring base64;
  var octetstring msg, dec;
}
testcase TC() runs on test_CT
  msg := char2oct("Test message.");
  log("Message is: ", msg);
  base64 := enc_MIME_Base64(msg);
  log("MIME Base64 encoded message is: ", base64);
  dec := dec_MIME_Base64(base64);
  log("Decoded message is: ", dec);
  if(dec != msq) {
    setverdict(fail);
  } else {
    setverdict(pass);
  }
}
testcase tc_2() runs on MyComp
  var octetstring v_bit := f_encGSM7bit("The last transaction cost $ 0.25. Your
account balance is $ 39.50. To refill your account go to www.att.com/GoPhone.")
log(v_bit)
var universal charstring v_char := f_decGSM7bit(v_bit);
log(v_char)
}
testcase tc_3() runs on MyComp
{ //Encoding and decoding the Greek capital letter delta
  var octetstring v_bit := f_encGSM7bit(char(0, 0, 3, 148))
log(v bit)
var universal charstring v_char := f_decGSM7bit(v_bit);
log(v_char)
}
testcase tc_4() runs on MyComp
log(f_dec_TBCD('01234F6789ABCDFE'0))
log(f_enc_TBCD("0123456789*#abc"))
}
control {
  execute(TC());
  execute(tc_2());
  execute(tc_3());
  execute(tc_4());
}
}
```

# Test Environment Handling Functions

### **Overview**

Environment Handling Functions can be used to get or set environment variables.

Environment Handling Functions are implemented in the following files:

- TCCEnv\_Functions.ttcn: external TTCN-3 function declarations
- TCCEnv.cc: source code of the functions

### **Function Definitions**

The following Environment Handling Functions are defined:

external function f\_GetEnv(in charstring p\_env\_name) return charstring;

Returns the environment variable p\_env\_name.

 external function f\_PutEnv(in charstring p\_env\_name, in charstring p\_env\_value) return boolean;

Sets the environment variable p\_env\_name to p\_env\_value. Returns false on error, true on success.

# **Error Messages**

None.

# **Warning Messages**

putenv failed with error code ...

An error happened while setting the environment variable.

# **Examples**

```
module TCCEnv_Example {
import from TCCEnv_Functions all;

type component test_CT { }

testcase TC() runs on test_CT
{
  log("PATH=", f_GetEnv("PATH"));
  f_PutEnv("ENV", "foobar");
  log("ENV=", f_GetEnv("ENV"));
}

control {
  execute(TC());
}
```

# **Network Interface Functions**

### **Overview**

Network Interface Functions can be used to modify interface related settings. For example, get/set IP address, set up/down interface.

Interface Functions are supported only on Linux and Solaris. For the setter functions root privilege is necessary. Otherwise warning messages will appear.

Network Interface Functions are implemented in the following files:

- TCCInterface\_Functions.ttcn
- TCCInterface.cc
- TCCInterface\_ip.h

### **Function Definitions**

The following Network Interface Functions are defined.

 external function f\_getPortAvailabilityStatus(in charstring ipAddress, in integer portNumber, in TCCInterface\_ProtocolType protocolType) return TCCInterface\_PortStatus;

The function returns what was the status of the IP/port/Protocol some time ago. The returned information was outdated before the function returned, so use it only as a hint.

• external function f\_setIP(in charstring interface, in charstring ip, in charstring netmask,

#### in charstring broadcast, in integer number := 1);

Set the IP address, subnet mask and broadcast address of the given interface. Parameter "number" is optional (and supported on Linux only).

If parameter "number" is given, a range of virtual interfaces are set up with continuous IP addresses, starting from the given IP address. If parameter "interface" is a real network interface, the first virtual interface is "<interface>:0". If parameter "interface" is virtual, the next sequence number is used.

**NOTE** No subnet mask and broadcast checking is done by the function.

	Linux	Solaris	Cygwin
IPv4	X	X	
IPv6			

external function f\_deleteIP(in charstring interface);

Delete the IP address of the given interface. If interface is virtual, it is set down.

	Linux	Solaris	Cygwin
IPv4	X	X	
IPv6			

 external function f\_setIP\_ip(in charstring interface, in charstring ipaddress, in integer prefix := 32, in integer v\_set := 1) return boolean;

This function is also used for setting up IPs on interfaces, but uses the NETLINK interface of the Linux kernel, what is far more fast than the original interface used by f\_setIP. Thus this function only works in Linux. Works with both IPv4 and IPv6 addresses.

On the specified interface the given new IP address will be registered with the addressprefix also given in the parameter list. The last parameter tells the behavior, other than 1 will cause deleting the ip from the interface. Thus  $f_{\text{setIP_ip}}$  with  $0 = v_{\text{set}}$  is equal to call  $f_{\text{delIP_ip}}$ . On success returns true, otherwise false and print some information into logs what was the problem.

It can only be used if the LINUX flag is specified when compiling the test, otherwise a warning message will be printed. When the USE\_IPROUTE flag is specified, the f\_setIP and f\_deleteIP functions will be redefined to be used with f\_setIP\_ip with the following parameter list mapping:

```
interface = interface,
ipaddress = ip,
prefix = 32,
v_set = 1
```

and

```
interface = interface,
ipaddress = ``'',
prefix = 32,
v_set = 0.
```

 external function f\_delIP\_ip(in charstring interface, in charstring ipaddress, in integer prefix := 32) return boolean;

Deletes the given IP address/prefix from an interface.\_\_

On success returns true, otherwise false and print some information into logs what was the problem.

 external function f\_getIP(in charstring interface, out charstring ip, out charstring netmask, out charstring broadcast, in TCCInterface\_IPAddressType addressType:=IPv4);

Returns the IP address, subnet mask and broadcast address of the given interface, in the standard Internet dotted format (for example, "10.0.0.2"). The type of address can be IPv4 or IPv6.

	Linux	Solaris	Cygwin
IPv4	X	X	X
IPv6	X		

 external function f\_setInterfaceUp(in charstring interface, in TCCInterface\_IPAddressType addressType:=IPv4);

Set up the given interface. The type of address can be IPv4 or IPv6.

	Linux	Solaris	Cygwin
IPv4	X	X	
IPv6	X	X	

 external function f\_setInterfaceDown(in charstring interface, in TCCInterface\_IPAddressType addressType:=IPv4);

Set down the given interface. The type of address can be IPv4 or IPv6.

	Linux	Solaris	Cygwin
IPv4	X	X	
IPv6	X	X	

external function f\_getHostName() return charstring;

Get name of the current host machine.

Linux	Solaris	Cygwin
X	X	X

 external function f\_getIpAddr(in charstring hostname, in TCCInterface\_IPAddressType addressType:=IPv4) return charstring;

Get IP address of the current host machine called with parameter hostname. The type of address can be IPv4 or IPv6.

	Linux	Solaris	Cygwin
IPv4	X	X	X
IPv6	X	X	

external function f\_getIpAddresses(in charstring hostname return IPAddresses;

Is a successor of f\_getIpAddr Get IP address of the machine called with parameter hostname. It will return two lists of **charstring**, one for all the IPv4 and one for all the IPv6 addresses of hostname.

NOTE

The returned lists are not compatible with any other record of **charstring** in TITAN's load run time library, which is the default, and thus it is not acceptable to directly copy this lists for example to <a href="EPTF\_CharstringList">EPTF\_CharstringList</a>.

	Linux	Solaris	Cygwin
IPv4	X	X	X
IPv6	X	X	

 external function\* \*f\_verifyIpAddr(in charstring pl\_host, in TCCInterface\_IPAddressType pl\_ipType := UNKNOWN) return boolean;

Validates the supplied pl\_host and returns true if it is a valid`\_\_` IP address. The validation can be restricted to IPv4 or IPv6 with the pl\_ipType parameter.

### **Error Messages**

Unbound argument '<parameter>'.

The given parameter is missing.

Argument '<parameter>' is an empty string.

The value of the given parameter is empty.

Argument 'interface' is too long (expected: at most %, given: % characters).

The given interface name is not valid (too long).

Invalid length of argument '<parameter>' (expected %, given: % octets).

The length of the given parameter is not correct.

Could not create socket.

Some kernel error occurred when opening the socket.

```
IP address range limit.
No more virtual interfaces can be set up.
```

```
Setting the IP address is supported on Linux and Solaris only.

Deleting the IP address is supported on Linux and Solaris only.

Getting the IP address is supported on Linux and Solaris only.

Setting up the interface is supported on Linux and Solaris only.

Setting down the interface is supported on Linux and Solaris only.
```

Network Interface Functions are supported on Linux and Solaris only.

# **Warning Messages**

```
Warning messages appear if the kernel could not execute the requested command.
```

```
Could not set IP address of interface '<interface>'.

Could not set subnet mask of interface '<interface>'.

Could not set broadcast address of interface '<interface>'.

Could not get the flags of interface '<interface>'.

Could not set the flags of interface '<interface>'.

Could not delete IP address on interface '<interface>'.

Could not get address of interface '<interface>'.

Could not get flags of interface '<interface>'.

Could not set up interface '<interface>'.

Could not get flags of interface '<interface>'.

Could not set up interface '<interface>'.

Could not set down interface '<interface>'.
```

# **Examples**

```
module TCCInterface_Example {
  import from TCCInterface_Functions all;
  type component test_CT { };
  testcase TC() runs on test_CT
   var charstring ip, subnet, broadcast;
    f_getIP("eth2", ip, subnet, broadcast);
   log("IP: " & ip);
    log("Subnetmask: " & subnet);
   log("Broadcast: " & broadcast);
    setverdict(pass);
  }
  testcase f_test_gethostname() runs on test_CT
   log(" ----- f_getHostName ----- ");
   log("Hostname: ", f_getHostName());
    setverdict(pass);
  }
  testcase f_test_getipaddr() runs on test_CT
    log(" ----- f_getIpAddr -----");
   log("IP address: ", f_getIpAddr(f_getHostName()));
    setverdict(pass);
  }
  control {
    execute(TC());
   execute(f_test_gethostname());
    execute(f_test_getipaddr());
  }
3.3.6
       Makefile
```

### **Makefile**

The -lresolv has to be added to SOLARIS8\_LIBS.

# File I/O Functions

### **Overview**

This bunch of external functions enables you to handle files from TTCN-3. These functions use the POSIX file I/O functions underneath, and they behave similarly. For examples see *TCCFileIO\_Example.ttcn*.

These File I/O Functions were tested under Linux/Solaris/Cygwin platforms.

File I/O Functions are implemented in the following files:

- TCCFileIO\_Functions.ttcn
- TCCFileIO.cc

### **Function Definitions**

The following File I/O Functions are defined. For the exact API check the generated NaturalDocs documentation.

external function f\_FIO\_get\_error\_code ();

The last error code. It simply returns the value of error. Error is a global variable defined by the ISO C standard. Its value is set by the system calls. It always holds the error code for the last error.

external function f\_FIO\_get\_error\_string ();

The last error message in textual format. It simply returns the string associated with the error value returned by f\_FIO\_get\_error\_code.

external function f FIO open (in charstring name);

These functions open the files in different ways using the open system call. Files can be opened in appending or truncating mode for reading only/writing only/reading and writing. These functions always return an integer, the file descriptor for the file name that is now opened or -1 if an error occurred. The error string/code will be available through f\_FIO\_get\_error\_string/f\_FIO\_get\_error\_code. The returned integer can be stored in TTCN-3 and can be used to do I/O operations on a specific file. It is possible to open files in exclusive mode (using the f\_FIO\_open\_\*\_excl functions), but it works differently on Linux/Unix and Cygwin platforms. If a file is opened in exclusive mode in Cygwin, it cannot be reopened from any other process or from the current one in any mode until the file is closed by the lock-holder. Closing the file implicitly releases the lock. Linux/Unix platforms are not that restrictive. It is possible to have a process, which opened the file in exclusive mode and another opened it with e.g.f\_FIO\_open\_append\_wronly. In this case the result is unpredictable. On these platforms it's advisable to always use the functions for exclusive opening to prevent these situations.

external function f\_FIO\_close (in integer fd);

With this function a file associated with a given file descriptor can be closed.

external function f\_FIO\_seek\_ (in integer fd);\*

These functions can seek in files. They can seek to the beginning or end of the file or they can move the file pointer with given bytes forward or backward from its actual position. They simply return what the POSIX function lseek returns.

external function f\_FIO\_write\_ (in integer fd, in octetstring/charstring data/text);

With this function you're able to write binary or textual data to a file. The output buffer is a CHARSTRING in text mode or an OCTETSTRING in binary mode. The buffer is written out from the actual position of the file pointer. To make sure that all data is written out to the disk, call f\_flush after each write or use the appropriate write functions with flush support (with \*\_flush suffix).

 external function f\_FIO\_read\_ (in integer fd, inout octetstring/charstring data/text, in integer bytes);

With these functions you can read a given number of bytes into a TTCN-3 CHARSTRING/OCTETSTRING buffer. CHARSTRING is used for text mode OCTETSTRING is used for binary mode. The given number of bytes are read from the actual position of the file pointer.

external function f\_FIO\_read\_\*\_until (in integer fd, inout octetstring/charstring data/text, in octetstring/charstring separator);

With these functions you can read textual or binary data from a given file token by token. Each token must be separated with the same characters (CHARSTRING) or octets (OCTETSTRING). If the given separator is first matched the appropriate CHARSTRING/OCTETSTRING is returned. Calling these functions next time, they will find the next token. If EOF is reached before the separator pattern is matched "-1" is returned.

 external function f\_FIO\_read\_data\_TLV (in integer pl\_fd, inout octetstring pl\_data) return integer;

With this function you can read binary data -containing a full ASN.1 TLV structure- from a given file. If the full ASN.1 TLV structure is matched the appropriate OCTETSTRING stored in pl\_data. Calling these functions next time, they will find the next ASN.1 TLV structure. This function works only files containing nothing else but full TLV structures. If no full TLV structure is found "-1" is returned, in case of success the length of the TLV structure is returned

• external function f\_FIO\_set\_filedescriptor\_previousline (in integer fd) return integer;

With this function you can set the given file descriptor to the previous line. Calling this function next time, the functions will find the previous previous line. If there was no problem, then the return value will be "1".

• external function f FIO chdir (in charstring pl name) return boolean;

With this function you can change the current directory. If directory change is successful, the true is returned, otherwise false is returned.

• external function f\_FIO\_mkdir (in charstring p\_dir\_name) return boolean;

With this function you can create a directory. If directory creation is successful, the true is returned, otherwise false is returned.

external function f\_FIO\_rmdir (in charstring p\_dir\_name) return boolean;

With this function you can delete a directory. If directory is successfully deleted, the true is returned, otherwise false is returned.

• external function f\_FIO\_fileOrDirExists (in charstring p\_ \_name) return boolean;

With this function you can rename an existing file or directory. If the file or directory not exists, then the return value is false. The target path has to exist as well, otherwise it returns false.

 external function f\_FIO\_rename (in charstring p\_old\_name, in charstring p\_new\_name) return boolean;

With this function you can check the existence of a directory or a file. If the directory or file exists, the true is returned, otherwise false is returned.

external function f\_FIO\_stat (in charstring p\_name, out FIO\_permissions p\_permissions)
 return boolean;

With this function you can query the permission of a directory or a file. If the operation is successful, the true is returned and the  $p_permissions$  contains the permissions, otherwise false is returned.

external function f\_FIO\_chmod (in charstring p\_name, in FIO\_permissions p\_permissions)
 return boolean;

With this function you can set the permissions of the file or directory according to the p\_permissions. If the value of the field is:

- true: sets the permission
- false: clears the permission
- omit: doesn't change the permission

If the operation is successful, the true is returned, otherwise false is returned.

external function f\_FIO\_remove (in charstring pl\_file\_name) return boolean;

With this function you can delete a directory or file. If directory or file is successfully deleted, the true is returned, otherwise false is returned.

external function f\_FIO\_getFileInfo (in charstring p\_name) return FIO\_FileInfo;

This function returns a FIO\_FileInfo, which contains several information about the given file, such as:

- **fileType** the type of the file
- nodeNumber inode number
- mode file type and mode
- linkCount number of hard links
- ownership user ID of owner
- groupId group ID of owner

- blockSize block size for file system I/O
- **fileSize** total size, in bytes
- blocksAllocated number of 512B blocks allocated
- lastStatusChange time of last access in seconds since 1970
- lastFileAccess time of last modification in seconds since 1970
- lastFileModification time of last status change in seconds since 1970

### **Error Messages**

These functions always return "-1" if an error occurs during the execution. The return values must be checked to detect these situations. The corresponding error message/code is available through calling f\_FIO\_get\_error\_string/f\_FIO\_get\_error\_code. By default the functions do not write anything to the standard output/error. If you want to get error reports on the screen, the functions must be compiled with -DVERBOSE\_DEBUG or define a macro VERBOSE\_DEBUG.

#### Cannot open file

The file cannot be opened.

The file is already opened

The file is already opened.

The file is not opened

The file is not yet opened.

Cannot lock file

The file cannot be opened in exclusive mode.

Cannot allocate memory

There's not enough memory to increase the size of the input buffer.

Cannot close file

Read error

Cannot write to file

End of file

EOF is reached unexpectedly.

# **Warning Messages**

None.

# **Examples**

```
module TCCFileIO_Example
{
import from TCCFileIO_Functions all;
type component empty_CT { };
testcase TC_test () runs on empty_CT
  var integer vl_fd;
  var charstring vl_text_out := "First lineabcdefSecond lineabcdefThird
lineabcdefFourth lineabcdef";
  var charstring vl_text_tmp := "abcdef";
  var charstring vl_text_in;
  vl_fd := f_FIO_open_trunc_rdwr_excl ("test1.txt");
  if (vl_fd < 0)
    {
      log (f_FIO_get_error_string ());
      setverdict (fail);
    }
  f_FIO_write_text (vl_fd, vl_text_out);
  f_FIO_flush (vl_fd);
  f_FIO_seek_home (vl_fd);
  for (var integer vl_i := 0; vl_i < 4; vl_i := vl_i + 1)
    {
      var integer n := f_FIO_read_text_until (vl_fd, vl_text_in, vl_text_tmp);
      if (n < 0)
        {
          log (f_FIO_get_error_string ());
          setverdict (fail);
        }
      log (vl_text_in);
    }
  f_FIO_seek_end (vl_fd);
  f_FIO_write_text (vl_fd, vl_text_out);
  f_FIO_close (vl_fd);
  /* Try to close it again. */
  if (f_FIO_close (vl_fd) < 0)</pre>
    {
      setverdict (pass);
    }
}
control
  execute (TC_test ());
}
}
```

# **Assertion Functions**

### **Overview**

Assertion functions enable you to apply assertion from TTCN-3.

These Assertion Functions were tested under Linux/Solaris/Cygwin platforms.

Assertion Functions are implemented in the following files:

- TCCAssertion\_Functions.ttcn
- TCCAssertion.cc

### **Function Definitions**

The following Assertion Functions are defined. For the exact API check the generated NaturalDocs documentation.

external function f\_assert(const CHARSTRING& pl\_assertMessage, boolean pl\_predicate);

If assertion is activated, <code>f\_assert</code> assures that the <code>pl\_predicate</code> parameter is true at call of the function. Else it fails with dynamic test case error and displays assertion message (<code>pl\_assertMessage</code>) as well. To use assertion, optimized build has to be turned on with the <code>-O2</code> switch and NDEBUG shall not be defined. By defining <code>NDEBUG</code>, the main block of <code>f\_assert</code> will be empty, therefore in case of enabled optimized build (<code>-O2</code>) the function is not compiled with the generated code. This results higher debug capability with higher performance.

### **Error Messages**

None.

# **Warning Messages**

None.

# **Examples**

None.

# **Conversion Functions**

### **Overview**

This set of functions enables you to apply conversions from TTCN-3 that have been not supported by TTCN-3 before, for example, universal charstring conversions.

These Assertion Functions were tested under Linux/Solaris/Cygwin platforms.

Conversion Functions are implemented in the following files:

- TCCConversion\_Functions.ttcn
- TCCConversion.cc

### **Function Definitions**

The following Conversion Functions are defined. For the exact API check the generated NaturalDocs documentation.

- external function f\_putInLowercase(charstring pl\_string) return charstring;
   Converts a charstring value to lowercase.
- external function f\_putInUppercase(charstring pl\_string) return charstring;
   Converts a charstring value to uppercase.
- function f\_unichar2charstr (in universal charstring p\_unichar) return charstring
   Converts a universal charstring to charstring.
- function f\_charstr2unichar (in universal charstring p\_unichar) return charstring
   Converts a charstring to universal charstring.

```
function f_replaceFirstOccurenceOfSubstring(
  in charstring parInStr,
  in charstring parSubStrA,
  in charstring parSubStrB) return charstring
```

Replace the first occurance of parSubStrA with parSubStrB in parInStr.

```
function f_replaceEveryOccurenceOfSubstring(
  in charstring parInStr,
  in charstring parSubStrA,
  in charstring parSubStrB) return charstring
```

Replace every occurance of parSubStrA with parSubStrB in parInStr.

```
function f_replaceFirstOccurenceOfPattern(
  in charstring parInStr,
  in charstring parSubStrA,
  in charstring parSubStrB) return charstring`
```

Replace the first occurrence of pattern parSubStrA with parSubStrB in parInStr.

```
function f_replaceEveryOccurenceOfPattern(
  in charstring parInStr,
  in charstring parSubStrA,
  in charstring parSubStrB) return charstring`
```

Replace every occurrence of pattern parSubStrA with parSubStrB in parInStr.

 external function f\_addOctetstring(in octetstring par1, in octetstring par2) return octetstring;

Add two integer values represented in OCTETSTRING. The function can be used in case when an integer representation is needed with larger range then it is available in TTCN-3. Note that negative values are not handled.

 external function f\_subOctetstring(in octetstring par1, in octetstring par2) return octetstring;

Subtract two integer values represented in OCTETSTRING. The function can be used in case when an integer representation is needed with larger range then it is available in TTCN-3.

**NOTE** Negative values are not handled.

 external function f\_compOctetstring(in octetstring par1, in octetstring par2) return integer;

Compares two integer values represented in OCTETSTRING. The function can be used in case when an integer representation is needed with larger range then it is available in TTCN-3.

**NOTE** Negative values are not handled.

- Return 0 in case of identical input arguments.
- Return 1 if the first argument is larger.
- Return 2 if the second argument is larger.
- external function f\_substr\_token(in charstring str,in charstring begin\_token, in charstring end\_token)return charstring;
- external function f\_substr\_token\_oct(in octetstring str,in octetstring begin\_token, in octetstring end\_token)return octetstring;

The function returns a substring from a value. The starting and the ending points are defined by the begin and end tokens. If one of the tokens is not found it returns an empty string. If end\_token is an empty string, the function returns the part of the value after the begin\_token. If

begin\_token is an empty string, the function returns the part of the value until the end\_token. If both of them empty string, the function returns the part whole value.

- function f\_substr\_all\_tokens(in charstring str, in charstring begin\_token, in charstring end\_token) return TCC\_Conversion\_ch\_list
- function f\_substr\_all\_tokens\_oct(in octetstring str, in octetstring begin\_token, in octetstring end\_token) return TCC\_Conversion\_ch\_list

The function returns a list of substring from a value. The starting and the ending points are defined by the begin and end tokens. If one of the tokens is not found it returns an empty string. If end\_token is an empty string, the function returns the part of the value after the begin\_token. If begin\_token is an empty string, the function returns the part of the value until the end\_token. If both of them empty string, the function returns the part whole value.

- external function f\_strstr(in charstring s1,in charstring s2, in integer offset:=0) return integer;
- external function f\_strstr\_oct(in octetstring s1,in octetstring s2, in integer offset:=0)
   return integer;

The f\_strstr function locates the first occurrence of the string s2 in string s1 and returns an index of starting point of the located string, or -1 if the string is not found. If s2 is an empty, the function returns 0. The offset determines the starting point of the search. Any occurrence of the s2 before the offset is ignored. The offset is optional.

function f\_OctetIpv4(in charstring pl\_ip) return octetstring;

Converts a IPv4 dot noted address to its octetstring representation. On error, "0" is returned.

• function f\_oct2str\_safe(in octetstring par1, out charstring par2) return boolean;

Works as the built-in function oct2str of Titan, but in a fault tolerant way. In case of any fault, false is returned, otherwise true. The second parameter will contain the decoded string as long as it could be decoded.

• function f\_IPv6CreateLiteral(in charstring pl\_ip) return charstring

Encloses parameter pl\_ip in square brackets. (Used to generate IPv6 literal address.)

external function f\_isNumber(charstring pl\_string, integer pl\_number) return charstring;

Checks if the input string starts with digits. If yes, then it returns the integer value in pl\_number and the remaining string as return value. If the string does not start with a conversable number, it will return 0 in pl number.

• function f\_isWhiteSpace(in charstring pl\_str) return boolean

Checks if the input string consists of only white space characters. If the string only contains white space characters then it returns true, else it returns false. For an empty string it returns false.

• function f\_prePadString(charstring pl\_string, charstring pl\_pad, integer pl\_length, inout charstring pl\_result) return Boolean

Pads a string to fit in a specified length (pl\_length). The pl\_string will be prepended by the first

### **Error Messages**

None.

# **Warning Messages**

None.

# **Examples**

The following code part shows an example for using replace pattern functions. The input string (replacestr) is "AaACCCAaABbB" and the pattern that every occurrence shall be replaced is "([Aa]#(3,3)". The substitution string is "<3A>". So the aim of this short test is to change three-character long A or a sequences to "<3A>". Notice that pattern shall match to the whole string and pattern to swap shall be grouped with opening and closing brackets (). Awaited response (rStr4) is <3A>CCC<3A>BbB.

```
testcase f_test_replaceEveryOccuranceOfPattern() runs on Conversion_CT
{
  log(" ------ f_replaceEveryOccurenceOfPattern ----- ");
  log("Original string: ", replacestr);
  tmpStr :=
    f_replaceEveryOccurenceOfPattern(
        replacestr, "*([Aa]#(3,3))*", "<3A>");
  log("Replace every occurence of *([Aa]#(3,3))* to <3A>: ",
        tmpStr);

if (tmpStr == rStr4) { setverdict(pass); }
  else { setverdict(fail); }
}
```

### **Makefile**

External functions, f\_substr\_token\_oct and f\_strstr\_oct use memmem, so D\_GNU\_SOURCE flag should be added to the CPPFLAGS in case of Cygwin environment.

### **Date and Time Functions**

#### **Overview**

Date and Time Functions enable you to handle date and time from TTCN-3.

These Date and Time Functions were tested under Linux/Solaris/Cygwin platforms.

Date and Time Functions are implemented in the following files:

- TCCDateTime Functions.ttcn
- TCCDateTime.cc

#### **Function Definitions**

The following Date and Time Functions are defined. For the exact API check the generated NaturalDocs documentation.

external function f\_time() return integer;

Provides the current calendar time of the system in seconds.

external function f\_time\_ms() return integer;

Provides the current calendar time of the system in milliseconds.

external function f\_ctime(integer pl\_sec) return charstring;

Converts a time value in seconds to human readable string in local system time.

external function f\_ctime\_ms(integer pl\_msec) return charstring;

Converts a time value in milliseconds to human readable string in local system time.

external function f\_ctime\_UTC(integer pl\_sec) return charstring;

Converts a time value in seconds to human readable string in UTC.

external function f\_ctime\_ms\_UTC(integer pl\_msec) return charstring;

Converts a time value in milliseconds to human readable string in UTC.

external function f\_getTpscts() return charstring;

Returns the current GMT time in TP-SCTS format, ex: 18020714540200 (i.e., 2018 February 07 14:54:02 GMT+00).

 external function f\_getTimeFormatted(integer pl\_sec, charstring pl\_format) return charstring;

Provides the current calendar time in a formatted way. Format string:

specifier	Replaced by	Example
%a	Abbreviated weekday name *	Thu
%A	Full weekday name *	Thursday
%b	Abbreviated month name *	Aug
%B	Full month name *	August

specifier	Replaced by	Example
%c	Date and time representation *	Thu Aug 23 14:55:02 2001
%d	Day of the month (01-31)	23
%Н	Hour in 24h format (00-23)	14
%I	Hour in 12h format (01-12)	02
%j	Day of the year (001-366)	235
%m	Month as a decimal number (01-12)	08
%M	Minute (00-59)	55
%p	AM or PM designation	PM
%S	Second (00-61)	02
%U	Week number with the first Sunday as the first day of week one (00-53)	33
%W	Weekday as a decimal number with Sunday as 0 (0-6)	4
%W	Week number with the first Monday as the first day of week one (00-53)	34
%x	Date representation *	08/23/01
%X	Time representation *	14:55:02
%y	Year, last two digits (00-99)	01
%Y	Year	2001
%Z	Timezone name or abbreviation	CDT
%%	A % sign	%

The specifiers whose description is marked with an asterisk (\*) are locale-dependent.

 external function f\_time2sec(integer pl\_year, integer pl\_mon, integer pl\_day, integer pl\_hour, integer pl\_min, integer pl\_sec) return integer;

Converts date format to seconds since January 1, 1970. The date treated as local time.

 external function f\_time2sec\_UTC(integer pl\_year, integer pl\_mon, integer pl\_day, integer pl\_hour, integer pl\_min, integer pl\_sec) return integer;

Converts date format to seconds since January 1, 1970. The date treated as UTC time.

external function f\_getCurrentDateWithOffset(integer pl\_sec) return charstring;

Generates a date from the actual date and time plus the parameter in seconds, for example getSdate(30) will return a charstring containing the date and time of 30 seconds later

external function f\_getCurrentGMTDate() return charstring;

Returns the current GMT date in format RFC 1123-Date ex: Sat Nov 13 23:30:02 2010

external function f\_getCurrentGMTDate\_ms() return charstring;

Returns the current GMT date in format Www Mmm dd hh:mm:ss.SSS yyyy ex: Sat Nov 13

external function f\_tic() return integer;

Returns the number of clock ticks used by the application since the program was launched.

WARNING

Functionality depends on the used library. Man page shall be read for clock() function.

external function f\_toc() return charstring;

Returns the elapsed seconds since time t.

WARNING

Functionality depends on the used library. Man page shall be read for clock() function. f\_toc() depends on f\_tic().

external function f\_timeDiff(integer t\_stop, integer t\_start) return integer;

Returns the difference between two time values.

 external function f\_getTpscts(in integer pl\_sec:=-1, in integer pl\_tz:=0) return charstring;
 external function f\_getOctTpscts(in integer pl\_sec:=-1, in integer pl\_tz:=0) return octettring;

Returns the special timestamp called TP Service Centre Time Stamp (TP SCTS), 3GPP TS 23.040

- pl sec time value in seconds since epoch or -1, if -1 is supplied the current time is used
- pl\_tz \*in\* \*integer\* time zone offset in minutes

### **Error Messages**

None.

### **Warning Messages**

None.

### **Examples**

The following code part shows some examples for date and time functions.

The first test case returns the current time in seconds (for example, 1195459285):

```
testcase f_test_time() runs on DateTime_CT
{
    log(" ----- f_time ----- ");
    log("Time (f_time): ", f_time());
    setverdict(pass);
}
```

The second test case converts time in seconds into time string. Note that time is in format Www Mmm dd hh:mm:ss yyyy and awaited result is current local time minus an hour because of subtraction of 3600 seconds from input.

```
testcase f_test_ctime() runs on DateTime_CT
{
    log(" ----- f_ctime ----- ");
    log("CTime (f_ctime) - an hour before: ",
        f_ctime(f_time() - 3600));
    setverdict(pass);
}
```

The third test case returns time as specified in format string

(for example, 1195459285 + "%m %I:%M%p." → 11 **09:01**AM.)

```
testcase f_test_getTimeFormatted() runs on DateTime_CT
{
   log(" ------ f_getTimeFormatted ----- ");
   log("TimeFormatted (f_getTimeFormatted): ",
      f_getTimeFormatted(f_time(),"Now is %m %I:%M%p."));
   setverdict(pass);
}
```

The fourth test case returns current time with offset seconds defined by input. (For example, with no input offset: Mon Nov 19 **09:01**:25 2007)

```
testcase f_test_getCurrentDateWithOffset() runs on DateTime_CT
{
   log(" ----- f_getCurrentDateWithOffset ----- ");
   log("Date (f_ getCurrentDateWithOffset): ",
      f_getCurrentDateWithOffset(0));
   setverdict(pass);
}
```

The fifth test case returns GMT time. Notice bolded time value compared to f\_getTimeFormatted() and f\_getCurrentDateWithOffset().

(For example, 1195459285 → Mon Nov 19 **08:01**:25 2007)

```
testcase f_test_getCurrentGMTDate() runs on DateTime_CT
{
  log(" ------ f_getCurrentGMTDate ----- ");
  log("GMT Date (f_getCurrentGMTDate): ",
    f_getCurrentGMTDate());
  setverdict(pass);
}
```

### **Maths Functions**

### **Overview**

Maths functions enable you to use mathematical functions straightforward from TTCN-3.

These Maths Functions were tested under Linux/Solaris/Cygwin platforms.

Maths Functions are implemented in the following files:

- TCCMaths\_Functions.ttcn
- TCCMaths\_GenericTypes.ttcn
- TCCMaths.cc

### **Function Definitions**

The following Maths Functions are defined:

external function f\_maxIL(in IntegerList ilist) return IntegerList;

Return an IntegerList with the highest number found at index 0 and the index of ilist where it's found at index 1.

external function f\_maxFL(in FloatList flist) return FloatList;

Return a FloatList with the highest number found at index 0 and the index of flist where it's found at index 1.

external function f\_minIL(in IntegerList ilist) return IntegerList;

Return an IntegerList with the lowest number found at index 0 and the index of ilist where it's found at index 1.

external function f minFL(in FloatList flist) return FloatList;

Return a FloatList with the lowest number found at index 0 and the index of flist where it's found at index 1.

external function f\_averageFL(in FloatList flist) return float;
 Return the average of flist.

external function f\_averageIL(in IntegerList ilist) return float;
 Return the average of ilist.

external function f\_updateFL(inout FloatList head, in FloatList tail);

external function f\_updateIL(inout IntegerList head, in IntegerList tail);
 Append tail to the end of head (head return as inout).

external function f\_stdFL(in FloatList flist) return float;

Append tail to the end of head (head return as inout).

Return the normalized standard deviation of flist (so the average square distance from the centre of points).

For example, let there be a list of list =  $\{2.0, 4.0\}$  and thereafter the average of elements is u = (2.0 + 4.0) / 2.0. The result of the function is afterwards the square root of the average square distance, so  $((2.0 - u)^2 + (4.0 - u)^2) / len$ , where len means the length of the list.

external function f\_stdFLL(in FloatList flist, in float u) return float;

Return the normalized standard deviation of flist from a user defined center value (so the average square distance from a user defined centre value). For example, let there be a list of list =  $\{2.0, 4.0\}$  and thereafter the user specifies a value. This value is named as u. The result of the function is afterwards the square root of the average square distance from u, so (  $(2.0 - u)^2 + (4.0 - u)^2$ ) / len, where len means the length of the list.

external function f\_stdIL(in IntegerList ilist) return float;

Return the normalized standard deviation of ilist (so the average square distance from the centre of points). For example, let there be a list of list =  $\{2, 4\}$  and thereafter the average of elements is u = (2 + 4) / 2. The result of the function is afterwards the square root of the average square distance, so  $((2 - u)^2 + (4 - u)^2) / len$ , where len means the length of the list.

external function f\_stdILL(in IntegerList ilist, in float u) return float;

Return the normalized standard deviation of ilist (so the average square distance from the center of points).

NOTE

u is the average value of flist and has to be calculated before a call to this function.

For example let there be a list of list =  $\{2, 4\}$  and thereafter the user specifies a value. This value is named as u. The result of the function is afterwards the square root of the average square distance from u, so ( $(2 - u)^2 + (4 - u)^2$ ) / len, where len means the length of the list.

```
external function f_sinVL(
  in float freq,
  in float altitude,
  in float start_val,
  in integer len,
  in float step) return FloatList;
```

Return the values of the sine function. The computation is the following: altitude \*  $sin(2 \pi freq*start_val)$  then start value is increased by step in every iteration till a number of len sine values are achieved.

```
external function f_cosVL(
  in float freq,
  in float altitude,
  in float start_val,
  in integer len,
  in float step) return FloatList;
```

Return the values of the cosine function. The computation is the following: altitude \*  $cos(2 \pi freq*start_val)$  then start value is increased by step in every iteration till a number of len cosine values are achieved.

- external function f\_sin(in float angle) return float;
   Return the sine of angle radians.
- external function f\_cos(in float angle) return float;
   Return the cosine of angle radians.
- external function f\_asin(in float val) return float; Return the arc sine of value in  $[-\pi/2, +\pi/2]$ .
- external function f\_acos(in float val) return float; Return the arc cosine of value in  $[0, \pi]$ .
- external function f\_powFF(in float base, in float expo) return float;
   Raise to power (float to float power).
- external function f\_powII(in integer base, in integer expo) return integer;
   Raise to power (integer to integer power).

- external function f\_powIF(in integer base, in float expo) return float;
   Raise to power (integer to float power).
- external function f\_powFI(in float base, in integer expo) return float;
   Raise to power (float to integer power).
- external function f\_sqrF(in float base) return float;
   Raise a float value to square.
- external function f\_sqrI(in integer base) return integer;
   Raise an integer value to square.
- external function f\_sqrtF(in float base) return float;
   Square root of a float value.
- external function f\_sqrtI(in integer base) return float;
   Square root of an integer value.
- external function f\_ceil(in float val) return integer;
   Return the smallest integer value that is not less then value.
- external function f\_floor(in float val) return integer;
   Return the largest integer value that is not greater then value.
- external function f\_exp(in float val) return float;
   Return the exponential value of the argument.
- external function f\_log(in float val) return float;
   Return the natural logarithm of the argument.
- function f\_generate\_poissonTable(in float p\_lambda, out t\_Poisson\_Table p\_pTable) return boolean;

Generate the Poisson cumulative probability distribution list for a given lambda and returns true if the generation was success. If the lambda is below 0, the function returns false and the Poisson table will contain false values. With the implemented method we can only generate correct values for lambda-s smaller than about 100-110. It is because the elements above about 300 in the table will be 1.0 due to rounding errors. The table will contain lambda \* 2 elements.

• function f\_getNext\_poissonValue(in float p\_lambda, inout t\_Poisson\_Table p\_pTable, out boolean p\_sucess) return integer

Return a random Poisson value by the given Poisson table and lambda. Regenerate the table if it is necessary.

function f\_gen\_Exponential\_Distribution(in float p\_lambda) return float

Return the exponential random variable for a given lambda.

### **Error Messages**

None.

# **Warning Messages**

None.

# **Examples**

The first example shows usage of f\_sinVL function. Let the following definitions be valid:

```
var float freq := 10.0;  // frequency
var float alti := 5.0;  // altitude
var float startval := 0.0; // start value
var float step := 0.37;  // steplength
var integer len := 5;  // length of returned value list
```

The function computes sine values as altitude \* sin(2 \* pi \* freq \* start\_val) and then start value is increased with step parameter. The returned value list will consist of the values computed this way and a number of len values will be stored in that list.

```
The awaited result in this case is: {0.0, -4.755283, 2.938926, 2.938926, -4.755283}
```

```
testcase f_test_sinVL() runs on Maths_CT
 log(" ----- f sinVL ----- ");
 log("SINUS (Frequency: ", freq,
   ", altitude: ", alti,
   ", startval: ", startval,
   ", step: ", step,
   ", return length: ", len, "):");
 fres := f_sinVL(freq, alti, startval, len, step);
 log("Sinus values returned: ", fres);
 // check
 sum := 0.0;
 for (var integer i := 0; i < len; i := i + 1)
   tmpFloat := fres[i] - sin1[i];
   sum := sum + tmpFloat * tmpFloat;
 if (sum < LIMIT) { setverdict(pass); }</pre>
 else { setverdict(fail); }
}
```

The second test case computes the normalized standard deviation from a user defined value of a float list. This case the user defined value is the average of values in the input list, so the awaited result is the same as  $f_stdFL()$ .

```
testcase f_test_stdFLL() runs on Maths_CT
{
  log(" ------ f_stdFLL ------ ");
  log("Original float list: ", flist1);
  tmpFloat := f_stdFLL(flist1, f_averageFL(flist1));
  log("Normalized, standard derivation (FLL): ", tmpFloat);

if ((tmpFloat - stdFLL1) * (tmpFloat - stdFLL1) < LIMIT) {
    setverdict(pass);
  }
  else {
    setverdict(fail);
  }
}</pre>
```

The third test case returns the value and the position of the maximal element in an integer list.

Return value for ilist1 =  $\{1, 2, 3, 4, 5\}$  is maxIL1 =  $\{5, 4\}$  as the maximal element is 5 and its index in the list is 4.

# **Security Functions**

#### **Overview**

Security Functions enable you to use some security related functions from TTCN-3.

These Security Functions were tested under Linux/Solaris/Cygwin platforms.

Security Functions are implemented in the following files:

- TCCSecurity\_Functions.ttcn
- TCCSecurity.cc

#### **Function Definitions**

The pl\_OP input of the following functions is the Operator Variant OP that configures the AKA Algorithms to generate the proper keys for the Operator who will verify the generated keys.

The following Security Functions are defined. For the exact API check the generated NaturalDocs documentation.

```
external function f_calculateDigestResponse(
    charstring nonce,
    charstring user,
    charstring realm,
    charstring passwd,
    charstring alg,
    charstring nonceCount,
    charstring method,
    charstring dop,
    charstring URI,
    charstring HEntity) return charstring;
```

Calculate digest response. Support HTTP authentication (detailed description in RFC 2617) using uses one-way hash (md5) specified in RFC 1321. When a request arrives to server for an access-protected object, it responds an "401 Unauthorized" status code and a WWW-Authenticate header (encapsulate nonce and other necessary parameters). The client is expected to retry the request, passing an Authorization header with response field calculated with f\_calculateDigestResponse(). Overview: http://en.wikipedia.org/wiki/Digest\_access\_authentication

```
*external function f_calculateDigestHA1(
  charstring nonce,
  charstring charstring user,
  charstring realm,
  charstring passwd,
  charstring alg) return charstring;*
```

Calculate digest H(A1) hash (detailed description in RFC 2617).

- external function f\_calculateMD5(in charstring pszHashInput) return charstring;
   Calculate the md5 hash value of pszHashInput. The result is the hash converted to hexa string.
- external function f\_calculateMD5\_oct(in octetstring pszHashInput) return octetstring;
   Calculate the md5 hash value of pszHashInput.
- external function f\_calculateHMACMD5(in octetstring msg, in OCT\_64 key) return octetstring;
   Calculate the HMAC MD5 hash value of msg with the encryption key. The result is the hash octetstring which is 16 octet long.
- external function f\_calculate\_HMAC\_MD5(in octetstring pl\_key, in octetstring pl\_input, in integer pl\_length) return octetstring;

Calculate the HMAC MD5 value of a message with specified key.

 external function f\_calculate\_HMAC\_SHA1(in octetstring pl\_key, in octetstring pl\_input, in integer pl\_length) return octetstring;

Calculate the HMAC SHA1 value of a message with specified key.

 external function f\_calculate\_HMAC\_SHA256(in octetstring pl\_key, in octetstring pl\_input, in integer pl\_length) return octetstring;

Calculate the HMAC SHA256 value of a message with specified key.

- external function f\_calculateRAND\_oct(in integer pl\_length) return octetstring;
   Generate a random octetstring via OpenSSL
- external function f\_calculateSHA1\_oct(in octetstring pszHashInput) return octetstring;
   Compute SHA1 hash value via OpenSSL in octetstring format
- external function f\_calculateSHA1(in charstring pszHashInput) return charstring;

Compute SHA1 hash value via OpenSSL

 external function f\_AES\_CBC\_Encrypt\_OpenSSL(octetstring p\_key, octetstring p\_iv, octetstring p\_data) return octetstring;

Calculate via OpenSSL the AES CBC encrypted value with arbitrary key length up to 128 bits

external function f\_AES\_CBC\_Decrypt\_OpenSSL(octetstring p\_key, octetstring p\_iv, octetstring p\_data) return octetstring;

Calculate via OpenSSL the AES CBC decrypted value with arbitrary key length up to 128 bits

The IMSAKA related functions have two forms:

- One which takes OP as input parameter
- One which works with OPC instead of OP

The latter ones are post-fixed with "\_opc"

 external function ef\_3DES\_ECB\_Decrypt(in octetstring pl\_data, in octetstring pl\_key, in boolean pl\_use\_padding:=true) return octetstring;

It encrypts the data using the triple DES algorithm in ECB (Electronic Codebook) mode taking key pl key. The pl use padding parameter controls the usage of standard PKCS padding.

 external function ef\_3DES\_ECB\_Decrypt(in octetstring pl\_data, in octetstring pl\_key, in boolean pl\_use\_padding:=true) return octetstring;

Decrypts triple DES ECB encrypted data using pl\_key. The pl\_use\_padding parameter controls the usage of standard PKCS padding.

 external function ef\_3DES\_CBC\_Encrypt(in octetstring pl\_data, in octetstring pl\_key, in octetstring pl\_iv, in boolean pl\_use\_padding:=true) return octetstring;

It encrypts the data using the triple DES algorithm in CBC (Cipher-block chaining) mode taking key pl\_key. The pl\_use\_padding parameter controls the usage of standard PKCS padding.

 f\_3DES\_CBC\_Encrypt(octetstring p\_key, octetstring p\_iv, octetstring p\_data) return octetstring

Wrapper function for above ef\_3DES\_CBC\_Encrypt

 external function ef\_3DES\_CBC\_Decrypt(in octetstring pl\_data, in octetstring pl\_key, in octetstring pl\_iv, in boolean pl\_use\_padding:=true) return octetstring;

Decrypts triple DES CBC encrypted data using pl\_key. The pl\_use\_padding parameter controls the usage of standard PKCS padding.

 function f\_3DES\_CBC\_Decrypt(octetstring p\_key, octetstring p\_iv, octetstring p\_data) return octetstring

Wrapper function for above ef 3DES CBC Decrypt

 external function ef\_Calculate\_AES\_XCBC\_128(in octetstring pl\_data, in octetstring pl\_key, in integer pl\_out\_length) return octetstring; Calculates the AES XCBC value from pl\_data and pl\_key. AES XCBC generates a value that is 16 bytes long and this can be truncated to the length given in pl\_out\_length.

external function ef\_DH\_shared\_secret(in octetstring pl\_pubkey, in octetstring pl\_privkey)
 return octetstring;

Computes the shared secret for the Diffie-Hellman exchange given the private key of the originating side and the public key of the responding side. The keys must be 96 or 128 or 256 bytes long. (DH MODP group 768 and 1024 and 2048)

 external function ef\_DH\_generate\_private\_public\_keys (in integer pl\_keyLength, inout octetstring pl\_pubkey, inout octetstring pl\_privkey) return integer;

Computes the shared secret from the originating side's private key and the public key of the responding side as described in DH group 2 and 14. Keys must be either 96, 128 or 256 bytes long.

### **Error Messages**

None.

### **Warning Messages**

None.

# **Examples**

The following example shows a basic usage of digest response calculation. The provided data values are acquired from the server resp`\_\_`onse and client data.

**NOTE** qop is equal to auth and therefore HEntity is the md5 hash value of empty string.

There is a sample test case for AKA key generation functions and EEA3 and EIA3 calculation.

```
type record DigestData {
  charstring nonce,
  charstring cnonce,
  charstring user,
  charstring realm,
  charstring passwd,
  charstring alg,
  charstring nonceCount,
  charstring method,
  charstring qop,
  charstring URI,
  charstring HEntity
}
type record AKAInput {
  octetstring k,
  octetstring rand,
  octetstring sqn,
  octetstring amf
}
type record SIMOutput {
  octetstring sres,
  octetstring kc
}
// test f_calculateDigestResponse function
testcase f_test_digestresponse() runs on Security_CT
{
  log(" ----- f_calculateDigestResponse ----- ");
  dg := {
    nonce := "dcd98b7102dd2f0e8b11d0f600bfb0c093",
    cnonce := "0a4f113b",
    user := "Mufasa",
    realm := "testrealm@host.com",
    passwd := "password",
    alg := "MD5",
    nonceCount := "00000001",
    method := "GET",
    qop := "auth",
    URI := "/dir/index.html",
    // MD5 hash of entity body
    HEntity := "d41d8cd98f00b204e9800998ecf8427e"
  }
  log("Data to compute digest from: ", dg);
  log("Digest response: ",
    f_calculateDigestResponse(
        dg.nonce,
```

```
dg.cnonce,
    dg.user,
    dg.realm,
    dg.passwd,
    dg.alg,
    dg.monceCount,
    dg.method,
    dg.qop,
    dg.URI,
    dg.HEntity));

// no check
setverdict(pass);
}
```

#### 3DES ECB encrypt decrypt

```
var octetstring vl_key := '000102030405060708090A0B0C0D0E0F0011223344556677'0

var octetstring vl_data := '61A7D3BEAA4C7DBD1FA3B2237A8CC92AE6575BADF894A34643D74AFF502BF523973DF1637453388CC4C06
EC02D8AB44E3EDC866555BC0FDC56D0B2029110D7A1A1F585B65FB84D3674EC87B30BF5E7E8F747330549C
77A9CCD348B7898825302408CE53D25ED62D56CA0FFACC0DFECDC9CFCBD03279047'0

var octetstring vl_encrypted_data := ef_3DES_ECB_Encrypt(vl_data, vl_key);

var octetstring vl_decrypted_data := ef_3DES_ECB_Decrypt(vl_encrypted_data, vl_key);
```

#### 3DES CBC encrypt decrypt

```
var octetstring vl_data :=
'61A7D3BEAA4C7DBD1FA3B2237A8CC92AE6575BADF894A34643D74AFF502BF523973DF1637453388CC4C06
EC02D8AB44E3EDC866555BC0FDC56D0B2029110D7A1A1F585B65FB84D3674EC87B30BF5E7E8F747330549C
77A9CCD348B7898825302408CE53D25ED62D56CA0FFACC0DFECDC9CFCBD03279047'0

var octetstring vl_key := '000102030405060708090A0B0C0D0E0F0011223344556677'0

var octetstring vl_iv := '0001020304050607'0

var octetstring vl_encrypted :=
ef_3DES_CBC_Encrypt(vl_data, vl_key, vl_iv);

var octetstring vl_decrypted := ef_3DES_CBC_Decrypt(vl_encrypted, vl_key, vl_iv);
```

#### AES XCBC 128 with 20 bytes of data

```
var octetstring vl_data := '000102030405060708090a0b0c0d0e0f10111213'0

var octetstring vl_key := '000102030405060708090a0b0c0d0e0f'0

var octetstring vl_computed_value := ef_Calculate_AES_XCBC_128(vl_data, vl_key, 16);
```

#### Diffie-Hellman secret key

```
var octetstring vl_key_other :=
'73DF1637453388CC4C06EC02D8AB44E3EDC866555BC0FDC56D0B2029110D7A1A1F585B65FB84D3674EC87
B30BF5E7E8F747330549C77A9CCD348B7898825302408CE53D25ED62D56CA0FFACC0DFECDC9CFCBD032790
47E90E4E5013F173AE9E61A7D3BEAA4C7DBD1FA3B2237A8CC92AE6575BADF894A34643D74AFF502BF5239'
0

var octetstring vl_priv_key :=
'9FCF731129397EF7DC51562D71DD819DE35891B739BD6BE7A5177F676F1A06775A0E915E3758130FE5493
B95C7A67F11F45E4C541DDD2834E4A9248F18EE2597936499C97D25227C4A4B78BABD4F33BBC3E3A2C5913
69A3A4FAF3D851839249E23E90D15051268986E562D76D756F7FAF942FFBC4669199A3C04E31335E2BD70'
0

var octetstring vl_shared_secret := ef_DH_shared_secret(vl_key_other, vl_priv_key);
```

# **Message Handling Functions**

#### **Overview**

Message handling functions enable you to get the length of the received message.

Message Handling Functions are implemented in the following files:

- TCCMessageHandling\_Functions.ttcn
- TCCMessageHandling.cc

#### **Function Definitions**

The following Message Handling Functions shall be defined:

- external function f\_\* \*TCCMessageHandling\_getMessageLength (in octetstring) return integer;
  - Return the length of the given message. This function is searching the Content-Length filed in the given character based message and returns with the value of this field. This function can be used for example by the HTTP and SIP message transport.
- external function f\_\* \*TCCMessageHandling\_getMessageLength4Diameter (in octetstring) return integer;

Return the length of the given message. This function can be used for Diameter message transport.

 external function f\_\* \*TCCMessageHandling\_getMessageLength4Radius (in octetstring) return integer;

Return the length of the given message. This function can be used for Radius message transport.

 $\bullet$  external function f\_\* \*TCCMessageHandling\_getMessageLength4BER (in octetstring) return integer;

Return the length of the given BER encoded message. For definite length format the length is determined by parsing the Length field. For indefinite length format the whole TLV message is parsed. The function returns -1 if the length cannot be determined (For definite length format the message segment does not contain the whole length field. For indefinite length format the message is not a complete TLV).

NOTE

The input can be a message segment or multiple concatenated messages as long as the beginning of the input is the beginning of a TLV encoded BER message. This function is useful for TCP transport in the IPL4 test port.

### **Error Messages**

None.

# **Warning Messages**

None.

# **Examples**

```
module TCCMessageHandling_Example {
import from TCCMessageHandling_Functions all;
control
{
    //the call of the function
    f_TCCMessageHandling_getMessageLength(''0);
}
```

# **Permutated Parameters Handling**

#### **Overview**

Permutated parameters functions enable you to determine permutations of multiple parameters. Parameters are assigned with their types and values in assignment lists. Permutation of the parameters are calculated with the available functions.

#### Permutation example:

#### Types and values:

```
• OPN (other party number): OPN_1, OPN_2
```

• TOD (Time Of Day): TOD\_1 (Monday morning), TOD\_2 (Saturday noon)

• CGI (Cell Global Identifier): CGI\_1, CGI\_2

• DUR (Call Duration): DUR\_1, DUR\_2

#### See generated permutations below:

Call #1	CDPN_1	TOD_1	CGI_1	DUR_1
Call #2	CDPN_1	TOD_1	CGI_1	DUR_2
Call #3	CDPN_1	TOD_1	CGI_2	DUR_1
Call #4	CDPN_1	TOD_1	CGI_2	DUR_2
Call #5	CDPN_1	TOD_2	CGI_1	DUR_1
Call #6	CDPN_1	TOD_2	CGI_1	DUR_2
Call #7	CDPN_1	TOD_2	CGI_2	DUR_1
Call #8	CDPN_1	TOD_2	CGI_2	DUR_2
Call #9	CDPN_2	TOD_1	CGI_1	DUR_1
Call #10	CDPN_2	TOD_1	CGI_1	DUR_2
Call #11	CDPN_2	TOD_1	CGI_2	DUR_1
Call #12	CDPN_2	TOD_1	CGI_2	DUR_2
Call #13	CDPN_2	TOD_2	CGI_1	DUR_1
Call #14	CDPN_2	TOD_2	CGI_1	DUR_2
Call #15	CDPN_2	TOD_2	CGI_2	DUR_1
Call #16	CDPN_2	TOD_2	CGI_2	DUR_2

Permutated parameters handling Functions are implemented in the following files:

- TCCPermutatedParameters\_Definitions.ttcn
- TCCPermutatedParameters\_Functions.ttcn

#### **Function Definitions**

```
function f_PP_getPermutatedParams(
   in integer pl_permutationIdx,
   in EPTF_CharstringList pl_paramTypes,
   in PP_ParamSet pl_assignmentList
) return PP_ParamSet
```

Returns a parameter set calculated from the index of the permutation. The values of the parameters are composed into the prefix field.

```
function f_PP_countPermutations(
  in EPTF_CharstringList pl_paramTypes,
  in PP_ParamSet pl_assignmentList
) return integer
```

Calculates the permutations of the parameters, using the parameter types as filters. Permutations are calculated by multiplying the number of parameters belonging to different types.

```
function f_PP_divideValuesOfTypes(
  in EPTF_CharstringList pl_paramTypes,
  in PP_ParamSet pl_assignmentList,
  in integer pl_LGenIdx,
  in integer pl_noOfLGens) return PP_ParamSet
```

Function returns a portion of parameters. The portion is calculated from the portion (ie LGen) index and number of portions (ie number of LGens).

```
function f_PP_countValuesOfTypes(
  in EPTF_CharstringList pl_paramTypes,
  in PP_ParamSet pl_assignmentList
  ) return integer \{
```

Returns the number of values present in the assignment list, filtered for the types requested.

```
public function f_PP_normalizeParams(
  in PP_ParameterAssignmentList pl_assignmentList,
  out PP_ParamSet pl_normalizedParams)
```

Function to be used on assignment list to group the values belonging to the same type together. The functions below can only work on normalized parameters.

```
public function f_PP_getParamValueFromSet(
  in PP_ParamSet pl_paramSet,
  in EPTF_CharstringList pl_typeList
) return EPTF_CharstringList
```

Function returns the single parameter value if its parameter types matches one of the given types.

### **Error Messages**

None.

### **Warning Messages**

None.

# **Examples**

None.

Please contact 'ttcn3 (ETH)' mailing list to get advice on usage.

# **Titan Metadata Functions**

### **Overview**

Titan Metadata functions enable you to get meta information provided by the Titan compiler directly from TTCN-3.

These Titan Metadata Functions were tested under Linux/Solaris/Cygwin platforms.

Titan Metadata Functions are implemented in the following files:

- TCCTitanMetadata\_Functions.ttcn
- TCCTitanMetadata.cc

### **Function Definitions**

The following Metadata Functions are defined. For the exact API check the generated NaturalDocs documentation.

```
external function f_assert(boolean pl_predicate);
```

Return the compilation time of module

# **Error Messages**

None.

### **Warning Messages**

None.

### **Examples**

The following example shows the compilation time of module, for example Nov 17 2007 17:14:09.

```
module TCCTitanMetadata_Example
import from TCCTitanMetadata Functions all;
type component Metadata_CT
{
}
// TitanMetadata functions
// test f_time function
function f_test_compilationTime() runs on Metadata_CT
 log(" ----- f_compilationTime ----- ");
 log("Compilation time: ", f_compilationTime());
}
// test all TitanMetadata functions
testcase tc_TitanMetadata_execAll() runs on Metadata_CT
 log(" ############### TITAN MetaData ############# ");
 f_test_compilationTime();
 setverdict(pass);
}
}
```

# Text Template Substitution Functions

#### **Overview**

This module enables to do string substitutions on a text template accord to a given dictionary. The dictionary tells what to substitute to a new string, but not only strings can be in the dictionary, but simple patterns too, and the may contain function references to calculate the new string.

Message Handling Functions are implemented in the following files:

• TCCTemplate\_Functions.ttcn

Patterns can be used as dictionary keys. Every character will match itself, but the "\w" meta string will match one or more characters in the text template. The substrings matched with "\w" will be passed to the function referenced in the dictionary as a list of charstrings.

#### **Function Definitions**

The following Template Functions shall be defined:

• function f\_Template\_substitutetemplate(in TCCSubstitutionList pl\_dict, in charstring pl\_string) return charstring

This function applies the dictionary to its parameter pl\_string, and gives the result back.

function f\_Template\_subsfiletemplate(in TCCSubstitutionList pl\_dict, in charstring pl\_file)
 return charstring

The function reads in the given files content, applies the dictionary to it, and gives the result back.

### **Error Messages**

Error while closing file!

May happen when f\_Template\_subsfiletemplate is used, and the file can not be closed. ``´´ returned in this case.

# **Warning Messages**

None.

# **Examples**

```
function nlist(in charstringList pl_params) return charstring{
    // log("params: ",pl_params,"\n");
    if (sizeof(pl_params)==3 and pl_params[2]=="R"){
        return int2str(6453);
    } else { return int2str(9);}
}

log(f_Template_subsfiletemplate({{"$(caiSs)","CAISS",omit},{"$(caiSq)","CAISQ",omit},{"$(<\\w.\\w>[\\w])","",
    refers(nlist)}},"cai3g_delete_PoCGroupsXDMSUser.body"));
```

### **IPsec Functions**

#### **Overview**

The IPsec Functions provides a TTCN interface to handle the IPsec parameters stored in two databases: the Security Associations Database (SAD) and the Security Policy Database (SPD). Both the PF\_KEY API and the Netlink XFRM API is supported with TTCN interfaces via different functions.

#### PF\_KEY API

IPsec Handling Functions are implemented in the following files:

- TCCIPsec\_Definitions.ttcn
- TCCIPsec Functions.ttcn
- TCCIPsec.cc

These functions can only be used if the kernel supports IPsec. Moreover, SPD handling functions can only be used if the kernel contains the KAME IPsec implementation. To use all functions the "-DUSE\_KAME\_IPSEC" compiler switch should be added to the CPPFLAGS variable in the *Makefile*. To use only the portable part (SAD handling) the "-DUSE\_KAME\_IPSEC" compiler switch should be added to the CPPFLAGS variable in the *Makefile*.

For using any of these functions root privileges are needed.

#### **Netlink XFRM API**

IPsec Handling Functions are implemented in the following files:

- TCCIPses\_XFRM\_Definitions.ttc
- TCCIPsec\_XFRM.hh
- TCCIPsec\_XFRM.cc

- TCCIPsec\_XFRM\_SA.cc
- TCCIPsec\_XFRM\_SP.cc

As only very old kernel versions do not support the XFRM interface, no extra build flags are required.

For using any of these functions root privileges are needed.

#### **Function Definitions**

#### **Security Parameter Index Query Function**

The Security Parameter Index (SPI) is an identification tag added to the header while using IPsec for tunneling the IP traffic. This tag helps the kernel discern between two traffic streams where different encryption rules and algorithms may be in use.

The kernel keeps track of the SPIs in use, and it does not allow creating multiple Security Associations with the same SPI. For this reason, it is recommended to query a unique SPI from the kernel before creating a new Security Association.

#### PF\_KEY API

```
external function f_IPsec_SPI_get (
  in charstring srcAddress,
  in charstring dstAddress,
  in TCCIPsec_Protocol protocol,
  out integer spi
) return TCCIPsec_Result;
```

Queries a unique SPI from the kernel and returns it in the 'spi' out parameter.

#### **Netlink XFRM API**

```
external function f_XFRM_allocate_SPI(
  in AllocSPI_Info pl_AllocSPI_info,
  inout integer pl_spi
) return XFRM_Result;
```

Queries a unique SPI value from the kernel that is from the default SPI range or from a defined range in the pl\_AllocSPI\_info parameter. The execution result returned in by the function and the reserved SPI will be in the pl\_spi parameter.

### **Security Association Database Handling Functions**

Security Associations are identified by the source address (srcAddress), security protocol (protocol)

and the Security Parameter Index (SPI).

#### PF KEY API

Security Associations may contain various extensions (extensionList) beside the algorithms (alg). The algorithm identifies the security or integrity protocol and the keys. The extensions include the soft and hard lifetime and an id to link the SAs to SPs.

IPSec supports two modes: transport, tunnel. It can be specified in the last IPSecMode parameter.

The useNatt parameter can be used to enable NAT traversal support specified in UDP Encapsulation of IPsec ESP Packets RFC 3948.

The functions return an error code to indicate success or the type of the error.

external function f\_IPsec\_SADB\_add ( in charstring srcAddress, in charstring dstAddress, in TCCIPsec\_Protocol protocol, in integer spi, in TCCIPsec\_ExtensionList extensionList := \{}, in TCCIPsec\_Algorithm alg in boolean useNatt := false, in TCCIPsec\_IPsecMode ipSecMode := anyMode) return TCCIPsec\_Result;

Add an SA (Security Association) into the SAD (Security Association Database).

```
external function f_IPsec_SADB_delete (
  in charstring srcAddress,
  in charstring dstAddress,
  in TCCIPsec_Protocol protocol,
  in integer spi
) return TCCIPsec_Result;
```

Delete an SA from the SAD.

```
external function f_IPsec_SADB_flush () return TCCIPsec_Result;
```

Delete all SAs from the SAD.

#### **Netlink XFRM API**

The main attributes of the SAs are the communication addresses, the used protocol, the used IPsec protocol, the mode of usage (transport and tunneling mode), the SPI value, algorithms and keys. In addition, the NAT (Network Address Traversal), selectors (identification purpose) and the lifetime is also configurable.

Each function returns an integer value, that represents the outcome of the execution. If it is zero, the execution was successful. If the execution fails, an additional string is returned that contains details on the cause of the failure. If the failure was on the application side, the error describes that, while if the error was on the kernel side processing, it contains the error message received from the kernel.

To add an SA the following function may be used:

```
external function f_XFRM_add_sa(
  in SAAddInfo pl_sa_info
) return XFRM_Result;
```

To delete an SA, the following function may be used:

```
external function f_XFRM_delete_sa(
  in SADelInfo pl_sa_info
) return XFRM_Result;
```

To flush the complete SADB, the following function may be used:

```
external function f_XFRM_flush_sa()
return XFRM_Result;
```

### **Security Policy Database Handling Functions**

Security Policies are identified by the source and destination addresses ranges and port values, the transport protocol (UDP or TCP) and the direction of the data traffic to which the policy is applied.

#### PF\_KEY API

The rule parameter specifies how IP packets should be handled.

```
external function f_IPsec_SPDB_add (
  in charstring srcAddress,
  in integer srcPrefixLen := c_TCCIPsec_prefixAll,
  in integer srcPort := c_TCCIPsec_anyPort,
  in charstring dstAddress,
  in integer dstPrefixLen := c_TCCIPsec_prefixAll,
  in integer dstPort := c_TCCIPsec_anyPort,
  in TCCIPsec_TranspProto transpProto := anyTranspProto,
  in TCCIPsec_PolicyDirection dir,
  in TCCIPsec_PolicyRule rule
) return TCCIPsec_Result;
```

Add an SP (Security Policy) into the SPD (Security Policy Database).

```
external function f_IPsec_SPDB_delete (
  in charstring srcAddress,
  in integer srcPrefixLen := c_TCCIPsec_prefixAll,
  in integer srcPort := c_TCCIPsec_anyPort,
  in charstring dstAddress,
  in integer dstPrefixLen := c_TCCIPsec_prefixAll,
  in integer dstPort := c_TCCIPsec_anyPort,
  in TCCIPsec_TranspProto transpProto := anyTranspProto,
  in TCCIPsec_PolicyDirection dir
) return TCCIPsec_Result;
```

Delete an SP from the SPD.

```
external function f_IPsec_SPDB_flush () return TCCIPsec_Result;
```

Delete all SPs from the SPD.

#### **Netlink XFRM API**

The main parameter of the SPs are the communication addresses, the transport protocol, the direction and the template list that identifies the SP. The template contains the SPI, the IPsec protocol and additional information.

To add an SP, the following function may be used:

```
external function f_XFRM_add_policy(
  in SPAddInfo pl_pol_info
) return XFRM_Result;
```

To delete an SP, the following function may be used:

```
external function f_XFRM_delete_policy(
  in SPDelInfo pl_pol_info
) return XFRM_Result;
```

To flush the SPDB, the following function may be used:

```
external function f_XFRM_flush_policy()
return XFRM_Result;
```

# **Error Messages**

None.

# **Warning Messages**

TCCIPsec: fIPsecSADB\_\_add: IPsec support was not specified during compilation

The -DUSE\_IPSEC or -DUSE\_KAME\_IPSEC compiler switch should be added to the CPPFAGS variable in the Makefile if the kernel supports IPsec.`

TCCIPsec: fIPsecSPDB\_\_add: IPsec SPDB support was not specified during compilation

The -DUSE\_KAME\_IPSEC compiler switch should be added to the CPPFLAGS variable in the Makefile in order to use SPD handling if the kernel contains the KAME IPsec implementation.

# **Examples**

```
testcase SA_example () runs on test_CT
  var TCCIPsec Result res;
  res := f_IPsec_SADB_flush ();
  if ( res != ok ) { setverdict(fail); }
  res := f_IPsec_SADB_add ( "192.168.1.1", "192.168.1.2",
    esp, 11001, { { hardLifetime := 180 }, { softLifetime := 60 } },
    { encrAndAuth := {
        ealgo := EALG_3DESCBC, ekey := { text := "123456789012345678901234" },
        aalgo := AALG_MD5HMAC, akey := { text := "1234567890123456" } } );
  if ( res != ok ) { setverdict(fail); }
  res := f_IPsec_SADB_delete ( "192.168.1.1", "192.168.1.2", esp, 11001 );
  log ( "f_IPsec_SADB_delete returns: ", res );
  select ( res ) {
    case ( ok ) { setverdict(pass); }
    case else { setverdict(fail); }
 }
}
testcase SP_delete () runs on test_CT
  var TCCIPsec_Result res;
  res := f_IPsec_SPDB_flush ();
  if ( res != ok ) { setverdict(fail); }
  res := f_IPsec_SPDB_add ( "192.168.1.1", -, 2001, "192.168.1.2", -, 3001,
    tcpProto, outDir,
   { ipSec := { { protocol := ah, mode := { transport := {} }, level := { unique := {
id := 101 } } } };
  if ( res != ok ) { setverdict(fail); }
  res := f_IPsec_SPDB_delete ( "192.168.1.1", -, 2001, "192.168.1.2", -, 3001,
tcpProto, outDir );
  log ( "f_IPsec_SPDB_delete returns: ", res );
  select ( res ) {
    case ( ok ) { setverdict(pass); }
    case else { setverdict(fail); }
  }
}
```

# **XPath Support Functions**

#### **Overview**

XPath Support Functions enable you to get any information stored in an XML document by making XPath queries. XPath is a language for finding information in an XML document. XPath is used to navigate through elements and attributes in an XML document. You can find reference and any further information about XPath 1.0 (base of the implementation) on the page:

#### http://www.w3.org/TR/xpath

XPath Support Functions are implemented in the following files:

- TCCXPathSupport\_Functions.ttcn
- TCCXPathSupport.cc

### **Function Definitions**

The following function was defined to enable you to use XPath queries in order to access the required data stored in the XML document.

```
external function XPathQuery (
        in universal charstring xml_doc,
        in universal charstring xpath_query )
return universal charstring;
```

#### Parameters:

• xml\_doc:

The XML document to be processed. It is modeled by a pure TTCN-3 universal charstring and passed as an input parameter to this function

xpath\_query:

The XPath Query. With this technology we can access a node of the XML tree. It is passed to the function as a universal charstring

Return Value: universal charstring - result of the query (information about a node of the XML tree)

Function to check the validity of the XML document:

```
external function XPathCheckXML (
    in universal charstring xml_doc,
    out charstring error_string)
return boolean;
```

#### Parameters:

• xml doc:

the XML document to be processed. It is modeled by a pure TTCN-3 universal charstring and passed as an input parameter to this function

error\_string:

The function returns the description of the error in that string

Return Value: boolean – true if the document is valid, false otherwise.

# **Building the TinyXPath External Library**

This TTCN-3 function is an application of the open-source TinyXPath external library.

TinyXPath is an XPath syntax decoder written in C++ built on top of the TinyXML package. TinyXML forms a tree form the XML document and TinyXPath uses this tree to apply XPath query on it.

So with TinyXPath you can apply an XPath syntax decoding to a TinyXML tree, and you can extract the required information from the XML document.

TinyXPath is covered by the zlib license.

In order to use the TinyXPath library, first you need to build the library, which you can import to your project.

You need to follow these instructions below.

First you have to get the whole TinyXPath folder and save it to your computer. You can find this folder in:

/vobs/ttcn/TCC\_Releases/Other/TinyXPath

You must remember the exact location of the directory (where you saved it).

Within the folder you can find subfolders containing:

• source files: /source

• header files: /include

• library file: /lib

In order to generate this library file from source files we provide a *Makefile*. You can find it outside the subfolders, in the TinyXPath directory. You can use two commands:

- make
- · make clean

First command is to build the library. The working directory must be:

<where you saved the dir>/TinyXPath

And then you type only: make.

You can find the library file (libtinyxpath.a) in the TinyXPath/lib subfolder.

# Preparing your TTCN-3 Environment for Using TinyXPath

### Modification of the TTCN-3 Files in your Project

You need to add two files:

TCCXPathSupport.cc

TCCXPathSupport\_Functions.ttcn

to your project. These contain the XPathSupport function declaration and definition.

In order to use the implemented function in your module you have to import definitions from the module containing the definition of XPathSupport function. You can use line below in the beginning of the module:

import from TCCXPathSupport\_Functions all;

### **Modification of the Makefile of Your Project**

Finally, your generated *Makefile* needs some changes to be able to find the external library.

1. Before every command in the *Makefile* you have to insert the next row specifying the place where you saved the TinyXPath folder:

```
TINYXPATH_DIR = <path to the dir>
```

For example, if you saved this folder straight to the project folder, you can write:

```
TINYXPATH_DIR = ./TinyXPath
```

2. Next you have to add text to the end of the line starting with CPPFLAGS:

```
-I$(TINYXPATH_DIR)/include
```

3. Finally, at the section of \$(TARGET): \$(OBJECTS) you will find this two lines:

```
-L$(TTCN3_DIR)/lib -l$(TTCN3_LIB) \
-L$(OPENSSL_DIR)/lib-lcrypto $($(PLATFORM)_LIBS)
```

You have to insert a line between them according to this:

```
-L$(TTCN3_DIR)/lib -l$(TTCN3_LIB) \
-L$(TINYXPATH_DIR)/lib -ltinyxpath \
-L$(OPENSSL_DIR)/lib-lcrypto $($(PLATFORM)_LIBS)
```

Now with this modified *Makefile* your project will be able to find and use the TinyXPath library.

### **Error Messages**

None.

# **Warning Messages**

None.

### **Examples**

```
module TCCXPathSupport_Example {
  import from TCCXPathSupport_Functions all;
 control {
    var universal charstring doc := "<a><b val='123'><b />
                <c/><!--- 122.0 --><d /></b><!-- 500.0 -->
                <x target='xyz'>sub text</x></a>";
   log ("The XML document:");
    log (doc);
    var universal charstring q := "sum(//*/comment())";
    log ("The XPath query:");
    log (q);
    var universal charstring res := XPathQuery (doc, q);
   log ("The result of the query:");
    log (res);
 }
}
```

# **System Functions**

#### Overview

The system functions implement various operating system and process related functions

Conversion Functions are implemented in the following files:

- TCCSystem\_Functions.ttcn
- TCCSystem.cc

### **Function definitions**

external function f\_SYS\_getpid() return integer;

Returns the pid of the process.

### **Error Messages**

None.

# **Warning Messages**

None

# **Examples**

None.

# **FileSystem Functions**

#### Overview

The FileSystem functions get information about the file system that contains the file named by the filename argument

FileSystem Functions are implemented in the following files:

- TCCFileSystem\_Functions.ttcn
- TCCFileSystem.cc

#### **Function Definitions**

external function f\_FS\_bsize(in charstring p\_name) return integer
 Returns the file system block size or -1 on error

external function f\_FS\_block(in charstring p\_name) return integer

Returns the total number of blocks in the file system or -1 on error

- external function f\_FS\_bfree(in charstring p\_name) return integer
   Returns the total number of free blocks in the file system or -1 on error
- external function f\_FS\_dspacerate(in charstring p\_name) return integer
   Returns the free space rate in the file system or -1 on error

# **Error Messages**

None.

# **Warning Messages**

None.

# **Examples**

```
testcase f_test_FS_bsize() runs on FileSystem_CT
 log(" ----- f_FS_bsize ----- ");
 log("Block size (f_FS_bsize): ", f_FS_bsize("./"));
 // no check
 setverdict(pass);
}
testcase f_test_FS_block() runs on FileSystem_CT
 log(" ----- f_FS_block ----- ");
 log("Number of blocks (f_FS_block): ", f_FS_block("./"));
 // no check
 setverdict(pass);
}
testcase f_test_FS_bfree() runs on FileSystem_CT
 log(" ----- f_FS_bfree ----- ");
 log("Number of free blocks (f_FS_bfree): ", f_FS_bfree("./"));
 // no check
 setverdict(pass);
}
testcase f_test_FS_dspacerate() runs on FileSystem_CT
 log(" ----- f_FS_dspacerate ----- ");
 log("The free space rate (f_FS_dspacerate): ", f_FS_dspacerate("./"));
 // no check
 setverdict(pass);
}
```

# **Regexp functions**

### **Overview**

The system functions implement non-TTCN-3 regular expression support functions

Regexp Functions are implemented in the following files:

- TCCRegexp\_Functions.ttcn
- TCCRegexp.cc

#### **Function Definitions**

 external function f\_pcre\_regexp(in charstring instr, in charstring expression, in integer groupno) return charstring;

This function returns the substring of the input character string instr, which is the content of n-th group matching to the expression. The expression is a Perl compatible regular expression pattern. The number of the group to be returned is specified by groupno, which shall be a positive integer or zero. Group numbers are assigned by the order of occurrences of the opening bracket of a group and counted starting from 1 by step 1. If the groupno is zero, a substring matched by the entire pattern is returned. If no substring fulfilling all conditions (i.e. pattern and group number) is found within the input string, an empty string is returned.

 external function f\_pcre\_regexp\_list(in charstring instr,in charstring expression) return charstring\_list;

This function returns a list of substrings of the input character string instr, which are the content of n-th group matching to the expression. The expression is a Perl compatible regular expression pattern. Group numbers are assigned by the order of occurrences of the opening bracket of a group and counted starting from 1 by step 1.

external function f\_pcre\_regexp\_list\_all\_matches(in charstring instr,in charstring expression) return t list of charstring list;

This function returns the full list of the substring of the input character string instr, which is the content of n-th group matching to the expression. The expression is a Perl compatible regular expression pattern. Group numbers are assigned by the order of occurrences of the opening bracket of a group and counted starting from 1 by step 1. If no substring fulfilling all conditions is found within the input string, an empty record of is returned.

The functions are based on the PCRE library. See: http://www.pcre.org/

### **Error Messages**

```
Compilation of the pcre regexp failed at position x. Reason: yyyyy
```

The supplied expression is not a valid PCRE expression.

### **Warning Messages**

None.

### **Examples**

```
    f_pcre_regexp( "abc", "(a|(z))(bc)" ,0)
    returns "abc"
    f_pcre_regexp( "abc", "(a|(z))(bc)" ,1)
```

```
returns "a"

• f_pcre_regexp( "abc", "(a|(z))(bc)" ,2)

returns "". The second sub expression is the "(z)"

• f_pcre_regexp( "abc", "(a|(z))(bc)" ,3)

returns "bc"

• f_pcre_regexp_list( "abc", "(a|(z))(bc)")

returns {"abc", "a", "", "bc"}

• f_pcre_regexp_list_all_matches("a1 b1 a2", "(a)(\d)")

returns { { "a1", "a", "1" }, { "a2", "a", "2" } }
```

# **Terminology**

No specific terminology used.

### **Abbreviations**

ES

ETSI Standard

#### **ETSI**

European Telecommunications Standards Institute

#### **RFC**

**Request for Comments** 

#### TTCN-3

Testing and Test Control Notation version 3

# References

[1] ETSI ES 201 873-1 v3.1.1 (06/2005)

The Testing and Test Control Notation version 3. Part 1: Core Language

- [2] Installation Guide for TITAN TTCN-3 Test Executor
- [3] User Guide for TITAN TTCN-3 Test Executor

#### [4] RFC 2045

Multipurpose Internet Mail Extensions (MIME) Part One: Format of Internet Message Bodies

#### [5] RFC 2849

The LDAP Data Interchange Format (LDIF) – Technical Specification

[6] NaturalDocs document for TCC UsefulFunctions

(/vobs/ttcn/TCC\_Common/Libraries/TCCUsefulFunctions\_CNL113472/doc/apidoc)

[7] An example algorithm set for the 3GPP authentication and key generation functions f1, f1, f2, f3, f4, f5 and f5; Document 2: Algorithm Specification3GPP TS 35.206 (v7.0.0 2007-06)

#### [8] 3GPP TS 33.102 V9.1.0 (2009-12)

3rd Generation Partnership Project; Technical Specification GroupServices and System Aspects; 3G Security; Security architecture (Release 9)

#### [9] 3GPP TS 34.108 V4.7.0

Common test environments for User Equipment (UE) conformance testing (Release 4) 2003.06.

[10] Specification of the 3GPP Confidentiality and Integrity Algorithms128-EEA3 & 128-EIA3. Document 1: 128-EEA3 and 128-EIA3Specification, Version 1.6, 1st July, 2011

[11] Specification of the 3GPP Confidentiality and Integrity Algorithms128-EEA3 & 128-EIA3. Document 2: ZUC SpecificationVersion 1.6, 28th June 2011

#### [12] GSM 03.38 V7.2.0

Digital cellular telecommunications system (Phase 2+)Alphabets and language-specific information

#### [13] ETR 060

Guidelines for using Abstract Syntax Notation One (ASN.1) in telecommunication application protocols

#### [14] ITU-T Q.763 (12/1999)

SERIES Q: SWITCHING AND SIGNALING

Specifications of Signaling System No. 7 – ISDN user part Signaling System No. 7 – ISDN user part formats and codes

#### [15] 3GPP TS 24.008 V12.0.0 (2012-12)

3rd Generation Partnership Project;

Technical Specification Group Core Network and Terminals;

Mobile radio interface Layer 3 specification;

Core network protocols; Stage 3(Release 12)

#### [16] 3GPP TS 33.401 V12.14.0 (2015-03)

3rd Generation Partnership Project;

Technical Specification Group Services and System Aspects;

3GPP System Architecture Evolution (SAE);

Security architecture(Release 12)