Chapter 3 Transport Layer

A note on the use of these Powerpoint slides:


We' re making these slides freely available to all (faculty, students, readers). They're in PowerPoint form so you see the animations; and can add, modify, and delete slides (including this one) and slide content to suit your needs. They obviously represent a *lot* of work on our part. In return for use, we only ask the following:

- If you use these slides (e.g., in a class) that you mention their source (after all, we' d like people to use our book!)
- If you post any slides on a www site, that you note that they are adapted from (or perhaps identical to) our slides, and note our copyright of this material.

Thanks and enjoy! JFK/KWR

All material ©pyright 1996-2016

J.F Kurose and K.W. Ross, All Rights Reserved



Computer Networking: A Top Down Approach

7th edition

Jim Kurose, Keith Ross Pearson/Addison Wesley April 2016

Chapter 3: Transport Layer

our goals:

- understand principles behind transport layer services:
 - · multiplexing, demultiplexing
 - reliable data transfer
 - flow control
 - congestion control

- learn about Internet transport layer protocols:
 - UDP: connectionless transport
 - TCP: connection-oriented reliable transport
 - TCP congestion control

Chapter 3 outline

- 3.1 transport-layer services
- 3.2 multiplexing and demultiplexing
- 3.3 connectionless transport: UDP
- 3.4 principles of reliable data transfer


3.5 connection-oriented transport:

TCP

- segment structure
- reliable data transfer
- flow control
- connection management
- 3.6 principles of congestion control
- 3.7 TCP congestion control

Transport services and protocols

- provide logical communication between app processes running on different hosts
- transport protocols run in end systems
 - send side: breaks app messages into segments, passes to network layer
 - rcv side: reassembles segments into messages, passes to app layer
- more than one transport protocol available to apps
 - Internet: TCP and UDP



Transport vs. network layer


- network layer: logical communication between hosts
- transport layer: logical communication between processes
 - relies on, enhances, network
 layer services

household analogy:

- 12 kids in Ann's house sending letters to 12 kids in Bill's house:
- hosts = houses
- processes = kids
- app messages = letters in envelopes
- transport protocol = Ann and Bill who demux to in-house siblings
- network-layer protocol = postal service

Internet transport-layer protocols

- reliable, in-order delivery (TCP)
 - congestion control
 - flow control
 - connection setup
- unreliable, unordered delivery: UDP
 - no-frills extension of "best-effort" IP
- services not available:
 - delay guarantees
 - bandwidth guarantees



Chapter 3 outline

- 3.1 transport-layer services
- 3.2 multiplexing and demultiplexing
- 3.3 connectionless transport: UDP
- 3.4 principles of reliable data transfer

3.5 connection-oriented transport:

TCP


- segment structure
- reliable data transfer
- flow control
- connection management
- 3.6 principles of congestion control
- 3.7 TCP congestion control


Multiplexing/demultiplexing

multiplexing at sender:

handle data from multiple sockets, add transport header (later used for demultiplexing) demultiplexing at receiver:


use header info to deliver received segments to correct socket





How demultiplexing works

- host receives IP datagrams
 - each datagram has source IP address, destination IP address
 - each datagram carries one transportlayer segment
 - each segment has source, destination
 port number
- host uses IP addresses & port numbers to direct segment to appropriate socket



TCP/UDP segment format

Connectionless demultiplexing

recall: created socket has hostlocal port #:

DatagramSocket mySocket1 = new DatagramSocket(12534);

- recall: when creating datagram to send into UDP socket, must specify
 - destination IP address
 - destination port #


- when host receives UDP segment:
 - checks destination port # in segment
 - directs UDP segment to socket with that port #



#, but different source IP addresses and/or source port numbers will be directed to same socket at dest



Connectionless demux: example




Connection-oriented demux

- TCP socket identified by 4tuple:
 - source IP address
 - source port number
 - dest IP address
 - dest port number
- demux: receiver uses all four values to direct segment to appropriate socket

- server host may support many simultaneous TCP sockets:
 - each socket identified by its own 4tuple
- web servers have different sockets for each connecting client
 - non-persistent HTTP will have
 different socket for each request


Connection-oriented demux: example



three segments, all destined to IP address: B,

dest port: 80 are demultiplexed to different sockets

Connection-oriented demux: example



Chapter 3 outline

- 3.1 transport-layer services
- 3.2 multiplexing and demultiplexing
- 3.3 connectionless transport: UDP
- 3.4 principles of reliable data transfer

3.5 connection-oriented transport:

TCP

- segment structure
- reliable data transfer
- flow control
- connection management
- 3.6 principles of congestion control
- 3.7 TCP congestion control


UDP: User Datagram Protocol [RFC 768]

- "no frills," "bare bones" Internet transport protocol
- "best effort" service, UDP segments may be:
 - lost
 - delivered out-of-order to app
- connectionless:
 - no handshaking between UDP sender, receiver
 - each UDP segment handled independently of others

UDP use:

- streaming multimedia apps (loss tolerant, rate sensitive)
- DNS
- SNMP
- reliable transfer over UDP:
 - add reliability at application layer
 - application-specific error recovery!

UDP: segment header



UDP segment format

length, in bytes of UDP segment, including header

why is there a UDP?

- no connection establishment (which can add delay)
- simple: no connection state at sender, receiver
- small header size
- no congestion control: UDP can blast away as fast as desired

UDP checksum

Goal: detect "errors" (e.g., flipped bits) in transmitted segment

sender:


- treat segment contents, including header fields, as sequence of 16-bit integers
- checksum: addition (one's complement sum) of segment contents
- sender puts checksum value into UDP checksum field

receiver:

- compute checksum of received segment
- check if computed checksum equals checksum field value:
 - · NO error detected
 - YES no error detected. But maybe errors nonetheless? More later

Internet checksum: example

example: add two 16-bit integers



Note: when adding numbers, a carryout from the most

significant bit needs to be added to the result

* Check out the online interactive exercises for more examples:

Chapter 3 outline


- 3.1 transport-layer services
- 3.2 multiplexing and demultiplexing
- 3.3 connectionless transport: UDP
- 3.4 principles of reliable data transfer

3.5 connection-oriented transport: TCP

- segment structure
- reliable data transfer
- flow control
- connection management
- 3.6 principles of congestion control
- 3.7 TCP congestion control

Principles of reliable data transfer

- important in application, transport, link layers
 - top-10 list of important networking topics!




(a) provided service

 characteristics of unreliable channel will determine complexity of reliable data transfer protocol (rdt)

Principles of reliable data transfer


- important in application, transport, link layers
 - top-10 list of important networking topics!



 characteristics of unreliable channel will determine complexity of reliable data transfer protocol (rdt)


Principles of reliable data transfer

- important in application, transport, link layers
 - top-10 list of important networking topics!



 characteristics of unreliable channel will determine complexity of reliable data transfer protocol (rdt)

Reliable data transfer: getting started



Reliable data transfer: getting started

we' ||:

- incrementally develop sender, receiver sides of reliable data transfer protocol
 (rdt)
- consider only unidirectional data transfer
 - but control info will flow on both directions!
- use finite state machines (FSM) to specify sender, receiver

event causing state transition

state: when in this "state"


next state uniquely

determined by next event



rdt1.0: reliable transfer over a reliable channel

- underlying channel perfectly reliable
 - no bit errors
 - no loss of packets
- separate FSMs for sender, receiver:
 - sender sends data into underlying channel
 - · receiver reads data from underlying channel



rdt2.0: channel with bit errors

- underlying channel may flip bits in packet
 - checksum to detect bit errors

How do humans recover from "errors" during conversation?

rdt2.0: channel with bit errors

- underlying channel may flip bits in packet
 - checksum to detect bit errors
- the question: how to recover from errors:
 - acknowledgements (ACKs): receiver explicitly tells sender that pkt received OK
 - negative acknowledgements (NAKs): receiver explicitly tells sender that pkt had errors
 - sender retransmits pkt on receipt of NAK
- new mechanisms in rdt2.0 (beyond rdt1.0):
 - error detection
 - feedback: control msgs (ACK, NAK) from receiver to sender

rdt2.0: FSM specification

```
rdt_send(data)
sndpkt = make_pkt(data, checksum)
udt_send(sndpkt)

rdt_rcv(rcvpkt) &&
isNAK(rcvpkt)

above

rdt_rcv(rcvpkt) && isNAK(rcvpkt)

rdt_send(sndpkt)


rdt_send(sndpkt)

sender
```


receiver

rdt_rcv(rcvpkt) && corrupt(rcvpkt) $udt_send(NAK)$ Wait for call from below rdt_rcv(rcvpkt) && notcorrupt(rcvpkt) extract(rcvpkt, data) deliver_data(data) udt_send(ACK)

rdt2.0: operation with no errors



rdt2.0: error scenario



rdt2.0 has a fatal flaw!

what happens if ACK/NAK corrupted?


- sender doesn' t know what happened at receiver!
- can' t just retransmit:possible duplicate

Stop and wait sender sends one packet, then waits for receiver response

handling duplicates:

- sender retransmits current pkt if ACK/NAK corrupted
- sender adds sequence number to each pkt
- receiver discards (doesn' tdeliver up) duplicate pkt

rdt2.1: sender, handles garbled ACK/NAKs



rdt2.1: receiver, handles garbled ACK/NAKs

rdt_rcv(rcvpkt) && notcorrupt(rcvpkt) && has_seqO(rcvpkt) extract(rcvpkt,data) rdt_rcv(rcvpkt) && deliver_data(data) (corrupt(rcvpkt) rdt_rcv(rcvpkt) && sndpkt = make_pkt(ACK, chksum) (corrupt(rcvpkt) udt_send(sndpkt) sndpkt = make_pkt(NAK, chksum) sndpkt = make_pkt(NAK, chksum) udt send(sndpkt) udt_send(sndpkt) Wait rdt_rcv(rcvpkt) && Wait for not corrupt(rcvpkt) && for rdt_rcv(rcvpkt) && has seg1(rcvpkt) 0 from/ from not corrupt(rcvpkt) && below below has_seq0(rcvpkt) sndpkt = make_pkt(ACK, chksum) sndpkt = make_pkt(ACK, chksum) rdt_rcv(rcvpkt) && notcorrupt(rcvpkt) udt_send(sndpkt) udt_send(sndpkt) && has_seq1(rcvpkt) extract(rcvpkt,data) deliver_data(data) sndpkt = make_pkt(ACK, chksum) udt send(sndpkt)

rdt2.1: discussion

sender:

- seq # added to pkt
- two seq. #' s (0,1) will suffice.
 Why?
- must check if received ACK/NAK corrupted
- twice as many states
 - state must "remember" whether "expected" pkt should have seq # of 0 or 1


receiver:

- must check if received packet is duplicate
 - state indicates whether 0 or 1 is expected pkt seq #
- note: receiver can not know if its last ACK/NAK received OK at sender

rdt2.2: a NAK-free protocol

- same functionality as rdt2.1, using ACKs only
- instead of NAK, receiver sends ACK for last pkt received
 OK
 - · receiver must explicitly include seq # of pkt being ACKed
- duplicate ACK at sender results in same action as NAK:
 retransmit current pkt

rdt2.2: sender, receiver fragments



rdt3.0: channels with errors and loss

new assumption: underlying
 channel can also lose packets
 (data, ACKs)


checksum, seq. #, ACKs,
retransmissions will be of help
... but not enough

approach: sender waits


"reasonable" amount of time for ACK


- retransmits if no ACK received in this time
- if pkt (or ACK) just delayed (not lost):
 - retransmission will be duplicate, but
 seq. #' s already handles this
 - receiver must specify seq # of pkt being ACKed
- requires countdown timer

rdt3.0 sender




rdt3.0 in action





rdt3.0 in action



Performance of rdt3.0

- rdt3.0 is correct, but performance stinks
- e.g.: 1 Gbps link, 15 ms prop. delay, 8000 bit packet:


$$D_{trans} = \frac{L}{R} = \frac{8000 \text{ bits}}{10^9 \text{ bits/sec}} = 8 \text{ microsecs}$$

• U sender: utilization - fraction of time sender busy sending

$$U_{\text{sender}} = \frac{L/R}{RTT + L/R} = \frac{.008}{30.008} = 0.00027$$

- if RTT=30 msec, 1KB pkt every 30 msec: 33kB/sec thruput over 1 Gbps link
- network protocol limits use of physical resources!


rdt3.0: stop-and-wait operation



Pipelined protocols


pipelining: sender allows multiple, "in-flight" , yet-to-beacknowledged pkts

- range of sequence numbers must be increased
- buffering at sender and/or receiver



• two generic forms of pipelined protocols: go-Back-N, selective repeat

Pipelining: increased utilization



Pipelined protocols: overview

Go-back-N:


- sender can have up to N unacked packets in pipeline
- receiver only sends cumulative ack
 - doesn' t ack packet if there's a gap
- sender has timer for oldest unacked packet
 - when timer expires, retransmit all unacked packets

Selective Repeat:

- sender can have up to N
 unack' ed packets in pipeline
- rcvr sends individual ack for each packet
- sender maintains timer for each unacked packet
 - when timer expires, retransmit only that unacked packet

Go-Back-N: sender

- k-bit seq # in pkt header
- "window" of up to N, consecutive unack' ed pkts allowed




- ACK(n): ACKs all pkts up to, including seq # n "cumulative ACK"
 - may receive duplicate ACKs (see receiver)
- timer for oldest in-flight pkt
- timeout(n): retransmit packet n and all higher seq # pkts in window

GBN: sender extended FSM

```
rdt_send(data)
                      if (nextseqnum < base+N) {
                        sndpkt[nextseqnum] = make_pkt(nextseqnum,data,chksum)
                        udt_send(sndpkt[nextseqnum])
                        if (base == nextseqnum)
                          start_timer
                        nextseqnum++
                      else
                       refuse_data(data)
  base=1
  nextseqnum=1
                                        timeout
                                       start_timer
                           Wait
                                       udt_send(sndpkt[base])
                                       udt_send(sndpkt[base+1])
rdt_rcv(rcvpkt)
 && corrupt(rcvpkt)
                                       udt_send(sndpkt[nextseqnum-1])
                       rdt_rcv(rcvpkt) &&
                         notcorrupt(rcvpkt)
                       base = getacknum(rcvpkt)+1
                       If (base == nextseqnum)
                          stop_timer
                        else
                          start_timer
```


GBN: receiver extended FSM



ACK-only: always send ACK for correctly-received pkt with highest in-order seq #

- may generate duplicate ACKs
- need only remember expectedseqnum
- out-of-order pkt:
 - discard (don' t buffer): no receiver buffering!
 - re-ACK pkt with highest in-order seq #


GBN in action



Selective repeat

- receiver individually acknowledges all correctly received pkts
 - buffers pkts, as needed, for eventual in-order delivery to upper layer
- sender only resends pkts for which ACK not received
 - sender timer for each unACKed pkt
- sender window
 - N consecutive seq #' s
 - limits seq #s of sent, unACKed pkts

Selective repeat: sender, receiver windows



(b) receiver view of sequence numbers

Selective repeat

sender

data from above:

if next available seq # in window,send pkt

timeout(n):

resend pkt n, restart timer

ACK(n) in [sendbase, sendbase+N]:

- mark pkt n as received
- if n smallest unACKed pkt, advance window base to next unACKed seq #

receiver

pkt n in [rcvbase, rcvbase+N-1]

- send ACK(n)
- out-of-order: buffer
- in-order: deliver (also deliver buffered, in-order pkts), advance window to next not-yet-received pkt


pkt n in [rcvbase-N,rcvbase-1]

ACK(n)

otherwise:

ignore

Selective repeat in action




Selective repeat:

dilemma

example:


- seq #' s: 0, 1, 2, 3
- window size=3
- receiver sees no difference in two scenarios!
- duplicate data accepted as new in (b)
- Q: what relationship between seq # size and window size to avoid problem in (b)?



receiver can't see sender side.

receiver behavior identical in both cases!

something's (very) wrong!



Chapter 3 outline

- 3.1 transport-layer services
- 3.2 multiplexing and demultiplexing
- 3.3 connectionless transport: UDP
- 3.4 principles of reliable data transfer

- 3.5 connection-oriented transport: TCP
 - segment structure
 - reliable data transfer
 - flow control
 - connection management
- 3.6 principles of congestion control
- 3.7 TCP congestion control

TCP: Overview RFCs: 793,1122,1323, 2018, 2581

- point-to-point:
 - one sender, one receiver
- reliable, in-order byte steam:
 - no "message boundaries"
- pipelined:
 - TCP congestion and flow control set window size

full duplex data:

- bi-directional data flow in same connection
- MSS: maximum segment size
- connection-oriented:
 - handshaking (exchange of control msgs) inits sender, receiver state before data exchange
- flow controlled:
 - sender will not overwhelm receiver

TCP segment structure

32 bits URG: urgent data counting source port # dest port # (generally not used) by bytes <u>sequence number</u> ACK: ACK #. of data acknowledgement number valid head not UAPRSF receive window (not segments!) PSH: push data now en used # bytes checksum <u>Urg data pointer</u> (generally not used) rcvr willing RST, SYN, FIN: options (variable length) to accept connection estab (setup, teardown application centrephes) data checksum (variable length) (as in UDP)

TCP seq. numbers, ACKs

sequence numbers:


byte stream "number" of first
 byte in segment's data

acknowledgements:


- seq # of next byte expected from other side
- cumulative ACK

Q: how receiver handles out-of-order segments

 A: TCP spec doesn' t say, - up to implementor



TCP seq. numbers, ACKs



TCP round trip time, timeout


- Q: how to set TCP timeout value?
- longer than RTT
 - but RTT varies
- too short: premature timeout,
 unnecessary retransmissions
- too long: slow reaction to segment loss

- Q: how to estimate RTT?
- SampleRTT: measured time from segment transmission until ACK receipt
 - ignore retransmissions
- SampleRTT will vary, want estimated
 RTT "smoother"
 - average several recent measurements, not just current SampleRTT

TCP round trip time, timeout

EstimatedRTT = (1- [])*EstimatedRTT + [] *SampleRTT

- exponential weighted moving average
- influence of past sample decreases exponentially fast
- typical value: □ = 0.125



TCP round trip time, timeout

- timeout interval: EstimatedRTT plus "safety margin"
 - · large variation in EstimatedRTT -> larger safety margin
- estimate SampleRTT deviation from EstimatedRTT:

```
DevRTT = (1-1)*DevRTT +

1 *|SampleRTT-EstimatedRTT|
(typically, 1 = 0.25)
```

TimeoutInterval = EstimatedRTT + 4*DevRTT

estimated RTT "safety margin"

^{*} Check out the online interactive exercises for more examples: http://gaia.cs.umass.edu/kurose_ross/interactive/ Transport Layer3-63

Chapter 3 outline

- 3.1 transport-layer services
- 3.2 multiplexing and demultiplexing
- 3.3 connectionless transport: UDP
- 3.4 principles of reliable data transfer

3.5 connection-oriented transport:

TCP

- segment structure
- reliable data transfer
- flow control
- connection management
- 3.6 principles of congestion control
- 3.7 TCP congestion control

TCP reliable data transfer

- TCP creates rdt service on top of IP's unreliable service
 - pipelined segments
 - cumulative acks
 - single retransmission timer
- retransmissions triggered by:
 - timeout events
 - duplicate acks

- let's initially consider simplified TCP sender:
 - ignore duplicate acks
 - ignore flow control,
 congestion control

TCP sender events:

data rcvd from app:

- create segment with seq #
- seq # is byte-stream numberof first data byte in segment
- start timer if not already running
 - think of timer as for oldest unacked segment
 - expiration interval: TimeOutInterval

timeout:

- retransmit segment that caused timeout
- restart timer


ack rcvd:

- if ack acknowledges previously unacked segments
 - update what is known to be ACKed
 - start timer if there are still unacked segments

TCP sender (simplified)


```
data received from application above
                                          create segment, seq. #: NextSeqNum
                                          pass segment to IP (i.e., "send")
                                          NextSeqNum = NextSeqNum + length(data)
                                          if (timer currently not running)
                                             start timer
                          wait
NextSeqNum = InitialSeqNum
SendBase = InitialSeqNum
                          for
                         event
                                           timeout
                                           retransmit not-yet-acked
                                                             with
                                           segment
                                           smallest seq. #
                                           start timer
    ACK received, with ACK field value y
      if (y > SendBase) {
         SendBase = y
         /* SendBase-1: last cumulatively ACKed byte */
         if (there are currently not-yet-acked segments)
              start timer
            else stop timer
```

TCP: retransmission scenarios



Transport Layer3-68

TCP: retransmission scenarios



cumulative ACK

TCP ACK generation [RFC 1122, RFC 2581]

event at receiver	TCP receiver action
arrival of in-order segment with expected seq #. All data up to expected seq # already ACKed	delayed ACK. Wait up to 500ms for next segment. If no next segment, send ACK
arrival of in-order segment with expected seq #. One other segment has ACK pending	immediately send single cumulative ACK, ACKing both in-order segments
arrival of out-of-order segment higher-than-expect seq. # . Gap detected	immediately send duplicate ACK, indicating seq. # of next expected byte
arrival of segment that partially or completely fills gap	immediate send ACK, provided that segment starts at lower end of gap

TCP fast retransmit


- time-out period often relatively long:
 - long delay before resending lost packet
- detect lost segments via duplicate ACKs.
 - sender often sends many segments back-to-back
 - if segment is lost, there will likely be many duplicate ACKs.

TCP fast retransmit

if sender receives 3 ACKs for same data
("triple duplicate ACKs"), resend unacked segment with smallest seq #

 likely that unacked segment lost, so don't wait for timeout

TCP fast retransmit



fast retransmit after sender receipt of triple duplicate ACK

Chapter 3 outline


- 3.1 transport-layer services
- 3.2 multiplexing and demultiplexing
- 3.3 connectionless transport: UDP
- 3.4 principles of reliable data transfer

- 3.5 connection-oriented transport: TCP
 - segment structure
 - reliable data transfer
 - flow control
 - connection management
- 3.6 principles of congestion control
- 3.7 TCP congestion control

TCP flow control

application may
remove data from
TCP socket buffers
... slower than TCP
receiver is
delivering
(sender is sending)


flow control
receiver controls sender, so sender
won' t overflow receiver' s buffer by
transmitting too much, too fast



receiver protocol stack

TCP flow control

- receiver "advertises" free buffer space by including rwnd value in TCP header of receiver-to-sender segments
 - RcvBuffer size set via socket options (typical default is 4096 bytes)
 - many operating systems autoadjust RcvBuffer
- sender limits amount of unacked ("inflight") data to receiver's rwnd value
- guarantees receive buffer will not overflow



receiver-side buffering

Chapter 3 outline

- 3.1 transport-layer services
- 3.2 multiplexing and demultiplexing
- 3.3 connectionless transport: UDP
- 3.4 principles of reliable data transfer


3.5 connection-oriented transport: TCP


- segment structure
- reliable data transfer
- flow control
- connection management
- 3.6 principles of congestion control
- 3.7 TCP congestion control

Connection Management

before exchanging data, sender/receiver "handshake":


- agree to establish connection (each knowing the other willing to establish connection)
- agree on connection parameters






Agreeing to establish a connection

2-way handshake:







- Q: will 2-way handshake always work in network?
- variable delays
- retransmitted messages (e.g.
 req_conn(x)) due to message loss
- message reordering
- can' t "see" other side

Agreeing to establish a connection


2-way handshake failure scenarios:



TCP 3-way handshake




TCP 3-way handshake: FSM



TCP: closing a connection

- client, server each close their side of connection
 - send TCP segment with FIN bit = 1
- respond to received FIN with ACK
 - · on receiving FIN, ACK can be combined with own FIN
- simultaneous FIN exchanges can be handled

TCP: closing a connection



Chapter 3 outline

- 3.1 transport-layer services
- 3.2 multiplexing and demultiplexing
- 3.3 connectionless transport: UDP
- 3.4 principles of reliable data transfer

3.5 connection-oriented transport:

TCP

- segment structure
- reliable data transfer
- flow control
- connection management
- 3.6 principles of congestion control
- 3.7 TCP congestion control

Principles of congestion control

congestion:


- informally: "too many sources sending too much data too fast for network to handle"
- different from flow control!
- manifestations:
 - lost packets (buffer overflow at routers)
 - long delays (queueing in router buffers)
- a top-10 problem!


two senders, two receivers


• one router, infinite buffers


output link capacity: R

no retransmission











large delays as arrival rate,
 l_{in}, approaches capacity
 Transport Layer3-86


- one router, finite buffers
- sender retransmission of timed-out packet
 - application-layer input = application-layer output: $l_{in} = l_{out}$
 - transport-layer input includes retransmissions : $I_{in} \ge I_{in}$



idealization: perfect knowledge


 sender sends only when router buffers available






Idealization: known loss packets can be lost, dropped at router due to full buffers


sender only resends if packet known to be lost



Idealization: known loss packets can be lost, dropped at router due to full buffers


 sender only resends if packet known to be lost






Realistic: duplicates


- packets can be lost, dropped at router due to full buffers
- sender times out prematurely, sending two copies, both of which are delivered





Realistic: duplicates

- packets can be lost, dropped at router due to full buffers
- sender times out prematurely, sending
 two copies, both of which are delivered




"costs" of congestion:


- more work (retrans) for given "goodput"
- unneeded retransmissions: link carries multiple copies of pkt
 - decreasing goodput

- four senders
- multihop paths
- timeout/retransmit

Q: what happens as I_{in} and I_{in} increase?

 \underline{A} : as red I_{in} increases, all arriving blue pkts at upper queue are dropped, blue throughput g 0





another "cost" of congestion:

• when packet dropped, any "upstream transmission capacity used for that packet was wasted!

Chapter 3 outline


- 3.1 transport-layer services
- 3.2 multiplexing and demultiplexing
- 3.3 connectionless transport: UDP
- 3.4 principles of reliable data transfer

- 3.5 connection-oriented transport:
 - TCP
 - segment structure
 - reliable data transfer
 - flow control
 - connection management
- 3.6 principles of congestion control
- 3.7 TCP congestion control


TCP congestion control: additive increase multiplicative decrease

- approach: sender increases transmission rate (window size), probing for usable bandwidth, until loss occurs
 - · additive increase: increase cwnd by 1 MSS every RTT until loss detected
 - multiplicative decrease: cut cwnd in half after loss

AIMD saw tooth behavior: probing for bandwidth



TCP Congestion Control: details



sender limits transmission:

LastByteSent- LastByteAcked≤ cwnd


 cwnd is dynamic, function of perceived network congestion

TCP sending rate:

roughly: send cwnd bytes, wait
 RTT for ACKS, then send more
 bytes

TCP Slow Start

- when connection begins, increase rate exponentially until first loss event:
 - initially cwnd = 1 MSS
 - double cwnd every RTT
 - done by incrementing cwnd for every
 ACK received
- summary: initial rate is slow but ramps up exponentially fast



TCP: detecting, reacting to loss

- loss indicated by timeout:
 - cwnd set to 1 MSS;
 - window then grows exponentially (as in slow start) to threshold,
 then grows linearly
- loss indicated by 3 duplicate ACKs: TCP RENO
 - dup ACKs indicate network capable of delivering some segments
 - cwnd is cut in half window then grows linearly
- TCP Tahoe always sets cwnd to 1 (timeout or 3 duplicate acks)


TCP: switching from slow start to CA

Q: when should the exponential increase switch to linear?

A: when cwnd gets to 1/2 of its value before timeout.




- variable ssthresh
- on loss event, ssthresh is set to 1/2 of cwnd just before loss event



^{*} Check out the online interactive exercises for more examples:


Summary: TCP Congestion Control



TCP throughput

- avg. TCP thruput as function of window size, RTT?
 - · ignore slow start, assume always data to send
- W: window size (measured in bytes) where loss occurs
 - avg. window size (# in-flight bytes) is $\frac{3}{4}$ W
 - avg. thruput is 3/4W per RTT

avg TCP thruput=
$$\frac{3}{4} \frac{W}{RTT}$$
 bytes/sec




TCP Futures: TCP over "long, fat pipes"

- example: 1500 byte segments, 100ms RTT, want 10 Gbps throughput
- requires W = 83,333 in-flight segments
- throughput in terms of segment loss probability, L [Mathis 1997]:
- TCP throughput = $\frac{1.22 \cdot MSS}{PTT\sqrt{L}}$ To achieve 10 Gbps throughput, need a loss rate of L = $2 \cdot 10^{-10}$ a very small loss rate!
- new versions of TCP for high-speed

TCP Fairness

fairness goal: if K TCP sessions share same bottleneck link of bandwidth R, each should have average rate of R/K




Why is TCP fair?

two competing sessions:

additive increase gives slope of 1, as throughout increases

multiplicative decrease decreases throughput proportionally



Fairness (more)

Fairness and UDP

- multimedia apps often do not use TCP
 - do not want rate throttled by congestion control
- instead use UDP:
 - send audio/video at constant rate, tolerate packet loss


Fairness, parallel TCP connections

- application can open multiple parallel connections between two hosts
- web browsers do this
- e.g., link of rate R with 9existing connections:
 - new app asks for 1 TCP, gets rate R/10
 - new app asks for 11 TCPs, gets R/2

Explicit Congestion Notification (ECN)

network-assisted congestion control:

- two bits in IP header (ToS field) marked by network router to indicate congestion
- congestion indication carried to receiving host
- receiver (seeing congestion indication in IP datagram)) sets ECE bit on receiverto-sender ACK segment to notify sender of congestion



Chapter 3: summary

- principles behind transport layer services:
 - · multiplexing, demultiplexing
 - reliable data transfer
 - flow control
 - congestion control
- instantiation, implementation in the Internet
 - UDP
 - TCP

next:

- leaving the network "edge"
 (application, transport layers)
- into the network "core"
- two network layer chapters:
 - · data plane
 - control plane