

Zimbra Collaboration Server Multi-Server Installation Guide

Open Source Edition 8.0

August 2012

Legal Notices

Copyright ©2005-2012 VMware, Inc. All rights reserved. This product is protected by U.S. and international copyright and intellectual property laws. VMware products are covered by one or more patents listed at http://www.vmware.com/go/patents.

VMware and Zimbra are registered trademarks or trademarks of VMware, Inc. in the United States and/ or other jurisdiction. All other marks and names mentioned herein may be trademarks of their respective companies.

VMware, Inc. 3401 Hillview Avenue Palo Alto, California 94304 USA

www.zimbra.com

Zimbra Collaboration Server - Open Source Edition 8.0

August 2012

Table of Contents

1	Introduction	5
	Audience	5
	For More Information	5
	Support and Contact Information	
2	Planning for the Installation	7
_	-	
	Zimbra Packages	
	Configuration Examples	
	Menu-Driven Configuration	
	Common Configuration Options	
	Zimbra LDAP Server Configuration Options	
	Zimbra Mailbox Server Configuration Options	
	Zimbra MTA Server Configuration Options	
	Configuring for Virtual Hosting	
3	Preparing Your Server Environment	19
	System Requirements	
	Modifying Operating System Configurations	
	DNS Configuration Requirement	
	2.10 comganation requirement in the second s	20
4	Multiple-Server Installation	21
	Starting the Installation Process	22
	Installing Zimbra LDAP Master Server	
	Installing Zimbra Mailbox Server	
	Installing Zimbra MTA on a Server	
	Installing the zimbra-SNMP Package	
	Final Set-Up	
	Note about MTA servers	
	Verifying Server Configuration	
	Post Installation Tasks	
	Defining Classes of Service	
	Provisioning Accounts	
	Uninstalling VMware Zimbra Collaboration Server	
5	Adding a Mailbox Server to a Single Server Configuration	11
5		
	Setup Requirements For Adding a Mailbox Server	
	Overview of Process	
	Configuring the Mailbox Server	
	Testing the Configuration	
	Move Mailboxes	
	Move Mailboxes Using CLI zmmboxmove	
	Turn Off Mailbox Server on Single-Server Node	

6	Configuring Multi-Master Replication	47
	Managing Multiple Master LDAP Servers	48 48 48
	Promote Existing Replicas to Multi-Master LDAP Servers	
	Monitoring Multiple LDAP Master Status	
	Feature Requirement	
	γ	
7	Configuring LDAP Replication	53
	Installing Zimbra Master LDAP Server	
	Enable Replication on the LDAP Master	
	Installing a Replica LDAP Server	
	Configuring Zimbra Servers to Use LDAP Replica	
	Uninstalling an LDAP Replica Server	
	Remove LDAP Replica from All Active Servers	
	Disable LDAP on the Replica	
	Monitoring LDAP Replication Status	
	Feature Requirement	
	Endi Godes and Status Explanations	50
Syste	em Requirements for VMware Zimbra Collaboration Server 8.0	61
	Available Languages	68
Index	x	71

1 Introduction

Information in this guide is intended for persons responsible for installing the VMware Zimbra Collaboration Server (ZCS). This guide will help you plan and perform all installation procedures necessary to deploy a fully functioning email system based on Zimbra's messaging technology.

This guide covers the installation of VMware Zimbra Collaboration Server Open Source Edition 8.0

Topics in this chapter include:

- "Audience" on page 5
- "For More Information" on page 5
- "Support and Contact Information" on page 6

Audience

This installation guide assumes you have a thorough understanding of system administration concepts and tasks and are familiar with email communication standards, security concepts, directory services, and database management.

For More Information

Zimbra documentation, including a readme text file, the administration guide, and other Zimbra guides are copied to the servers during the installation. The major documentation types are listed below. You can access all the documents on the Zimbra website, www.zimbra.com and from the administration console, Help Desk page.

- Administrator's Guide. This guide describes product architecture, server functionality, administration tasks, configuration options, and backup and restore procedures.
- Administrator Help. The administrator Help provides instructions about how to add and maintain your servers, domains, and user accounts from the admin console.
- Web Client Help. The Web Client Help provides instructions about how to use the Zimbra Web Client features.

■ **Migration Wizard Guides**. These guides describe how to migrate users that are on Microsoft Exchange or Lotus Domino systems to the VMware Zimbra Collaboration Server.

Support and Contact Information

Visit www.zimbra.com to join the community and to be a part of building the best open source messaging solution. We appreciate your feedback and suggestions.

- Contact Zimbra Sales to purchase VMware Zimbra Collaboration Server.
- Explore the Zimbra Forums for answers to installation or configuration. problems
- Join the Zimbra Community Forum, to participate and learn more about the VMware Zimbra Collaboration Server.
- Send an email to feedback@zimbra.com to let us know what you like about the product and what you would like to see in the product. If you prefer, post your ideas to the Zimbra Forum.

If you encounter problems with this software, visit www.zimbra.com and submit a bug report. Make sure you provide enough detail so that the bug can be easily duplicated.

2 Planning for the Installation

This chapter describes the components that are installed and reviews the configuration options that can be made when you install the VMware Zimbra Collaboration Server (ZCS).

Topics in this chapter include:

- "Zimbra Packages" on page 7
- "Configuration Examples" on page 8
- "Downloading the Zimbra Software" on page 9
- "Menu-Driven Configuration" on page 10
- "Configuring for Virtual Hosting" on page 17
- "Configuring ZCS HTTP Proxy" on page 23
- "Configuring for Virtual Hosting" on page 17

Zimbra Packages

Zimbra architecture includes open-source integrations using industry standard protocols. The third-party software has been tested and configured to work with the Zimbra software.

The following describes the Zimbra packages that are installed.

- Zimbra Core. This package includes the libraries, utilities, monitoring tools, and basic configuration files. Zimbra Core is automatically installed on each server.
- Zimbra LDAP. User authentication is provided through OpenLDAP® software. Each account on the Zimbra server has a unique mailbox ID that is the primary point of reference to identify the account. The OpenLDAP schema has been customized for ZCS. The Zimbra LDAP server must be configured before the other servers. You can set up LDAP replication, configuring a master LDAP server and replica LDAP servers.
- Zimbra Store. The Zimbra store includes the components for the mailbox server, including Jetty, which is the servlet container the Zimbra software runs within. The Zimbra mailbox server includes the following components:
 - Data store. The data store is a MySQL® database.

- Message store. The message store is where all email messages and file attachments reside.
- Index store. Index and search technology is provided through Lucene.
 Index files are maintained for each mailbox.
- Zimbra MTA. Postfix is the open source mail transfer agent (MTA) that receives email via SMTP and routes each message to the appropriate Zimbra mailbox server using Local Mail Transfer Protocol (LMTP). The Zimbra MTA also includes the anti-virus and anti-spam components.
- **Zimbra SNMP**. Installing the Zimbra SNMP package is optional. If you choose to install zimbra-SNMP for monitoring, this package should be installed on every Zimbra server.
- Zimbra Logger. Installing the Zimbra Logger package is optional and is installed on one mailbox server. The Zimbra Logger installs tools for syslog aggregation and reporting. If you do not install Logger, the server statistics section of the administration console will not display.

Note: The Logger package must be installed at the same time as the mailbox server.

- Zimbra Spell. Installing the Zimbra Spell package is optional. Aspell is the open source spell checker used on the Zimbra Web Client.
- **Zimbra Apache**. This package is installed automatically when Zimbra Spell is installed.

The Zimbra server configuration is menu driven. The installation menu displays the default configuration values. The menu displays the logical host name and email domain name [example.com] as configured for the computer.

Configuration Examples

ZCS can be easily scaled for any size of email environment, from very small businesses with fewer than 25 email accounts to large businesses with thousands of email accounts. The following table shows examples of different configuration options.

ZCS	Configu	ration	Options
-			

Small	Medium	Large	Very Large
All ZCS components installed on one server. See the Zimbra Single Sever Installation for quick start installation instructions.	 Zimbra LDAP and Zimbra message store on one server. Zimbra MTA on a separate server. Possibly include additional Zimbra MTA servers. 	 Zimbra LDAP on one server. Multiple Zimbra mailbox servers Multiple Zimbra MTA servers. One or more Zimbra Proxy servers. 	 Zimbra Master LDAP server. Replicas LDAP servers. Multiple Zimbra mailbox servers. Multiple Zimbra MTA servers. Multiple Zimbra Proxy servers.

Downloading the Zimbra Software

For the latest Zimbra software download, go to www.zimbra.com. Save the VMware Zimbra Collaboration Server download file to the computer from which you will install the software.

When the ZCS is installed, the following Zimbra applications are saved to the Zimbra server.

You can access these download files from your administration console Download page, and instruction guides are available from the Help Desk page or from the Zimbra Website, Documents page.

Alternatively, you can download the following applications from http://{example.com/downloads}/index.html (with "example" being your Zimbra server name).

- Zimbra Migration Wizard for Microsoft Exchange .exe file to migrate Microsoft® Exchange server email accounts to the Zimbra server.
- Zimbra Migration Wizard for IBM Lotus Domino .exe file to migrate Lotus Domino server email accounts to the Zimbra server.
- Zimbra Import Wizard for Microsoft Outlook .exe file to allow users to import their Outlook .pst files to the Zimbra server.

Supporting documentation can be found on the administration console Help Desk page or at www.zimbra.com.

Menu-Driven Configuration

The menu driven installation displays the components and their existing default values. During the installation process you can modify the default values. Only those menu options associated with the package being installed are displayed.

Common Configuration Options

The packages installed in common configuration include libraries, utilities, monitoring tools, and basic configuration files under Zimbra Core. These options are configured on all servers.

The following table describes the Main menu common configuration options.y

Main Menu Options

Server Configured	Main Menu	Description
Common Conf	iguration	
All	Hostname	The host name configured in the operating system installation
All	LDAP master host	The LDAP master host name. This LDAP host name is configured on every server
All	LDAP port	The default port is 389
All	LDAP Admin password	Password for the Zimbra admin user and is configured on every server
All	Secure interprocess communications	The default is YES. Secure interprocess communications requires that connections between the mail store, and other processes that use Java, use secure communications. It also specifies whether secure communications should be used between the master LDAP server and the replica LDAP servers for replication.
All	TimeZone	Select the time zone to apply to the default COS. The time zone that should be entered is the time zone that the majority of users in the COS will be located. The default time zone is PST (Pacific Time)
	IP Mode	IPv4 is the default.(IPv6 is ZCS 8.0 Beta only.)

Main Menu Options

Server Configured	Main Menu	Description
All servers, if installed	zimbra-snmp Installing SNMP is optional, but if installed it must be on all servers.	 You can modify the following options Enable SNMP notifications. The default is No. If you enter yes, you must enter the SNMP Trap hostname. SNMP Trap hostname Enable SMTP notification — The default is No. SMTP Source email address — If you enter yes for SMTP notification, you must enter the SMTP source email address and SMTP Destination email address. — destination email address.
	c) Collapse menu	Allows you to expand or collapse the menu.
	r) Start servers after configuration	When the installation and configuration is complete, if this is set to Yes , the Zimbra server is automatically started.
	s) Save config to file	At any time during the installation, you can save the configuration to a file.
	x) Expand menu	Expand menus to see the underlying options
	q) Quit	Quit can be used at any time to quit the installation.

Zimbra LDAP Server Configuration Options

These options are configured on the Zimbra LDAP server.

The table below describes the Main menu LDAP server configuration options.

Zimbra LDAP Server Menu Options

Zimbra **LDAP** Server

zimbra-ldap

Configuration includes the following:

- Status Enabled. For replica LDAP servers, the status can be changed to Disabled if the database is manually loaded after installation completes.
- Create Domain Yes. You can create one domain during installation. Additional domains can be created from the administration console.
- **Domain to create** The default domain is the fully qualified hostname of the server. If you created a valid mail domain on your DNS server, enter it here.
- LDAP Root password. This password is automatically generated and is used for internal LDAP operations.
- LDAP Replication password. This password is automatically generated and is the password used by the LDAP replication server and must be the same password on the LDAP master server and on the replica server.

Table 1:

Zimbra LDAP zimbra-ldap Server

- LDAP Postfix password. This password is automatically generated and is the password used by the postfix user to identify itself to the LDAP server and must be the same password on the LDAP master server and on the MTA server.
- LDAP Amavis password. This password is automatically generated and is the password used by the amavis user to identify itself to the LDAP server and must be the same password on the LDAP master server and on the MTA server.
- LDAP Bes Searcher Password

Zimbra Mailbox Server Configuration Options

These options are configured on the Zimbra Mailbox server.

The following table describes the Zimbra Mailbox server menu options.

Zimbra Mailbox Server Menu Options

Zimbra Mailbox Server

zimbra-store

Configuration includes the following.

- Create Admin User The administrator account is created during installation. This account is the first account provisioned on the Zimbra server and allows you to log on to the administration console.
- Admin user to create The user name assigned to the administrator account. Once the administrator account has been created, it is suggested that you do not rename the account as automatic ZCS notifications might not be received.
- **Admin Password** You must set the admin account password. The password is case sensitive and must be a minimum of six characters. The administrator name, mail address, and password are required to log in to the administration console.
- Anti-virus quarantine user A virus quarantine account is automatically created during installation. When AmivisD identifies an email message with a virus, the email is automatically sent to this mailbox. The virus quarantine mailbox is configured to delete messages older than 7 days.
- **Enable automated spam training By default,** the automated spam training filter is enabled and two mail accounts are created.
 - 1 -Spam training user to receive mail notification about mail that was not marked as junk, but should be.
 - 2 -Non-spam (HAM) training user to receive mail notification about mail that was marked as iunk, but should not have been.

These addresses are automatically configured to work with the spam training filter. The accounts created have a randomly selected name. To recognize what the account is used for you may want to change this name.

The spam training filter is automatically added to the cron table and runs daily.

Zimbra Mailbox Server Menu Options

Zimbra
Mailbox
Server

zimbra-store (continued)

Global Document Account — This account is automatically created when ZCS is installed. The account holds the templates and the default Documents Notebook. The Documents feature is enabled from the COS or in individual accounts.

These default port configurations are shown.

- SMTP host
- Web server HTTP port:- 80
- Web server HTTPS port: 443
- Web server mode Can be HTTP, HTTPS, Mixed, Both or Redirect.

Mixed mode uses HTTPS for logging in and HTTP for normal session traffic

Both mode means that an HTTP session stays HTTP, including during the login phase, and an HTTPS session remains HTTPS throughout, including the login phase.

Redirect mode redirects any users connecting via HTTP to a HTTPS connection.

All modes use SSL encryption for back-end administrative traffic.

- IMAP server port: 143
- IMAP server SSL port: 993
- POP server port: 110
- POP server SSL port: 995
- Use spell check server: yes (if installed)
- Spell server URL: http://<example.com>:7780/ aspell.php

Zimbra Mailbox Server Menu Options

- Enable version update checks. ZCS automatically checks to see if a new ZCS update is available. The default is TRUE.
- Enable version update notifications. This enables automatic notification when updates are available when this is set to True.
- Version update notification email. This is the email address of the account to be notified when updates are available. The default is to send the notification to the admin's account.
- Version update source email. This is the email address of the account that sends the email notification. The default is the admin's account.

Note: The software update information can be viewed from the Administration Console Tools Overview pane.

Zimbra mailbox server	zimbra-mta	Postfix is the open source mail transfer agent (MTA) that receives email via SMTP and routes each message to the appropriate Zimbra mailbox server using Local Mail Transfer Protocol (LMTP). The Zimbra MTA also includes the anti-virus and anti-spam components.
Zimbra mailbox server	zimbra-snmp	Installing the Zimbra-SNMP package is optional. If you choose to install Zimbra-SNMP for monitoring, the package should be run on every server (Zimbra server, Zimbra LDAP, Zimbra MTA) that is part of the Zimbra configuration. Zimbra uses swatch to watch the syslog output to generate SNMP traps.
Zimbra mailbox server	zimbra-logger	The Logger package is installed on the one mail server. If installed, it is automatically enabled. Logs from all the hosts are sent to the mailbox server where the logger package is installed. This data is used to generate the statistics graphs and reporting.
Zimbra mailbox server	zimbra-spell	If installed, it is automatically enabled. When composing messages in the Zimbra Web Client, spell check can be run.
Zimbra mailbox server	zimbra- apache	When you install zimbra-spell, zimbra-apache gets installed automatically.
Zimbra mailbox server	Enable VMware HA	VMware HA Clustering Heartbeat is only available when running within a virtual machine running vmware-tools.

Zimbra Mailbox Server Menu Options

Zimbra mailbox server	Default Class of Service Configuration	This menu lists major new features for the ZCS release and whether feature are enabled or not. When you change the feature setting during ZCS installation, you change the default COS settings.
Zimbra mailbox server	Start servers after configuration	Start servers after configuration.
Zimbra mailbox server	Save config to file	Save the configuration to file.
Zimbra mailbox server	Expand menu	Expand the menu.

Zimbra MTA Server Configuration Options

Zimbra MTA server configuration involves installation of the Zimbra-MTA package. This also includes anti-virus and anti-spam components.

The following table describes the MTA server menu options:

MTA Server Configuration Options

Zimbra	zimbra-mta	The following options can be modified.
MTA Server		 MTA Auth host. This is configured automatically if the MTA authentication server host is on the same server, but must be configured if the authentication server is not on the MTA. The MTA Auth host must be one of the mailbox servers. Enable Spamassassin. Default is enabled.
		Enable ClamAV. Default is enabled.
		Notification address for AV alerts. Sets the notification address for AV alerts. You can either accept the default or create a new address. If you create a new address, remember to provision this address from the admin console. Note: If the virus notification address does not exist and your host name is the
		same as the domain name on the Zimbra server, the virus notifications queue in the Zimbra MTA server and cannot be delivered.
		Bind password for postfix LDAP user. This password must be the same as the postfix password configured on the master LDAP server.
		Bind password for amavis LDAP user. This password must be the same as the amavis password configured on the master LDAP server.

Note: New installs of ZCS limit spam/ham training to the first MTA installed. If you uninstall or move this MTA, you will need to enable spam/ham training on another MTA, as one host should have this enabled to run zmtrainsa --cleanup. To do this set zmlocalconfig -e zmtrainsa_cleanup_host=TRUE.

Configuring for Virtual Hosting

You can configure multiple virtual hostnames to host more than one domain name on a server. When you create a virtual host, users can log in without have to specify the domain name as part of their user name.

Virtual hosts are configured from the administration console Configure>Domains>Virtual Hosts page. The virtual host requires a valid DNS configuration with an A record.

When users log in, they enter the virtual host name in the browser. For example, https://mail.example.com. When the Zimbra logon screen displays, users enter only their user name and password. The authentication request searches for a domain with that virtual host name. When the virtual host is found, the authentication is completed against that domain.

3 Preparing Your Server Environment

In order to successfully install and run VMware Zimbra Collaboration Server, ensure your system meets the requirements described in this section.

Topics in this chapter include:

- "System Requirements" on page 19
- "Modifying Operating System Configurations" on page 19
- "DNS Configuration Requirement" on page 20

Important: Do not manually create the user 'zimbra' before running the ZCS installation. The installation automatically creates this user and sets up its environment.

System Requirements

For the ZCS system requirements see System Requirements for VMware Zimbra Collaboration Server 8.0 at the end of this guide.

Modifying Operating System Configurations

Important: The operating system that you use should be at the current patch level before you install ZCS. See the latest release notes for a list of the operating systems patches that have been tested with ZCS.

The VMware Zimbra Collaboration Server runs on one of several operating systems, including Ubuntu® LTS, Red Hat® Enterprise Linux, and SUSE® Linux Enterprise.

Installation modifications for frequently used operating systems are described in individual configuration documents found on the ZCS documentation website, such as *Installation Modifications for ZCS with Ubuntu LTS*, or *Installation Modifications for ZCS with Red Hat*. Other operating systems may require similar modifications, and you can use the information contained in these documents as a reference to gauge whether your operating system might need to be modified.

A full default installation of the Linux distribution that you select is required.

For more information, refer to the System Requirements for VMware Zimbra Collaboration Server 8.0 document for information on hardware and software configurations supported by VMware Zimbra Collaboration Server.

Note: Zimbra recommends that the operating systems you use are updated with the latest patches that have been tested with ZCS. See the latest release notes to see the operating systems patch list that has been tested with ZCS.

DNS Configuration Requirement

When you create a domain during the installation process, ZCS checks to see if you have an MX record correctly configured. If it is not, an error is displayed suggesting that the domain name have an MX record configured in DNS.

In order to send and receive email, the Zimbra MTA must be configured in DNS with both A and MX records. For sending mail, the MTA uses DNS to resolve hostnames and email-routing information. To receive mail the MX record must be configured correctly to route the message to the mail server.

You must configure a relay host if you do not enable DNS. After ZCS is installed, go to the **Configure>Global Settings>MTA** page on the administration console and uncheck **Enable DNS lookups**. Enter the relay MTA address to use for external delivery.

Note: Even if a relay host is configured, an MX record is still required if the ZCS server is going to receive email from the Internet.

4 Multiple-Server Installation

The multiple-server installation is straight-forward and easy to run. You run the same install script on each server, select the component(s) to install, and use the menu to configure the system.

Topics in this chapter include:

- "Starting the Installation Process" on page 22
- "Installing Zimbra LDAP Master Server" on page 24
- "Installing Zimbra Mailbox Server" on page 27
- "Installing Zimbra MTA on a Server" on page 33
- "Installing zimbra-proxy" on page 44
- "Installing zimbra-archiving Package" on page 48
- "Installing the zimbra-SNMP Package" on page 36
- "Final Set-Up" on page 36
- "Verifying Server Configuration" on page 38
- "Logging on to the Administration Console" on page 38
- "Post Installation Tasks" on page 38
- "Uninstalling VMware Zimbra Collaboration Server" on page 40

After the installation is complete, two additional steps should be run as described in "Final Set-Up" on page 36:

- Fetch the ssh encryption keys
- Enable some logger functionality

When the server installation is complete, the servers are started and the status is displayed.

Important: Install the servers in the following order

- 1. LDAP server
- 2. Zimbra mailbox servers
- 3. Zimbra MTA servers

Important: Do not manually create the user 'zimbra' before running the ZCS installation. The installation automatically creates this user and sets up its environment.

Important: Before you start, verify that the system clocks are synced on all servers.

Starting the Installation Process

Important: Before you begin, make sure to:

Confirm you have the latest system requirements and prerequisites for installing ZCS, as described in "System Requirements for VMware Zimbra Collaboration Server 8.0" on page 61.

For the latest Zimbra software downloads, go to www.zimbra.com. Save the VMware Zimbra Collaboration Server tar file to the computer from which you are installing the software.

Step 1 through step 4 are performed for each server to be installed.

- 1. Log in as **root** to the Zimbra server and **cd** to the directory where the VMware Zimbra Collaboration Server archive file is saved (cd /var/<tmp>). Type the following commands.
 - tar xzvf [zcs.tgz] to unpack the file
 - cd [zcs filename] to change to the correct directory. The file name includes the release and build date.
 - ./install.sh to begin the installation.

Note: As the installation proceeds, press **Enter** to accept the defaults that are shown in brackets [] or enter the appropriate answer for your configuration.

The screen shots are examples of the Zimbra installation script.

```
[root@mailhost tmp]# tar xzvf zcs.tgz
zcs-NETWORK-8.0.0_GA_3107.UBUNTU10_64.20100916012803/
zcs-NETWORK-8.0.00_GA_3107.UBUNTU10_64.20100916012803/packages/
zcs-NETWORK-8.0.0_GA_3107.UBUNTU10_64.20100916012803/packages/
zimbra-apache_8.0.0_GA_3107.UBUNTU10_64_amd64.deb
zcs-NETWORK-8.0.0_GA_3107.UBUNTU10_64.20101015012627/install.sh
zcs-NETWORK-8.0.0_GA_3107.UBUNTU10_64.20101015012627/README.txt
[root@mailhost tmp]# cd zcs-NETWORK-
8.0.0 GA 3107.UBUNTU10 64.20101015012627
[root@mailhost tmp/zcs-NETWORK-
8.0.0 GA 3107.UBUNTU10 64.20101015012627# ./install.sh
Operations logged to /tmp/install.log.3833
Checking for existing installation...
    zimbra-ldap...NOT FOUND
    zimbra-logger...NOT FOUND
   zimbra-mta...NOT FOUND
   zimbra-snmp...NOT FOUND
   zimbra-store...NOT FOUND
   zimbra-apache...NOT FOUND
    zimbra-spell...NOT FOUND
               zimbra-core...NOT FOUND
```

Screen shots in this guide are examples of the Zimbra installation script. The actual script may be different.

- 2. The installation process checks to see if Sendmail, Postfix, and MySQL software are running. If any application is running, you are asked to disable it. The default is Yes to disable the applications. Disabling MySQL is optional, but highly recommended. Sendmail and Postfix must be disabled for the VMware Zimbra Collaboration Server to start correctly.
- 3. Next, the installer checks to see that the prerequisite software is installed. If NPTL, sudo, libidn, cURL, fetchmail, GMP or compat-libstdc++- are not installed, the installation process guits. You must fix the problem and start the installation again. See Other Dependencies in System Requirements for VMware Zimbra Collaboration Server 8.0.

Note: Before the Main menu is displayed, the installer checks to see if the hostname is resolvable via DNS and if there is an error asks you if would like to change the hostname. The domain name should have an MX record configured in DNS.

Installing Zimbra LDAP Master Server

You must configure the Zimbra Master LDAP server before you can install other Zimbra servers. You can set up LDAP replication, configuring a master LDAP server and replica LDAP servers, either configuring all LDAP servers now or after you set up the initial ZCS servers. See Chapter 7, Configuring LDAP Replication.

Important: If you are installing more than one LDAP server, see Chapter 7, Configuring LDAP Replication.

- 1. Follow steps 1 through 4 in "Starting the Installation Process" on page 22 to open an SSH session to the LDAP server, log on to the server as **root**, and unpack the Zimbra software.
- 2. Type Y and press Enter to install the zimbra-Idap package. The MTA, Store and Logger packages should be marked N. In the following screen shot example, the package to be installed is emphasized.

Note: If SNMP is being used, the SNMP package is installed on every Zimbra server. Mark Y.

```
Select the packages to install
Install zimbra-ldap [Y] y
Install zimbra-logger [Y] n
Install zimbra-mta [Y] n
Install zimbra-snmp [Y] n
Install zimbra-store [Y] n
Install zimbra-apache [Y] n
Install zimbra-spell [Y] n
Checking required space for zimbra-core
Installing:
   zimbra-core
   zimbra-ldap
The system will be modified. Continue? [N] y
```

3. Type Y, and press Enter to modify the system. The selected packages are installed on the server.

The Main menu displays the default entries for the Zimbra component you are installing. To expand the menu to see the configuration values type x and press Enter. The main menu expands to display configuration details for the package being installed. Values that require further configuration are marked with asterisks (*).

To navigate the Main menu, select the menu item to change. You can modify any of the values. See Table, "Main Menu Options," on page 10 for a description of the Main menu.

```
Main menu
  1) Common Configuration:
  2) zimbra-ldap:
                                               Enabled
  3) zimbra-store:
                                               yes
  r) Start servers after configuration
                                               yes
  s) Save config to file
  x) Expand menu
  q) Quit
*** CONFIGURATION COMPLETE - press 'a' to apply
Select from menu, or press 'a' to apply config (? - help)
```

4. Type 1 to display the **Common Configuration** submenus.

```
Common Configuration:
   1)Hostname:
                                       ldap-1.example.com
   2)Ldap master host:
                                       ldap-1.example.com
   3)Ldap port:
                                          389
   4)Ldap Admin password:
                                          set
   5) Secure interprocess communications: Yes
                 (GMT-08.00) Pacific Time (US & Canada)
   6) TimeZone:
   7) IP Mode:
                                          ipv4
```

5. Type 4 to display the automatically generated LDAP admin password. You can change this password. Write down the LDAP password, the LDAP host name and the LDAP port. You must configure this information when you install the mailbox servers and MTA servers.

LDAP Admin Password	
LDAP Host name	
LDAP Port	

- 6. Type 6 to set the correct time zone, if your time zone is not Pacific Time.
- 7. Type **r** to return to the Main menu.
- 8. From the Main menu, type 2) zimbra-ldap to view the Ldap configuration settings.

```
Ldap configuration
  1) Status:
                                               Enabled
  2) Create Domain:
                                               ves
  3) Domain to create
                                               ldap-1.example.com
  4) Ldap Root password:
                                               set
  5) Ldap Replication password:
                                               set
  6) Ldap Postfix password:
                                               set
   7) Ldap Amavis password:
                                               set
   8) Ldap Nginx password:
                                               set
   9) Ldap Bes Searcher password:
                                               set
Select, or 'r' for previous menu [r] 3
Create Domain: [ldap-1.example.com] example.com
```

- Type 3) Domain to create to change the default domain name to the domain name, (example.com).
- The passwords listed in the LDAP configuration menu are automatically generated. You need these passwords when configuring the MTA and the LDAP replica servers. Write them down. If you want to change the passwords for LDAP root, LDAP replication, LDAP Postfix, LDAP Amavis, and LDAP Nginx, enter the corresponding number 4 through 8 and change the passwords.

Ldap replication password
Ldap postfix password
Ldap amavis password
Ldap nginx password

- 9. When changes to the LDAP configuration menu are complete, enter r to return to the main menu. Type **a** to apply the configuration changes.
- 10. When Save configuration data to file appears, type Yes and press Enter.
- 11. The next request asks where to save the files. To accept the default, press **Enter**. To save the files to another directory, enter the directory and press Enter.
- 12. When The system will be modified continue? appears, type y and press Enter.

The server is modified. Installing all the components and configuring the server can take a few minutes. This includes but is not limited to setting local config values, creating and installing SSL certificates, setting passwords, timezone preferences, and starting the servers, among other processes.

13. When Configuration complete - press return to exit displays, press Enter.

```
*** CONFIGURATION COMPLETE - press 'a' to apply
Select from menu, or press 'a' to apply config (? - help) a
Save configuration data to a file? [Yes] y
Save config in file: [/opt/zimbra/config.26148]
Saving config in /opt/zimbra/config.26148...done.
The system will be modified - continue? [No] y
Operations logged to /tmp/zmsetup.07032012-151126.log
Setting local config values...done.
Starting servers...done.
Setting up zimbra crontab...done.
Moving /tmp/zmsetup.07032012-151126.log to /opt/zimbra/log
Configuration complete - press return to exit
```

The installation of the LDAP server is complete.

Installing Zimbra Mailbox Server

The zimbra-store package can be installed with the LDAP server, the MTA server, or as a separate mailbox server. You can have more than one mailbox server and new mailbox servers can be added at any time.

Note: The zimbra-logger package is installed only on the first Zimbra mailbox server.

- 1. Follow steps 1 through 4 in "Starting the Installation Process" on page 22 to log on to the server as root and unpack the Zimbra software.
- 2. Type Y and press Enter to install the zimbra-logger (optional and only on one mailbox server), zimbra-store, and zimbra-spell (optional) packages. When zimbra-spell is installed, the **zimbra-apache** package also gets installed. In the following screen shot example, the packages to be installed are emphasized.

Note: If SNMP is being used, the SNMP package is installed on every Zimbra server, Mark Y.

```
Install zimbra-ldap [Y] N
Install zimbra-logger [Y] Y
Install zimbra-mta [Y] N
Install zimbra-snmp [Y] N
Install zimbra-store [Y] Y
Install zimbra-apache [Y] Y
Install zimbra-spell [Y] Y
Installing:
    zimbra-core
    zimbra-logger
   zimbra-store
   zimbra-apache
   zimbra-spell
    zimbra-convertd
The system will be modified. Continue [N] Y
```

3. Type Y, and press Enter to modify the system. The selected packages are installed on the server.

The Main menu displays the default entries for the Zimbra component you are installing. To expand the menu to see the configuration values type x and press Enter.

To navigate the Main menu, select the menu item to change. You can modify any of the values. For information about the menu values, see "Planning for the Installation" chapter, Menu-Driven Configuration section.

```
Main menu
   1) Common Configuration:
        +Hostname:
                                               mailstore-1.example.com
***** +Ldap master host:
                                               UNSET
       +Ldap port:
                                               389
****** +Ldap Admin password:
                                               UNSET
        +Secure interprocess communications: yes
        +TimeZone:
                                               (GMT-08.00) Pacific Time
(US & Canada)
       +IP Mode:
                                               ipv4
   2) zimbra-ldap:
                                               Enabled
                                               Enabled
   3) zimbra-store:
        +Create Admin User:
                                               yes
        +Admin user to create:
                                          admin@mailstore-1.example.com
***** +Admin Password
                                              UNSET
        +Anti-virus quarantine user::
                                               virus-
quarantine.gw98bctr0@mailstore-1.example.com
       +Enable automated spam training:
                                              yes
        +Spam training user: spam.cc_v05j4@mailstore-1.example.com
        +Non-spam(Ham) training user: ham.msoyzx@mailstore-1.example.com
        +SMTP host
                                              mailstore-1.example.com
        +Web server HTTP port:
                                              80
       +Web server HTTPS port:
                                               443
       +Web server mode:
                                              http
       +IMAP server port:
                                               143
        +IMAP server SSL port:
                                               993
        +POP server port:
                                               110
        +POP server SSL port:
                                               995
        +Use spell check server:
                                               yes
        +Spell server URL:
                                              http://mailstore-
1.example.com:7780/aspell.php
              +Enable version update checks:
                                                      TRUE
        +Enable version update notifications: TRUE
        +Version update notification email: admin@mailstore-
1.example.com
                                             admin@mailstore-
        +Version update source email:
1.example.com
 4) zimbra-mta:
                                             Enabled
 5) zimbra-snmp:
                                             Enabled
                                             Enabled
 6) zimbra-logger:
   7) zimbra-spell:
                                               Enabled
  8) zimbra-convertd:
                                               Enabled
  9) Enable VMware HA:
                                               Enabled
  10) Default Class of Service Configuration:
    r) Start servers after configuration
                                                yes
  s) Save config to file
  x) Expand menu
   q) Quit
```

Type 1 and press Enter to go to the Common Configuration menu.

```
Common Configuration:

1)Hostname: mailstore-1.example.com
2)Ldap master host: mailstore-1.example.com
3)Ldap port: 389
4)Ldap Admin password: set
5)Secure interprocess communications Yes
6)TimeZone: (GMT-08.00) Pacific Time (US & Canada)
7)IP Mode: ipv4
```

The mailbox server hostname is displayed. You must change the LDAP master host name and password to be the values configured on the LDAP server.

- Type 2, press Enter, and type the LDAP host name. (Idap-1.example.com in this example.)
- Type 4, press Enter, and type the LDAP password.

After you set these values, the server immediately contacts the LDAP server. If it cannot contact the server, you cannot proceed.

- Type 6 to set the correct time zone, if your time zone is not Pacific Time.
- 5. Type **r** to return to the Main menu.
- 6. From the Main menu, type 2 to go to the Store configuration menu.

```
Store configuration
  1) Status:
                                            Enabled
  2) Create Admin User:
                                            yes
   3) Admin user to create:
                                             admin@mailhost.example.com
** 4) Admin Password
  5) Anti-virus quarantine user:
                                             virus-
quarantine.zodi72xmm6@mailhost.example.com
  6) Enable automated spam training:
                                             yes
  7) Spam training user: spam.vviwu_izoj@mailhost.example.com
  8) Non-spam(Ham) training user: ham.unsbogyzer@mailhost.example.com
  9) SMTP host:
                                             mailhost.example.com
 10) Web server HTTP port:
                                             80
 11) Web server HTTPS port:
                                             443
 12) Web server mode:
                                             http
 13) IMAP server port:
                                             143
 14) IMAP server SSL port:
                                             993
 15) POP server port:
                                             110
 16) POP server SSL port:
                                             995
 17) Use spell check server:
                                             yes
 18) Spell server URL: http://mailhost.example.com :7780/aspell.php
 21) Enable version update checks:
                                             TRUE
 22) Enable version update notifications:
                                             TRUE
Select, or 'r' for previous menu [r] 4
Password for admin@mailhost.example.com (min 6 characters): [2LPoBSob]
zimbra
```

- 7. Configure the zimbra mailbox store server settings.
 - Type 4 and set the password for the administrator account. The password is case sensitive and must be a minimum of six characters. During the install process, the admin account is provisioned on the mailbox store server. You log on to the administration console with this password.

Note: By default, the email addresses for the admin account, spam, nonspam, wiki are set to be the zimbra mailstore server address. You may want to change these to be the ZCS primary domain address instead. (example.com in this example)

- Type the corresponding number to set the SMTP host. This is the mtaserver host name.
- Type the corresponding number if you want to change the default web server mode. The communication protocol options are HTTP, HTTPS, mixed, both or redirect.

Mixed mode uses HTTPS for logging in and HTTP for normal session traffic

Both mode means that an HTTP session stays HTTP, including during the login phase, and an HTTPS session remains HTTPS throughout, including the login phase.

Redirect mode redirects any users connecting via HTTP to a HTTPS connection.

All modes use SSL encryption for back-end administrative traffic.

- If you install the zimbra spell package, it is installed on every mailstore. The http address for each is the mailstore server it is installed on host name.
- Enable version update checks and Enable version update notifications are set to TRUE. ZCS automatically checks for the latest ZCS software updates and notifies the account that is configured in Version update notification email. You can modify this later from the administration console.
- 8. Type **r** to return to the Main menu.
- 9. Review the Default Class of Service Configuration settings. If you want to change the COS default configuration of these features, type the number (6) for the Default Class of Service Configuration. Then type the corresponding number for the feature to be enabled or disabled. The default COS settings are adjusted to match.
- 10. When the mailbox server is configured, return to the Main menu and type a to apply the configuration changes. Press Enter to save the configuration
- 11. When Save Configuration data to a file appears, press Enter.
- 12. The next request asks where to save the files. To accept the default, press **Enter.** To save the files to another directory, enter the directory and then press Enter.
- 13. When The system will be modified continue? appears, type y and press

The server is modified. Installing all the components and configuring the mailbox server can take a few minutes. This includes installing SSL certificates, setting passwords, setting ports, installing skins and zimlets, setting time zone preferences, and starting the servers, among other processes.

14. When Configuration complete - press return to exit displays, press Enter.

The installation of the mailbox server is complete.

```
Select, or press 'a' to apply config (? - help) a
Save configuration data? [Yes]
Save config in file: [/opt/zimbra/config.32288]
Saving config in /opt/zimbra/config.32288...Done
The system will be modified - continue? [No] y
Operations logged to /tmp/zmsetup.07032012-110412.log
Setting local config zimbra_server_hostname to [mailhost.example.com]
Operations logged to /tmp/zmsetup.log.32288
Configuration complete - press return to exit
```

Installing Zimbra MTA on a Server

When zimbra-mta is installed, the LDAP host name and the Zimbra LDAP password must be known to the MTA server. If not, the MTA cannot contact the LDAP server and is not able to complete the installation.

- 1. Follow steps 1 through 4 in "Starting the Installation Process" on page 22 to open a SSH session to the MTA server, log on to the server as root, and unpack the Zimbra software.
- 2. Type Y and press Enter to install the zimbra-mta package. The other packages should be marked N. In the following screen shot example, the package to be installed is emphasized.

Note: If SNMP is used, it is installed on every server.

```
Select the packages to install
Install zimbra-ldap [Y] N
Install zimbra-logger [Y] N
Install zimbra-mta [Y] Y
Install zimbra-snmp [Y] N
Install zimbra-store [Y] N
Install zimbra-apache [Y] N
Install zimbra-spell [Y] N
Installing:
   zimbra-mta
This system will be modified. Continue [N] Y
Configuration section
```

3. Type Y, and press Enter to install the selected package(s).

The Main menu displays the default entries for the Zimbra component you are installing. To expand the menu to see all the configuration values type x and press Enter.

To navigate the Main menu, select the menu item to change. You can modify any of the values.

```
Main menu
   1) Common Configuration:
                                              mta-1.example.com
       +Hostname:
****** +Ldap master host:
                                              UNSET
       +Ldap port:
                                              389
****** +Ldap Admin password:
                                              UNSET
       +Secure interprocess communications: yes
       +TimeZone:
                                              (GMT-08.00) Pacific
Time (US & Canada)
       +IP Mode:
                                              ipv4
  2) zimbra-mta:
                                              Enabled
********+MTA Auth host:
                                              mta-1.example.com
       +Enable Spamassassin:
                                              yes
       +Enable Clam AV:
                                              yes
       +Notification address for AV alerts: admin@mta-
1.example.com
       +Bind password for postfix ldap user: UNSET
       +Bind password for amavis ldap user:
                                              UNSET
  r) Start servers after configuration
                                              ves
  s) Save config to file
  x) Expand menu
   q) Quit
```

4. The Main menu displays. Type 1 and press Enter to go to the Common Configuration menu.

```
Common Configuration:
   1)Hostname:
                                             mta-1.example.com
   2)Ldap master host:
                                             ldap-1.example.com
   3)Ldap port:
                                             389
   4)Ldap Admin password:
                                             set
    5) Secure interprocess communications
                                            ves
                                            (GMT-08.00) Pacific Time
    6) Time Zone:
(US & Canada)
   7) IP Mode:
                                             ipv4
```

The mailbox server hostname is displayed. You must change the LDAP master host name and password to be the values configured on the LDAP server.

• Type 2, press Enter, and type the LDAP host name. (Idap-1.example.com in this example.)

Type 4, press Enter, and type the LDAP password.

After you set these values, the server immediately contacts the LDAP server. If it cannot contact the server, you cannot proceed.

- Type 6 to set the correct time zone, if your time zone is not Pacific Time.
- 5. Type **r** to return to the Main menu.
- 6. Type 2 to go to the Mta menu.

```
Select, or press 'a' to apply config (? - help) 2
Mta configuration
 1) Status:
                                              Enabled
**2) MTA Auth host:
                                              UNSET
 3) Enable Spamassassin:
                                              ves
 4) Enable Clam AV:
 5) Notification address for AV alerts: admin@mta-1.example.com
**6) Bind password for postfix ldap user: UNSET
**7) Bind password for amavis ldap user:
                                              UNSET
```

- Type 2 to set the MTA Auth host. This is the MTA authentication server host name and is set to one of the Zimbra mailbox server's hostname.
- You can change 5. AV alerts notification address. This should be an address on the domain, such as the admin address. (admin@example.com)

Note: If you enter an address other than the admin address, you must provision an account with that address after the installation is complete.

You must set the same postfix Idap user password and the same amavis Idap user password that is configured on the LDAP master server.

- Type 6 and enter the postfix password.
- Type 7 and enter the amavis password.
- 7. Type **r** to return to the Main menu.
- 8. When the MTA server is configured, return to the Main menu and type a to apply the configuration changes. Press **Enter** to save the configuration data.
- 9. When Save Configuration data to a file appears, press Enter.
- 10. The next request asks where to save the files. To accept the default, press **Enter**. To save the files to another directory, enter the directory and then press Enter.
- 11. When The system will be modified continue? appears, type y and press Enter.

The server is modified. Installing all the components and configuring the MTA server can take a few minutes. This can include setting passwords, setting ports, setting time zone preferences, and starting the server, among other processes.

12. When **Installation complete - press return to exit** displays, press **Enter**.

The installation of the MTA server is complete.

13.

Installing the zimbra-SNMP Package

Installing the zimbra-SNMP package is optional, but if you use SNMP monitoring, this package should be installed on each Zimbra server.

In the Main menu, select zimbra-snmp to make changes to the default values.

The following questions are asked for SNMP configuration.

- Configure whether to be notified by SNMP or SMTP. The default is No. If you enter yes, you must enter additional information.
 - For SNMP type the SNMP Trap host name.
 - For SMTP type the SMTP source email address and destination email address.

```
8) zimbra-snmp:
                                          Enabled
  +Enable SNMP notifications:
                                          yes
  +SNMP Trap hostname:
                                          example.com
  +Enable SMTP notifications:
  +SMTP Source email address:
                                          admin@example.com
   +SMTP Destination email address:
                                          admin@example.com
```

Final Set-Up

After the Zimbra servers are configured in a multi-node configuration, the following functions must be configured:

- In order for remote management and postfix queue management, the ssh keys must be manually populated on each server.
- If logger is installed, set up the syslog configuration files on each server to enable server statistics to display on the administration console, and then enable the logger monitor host. The server statistics includes information about the message count, message volume, and anti-spam and anti-virus activity.
- ZCS ships a default zimbra user with a disabled password. ZCS requires access to this account via ssh public key authentication. On most operating systems this combination is okay, but if you have modified pam rules to

disallow any ssh access to disabled accounts then you must define a password for the zimbra UNIX account. This will allow ssh key authentication for checking remote queues. See the Zimbra wiki article, Mail Queue Monitoring.

Set Up the SSH Keys

To populate the ssh keys, on each server, as Zimbra user (su - zimbra). Type **zmupdateauthkeys** and press **Enter**. The key is updated on /opt/zimbra/.ssh/authorized keys.

Enabling Server Statistics Display

In order for the server statistics to display on the administration console, the syslog configuration files must be modified.

Important: Depending on your operating system, the steps below may not be correct. See your operating system documentation for specific information about how to enable syslog.

- 1. On each server, as root, type /opt/zimbra/libexec/zmsyslogsetup. This enables the server to display statistics.
- 2. On the logger monitor host, you must enable either syslog or rsyslog to log statistics from remote machines:

For syslog:

- a. Edit the /etc/sysconfig/syslog file, add -r to the SYSLOGD_OPTIONS setting, SYSLOGD_options="-r -m 0"
- b. Stop the syslog daemon. Type /etc/init.d/syslog stop
- c. Start the syslog daemon. Type /etc/init.d/syslog start

For syslog on Debian or Ubuntu:

- a. Edit the /etc/default/syslogd file, add -r to the SYSLOGD OPTIONS setting, SYSLOGD_options="-r -m 0"
- b. Stop the syslog daemon. Type /etc/init.d/sysklogd stop
- c. Start the syslog daemon. Type /etc/init.d/sysklogd start

For rsyslog:

a. Uncomment the following lines in /etc/rsyslog.conf

\$modload imudp \$UDPServerRun 514

b. Restart rsyslog

Note about MTA servers

New installs of ZCS limit spam/ham training to the first MTA installed. If you uninstall or move this MTA, you will need to enable spam/ham training on another MTA, as one host should have this enabled to run zmtrainsa -cleanup. To do this, set zmlocalconfig -e zmtrainsa_cleanup_host=TRUE.

Verifying Server Configuration

When Configuration complete - press return to exit is displayed, the installation is finished and the server has been started. Before going to the next server, you should verify that the server is running.

Use the CLI command, **zmcontrol status**, to verify that each server is running.

- 1. For each server in the VMware Zimbra Collaboration Server environment. log on as a Zimbra administrator, from the root.
- 2. Type su zimbra.
- 3. Type zmcontrol status. The services status information is displayed. All services should be running.

Note: If services are not started, you can type zmcontrol start. See the CLI command appendix in the Administration Guide for more zmcontrol commands.

Logging on to the Administration Console

To log on to the administration console, open your browser, type the administration console URL and log on to the console. The administration console URL is entered as

https://[example.com]:7071/zimbraAdmin.

Note: The administration console address must be typed with "https", even if you configured only "http".

The first time you log on, a certificate authority (CA) alert may be displayed. Click Accept this certificate permanently to accept the certificate and be able connect to the Zimbra administration console. Then click **OK**.

Enter the admin user name and password configured during the installation process. Enter the user name as admin@example.com.

Post Installation Tasks

Once the VMware Zimbra Collaboration Server is installed, you can log on to the administration console and configure additional domains, create Classes of Service, and provision accounts. See the Zimbra Administrator's Guide.

Defining Classes of Service

A default Class of Service (COS) is automatically created during the installation of Zimbra software. The COS controls mailbox quotas, message lifetime, password restrictions, attachment blocking and server pools. You can modify the default COS and create new COSs to assign to accounts according to your group management policies.

In an environment with multiple mailbox servers, COS is used to assign the new accounts to a mailbox server. The COS server pool page lists the mailbox servers in your Zimbra environment. When you configure the COS, select which servers to add to the server pool. Within each pool of servers, a random algorithm assigns new mailboxes to any available server.

To create or modify a COS, from the administration console, click COS. If you have questions, refer to the Help.

Provisioning Accounts

You can configure one account at a time with the New Account Wizard or you can create many accounts at once using the Account Migration Wizard.

Configuring One Account

The administration console New Account Wizard steps you through the account information to be completed.

1. From the administration console Navigation pane, click **Accounts**.

Note: Four accounts are listed: admin account, two spam training accounts, and a global Documents account. These accounts do not need any additional configuration.

- Click New. The first page of the New Account Wizard opens.
- Enter the account name to be used as the email address and the last name. This the only required information to create an account.
- 4. You can click **Finish** at this point, and the account is configured with the default COS and global features.

To configure aliases, forwarding addresses, and specific features for this account, proceed through the dialog before you click Finish.

When the accounts are provisioned, these accounts can immediately start to send and receive emails.

Configuring Many Accounts at Once

You can provision multiple accounts at once using the Account Migration tool from the administration console. The wizard guides you through the steps to import accounts from an external directory server, either Active Directory or an LDAP server. The wizard downloads account information from your directory and creates the accounts in ZCS.

Refer to the administration guide to learn more about provisioning accounts.

Import the Content of Users' Mailboxes

Zimbra's migration and import tools can be used to move users' email messages, calendars, and contacts from their old email servers to their accounts on the Zimbra server. When the user's files are imported, the folder hierarchy is maintained. These tools can be accessed from the administration console Download page and instruction guides are available from the Administration Console Help Desk.

Uninstalling VMware Zimbra Collaboration Server

To uninstall servers, you run the install script -u and then delete the zcs directory and remove the ZCS tgz file on the servers.

- 1. Change directories to the original install directory for the zcs files.
- 2. Type ./install.sh -u.
- 3. When **Completely remove existing installation?** is displayed, type Yes. The Zimbra servers are stopped, the existing packages, the webapp directories, and the /opt/zimbra directory are removed.
- 4. Delete the zcs directory, type rm -rf [zcsfilename].
- 5. Delete the zcs.tgz file, type rm -rf zcs.tgz.
- 6. Additional files may need to be delete. See the Zimbra Wiki Installation section on http://wiki.zimbra.com/index.php?title=Main Page.

5 Adding a Mailbox Server to a Single Server Configuration

In the Zimbra Collaboration Server single server environment, the LDAP, MTA, and mailbox services are on one machine. This chapter explains how to add a new machine that is configured as a mailbox server to a single server configuration and how to remove the mailbox server from the single server node.

Setup Requirements For Adding a Mailbox Server

- The new machine you are adding must have the same operating system, including the latest version and patch levels, as installed on the Zimbra single server.
- The system clock must be configured with the same time on both machines.
- You must install the same version of the ZCS software that is installed on the single server node.
- A copy of the ZCS license needs to be added to a directory on the new machine.
- If you are adding Zimbra Proxy to ZCS, this should be installed on the existing single-server before you set up the new mailbox server. See the Multi-server Installation chapter, Installing zimbra-proxy section.

Overview of Process

- Zimbra Mailbox Server is installed on the prepared machine.
- Customized configuration for the single-server, such as custom themes and zimlets are added to the new mailbox server.
- Commercial SSL certificates are added to the new mailbox server.
- User accounts are moved from the single server to the new mailbox server.
- If you are moving all accounts from the single server, the mailbox server is stopped on the single server machine.

Configuring the Mailbox Server

The host name and zmhostname configured on the mailbox server is the same as on the name on the single server.

Make sure you know the LDAP master password as you configure it on the sever that is being added. To find the master LDAP password on the single server node, type

zmlocalconfig -s zimbra_ldap_password

Important: Before you begin make sure you have an up-to-date backup!

- 1. Follow steps 1 through 4 in Starting the Installation Process on page 22 to log on to the server as root and unpack the Zimbra software.
- 2. Type Y for each package you are installing.
 - Install zimbra-store, and zimbra-spell (optional) packages. When zimbraspell is installed, the **zimbra-apache** package also is installed.
 - If zimbra proxy is configured, install memcached.
 - The zimbra-logger package is installed only on one mailbox server. If you are moving all mailboxes to this server from the original single server, install the zimbra logger package.
 - If Archive and Discovery is installed on the single-server node, install zimbra-archiving on the new mailbox server.

Note: If SNMP is being used, type Y for the zimbra-SNMP. If SNMP is used, it is installed on every Zimbra server.

3. Type Y, and press Enter to modify the system. The selected packages are installed on the server.

The Main menu displays the default entries for the Zimbra component you are installing.

4. Type 1 and press Enter to go to the Common Configuration menu.

The mailbox server hostname is displayed. You must change the LDAP master host name and password to be the values configured on the singleserver node.

- Type 2, press Enter, and type the LDAP host name.
- Type 4, press Enter, and type the LDAP password.

After you set these values, the server immediately contacts the LDAP server. If it cannot contact the server, you cannot proceed.

- Type 6 to set the correct time zone, if your time zone is not Pacific Time.
- 5. Type **r** to return to the Main menu.
- 6. From the Main menu, type **2** to go to the Store configuration menu.
 - Type 4 and set the password for the administrator account. This should be the same password as configured on the original single-server node.

- Type the corresponding number to set the SMTP host. This is the mtaserver host name.
- Type the corresponding number if you want to change the default web server mode.
- If you are setting up IMAP/POP proxy servers, type the corresponding number to enable the servers.
- If the zimbra-proxy is used and is installed on another server, configure the following menu options
 - Configure for use with mail proxy
 - Configure to use with web proxy

Set either or both of these to TRUE if you are going to set up zimbra proxy.

- Type the corresponding menu number to install the Zimbra license file. Enter the location of the license file. For example, if you saved the license file to the tmp directory, you would type /tmp/ZCSLicense.xml. You cannot proceed without a license file.
- 7. When the mailbox server is configured, return to the Main menu and type a to apply the configuration changes. Press **Enter** to save the configuration data.
- 8. When **Save Configuration data to a file** appears, press **Enter**.
- 9. The next request asks where to save the files. To accept the default, press **Enter**. To save the files to another directory, enter the directory and then press Enter.
- 10. When The system will be modified continue? appears, type y and press Enter.

The server is modified. Installing all the components and configuring the mailbox server can take a few minutes. This includes installing SSL certificates, setting passwords, setting ports, installing skins and zimlets, setting time zone preferences, and starting the servers, among other processes.

11. When Configuration complete - press return to exit displays, press Enter.

The installation of the mailbox server is complete.

Adding Customized Features

Any customizing of themes, or Zimlets, and any signed certificates stored on the single-server must be added to the new mailbox server. See the ZCS Administrator's Guide for information about adding the customized features.

Testing the Configuration

To make sure that the new mail store server is correctly configured, create a new user on the new mailbox server and log into the account to verify that your configuration is correct. See Provisioning Accounts in the Multiple-Server Installation chapter.

Move Mailboxes

The command, **zmmboxmove**, is run to move user accounts from the mailbox server on the single-sever node to the new mailbox server.

You can set global options to exclude items from the mailbox move. See the ZCS Administrator's Guide, Managing User Accounts chapter for more information about the mailbox move feature.

Move the following types of mailboxes

- User accounts.
- Admin mailboxes. If you do not move the admin mailbox, you cannot log into the Zimbra Web Client.
- Spam and ham mailboxes.

Note: If you were using Archive and Discovery on the single server mailbox, move the archival mailboxes as well.

Move Mailboxes Using CLI zmmboxmove

- 1. To move a mailbox to a new server
 - zmmboxmove -a <email@address> --from <servername> --to <servername>
- 2. To verify that the content of the mailbox was moved successfully, go to the administration console, select the account that was moved. Click View Mail on the toolbar. When the account opens, verify that the account's content is displayed and can be opened.
- Purge the mailbox from the old server zmpurgeoldmbox -a <email@address> -s <oldservername>

Turn Off Mailbox Server on Single-Server Node

When all mailboxes have moved from the single-server node to the new mailbox server node, disable the Mailbox services on the original single-server machine.

- 1. On the original single-server node, disable the following mailbox server components:
 - mailbox. zmprov -l ms <singleserver.com> -- -zimbraServiceEnabled mailbox

- logger. zmprov -l ms <singleserver.com> -- -zimbraServiceEnabled logger
- stats. zmprov -1 ms <singleserver.com> -- -zimbraServiceEnabled stats
- spell. zmprov -1 ms <singleserver.com> -- -zimbraServiceEnabled spell
- convertd. zmprov -1 ms <singleserver.com> -- -zimbraServiceEnabled convertd If archiving was installed, disable it as well,
- zmprov -l ms <singleserver.com> -- -zimbraServiceEnabled archiving
- 2. After the mailbox services are disabled, verify that antispam, antivirus, ldap, mta, snmp, proxy, and memcached are the only services on the original single-server node.
 - zmprov -l gs <singleserver.com> | grep -i serviceenabled

6 Configuring Multi-Master Replication

Set up multi-master LDAP replication to have a copy of the LDAP database saved on each server in a group of LDAP servers identified for multi-master replication. The database can be updated by any member of the group. If one master fails, the other masters continue to update the database.

The Zimbra install program is used to configure the multi-master LDAP servers. Each master LDAP server is given an unique identifier when they are configured and zmlocalconfig is used to add the ldap server to the multi-master group.

You can also promote an existing replica to be part of the multi-master group.

Topics in this chapter include:

- "Managing Multiple Master LDAP Servers" on page 47
- "Enabling Multi-Master Replication on Initial Stand-Alone LDAP Master" on page 48
- "Installing a Secondary Master LDAP Server" on page 48
- "Promote Existing Replicas to Multi-Master LDAP Servers" on page 50
- "Monitoring Multiple LDAP Master Status" on page 50

Managing Multiple Master LDAP Servers

When you enable multi-master replication, you assign a server ID to each master server to identify them in the group. This is used to distinguish the servers in the group and to help resolve conflicts that might occur.

In addition, each server is configured to assign internal replication ID's that are unique to that specific server. Other LDAP master server can use the same replication ID, but within the server, these replication IDs must be unique.

You can run the ZCS multiple master CLI, **zmldapquery-mmr** from a specific master to see the server ID for that master and all multi-master servers that are in the group and to see the replication ID values for those masters.

On the server, enter the command as

/opt/zimbra/libexec/zmldapquery-mmr

Enabling Multi-Master Replication on Initial Stand-Alone LDAP Master

Before you can enable the multi-master replication feature, you must know the hostname of the first secondary master that is being added to the group. The hostname is entered when you enable the feature. Once you enable the multi-master replication feature, you do not need to run the command again.

When zmlocalconfig is run the first time, the master LDAP servers are configured as follows:

- The first master LDAP server ID is set to 1.
- The master LDAP server is put in a group with a secondary master that is listening to LDAP on port 389.
- The replication ID is set to 100 by default on the secondary master.
- Writes initiated from the server go to the Idap master1 by default. If Idap master1 is down, writes move to Idap master2
- 1. To enable the feature run:
 - ./libexec/zmldapenable-mmr -s 1 -m ldap://<<master2.example.com>>:389/
- 2. Once the feature is enabled use the zmlocalconfig command to add the LDAP servers to a group.

zmlocalconfig -e ldap_master_url="ldap://<<master1.example.com>>:389 ldap://
<<master2.example.com>>:389"

Installing a Secondary Master LDAP Server

The master LDAP server must be running when you install the secondary LDAP servers. You run the ZCS install program on the secondary master LDAP servers to install the LDAP package.

Passwords Required to Install the Secondary Master

Before you install a secondary master, you must know the following passwords:

- Zimbra admin LAP password.
- LDAP replication password
- NGINX LDAP password
- Amavis LDAP password
- Postfix LDAP password

To find these passwords, on the ZCS server run

zmlocalconfig -s | grep passw | grep ldap

Setting Up a Secondary Master LDAP Server

- 1. Follow steps 1 through 4 in "Starting the Installation Process" on page 22 to open a SSH session to the LDAP server, log on to the server as root, and unpack the Zimbra software.
- 1. Type Y and press Enter to install the zimbra-ldap package.
- 2. Type Y, and press Enter to modify the system. The selected packages are installed.

The Main menu shows the default entries for the LDAP server.

- 3. Type 1 to display the Common Configuration submenus.
 - a. Type 2 to change the Ldap Master host name to the name of the primary master name host (example, master1.example.com).
 - b. Type 4 to change the LDAP admin password to the Zimbra admin password of the primary master.

Type \mathbf{r} to return to the main menu.

- 4. Type **2** to display the LDAP configuration submenu.
 - a. Type 4 to change the type to mmr.
 - b. Note that 5, LDAP Server ID, is set to 2. If this is the second master, leave it unchanged. If it the third or later master, select 5 and update the server ID.

The next four steps are to change the default passwords on this server to match the passwords on the master1 LDAP server.

- c. Type **7** to change the LDAP replication password.
- d. Type 8 to change the LDAP postfix password.
- e. Type **9** to change the LDAP amavis password.
- f. Type 10 to change the LDAP NGINX password.

Type \mathbf{r} to return to the main menu.

- 5. Type a to apply the configuration changes. Press **Enter** to save the configuration data.
- 6. When Save Configuration data to a file appears, press Enter.
- 7. When **The system will be modified continue?** appears, type **y** and press Enter.

The server is modified. Installing all the components and configuring the server can take a few minutes.

- 8. When Installation complete press return to exit displays, press Enter. The installation is complete.
- 9. Update the Idap master url attribute to contain both masters, enter this new master as the first master in the list.

zmlocalconfig -e ldap_master_url="ldap://<<master2.example.com>>:389 ldap:// <<master1.example.com>>:389"

Promote Existing Replicas to Multi-Master LDAP Servers

In an existing ZCS setup where there is already a single master and multiple replicas, you can promote an existing replica to become a secondary master.

1. On the master LDAP server find the LDAP replication, Postfix, Amavis, and NGINX passwords

```
zmlocalconfig -s | grep passw | grep ldap
```

- 2. Change the LDAP passwords on the server you are promoting to be the same as the first master LDAP server.
 - LDAP replication password = zmldappasswd -l <password>
 - LDAP postfix password = zmldappasswd -p <password>
 - LDAP amavis password = zmldappasswd -a <password>
 - LDAP NGINX password = zmldappasswd -n <password>
- 3. Assign the next Server ID to this master. This example is 3 /opt/zimbra/libexec/zmldappromote-replica-mmr -s 3
- 4. Update the **Idap master url** attribute to add the master to the list.

```
zmlocalconfig -e ldap_master_url="ldap://<<master1.example.com>>:389 ldap://
<<master2.example.com>>:389 ldap://<<master3.example.com>>:389"
```

This updates the replica to be a multi-master replica, enabled with a server ID. It is automatically configured to be a paired master with the master it was previously replicating from.

Monitoring Multiple LDAP Master Status

The Monitoring LDAP Replication Status feature monitors the change sequence number (CSN) values between an LDAP master server and an LDAP replica server. The replica server is considered a shadow copy of the master server. If the servers become out of sync, the monitoring feature indicates the problem. The out of sync time period is typically five minutes, although this value is configurable.

Feature Requirement

Run the script zmreplchk located in /opt/zimbra/libexec.

Important: This script must be run on a ZCS server that has a localconfig value set for Idap url that includes all of the master servers.

Error Codes and Status Explanations

The following monitoring error codes and status explanations are given with this feature:

Error Code	Status	Description
Code 0	In Sync	The servers are currently in sync.
Code 1	No contact	No connection to the master server and the system exits.
Code 2	Stand-alone	The master server has no replica servers and is considered a standalone master server.
Code 3	Could not execute StartTLS	The replica server requires StartTLS and fails.
Code 4	Server down	The replica server is currently down.
Code 5	Unable to search	Searching the replica server for the context CSN fails.
Code 6	Xw Xd Xh Xm Xs behind	The replica server becomes out of sync. Status indicates amount of time the replica server is behind the master server in w=weeks, d=days, h=hours, m=minutes, and s=seconds.

For example, Idap002.example.com is the master server, and Idap003.example.com and Idap004.example.com are additional servers. The following screen-shot shows the additional master servers are in sync with the master server, as indicated by the Code:0 and Status: In Sync, and master server Idap005 is currently down, as indicated by Code: 4 and Status: Server down.

zimbra@ldap 002. example.com

Master: ldap://ldap003.example.com:389 Code: 0 Status: In Sync CSN:

20120528123456.123456Z#000000#001#000000

Master: ldap://ldap004.example.com:389 Code: 0 Status: In Sync CSN:

20120528123456.123456Z#000000#001#000000

Master: ldap://ldap005.example.com:389 Code: 4 Status: Server down

7 Configuring LDAP Replication

Setting up LDAP replication lets you distribute Zimbra server queries to specific replica LDAP servers. Only one master LDAP server can be set up. This server is authoritative for user information, server configuration, etc. Replica LDAP servers can be defined to improve performance and to reduce the load on the master server. All updates are made to the master server and these updates are copied to the replica servers.

The Zimbra install program is used to configure a master LDAP server and additional read-only replica LDAP servers. The master LDAP server is installed and configured first, following the normal ZCS installation options. The LDAP replica server installation is modified to point the replica server to the LDAP master host.

When the master LDAP server and the replica LDAP servers are correctly installed, the following is automatically configured:

- SSH keys are set up on each LDAP server
- Trusted authentication between the master LDAP and the LDAP replica servers is set up
- The content of the master LDAP directory is copied to the replica LDAP server. Replica LDAP servers are read-only.
- Zimbra servers are configured to query the replica LDAP server instead of the master LDAP server.

Topics in this chapter include:

- "Installing Zimbra Master LDAP Server" on page 53
- "Enable Replication on the LDAP Master" on page 54
- "Installing a Replica LDAP Server" on page 54
- "Configuring Zimbra Servers to Use LDAP Replica" on page 57
- "Uninstalling an LDAP Replica Server" on page 57
- "Monitoring LDAP Replication Status" on page 58

Installing Zimbra Master LDAP Server

You must install the master LDAP server before you can install replica LDAP servers. Refer to "Installing Zimbra LDAP Master Server" on page 24 for master LDAP server installation instructions. After the installation of the

master LDAP server has completed continue to the section titled 'Enabling Replication on the LDAP Master.

Enable Replication on the LDAP Master

On the master LDAP server, as a Zimbra user, type: /opt/zimbra/libexec/ zmldapenablereplica and press Enter. This enables replication on the LDAP Master.

Installing a Replica LDAP Server

The master LDAP server must be running when you install the replica server. You run the ZCS install program on the replica server to install the LDAP package.

Follow steps 1 through 4 in "Starting the Installation Process" on page 22 to open a SSH session to the LDAP server, log on to the server as root, and unpack the Zimbra software.

1. Type Y and press Enter to install the zimbra-ldap package. In the screen shot below, the package to be installed is emphasized.

```
Select the packages to install
Install zimbra-ldap [Y] Y
Install zimbra-logger [Y] N
Install zimbra-mta [Y] N
Install zimbra-snmp [Y] N
Install zimbra-store [Y] N
Install zimbra-spell [Y] N
Installing:
    zimbra-core
    zimbra-ldap
This system will be modified. Continue [N] Y
Configuration section
```

2. Type Y, and press Enter to modify the system. The selected packages are installed.

The Main menu shows the default entries for the LDAP replica server. To expand the menu type X and press Enter.

```
Main menu
  1) Common Configuration:
  2) zimbra-ldap:
                                              Enabled
   3) zimbra-snmp:
                                              Enabled
r) Start servers after configuration yes
  s) Save config to file
  x) Expand menu
  q) Quit
*** CONFIGURATION COMPLETE - press 'a' to apply
Select from menu, or press 'a' to apply config (? - help)
```

3. Type 1 to display the Common Configuration submenus.

```
Common Configuration:
                                       ldap-1.example.com
   1)Hostname:
                                       ldap-1.example.com
   2)Ldap master host:
                                          389
   3)Ldap port:
   4)Ldap Admin password:
                                          set
   5)Secure interprocess communications: Yes
    6) TimeZone:
                   (GMT-08.00) Pacific Time (US & Canada)
```

- 4. Type 2 to change the Ldap Master host name to the name of the Master LDAP host.
- 5. Type 3, to change the port to the same port as configured for the Master LDAP server.
- 6. Type 4 and change the password to the Master LDAP Admin user password. Type **r** to return to the main menu.
- 7. Type 2 to display the LDAP configuration submenu.

```
Ldap configuration
  1) Status:
                                                Enabled
   2) Create Domain:
                                                no
  3) Ldap Root password:
                                                set
   4) Ldap Replication password:
                                                set
   5) Ldap Postfix password:
                                                set
   6) Ldap Amavis password:
                                                set
   7) Ldap Nginx password:
                                                set
```

- Type 2 and change Create Domain: to No.
- Type 4 for LDAP replication password, enter the same password to match the value on the Master LDAP Admin user password for this local config variable.

Note: All passwords must be set to match the master Idap admin user password. To determine this value on the master LDAP, run zmlocalconfig -s Idap_replication_password

Important: If you have installed Zimbra MTA on the LDAP server, configure the Amavis and the Postfix passwords. To find these values, run zmlocalconfig -s ldap_amavis_password zmlocalconfig -s ldap_postfix_password

8. When the LDAP server is configured, type **a** to apply the configuration changes. Press **Enter** to save the configuration data.

```
Select, or press 'a' to apply config (? - help) a
Save configuration data? [Yes]
Save config in file: [/opt/zimbra/config.2843]
Saving config in /opt/zimbra/config.2843...Done
The system will be modified - continue? [No] y
Operations logged to /tmp/zmsetup.log.2843
Setting local config zimbra_server_hostname to [ldap.example.com]
.
Operations logged to /tmp/zmsetup.log.2843
Installation complete - press return to exit
```

- 9. When Save Configuration data to a file appears, press Enter.
- 10. When **The system will be modified continue?** appears, type **y** and press **Enter**.

The server is modified. Installing all the components and configuring the server can take a few minutes.

11. When Installation complete - press return to exit displays, press Enter.

The installation on the replica LDAP server is complete. The content of the master LDAP directory is copied to the replica LDAP server.

Test the Replica

 Create several user accounts, either from the admin console or on the master LDAP server. The CLI command to create these accounts is

```
zmprov ca <name@domain.com> <password>
```

If you do not have a mailbox server setup, you can create domains instead. Use this CLI command to create a domain

```
zmprov cd <domain name>
```

2. To see if the accounts were correctly copied to the replica LDAP server, on the replica LDAP server, type zmprov -1 gaa. Type zmprov gad to check all domains.

The accounts/domains created on the master LDAP server should display on the replica LDAP server.

In cases where the mailbox server is not setup, you can also use the following command for account creation.

zmprov ca <name@domain> <password> zimbraMailTransport <where_to_deliver>

Configuring Zimbra Servers to Use LDAP Replica

To use the replica LDAP server instead of the master LDAP server, you must update the Idap url value on the Zimbra servers that will guery the replica instead of the master. For each server that you want to change:

- 1. Stop the Zimbra services on the server. Type zmcontrol stop.
- Update the Idap_url value. Enter the replica LDAP server URL

zmlocalconfig -e ldap url="ldap://<replicahost> ldap://<masterhost>"

Enter more than one replica hostnames in the list typed as "ldap:// <replicahost1> ldap://<replicahost2> ldap://<masterhost>". The hosts are tried in the order listed. The master URL must always be included and is listed last.

3. Update the Idap master url value. Enter the master LDAP server URL, if not already set.

zmlocalconfig -e ldap_master_url=ldap://<masterhost>:port

Additional Steps for MTA hosts. After updating the Idap_url, rerun /opt/zimbra/ libexec/zmmtainit.

This rewrites the Postfix configuration with the updated Idap_url.

Uninstalling an LDAP Replica Server

If you do not want to use an LDAP replica server, follow these steps to disable it.

Note: Uninstalling an LDAP server is the same as disabling it on the master LDAP server.

Remove LDAP Replica from All Active Servers

- 1. On each member server, including the replica, verify the Idap_url value. Type zmlocalconfig [ldap_url]
- 2. Remove the disabled LDAP replica server URL from zmlocalconfig. Do this by modifying the Idap_url to only include enabled ZCS LDAP servers. The master LDAP server should always be at the end of the Idap url string value.

```
zmlocalconfig -e ldap_url="ldap://<replica-server-host> ldap://
<master-server-host>"
```

Disable LDAP on the Replica

To disable LDAP on the replica server,

- 1. Type **zmcontrol stop** to stop the Zimbra services on the server.
- 2. To disable LDAP service, type

```
zmprov -1 ms <zmhostname> -zimbraServiceEnabled ldap
```

Type zmcontrol start to start other current Zimbra services on the server.

Additional steps for MTA host. After updating the Idap url with zmlocalconfig, rerun /opt/zimbra/libexec/zmmtainit. This rewrites the Postfix configuration with the updated Idap_url.

Monitoring LDAP Replication Status

The Monitoring LDAP Replication Status feature monitors the change sequence number (CSN) values between an LDAP master server and an LDAP replica server. The replica server is considered a shadow copy of the master server. If the servers become out of sync, the monitoring feature indicates the problem. The out of sync time period is typically five minutes, although this value is configurable.

Feature Requirement

Run the script zmreplchk located in /opt/zimbra/libexec.

Important: This script must be run on a ZCS server that has a localconfig value set for Idap_url that includes all of the replica servers and ends with the master server.

Error Codes and Status Explanations

The following monitoring error codes and status explanations are given with this feature:

Error Code	Status	Description
Code 0	In Sync	The servers are currently in sync.
Code 1	No contact	No connection to the master server and the system exits.
Code 2	Stand-alone	The master server has no replica servers and is considered a standalone master server.

Code 3	Could not execute StartTLS	The replica server requires StartTLS and fails.
Code 4	Server down	The replica server is currently down.
Code 5	Unable to search	Searching the replica server for the context CSN fails.
Code 6	Xw Xd Xh Xm Xs behind	The replica server becomes out of sync. Status indicates amount of time the replica server is behind the master server in w=weeks, d=days, h=hours, m=minutes, and s=seconds.

For example, Idap002.example.com is the master server, and Idap003.example.com and Idap004.example.com are replicas servers. The following screen-shot shows that replica server Idap003 is in sync with the master server, as indicated by the Code:0 and Status: In Sync, and replica server Idap004 is currently down, as indicated by Code: 4 and Status: Server down.

zimbra@ldap002.example.com

Replica: ldap://ldap003.example.com:389 Code: 0 Status: In Sync Replica: ldap://ldap004.example.com:389 Code: 4 Status: Server down

If the replica server becomes out of sync with the master server, the status given indicates in a time format how far behind the master server it has become:

Replica: ldap://ldap003.example.com:389 Code: 0 Status: In Sync

Replica: ldap://ldap004.example.com:389 Code: 6 Status: 0w 0d 0h 14m 42s behind

VMware Zimbra

System Requirements for VMware Zimbra Collaboration Server 8.0

This document contains VMware Zimbra Collaboration Server system requirements and available language information for both the Network Edition and the Open Source Edition.

System Requirements

	Requirements
Servers	Evaluation and Testing
	Intel/AMD 32-bit or 64-bit CPU 1.5 GHz
	• 1 GB RAM
	5 GB free disk space for software and logs
	 Temp file space for installs and upgrades*
	Additional disk space for mail storage
	Production environments
	 Minimum - 32-bit OS with Intel/AMD 2.0 GHZ+ CPU
	Recommended - 64-bit OS
	Minimum - 2 GB RAM
	Recommend minimum - 4 GB RAM
	 Temp file space for installs and upgrades*
	 10 GB free disk space for software and logs (SATA or SCSI for performance, and RAID/Mirroring for redundancy)
	Additional disk space for mail storage
	*Temp files space- The zimbra-store requires 5GB for opt/zimbra, plus additional space for mail storage. The other nodes require 100MB.
	General Requirements
	 Firewall Configuration should be set to "No firewall".
	RAID-5 is not recommended for installations with more than 100 accounts.

Operating System Network Edition	The following operating systems are supported: • Red Hat® Enterprise Linux®, AS/ES 6 (64-bit) requires RHEL6 6.1 or later.
	SUSE Linux Enterprise Server 11, SP1 (64-bit) Note: Cluster feature is not available on SUSE Linux versions.
	Ubuntu 12.04 LTS Server Edition (64-bit)
	Ubuntu 10.04 LTS Server Edition (64-bit) Note: Cluster feature is not available on Ubuntu Linux versions.
Operating System	In addition to supporting the operating systems listed
Open Source Edition	above for the Network Edition, other operating system versions are available for the Open Source Edition. Check the Zimbra Open Source Downloads page on www.zimbra.com.
File Systems	ext3 file system for Linux deployments

Other Dependencies

Netcat (nc) is required on all operating systems using ZCS. The nc utility must be installed prior to installation or upgrading.

For SUSE, Ubuntu, and Debian systems, disable AppArmor and verify services that are running before installing ZCS.

For Red Hat Enterprise, Fedora Core and SUSE operating systems, the server must also have the following installed:

- NPTL. Native POSIX Thread Library
- Sudo. Superuser, required to delegate admins.
- **libidn**. For internationalizing domain names in applications (IDNA)
- GMP. GNU Multiple-Precision Library.

For Ubuntu 10.04 LTS and Debian 5:

- Sudo
- libidn11
- libpcre3
- libexpat1
- libgmp3c2

Note: Debian 5 and Ubuntu 10 (64-bit) require libperl5.10

Miscellaneous

- SSH client software to transfer and install the VMware Zimbra Collaboration Server software.
- Valid DNS configured with an A record and MX record
- Servers should be configured to run Network Time Protocol (NTP) on a scheduled basis

Administrator Computers

Note: Other configurations may work.

The following operating system/browser combinations are supported:

Windows XP SP3, Vista, and Windows 7 with one of the following:

- Internet Explorer 8.0 and higher (IE 8.x for XP, and 9.x and higher for Vista/Windows 7)
- The latest stable release of:
 - Firefox
 - Safari
 - Google Chrome

Mac OS X 10.5 "Leopard", 10.6 "Snow Leopard", 10.7 "Lion" with one of the following:

- The latest stable release of:
 - Firefox
 - Safari
 - Google Chrome

Linux (Red Hat, Ubuntu, Debian, Fedora, or SUSE) with one of the following:

- The latest stable release of:
 - Firefox
 - Google Chrome

End User Computers using Zimbra Web Client

Note: Other configurations may work.

Minimum

- Intel/AMD/Power PC CPU 750MHz
- 256MB RAM

Recommended

- Intel/AMD/Power PC CPU 1.5GHz
- 512MB RAM

For Zimbra Web Client - Advanced version:

The following operating system/browser combinations for the advanced Zimbra Web Client are supported:

Windows XP SP3, Vista, and Windows 7 with one of the following:

- Internet Explorer 8.0 and higher (IE 8.x for XP, and 9.x and higher for Vista/Windows 7)
- The latest stable release of:
 - Firefox
 - Safari
 - Google Chrome

Mac OS X 10.5 "Leopard", 10.6 "Snow Leopard", 10.7 "Lion" with one of the following:

- The latest stable release of:
 - Firefox
 - Safari
 - Google Chrome

Linux (Red Hat, Ubuntu, Debian, Fedora, or SUSE) with one of the following:

- The latest stable release of:
 - Firefox
 - · Google Chrome

End User Computers using **Zimbra Web Client** (continued)

For Zimbra Web Client - Standard version

The following operating system/browser combinations for the standard Zimbra Web Client are supported:

Windows XP SP3, Vista, and Windows 7 with one of the following:

- Internet Explorer 8.0 and higher (IE 8.x for XP, and 9.x and higher for Vista/Windows 7)
- The latest stable release of:
 - Firefox
 - Safari
 - Google Chrome

Mac OS X 10.5 "Leopard", 10.6 "Snow Leopard", 10.7 "Lion" with one of the following:

- The latest stable release of:
 - Firefox
 - Safari
 - · Google Chrome

Linux (Red Hat, Ubuntu, Debian, Fedora, or SUSE) with one of the following browsers:

- The latest stable release of:
 - Firefox
 - Google Chrome

End User Computers Using Other Clients	Minimum Intel/AMD/Power PC CPU 750MHz 256MB RAM
	Recommended Intel/AMD/Power PC CPU 1.5GHz 512MB RAM
	Operating system POP/IMAP combinations Windows XP SP 3, Vista SP 2, Windows 7 with Outlook Express 6, Outlook 2003, (MAPI), Thunderbird Fedora Core 4 or later with Thunderbird
	Mac OS X 10.4 or later with Apple Mail
	Accessibility and Screen Readers Zimbra recommends that customers requiring use of screen readers for accessibility leverage the use of the Standard Zimbra Web Client (HTML).
	Zimbra continues to invest in improving the accessibility of this interface.
	**Recommendation - If users are presently using IE 6, Zimbra strongly recommends that they upgrade to the latest version of Internet Explorer for optimal performance with ZWC.
Monitor	Display minimum resolution 1024 x 768
Internet Connection Speed	128 kbps or higher

Available Languages

This section includes information about available languages, including End User Translations and Administrator Translations.

End User Translations

Component	Category	Languages
Zimbra Web Client	Application/UI	Arabic, Chinese (Simplified PRC and Traditional HK), Danish, Dutch, English (AU, UK, US), French, German, Hindi, Hungarian, Italian, Japanese, Korean, Polish, Portuguese (Brazil), Romanian, Russian, Spanish, Swedish, Thai, Turkish, Ukrainian
Zimbra Web Client - Online Help (HTML)	Feature Documentation	Chinese (Simplified PRC and Traditional HK), Dutch, English, French, German, Italian, Japanese, Portuguese (Brazil), Russian, Spanish
Zimbra Web Client - End User Guide (PDF)	Feature Documentation	English
Zimbra Connector for Microsoft Outlook	Installer + Application/UI	Arabic, Chinese (Simplified PRC and Traditional HK), Danish, Dutch, English (AU, UK, US), French, German, Hindi, Hungarian, Italian, Japanese, Korean, Polish, Portuguese (Brazil), Romanian, Russian, Spanish, Swedish, Thai, Turkish, Ukrainian
Zimbra Connector for Microsoft Outlook - End User Guide (PDF)	Feature Documentation	English

Administrator Translations

Component	Category	Languages
Zimbra Admin Console	Application	Arabic, Chinese (Simplified PRC and Traditional HK), Danish, Dutch, English (AU, UK, US), French, German, Hindi, Hungarian, Italian, Japanese, Korean, Polish, Portuguese (Brazil), Romanian, Russian, Spanish, Swedish, Turkish, Ukrainian
Zimbra Admin Console Online Help (HTML)	Feature Documentation	English
"Documentation" Install + Upgrade / Admin Manual / Migration / Import / Release Notes / System Requirements	Guides	English
Zimbra Connector for Microsoft Outlook - Admin Guide (PDF)	Install + Configuration Guide	English

Copyright © 2012 Zimbra and VMware, Inc. All rights reserved.

VMware Zimbra Collaboration Server 8.0 August 2012

Index

Symbols	menu - main, description 10
administration console	menu configuration 10
logging on 38	migrate mailbox 40
URL 38	MTA Auth host 35
audience 5	MTA server
certificate authority 38	configuration 17
class of service 39	install 33
common configuration 10	multiple-server installation 21
configuration	MX record 20
common 10	operating system configurations 19
menu 10	overview of Zimbra packages 7
operating system 19 options 8	passwords, amavis and postfix 56
configuration, examples 8	port configurations, default 14
contact information 6	post installation tasks 38
disable MySQL 23	relay host 20
DNS 20	server configuration
download software 9	verify 38
examples	Zimbra LDAP 11
configuration 8	SNMP, install 36
feedback 6	software agreement 23
firewall, Red Hat 20	spam training filter 13
forums, join Zimbra 6	spell checker, install 15
import user mailboxes 40	support
information	contact Zimbra 6 support information 6
contact 6	system requirements 19
support 6	test, LDAP replica 56
installation 22	uninstall ZCS 40
prerequisite software 23	uninstall ZCS for Mac server 40
process 22	URL, administration console 38
LDAP replication	virtual hosting 17
configuring 57 disable 58	Zimbra Collaboration Server, uninstall 40
enable 54	Zimbra packages 7
install 48, 54	zmcontrol status 38
monitor status 50, 58	Zincontrol status 30
password 55	
test 56 uninstall 57	
LDAP server	
configuration 12	
install 24	
installing 53	
logger package 15	
mailbox server	
configuration 13	
install 27 mailbox server, install 27	
main menu options 10	
main menu opuons 10	