Create PersistentVolumes (PV) and PersistentVolumeClaims (PVC) for Data Storage

Table of Contents

- 1. Introduction
- 2. Problem Statement
- 3. Prerequisites
- 4. Setup Instructions
 - Step 1: Create a PersistentVolume (PV)
 - Step 2: Create a PersistentVolumeClaim (PVC)
 - Step 3: Use the PVC in a Pod
- 5. References

Introduction

In Kubernetes, **PersistentVolumes (PV)** and **PersistentVolumeClaims (PVC)** provide a way to manage storage resources for your applications. Persistent storage allows data to be retained even if the pod is terminated or restarted. This is critical for stateful applications like databases or any app that requires data persistence across pod restarts.

- **PersistentVolume (PV)**: A storage resource in the cluster that can be provisioned dynamically or manually by an administrator. It abstracts the underlying storage from the application.
- **PersistentVolumeClaim (PVC)**: A request by a user for storage. PVCs are used by pods to request specific storage resources from available PVs.

In this lab, we will create a PersistentVolume and a PersistentVolumeClaim, and then use the PVC in a Kubernetes pod.

Problem Statement

Many applications require persistent data storage that survives pod restarts and scaling events. To solve this, Kubernetes provides PersistentVolumes (PVs) and PersistentVolumeClaims (PVCs) as a means to allocate and consume storage resources within the cluster. This lab will guide you through the steps required to configure persistent storage for an NGINX application.

Prerequisites

Completion of all previous lab guides (up to Lab Guide-04) is required before proceeding with Lab Guide-05.

- A running Kubernetes cluster on Minikube.
- kubect1 installed and configured to interact with your Minikube cluster.

Step 1: Create a PersistentVolume (PV)

A **PersistentVolume** represents a piece of storage in the cluster. This storage can be provided by cloud services, local disk, NFS, or other means.

1. Create a PV YAML File

Create a file named pv.yaml with the following content:

```
apiVersion: v1
kind: PersistentVolume
metadata:
   name: nginx-pv
spec:
   capacity:
    storage: 1Gi
   accessModes:
    - ReadWriteOnce
hostPath:
    path: "/mnt/data"
```

Key points:

- o capacity: The size of the persistent storage (1Gi).
- accessModes: Specifies how the storage can be accessed. ReadWriteOnce means it can be mounted as read-write by a single node.
- **hostPath**: The path to the storage location on the host machine. For this lab, we use a directory on the Minikube node.

2. Apply the PV

Run the following command to create the PersistentVolume:

```
kubectl apply -f pv.yaml
```

3. Verify the PersistentVolume

Check the status of the PV to ensure it's available:

Step 2: Create a PersistentVolumeClaim (PVC)

A **PersistentVolumeClaim** is a request for storage by a user. The PVC must match the properties of the PV, such as storage size and access modes.

1. Create a PVC YAML File

Create a file named pvc.yaml with the following content:

```
apiVersion: v1
kind: PersistentVolumeClaim
metadata:
   name: nginx-pvc
spec:
   accessModes:
   - ReadWriteOnce
   resources:
    requests:
     storage: 1Gi
```

Key points:

- o accessModes: Matches the access mode of the PV (ReadWriteOnce).
- resources.requests.storage: Requests 1Gi of storage.

2. Apply the PVC

Run the following command to create the PersistentVolumeClaim:

```
kubectl apply -f pvc.yaml
```

3. Verify the PVC

Check that the PVC is successfully bound to the PV:

```
kubectl get pvc

PS C:\Users\Administrator> kubectl apply -f pvc.yaml
persistentvolumeclaim/nginx-pvc created
PS C:\Users\Administrator> kubectl get pvc
NAME STATUS VOLUME CAPACITY ACCESS MODES STORAGECLASS VOLUMEATTRIBUTESCLASS AGE
```

The status should show Bound, meaning the PVC has successfully claimed the PV.

Step 3: Use the PVC in a Pod

Now that the PVC is created and bound to the PV, we can use it in a pod to provide persistent storage for the application.

1. Create the Pod YAML File

Create a file named nginx-pv-pod.yaml with the following content:

```
apiVersion: v1
kind: Pod
metadata:
  name: nginx-pv-pod
spec:
  containers:
  - name: nginx
    image: nginx:latest
    ports:
    - containerPort: 80
    volumeMounts:
    - mountPath: "/usr/share/nginx/html"
      name: nginx-storage
  volumes:
  - name: nginx-storage
    persistentVolumeClaim:
      claimName: nginx-pvc
```

Key points:

- **volumeMounts**: The PVC is mounted to /usr/share/nginx/html in the container, which is the default directory for serving content in NGINX.
- **volumes**: The volume is backed by the PersistentVolumeClaim (nginx-pvc).

2. Apply the Pod Configuration

Run the following command to create the pod:

```
kubectl apply -f nginx-pv-pod.yaml
```

3. Verify the Pod

Check the status of the pod to ensure it's running:

```
kubectl get pods
```

```
PS C:\Users\Administrator> kubectl apply -f nginx-pv-pod.yaml
pod/nginx-pv-pod created
PS C:\Users\Administrator> kubectl get pods
NAME
               READY
                       STATUS
                                 RESTARTS
                                             AGE
               1/1
nginx-pod
                       Running
                                 0
                                             43m
nginx-pv-pod
               1/1
                       Running
                                 0
                                             18s
```

4. Test the Persistent Storage

You can now write files to the /mnt/data directory on the Minikube node, and they will persist even if the pod is deleted or restarted.

To test, exec into the pod and create a file:

```
kubectl exec -it nginx-pv-pod -- /bin/bash
echo "Hello, Kubernetes!" > /usr/share/nginx/html/index.html
```

```
PS C:\Users\Administrator> kubectl exec -it nginx-pv-pod -- /bin/bash root@nginx-pv-pod:/# echo "Hello, Kubernetes!" > /usr/share/nginx/html/index.html root@nginx-pv-pod:/# exit exit
```

Now, access the NGINX pod using port-forwarding to see the content you just created:

```
kubectl port-forward nginx-pv-pod 8085:80
```

```
PS C:\Users\Administrator> kubectl port-forward nginx-pv-pod 8085:80
Forwarding from 127.0.0.1:8085 -> 80
Forwarding from [::1]:8085 -> 80
Handling connection for 8085
Handling connection for 8085
```

Open your browser and navigate to http://localhost:8085. You should see "Hello, Kubernetes!" displayed.



Hello, Kubernetes!

References

- Kubernetes Persistent Volumes Documentation
- Kubernetes Persistent Volume Claims Documentation