HDF5 User's Guide

Release 1.8.3 May, 2009

The HDF Group (THG)

The *HDF5 User's Guide* has not been fully updated for the Release 1.8.x series. However, all of the principles and programming models described still apply. For further information, see "Using This Guide with HDF5 Release 1.8.x" on the page immediately after the table of contents.

(Date printed: May 2000)

Copyright Notice and License Terms for HDF5 (Hierarchical Data Format 5) Software Library and Utilities

HDF5 (Hierarchical Data Format 5) Software Library and Utilities Copyright 2006-2009 by The HDF Group.

NCSA HDF5 (Hierarchical Data Format 5) Software Library and Utilities Copyright 1998-2006 by the Board of Trustees of the University of Illinois.

All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted for any purpose (including commercial purposes) provided that the following conditions are met:

- 1. Redistributions of source code must retain the above copyright notice, this list of conditions, and the following disclaimer.
- 2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions, and the following disclaimer in the documentation and/or materials provided with the distribution.
- 3. In addition, redistributions of modified forms of the source or binary code must carry prominent notices stating that the original code was changed and the date of the change.
- 4. All publications or advertising materials mentioning features or use of this software are asked, but not required, to acknowledge that it was developed by The HDF Group and by the National Center for Supercomputing Applications at the University of Illinois at Urbana-Champaign and credit the contributors.
- 5. Neither the name of The HDF Group, the name of the University, nor the name of any Contributor may be used to endorse or promote products derived from this software without specific prior written permission from The HDF Group, the University, or the Contributor, respectively.

DISCLAIMER: THIS SOFTWARE IS PROVIDED BY THE HDF GROUP AND THE CONTRIBUTORS "AS IS" WITH NO WARRANTY OF ANY KIND, EITHER EXPRESSED OR IMPLIED. In no event shall The HDF Group or the Contributors be liable for any damages suffered by the users arising out of the use of this software, even if advised of the possibility of such damage.

Contributors: National Center for Supercomputing Applications (NCSA) at the University of Illinois, Fortner Software, Unidata Program Center (netCDF), The Independent JPEG Group (JPEG), Jean-loup Gailly and Mark Adler (gzip), and Digital Equipment Corporation (DEC).

Portions of HDF5 were developed with support from the University of California, Lawrence Livermore National Laboratory (UC LLNL). The following statement applies to those portions of the product and must be retained in any redistribution of source code, binaries, documentation, and/or accompanying materials:

This work was partially produced at the University of California, Lawrence Livermore National Laboratory (UC LLNL) under contract no. W-7405-ENG-48 (Contract 48) between the U.S. Department of Energy (DOE) and The Regents of the University of California (University) for the operation of UC LLNL.

DISCLAIMER: This work was prepared as an account of work sponsored by an agency of the United States Government. Neither the United States Government nor the University of California nor any of their employees, makes any warranty, express or implied, or assumes any liability or responsibility for the accuracy, completeness, or usefulness of any information, apparatus, product, or process disclosed, or represents that its use would not infringe privately- owned rights. Reference herein to any specific commercial products, process, or service by trade name, trademark, manufacturer, or otherwise, does not necessarily constitute or imply its endorsement, recommendation, or favoring by the United States Government or the University of California. The views and opinions of authors expressed herein do not necessarily state or reflect those of the United States Government or the University of California, and shall not be used for advertising or product endorsement purposes.

Table of Contents

Part I: The Broad View	1
Chapter 1: The HDF5 Data Model and File Structure	3
Chapter 2: The HDF5 Library and Programming Model	
Part II: Using HDF5 - The Specifics	41
Chapter 3: The HDF5 File	43
Chapter 4: HDF5 Groups	65
Chapter 5: HDF5 Datasets	95
Chapter 6: HDF5 Datatypes	153
Chapter 7: HDF5 Dataspaces and Partial I/O	231
Chapter 8: HDF5 Attributes	271
Chapter 9: HDF5 Error Handling	281
Part III: Special Topics	293
Chapter 10: HDF5 Special Topics	295
Metadata Caching in HDF5	295
Glossary	313

Using This Guide with HDF5 Release 1.8.x

Several sections describing new features introduced in the HDF5 Release 1.8.x series have been added to this *HDF5 User's Guide*:

- N-bit and scale/offset filters, in the chapter "HDF5 Datasets"
- New Error API functions, H5E, in the chapter "HDF5 Error Handling"
- Metadata caching, in the chapter "Special Topics"

Other work to bring the *Guide* up to date with the HDF5 Release 1.8.x series remains to be done. Readers should keep the following things in mind:

- Principles and models described in the *Guide* remain applicable to the 1.8.x series.
- The function summaries in several chapters are incomplete for the 1.8.x series. Refer to the *HDF5 Reference Manual* for complete lists.
- Code examples use function syntax from the 1.6.x release series. See the note below regarding the use of 1.6.x syntax with a 1.8.x version of the HDF5 Library.

Using 1.6.x syntax with the 1.8.x library

HDF5 Release 1.8.x includes an API compatibility feature that enables codes written with 1.6.x function syntax to be compiled against and linked with an HDF5 Release 1.8.x Library.

When working with an installed version of the HDF5 Library that has been built with default settings, use the h5cc script and the H5_USE_16_API flag to compile and link your C program as follows:

```
h5cc <other_instructions> -D H5_USE_16_API . . .
```

A comparable script, h5fc, is provided for for Fortran90 programs. h5cc and h5fc are described in the "Tools" section of the HDF5 Reference Manual.

For further details or alternate approaches, see "API Compatibility Macros in HDF5."

Part I

The Broad View

Chapter 1 The HDF5 Data Model and File Structure

1. Introduction

1.1. Introduction and Definitions

The Hierarchical Data Format (HDF) implements a model for managing and storing data. The model includes an abstract data model and an abstract storage model (the data format), and libraries to implement the abstract model and to map the storage model to different storage mechanisms. The HDF5 library provides a programming interface to a concrete implementation of the abstract models. The library also implements a model of data transfer, i.e., efficient movement of data from one stored representation to another stored representation. Figure 1 illustrates the relationships between the models and implementations. This chapter explains these models in detail.




Figure 1

The *Abstract Data Model* is a conceptual model of data, data types, and data organization. The Abstract Data Model is independent of storage medium or programming environment. The *Storage Model* is a standard representation for the objects of the *Abstract Data Model*. The *HDF5 File Format Specification* defines the *Storage Model*.

The *Programming Model* is a model of the computing environment, which includes many platforms, from small single systems to large multiprocessors and clusters. The *Programming Model* manipulates (instantiates, populates, and retrieves) objects from the *Abstract Data Model*.

The *Library* is the concrete implementation of the *Programming Model*. The *Library* exports the HDF5 APIs as its interface. In addition to implementing the objects of the *Abstract Data Model*, the *Library* manages data transfers from one stored form to another (e.g., read from disk to memory, write from memory to disk, etc.).

The *Stored Data* is the concrete implementation of the *Storage Model*. The *Storage Model* is mapped to several storage mechanisms, including single disk files, multiple files (family of files), and memory representations.

The HDF5 Library is a C module that implements the *Programming Model* and *Abstract Data Model*. The HDF5 Library calls the Operating System or other Storage Management software (e.g., the MPI/IO Library) to store and retrieve persistent data. The HDF5 Library may also link to other software, such as filters for compression. The HDF5 Library is linked to an application program, which may be written in C, C++, Fortran 90, or Java. The application program implements problem specific algorithms and data structures, and calls the HDF5 Library to store and retrieve data. Figure 2 shows the dependencies of these modules.




Figure 2

It is important to realize that each of the software components manages data using models and data structures that are appropriate to the component. When data is passed between layers-during storage or retrieval-it is transformed from one representation to another. Figure 3 suggests some of the kinds of data structures used in the different layers.

The *Application Program* uses data structures that represent the problem and algorithms, including variables, tables, arrays, and meshes, among other data structures. Obviously, an application might have quite a few different kinds of data structures, and different numbers and sizes of objects, depending on its design and function.

The HDF5 *Library* implements the objects of the HDF5 *Abstract Data Model*. These include Groups, Datasets, and Attributes and other objects as defined in this Chapter. The Application Program maps the application data structures to a hierarchy of HDF5 objects. Each application will create a mapping best suited to its purposes.

The objects of the HDF5 *Abstract Data Model* are mapped to the objects of the HDF5 *Storage Model*, and stored in a storage medium. The stored objects include header blocks, free lists, data blocks, B-trees, and other objects. Each Group, Dataset, etc. is stored as one or more header and data blocks, organized as defined in the *HDF5 File Format Specification*. The HDF5 *Library* can also use other libraries and modules, such as compression.




Figure 3

The important point to note is that there is not necessarily any simple correspondence between the objects of the *Application Program*, the *Abstract Data Model*, and those of the *Format Specification*. The organization of the data of *Application Program*, and how it is mapped to the HDF5 *Abstract Data Model* is up to the application developer. The Application Program only needs to deal with the *Library* and the *Abstract Data Model*. Most applications need not consider any details of the *HDF5 File Format Specification*, or the details of how objects of *Abstract Data Model* are translated to and from storage.

2. The Abstract Data Model

2.1. Purpose and Summary of the Abstract Data Model

The Abstract Data Model (ADM) defines concepts for defining and describing complex data stored in files. The HDF5 ADM is a very general model which is designed to conceptually cover many specific models of data. Many different kinds of data can be mapped to objects of the HDF5 ADM, and therefore stored and retrieved using HDF5. The ADM is not, however, a model of any particular problem or application domain. Users need to map their data to the concepts of the ADM.

The key concepts include:

- File a contiguous string of bytes in a computer store (memory, disk, etc.). The bytes represent zero or more objects of the model.
- *Group* a collection of objects (including groups).
- Dataset a multidimensional array of Data Elements, with Attributes and other metadata.
- Datatype a description of a specific class of data element, including its storage layout as a pattern of bits.
- Dataspace a description of the dimensions of a multidimensional array.
- Attribute a named data value associated with a group, dataset, or named datatype
- *Property List* a collection of parameters controlling options in the library. Some properties are permanently stored as part of the object; others are transient and apply to a specific access. Each class of property list has specific properties.

2.2. Definitions

File

Abstractly, an HDF5 File is a container for an organized collection of objects. The objects are Groups and Datasets and other objects as defined below. The objects are organized as a rooted, directed graph. Every HDF5 file has at least one object, the root group (Figure 4). All objects are members of the root group or descendents of the root group.




Figure 4

HDF5 objects have a unique identity *within a single HDF5 file*, and can be accessed only by its names within the hierarchy of the file. HDF5 objects in different files do not necessarily have unique identities, and it is not possible to access a permanent HDF5 object except through a file. See the section "The Structure of an HDF5 File" below for an explanation of the structure of the HDF5 file.

When the file is created, the *File Creation Properties* specify settings for the file. File Creation Properties include version information and parameters of global data structures. When the file is opened, the *File Access Properties* specify settings for the current access to the file. File Access Properties include parameters for storage drivers and parameters for caching and garbage collection. The *File Creation Properties* are permanent for the life of the file, the *File Access Properties* can be changed by closing and reopening the file.

An HDF5 file can be "mounted" as part of another HDF5 file. This is analogous to Unix File System mounts. The root of the mounted file is attached to a Group in the mounting file, and all the contents can be accessed as if the mounted file were part of the mounting file.

Group

An HDF5 *Group* is analogous to a file system directory. Abstractly, a Group contains zero or more objects, and every object must be a member of at least one Group. (The root Group is a special case; it may not be a member of any group.)

Group membership is actually implemented via *Link* objects (Figure 5). A Link object is owned by a Group and points to a *Named Object*. Each Link has a *name*, and each link points to exactly one object. Each Named Object has at least one and possibly many Links to it.




Figure 5

There are three classes of Named Objects: *Group*, *Dataset*, and *Named Datatype* (Figure 6). Each of these objects is the member of at least one Group, which means there is at least one *Link* to it.




Figure 6

An HDF5 *Dataset* is a multidimensional (rectangular) array of *Data Elements* (Figure 7). The shape of the array (number of dimensions, size of each dimension) is described by the *Dataspace* object (see below).

A Data Element is a single unit of data which may be a number, a character, an array of numbers or characters, or a record of heterogeneous data elements. A Data Element is a set of bits, the layout of the bits is described by the *Datatype* (see below).

The *Dataspace* and *Datatype* are set when the *Dataset* is created, they can not be changed for the life of the Dataset. The *Dataset Creation Properties* are set when the Dataset is created. The Dataset Creation Properties include the fill value and storage properties such as chunking and compression. These properties cannot be changed after the Dataset is created.

The Dataset object manages the storage and access to the Data. While the Data is conceptually a contiguous rectangular array, it is physically stored and transferred in different ways depending on the storage properties and the storage mechanism used. The actual storage may be a set of chunks, which may be compressed, and the access may be through different storage mechanisms and caches. The Dataset maps between the conceptual array of elements and the actual stored data.




Figure 7

Dataspace

The HDF5 *Dataspace* describes the layout of the elements of a multidimensional array. Conceptually, the array is a hyper-rectangle with one to 32 dimensions. HDF5 Dataspaces can be extendable. Therefore, each dimension has a current and maximum size, and the maximum may be unlimited. The *Dataspace* describes this hyper-rectangle: it is a list of dimensions, with the current and maximum (or unlimited) size (Figure 8).

Dataspace
rank:int
current_size:hsize_t[rank]
maximum_size:hsize_t[rank]

Figure 8

Dataspace objects are also used to describe hyperslab selections from a dataset. Any subset of the elements of a Dastaset can be selected for *read* or *write* by specifying a set of hyperslabs. A non-rectangular region can be selected by the union of several (rectangular) Dataspaces.

Datatype

The HDF5 *Datatype* object describes the layout of a single data element. A data element is a single element of the array; it may be a single number, a character, an array of numbers or carriers, or other data. The Datatype object describes the storage layout of this data.

Data types are categorized into 11 classes of Datatype. Each class is interpreted according to a set of rules and has a specific set of properties to describe its storage. For instance, floating point numbers have exponent position and sizes, which are interpreted according to appropriate standards for number representation. Thus, the Dataype Class tells what the element means, and the Datatype describes how it is stored.

Figure 9 shows the classification of data types. Atomic Datatypes are indivisible, each may be a single object; a number, a string, or some other objects. The Composite Datatypes are composed of multiple elements of atomic Datatypes. In addition to the standard types, users can define additional Datatypes, such as a 24-bit integer, or a 16-bit float.

A Dataset or Attribute has a single Datatype object associated with it (Figure 7). The Datatype object may be used in the definition of several objects, but by default, a copy of the Datatype object will be private to the Dataset.

Optionally, a Datatype object can be stored in the HDF5 file. The Datatype is linked into a Group, and therefore given a name. A *Named Datatype* can be opened and used in any way that a Datatype object can be used.

The details of Datatypes, their properties, and how they are used are explained in the datatypes chapter, "HDF5 Datatypes."




Figure 9

Attribute

Any HDF5 Named Data Object (Group, Dataset, or Named Datatype) may have zero or more user defined *Attributes*. Attributes are used to document the object. The Attributes of an object are stored with the object. An HDF5 Attribute has a *name* and data. The data is described analogously to the Dataset: the Dataspace defines the layout of an array of Data Elements, and the Datatype defines the storage layout and interpretation of the elements (Figure 10).




Figure 10

In fact, a Attribute is very similar to a Dataset with the following limitations:

- An attribute can only be accessed via the object, attribute names are significant only within the object. Attributes cannot be shared.
- For practical reasons, an Attribute should be a small object, no more than 1000 bytes.
- The data of an Attribute must be read or written in a single access, selection is not allowed.
- Attributes do not have Attributes.

Note that the value of an Attribute can be an *Object Reference*. A shared Attribute, or an Attribute that is a large array can be implemented as a Reference to a Dataset.

The name, Dataspace and Datatype of the Attribute are specified when it is created, and can not be changed over the life of the Attribute. The Attribute can be opened by name, by index, or by iterating through all the attributes of the object.

Property List

HDF5 has a generic Property List object, which is a collection of (*name*, *value*) pairs. Each class of Property List has a specific set of Properties. Each Property has an implicit name, an HDF5 Datatype, and a value (Figure 11). A Property List object is created and used similar to the other objects of the HDF5 library.

Property Lists are attached to the object in the library, they can be used by any part of the library. Some properties are permanent (e.g., the chunking strategy for a dataset), others are transient (e.g., buffer sizes for data transfer). A common use of a Property List is to pass parameters from the calling program to a VFL driver or a module of the pipeline.

Property Lists are conceptually similar to Attributes. Property Lists are information relevant to the behavior of the library, while Attributes are relevant to the user's data and application.




Figure 11

Properties are used to control optional behavior for file creation, file access, dataset creation, dataset transfer (read, write), and file mounting (Table 1). Details of the different Property Lists are explained in the relevant sections of this document.

Table 1.

Property List Class	Used	Examples
H5P_FILE_CREATE	Properties for file creation.	Set size of user block.
H5P_FILE_ACCESS	Properties for file access.	Set parameters for VFL driver, e.g., MPI I/O
H5P_DATASET_CREATE	Properties for dataset creation.	Set chunking, compression, fill value.
H5P_DATASET_XFER	Properties for raw data transfer (i.e., read and write).	Tune buffer sizes, memory management.
H5P_MOUNT	Properties for file mounting.	

3. The HDF5 Storage Model

3.1. The Abstract Storage Model: the HDF5 Format Specification

The *HDF5 Format Specification* defines how the HDF5 objects and data are mapped to a *linear address space*. The address space is assumed to be a contiguous array of bytes, stored on some random access medium. The HDF5 Format defines the standard for how the objects of the HDF5 Abstract Data Model are mapped to the linear addresses. The stored representation is self-describing in the sense that the Format defines all the information necessary to read and reconstruct the original objects of the ADM.

The HDF5 Format Specification is organized in three parts:

- 1. Level 0: File Signature and Super Block
- 2. Level 1: File Infrastructure
 - a. Level 1A: B-link Trees and B-tree nodes.
 - b. Level 1B: Group
 - c. Level 1C: Group Entry
 - d. Level 1D: Local Heaps
 - e. Level 1E: Global Heap
 - f. Level 1F: Free-space index
- 3. Level 2: Data Object
 - a. Level 2A: Data Object Headers
 - b. Level 2B: Shared Data Object Headers
 - c. Level 2C: Data Object Data Storage

The **Level 0** specification defines the header block for the file, which has a signature, version information, key parameters of the file layout (such as which VFL file drivers are needed) and pointers to the rest of the file. **Level 1** defines the data structures used throughout the file: the B-trees, heaps, and groups. **Level 2** defines the data structure for storing the data objects and data. In all cases, the data structures are completely specified so that every bit in the file can be faithfully interpreted.

It is important to realize that the structures defined in the HDF5 File Format are not the same as the Abstract Data Model: the object headers, heaps, and B-trees of the HDF5 File Specification are not represented in the Abstract Data Model. The HDF5 Format defines a number of objects for managing the storage, including header blocks, B-trees, and heaps. The *HDF5 Format Specification* defines how the Abstract objects (Groups, Datasets, etc.) are represented as headers, B-tree blocks, etc..

The HDF5 Library implements operations to write HDF5 objects to the linear format and to read from the linear format to create HDF5 objects. It is important to realize that a single HDF5 object, such as a *Dataset*, is usually stored as several objects (a header, one or more blocks for data, etc.), which may well not be contiguous on disk.

3.2. Concrete Storage Model

The HDF5 Format defines an abstract linear address space. This can be implemented in different storage media, such as a single file, multiple files, or memory. The HDF5 Library defines an open interface, called the *Virtual File Layer* (VFL), that allows different concrete storage models to be selected.

The Virtual File Layer defines an abstract model and API for random access storage, and an API to plug in alternative VFL driver modules. The model defines the operations that the VFL driver must and may support, and the plug-in API enables the HDF5 Library to recognize the driver and pass it control and data.

The HDF5 Library defines six VFL drivers: serial unbuffered, serial buffered, memory, MPI/IO, family of files, and split files (Figure 12, Table 2). Other drivers may also be available, such as a socket stream driver or Globus driver, and new drivers can be added.




Figure 12. Conceptual hierarchy of VFL drivers.

Each driver isolates the details of reading and writing storage, so the rest of the HDF5 Library and user program can be almost the same for different storage methods. The exception to this rule is that some VFL drivers need information from the calling application, passed using property lists. For example, the MPI/IO driver requires certain control information that must be provided by the application.

Table 2

Driver Description

Unbuffered Posix I/O (H5FD_SEC2) Uses Posix file-system functions like read and

write to perform I/O to a single file. Default

This driver uses functions from the Unix/Posix Buffered single file (H5FD_STDIO) `stdio.h' to perform buffered I/O to a single file.

This driver performs I/O directly to memory. The Memory (H5FD_CORE)

I/O is memory to memory operations, but the

'file' is not persistent.

This driver implements parallel file IO using MPI MPI/IO (H5FD_MPIIO)

and MPI-IO

Family of files (H5FD_FAMILY) The address space is partitioned into pieces and

sent to separate storage locations using an underlying driver of the user's choice.

Split File (H5FD_SPLIT) The format address space is split into meta data and raw data and each is mapped onto separate

storage using underlying drivers of the user's

choice.


Stream This driver reads and writes the bytes to a Unix Contributed style socket, which can be a network channel.

This is an example of a user defined VFL driver.

4. The Structure of an HDF5 File

4.1. Overall File Structure

An HDF5 file is organized as a rooted, directed graph. The Named Data Objects are the nodes of the graph, and the links are the directed arcs. Each arc of the graph has a name, the root group has the name "/". Objects are created and then inserted into the graph with the link operation, which creates a named link from a Group to the object. For example, Figure 38 illustrates the structure of an HDF5 file when one dataset is created. An object can be the target of more than one link.



The names on the links must be unique within each Group, but there may be many links with the same name in different groups. These are unambiguous, because some ancestor must have a different name, or else they are the same object. The graph is navigated with path names, analogous to Unix file systems. An object can be opened with a full path starting at the root group, or with a relative path and a starting node (Group). Note that all paths are relative to a single HDF5 File. In this sense, an HDF5 File is analogous to a single Unix File System. ³

It is important to note that, just like the Unix file system, the Objects do not have *names*, the names are associated with *paths*. An object has a unique (within the file) *object id*, but a single object can have many *names* because there are many paths to the same object. An object can be renamed (moved to another Group) by adding and deleting links. In this case, the object itself never moves. For that matter, membership in a Group has no implication for the physical location of the stored object.

Deleting a link to an object does not necessarily delete the object. The object remains available as long as there is at least one link to it. After all links to an object are deleted, it can no longer be opened, although the storage may or may not be reclaimed. ⁴

It is important to realize that the linking mechanism can be used to construct very complex graphs of objects. For example, it is possible for object to be shared between several groups and even to have more than one name in the same group. It is also possible for a group to be a member of itself, or create other "cycles" in the graph, such as a case where a child is the parent of one of its own ancestors.

HDF5 also has *Soft Links* similar to Unix soft links. A *Soft Link* is an object that contains a name and a path name for the target object. The Soft Link can be followed to open the target of the link, just like a regular (hard) link. Unlike hard Links, the target of a Soft Link has no count of the Soft Link to it. The reference count of an object is the number of hard Links (which must be >= 1). A second difference is that the hard link cannot be created if the target object does not exist, and always points to the same object. A Soft Link can be created with any path name, whether or not the object exists. Therefore, it may or may not be possible to follow a Soft Link, or the target object may change from one access to another access of the same Soft Link.

4.2. HDF5 Path Names and Navigation

The structure of the file constitutes the name space for the objects in the file. A path name is a string of components separated by '/'. Each component is the name of a (hard or soft) link, or the special characters "." (meaning current group). Link names (components) can be any string of ASCII characters not containing '/' (except the string ".", which is reserved). However, users are advised to avoid the use of punctuation and non-printing characters, because they may create problems for other software. Figure 39 gives a BNF grammar for HDF5 *path names*.

```
PathName ::= AbsolutePathName | RelativePathName
Separator ::= "/" ["/"]*
AbsolutePathName ::= Separator [ RelativePathName ]
RelativePathName ::= Component [ Separator RelativePathName ]*
Component ::= "." | Name
Name ::= Character+ - {"."}
Character ::= {c: c in {{ legal ASCII characters } - {'/'}}}
```

Figure 39

An object can always be addressed by a *full or absolute path*, i.e., starting at the root group. As already noted, a given object can have more than one full path name. An object can also be addressed by a relative path, i.e., a group plus a path starting at the group.

The structure of an HDF5 file is "self-describing", in that it is possible to *navigate* the file to discover all the objects in the file. Basically, the structure is traversed as a graph, starting at one node, and recursively visiting the nodes of the graph.

The members of a Group can be discovered with the H5Giterate function, and a description of the object can be retrieved with the H5Gget_obj_info function. In this way, all the members of a given group can be determined, and each can be opened to retrieve a description, or the data and attributes of the object.

4.3. Examples of HDF5 File Structures


Figure 40 shows some examples of the structure of a file with three groups and one dataset. Figure 40a shows the structure of a file with three groups, the root with two members. Figure 40b shows a dataset created in "/group1". Figure 40c shows the structure after the dataset is linked (with H5Glink) to "/group2" with the name "dset2". Note that there is only one copy of the dataset, it has two different links to it and can be accessed by two different paths: "/group1/dset1" and "/group2/dset2".


Figure 40d shows that one of the two links to the dataset can be deleted (with H5Gunlink()). In this case, the link from "/group1" is removed. The dataset is not deleted, it is still in the file but can only be accessed as "/group1/dset2".

a) Three groups; two are members of the root group,

/group1 and /group2

b) Create a dataset in /group1: /group1/dset1





c) Another dataset, a member of the root group:

/dset2

d) And another group and dataset, reusing object names:

/group2/group2/dset2




Figure 40: Examples of HDF5 file structures with groups and datasets

¹HDF5 requires random access to the linear address space. For this reason it is not well suited for some data media, such as streams.

²However, a Compound Datatype with zero members can have no data, so it is useless.

³It could be said that HDF5 extends the organizing concepts of a file system to the internal structure of a single file.

⁴As of HDF5-1.4, the storage used for an object is reclaimed, even if all links are deleted.

Chapter 2 The HDF5 Library and Programming Model

1. Introduction

The HDF5 Library implements the HDF5 abstract data model and storage model as described in the preceding chapter, "The HDF5 Data Model". The library exports a set of application programming interfaces, APIs, as its external interface. These APIs perform several categories of operations, as listed in Table 1, "The HDF APIs."

Two major objectives of the HDF5 products are to provide tools that can be used on as many computational platforms as possible, i.e., portability, and to provide a reasonably object oriented data model and programming interface. These objectives are somewhat in conflict as cross-platform portability is still a weak point with true object oriented programming languages. [[Explain? E.g., Java is portable, but there are many platforms on which it does not run. 111

To be as portable as possible, the HDF5 Library is implemented in portable C. C is not an object-oriented language, but the library uses several mechanisms and conventions to implement an object model.

First, the HDF5 library implements the objects as data structures. To refer to an object, the HDF5 library implements its own pointers, called *identifiers*. The identifier is then used to invoke operations on a specific instance of an object. For example, when a group is opened, the API returns a group identifier. This identifier is a reference to that specific group and will be used to invoke future operations on that group. The identifier is valid only within the context it is created and remains valid until it is closed or the file is closed. This mechanism is essentially the same that C++ or other object-oriented languages use to refer to objects, except the syntax is C.

Similarly, object-oriented languages collect all the methods for an object in a single name space, e.g., the methods of a C++ Class. The C language does not have any such mechanism, but the HDF5 Library API simulates this through its scheme of API names by giving names that begin with a common prefix to operations on a particular class of objects. Table 1 lists the HDF5 objects and the standard prefixes used by the corresponding HDF5 APIs. For example, functions that operate on datatype objects all have names beginning with H5T.

Table 1. The HDF5 API naming scheme

Prefix	Operates on
H5A	Attributes
H5D	Datasets
H5E	Error reports
H5F	Files
H5G	Groups
H5I	Identifiers
H5P	Property lists
H5R	References
H5S	Dataspaces
H5T	Datatypes
H5Z	Filters

2. The HDF5 Programming Model

In this section we introduce the HDF5 programming model by means of a series of short code samples illustrating a broad selection of common HDF5 tasks. These are merely illustrative examples; full details are provided in the following chapters and in the *HDF5 Reference Manual*

[[The following is based on text from the old "Intro to HDF5" and presumably needs some technical verification.]]]

2.1 Creating an HDF5 file

Before an HDF5 file can be used or referred to in any matter, must be explicitly created or opened. When using the default property lists, as we will for now, this is a simple matter. When the need for access to a file ends, the file must be closed. Figure 1 provides a C code fragment illustrating these steps.

If there is a possibility that a file of the declared name already exists and you wish to open a new file regardless of that possibility, the flag H5ACC_TRUNC will cause the operation to overwrite the previous file. If the operation should fail in such a circumstance, use the flag H5ACC_EXCL instead.

Figure 1. Creating and closing an HDF5 file.

2.2 Creating and initializing the essential components of a dataset

The dataspace, i.e., the dimensionality of the array containing raw data of the dataset, are independent objects and are created separately from any dataset it which they may be attached. Hence, creating a dataset requires, at a minimum, the following steps:

- 1. Create and initialize a dataspace defining the dimensions of the dataset array.
- 2. Define the dataset datatype.
- 3. Create and initialize the dataset itself.

The code in Figure 2 illustrates the execution of these steps.

```
hid t
        dataset, datatype, dataspace; /* declare identifiers */
* Create a dataspace: Describe the size of the array and
* create the dataspace for a fixed-size dataset.
* /
dimsf[0] = NX;
dimsf[1] = NY;
dataspace = H5Screate_simple(RANK, dimsf, NULL);
* Define a datatype for the data in the dataset.
* We will store little endian integers.
datatype = H5Tcopy(H5T_NATIVE_INT);
status = H5Tset_order(datatype, H5T_ORDER_LE);
* Create a new dataset within the file using the defined
* dataspace and datatype and default dataset creation
 * properties.
 * NOTE: H5T_NATIVE_INT can be used as the datatype if
 * conversion to little endian is not needed.
dataset = H5Dcreate(file, DATASETNAME, datatype, dataspace,
H5P DEFAULT);
```

Figure 2. The most basic steps in creating an HDF5 dataset.

2.3 Closing an object once it is no longer needed

An application should close a datatype, dataspace, or dataset object once it is no longer needed. Since each is an independent object, the must be released (or closed) separately. This action is frequently referred to as releasing the object's identifier. The code in Figure 3 closes the datatype, dataspace, and dataset that were created in the preceding section.

```
H5Tclose(datatype);
H5Dclose(dataset);
H5Sclose(dataspace);
```

Figure 3. Closing objects in an HDF5 file, or releasing their identifiers.

2.4 Writing or reading a dataset from/to a file

Having created the dataset, the actual data can be written with a call to H5Dwrite, as illustrated in Figure 4.

Figure 4. Writing the dataset.

Note that the third and fourth H5Dwrite parameters in the above example describe the dataspaces in memory and in the file, respectively. For now, these are both set to H5S_ALL, indicating that the entire dataset is to be written. The selection of partial datasets and the use of differing dataspaces in memory and in storage will be discussed later in this chapter and in more detail elsewhere in this guide.

Reading the dataset from storage is analogous to writing. If we wished to read an entire dataset, we could simply substitute H5Dread for H5Dwrite in the above example.

2.5 Reading and writing a portion of a dataset

In the previous discussion, we described writing or reading an entire dataset. HDF5 also supports access to selected portions of a dataset, known as selections, without having to read or write the entire dataset.

The simplest type of selection is a simple hyperslab, an n-dimensional rectangular subset of a dataset where n is equal to the dataset's rank. Other available selections include a more complex hyperslab with user-defined stride and block size, a list of independent points, and the union of any of these.

Figure 5 illustrates several sample instances of selections.




Figure 5. HDF5 dataspace selections can take the form of a simple hyperslab, a hyperslab with user-defined stride and block, a selection of points, or a union of any of the above.

Selections and hyperslabs are portions of a dataset. As described above, a simple hyperslab is a rectangular array of data elements with the same rank as the dataset's dataspace. Thus, a simple hyperslab is a logically contiguous collection of points within the datset.

The more general case of a hyperslab, can also be a regular pattern of points or blocks within the dataspace. Four parameters are required to describe a general hyperslab: the starting coordinates, the block size, the stride or space between blocks, and the number of blocks. These parameters are each expressed as a one-dimensional array whose length is equal to the rank of the dataspace. These parameters are described in Table 2.

Table 2. The parameters required to fully define a general hyperslab.

Parameter	Definition
start	The coordinates of the starting location of the hyperslab in the dataset's dataspace.
block	The size of each block to be selected from the dataspace. If the block parameter is set to NULL, the block size defaults to a single element in each dimension, as if the block array was set to all 1s (all ones). This will result in the selection of a uniformly spaced set of count points starting at start and on the interval defined by stride.
stride	The number of elements separating the starting point of each element or block to be selected. If the stride parameter is set to NULL, the stride size defaults to 1 (one) in each dimension and no elements are skipped.
count	The number of elements or blocks to select along each dimension.

Hyperslab example without strides or blocks. For maximum flexibility in user applications, a selection in storage can be mapped into a differently-shaped selection in memory; all that is required is that the two selections contain the same number of data elements. In this example, we will first define the selection to be read from the dataset in storage; we will then define the selection as it will appear in application memory.

Suppose we want to read a 3x4 hyperslab from a two-dimensional dataset in a file, beginning at the dataset element <1,2>. As illustrated in Figure 6, we must create the dataspace that describes the overall rank and dimensions of the dataset in the file, as well as the position and size of the in-file hyperslab that we are extracting from that dataset.

Figure 6. Define the selection to be read from storage.

The next task is to define an analogous dataspace in memory. Suppose, for instance, that we have in memory a three-dimensional 7x7x3 array into which we wish to read the two-dimensional 3x4 hyperslab described above and that we want the memory to selection to begin at the element <3,0,0> and reside in the plane of the first two dimensions of the array. Since the in-memory dataspace is three-dimensional, we have to describe the in-memory selection as three-dimensional. Since we are keeping the selection in the plane of the first two dimensions of the in-memory dataset, the in-memory selection will be a 3x4x1 array, defined as <3,4,1>.

Notice that we must describe two things: the dimensions of the in-memory array, and the size and position of the hyperslab that we wish to read in. Figure 7 illustrates how this would be done.

Figure 7.

The hyperslab in the above figure has the following parameters: start=(3,0,0), count=(3,4,1), stride and block size are NULL.

For a second example, consider an example going in the other direction, writing a selection from memory to a selection in a dataset in a file. Suppose that the source dataspace in memory is a 50-element, one-dimensional array called vector, as illustrated in Figure 8 and that the source selection is a 48-element simple hyperslab selection that starts at the second element of vector.



Figure 8

Further suppose that we wish to write this data to the file as a series of 3x2-element blocks in a 2-dimensional dataset, skipping one row and one column between blocks. Since the source selection contains 48 data elements and each block in the destination selection contains 6 data elements, we must define the destination selection with 8 blocks; we'll write 2 blocks in the first dimension and 4 in the second. Figure 9 provides sample code to achieve this objective.

```
/* Select the hyperslab for the dataset in the file, using 3x2 blocks,
 * a (4,3) stride, a (2,4) count, and starting at the position (0,1).
start[0] = 0; start[1] = 1;
stride[0] = 4; stride[1] = 3;
count[0] = 2i count[1] = 4i
block[0] = 3; block[1] = 2;
ret = H5Sselect_hyperslab(fid, H5S_SELECT_SET, start, stride, count, block);
/*
* Create dataspace for the first dataset.
mid1 = H5Screate_simple(MSPACE1_RANK, dim1, NULL);
/*
/*
* Select hyperslab.
* We will use 48 elements of the vector buffer starting at the second element.
 * Selected elements are 1 2 3 . . . 48
 * /
start[0] = 1;
stride[0] = 1;
count[0] = 48;
block[0] = 1;
ret = H5Sselect_hyperslab(mid1, H5S_SELECT_SET, start, stride, count, block);
/*
 * Write selection from the vector buffer to the dataset in the file.
ret = H5Dwrite(dataset, H5T_NATIVE_INT, mid1, fid, H5P_DEFAULT, vector)
```

Figure 9

2.6 Getting information about a dataset

Although reading is analogous to writing, it is often first necessary to query a file to obtain information about the dataset to be read. For instance, we often need to determine the datatype associated with a dataset, or its dataspace (i.e., rank and dimensions). As illustrated in Figure 10, there are several get routines for obtaining this information.

```
* Get datatype and dataspace identifiers,
* then query datatype class, order and size, and
* dataspace rank and dimensions.
datatype = H5Dget_type(dataset);
                                   /* datatype identifier */
class = H5Tget_class(datatype);
if (class == H5T_INTEGER) printf("Dataset has INTEGER type \n");
order = H5Tget_order(datatype);
if (order == H5T_ORDER_LE) printf("Little endian order \n");
size = H5Tget_size(datatype);
printf(" Data size is %d \n", size);
                                   /* dataspace identifier */
dataspace = H5Dget_space(dataset);
     = H5Sget_simple_extent_ndims(dataspace);
status n = H5Sqet simple extent dims(dataspace, dims out);
printf("rank %d, dimensions %d x %d \n", rank, dims_out[0], dims_out[1]);
```

Figure 10

2.7 Creating and defining compound datatypes

An HDF5 compound datatype is similar to a C struct or a Fortran common block. Though not originally designed with databases in mind, HDF5 compound datatypes are sometimes used in a manner analogous to a database record.

HDF5 defines a compound datatype as a collection of one or more data elements. Each elements is an atomic type, a small array, or another compound datatype. The provision for nested compound datatypes allows these structures become quite complex. Compound datatypes thus become either a powerful tool or a complex and difficult to debug construct; reasonable caution is advised.

To create and use a compound datatype, you need to create a datatype with class compound (H5T_COMPOUND) and specify the total size of the data element in bytes. A compound datatype consists of zero or more uniquely named members. Members can be defined in any order but must occupy non-overlapping regions within the datum. Table 3 lists the properties of compound datatype members.

Table 3

Parameter Index Definition

An index number between zero and N-1, where N is the number of members in the compound. The elements are indexed in the order of their location in the array of bytes.

Name A string that must be unique within the members

of the same datatype.

Datatype An HDF5 datatype.

Offset A fixed byte offset, which defines the location of

the first byte of that member in the compound

datatype.

Properties of the members of a compound datatype are defined when the member is added to the compound type and cannot be subsequently modified.

Defining compound datatypes.

Compound datatypes must be built out of other datatypes. First, one creates an empty compound datatype and specifies its total size. Members are then added to the compound datatype in any order.

Each member must have a descriptive name, which is the key used to uniquely identify the member within the compound datatype. A member name in an HDF5 datatype does not necessarily have to be the same as the name of the corresponding member in the C struct in memory, although this is often the case. Nor does one need to define all members of the C struct in the HDF5 compound datatype (or vice versa).

Usually a C struct will be defined to hold a data point in memory, and the offsets of the members in memory will be the offsets of the struct members from the beginning of an instance of the struct. The library defines the macro that computes the offset of member m within a struct variable s.:

```
HOFFSET(s,m)
```

Figure 11 shows an example in which a compound datatype is created to describe complex numbers whose type is defined by the complex_t struct.

Figure 11

2.8 Creating and writing extendible and chunked datasets

An extendible dataset is one whose dimensions can grow. One can define an HDF5 dataset to have certain initial dimensions, with the capacity to later increase the size of any of the initial dimensions.

For example, Figure 12 shows a 3x3 dataset (a), which is later extended to be a 10x3 dataset by adding 7 rows (b), and further extended to be a 10x5 dataset by adding two columns (c).

	1	1	1
	1	1	1
	1	1	1
í	a) Initially, 3 x 3		
	1	1	1
	1	1	1
	1	1	1
	2	2	2
	2	2	2
	2	2.	2
	2	2	2
	2	2	2
	2	2	2
	2	2	2
b`	b) Extend to 10 x		

1	1	1	3	3
1	1	1	3	3
1	1	1	3	3
2 2 2 2	2	2	3	3
2	2	2	3	3
2	2	2	3	3
2	2	2	3	3
2	2	2	3	3
2 2 2	2	2	3	3
2	2	2	3	3
	_	_		_

c) Extend to 10 x 5

b) Extend to 10 x 3

Figure 12

HDF5 requires the use of chunking when defining extendible datasets. Chunking makes it possible to extend datasets efficiently, without having to reorganize contiguous storage excessively. To summarize, an extendible dataset requires two conditions:

- 1. The dataspace of the dataset to be defined as unlimited in all dimensions that might eventually be extended.
- 2. The dataset creation properties must enable chunking.

For example, suppose we wish to create a dataset similar to the one shown in Figure 12. We want to start with a 3x3 dataset, then later extend it.

Declare the dataspace to have unlimited dimensions with the following code. Note the use of the predefined constant H5S_UNLIMITED to specify that a dimension is unlimited.

```
Hsize_t dims[2] = {3, 3}; /* dataset dimensions
at the creation time */
hsize_t maxdims[2] = {H5S_UNLIMITED, H5S_UNLIMITED};
 * Create the data space with unlimited dimensions.
dataspace = H5Screate_simple(RANK, dims, maxdims);
```

Figure 13

Next set the dataset creation property list to enable chunking:

```
Hid_t cparms;
hsize_t chunk_dims[2] ={2, 5};
/*
   * Modify dataset creation properties to enable chunking.
   */
cparms = H5Pcreate (H5P_DATASET_CREATE);
status = H5Pset_chunk( cparms, RANK, chunk_dims);
```

Figure 14

Then create the dataset:

Figure 15

Finally, when the time comes to extend the size of the dataset, invoke H5Dextend. Extending the dataset along the first dimension, by seven rows, leaves the dataset with new dimensions of <10,3>:

```
/*
  * Extend the dataset. Dataset becomes 10 x 3.
  */
dims[0] = dims[0] + 7;
size[0] = dims[0];
size[1] = dims[1];
status = H5Dextend (dataset, size);
```

Figure 16

2.9 Creating and working with groups in a file

Groups provide a mechanism for organizing meaningful and extendible sets of datasets within an HDF5 file. The H5G API provides several routines for working with groups.

Creating a group.

With no datatype, dataspace or storage layout to define, creating a group is considerably simpler than creating a dataset. For example, the following code creates a group called Data in the root group of file.

```
/*
  * Create a group in the file.
  */
grp = H5Gcreate(file, "/Data", 0);
```

Figure 17

A group may be created in another group by providing the absolute name of the group to the H5Gcreate function or by specifying its location. For example, to create the group Data_new in the group Data, one can use the following sequence of calls:

```
/*
  * Create group "Data_new" in the group "Data" by specifying
  * absolute name of the group.
  */
  grp_new = H5Gcreate(file, "/Data/Data_new", 0);

or

/*
  * Create group "Data_new" in the "Data" group.
  */
  grp_new = H5Gcreate(grp, "Data_new", 0);
```

Figure 18

This first parameter is a location identifier. file in the first example specifies only the file. grp in the second example specifies a particular group in a particular file. Note that in this instance, the group identifier grp is used as the first parameter in the H5Gcreate call so that the relative name of Data_new can be used.

The third parameter of H5Gcreate optionally specifies how much file space to reserve to store the names of objects that will be created in this group. If a non-positive value is supplied, the library provides a default size.

H5Gclose closes the group and releases the group identifier.

Creating a dataset in a particular group. As with groups, a dataset can be created in a particular group by specifying either its absolute name in the file or its relative name with respect to that group. The next code excerpt uses the absolute name:

```
* Create the dataset "Compressed_Data" in the group Data using the
 * absolute name. The dataset creation property list is modified
* to use GZIP compression with the compression effort set to 6.
 * Note that compression can be used only when the dataset is
 * chunked.
 * /
dims[0] = 1000;
dims[1] = 20;
cdims[0] = 20;
cdims[1] = 20;
dataspace = H5Screate_simple(RANK, dims, NULL);
        = H5Pcreate(H5P_DATASET_CREATE);
            H5Pset_chunk(plist, 2, cdims);
            H5Pset_deflate( plist, 6);
dataset = H5Dcreate(file, "/Data/Compressed_Data",
              H5T_NATIVE_INT, dataspace, plist);
```

Figure 19

Alternatively, one can first obtain an identifier for the group in which the dataset is to be created, then create the dataset with a relative name:

Figure 20

Accessing an object in a group. Any object in a group can be accessed by its absolute or relative name. The first code snippet below illustrates the use of the absolute name to access the dataset Compressed_Data in the group Data created in the examples above. The second code snippet illustrates the use of the relative name.

```
/*
  * Open the dataset "Compressed_Data" in the "Data" group.
  */
dataset = H5Dopen(file, "/Data/Compressed_Data");

  Figure 21

/*
  * Open the group "data" in the file.
  */
grp = H5Gopen(file, "Data");

/*
  * Access the "Compressed_Data" dataset in the group.
  */
dataset = H5Dopen(grp, "Compressed_Data");
```

Figure 22

2.10 Working with attributes

An attribute is a small datasets that is attached to a normal dataset or group. Attributes share many of the characteristics of datasets, so the programming model for working with attributes is analogous in many ways to the model for working with datasets. The primary differences are that an attribute must be attached to a dataset or a group and subsetting operations cannot be performed on attributes.

To create an attribute belonging to a particular dataset or group, first create a dataspace for the attribute with the call to H5Screate, then create the attribute using H5Acreate. For example, the following code creates an attribute called Integer_attribute that is a member of a dataset whose identifier is dataset. The attribute identifier is attr2. H5Awrite then sets the value of the attribute of that of the integer variable point. H5Aclose then releases the attribute identifier.

Figure 23

To read a scalar attribute whose name and datatype are known, first open the attribute using H5Aopen_name, then use H5Aread to get its value. For example the following reads a scalar attribute called Integer_attribute whose datatype is a native integer, and whose parent dataset has the identifier dataset.

```
/*
 * Attach to the scalar attribute using attribute name, then read and
 * display its value.
 */
attr = H5Aopen_name(dataset, "Integer attribute");
ret = H5Aread(attr, H5T_NATIVE_INT, &point_out);
printf("The value of the attribute \"Integer attribute\" is %d \n", point_out);
ret = H5Aclose(attr);
```

Figure 24

Reading an attribute whose characteristics are not known. It may be necessary to query a file to obtain information about an attribute, namely its name, datatype, rank and dimensions. The following code opens an attribute by its index value using H5Aopen_index, then reads in information about its datatype.

Figure 25

In practice, if the characteristics of attributes are not known, the code involved in accessing and processing the attribute can be quite complex. For this reason, HDF5 includes a function called H5Aiterate, which applies a user-supplied function to each of a set of attributes. The user-supplied function can contain the code that interprets, accesses and processes each attribute.

3. The Data Transfer Pipeline

The HDF5 Library implements data transfers between different storage locations. At the lowest levels, the HDF5 Library reads and writes blocks of bytes to and from storage using calls to the VFL drivers. In addition to this, the HDF5 Library manages caches of metadata and a data I/O pipeline that applies compression to data blocks, transforms data elements, and implements selections.

As a data management library, a substantial portion of the HDF5 Library's work is in transferring data from one environment or media to another. This most often involves a transfer between system memory and a storage medium. With the use of compression and encryption, machine-dependent differences in numerical representation, etc., the bit-by-bit representation of a given dataset is often substantially different in the two environments.

Consider the representation on disk of a compressed and encrypted little-endian array as compared to the same array after it has read from disk, decrypted, decompressed and loaded into memory on a big-endian system. HDF5 performs all of the operations necessary to make that transition during the I/O process, with many of the operations being handled by the virtual file layer (VFL) and the data transfer pipeline.

Figure 26 provides a simplified view of a sample data transfer with four stages. Note that the modules are used only when needed, e.g., if the data is not compressed, the compression stage is omitted.




Figure 26

For a given I/O requests, different combinations of actions may be performed by the pipeline. The library automatically sets up the pipeline and passes data through the processing steps. For example, for a *read* request (from disk to memory), the library must determine which logical blocks contain the requested data elements and fetch each block into the library's cache. If the data needs to be decompressed, then the compression algorithm is applied to the block after it is read from disk. If the data is a selection, the selected elements are extracted from the data block after it is decompressed. If the data needs to be transformed (e.g., byte swapped), then the data elements are transformed after decompression and selection.

While an application must sometimes set up some elements of the pipeline, e.g., the use of a custom error-checking algorithm, use of the pipeline is normally transparent to the user program; the library determines what must be done based on the metadata for the file, the object, and the specific request.

In some cases it is necessary to pass parameters to and from modules in the pipeline, or among other parts of the library that are not directly called through the programming API. This is accomplished through the use of dataset transfer and data access property lists.

The VFL, or virtual file layer, provides an interface whereby user applications can add custom modules to the data transfer pipeline. For example, a custom compression algorithm can be used with the HDF5 Library by linking an appropriate module into the pipeline through the VFL. This requires creating an appropriate wrapper for the compression module and registering it with the library with H5Zregister. It can then be applied to a dataset with an H5Pset_filter call, which will add it to the selected dataset's transfer property list.

¹HDF5 requires random access to the linear address space. For this reason it is not well suited for some data media, such as streams.

³It could be said that HDF5 extends the organizing concepts of a file system to the internal structure of a single file.

⁴As of HDF5-1.4, the storage used for an object is reclaimed, even if all links are deleted.

Part II

The Specifics:

Using HDF5

Chapter 3 The HDF5 File

1. Introduction

If HDF5 data is to be written to or read from a file, that file must first be explicitly created or opened with the appropriate file driver and access privileges. Once all work with data is complete, the file must be explicitly closed.

This chapter discusses the following:

- File access modes
- Creating, opening, and closing files
- The use of file creation property lists
- The use of file access property lists, including low-level file drivers

The remaining sections of this chapter require a brief summary of the HDF5 mechanisms for handling file access modes, file access properties and file creation properties, and the use of low-level file drivers. These topics are discussed briefly in the following paragraphs. This chapter assumes an understanding of the material presented in the data model chapter, "HDF5 Data Model and File Structure."

File access modes

There are two issues regarding file access:

- What should happen when a new file is created but a file of the same name already exists? Should the create action fail or should the existing file be overwritten?
- Is a file to be opened with read-only or read-write access?

Four access modes address these concerns, with H5Fcreate and H5Fopen each accepting two of them:

- H5Fcreate accepts H5F_ACC_TRUNC or H5F_ACC_EXCL.
- H5Fopen accepts H5F_ACC_RDONLY or H5F_ACC_RDWR.

Access flag	Resulting access mode
H5F_ACC_EXCL	If the file already exists, H5Fcreate fails. If the file does not exist, it is created and opened with read-write access. (Default)
H5F_ACC_TRUNC	If the file already exists, the file is opened with read-write access and new data will overwrite any existing data, i.e., the file's content is truncated upon opening, destroying all prior data and meta data. If the file does not exist, it is created and opened with read-write access.
H5F_ACC_RDONLY	An existing file is opened with read-only access. If the file does not exist, H5Fopen fails. (Default)
H5F_ACC_RDWR	An existing file is opened with read-write access. If the file does not exist, H5Fopen fails.

By default, H5Fopen opens a file for read-only access; passing H5F_ACC_RDWR allows read-write access to the file

By default, H5Fcreate fails if the file already exists; only passing H5F_ACC_TRUNC allows the truncation of an existing file.

File creation and file access properties

File creation and file access property lists control the more complex aspects of creating and accessing files.

File creation property lists control characteristics of a file, such as the size of the user-block, a user-definable data block; the size of data address parameters; properties of the B-trees are used to manage the data in the file; and certain HDF5 library versioning information.

See "file creation properties," below, for a more detailed discussion of file creation properties and appropriate references to the *HDF5 Reference Manual*. If you have no special requirements for these file characteristics, you can simply specify H5P_DEFAULT, for the default file creation property list, when a file creation property list is called for.

File access property lists control properties and means of accessing a file, such as data alignment characteristics, meta data block and cache sizes, data sieve buffer size, garbage collection settings, and parallel I/O. Data alignment, meta data block and cache sizes, and data sieve buffer size are factors in improving I/O performance.

See "file access properties," below, for a more detailed discussion of file access properties and appropriate references to the *HDF5 Reference Manual*. If you have no special requirements for these file access characteristics, you can simply specify H5P_DEFAULT, for the default file access property list, when a file access property list is called for.

Low-level file drivers

The concept of an HDF5 file is actually rather abstract: the address space for what is normally thought of as an HDF5 file might correspond to any of the following at the storage level:

- Single file on a standard file system
- Multiple files on a standard file system
- Multiple files on a parallel file system
- Block of memory within an application's memory space
- More abstract situations, such as virtual files

This HDF5 address space is generally referred to as an *HDF5 file* regardless of its organization at the storage level.

HDF5 accesses a file, i.e., the address space, through various types of *low-level file drivers*. The default HDF5 file storage layout is as an unbuffered permanent file, which is a single, contiguous file on local disk. Alternative layouts are designed to suit the needs of a variety of systems, environments, and applications.

2. Programming Model




Figure 1: UML model for an HDF5 file and its file creation and file access property lists

2.1 Creating a new file

The programming model for creating a new HDF5 file can be summarized as follows:

- Define file creation property list (optional).
- Define file access property list, including low-level file driver (optional).
- Create file.

First consider the simple case where we wish to rely on the HDF5 defaults. All we have to do is create the file:

Note that this example specifies that H5Fcreate should fail if SampleFile. h5 already exists.

Now consider the more generalized case, in which we define file creation and access property lists (though we do not assign any properties), specify that H5Fcreate should fail if SampleFile.h5 already exists, and create a new file named SampleFile.h5. The example does not specify a driver, so the default driver, SEC2 or H5FD_SEC2, will be used.

```
fcplist_id = H5Pcreate (H5P_FILE_CREATE)
    <...set desired file creation properties...>
faplist_id = H5Pcreate (H5P_FILE_ACCESS)
    <...set desired file access properties...>
file_id = H5Fcreate ("SampleFile.h5", H5F_ACC_EXCL, fcplist_id, faplist_id)
```

Notes: A root group is automatically created in a file when the file is first created. File property lists, once defined, can be reused when another file is created within the same application.

2.2 Opening an existing file

The programming model for opening an existing HDF5 file can be summarized as follows:

- Define or modify file access property list, including low-level file driver (optional).
- Open file.

Now consider an example in which we re-open SampleFile.h5. For the sake of the example, we will open it with a different driver, stdio or H5FD_STDIO, and declare read-only access.

faplist_id = H5Pcreate (H5P_FILE_ACCESS) status = H5Pset_fapl_stdio (faplist_id) file_id = H5Fopen ("SampleFile.h5", H5F_ACC_RDONLY, faplist_id)

2.3 Closing a file

The programming model for closing an HDF5 file is very simple:

• Close file.

We close SampleFile.h5 with the following line of code.

```
status = H5Fclose (file_id)
```

Note that H5Fclose flushes all unwritten data to storage. file_id is the identifier returned for SampleFile.h5 by H5Fopen.

More comprehensive discussions regarding all of these steps are provided below.

3. Using h5dump

The HDF5 distribution includes a command-line utility, h5dump, which provides a straight-forward means of inspecting the contents of an HDF5 file. h5dump thus enables a programmer to verify that a program is generating the intended HDF5 file. h5dump displays ASCII output formatted according to the HDF5 DDL grammar.

The following h5dump command will display the contents of SampleFile.h5:

h5dump SampleFile.h5

If no datasets or groups have been created in and no data has been written to the file, the output will look something like the following:

```
HDF5 "SampleFile.h5" { GROUP "/" { } }
```

Note that the root group, indicated above by /, was automatically created when the file was created.

h5dump is fully described on the Tools page of the *HDF5 Reference Manual*. The HDF5 DDL grammar is fully described in the document DDL in BNF for HDF5, an element of this *HDF5 User's Guide*.

4. File (H5F) Function Summaries

4.1 File functions

C Function Purpose
F90 Function

H5Fcreate Creates new HDF5 file.

h5fcreate_f

H5Fopen Opens existing HDF5 file.

h5fopen_f

H5Fclose Closes HDF5 file.

h5fclose_f

H5Fflush Flushes data to HDF5 file on storage medium.

h5fflush_f

4.2 File creation property list functions

C Function F90 Function	Purpose
H5Pset/get_userblock h5pset/get_userblock_f	Sets/retrieves size of user block.
H5Pset/get_sizes h5pset/get_sizes_f	Sets/retrieves byte size of offsets and lengths used to address objects in HDF5 file.
H5Pset/get_sym_k h5pset/get_sym_k_f	Sets/retrieves size of parameters used to control symbol table nodes.
<pre>H5Pset/get_istore_k h5pset/get_istore_k_f</pre>	Sets/retrieves size of parameter used to control B-trees for indexing chunked datasets.
H5Pget_version h5pget_version_f	Retrieves version information for various objects for file creation property list.

4.3 File access property list functions (except file drivers)

C Function F90 Function	Purpose
H5Pset/get_meta_block_size h5pset/get_meta_block_size_f	Sets the minimum meta data block size or retrieves the current meta data block size setting.
H5Pset/get_sieve_buf_size h5pset/get_sieve_buf_size_f	Sets/retrieves maximum size of data sieve buffer.
H5Pset/get_alignment h5pset/get_alignment_f	Sets/retrieves alignment properties.
H5Pset/get_cache h5pset/get_cache_f	Sets/retrieves meta data cache and raw data chunk cache parameters.
H5Pset/get_fclose_degree h5pset/get_fclose_degree_f	Sets/retrieves file close degree property.

H5Pset/get_gc_references
h5pset/get_gc_references_f

Sets/retrieves garbage collecting references flag.

4.4 File driver functions

C Function F90 Function	Purpose
H5Pget_driver h5pget_driver_f	Determines driver used to create file.
H5Pset_fapl_sec2 h5pset_fapl_sec2_f	Sets driver for unbuffered permanent files or retrieves information regarding driver.
H5Pset_fapl_stdio (none)	Sets driver for buffered permanent files.
H5Pset/get_fapl_mpio h5pset/get_fapl_mpi_f	Sets driver for files on parallel file systems (MPI I/O) or retrieves information regarding the driver.
H5Pset/get_fapl_family h5pset/get_fapl_family_f	Sets driver for file families, designed for systems that do not support files larger than 2 gigabytes, or retrieves information regarding driver.
H5Pset/get_fapl_multi h5pset/get_fapl_multi_f	Sets driver for multiple files, separating categories of meta data and raw data, or retrieves information regarding driver.
H5Pset_fapl_split h5pset_fapl_split_f	Sets driver for split files, a limited case of multiple files with one meta data file and one raw data file.
H5Pset/get_fapl_core h5pset/get_fapl_core_f	Sets driver for buffered memory files (i.e., in RAM) or retrieves information regarding driver.
H5Pset_fapl_log (none)	Sets logging driver.

5. Creating or Opening an HDF5 File

5.1 Defining the file creation and file access property lists

This step is optional; you can always rely on the default property lists in creating a new file and the default or previously-defined file access property list with an existing file.

See "File Property Lists," below, for details of setting property list values. See "File Access Modes," in the introduction to this chapter above, for the complete list of file access flags and their descriptions.

5.2 Working with the file

New HDF5 files are created and opened with H5Fcreate; existing files are opened with H5Fopen. Both functions return an object identifier, which must eventually be released by calling H5Fclose.

To create a new file, call H5Fcreate:

H5Fcreate creates a new file named *name* in the current directory. The file is opened with read and write access; if the H5F_ACC_TRUNC flag is set, any pre-existing file of the same name in the same directory is truncated. If either H5F_ACC_TRUNC is not set or H5F_ACC_EXCL is set and if a file of the same name exists, H5Fcreate will fail.

The new file is created with the properties specified in the property lists fcpl_id and fapl_id. Specifying H5P_DEFAULT for either the creation or access property list calls for the library's default creation or access properties.

If H5Fcreate successfully creates the file, it returns a file identifier for the new file. This identifier will be used by the application any time an object identifier, an OID, for the file is required. Once the application has finished working with a file, the identifier should be released and the file closed with H5Fclose.

To open an existing file, call H5Fopen:

```
hid_t H5Fopen (const char *name, unsigned flags, hid_t fapl_id)
```

H5Fopen opens an existing file with read-write access if H5F_ACC_RDWR is set and read-only access if H5F_ACC_RDONLY is set.

fapl_id is the file access property list identifier. Alternatively, H5P_DEFAULT indicates that the application relies on the default I/O access parameters. Creating and changing access property lists is documented further below.

A file can be opened more than once via multiple H5Fopen calls. Each such call returns a unique file identifier and the file can be accessed through any of these file identifiers as long as they remain valid. Each of these file identifiers must be released by calling H5Fclose when it is no longer needed.

6. Closing an HDF5 File

H5Fclose both closes a file and releases the file identifier returned by H5Fopen or H5Fcreate. H5Fclose must be called when an application is done working with a file; while the HDF5 Library makes every effort to maintain file integrity, failure to call H5Fclose may result in the file being abandoned in an incomplete or corrupted state.

```
To close a file, call H5Fclose:

herr_t H5Fclose (hid_t file_id)
```

This function releases resources associated with an open file. After closing a file, the file identifier, file_id, cannut be used again as it will be undefined.

H5Fclose fulfills three purposes: to ensure that the file is left in an uncorrupted state, to ensure that all data has been written to the file, and to release resources. Use H5Fflush if you wish to ensure that all data has been written to the file but it is premature to close it.

Note regarding serial mode behavior: When H5Fclose is called in serial mode, it closes the file and terminates new access to it, but it does not terminate access to objects that remain individually open within the file. That is, if H5Fclose is called for a file but one or more objects within the file remain open, those objects will remain accessible until they are individually closed. To illustrate, assume that a file, fileA, contains a dataset, data_setA, and that both are open when H5Fclose is called for fileA. data_setA will remain open and accessible, including writable, until it is explicitly closed. The file will be automatically and finally closed once all objects within it have been closed.

Note regarding parallel mode behavior: Once H5Fclose has been called in parallel mode, access is no longer available to any object within the file.

7. File Property Lists

Additional information regarding file structure and access are passed to H5Fcreate and H5Fopen through property list objects. Property lists provide a portable and extensible method of modifying file properties via simple API functions. There are two kinds of file-related property lists:

- File creation property lists
- File access property lists

In the following subsections, we discuss only one file creation property, user-block size, in detail as a model for the user. Other file creation and file access properties are mentioned and defined briefly, but the model is not expanded for each; complete syntax, parameter, and usage information for every property list function is provided in the "H5P: Property List Interface" chapter of the *HDF5 Reference Manual*.

7.1 Creating a property list

If you do not wish to rely on the default file creation and access properties, you must first create a property list with H5Pcreate.

```
hid_t H5Pcreate (hid_t cls_id)
```

type is the type of property list being created. In this case, the appropriate values are H5P_FILE_CREATE for a file creation property list and H5P_FILE_ACCESS for a file access property list.

Thus, the following calls create first a file creation property list then a file access property list with identifiers $fcpl_id$ and $fapl_id$, respectively:

```
fcpl_id = H5Pcreate (H5P_FILE_CREATE)
fapl_id = H5Pcreate (H5P_FILE_ACCESS)
```

Once the property lists have been created, the properties themselves can be modified via the functions described in the following subsections.

7.2 File creation properties

File creation property lists control the file meta data, which is maintained in the super block of the file. These properties are used only when a file is first created.

User-block size

```
herr_t H5Pset_userblock (hid_t plist, hsize_t size)
herr t H5Pget userblock (hid t plist, hsize t *size)
```

The *user-block* is a fixed-length block of data located at the beginning of the file and which is ignored by the HDF5 Library. This block is specifically set aside for any data or information that developers determine to be useful to their application but that will not be used by the HDF5 Library. The *size* of the user-block is defined in bytes and may be set to any power of two, with a minimum size of 512 bytes (i.e. 512, 1024, 2048, etc). This property is set with H5Pset_userblock and queried via H5Pget_userblock.

For example, if an application was thought to reqire a 4K user-block, that could be set with the following function call:

```
status = H5Pset_userblock(fcpl_id, 4096)
The property list could later be queried with
    status = H5Pget_userblock(fcpl_id, size)
and the value 4096 would be returned in the parameter size.
```

Other properties, below, are set and queried in exactly the same manner. Syntax and usage are detailed in the "H5P: Property List Interface" section of the *HDF5 Reference Manual*.

Offset and length sizes

This property specifies the number of bytes used to store the offset and length of objects in the HDF5 file. Values of 2, 4, and 8 bytes are currently supported to accommodate 16-bit, 32-bit, and 64-bit file address spaces.

These properties are set and queried via H5Pset_sizes and H5Pget_sizes.

Symbol table parameters

The size of symbol table B-trees can be controlled by setting the 1/2-rank and 1/2-node size parameters of the B-tree.

These properties are set and queried via H5Pset_sym_k and H5Pget_sym_k. Indexed storage parameters

The size of indexed storage B-trees can be controlled by setting the 1/2-rank and 1/2-node size parameters of the B-tree.

These properties are set and queried via H5Pset_istore_k and H5Pget_istore_k. Version information

Various objects in an HDF5 file may over time appear in different versions. The HDF5 Library keeps track of the version of each object in the file.

Version information is retrieved via H5Pget_version.

7.3 File access properties

This section discusses file access properties that are not related to the low-level file drivers. File drivers are discussed separately in "Alternate File Storage Layouts and Low-level File Drivers," later in this chapter.

File access property lists control various aspects of file I/O and structure.

Data alignment

Sometimes file access is faster if certain data elements are aligned in a specific manner. This can be controlled by setting alignment properties via the H5Pset_alignment function. Two values are involved.

♦ a threshhold value and

♦ an alignment interval.

Any allocation request at least as large as the threshold will be aligned on an address that is a multiple of the alignment interval.

Meta data block allocation size

Meta data typically exists as very small chunks of data; storing meta data elements in a file without blocking them can result in hundreds or thousands of very small data elements in the file. This can result in a highly fragmented file and seriously impede I/O. By blocking meta data elements, these small elements can be grouped in larger sets, thus alleviating both problems.

H5Pset_meta_block_size sets the minimum size in bytes of meta data block allocations. H5Pget_meta_block_size retrieves the current minimum meta data block allocation size.

Meta data cache

Meta data and raw data I/O speed are often governed by the size and frequency of disk reads and writes. In many cases, the speed can be substantially improved by the use of an appropriate cache.

H5Pset_cache sets the minimum cache size for both meta data and raw data and a preemption value for raw data chunks. H5Pget_cache retrieves the current values.

Data sieve buffer size

Data sieve buffering is used by certain file drivers to speed data I/O, most commonly when working with dataset hyperslabs. For example, using a buffer large enough to hold several pieces of a dataset as it is read in for hyperslab selections will boost performance noticeably.

H5Pset_sieve_buf_size sets the maximum size in bytes of the data sieve buffer.

H5Pget_sieve_buf_size retrieves the current maximum size of the data sieve buffer.

Garbage collection references

Dataset region references and other reference types use space in an HDF5 file's global heap. If garbage collection is on (1) and the user passes in an uninitialized value in a reference structure, the heap might become corrupted. When garbage collection is off (0), however, and the user re-uses a reference, the previous heap block will be orphaned and not returned to the free heap space. When garbage collection is on, the user must initialize the reference structures to 0 or risk heap corruption.

H5Pset_gc_references sets the garbage collecting references flag.

8. Alternate File Storage Layouts and Low-level File Drivers

The concept of an HDF5 file is actually rather abstract: the address space for what is normally thought of as an HDF5 file might correspond to any of the following:

- Single file on standard file system
- Multiple files on standard file system
- Multiple files on parallel file system
- Block of memory within application's memory space
- More abstract situations, such as virtual files

This HDF5 address space is generally referred to as an *HDF5 file* regardless of its organization at the storage level

HDF5 employs an extremely flexible mechanism called the *virtual file layer*, or VFL, for file I/O. A full understanding of the VFL is only necessary if you plan to write your own drivers (see "Virtual File Layer" and "List of VFL Functions" in the *HDF5 Technical Notes*). For our purposes here, it is sufficient to know that the low-level drivers used for file I/O reside in the VFL, as illustrated in the following figure.




Figure 2: I/O path from application through VFL and low-level drivers to storage level

As mentioned above, HDF5 applications access HDF5 files through various *low-level file drivers*. The default HDF5 file storage layout is as an unbuffered permanent file, which is a single, contiguous file on local disk. The default driver for that layout is the SEC2 driver, H5FD_SEC2. Alternative layouts and drivers are designed to suit the needs of a variety of systems, environments, and applications.

The following table lists the supported drivers distributed with the HDF5 Library and their associated file storage layouts.

Storage layout	Driver	Intended usage
Unbuffered permanent file	H5FD_SEC2	Permanent file on local disk with minimal buffering. Posix-compliant. Default.
Buffered permanent file	H5FD_STDIO	Permanent file on local disk with additional low-level buffering.
File family	H5FD_FAMILY	Several files that, together, constitute a single virtual HDF5 file. Designed for systems that do not support files larger than 2 gigabytes.
Multiple files	H5FD_MULTI	Separate files for different types of meta data and for raw data.
Split files	H5FD_SPLIT	Two files, one for meta data and one for raw data (limited case of H5FD_MULTI).
Parallel files (MPI I/O)	H5FD_MPI	Parallel files accessed via the MPI I/O layer. The standard HDF5 file driver for parallel file systems.
Buffered temporary file	H5FD_CORE	Temporary file maintained in memory, not written to disk.
Access logs	H5FD_LOG	The SEC2 driver with logging capabilities.

Note that the low-level file drivers manage alternative file storage layouts. Alternative dataset storage layouts, such as chunking, compression, and external dataset storage, are orthogonal to file storage layout and are managed independently.

If an application requires a special-purpose low-level driver, the VFL provides a public API for creating one. But that activity is beyond the scope of this document (see "Virtual File Layer" and "List of VFL Functions" in the *HDF5 Technical Notes*).

8.1 Identifying the previously-used file driver

When creating a new HDF5 file, no history exists, so the file driver must be specified if it is to be other than the default.

When opening existing files, however, the application may need to determine which low-level driver was used to create the file. The function H5Pget_driver is used for this purpose.

```
hid_t H5Pget_driver (hid_t fapl_id)
```

H5Pget_driver returns a constant identifying the low-level driver for the access property list *fapl_id*. For example, if the file was created with the SEC2 driver, H5Pget_driver returns H5FD_SEC2.

fapl_id has presumably been previously identified as the access property list for the file being opened.

If the application opens an HDF5 file without both determining the driver used to create the file and setting up the use of that driver, the HDF5 Library will examine the super block and the driver definition block to identify the driver. See the *HDF5 File Format Specification* for detailed descriptions of the super block and the driver definition block.

8.2 Unbuffered permanent files -- SEC2 driver

The SEC2 driver, H5FD_SEC2, uses functions from section 2 of the Posix manual to access unbuffered files stored on a local file system. The HDF5 Library buffers meta data regardless of the low-level driver, but using this driver prevents data from being buffered again by the lowest layers of the library.

The function H5Pset fapl sec2 sets the file access properties to use the SEC2 driver.

```
herr_t H5Pset_fapl_sec2 (hid_t fapl_id)
```

Any previously-defined driver properties are erased from the property list.

Additional parameters may be added to this function in the future. Since there are no additional variable settings associated with the SEC2 driver, there is no H5Pget_fapl_sec2 function.

8.3 Buffered permanent files -- STDIO driver

The STDIO driver, H5FD_STDIO also accesses permanent files in a local file system, but with an additional layer of buffering beneath the HDF5 Library.

The function H5Pset_fapl_stdio sets the file access properties to use the STDIO driver.

```
herr_t H5Pset_fapl_stdio (hid_t fapl_id)
```

Any previously defined driver properties are erased from the property list.

Additional parameters may be added to this function in the future. Since there are no additional variable settings associated with the STDIO driver, there is no H5Pget_fapl_stdio function.

8.4 File families -- FAMILY driver

HDF5 files can become quite large, creating problems on systems that do not support files larger than 2 gigabytes. The HDF5 file family mechanism is designed to solve the problems this creates by simply splitting the HDF5 file address space across several smaller files. This structure does nothing to segregate meta data and raw data; they are mixed in the address space just as they would be in a single contiguous file.

HDF5 applications access such a family of files via the FAMILY driver, H5FD_FAMILY. The functions H5Pset_fapl_family and H5Pget_fapl_family are used to manage file family properties:

Each member of the family is the same logical size, though the size and disk storage reported by file system listing tools (e.g., 'ls -l' on a UNIX system or the detailed folder listing on a Macintosh or Microsoft Windows system) may be substantially smaller. The name passed to H5Fcreate or H5Fopen should include a printf(3c)-style integer format specifier which will be replaced with the family member number. The first family member is numbered zero (0).

H5Pset_fapl_family sets the access properties to use the FAMILY driver; any previously defined driver properties are erased from the property list. <code>member_properties</code> will serve as the file access property list for each member of the file family. <code>memb_size</code> specifies the logical size, in bytes, of each family member. <code>memb_size</code> is used only when creating a new file or truncating an existing file; otherwise the member size is determined by the size of the first member of the family being opened. Note: If the size of the <code>off_t</code> type is four bytes, the maximum family member size is usually 2^31-1 because the byte at offset 2,147,483,647 is generally inaccessible.

H5Pget_fapl_family is used to retrieve file family properties. If the file access property list is set to use the FAMILY driver, *member_properties* will be returned with a pointer to a copy of the appropriate member access property list. If *memb_size* is non-null, it will contain the logical size, in bytes, of family members.

Additional parameters may be added to these functions in the future.

UNIX tools and an HDF5 utility

It occasionally becomes necessary to repartition a file family. A command-line utility for this purpose, h5repart, is distributed with the HDF5 Library.

h5repart [-v] [-b block_size[suffix]] [-m member_size[suffix]] source destination

h5repart repartitions an HDF5 file by copying the source file or file family to the destination file or file family, preserving holes in the underlying UNIX files. Families are used for the source and/or destination if the name includes a printf-style integer format such as %d. The -v switch prints input and output file names on the standard error stream for progress monitoring, -b sets the I/O block size (the default is 1kB), and -m sets the output member size if the destination is a family name (the default is 1GB). block_size and member_size may be suffixed with the letters g, m, or k for GB, MB, or kB respectively.

The h5repart utility is fully described on the Tools page of the HDF5 Reference Manual.

An existing HDF5 file can be split into a family of files by running the file through split(1) on a UNIX system and numbering the output files. However, the HDF5 Library is lazy about extending the size of family members, so a valid file cannot generally be created by concatenation of the family members.

Splitting the file and rejoining the segments by concatenation (split(1) and cat(1) on UNIX systems) does not generate files with holes; holes are preserved only through the use of h5repart.

8.5 Multiple meta data and raw data files -- MULTI driver

In some circumstances, it is useful to separate meta data from raw data and some types of meta data from other types of meta data. Situations that would benefit from use of the MULTI driver include the following:

- In networked situations where the small meta data files can be kept on local disks but larger raw data files must be stored on remote remote media
- In cases where the raw data is extremely large
- In situations requiring frequent access to meta data held in RAM while the raw data can be efficiently held on disk.

In either case, access to the meta data is substantially easier with the smaller, and possibly more localized, meta data files. This often results in improved application performance.

The MULTI driver, H5FD_MULTI, provides a mechanism for segregating raw data and different types of meta data into multiple files. The functions H5Pset_fapl_multi and H5Pget_fapl_multi are used to manage access properties for these multiple files:

```
herr_t H5Pset_fapl_multi (hid_t fapl_id, const H5FD_mem_t *memb_map, const hid_t *memb_fapl, const char * const *memb_name, const haddr_t *memb_addr, hbool_t relax)

herr_t H5Pget_fapl_multi (hid_t fapl_id, const H5FD_mem_t *memb_map, const hid_t *memb_fapl, const char **memb_name, const haddr_t *memb_addr, hbool_t *relax)
```

H5Pset_fapl_multi sets the file access properties to use the MULTI driver; any previously defined driver properties are erased from the property list. With the MULTI driver invoked, the application will provide a base name to H5Fopen or H5Fcreate. The files will be named by that base name as modified by the rule indicated in memb_name. File access will be governed by the file access property list memb_properties.

See H5Pset_fapl_multi and H5Pget_fapl_multi in the *HDF5 Reference Manual* for complete descriptions of these functions and their usage.

Additional parameters may be added to these functions in the future.

8.6 Split meta data and raw data files -- SPLIT driver

The SPLIT driver, H5FD_SPLIT, is a limited case of the MULTI driver, creating exactly two files: one containing all the meta data and another for raw data.

The function H5Pset_fapl_split is used to manage SPLIT file access properties:

```
herr_t H5Pset_fapl_split (hid_t access_properties, const char *meta_extension, hid_t meta_properties, const char *raw_extension, hid_t raw_properties
```

H5Pset_fapl_split sets the file access properties to use the SPLIT driver; any previously defined driver properties are erased from the property list.

With the SPLIT driver invoked, the application will provide a base file name, file_name to H5Fcreate or H5Fopen. The meta data and raw data files in storage will then be named file_name.meta_extension and file_name.raw_extension, respectively. For example, if meta_extension is defined as .meta and raw_extension is defined as .raw, the final filenames will be file_name.meta and file_name.raw.

Each file can have its own file access property list. This allows the creative use of other low-level file drivers. For instance, the meta data file can be held in RAM and accessed via the CORE driver while the raw data file is stored on disk and accessed via the SEC2 driver. Meta data file access will be governed by the file access property list in *meta_properties*. Raw data file access will be governed by the file access property list in *raw_properties*.

Additional parameters may be added to these functions in the future. Since there are no additional variable settings associated with the SPLIT driver, there is no H5Pget_fapl_split function.

8.7 Parallel I/O with MPI I/O -- MPI driver

Most of the low-level file drivers described here are for use with serial applications on serial systems. Parallel environments, on the other hand, require a parallel low-level driver. HDF5 relies on MPI I/O in parallel environments and the MPI driver, H5FD_MPI, for parallel file access.

The functions H5Pset_fapl_mpio and H5Pget_fapl_mpio are used to manage parallel file access properties.

The file access properties managed by H5Pset_fapl_mpio and retrieved by H5Pget_fapl_mpio are the MPI communicator, comm, and the MPI info object, info.

comm is the MPI communicator to be used for file open. info is the MPI info object, an information object much like an HDF5 property list, to be used for file open. Both are defined in MPI_FILE_OPEN of MPI-2.

The communicator and the info object are saved in the file access property list fapl_id. fapl_id can then be passed to MPI_File_open to create and/or open the file.

This function does not create duplicate *comm* or *info* objects. Any modification to either object after this function call returns may have an undetermined effect on the access property list; users should not modify either of the *comm* or *info* objects while they are defined in a property list.

H5Pset_fapl_mpio and H5Pget_fapl_mpio are available only in the parallel HDF5 Library and are not collective functions. The MPI driver is available only in the parallel HDF5 Library.

Additional parameters may be added to these functions in the future.

8.8 Buffered temporary files in memory -- CORE driver

There are several situations in which it is it is reasonable, sometimes even required, to maintain a file entirely in system memory. You might want to do so if, for example, either of the following conditions apply:

- Performance requirements are so stringent that disk latency is a limiting factor.
- You are working with small, temporary files that will not be retained and, thus, need not be written to storage media.

The CORE driver, H5FD_CORE, provides a mechanism for creating and managing such in-memory files. The functions H5Pset_fapl_core and H5Pget_fapl_core manage CORE file access properties:

H5Pset_fapl_core sets the file access property list to use the CORE driver; any previously defined driver properties are erased from the property list.

Memory for the file will always be allocated in units of the specified block_size.

While using H5Fcreate to create a CORE file, backing_store is a boolean flag indicating whether to write the file contents to disk when the file is closed. If backing_store is set to 1 (TRUE), the file contents are flushed to a file with the same name as the CORE file when the file is closed or access to the file is terminated in memory. If backing_store is set to 0 (FALSE), the file is not saved.

The application is allowed to open an existing file with H5FD_CORE driver. While using H5Fopen to open an existing file, if the backing_store is set to 1 and the flags for H5Fopen is set to H5F_ACC_RDWR, any change to the file contents are saved to the file when the file is closed. If backing_store is set to 0 and the flags for H5Fopen is set to H5F_ACC_RDWR, any change to the file contents will be lost when the file is closed. If the flags for H5Fopen is set to H5F_ACC_RDONLY, no change to the file is allowed either in memory or on file.

If the file access property list is set to use the CORE driver, H5Pget_fapl_core will return block_size and backing_store with the relevant file access property settings.

Note the following important points regarding in-memory files:

- Local temporary files are created and accessed directly from memory without ever being written to disk.
- Total file size must not exceed the available virtual memory.
- Only one HDF5 file identifier can be opened for the file, the identifier returned by H5Fcreate or H5Fopen.
- The changes to the file will be discarded when access is terminated unless backing store is set to 1.

Additional parameters may be added to these functions in the future.

8.10 Access logging -- LOG driver

The LOG driver, H5FD_LOG, is designed for situations where it is necessary to log file access activity.

The function H5Pset_fapl_log is used to manage logging properties:

```
herr_t H5Pset_fapl_log (hid_t fapl_id, const char *logfile, unsigned int flags, size_t buf_size)
```

H5Pset_fapl_log sets the file access property list to use the LOG driver. File access characteristices are identical to access via the SEC2 driver. Any previously defined driver properties are erased from the property list.

Log records are written to the file logfile.

The following values of *verbosity* set the indicated logging levels:

- 0 Performs no logging.
- 1 Records where writes and reads occur in the file.
- Records where writes and reads occur in the file and what kind of data is written at each location: raw data or any of several types of metadata (object headers, superblock, B-tree data, local headers, or global headers).

There is no H5Pget_fapl_log function.

Additional parameters may be added to this function in the future.

9. Code Examples for Opening and Closing Files

9.1 Example using the H5ACC_TRUNC flag

The following example creates a new file with the default file creation and file access properties. Since H5Fcreate is called with the H5ACC_TRUNC flag, any existing file content is overwritten if the file already exists, i.e., it is truncated. If H5Fcreate should fail if the file already exists, use the flag H5ACC_TRUNC instead of H5ACC_TRUNC.

9.2 Example with file creation property list

This example shows how to create a file with 64-bit object offsets and lengths:

9.3 Example with file access property list

This example shows how to open an existing file for independent datasets access by MPI parallel I/O:

```
hid_t access_plist;
hid_t file_id;
access_plist = H5Pcreate(H5P_FILE_ACCESS);
H5Pset_fapl_mpi(access_plist, MPI_COMM_WORLD, MPI_INFO_NULL);

/* H5Fopen must be called collectively */
file_id = H5Fopen("test.h5", H5F_ACC_RDWR, access_plist);
    .
    .
    .
    /* H5Fclose must be called collectively */
H5Fclose(file_id);
```

HDF5 User's Guide HDF5 Groups

Chapter 4 HDF5 Groups

1. Introduction

As suggested by the name Hierarchical Data Format, an HDF5 file is hierarchically structured. The HDF5 group and link objects implement this hierarchy.

In the simple and most common case, the file structure is a tree structure; in the general case, the file structure may be a directed graph with a designated entry point. The tree structure is very similar to the file system structures employed on UNIX systems, directories and files, and on Apple Macintosh and Microsoft Windows systems, folders and files. HDF5 groups are analogous to the directories and folders; HDF5 datasets are analogous to the files.

The one very important difference between the HDF5 file structure and the above-mentioned file system anologs is that HDF5 groups are linked as a directed graph, allowing circular references; the file systems are strictly hierarchical, allowing no circular references. The figures below illustrate the range of possibilities.

In Figure 1, the group structure is strictly hierarchical, identical to the file system analogs.

In Figures 2 and 3, the structure takes advantage of the directed graph's allowance of circular references. In Figure 2, GroupA is not only a member of the root group, /, but a member of GroupC. Since Group C is a member of Group B and Group B is a member of Group A, Dataset1 can be accessed by means of the circular reference /Group A/Group B/Group C/Group A/Dataset1. Figure 3 illustrates an extreme case in which GroupB is a member of itself, enabling a reference to a member dataset such as /Group A/Group B/Group B/Group B/Group B/Dataset2.




Figure 1: An HDF5 file with a strictly hierarchical group structure




Figure 2: An HDF5 file with a directed graph group structure, including a circular reference




Figure 3: An HDF5 file with a directed graph group structure and one group as a member of itself

HDF5 Groups HDF5 User's Guide

As becomes apparent upon reflection, directed graph structures can become quite complex; caution is advised!

The balance of this chapter discusses the following topics:

- The HDF5 group object (or a group) and its structure in more detail
- HDF5 link objects (or links)
- The programming model for working with groups and links
- HDF5 functions provided for working with groups, group members, and links
- Retrieving information about objects in a group
- Discovery of the structure of an HDF5 file and the contained objects
- Examples of file structures

2. Description of the Group Object

2.1 The Group Object

Abstractly, an HDF5 group contains zero or more objects and every object must be a member of at least one group. The root group, the sole exception, may not belong to any group.




Figure 4: Abstract model of the HDF5 group object

Group membership is actually implemented via *link* objects (see Figure 4). A link object is owned by a group and points to a *named object*. Each link has a *name*, and each link points to exactly one object. Each named object has at least one and possibly many links to it.

There are three classes of named objects: *group*, *dataset*, and *named datatype* (see Figure 5). Each of these objects is the member of at least one group, which means there is at least one link to it.




Figure 5:

The primary operations on a group are to add and remove members and to discover member objects. These abstract operations, as listed in Figure 6, are implemented in the H5G APIs, as listed in section 4, "Group Function Summaries."

To add and delete members of a group, links from the group to *existing* objects in the file are created and deleted with the *link* and *unlink* operations. When a *new* named object is created, the HDF5 Library executes the link operation in the background immediately after creating the object (i.e., a new object is added as a member of the group in which it is created without further user intervention).

Given the name of an object, the *get_object_info* method retrieves a description of the object, including the number of references to it. The *iterate* method iterates through the members of the group, returning the name and type of each object.

Group
size:size_t
create()
open()
close()
<pre>link() unlink() move()</pre>
<pre>iterate() get_object_info() get_link_info()</pre>

Figure 6: The group object

Every HDF5 file has a single root group, with the name /. The root group is identical to any other HDF5 group, except:

- The root group is automatically created when the HDF5 file is created (H5Fcreate).
- The root group has no parent, but, by convention has a reference count of 1.
- The root group cannot be deleted (i.e., unlinked)!

2.2 The Hierarchy of Data Objects

An HDF5 file is organized as a rooted, directed graph using HDF5 group objects. The named data objects are the nodes of the graph, and the links are the directed arcs. Each arc of the graph has a name, with the special name / reserved for the root group. New objects are created and then inserted into the graph with a link operation tht is automatically executed by the library; existing objects are inserted into the graph with a link operation explicitly called by the user, which creates a named link from a group to the object. An object can be the target of more than one link.

The names on the links must be unique within each group, but there may be many links with the same name in different groups. These are unambiguous, because some ancestor must have a different name, or else they are the same object. The graph is navigated with path names, analogous to Unix file systems (see section 2.3, "HDF5 Path Names"). An object can be opened with a full path starting at the root group, or with a relative path and a starting point. That starting point is always a group, though it may be the current working group, another specified group, or the root group of the file. Note that all paths are relative to a single HDF5 file. In this sense, an HDF5 file is analogous to a single UNIX file system. ¹

It is important to note that, just like the UNIX file system, HDF5 objects do not have *names*, the names are associated with *paths*. An object has an *object identifier* that is unique within the file, but a single object may have many *names* because there may be many paths to the same object. An object can be renamed, or moved to another group, by adding and deleting links. In this case, the object itself never moves. For that matter, membership in a group has no implication for the physical location of the stored object.

Deleting a link to an object does not necessarily delete the object. The object remains available as long as there is at least one link to it. After all links to an object are deleted, it can no longer be opened, although the storage may or may not be reclaimed. ²

It is also important to realize that the linking mechanism can be used to construct very complex graphs of objects. For example, it is possible for object to be shared between several groups and even to have more than one name in the same group. It is also possible for a group to be a member of itself, or to create other *cycles* in the graph, such as in the case where a child group is linked to one of its ancestors.

HDF5 also has *soft links* similar to UNIX soft links. A *soft link* is an object that has a name and a path name for the target object. The soft link can be followed to open the target of the link just like a regular or *hard* link. The differences are that the hard link cannot be created if the target object does not exist and it always points to the same object. A soft link can be created with any path name, whether or not the object exists; it may or may not, therefore, be possible to follow a soft link. Furthermore, a soft link's target object may be changed.

2.3 HDF5 Path Names

The structure of the HDF5 file constitutes the name space for the objects in the file. A path name is a string of components separated by slashes (/). Each component is the name of a hard or soft link which points to an object in the file. The slash not only separates the components, but indicates their hierarchical releationship; the component indicated by the link name following a slash is a always a member of the component indicated by the link name preceding that slash.

The first component in the path name may be any of the following:

- the special character dot (., a period), indicating the current group
- the special character slash (/), indicating the root group
- any member of the current group

Component link names may be any string of ASCII characters not containing a slash or a dot (/ and ., which are reserved as noted above). However, users are advised to avoid the use of punctuation and non-printing characters, as they may create problems for other software. Figure 7 provides a BNF grammar for HDF5 path names.

```
PathName ::= AbsolutePathName | RelativePathName | Separator ::= "/" ["/"]*
AbsolutePathName ::= Separator [ RelativePathName ] RelativePathName ::= Component [ Separator RelativePathName ]*
Component ::= "." | Characters
Characters ::= Character+ - { "." }
Character ::= {c: c î { legal ASCII characters } - {'/'} }
```

Figure 7: A BNF grammar for for HDF5 path names




Figure 8: An HDF5 file with a directed graph group structure, including a circular reference

An object can always be addressed by a either a *full or absolute* path name, starting at the root group, or by a *relative* path name, starting in a known location such as the current working group. As noted elsewhere, a given object may have multiple full and relative path names.

Consider, for example, the file illustrated in Figure 8. Dataset1 can be identified by either of these absolute path names:

```
/GroupA/Dataset1
/GroupA/GroupB/GroupC/Dataset1
```

Since an HDF5 file is a directed graph structure, and is therefore not limited to a strict tree structure, and since this illustrated file includes the sort of circular reference that a directed graph enables, Dataset1 can also be identified by this absolute path name:

```
/GroupA/GroupB/GroupC/GroupA/Dataset1
```

Alternatively, if the current working location is GroupB, Dataset1 can be identified by either of these relative path names:

```
GroupC/Dataset1
GroupC/GroupA/Dataset1
```

Note that relative path names in HDF5 do not employ the . . / notation, the UNIX notation indicating a parent directory, to indicate a parent group.

3. Using h5dump

You can use h5dump, the command-line utility distributed with HDF5, to examine a file for purposes either of determining where to create an object within an HDF5 file or to verify that you have created an object in the intended place. inspecting the contents of an HDF5 file.

In the case of the new group created in section 5.1, "Creating a group," the following h5dump command will display the contents of FileA.h5:

h5dump FileA.h5

Assuming that the discussed objects, GroupA and GroupB are the only objects that exist in FileA.h5, the output will look something like the following:

```
HDF5 "FileA.h5" {
GROUP "/" {
GROUP GroupA {
GROUP GroupB {
}
}
}
```

h5dump is fully described on the Tools page of the *HDF5 Reference Manual*. The HDF5 DDL grammar is fully described in the document DDL in BNF for HDF5, an element of this *HDF5 User's Guide*.

4. Group (H5G) Function Summaries

C Function Purpose F90 Function H5Gcreate Creates a new empty group and gives it a name. h5qcreate f H5Gopen Opens an existing group for modification and returns a group identifier for that group. h5qopen f Closes the specified group. H5Gclose h5gclose_f H5Gset comment Sets the comment for the specified object. h5gset_comment_f H5Gget_comment Retrieves the comment for the specified object. h5gget_comment_f H5Glink Creates a link of the specified type from a new name to a current h5glink_f name. H5Glink2 Creates a link of the specified type from a new name to a current h5glink2_f name. H5Gunlink Removes a link to an object from a group. h5qunlink f Renames an object within an HDF5 file. H5Gmove h5qmove f Renames an object within an HDF5 file. H5Gmove2 h5gmove2_f H5Giterate Iterates an operation over the entries of a group. (none) (none) Returns the name and type of a specified group member. h5gget_obj_info_idx_f (none) Returns the number of group members. h5gn_members_f H5Gget_objinfo Returns information about an object. (none) H5Gget_num_objs Returns number of objects in the specified group. (none) H5Gget_objname_by_idx Returns a name of an object specified by its index. (none) H5Gget_objtype_by_idx Returns the type of an object specified by its index. (none) H5Gget linkval Returns the name of the object that the specified symbolic link h5gget_linkval_f points to.

5. Programming Model: Working with Groups

The programming model for working with groups is as follows:

- 1. Create a new group or open an existing one.
- 2. Perform the desired operations on the group.
 - ♦ Create new objects in the group.
 - ♦ Insert existing objects as group members.
 - ♦ Delete existing members.
 - ♦ Open and close member objects.
 - ♦ Access information regarding member objects.
 - ♦ Iterate across group members.
 - ♦ Manipulate links.
- 3. Terminate access to the group. (Close the group.)

5.1 Creating a Group

To create a group, use H5Gcreate, specifying the location and the path of the new group. The location is the identifier of the file or the group in a file with respect to which the new group is to be identified. The path is a string that provides wither an absolute path or a relative path to the new group (see section 2.3, "HDF5 Path Names"). A path that begins with a slash (/) is an absolute path indicating that it locates the new group from the root group of the HDF5 file. A path that begins with any other character is a relative path. When the location is a file, a relative path is a path from that file's root group; when the location is a group, a relative path is a path from that group.

The sample code in Figure 9 creates three groups. The group Data is created in the root directory; two groups are then created in /Data, one with absolute path, the other with a relative path.

```
hid_t file;
file = H5Fopen(...);
group = H5Gcreate(file, "/Data", 0);
group_new1 = H5Gcreate(file, "/Data/Data_new1", 0);
group_new2 = H5Gcreate(group, "Data_new2", 0);
```

Figure 9: Creating three new groups

The third H5Gcreate parameter optionally specifies how much file space to reserve to store the names that will appear in this group. If a non-positive value is supplied, a default size is chosen.

5.2 Opening a group and accessing an object in that group

Though it is not always necessary, it is often useful to explicitly open a group when working with objects in that group. Using the file created in the example above, Figure 10 illustrates the use of a previously-acquired file identifier and a path relative to that file to open the group Data.

Any object in a group can be also accessed by its absolute or relative path. To open an object using a relative path, an application must first open the group or file on which that relative path is based. To open an object using an absolute path, the application can use any location identifier in the same file as the target object; the file identifier is commonly used, but object identifier for any object in that file will work. Both of these approaches are illustrated in Figure 10 offers example code in the first two lines to open a group then open a dataset with the appropriate relative path to open the same dataset with an absolute path and .

Using the file created in the examples above, Figure 10 provides example code illustrating the use of both relative and absolute paths to access an HDF5 data object. The first sequence (two function calls) uses a previously-acquired file identifier to open the group Data then uses the returned group identifier and a relative path to open the dataset CData. The second approach (one function call) uses the same previously-acquired file identifier and an absolute path to open the same dataset.

```
group = H5Gopen(file, "Data");
dataset1 = H5Dopen(group, "CData");
dataset2 = H5Dopen(file, "/Data/CData");
```

Figure 10: Open a dataset with relative and absolute paths

5.3 Creating a dataset in a specific group

Any dataset must be created in a particular group. As with groups, a dataset may be created in a particular group by specifying its absolute path or a relative path. Figure 11 illustrates both approaches to creating a dataset in the group /Data.

Figure 11: Create a dataset with absolute and relative paths

5.4 Closing a group

To ensure the integrity of HDF5 objects and to release system resources, an application should always call the appropriate close function when it is through working with an HDF5 object. In the case of groups, H5Gclose ends access to the group and releases any resources the HDF5 Library has maintained in support of that access, including the group identifier.

As illustrated in Figure 12, all that is required for an H5Gclose call is the group identifier acquired when the group was opened; there are no relative versus absolute path considerations.

```
herr_t status;
status = H5Gclose(group);
```

Figure 12: Close a group

A non-negative return value indicates that the group was successufly closed and the resources released; a negative return value indicates that the attempt to close the group or release resources failed.

5.5 Creating Links

As previously mentioned, every object is created in a specific group. Once created, an object can be made a member of additional groups by means of links created with H5Glink or H5Glink2.

A link is, in effect, is a path by which the target object can be accessed; it therefore has a name which functions as a single path component. A link can be removed with an H5Gunlink call, effectively removing the target object from the group that contained the link (assuming, of course, that the removed link was the only link to the target object in the group).

Hard links

There are two kinds of links, hard links and soft links. Hard links are reference counted; soft links are not. When an object is created, a hard link is automatically created. An object can be deleted from the file by removing all the hard links to it.

Working with the file from the previous examples, the code in Figure 13 illustrates the creation of a hard link, named Data_link, in the root group, /, to the group Data. Once that link is created, the dataset Cdata can be accessed via either of two absolute paths, /Data/Cdata or /Data_Link/Cdata.

```
status = H5Glink(file, H5G_LINK_HARD, "Data", "Data_link");
dataset1 = H5Dopen(file, "/Data_link/CData");
dataset2 = H5Dopen(file, "/Data/CData");
```

Figure 13

This and subsequent examples could also use H5Glink2, which is used exactly like H5Glink except that a second location identifier is specified and the new object name is specified relative to the second location identifier.

Figure 14 shows example code to delete a link, deleting the hard link Data from the root group. The group /Data and its members are still in the file, but they can no longer be accessed via a path using the component /Data.

When the last hard link to an object is deleted, the object is no longer accessible (although space in the file may not be deallocated). Figure 15 shows deletion of the last link, Data_link, to the group originally called Data. After the unlinking operation, the group is no longer accessible; consequently, the dataset Cdata is inaccessible.

Soft links

Soft links are objects that assign a name in a group to a path. Notably, the target object is determined only when the soft link is accessed, and may, in fact, not exist. Soft links are not reference counted, so there may be one or more soft links to an object.

Like hard links, soft links are also created and deleted with the H5Glink, H5Glink2, and H5Gunlink functions, except that soft links are created as type H5G_LINK_SOFT while hard links are created as type H5G_LINK HARD.

Returning to our sample file as it was initially created, Figure 16 shows examples of creating two soft links to the group /Data.

```
status = H5Glink(file, H5G_LINK_SOFT, "Data", "Soft2");
status = H5Glink(file, H5G_LINK_SOFT, "Soft2", "Soft3");
dataset = H5Dopen(file, "/Soft2/CData");
```

Figure 16

With the soft links defined in Figure 16, the dataset CData in the group /Data can now be opened with any of the names /Data/CData, /Soft2/CData, or /Soft2/CData.

Not regarding hard links versus soft links

Note that an object's existence in a file is governed by the presence of at least one hard link to that object. If the last hard link to an object is removed, the object is removed from the file and any remaining soft link becomes a dangling link, a link whose target object does not exist.

Moving or renaming objects, and a warning

An object can be renamed by changing the name of a link to it with either H5Gmove or H5Gmove 2. This has the same effect as creating a new link with the new name and deleting the link with the old name.

Exercise caution in the use of H5Gmove, H5Gmove2 and H5Gunlink as these functions each include a step that unlinks a pointer to a dataset or group. If the link that is removed is on the only path leading to an HDF5 object, that object will become permanently inaccessible in the file.

Consider the following example: assume that the group 2 can only be accessed via the following path, where top_group is a member of the file's root group:

```
/top_group/group1/group2/
```

Using H5Gmove or H5Gmove2, top_group is renamed to be a member of group2. At this point, since top_group was the only route from the root group to group1, there is no longer a path by which one can access group1, group2, or any member datasets. And since top_group is now a member of group2, top group itself and any member datasets have thereby also become inaccessible.

6. Discovering Information about Objects

There is often a need to retrieve information about a particular object. The H5Gget_objinfo function fills this niche by returning a description of the specified object in an H5G_stat_t structure. The structure contains the following information:

- The file and object identifiers, which together provide unique identification of the object
- The number of references, or hard links, to the object
- The object type: group, dataset, named datatype, or soft link, returned as H5G_GROUP, H5G_DATASET, H5G_TYPE, or H5G_LINK, respectively
- The modification time (datasets only)
- A link length value; the length of the path name of a symbolic link's target object (returned for symolic links, or soft links, only)

The H5G_stat_t structure specification and the H5Gget_objinfo function signature appear in Figure 17. The H5G_stat_t structure elements are as listed above. The H5Gget_objinfo function parameters are used follows:

- loc id specifies the object for which information being sought.
- A path to the object is returned in name.
- follow_link is a Boolean value specifying whether to follow a soft link and open the target object (TRUE) or not (FALSE).
- The H5G_stat_t struct is returned in the *statbuf* buffer.

```
typedef struct H5G_stat_t {
          unsigned long fileno[2];
          unsigned long objno[2];
          unsigned nlink;
          int type;
          time_t mtime;
          size_t linklen;
     } H5G_stat_t

herr_t H5Gget_objinfo(hid_t loc_id, const char *name, hbool_t follow_link, H5G_stat_t *statbuf )
```

Figure 17: The H5G_stat_t struct specification and the H5Gget_objinfo function signature

Figure 18 provides a code example that prints the local paths to the members of a group, following a soft link when it is found.

```
H5G_stat_t statbuf;
H5Gget_objinfo(loc_id, name, FALSE, &statbuf);
switch (statbuf.type) {
case H5G_GROUP:
     printf(" Object with name %s is a group \n", name);
     break;
case H5G_DATASET:
    printf(" Object with name %s is a dataset \n", name);
case H5G_TYPE:
     printf(" Object with name %s is a named datatype \n", name);
     break;
case H5G_LINK:
    lname = (char *)malloc(statbuf.linklen);
     H5Gget_linkval(loc_id, name, statbuf.linklen, lname);
     printf(" Object with name %s is a link to %s \n", name, lname);
     H5Gget_objinfo(loc_id, name, TRUE, &statbuf);
     switch (statbuf.type) {
         case H5G_GROUP:
             printf(" Target of link name %s is a group \n", name);
        case H5G_DATASET:
             printf(" Target of link name %s is a dataset \n", name);
             break;
        case H5G_TYPE:
             printf(" Target of link name %s is a named datatype \n", name);
       case H5G_LINK:
            printf(" Target of link name %s is a soft link \n", name);
            break;
       default:
          printf(" Unable to identify target ");
       }
      break;
default:
     printf(" Unable to identify an object ");
```

Figure 18: Printing a specified object's name and type and, in the case of a link, opening the target object

7. Discovering Objects in a Group

There are two means of examining all the objects in a group. The first, H5Giterate, is discussed below H5Giterate is useful both with a single group and in an iterative process that examines an entire file or section of a file (the contents of a group, the contents of all the groups that are members of that group, etc.) and acts on objects as they are encountered.

An alternative approach is to determine the number of objects in a group then approach them one at a time. This is accomplished with the functions H5Gget_num_objs, H5Gget_objname_by_idx, and H5Gget_objtype_by_idx.

H5Gget_num_objs retrieves the number of objects, say n, in the group. The values from 0 through n-1 can then be used as indices to access the members of the group. For example, an index value of 0 identifies the first member, an index value of 1 identifies the second member, and an index value of n-1 identifies the last member. (Note that HDF5 objects do not have permanent indices; these values are strictly transient and may be different each time a group is opened.)

Using the index described above, the name and object type can be retrieved using H5Gget_objname_by_idx and H5Gget_objtype_by_idx, respectively. With the name and object type, an application can proceed to operate as necessary on all or selected group members.

8. Discovering All the Objects in the File

The structure of an HDF5 file is self-describing, meaning that an application can navigate an HDF5 file to discover and understand all the objects it contains. This is an iterative process wherein the structure is traversed as a graph, starting at one node and recursively visiting linked nodes. To explore the entire file, the traversal should start at the root group.

The function H5Giterate, used to discover the members of a group, is the key to the discovery process. An application calls H5Giterate with a pointer to a callback function (see Figure 19). The HDF5 Library iterates through the group specified by the loc_id and name parameters, calling the callback function once for each group member. The callback function must have the signature defined by H5G_iterate_t. When invoked, the arguments to the callback function are the group being iterated, the group member's name (the object name), and a pointer set by the user program. The callback function is part of the application, so it can execute any actions the program requires to discover and store information about the objects.

Figure 19

Note that the H5Giterate function follows the links from a single group and that these links correspond to the components in a path name. To iterate over an entire substructure, H5Giterate must be called recursively on every member of the original group that turns out to also be a group. To iterate over an entire file, the first call to H5Giterate must iterate over the root group; subsequent calls to H5Giterate must then iterate over every subsequent group.

Figure 20 illustrates the relationship between the calling module of the application, the callback function (do_obj), and calls to the HDF5 Library. In this diagram, "Global Variables and Functions" symbolizes the fact that the callback function executes as part of the application, and may therefore call functions and update data structures to describe the file and its objects.




Figure 20: Relationships between a calling module, the callback function, and the callback function's calls back to the HDF5 library

Figure 21 illustrates the sequence of events precipitated by an H5Giterate call.

1. The application first calls H5Giterate, passing a pointer to a callback function (do_obj in the figure). Note that the callback function is part of the application.

- 2. The HDF5 Library then iterates through the members of the group, calling the callback function in the application once for each group member.
- 3. When the iteration is complete, the H5Giterate call returns to the calling application.




Figure 21

Figure 22 shows the sequence of calls involved in one iteration of a callback function that employs the HDF5 function H5Gget_objinfo to discover properties of the object that is the subject of the current step of the iteration (e.g., the object's type and reference count). The HDF5 Library then calls the application's callback function do_obj(), which in turn calls the HDF5 Library to get the object information. The callback function can process the information as needed, accessing any function or data structure of the application program, and it can call the HDF5 Library again to, for example, iterate through a group member that is itself a group.




Figure 22

Over the course of a successful H5Giterate call, the HDF5 Library will call the application's callback function once for each member of the group, as illustrated in Figure 23. At each iteration, the callback function must return a status which implies a subsequent course of action:

- 1 Continue iterating.
- 0 Stop iterating and return to the caller.

Once the iteration has been completed, H5Giterate returns to the calling application.




Figure 23

The overall sequence of calls can become quite complex, especially when the callback function in turn calls the HDF5 Library. Figure 24 provides a sequence diagram for a case similar to the simple case described above:

- 1. The calling program invokes H5Giterate on a group,
- 2. which calls do_obj once for each group members (three group members in this case).
- 3. The *do_obj* callback function in turn calls H5Gget_objinfo each time it is invoked to discover information about each object.






Figure 24

Recursively iterating through the members of every group will result in visiting an object once for each link to it. This may result in visiting an object more than once. The calling application must be prepared to recognize this case and handle it appropriately. If an action should be undertaken only once per object, the application must make sure that it does not repeat the action for an object with two links. For example, if the objects are being copied, it is important that an object with two names be copied once, not twice. Figure 25 illustrates this case.



a) The required action is to copy all the objects from one file to another.



b) A shared dataset should not be copied twice.

c) A shared dataset should be copied once and the apppropriate link should be created.

Figure 25





Figure 26


There is a second important case when the twice-visited member is a group. Any group with more than one link to it can potentially be part of a circular path. I.e., recursively iterating through member groups may eventually bring the the iteration back to the current group and may generate an infinite path within the file's linked structure. To embark upon the resulting infinite iteration would clearly be unacceptable in the general case. Figure 26 illustrates an HDF5 file with such potential.

In such a case, the callback function should check the reference count in the H5G_stat_t buffer as returned by $H5Gget_objinfo$. If the count is greater than one, there is more than one path to the object in question and it may be in a loop; the program should act accordingly. For example, it may be necessary to construct a global table of all the objects visited. Note that the object's name is not unique, but the full path and the object number (found in the above-mentioned H5G_stat_t buffer) are unique within an individual HDF5 file.


9. Examples of File Structures

This section presents several samples of HDF5 file structures.






a) The file contains three groups: the root group, /group1, and /group2.



b) The dataset dset1 (or /group1/dset1) is created in /group1.




c) A link named dset2 to the same dataset is created in /group2.


d) The link from /group1 to dset1 is removed. The dataset is still in the file, but can be accessed only as /group2/dset2.

Figure 27

Figure 27 shows examples of the structure of a file with three groups and one dataset. The file in Figure 27a contains three groups: the root group and two member groups. In Figure 27b, the dataset dset1 has been created in /group1. In Figure 27c, a link named dset2 from /group2 to the dataset has been added. Note that there is only one copy of the dataset; there are two links to it and it can be accessed either as /group1/dset1 or as /group2/dset2.


Figure 27d illustrates that one of the two links to the dataset can be deleted. In this case, the link from /group1 has been removed. The dataset itself has not been deleted; it is still in the file but can only be accessed as /group1/dset2.






a) dset1 has two names: /group2/dset1 and /group1/GXX/dset1.

b) dset1 again has two names: /group1/dset1 and /group1/dset2.





c) dset1 has three names: /group1/dset1, /group2/dset2, and /group1/GXX/dset2.

d) dset1 has an infinite number of available path names.


Figure 28

Figure 28 illustrates loops in an HDF5 file structure. The file in Figure 28a contains three groups and a dataset; group2 is a member of the root group and of the root group's other member group, group1. group2 thus can be accessed by either of two paths: /group2 or /group1/GXX. Similarly, the dataset can be accessed either as /group2/dset1 or as /group1/GXX/dset1.


Figure 28b illustrates a different case: the dataset is a member of a single group but with two links, or names, in that group. In this case, the dataset again has two names, /group1/dset1 and /group1/dset2.

In Figure 28c, the dataset dset1 is a member of two groups, one of which can be accessed by either of two names. The dataset thus has three path names: /group1/dset1, /group2/dset2, and /group1/GXX/dset2.


And in Figure 28d, two of the groups are members of each other and the dataset is a member of both groups. In this case, there are an infinite number of paths to the dataset because GXX and GYY can be traversed any number of times on the om the root group, /, way frto the dataset. This can yield a path name such as /group1/GXX/GYY/GXX/GYY/GXX/dset2.




a) The file contains only hard links.



c) A soft link named dset3 is added with a target that does not yet exist.



b) A soft link is added from group2 to /group1/dset1.



d) Tht target of soft link is created or linked.

Figure 29

Figure 29 takes us into the realm of soft links. The original file, in Figure 29a, contains only three hard links. In Figure 29b, a soft link named dset2 from group2 to /group1/dset1 has been created, making this dataset accessible as /group2/dset2.

In Figure 29c, another soft link has been created in group 2. But this time the soft link, dset 3, points to a target object that does not yet exist. That target object, dset, has been added in Figure 29d and is now accessible as either /group 2/dset or /group 2/dset 3.

¹It could be said that HDF5 extends the organizing concepts of a file system to the internal structure of a single file.

²As of HDF5-1.4, the storage used for an object is reclaimed, even if all links are deleted.

HDF5 User's Guide HDF5 Datasets

Chapter 5 HDF5 Datasets

1. Introduction

An HDF5 dataset is an object composed of a collection of data elements, or raw data, and metadata that stores a description of the data elements, data layout, and all other information necessary to write, read, and interpret the stored data. From the viewpoint of the application the raw data is stored as a one-dimensional or multi-dimensional array of elements (the *raw data*), those elements can be any of several numerical or character types, small arrays, or even compound types similar to C structs. The dataset object may have attribute objects.




Figure 1

A dataset objects is stored in a file in two parts: a header and a data array. The header contains information that is needed to interpret the array portion of the dataset, as well as metadata (or pointers to metadata) that describes or annotates the dataset. Header information includes the name of the object, its dimensionality, its number-type, information about how the data itself is stored on disk (the *storage layout*), and other information used by the library to speed up access to the dataset or maintain the file's integrity.

The HDF5 dataset interface, comprising the H5D functions, provides a mechanism for managing HDF5 datasets, including the transfer of data between memory and disk and the description of dataset properties.

A dataset is used by other HDF5 APIs, either by name or by a handle (e.g., returned by H5Dopen).

HDF5 Datasets HDF5 User's Guide

Link/Unlink

A dataset can be added to a group with the H5Glink call, and deleted from a group with H5Gunlink. The link and unlink operations use the name of an object, which may be a dataset. The dataset does not have to open to be linked or unlinked.

Object reference

A dataset may be the target of an object reference. The object reference is create by H5Rcreate, with the name of an object which may be a dataset and the reference type H5R_OBJECT. The dataset does not have to be open to create a reference to it.

An object reference may also refer to a region (selection) of a dataset. The reference is created with H5Rcreate and a reference type of H5R_DATASET_REGION.

An object reference can be accessed by a call to H5Rdereference. When the reference is to a dataset or dataset region, the H5Rdeference call returns a handle to the dataset, just as if H5open has been called.

Adding attributes

A dataset may have user defined attributes, which are created with H5Acreate, and accessed through the H5A API. To create an attribute for a dataset, the dataset must be open, and the handle is passed to H5Acreate. The attributes of a dataset are discovered, and opened using H5Aopen_name, H5Aopen_idx, or H5Aiterate; which use the handle of the dataset. An attribute can be deleted with H5Adelete, which uses the handle of the dataset.

HDF5 User's Guide HDF5 Datasets

2. Dataset (H5D) Function Summaries

h5dfill_f

C Function Purpose F90 Function H5Dcreate Creates a dataset at the specified location. h5dcreate f H5Dopen Opens an existing dataset. h5dopen_f H5Dclose Closes the specified dataset. h5dclose f Returns an identifier for a copy of the dataspace for a dataset. H5Dget_space h5dget_space_f H5Dget_space_status Determines whether space has been allocated for a dataset. h5dget_space_status_f H5Dget_type Returns an identifier for a copy of the datatype for a dataset. h5dget_type_f H5Dget_create_plist Returns an identifier for a copy of the dataset creation property list h5dget_create_plist_f for a dataset. H5Dget_offset Returns dataset address in file. h5dget_offset_f H5Dget_storage_size Returns the amount of storage required for a dataset. h5dget storage size f H5Dvlen get buf size Determines the number of bytes required to store VL data. h5dvlen_get_max_len_f H5Dvlen reclaim Reclaims VL datatype memory buffers. (none) H5Dread Reads raw data from a dataset into a buffer. h5dread f H5Dwrite Writes raw data from a buffer to a dataset. h5dwrite f Iterates over all selected elements in a dataspace. H5Diterate (none) Extends dataset dimensions. H5Dextend h5dextend f H5Dfill Fills dataspace elements with a fill value in a memory buffer.

HDF5 Datasets HDF5 User's Guide

Dataset creation property list functions

C Function F90 Function	Purpose
H5Pset_layout h5pset_layout_f	Sets the type of storage used to store the raw data for a dataset.
H5Pget_layout h5pget_layout_f	Returns the layout of the raw data for a dataset.
H5Pset_chunk h5pset_chunk_f	Sets the size of the chunks used to store a chunked layout dataset.
H5Pget_chunk h5pget_chunk_f	Retrieves the size of chunks for the raw data of a chunked layout dataset.
H5Pset_deflate h5pset_deflate_f	Sets compression method and compression level.
H5Pset_fill_value h5pset_fill_value_f	Sets the fill value for a dataset.
H5Pget_fill_value h5pget_fill_value_f	Retrieves a dataset fill value.
H5Pfill_value_defined (none)	Determines whether fill value is defined.
H5Pset_fill_time h5pset_fill_time_f	Sets the time when fill values are written to a dataset.
H5Pget_fill_time h5pget_fill_time_f	Retrieves the time when fill value are written to a dataset.
H5Pset_alloc_time h5pset_alloc_time_f	Sets the timing for storage space allocation.
H5Pget_alloc_time h5pget_alloc_time_f	Retrieves the timing for storage space allocation.
H5Pset_filter h5pset_filter_f	Adds a filter to the filter pipeline.
H5Pall_filters_avail (none)	Verifies that all required filters are available.
H5Pget_nfilters h5pget_nfilters_f	Returns the number of filters in the pipeline.
H5Pget_filter h5pget_filter_f	Returns information about a filter in a pipeline.
H5Pget_filter_by_id h5pget_filter_by_id_f	Returns information about the specified filter.
H5Pmodify_filter h5pmodify_filter_f	Modifies a filter in the filter pipeline.
H5Premove_filter h5premove_filter_f	Delete one or more filters in the filter pipeline.
H5Pset_fletcher32 h5pset_fletcher32_f	Sets up use of the Fletcher32 checksum filter.
H5Pset_nbit (none)	Sets up use of the n-bit filter.

HDF5 User's Guide HDF5 Datasets

H5Pset_scaleoffset Sets up use of the scale-offset filter.

(none)

H5Pset_shuffle Sets up use of the shuffle filter.

h5pset_shuffle_f

H5Pset_szip Sets up use of the Szip compression filter.

 $h5pset_szip_f$

H5Pset_external Adds an external file to the list of external files.

h5pset_external_f

H5Pget_external_count Returns the number of external files for a dataset.

h5pget_external_count_f

H5Pget_external Returns information about an external file.

h5pget_external_f

Dataset access property list functions

F90 Function

H5Pset_buffer Sets type conversion and background buffers.

Purpose

h5pset_buffer_f

C Function

H5Pget_buffer Reads buffer settings.

h5pget_buffer_f

H5Pset_preserve Sets the dataset transfer property list status to TRUE or FALSE.

h5pset_preserve_f

H5Pget preserve Checks status of the dataset transfer property list.

h5pget preserve f

H5Pset_edc_check Sets whether to enable error-detection when reading a dataset.

h5pset_edc_check_f

H5Pget_edc_check Determines whether error-detection is enabled for dataset reads.

h5pget_edc_check_f

H5Pset_filter_callback Sets user-defined filter callback function.

(none)

H5Pset data transform Sets a data transform expression.

(none)

H5Pget_data_transform Retrieves a data transform expression.

(none)

H5Pset_type_conv_cb Sets user-defined data type conversion callback function.

(none)

H5Pget_type_conv_cb Gets user-defined data type conversion callback function.

(none)

H5Pset_hyper_vector_size Sets number of I/O vectors to be read/written in hyperslab I/O.

h5pset_hyper_vector_size_f

h5pset_btree_ratios_f

H5Pget_hyper_vector_size Retrieves number of I/O vectors to be read/written in hyperslab

h5pget_hyper_vector_size_f

H5Pset_btree_ratios Sets B-tree split ratios for a dataset transfer property list.

HDF5 Datasets HDF5 User's Guide

H5Pget_btree_ratios h5pget_btree_ratios_f	Gets B-tree split ratios for a dataset transfer property list.
<pre>H5Pset_vlen_mem_manager (none)</pre>	Sets the memory manager for variable-length datatype allocation in H5Dread and H5Dvlen_reclaim.
<pre>H5Pget_vlen_mem_manager (none)</pre>	Gets the memory manager for variable-length datatype allocation in H5Dread and H5Dvlen_reclaim.
<pre>H5Pset_dxpl_mpio h5pset_dxpl_mpio_f</pre>	Sets data transfer mode.
<pre>H5Pget_dxpl_mpio h5pget_dxpl_mpio_f</pre>	Returns the data transfer mode.
<pre>H5Pset_dxpl_multi (none)</pre>	Sets the data transfer property list for the multi-file driver.
H5Pget_dxpl_multi (none)	Returns multi-file data transfer property list information.
H5Pset_multi_type (none)	Sets type of data property for MULTI driver.
<pre>H5Pget_multi_type (none)</pre>	Retrieves type of data property for MULTI driver.
H5Pset_small_data_block_size h5pset_small_data_block_size_f	Sets the size of a contiguous block reserved for small data.
H5Pget_small_data_block_size h5pget_small_data_block_size_f	Retrieves the current small data block size setting.

HDF5 User's Guide HDF5 Datasets

3. Programming Model

This section explains the programming model for a datasets.

3.1 General Model

The programming model for using a dataset has three main phases:

obtain access to the dataset operate on the dataset using the dataset handle returned above release the dataset. A dataset may be opened several times, and operations performed with several different handles to the same dataset. All the operations affect the dataset, although the calling program must synchronize if necessary to serialize accesses.

Note that the dataset remains open until the last handle is closed. Figure 2 shows the basic sequence of operations.




Figure 2

Creation and data access operations may have optional parameters which are set with property lists. The general programming model is:

- 1. create property list of appropriate class (dataset create, dataset transfer)
- 2. set properties as needed. Each type of property has its own format and datatype.
- 3. pass the property list as a parameter of the API call.

Step 1. Obtain Access

A new dataset is created by a call to H5Dcreate. If successful, the call returns a handle for the newly created dataset.

Access to an existing dataset is obtained by a call to H5Dopen. This call returns a handle for the existing dataset.

An object reference may be dereferenced to obtain a handle to the dataset it points to.

HDF5 Datasets HDF5 User's Guide

In each of these cases, the successful call returns a handle to the dataset. The handle is used in subsequent operations until it is closed.

Step 2. Operate on the Dataset

The dataset handle can be used to write and read data to the dataset, to query and set properties, and to perform other operations such as adding attributes, linking in groups, creating references, and so on.

The dataset handle can be used for any number of operations until it is closed.

Step 3. Close the Dataset

When all operations are completed, the dataset handle should be closed. This releases the dataset.

After the handle is closed, it cannot be used for further operations.

3.2 Create Dataset

A dataset is created and initialized with a call to H5Dcreate. The dataset create operation sets permanent properties of the dataset:

- name
- dataspace
- datatype
- storage properties

These properties cannot be changed for the life of the dataset, although the dataspace may be expanded up to its maximum dimensions.

Name

A dataset name is a sequence of alphanumeric ASCII characters. The full name would include a tracing of the group hierarchy from the root group of the file, e.g., /rootGroup/groupA/subgroup23/dataset1. The local name or relative name within the lowest-level group containing the dataset would include none of the group hierarchy. e.g., Dataset1.

Dataspace

The dataspace of a dataset defines the number of dimensions and the size of each dimension. The dataspace defines the number of dimensions, and the maximum dimension sizes and current size of each dimension. The maximum dimension size can be a fixed value or the constant H5D_UNLIMITED, in which case the actual dimension size can be incremented with calls to H5Dextend, up to the maximum set with the maxdims parameter in the H5Screate_simple call that established the dataset's original dimensions. The maximum dimension size is set when the dataset is created and cannot be changed.

Datatype

Raw data has a datatype, which describes the layout of the raw data stored in the file. The file datatype is set when the dataset is created and can never be changed. When data is transferred to and from the dataset, the HDF5 Library will assure that the data is transformed to and from the stored format.

Storage Properties

Storage properties of the dataset are set when it is created. Table 1 shows the categories of storage properties. The storage properties cannot be changed after the dataset is created. The storage properties are described below.

Filters

When a dataset is created, optional filters are specified. The filters are added to the data transfer pipeline when data is read or written. The standard library includes filters to implement compression, data shuffling, and error detection code. Additional user defined filters may also be used.

The required filters are stored as part of the dataset, and the list may not be changed after the dataset is created. The HDF5 Library automatically applies the filters whenever data is transferred.

Summary

A newly created dataset has no attributes and no data values. The dimensions, data type (in the file), storage properties, and selected filters are set. Table 1 lists the required inputs, Table 2 lists the optional inputs.

Table 1

Required inputs Description

Dataspace The shape of the array

Datatype The layout of the stored elements name The name of the dataset in the group

Table 2

Optional Setting Description

Storage Layout How the data is organized in the file, including chunking.

Fill value The behavior and value for uninitialized data.

External Storage (optional) Option to store the raw data in an external file.

Folders Select optional filters to be applied, e.g., compression.

Example

To create a new dataset

Set dataset characteristics. (Optional where default settings are acceptable)

Datatype

Dataspace

Dataset creation property list Create the dataset.

Close the datatype, dataspace, and property list. (As necessary)

Close the dataset.

Figure 3 shows example code to create an empty dataset. The dataspace is 7 X 8, the datatype is a big endian integer. The dataset is created with the name "dset1", it is a member of the root group, "/".

```
hid_t
        dataset, datatype, dataspace;
  * Create dataspace: Describe the size of the array and
 * create the data space for fixed-size dataset.
dimsf[0] = 7;
 dimsf[1] = 8;
 dataspace = H5Screate_simple(2, dimsf, NULL);
  * Define datatype for the data in the file.
  * For this example, store little-endian integer numbers.
 datatype = H5Tcopy(H5T_NATIVE_INT);
 status = H5Tset_order(datatype, H5T_ORDER_LE);
  * Create a new dataset within the file using defined
  * dataspace and datatype. No properties are set.
 dataset = H5Dcreate(file, "/dset", datatype, dataspace, H5P_DEFAULT);
H5Dclose(dataset);
 H5Sclose(dataspace);
 H5Tclose(datatype);
```

Figure 3

Figure 4 shows example code to create a similar dataset with a fill value of '-1'. This code has the same steps as in Figure 3, but uses a non-default property list. A file creation property list is created, and then the fill value is set to the desired value. Then the property list is passed to the H5Dcreate call.

```
hid t
        dataset, datatype, dataspace;
hid_t plist; /* property list */
int fillval = -1;
dimsf[0] = 7;
dimsf[1] = 8;
dataspace = H5Screate_simple(2, dimsf, NULL);
datatype = H5Tcopy(H5T_NATIVE_INT);
 status = H5Tset_order(datatype, H5T_ORDER_LE);
 * Example of Dataset Creation property list: set fill value to '-1'
plist = H5Pcreate((H5P_DATASET_CREATE);
status = H5Pset_fill_value(plist,datatype, &fillval);
/* Same as above, but use the property list */
dataset = H5Dcreate(file, "/dset", datatype, dataspace, plist);
H5Dclose(dataset);
H5Sclose(dataspace);
H5Tclose(datatype);
H5Pclose(plist);
```

Figure 4

After this code is executed, the dataset has been created and written to the file. The data array is uninitialized. Depending on the storage strategy and fill value options that have been selected, some or all of the space may be allocated in the file, and fill values may be written in the file.


3.3 Data Transfer Operations on a Dataset

Data is transferred between from memory and the raw data array of the dataset through H5Dwrite and H5Dread operations. A data transfer has the following basic steps:

- 1. allocate and initialize memory space as needed
- 2. define the datatype of the memory elements
- 3. define the elements to be transferred (a selection, or all the elements)
- 4. set data transfer properties (including parameters for filters or file drivers) as needed
- 5. call the H5D API

Note that the location of the data in the file, the datatype of the data in the file, the storage properties, and the filters do not need to be specified, because these are stored as a permanent part of the dataset. A selection of elements from the dataspace is specified, which may be the whole dataspace.

Figure 5 shows a diagram of a write operation, which transfers a data array from memory to a dataset in the file (usually on disk). A read operation has similar parameters, with the data flowing the other direction.



Memory Space

The calling program must allocate sufficient memory to store the data elements to be transferred. For a write (from memory to the file), the memory must be initialized with the data to be written to the file. For a read, the memory must be large enough to store the elements that will be read. The amount of storage needed can be computed from the memory datatype (which defines the size of each data element) and the number of elements in the selection.

Memory Datatype

The memory layout of a single data element is specified by the memory datatype. This specifies the size, alignment, and byte order of the element, as well as the datatype class. Note that the memory data type must be the same datatype class as the file, but may have different byte order and other properties. The HDF5 Library automatically transforms data elements between the source and destination layouts. See the chapter "HDF5 Datatypes" for more details.

For a write, the memory datatype defines the layout of the data to be written, e.g., IEEE floating point numbers in native byte order. If the file datatype (defined when the dataset is created) is different but compatible, the HDF5 Library will transform each data element when it is written. For example, if the file byte order is different than the native byte order, the HDF5 Library will swap the bytes.

For a read, the memory datatype defines the desired layout of the data to be read. This must be compatible with the file datatype, but should generally use native formats, e.g., byte orders. The HDF5 Library will transform each data element as it is read.

Selection

The data transfer will transfer some or all of the elements of the dataset, depending on the dataspace selection. The selection is two dataspace objects (one for the source, and one for the destination) which describe which elements of the dataspace to be transferred, which may be all of the data, or just some elements (partial I/O). Partial I/O is defined by defining hyperslabs or lists of elements in a dataspace object.

The dataspace selection for the source defines the indices of the elements to be read, the dataspace selection for the destination defines the indices of the elements to be written. The two selections must define the same number of points, but the order and layout may be different. The HDF5 Library automatically selects and distributes the elements, according to the selections, e.g., to perform a scatter-gather or sub-set of the data.

Data Transfer Properties

For some data transfers, additional parameters should be set using the transfer property list. Table 2 lists the categories of transfer properties. These properties set parameters for the HDF5 Library, and may be used to pass parameters for optional filters and file drivers. For example, transfer properties are used to select independent or collective operation when using MPI-I/O.

Table 3

Properties Description

Library parameters Internal caches, buffers, B-Trees, etc.

Memory management Variable length memory management, data overwrite

File driver management Parameters for file drivers
Filter management Parameters for filters

Data Transfer Operation (read or write)

The data transfer is done by calling H5Dread or H5Dwrite with the parameters described above. The HDF5 Library constructs the required pipe-line, which will scatter-gather, transform data types, apply the requested filters, and use the correct file driver.

During the data transfer, the transformations and filters are applied to each element of the data, in the required order, until all the data is transferred.

Summary

To perform a data transfer, it is necessary to allocate and initialize memory, describe the source and destination, set required and optional transfer properties, and call the H5D API.

Examples

The basic procedure to write to a dataset

Open the dataset.

Set dataset dataspace of write. (Optional if dataspace is H5S_SELECT_ALL)

Write data.

Close the datatype, dataspace, and property list. (As necessary)

Close the dataset.

Figure 6 shows example code to write a 4 X 6 array of integers. In the example, the data is initialized in the memory array dset_data. The dataset has already been created in the file, so it is opened with H5Dopen.

The data is written with H5Dwrite. The arguments are the dataset handle, the memory datatype (H5T_NATIVE_INT), the memory and file selections (H5S_ALL in this case: the whole array), and the default (empty) property list. The last argument is the data to be transferred.

```
file_id, dataset_id; /* identifiers */
hid t
herr_t status;
           i, j, dset_data[4][6];
/* Initialize the dataset. */
for (i = 0; i < 4; i++)
   for (j = 0; j < 6; j++)
      dset_data[i][j] = i * 6 + j + 1;
/* Open an existing file. */
file_id = H5Fopen("dset.h5", H5F_ACC_RDWR, H5P_DEFAULT);
/* Open an existing dataset. */
dataset_id = H5Dopen(file_id, "/dset");
/* Write the entire dataset, using 'dset_data':
      memory type is 'native int'
      write the entire dataspace to the entire dataspace,
      no transfer properties,
status = H5Dwrite(dataset_id, H5T_NATIVE_INT, H5S_ALL,
        H5S ALL, H5P DEFAULT, dset_data);
status = H5Dclose(dataset_id);
```

Figure 6

Figure 7 shows a similar write, setting a non-default value for the transfer buffer. The code is the same as Figure 6, but a transfer property list is created and the desired buffer size is set. The H5Dwrite has the same arguments, but uses the property list to set the buffer.

```
file_id, dataset_id;
hid_t
hid_t xferplist;
herr_t status;
int
          i, j, dset_data[4][6];
file_id = H5Fopen("dset.h5", H5F_ACC_RDWR, H5P_DEFAULT);
dataset_id = H5Dopen(file_id, "/dset");
  * Example: set type conversion buffer to 64MB
xferplist = H5Pcreate(H5P_DTASET_XFER);
 status = H5Pset_buffer( xferplist, 64 * 1024 *1024, NULL, NULL);
/* Write the entire dataset, using 'dset_data':
      memory type is 'native int'
     write the entire dataspace to the entire dataspace,
      set the buffer size with the property list,
 * /
status = H5Dwrite(dataset_id, H5T_NATIVE_INT, H5S_ALL,
       H5S_ALL, plist, dset_data);
status = H5Dclose(dataset_id);
```

Figure 7

To read from a dataset

Define memory dataspace of read. (Optional if dataspace is H5S_SELECT_ALL) Open the dataset.

Get the dataset dataspace. (If using H5S_SELECT_ALL above)

Else define dataset dataspace of read. Define the memory datatype. (Optional)

Define the memory buffer.

Open the dataset.

Read data.

Close the datatype, dataspace, and property list. (As necessary)

Close the dataset.

Figure 8 shows example code that reads a 4 X 6 array of integers from a dataset called "dset1". First, the dataset is opened. The H5Dread call has parameters:

- the dataset handle (from H5Dopen)
- The memory datatype (H5T_NATVE_INT)
- The memory and file dataspace (H5S_ALL, the whole array)
- A default (empty) property list
- The memory to be filled.

```
hid_t
          file_id, dataset_id;
herr_t
          status;
           i, j, dset_data[4][6];
int
/* Open an existing file. */
file_id = H5Fopen("dset.h5", H5F_ACC_RDWR, H5P_DEFAULT);
/* Open an existing dataset. */
dataset_id = H5Dopen(file_id, "/dset");
/* read the entire dataset, into 'dset_data':
      memory type is 'native int'
      read the entire dataspace to the entire dataspace,
      no transfer properties,
status = H5Dread(dataset_id, H5T_NATIVE_INT, H5S_ALL,
        H5S_ALL, H5P_DEFAULT, dset_data);
status = H5Dclose(dataset_id);
```

Figure 8

3.4 Retrieve properties of a Dataset

The functions in the table below allow the user to retrieve information regarding a dataset, including the datatype, the dataspace, the dataset creation property list, and the total stored size of the data.

Query Function Description	
H5Dget_space Retrieve the dataspace of the dataset as stored in the file.	
H5Dget_type Retrieve the datatype of the dataset as stored in the file.	
H5Dget_create_plist Retrieve the dataset creation properties.	
H5Dget_storage_size Retrieve the total bytes for all the data of the dataset.	
H5Dvlen_get_buf_size Retrieve the total bytes for all the variable length data of the data	set.

Example

```
hid_t file_id, dataset_id;
hid_t dspace_id, dtype_id, plist_id;
herr_t status;

/* Open an existing file. */
file_id = H5Fopen("dset.h5", H5F_ACC_RDWR, H5P_DEFAULT);

/* Open an existing dataset. */
dataset_id = H5Dopen(file_id, "/dset");

dspace_id = H5Dget_space(dataset_id);
dtype_id = H5Dget_type(dataset_id);
plist_id = H5Dget_create_plist(dataset_id);

/* use the objects to discover the properties of the dataset */
status = H5Dclose(dataset_id);
```

3.5 Other Operations

The dataset is used for other miscellaneous operations.

Table 4

Operation Description
H5Dextend See below

H5Diterate

H5Dvlen_reclaim See below

4. Data Transfer: Raw Data I/O

The HDF5 Library implements data transfers through a pipeline which implements data transformations (according to the datatype and selections), chunking (as requested), and I/O operations using different mechanisms (file drivers). The pipeline is automatically configured by the HDF5 Library. Metadata is stored in the file so that the correct pipeline can be constructed to retrieve the data. In addition, optional filters, such as compression, may be added to the standard pipeline.

Figure 9 illustrates data layouts for different layers of an application using HDF5. The application data is organized as a multidimensional array of elements. The HDF5 format specification defines the stored layout of the data and metadata. The storage layout properties define the organization of the abstract data. This data is written and read to and from some storage medium.




Figure 9

The last stage of a write (and first stage of a read) is managed by an HDF5 file driver module. The virtual file layer of the HDF5 Library implements a standard interface to alternative I/O methods, including memory (AKA "core") files, single serial file I/O, multiple file I/O, and parallel I/O. The file driver maps a simple abstract HDF5 file to the specific access methods.

The raw data of an HDF5 dataset is conceived to be a multi-dimensional array of data elements. This array may be stored in the file according to several storage strategies:

- COMPACT
- CONTIGUOUS
- CHUNKED

The storage strategy does not affect data access methods, except that certain operations may be more or less efficient depending on the storage strategy and the access patterns.

Overall, the data transfer operations (H5Dread and H5Dwrite) work identically for any storage method, for any file driver, and for any filters and transformations. The HDF5 Library automatically manages the data transfer process. In some cases, transfer properties should or must be used to pass additional parameters, such as MPI/IO directives when used the parallel file driver.

4.1 Data pipeline

Actual I/O

When data is written or read to or from and HDF5 file, the HDF5 Library passes the data through a sequence of processing steps, the HDF5 data pipeline. This data pipeline performs operations on the data in memory, including byte swapping, alignment, scatter-gather, and hyperslab selections. The HDF5 Library automatically determines which operations are needed and manages the organization of memory operations, such as extracting selected elements from a data block. The data pipeline modules operate on data buffers, each processes the buffer and passes the transformed buffer to the next stage.

Table 5


Table 5 lists the stages of the data pipeline Figure 10 shows the order of processing during a read or write.

dataset is not chunked).

Virtual File Layer Facilitate easy plug-in file drivers, like MPIO, POSIX I/O.

Layers	Description
I/O initiation	Initiation of HDF5 I/O activities in user's application program, i.e. H5Dwrite and H5Dread.
Memory hyperslab operation	Data is scattered to (for read), or gathered from (for write) application's memory buffer (bypassed if no datatype conversion is needed).
Datatype conversion	Datatype is converted if it is different between memory and storage (bypassed if no datatype conversion is needed).
File hyperslab operation	Data is gathered from (for read), or scattered to (for write) to file space in memory (bypassed if no datatype conversion is needed).
Filter pipeline	Data is processed by filters when it passes. Data can be modified and restored here (bypassed if no datatype conversion is needed, no filter is enabled, or

Actual file driver used by the library, like MPIO or STDIO.



The HDF5 Library automatically applies the stages as needed.

When the memory dataspace selection is other than the whole dataspace, the memory hyperslab stage scatters/gathers the data elements between the appliation memory (described by the selection) and contiguous memory buffer for the pipeline. On a write, this is a gather operation, on a read, this is a scatter operation.

When the memory datatype is different from the file datatype, the datatype conversion stage transforms each data element. For example, if data is written from 32-bit big endian memory, and the file datatype is 32-bit little endian, the datatype conversion stage will swap the bytes of every elements. Similarly, when data is read from the file to native memory, byte swapping will be applied automatically when needed.

The file hyperslab stage is similar to the memory hyperslab stage, but is managing the arrangement of the elements according to the file dataspace selection. When data is read, data elements are gathered from the data blocks from the file to fill the contiguous buffers, which are processed by the pipeline. When data is read, the elements from a buffer are scattered to the data blocks of the file.

4.2 Filters

In addition to the standard pipeline, optional stages, called filters, can be inserted in the pipeline. The standard distribution includes optional filters to implement compression and error checking. User applications may add custom filters as well.

The HDF5 Library distribution includes or employs several optional filters, as listed in Table 6. The filters are applied in the pipeline between the virtual file layer and the file hyperslab operation (Figure 10). The application can use any number of filters, in any order.

Table 6

Filter	Description
gzip compression	Data compression using zlib.
Szip compression	Data compression using the Szip library.
N-bit compression	Data compression using an algorithm specialized for n-bit datatypes.
Scale-offset compression	Data compression using using a "scale and offset" algorithm.
Shuffling	To improve compression performance, data is regrouped by its byte position in the data unit. I.e. 1 st , 2 nd , 3 rd , 4 th bytes of integers are stored together respectively.
Fletcher32	Fletcher32 checksum for error-detection.

Filters may be used only for chunked data and are applied to chunks of data between the file hyperslab stage and the virtual file layer. At this stage in the pipeline, the data is organized as fixed-size blocks of elements, and the filter stage processes each chunk separately.

Filters are selected by dataset creation properties, and some behavior may be controlled by data transfer properties. The library determines what filters must be applied and in what order.

See The HDF Group website for further information regarding the Szip filter.

Information regarding the n-bit and scale-offset filters can be found in Using the N-bit Filter and Using the Scale-offset Filter, respectively.

4.3 File drivers

I/O is performed by the HDF5 virtual file layer. The file driver interface writes and reads blocks of data, each driver module implements the interface using different I/O mechanisms. Table 7 lists the file drivers currently supported. Note that the I/O mechanisms are separated from the pipeline processing: the pipeline and filter operations are identical no matter what data access mechanism is used.

Table 7

File Driver	Description
H5FD_CORE	Store in memory (optional backing store to disk file)
H5FD_DPSS	
H5FD_FAMILY	Store in a set of files
H5FD_GASS	Store using Globus Access to Secondary Storage
H5FD_LOG	Store in logging file.
H5FD_MPIO	Store using MPI/IO

H5FD_MULTI Store in multiple files, several options to control layout.
H5FD_SEC2 Serial I/O to file using Unix "section 2" functions.
H5FD_STDIO Serial I/O to file using Unix "stdio" functions

H5FD_STREAM I/O to socket.

Each file driver writes/reads contiguous blocks of bytes from a logically contiguous address space. The file driver is responsible for managing the details of the different physical storage methods.

In general, everything above the virtual file layer works identically no matter what storage method is used. However, some combinations of storage strategies and file drivers are not allowed. Also, some options may have substantially different performance depending on the file driver that is used. In particular, multi-file and parallel I/O may perform considerably differently from serial drivers, depending on chunking and other settings.

4.4 Data Transfer Properties to manage the pipeline

Data transfer properties set optional parameters that control parts of the data pipeline. Table 8 lists three transfer properties that control the behavior of the library.

Table 8

Property Description

H5Pset_buffer Maximum size for the type conversion buffer and background buffer and

optionally supplies pointers to application-allocated buffers

H5Pset_hyper_cache Whether to cache hyperslab blocks during I/O.

H5Pset_btree_ratios Set the B-tree split ratios for a dataset transfer property list. The split ratios

determine what percent of children go in the first node when a node splits.

Some filters and file drivers require or use additional parameters from the application program. These can be passed in the transfer property list. Table 9 lists the four file driver property lists.

Table 9

Property Description

H5Pset_dxpl_mpio Control the MPI I/O transfer mode (independent or collective)

during data I/O operations.

H5Pset_dxpl_multi

H5Pset small data block size Reserves blocks of size bytes for the contiguous storage of the raw

data portion of small datasets. The HDF5 Library then writes the raw data from small datasets to this reserved space, thus reducing unnecessary discontinuities within blocks of meta data and

improving IO performance.

H5Pset edc check Disable/enable EDC checking for read. (When selected, EDC is

always written)

The transfer properties are set in a property list, which is passed as a parameter of the H5Dread or H5Dwrite call. The transfer properties are passed to each pipeline stage, which may use or ignore any property in the list. In short, there is one property list, which contains all the properties.

4.5 Storage strategies

The raw data is conceptually a multi-dimensional array of elements, stored as a contiguous array of bytes. The data may be physically stored in the file in several ways. Table 6 lists the storage strategies for a dataset.

Table 10

Storage Strategy Description

CONTIGUOUS The dataset is stored as one continuous array of bytes

CHUNKED The dataset is stored as fixed-size chunks.

COMPACT A small dataset is stored in the metadata header.

The different storage strategies do not affect the data transfer operations of the dataset: reads and writes work the same for any storage strategy.

These strategies are described in the following sections.

Contiguous

A contiguous dataset is stored in the file as a header and a single continuous array of bytes. (Figure 12) The data elements are arranged in row major order, with according to the datatype. By default, data is stored contiguously.




Figure 12

Contiguous storage is the simplest model. It has several limitations. First, the dataset must be a fixed size: it is not possible to extend the limit of dataset, or to have unlimited dimensions. Second, because data is passed through the pipeline as fixed-size blocks, compression and other filters cannot be used with contiguous data.

Chunked

The data of a dataset may be stored as fixed-size chunks (Figure 13). A chunk is a hyper-rectangle of any shape. When a dataset is chunked, each chunk is read or written as a single I/O operation, and individually passed from stage to stage of the pipeline and filters.




Figure 13

Chunks may be any size and shape that fits in the dataspace of the dataset. For example, a three dimensional dataspace can be chunked as 3-D cubes, 2-D planes, or 1-D lines. The chunks may extend beyond the size of the dataspace, for example a 3 X 3 dataset might by chunked in 2 X 2 chunks. Sufficient chunks will be allocated to store the array, any extra space will not be accessible. So, to store the 3X3 array, four 2X2 chunks would be allocated, with 5 unused elements stored.

Chunked datasets can be unlimited (in any direction), and can be compressed or filtered.

Since the data is read or written by chunks, chunking can have a dramatic effect on performance by optimizing what is read and written. Note, too, that for specific access patterns (e.g., parallel I./O) decomposition into chunks can have a large impact on performance.

Two restrictions are placed on chunk shape and size:

- The rank of a chunk must be less than or equal to the rank of the dataset.
- Chunk size cannot exceed the size of a fixed-size dataset. For example, a dataset consisting of a 5x4 fixed-size array cannot be defined with 10x10 chunks.

Compact

For contiguous and chunked storage, the dataset header information and data are stored in two (or more) blocks (Figure 14). Therefore, at least two I/O operations are required to access the data, one to access the header, and one (or more) to access data. For a small dataset, this is considerable overhead.




Figure 14

A small dataset may be stored in a continuous array of bytes in the header block, using the COMPACT storage option. This dataset can be read entirely in one operation, which retrieves the header and data. The dataset must fit in the header, which varies depending on what metadata may be stored. In general, a compact dataset should be approximately 30 KB or less total size.

4.6 Partial I/O-Subseting and Hyperslabs

Data transfers can write or read some of the data elements of the dataset. This is controlled by specifying two selections, one for the source and one for the destination. Selections are specified by creating a dataspace with selections.

Selections may be a union of hyperslabs, where a hyperslab is a contiguous hyper-rectangle from the dataspace. A second form of selection is a list of points. Selected fields of compound data type may be read or written. In this case, the selection is controlled by the memory and file datatypes.

Summary of procedure:

- 1. open the dataset
- 2. define the memory datatype
- 3. define the memory dataspace selection and file dataspace selection
- 4. transfer data (H5Dread or H5Dwrite)

For a detailed explanation of selections, see the chapter "HDF5 Dataspaces and Partial I/O."

5. Allocation of Space in the File

When a dataset is created, space is allocated in the file for its header and initial data. The amount of space allocated when the dataset is created depends on the storage properties. When the dataset is modified (data is written, attributes added, or other changes), additional storage may be allocated if necessary.

Table 11

Object Size (bytes)

Header Variable, but typically around 256 bytes at the creation of a simple dataset with a simple

datatype

Data Size of the data array (number of elements X size of element). Space allocated in the file

depends on storage strategy and allocation strategy.

Header

A dataset header consists of one or more header messages containing persistent metadata describing various aspects of the dataset. These records are defined in the *HDF5 File Format Specification*. The amount of storage required for the metadata depends on the metadata to be stored. Table 12 summarizes the metadata.

Table 12

Header Information Approximate Storage Size

Datatype (required) bytes or more, depends on type

Dataspace (required) bytes or more, depends on num

bytes or more, depends on number of dimensions

and hsize_t

Layout (required) - points to the stored data bytes or more, depends on hsize_t and number of

dimensions

Filters Depends on the number of filters, size of filter

message depends on name and data that will be

passed.

The header blocks also store the name and values of attributes, so the total storage depends on the number and size of the attributes.

In addition, the data set must have at least one link, including a name, which is stored in the file and in the group it is a linked from.

The different storage strategies determine when and how much space is allocated for the data array. See the discussion of fill values below for a detailed explanation of the storage allocation.

Contiguous Storage

For a continuous storage option, the data is stored in a single, contiguous block in the file. The data is nominally a fixed size, (number of elements X size of element). Figure 15 shows and example of a two dimensional array, stored as a contiguous dataset.

Depending on the fill value properties, the space may be allocated when the dataset is created or when first written (default), and filled with fill values if specified. For parallel I/O, by default the space is allocated when the dataset if created.




Figure 15

Chunked

For chunked storage, the data is stored in one or more chunks. Each chunk is a continuous block in the file, but chunks are not necessarily stored contiguously. Each chunk has the same size. The data array has the same nominal size as a contiguous array (number of elements X size of element), but the storage is allocated in chunks, so the total size in the file can be larger that the nominal size of the array.




Figure 16

If a fill value is defined, each chunk will be filled with the fill value. Chunks must be allocated when data is written, but they may be allocated when the file is created, as the file expands, or when data is written.

For serial I/O, by default chunks are allocated incrementally, as data is written to the chunk. For a sparse dataset, chunks are allocated only for the parts of the dataset that are written. In this case, if the dataset is extended, no storage is allocated.

For parallel I/O, by default the chunks are allocate when the dataset is created or extended., with fill values written to the chunk.

In either case, the default can be changed using fill value properties. For example, using serial I/O, the properties can select to can allocate chunks when the dataset is created

H5Dextend is used to change the current dimensions of the dataset, within the limits of the dataspace. Each dimension can be extended up to its maximum, or unlimited. Extending the dataspace may or may not allocate space in the file, and may or may not write fill values, if they are defined. See the next section for an explanation.

```
hid_t file_id, dataset_id;
Herr_t status;
size_t newdims[2];

/* Open an existing file. */
file_id = H5Fopen("dset.h5", H5F_ACC_RDWR, H5P_DEFAULT);
/* Open an existing dataset. */
```

```
dataset_id = H5Dopen(file_id, "/dset");

/* Example: dataset is 2 X 3, each dimension is UNLIMITED */
/* extend to 2 X 7 */
newdims[0] = 2;
newdims[1] = 7;

status = H5Dextend(dataset_id, newdims);

/* dataset is now 2 X 7 */
status = H5Dclose(dataset_id);
```

Figure 17

5.1 Storage Allocation in the File: Early, Incremental, Late

The HDF5 Library implements several strategies for when storage is allocated if and when it is filled with fill values for elements not yet written by the user. Different strategies are recommended for different storage layouts and file drivers. In particular, a parallel program needs storage allocated during a collective call (e.g., create or extend), while serial programs may benefit from delaying the allocation until the data is written.

Two file creation properties control "when to allocate space", "when to write the fill-value" and the actual fill-value to write.

Table 13 shows the three options for when data is allocated in the file. "Early" allocation is done during dataset create call. Certain file drivers (especially MPI-I/O and MPI-posix) require space to be allocated when a dataset is created, so all processors will have the correct view of the data.

Table 13

Strategy	Description
Early	Allocate storage for the dataset immediately when the dataset is created.
Late	Defer allocating space for storing the dataset until the dataset is written.
Incremental	Defer allocating space for storing each chunk until the chunk is written.
Default	Use the strategy (Early, Late, Incremental) for the storage method and access method. (Recommended)

"Late" allocation is done at the time of the first write to dataset. Space for the whole dataset is allocated at the first write.

"Incremental" allocation (chunks only) is done at the time of the first write to the chunk. Chunks that have never been written are not allocated in the file. In a sparsely populated dataset, this option allocates chunks only where data is actually written.

The "Default" property selects the option recommended as appropriate for the storage method and access method. The defaults are shown in Table 14. Note that "Early" allocation is recommended for all Parallel I/O, while other options are recommended as the default for serial I/O cases.

Table 14

	Serial I/O	Parallel I/O
Contiguous Storage	Late	Early
Chunked Storage	Incremental	Early
Compact Storage	Early	Early

The second property is when to write fill value, "Never" and "Allocation". Table 15 shows these options.

Table 15

When Description

Never Fill value will never be written.

Allocation Fill value is written when space is allocated. (Default for chunked and contiguous data storage.)

The third property is the fill value to write. Table 16 shows the values. By default, the data is filled with zeroes. The application may choose no fill value (Undefined), in which case uninitialized data may have any random values. The application may define a fill-value of the appropriate type. See the chapter "HDF5 Datatypes" for more information regarding fill values.

What to Write Description

Undefined No value stored, do not fill with zeroes (the default)

Default By default, the library defines a fill-value of all zero bytes

User-defined The applications specifies the fill value.

Together these three properties control the library's behavior. Table 16 summarizes the possible behavior of during the dataset create-write-close cycle.

Table 16

When to allocate space	When to write fill value	What fill value to write	Library create-write-close behavior
Early	Never	-	Library allocates space when dataset is created, but never writes fill value to dataset. (Read of unwritten data returns undefined values.)
Late	Never	-	Library allocates space when dataset is written to, but never writes fill value to dataset. (Read of unwritten data returns undefined values.)
Incremental	Never	-	Library allocates space when dataset or chunk (whichever is smallest unit of space) is written to, but never writes fill value to dataset or chunk. (Read of unwritten data returns undefined values.)
-	Allocation	undefined	Error on creating dataset, dataset not created.
Early	Allocation	default or user-defined	Allocate space for dataset when dataset is created. Write fill value (default or user-defined) to entire dataset when dataset is created.
Late	Allocation	default or user-defined	Allocate space for dataset when application first writes data values to the dataset. Write fill value to entire dataset before writing application data value.
Incremental	Allocation	default or user-defined	Allocate space for dataset when application first writes data values to the dataset or chunk (whichever is smallest unit of space). Write fill value to entire dataset or chunk before writing user's data value.

During the H5Dread function call, the library behavior depends on whether space has been allocated, whether fill value has been written to storage, how fill value is defined, and when to write fill value. Table 17 summarizes the different behaviors.

٦	Га	h	P	1	7

Is space allocated in the file?		When to write fill value?	Library read behavior
No	undefined	< <any>></any>	Error. Cannot create this dataset.
	default or user-defined	< <any>></any>	Fill memory buffer with the fill value.
Yes	undefined	< <any>></any>	Return data from storage (dataset), trash is possible if user has not written data to portion of dataset being read.
	default or user-defined	Never	Return data from storage (dataset), trash is possible if user has not written data to portion of dataset being read.
	default or user-defined	Allocation	Return data from storage (dataset).

There are two cases to consider, depending on whether the space in the file has been allocated before the read or not. When space has not yet been allocated, if a fill value is defined the memory buffer will be filled with the values and returned (no read from disk).

If the space has been allocated, the values are returned from the stored data. The unwritten elements will be filled according to the fill value, or undefined.

5.2 Deleting a dataset from a file, reclaiming space

The size of the dataset cannot be reduced after it is created. The dataset can be expanded by extending one or more dimensions, with H5Dextend. It is not possible to contract a dataspace, or to reclaim allocated space.

HDF5 does not at this time provide a mechanism to remove a dataset from a file, or to reclaim the storage from deleted objects. Through the H5Gunlink function one can remove links to a dataset from the file structure. Once all links to a dataset have been removed, that dataset becomes inaccessible to any application and is effectively removed from the file. But this does not recover the space the dataset occupies.

The only way to recover the space is to write all the objects of the file into a new file. Any unlinked object is inaccessible to the application and will not be included in the new file.

See the chapter "HDF5 Groups" for further discussion of HDF5 file structures and the use of links.

5.3 Releasing memory resources (handles) when no longer needed

The system resources required for HDF5 objects, including datasets, datatypes, and dataspaces, should be released once access to the object is no longer needed. This is accomplished via the appropriate close function. This is not particular to datasets but a general requirement when working with the HDF5 Library; failure to close objects will result in resource leaks.

In the case where a dataset is created or data has been transferred, there are several objects that must be closed,

including the dataset, the datatype, dataspace, and property lists.

The application program must free any memory variables and buffers it allocates. When accessing data from the file, the amount of memory required can be determined by determining the size of the memory datatype and the number of elements in the memory selection.

Variable length data are organized in two or more areas of memory (see "HDF5 Datatypes"). When writing data, the application creates an array of vl_info_t, which contains pointers to the elements, e.g., strings. In the file, the variable length data is stored in two parts: a heap with the variable length values of the data elements, and an array vlinfo_t elements. When the data is read, the amount of memory required for the heap can be determined with the H5Dget_vlen_buf_size call.

The data transfer property may be used to set a custom memory manager for allocating variable length data for a H5Dread. This is set with the H5Pset_vlen_mem_manager call.

To free the memory for variable length data, it is necessary to visit each element, free the variable length data, and reset the element. The application must free the memory it has allocated. For memory allocated by the HDF5 Library during a read, the H5Dvlen_reclaim function can be used to perform this operation.

5.4 External Storage Properties

The external storage format allows data to be stored across a set of non-HDF5 files. A set segments (offsets and sizes) in one or more files is defined as an external file list, or EFL, and the contiguous logical addresses of the data storage are mapped onto these segments. Currently, only the H5D_CONTIGUOUS storage format allows external storage. External storage is enabled by a dataset creation property. Table 18 shows the API.

Table 18

Function	Description
herr_t H5Pset_external (hid_t plist, const char *name, off_t offset, hsize_t size)	This function adds a new segment to the end of the external file list of the specified dataset creation property list. The segment begins a byte offset of file name and continues for size bytes. The space represented by this segment is adjacent to the space already represented by the external file list. The last segment in a file list may have the size H5F_UNLIMITED, in which case the external file may be of unlimited size and no more files can be added to the external files list.
<pre>int H5Pget_external_count (hid_t plist)</pre>	Calling this function returns the number of segments in an external file list. If the dataset creation property list has no external data then zero is returned.
herr_t H5Pget_external (hid_t plist, int idx, size_t name_size, char *name, off_t *offset, hsize_t *size)	This is the counterpart for the H5Pset_external() function. Given a dataset creation property list and a zero-based index into that list, the file name, byte offset, and segment size are returned through non-null arguments. At most name_size characters are copied into the name argument which is not null terminated if the file name is longer than the supplied name buffer (this is similar to strncpy()).

Figure 19 shows an example of how a contiguous, one-dimensional dataset is partitioned into three parts and each of those parts is stored in a segment of an external file. The top rectangle represents the logical address space of the dataset while the bottom rectangle represents an external file.




Figure 19

Figure 19a shows code that defines the external storage for the example. Note that the segments are defined in order of the logical addresses they represent, not their order within the external file. It would also have been possible to put the segments in separate files. Care should be taken when setting up segments in a single file since the library doesn't automatically check for segments that overlap.

```
Plist = H5Pcreate (H5P_DATASET_CREATE);
H5Pset_external (plist, "velocity.data", 3000, 1000);
H5Pset_external (plist, "velocity.data", 0, 2500);
H5Pset_external (plist, "velocity.data", 4500, 1500);
```

Figure 19a

Figure 20 shows an example of how a contiguous, two-dimensional dataset is partitioned into three parts and each of those parts is stored in a separate external file. The top rectangle represents the logical address space of the dataset while the bottom rectangles represent external files.




Figure 20

Figure 21 shows code for this example.

In this example, the library maps the multi-dimensional array onto a linear address space as defined by the HDF5 format specification, and then maps that address space into the segments defined in the external file list.

```
Plist = H5Pcreate (H5P_DATASET_CREATE);
H5Pset_external (plist, "scan1.data", 0, 24);
H5Pset_external (plist, "scan2.data", 0, 24);
H5Pset_external (plist, "scan3.data", 0, 16);
```

Figure 21

The segments of an external file can exist beyond the end of the (external) file. The library reads that part of a segment as zeros. When writing to a segment that exists beyond the end of a file, the external file is automatically extended. Using this feature, one can create a segment (or set of segments) which is larger than the current size of the dataset, which allows to dataset to be extended at a future time (provided the data space also allows the extension).

All referenced external data files must exist before performing raw data I/O on the dataset. This is normally not a problem since those files are being managed directly by the application, or indirectly through some other library. However, if the file is transferred from its original context, care must be taken to assure that all the external files are accessible in the new location.

6. Using HDF5 Filters

6.1. N-bit Filter

N-bit data has *n* significant bits, where *n* may not correspond to a precise number of bytes. On the other hand, computing systems and applications universally, or nearly so, run most efficiently when manipulating data as whole bytes or multiple bytes. This can easily lead to a situation where requirements to facilitate high-speed operation

Consider the case of 12-bit integer data. In memory, that data will be handled in at least 2 bytes, or 16 bits, and on some platforms in 4 or even 8 bytes. The size of such a dataset can be significantly reduced when written to disk if the unused bits are stripped out.

The *n-bit filter* is provided for this purpose, *packing* n-bit data on output by stripping off all unused bits and *unpacking* on input, restoring the extra bits required by the computational processor.

N-bit Datatype

An *n-bit datatype* is a datatype of *n* significant bits. Unless it is packed, an *n*-bit datatype is presented as an *n*-bit bitfield within a larger-sized value. For example, a 12-bit datatype might be presented as a 12-bit field in a 16-bit, or 2-byte, value.

Currently, the datatype classes of n-bit datatype or n-bit field of a compound datatype or an array datatype are limited to integer or floating-point.

The HDF5 user can create an n-bit datatype through a series of of function calls. For example, the following calls create a 16-bit datatype that is stored in a 32-bit value with a 4-bit offset:

```
hid_t nbit_datatype = H5Tcopy(H5T_STD_I32LE);
H5Tset_precision(nbit_datatype, 16);
H5Tset_offset(nbit_datatype, 4);
```

In memory, one value of above example n-bit datatype would be stored on a little-endian machine as follows:

byte 3	byte 2	byte 1	byte 0
????????	????SPPP	PPPPPPPP	PPPP????

Key: S - sign bit, P - significant bit, ? - padding bit Sign bit is included in signed integer datatype precision.

N-bit Filter

When data of an n-bit datatype is stored on disk using the n-bit filter, the filter *packs* the data by stripping off the padding bits; only the significant bits are retained and stored. The values on disk will appear as follows:

1st value	2nd value	
SPPPPPPP PPPPPPPP	SPPPPPPP PPPPPPP	•••

Key: S - sign bit, P - significant bit, ? - padding bit Sign bit is included in signed integer datatype precision.

The n-bit filter can used effectively for compressing data of an n-bit datatype, including arrays and the n-bit fields of compound datatypes. The filter supports complex situations where a compound datatype contains member(s) of compound datatype or an array datatype has a compound datatype as the base type.

At present, the n-bit filter supports all datatypes. For datatypes of class time, string, bitfield, opaque, reference, ENUM, and variable length, the n-bit filter acts as a no-op. For convenience, the rest of this section refers to such datatypes as *no-op datatypes*.

As is the case with all HDF5 filters, an application using the n-bit filter must store data with chunked storage.

How does the n-bit filter work?

The n-bit filter always compresses and decompresses according to dataset properties supplied by the HDF5 library in the datatype, dataspace or dataset creation property list.

The dataset datatype refers to how data is stored in an HDF5 file while the memory datatype refers to how data is stored in memory. The HDF5 library will do datatype conversion when writing data in memory to the dataset or reading data from the dataset to memory if the memory datatype differs from the dataset datatype. Datatype conversion is performed by HDF5 Library before n-bit compression and after n-bit decompression.

The following subsections examine the common cases:

- N-bit integer conversions
- N-bit floating point conversions

Integer/n-bit conversions

Integer data, with a dataset of integer datatype of less than full precision and a memory datatype of H5T_NATIVE_INT, provides the simplest application of the n-bit filter.

The precision of H5T_NATIVE_INT is 8 muliplied by sizeof(int). This value, the size of an int in bytes, differs from platform to platform; we assume a value of 4 for the following illustration. We further assume the memory byte order to be little-endian.

In memory, therefore, the precision of H5T_NATIVE_INT is 32 and the offset is 0. One value of H5T_NATIVE_INT is layed out in memory as follows:

Key: S - sign bit, P - significant bit, ? - padding bit Sign bit is included in signed integer datatype precision.

Suppose the dataset datatype has a precision of 16 and an offset of 4. After HDF5 converts values from the memory datatype to the dataset datatype, it passes something like the following to the n-bit filter for compression:

Key: S - sign bit, P - significant bit, ? - padding bit Sign bit is included in signed integer datatype precision.

Notice that only the specified 16 bits (15 significant bits and the sign bit) are retained in the conversion. All other significant bits of the memory datatype are discarded because the dataset datatype calls for only 16 bits of precision. After n-bit compression, none of these discarded bits, known as *padding bits* will be stored on disk.

Floating-point/n-bit conversions

Things get more complicated in the case of a floating-point dataset datatype class. This subsection provides such an example, illustrating the conversion from a memory datatype of H5T_NATIVE_FLOAT to a dataset datatype of class floating-point.

As before, let the H5T_NATIVE_FLOAT be 4 bytes long, and let the memory byte order be little-endian. Per the IEEE standard [4], one value of H5T_NATIVE_FLOAT is layed out in memory as follows:

Key: S - sign bit, E - exponent bit, M - mantissa bit, ? - padding bit Sign bit is included in floating point datatype precision.

Suppose the dataset datatype has a precision of 20, offset of 7, mantissa size of 13, mantissa position of 7, exponent size of 6, exponent position of 20, and sign position of 26. (Refer to [3] for details of how to create a user-defined floating-point datatype.)

After HDF5 converts values from the memory datatype to the dataset datatype, it passes something like the following to the n-bit filter for compression:

Key: S - sign bit, E - exponent bit, M - mantissa bit, ? - padding bit Sign bit is included in floating point datatype precision.

The sign bit and truncated mantissa bits are not changed during datatype conversion by the HDF5 Library. On the other hand, the conversion of the 8-bit exponent to a 6-bit exponent is a little tricky:

The bias for the new exponent in the n-bit datatype is: $2^{(n-1)}-1$

The following formula is used for this exponent conversion: exp8 - $(2^{(8-1)}-1) = \exp6 - (2^{(6-1)}-1) = actual exponent value$

where exp8 is the stored decimal value as represented by the 8-bit exponent and exp6 is the stored decimal value as represented by the 6-bit exponent

In this example, caution must be taken to ensure that, after conversion, the actual exponent value is within the range that can be represented by a 6-bit exponent. For example, an 8-bit exponent can represent values from -127 to 128 while a 6-bit exponent can represent values only from -31 to 32.

N-bit filter behavior

The n-bit filter was designed to treat the incoming data byte by byte at the lowest level. The purpose was to make the n-bit filter as generic as possible so that no pointer cast related to the datatype is needed.

Bitwise operations are employed for packing and unpacking at the byte level.

Recursive function calls are used to treat compound and array datatypes.

N-bit compression

The main idea of n-bit compression is to use a loop to compress each data element in a chunk. Depending on the datatype of each element, the n-bit filter will call one of four functions. Each of these functions performs one of the following tasks:

- Compress a data element of a no-op datatype.
- Compress a data element of an atomic datatype.
- Compress a data element of a compound datatype.
- Compress a data element of an array datatype.

No-op datatypes: The n-bit filter does not actually compress no-op datatypes. Rather, it copies the data buffer of the no-op datatype from the noncompressed buffer to proper location in the compressed buffer; the compressed buffer has no holes. The term "compress" is used here simply to distinguish this function from the function that performs the reverse operation during decompression.

Atomic datatypes: The n-bit filter will find the bytes where significant bits are located and try to compress these bytes, one byte at a time, using a loop. At this level, the filter needs the following information:

- The byte offset of the beginning of the current data element with respect to the beginning of the input data buffer
- Datatype size, precision, offset, and byte order

The n-bit filter compresses from the most significant byte containing significant bits to the least significant byte. For big-endian data, therefore, the loop index progresses from smaller to larger while for little-endian, the loop index progresses from larger to smaller.

In the extreme case, i.e., when the n-bit datatype has full precision, this function copies the content of the entire noncompressed datatype to the compressed output buffer.

Compound datatypes: The n-bit filter will compress each data member of the compound datatype. If the member datatype is of an integer or floating-point datatype, the n-bit filter will call the function described above in section 2.1.2. If the member datatype is of a no-op datatype, the filter will call the function described above in section 2.1.1. If the member datatype is of a compound datatype, the filter will make a recursive call to itself (i.e., to the function described in this section, 2.1.3). If the member datatype is of an array datatype, the filter will call the function described below in section 2.1.4.

Array datatypes: The n-bit filter will use a loop to compress each array element in the array. If the base datatype of array element is of an integer or floating-point datatype, the n-bit filter will call the function described above in section 2.1.2. If the base datatype is of a no-op datatype, the filter will call the function described above in section 2.1.1. If the base datatype is of a compound datatype, the filter will call the function described above in section 2.1.3. If the member datatype is of an array datatype, the filter will make a recursive call of itself (i.e., to the function described in this section, 2.1.4).

N-bit decompression

The n-bit decompression algorithm is very similar to n-bit compression. The only difference is that at the byte level, compression packs out all padding bits and stores only significant bits into a continous buffer (unsigned char) while decompression unpacks significant bits and inserts padding bits (zeros) at the proper positions to recover the data bytes as they existed before compression.

Storing n-bit parameters to array cd_value[]

All of the information, or parameters, required by the n-bit filter are gathered and stored in the array cd_values[] by the private function H5Z_set_local_nbit and are passed to another private function, H5Z_filter_nbit, by the HDF5 Library.

These parameters ar as follows:

- 1. Parameters related to the datatype
- 2. The number of elements within the chunk
- 3. A flag indicating whether compression is needed

The first and second parameters can be obtained using the HDF5 dataspace and datatype interface calls. The third parameter is set during the storing process as described in section 3.2.

A compound datatype can have members of array or compound datatype. An array datatype's base datatype can be a complex compound datatype. Recursive calls are required to set parameters for these complex situations.

Before setting the parameters, the number of parameters should be calculated to dynamically allocate the array cd_values[], which will be passed to the HDF5 Library. This also requires recursive calls.

For an atomic datatype (integer or floating-point), parameters to store include the datatype's size, endianness, precision, and offset.

For a no-op datatype, only the size is required.

For a compound datatype, parameters to store include the datatype's total size and number of members. For each member, its member offset needs to be stored. Other parameters for members will depends on the respective datatype class.

For an array datatype, parameters to store include total size. Other parameters for the array's base type depend on the base type's datatype class.

Further, to correctly retrieve the parameter for use of n-bit compression or decompression later, parameters for distinguishing between datatype classes should be stored.

Implementation

Three filter call-back functions were written for the n-bit filter:

```
H5Z_can_apply_nbit
H5Z_set_local_nbit
H5Z filter nbit
```

These functions are called internally by the HDF5 library. A number of utility functions were written for the function H5Z_set_local_nbit. Compression and decompression functions were written and are called by function H5Z filter nbit. All these functions are included in the file H5Znbit.c.

The public function H5Pset_nbit is called by the application to sett up the use of the n-bit filter [2]. This function is included in the file H5Pdcpl.c. The application does not need to supply any parameters.

How n-bit parameters are stored

A scheme of storing parameters required by the n-bit filter in the array cd_values[] was developed utilizing recursive function calls.

Four private utility functions were written for storing the paramters associated with atomic (integer or floating-point), no-op, array, and compound datatypes:

H5Z_set_parms_atomic H5Z_set_parms_array H5Z_set_parms_nooptype H5Z_set_parms_compound

The scheme is briefly described below.

First assign a numeric code for datatype class atomic (integer or float), no-op, array, and compound datatype. The code is stored before other datatype related parameters are stored.

The first three parameters of cd_values[] are reserved for:

- 1. Number of valid entries in the array cd_values[]
- 2. A flag indicating whether compression is needed
- 3. The number of elements in the chunk

Throughout the balance of this explanation, i represents the index of cd_values[].

In the function H5Z_set_local_nbit:

- 1. i = 2
- 2. Get number of elements in the chunk and store in cd_value[i]; increment i.
- 3. Get class of datatype:

If integer or floating-point datatype, call H5Z_set_parms_atomic.

If array datatype, call H5Z_set_parms_array.

If compound datatype, call H5Z_set_parms_compound.

If none of the above, call H5Z_set_parms_noopdatatype.

4. Store i in cd_value[0] and flag in cd_values[1].

In the function H5Z_set_parms_atomic:

- 1. Store code for atomic datatype in cd_value[i]; increment i.
- 2. Get size of atomic datatype and store in cd_value[i]; increment i.
- 3. Get order of atomic datatype and store in cd_value[i]; increment i.
- 4. Get precision of atomic datatype and store in cd_value[i]; increment i.
- 5. Get offset of atomic datatype and store in cd_value[i]; increment i.
- 6. Determine need to do compression at this point.

In the function H5Z_set_parms_nooptype:

- 1. Store code for no-op datatype in cd_value[i]; increment i.
- 2. Get size of no-op datatype and store in cd_value[i]; increment i.

In the function H5Z_set_parms_array:

- 1. Store code for array datatype in cd_value[i]; increment i.
- 2. Get size of array datatype and store in cd_value[i]; increment i.
- 3. Get class of array's base datatype.

If integer or floating-point datatype, call H5Z set parms atomic.

If array datatype, call H5Z_set_parms_array.

If compound datatype, call H5Z_set_parms_compound.

If none of the above, call H5Z set parms noopdatatype.

In the function H5Z_set_parms_compound:

- 1. Store code for compound datatype in cd_value[i]; increment i.
- 2. Get size of compound datatype and store in cd_value[i]; increment i.
- 3. Get number of members and store in cd_values[i]; increment i.
- 4. For each member

Get member offset and store in cd_values[i]; increment i.

Get class of member datatype.

If integer or floating-point datatype, call H5Z_set_parms_atomic.

If array datatype, call H5Z_set_parms_array.

If compound datatype, call H5Z_set_parms_compound.

If none of the above, call H5Z_set_parms_noopdatatype.

N-bit compression and decompression functions

The n-bit compression and decompression functions above are called by the private HDF5 function H5Z_filter_nbit. The compress and decompress functions retrieve the n-bit parameters from cd_values[] as it was passed by H5Z_filter_nbit. Parameters are retrieved in exactly the same order in which they are stored and lower-level compression and decompression functions for different datatype classes are called. These functions are implementated according to the descriptions in sections 2.1 and 2.2.

N-bit compression is not implemented in place. Due to the difficulty of calculating actual output buffer size after compression, the same space as that of the input buffer is allocated for the output buffer as passed to the compression function. However, the size of the output buffer passed by reference to the compression function will be changed (smaller) after the compression is complete.

Usage Examples

The following code example illustrates the use of the n-bit filter for writing and reading n-bit integer data.

```
#include "hdf5.h"
#include <stdlib.h>
#include <math.h>
#define H5FILE_NAME "nbit_test_int.h5"
#define DATASET_NAME "nbit_int"
#define NX 200
#define NY 300
#define CH_NX 10
#define CH_NY 15
int main(void)
  hid_t file, dataspace, dataset, datatype, mem_datatype, properties;
  hsize_t dims[2], chunk_size[2];
   int orig_data[NX][NY];
   int
         new_data[NX][NY];
         i, j;
  size_t precision, offset;
   /* Define dataset datatype (integer), and set precision, offset */
  datatype = H5Tcopy(H5T_NATIVE_INT);
  precision = 17; /* precision includes sign bit */
   if(H5Tset_precision(datatype,precision)<0) {</pre>
     printf("Error: fail to set precision\n");
     return -1;
  offset = 4;
   if(H5Tset_offset(datatype,offset)<0) {</pre>
     printf("Error: fail to set offset\n");
     return -1;
   }
   /* Copy to memory datatype */
  mem_datatype = H5Tcopy(datatype);
   /* Set order of dataset datatype */
   if(H5Tset_order(datatype, H5T_ORDER_BE)<0) {</pre>
     printf("Error: fail to set endianness\n");
```

```
return -1;
 }
/* Initiliaze data buffer with random data within correct range
* corresponding to the memory datatype's precision and offset.
* /
for (i=0; i < NX; i++)
    for (j=0; j < NY; j++)
         orig_data[i][j] = rand() % (int)pow(2, precision-1) <<offset;</pre>
/* Describe the size of the array. */
dims[0] = NX;
dims[1] = NY;
if((dataspace = H5Screate_simple (2, dims, NULL))<0) {</pre>
   printf("Error: fail to create data space\n");
   return -1;
 }
* Create a new file using read/write access, default file
* creation properties, and default file access properties.
if((file = H5Fcreate (H5FILE_NAME, H5F_ACC_TRUNC,
                       H5P_DEFAULT, H5P_DEFAULT))<0) {</pre>
   printf("Error: fail to create file\n");
   return -1;
 }
* Set the dataset creation property list to specify that
* the raw data is to be partitioned into 10x15 element
* chunks and that each chunk is to be compressed.
* /
chunk_size[0] = CH_NX;
chunk_size[1] = CH_NY;
if((properties = H5Pcreate (H5P_DATASET_CREATE))<0) {</pre>
   printf("Error: fail to create dataset property\n");
   return -1;
if(H5Pset_chunk (properties, 2, chunk_size)<0) {</pre>
   printf("Error: fail to set chunk\n");
   return -1;
 }
```

```
* Set parameters for n-bit compression; check the description of
* the H5Pset_nbit function in the HDF5 Reference Manual for more
* information.
* /
if(H5Pset_nbit (properties)<0) {</pre>
  printf("Error: fail to set nbit filter\n");
  return -1;
}
* Create a new dataset within the file. The datatype
* and data space describe the data on disk, which may
* be different from the format used in the application's
* memory.
* /
if((dataset = H5Dcreate (file, DATASET_NAME, datatype,
                         dataspace, properties))<0) {</pre>
  printf("Error: fail to create dataset\n");
  return -1;
}
* Write the array to the file. The datatype and dataspace
* describe the format of the data in the 'orig_data' buffer.
* The raw data is translated to the format required on disk,
* as defined above. We use default raw data transfer properties.
* /
if(H5Dwrite (dataset, mem_datatype, H5S_ALL, H5S_ALL,
             H5P_DEFAULT, orig_data)<0) {</pre>
   printf("Error: fail to write to dataset\n");
   return -1;
H5Dclose (dataset);
if((dataset = H5Dopen(file, DATASET_NAME))<0) {</pre>
  printf("Error: fail to open dataset\n");
  return -1;
}
* Read the array. This is similar to writing data,
* except the data flows in the opposite direction.
* Note: Decompression is automatic.
* /
if(H5Dread (dataset, mem_datatype, H5S_ALL, H5S_ALL,
            H5P_DEFAULT, new_data)<0) {</pre>
   printf("Error: fail to read from dataset\n");
  return -1;
}
```

```
H5Tclose (datatype);
H5Tclose (mem_datatype);
H5Dclose (dataset);
H5Sclose (dataspace);
H5Pclose (properties);
H5Fclose (file);

return 0;
}
```

Example 1, n-bit compression: illustrating use of the n-bit filter for writing and reading n-bit integer data.

The following code example illustrates the use of the n-bit filter for writing and reading n-bit floating-point data.

```
#include "hdf5.h"
#define H5FILE_NAME "nbit_test_float.h5"
#define DATASET_NAME "nbit_float"
#define NX 2
#define NY 5
#define CH NX 2
#define CH_NY 5
int main(void)
  hid_t file, dataspace, dataset, datatype, properties;
  hsize_t dims[2], chunk_size[2];
  /* orig_data[] are initialized to be within the range that can be
  * represented by dataset datatype (no precision loss during
  * datatype conversion)
  * /
         orig data[NX][NY] = \{\{188384.00, 19.103516, -1.0831790e9, \}
  -84.242188, 5.2045898}, {-49140.000, 2350.2500, -3.2110596e-1,
  6.4998865e-5, -0.0000000}};
  float new_data[NX][NY];
  size_t precision, offset;
  /* Define single-precision floating-point type for dataset
   *-----
  * size=4 byte, precision=20 bits, offset=7 bits,
  * mantissa size=13 bits, mantissa position=7,
   * exponent size=6 bits, exponent position=20,
  * exponent bias=31.
   * It can be illustrated in little-endian order as:
   * (S - sign bit, E - exponent bit, M - mantissa bit,
    ? - padding bit)
                       2
                               1
          ?????SEE EEEEMMMM MMMMMMMM M???????
  * To create a new floating-point type, the following
  * properties must be set in the order of
        set fields -> set offset -> set precision -> set size.
  * All these properties must be set before the type can function.
  * Other properties can be set anytime. Derived type size cannot
   * be expanded bigger than original size but can be decreased.
   * There should be no holes among the significant bits. Exponent
   * bias usually is set 2^{(n-1)-1}, where n is the exponent size [3].
  datatype = H5Tcopy(H5T_IEEE_F32BE);
  if(H5Tset_fields(datatype, 26, 20, 6, 7, 13)<0) {
     printf("Error: fail to set fields\n");
     return -1;
  }
  offset = 7;
  if(H5Tset_offset(datatype,offset)<0) {</pre>
     printf("Error: fail to set offset\n");
     return -1;
  precision = 20;
```

```
if(H5Tset_precision(datatype,precision)<0) {</pre>
   printf("Error: fail to set precision\n");
   return -1;
if(H5Tset_size(datatype, 4)<0) {</pre>
   printf("Error: fail to set size\n");
   return -1;
if(H5Tset_ebias(datatype, 31)<0) {</pre>
   printf("Error: fail to set exponent bias\n");
   return -1;
/* Describe the size of the array. */
dims[0] = NX;
dims[1] = NY;
if((dataspace = H5Screate_simple (2, dims, NULL))<0) {</pre>
   printf("Error: fail to create data space\n");
   return -1;
}
* Create a new file using read/write access, default file
* creation properties, and default file access properties.
if((file = H5Fcreate (H5FILE_NAME, H5F_ACC_TRUNC,
                       H5P_DEFAULT, H5P_DEFAULT))<0) {</pre>
   printf("Error: fail to create file\n");
   return -1;
}
* Set the dataset creation property list to specify that
* the raw data is to be partitioned into 2x5 element
* chunks and that each chunk is to be compressed.
*/
chunk_size[0] = CH_NX;
chunk_size[1] = CH_NY;
if((properties = H5Pcreate (H5P_DATASET_CREATE))<0) {</pre>
   printf("Error: fail to create dataset property\n");
   return -1;
if(H5Pset_chunk (properties, 2, chunk_size)<0) {</pre>
   printf("Error: fail to set chunk\n");
   return -1;
}
* Set parameters for n-bit compression; check the description
* of the H5Pset nbit function in the HDF5 Reference Manual
* for more information.
if(H5Pset_nbit (properties)<0) {</pre>
   printf("Error: fail to set nbit filter\n");
   return -1;
```

```
* Create a new dataset within the file. The datatype
   * and data space describe the data on disk, which may
   * be different from the format used in the application's
   * /
   if((dataset = H5Dcreate (file, DATASET_NAME, datatype,
                            dataspace, properties))<0) {</pre>
      printf("Error: fail to create dataset\n");
     return -1;
   }
   * Write the array to the file. The datatype and dataspace
  * describe the format of the data in the 'orig_data' buffer.
   * The raw data is translated to the format required on disk,
   * as defined above. We use default raw data transfer properties.
   if(H5Dwrite (dataset, H5T_NATIVE_FLOAT, H5S_ALL, H5S_ALL,
               H5P_DEFAULT, orig_data)<0) {</pre>
      printf("Error: fail to write to dataset\n");
      return -1;
  H5Dclose (dataset);
   if((dataset = H5Dopen(file, DATASET_NAME))<0) {</pre>
     printf("Error: fail to open dataset\n");
     return -1;
   }
   * Read the array. This is similar to writing data,
   * except the data flows in the opposite direction.
   * Note: Decompression is automatic.
   * /
   if(H5Dread (dataset, H5T NATIVE FLOAT, H5S ALL, H5S ALL,
              H5P_DEFAULT, new_data)<0) {</pre>
     printf("Error: fail to read from dataset\n");
     return -1;
  H5Tclose (datatype);
  H5Dclose (dataset);
  H5Sclose (dataspace);
  H5Pclose (properties);
  H5Fclose (file);
  return 0;
}
```

Example 2, n-bit compression: illustrating the use of the n-bit filter for writing and reading n-bit floating-point data.

Limitations

Because the array cd_values[] has to fit into an object header message of 64K, the n-bit filter has an uppper limit on the number of n-bit paramters that can be stored in it. To be conservative, a maximum of 4K is allowed for the number of parameters.

The n-bit filter currently only compresses n-bit dataypes or fields derived from integer or floating-point datatypes. The n-bit filter assumes padding bits of zero. This may not be true since the HDF5 user can set padding bit to be zero, one, or leave the background alone. However, it is expected the n-bit filter will be modified to adjust to such situations.

The n-bit filter does not have a way to handle the situation where the fill value of a dataset is defined and the fill value is not of an n-bit datatype although the dataset datatype is.

6.2. Scale-offset Filter

Generally speaking, scale-offset compression performs a scale and/or offset operation on each data value and truncates the resulting value to a minimum number of bits (minimum-bits) before storing it [1].

The current scale-offset filter supports integer and floating-point datatype only. For floating-point datatype, float and double are supported while long double is not supported.

Integer data compression uses a straight-forward algorithm. Floating-point data compression adopts the GRiB data packing mechanism [2], which offers two alternate methods: a fixed minimum-bits method, and a variable minimum-bits method. Currently, only the variable minimum-bits method is implemented.

Like other I/O filters supported by the HDF5 library, application using the scale-offset filter must store data with chunked storage.

Integer type: The minimum-bits of integer data can be determined by the filter. For example, if the maximum value of data to be compressed is 7065 and the minimum value is 2970. Then the "span" of dataset values is equal to(max-min+1), which is 4676. If no fill value is defined for the dataset, the minimum-bits is: ceiling(log2(span)) = 12. With fill value set, the minimum-bits is: ceiling(log2(span+1)) = 13[1].

HDF5 user can also set the minimum-bits. However, if the user gives a minimum-bits that is less than that calculated by the filter, the compression will be lossy.

Floating-point type The basic idea of scaleoffset filter for floating-point type is to transform the data by some kind of scaling to integer data and then follow the procedure of scaleoffset filter for integer type to do the data compression. Due to the data transformation from floating-point to integer, the scaleoffset filter is lossy in nature.

Two methods of scaling the floating-point data are used, the so-called D-scaling and E-scaling. D-scaling is more straightforward and easy to understand. For HDF5 1.8 release, only D-scaling method is implemented. More information about D-scaling and E-scaling can be found from [2].

Design

Before the filter does any real work, it needs to gather some information from the HDF5 library through API calls. The parameters the filter needs are: Minimum-bits of the data value, number of data elements in the chunk, datatype class, size, sign (only for integer type), byte order, fill value if defined. Size and sign are needed to determine what kind of pointer cast to use when retrieving values from data buffer.

The pipeline of filter can be divided into four parts: (1)pre-compression; (2)compression; (3)decompression; (4)post-decompression.

Depending on whether fill value is defined or not, the filter will handle pre-compression and post-decompression differently.

The scaleoffset filter only needs the memory byte order, size of datatype, and minimum-bits for compression and decompression.

Since decompression has no access to the original data, the minimum-bits and the minimum value need to be stored with the compressed data for decompression and post-decompression.

Integer type

Pre-compression

During pre-compression Minimum-bits is calculated if it is not set by the user. Calculation of Minimum-bits has already been illustrated in section 1.

If fill value is defined, finding of maximum and minimum value should ignore the data element whose value is equal to the fill value.

If no fill value is defined, value of each data element is subtracted by minimum value during this stage.

If fill value is defined, fill value is assigned to the maximum value. In this way minimum-bits can represent data element whose value is equal to the fill value and subtracts the minimum value from data element whose value is not equal to the fill value.

Fill value, if defined, number of elements inside the chunk, class of datatype, size of datatype, memory order of the datatype etc. should be stored into HDF5 object header for the usage of post-decompression.

After pre-compression, all values are non-negative and are within the range that can be store by Minimum-bits.

Compression

All modified data values after pre-compression are packed together into the compressed data buffer. The number of bit for each data value decreases from the number of bit of integer (32 for most platforms) to minimum-bits. The value of minimum-bits and minimum-value are added to the data buffer and the whole buffer is sent back to the library. In this way, number of bit for each modified value is no more than the size of minimum-bits.

Decompression

In this stage, the number of bit for each data value is resumed from minimum-bits to the number of bit of integer.

Post-decompression

For the stage of the post-decompression the filter does the opposite of what it does during pre-compression except that it does not calculate the minimum-bits or the minimum value.

They have been saved during compression and can be retrieved through the resumed data buffer. If no fill value is defined, the filter adds the minimum value back to each data element.

If fill value is defined, the filter assigns the fill value to data element whose value is equal to the maximum value that minimum-bits can represent and adds the minimum value back to each data element whose value is not equal to the maximum value that minimum-bits can represent.

Floating-point type

The filter will do data transformation from floating-point type to integer type and then handle the data by using the procedure for handling the integer data inside the filter. Since insignificant bits of floating-point data will be cut off during data transformation, so this filter is a lossy compression method.

Two scaling methods are introduced by[2]; namely D-scaling and E-scaling. HDF5 1.8 release only supports D-scaling. In this document, we only introduce D-scaling. E-scaling should be similar conceptually. D-scaling means decimal scaling. In order to transform data from floating-point to integer, a scale factor is introduced. The

minimum value will be calculated. Each data element value will subtract the minimum value. The modified data will be multiplied by 10(Decimal) to the power of scale_factor and only the integer part will be kept and manipulated through the routines for integer type of the filter during the pre-compression and compression. The integer data will be divided by 10 to the power of scale_factor to transform back to the floating-point data during the decompression and post-decompression. Each data element value will then add the minimum value and the floating-data are resumed. However, the resumed data will lose some insignificant bits compared with the original value.

For example, the following floating point data are manipulated by the filter, the D-scaling factor is 2.

```
{104.561, 99.459, 100.545, 105.644}
```

The minimum value is 99.459, each data element subtracts 99.459, the modified data is {5.102, 0, 1.086, 6.185}

Since D-scaling factor is 2, all floating-point data will be multiplied by 10²,

```
{510.2, 0, 108.6, 618.5}
```

The digit after decimal point will be rounded off. The set looks like: {510, 0, 109, 619}

After decompression, each value will be divided by 10² and add the offset 99.459,

The floating point data becomes {104.559, 99.459, 100.549, 105.649}

The relative error for each value should be no more than 5* (10^(D-scaling factor +1)). D-scaling sometimes is also refered as variable Minimum-bits method since for different datasets the minimum-bits to represent the same decimal precision will vary. The Data value is modified to 2 to power scale_factor of for E-scaling. E-scaling is also called fixed-bits method since for different datasets the minimum-bits will always be fixed to the scale factor of E-scaling. Currently HDF5 ONLY supports D-scaling(variable Minimum-bits) method.

Implementation

The scale-offset filter implementation was written and included in the file H5Zscaleoffset.c. Function H5Pset_scaleoffset was written and included in the file "H5Pdcpl.c". The HDF5 user can supply minimum-bits by calling function H5Pset_scaleoffset [3].

The scale-offset filter was implemented based on the design outlined in section 2. However, the following factors need to be considered:

- 1. The filter needs the appropriate cast pointer whenever it needs to retrieve data values.
- 2. The HDF5 library passes to the filter the to-be-compressed data in format of dataset datatype and the filter passes back the decompressed data in the same format. If fill value is defined, it is also in dataset datatype format. For example, if byte order of dataset datatype is different from that of the memory datatype of the platform compression or decompression performs, endianness conversion of data buffer is needed. Moreover, it should be aware that memory byte order can be different during compression and decompression.
- 3. The difference of endianness and datatype between file and memory should be considered when saving and retrieval of minimum-bits, minimum value, and fill value.
- 4. If the user sets the minimum-bits to full precision of the datatype, no operation is needed at the filter side. If the full precision is a result of calculation by the filter, then the minimum-bits needs to be saved for decompression but no compression or decompression is needed (only copy of the input buffer is needed).
- 5. If by calculation of the filter, the minimum-bits is equal to zero, special handling is needed. Since it means all values are the same, no compression or decompression is needed. But the minimum-bits and minimum value still need to be saved during compression.
- 6. For floating-point data, the minimum value of the dataset should be calculated at first. Each data element value will then subtract the minimum value to obtain the "offset" data. The offset data will then follow 2.2 (3.1.2??) to do data transformation to integer and rounding.

Usage Examples

The following code example illustrates the use of the scale-offset filter for writing and reading integer data.

```
#include "hdf5.h"
#include <stdlib.h>
#define H5FILE_NAME "scaleoffset_test_int.h5"
#define DATASET_NAME "scaleoffset_int"
#define NX 200
#define NY 300
#define CH NX 10
#define CH NY 15
int main(void)
  hid_t
         file, dataspace, dataset, datatype, properties;
  hsize_t dims[2], chunk_size[2];
  int
        orig_data[NX][NY];
   int
          new_data[NX][NY];
          i, j, fill_val;
   int
   /* Define dataset datatype */
  datatype = H5Tcopy(H5T_NATIVE_INT);
   /* Initiliaze data buffer */
  for (i=0; i < NX; i++)
      for (j=0; j < NY; j++)
           orig_data[i][j] = rand() % 10000;
   /* Describe the size of the array. */
  dims[0] = NX;
  dims[1] = NY;
   if((dataspace = H5Screate_simple (2, dims, NULL))<0) {</pre>
```

```
printf("Error: fail to create data space\n");
  return -1;
}
* Create a new file using read/write access, default file
* creation properties, and default file access properties.
if((file = H5Fcreate (H5FILE_NAME, H5F_ACC_TRUNC,
                      H5P_DEFAULT, H5P_DEFAULT))<0) {
   printf("Error: fail to create file\n");
   return -1;
}
* Set the dataset creation property list to specify that
* the raw data is to be partitioned into 10x15 element
* chunks and that each chunk is to be compressed.
* /
chunk_size[0] = CH_NX;
chunk_size[1] = CH_NY;
if((properties = H5Pcreate (H5P_DATASET_CREATE))<0) {</pre>
   printf("Error: fail to create dataset property\n");
   return -1;
if(H5Pset_chunk (properties, 2, chunk_size)<0) {</pre>
  printf("Error: fail to set chunk\n");
   return -1;
/* Set the fill value of dataset */
fill_val = 10000;
if (H5Pset_fill_value(properties, H5T_NATIVE_INT,
   &fill_val)<0) {
   printf("Error: can not set fill value for dataset\n");
   return -1;
}
* Set parameters for scale-offset compression. Check the
* description of the H5Pset_scaleoffset function in the
* HDF5 Reference Manual for more information [3].
* /
if(H5Pset_scaleoffset (properties, H5_S0_INT,
                       H5_SO_INT_MINIMUMBITS_DEFAULT)<0) {</pre>
   printf("Error: fail to set scaleoffset filter\n");
  return -1;
}
* Create a new dataset within the file. The datatype
* and data space describe the data on disk, which may
* or may not be different from the format used in the
* application's memory.
* /
if((dataset = H5Dcreate (file, DATASET_NAME, datatype,
                         dataspace, properties))<0) {</pre>
   printf("Error: fail to create dataset\n");
  return -1;
}
```

```
* Write the array to the file. The datatype and dataspace
  * describe the format of the data in the 'orig_data' buffer.
  * We use default raw data transfer properties.
   if(H5Dwrite (dataset, H5T NATIVE INT, H5S ALL, H5S ALL,
                H5P_DEFAULT, orig_data)<0) {</pre>
     printf("Error: fail to write to dataset\n");
     return -1;
  H5Dclose (dataset);
  if((dataset = H5Dopen(file, DATASET_NAME))<0) {</pre>
     printf("Error: fail to open dataset\n");
     return -1;
   * Read the array. This is similar to writing data,
  * except the data flows in the opposite direction.
   * Note: Decompression is automatic.
  if(H5Dread (dataset, H5T_NATIVE_INT, H5S_ALL, H5S_ALL,
               H5P_DEFAULT, new_data)<0) {</pre>
     printf("Error: fail to read from dataset\n");
     return -1;
   }
  H5Tclose (datatype);
  H5Dclose (dataset);
  H5Sclose (dataspace);
  H5Pclose (properties);
  H5Fclose (file);
  return 0;
}
```

Example 3, scale-offset compression: illustrating the use of the scale-offset filter for writing and reading integer data

The following code example illustrates the use of the scale-offset filter (set for variable minimum-bits method) for writing and reading floating-point data.

```
#include "hdf5.h"
#include <stdlib.h>
#define H5FILE_NAME "scaleoffset_test_float_Dscale.h5"
#define DATASET_NAME "scaleoffset_float_Dscale"
#define NX 200
#define NY 300
#define CH_NX 10
#define CH_NY 15
int main(void)
  hid_t file, dataspace, dataset, datatype, properties;
  hsize_t dims[2], chunk_size[2];
  float orig_data[NX][NY];
  float new_data[NX][NY];
  float fill_val;
   int
          i, j;
   /* Define dataset datatype */
   datatype = H5Tcopy(H5T_NATIVE_FLOAT);
   /* Initiliaze data buffer */
   for (i=0; i <NX; i++)
       for (j=0; j < NY; j++)
           orig_data[i][j] = (rand() % 10000) / 1000.0;
   /* Describe the size of the array. */
   dims[0] = NX;
   dims[1] = NY;
   if((dataspace = H5Screate_simple (2, dims, NULL))<0) {</pre>
     printf("Error: fail to create data space\n");
     return -1;
   }
   * Create a new file using read/write access, default file
   * creation properties, and default file access properties.
   * /
   if((file = H5Fcreate (H5FILE_NAME, H5F_ACC_TRUNC,
                         H5P_DEFAULT, H5P_DEFAULT))<0) {</pre>
      printf("Error: fail to create file\n");
      return -1;
   }
   * Set the dataset creation property list to specify that
   * the raw data is to be partitioned into 10x15 element
   * chunks and that each chunk is to be compressed.
   chunk_size[0] = CH_NX;
   chunk_size[1] = CH_NY;
   if((properties = H5Pcreate (H5P_DATASET_CREATE))<0) {</pre>
     printf("Error: fail to create dataset property\n");
   if(H5Pset_chunk (properties, 2, chunk_size)<0) {</pre>
     printf("Error: fail to set chunk\n");
```

```
return -1;
}

/* Set the fill value of dataset */
fill_val = 10000.0;
if (H5Pset_fill_value(properties, H5T_NATIVE_FLOAT,
    &fill_val)
```

Example 4, scale-offset compression: illustrating the use of the scale-offset filter for writing and reading floating-point data

Limitations

For floating-point data handling, there are some algorithmic limitations to the GRiB data packing mechanism:

- 1. Both E-scaling and D-scaling method are lossy compression.
- 2. For D-scaling method, since data values have been rounded to integer values (positive) before truncating to the minimum-bits, their range is limited by the maximum value that can be represented by the corresponding unsigned integer type (same size with that of floating-point type).

Suggestions

Some suggestions for using the filter for floating-point data:

- 1. It is better to convert the units of data so that it is within certain common range (e.g. 1200m to 1.2km).
- 2. If data values to be compressed are very near to zero, it is strongly recommended that the user sets the fill value away from zero (e.g. a large positive number) because if the user does nothing the HDF5 library will set the fill value to zero, which may cause the compression not as desirable.
- 3. Users are not encouraged to use a very large decimal scale factor (e.g. 100) for the D-scaling method. This can cause the filter not to ignore fill value when finding maximum and minimum values, and get a much larger minimum-bits (poor compression).

6.3. Using the Szip Filter

See The HDF Group website for further information regarding the Szip filter.

Chapter 6 HDF5 Datatypes

1. Introduction

1.1 Introduction and Definitions

An HDF5 dataset is an array of data elements, arranged according to the specifications of the dataspace. In general, a data element is the smallest addressable unit of storage in the HDF5 file. (Compound datatypes are the exception to this rule.) The HDF5 datatype defines the storage format for a single data element (Figure 1).

The model for HDF5 attributes is extremely similar to datasets: an attribute has a dataspace and a datatype, as shown in Figure 1. The information in this chapter applies to both datasets and attributes.




Figure 1

Abstractly, each data element within the dataset is a sequence of bits, interpreted as a single value from a set of values (e.g., a number or a character). For a given data type, there is a standard or convention for representing the values as bits, and when the bits are represented in a particular storage the bits are laid out in a specific storage scheme, e.g., as 8-bit bytes, with a specific ordering and alignment of bytes within the storage array.

HDF5 datatypes implement a flexible, extensible, and portable mechanism for specifying and discovering the storage layout of the data elements, determining how to interpret the elements (e.g., as floating point numbers), and for transferring data from different compatible layouts.

An HDF5 datatype describes one specific layout of bits, a dataset has a single datatype which applies to every data element. When a dataset is created, the storage datatype is defined, the datatype cannot be changed.

- The datatype describes the storage layout of a single data element.
- All elements of the dataset must have the same type.
- The datatype of a dataset is immutable.

When data is transferred (e.g., a read or write), each end point of the transfer has a datatype, which describes the correct storage for the elements. The source and destination may have different (but compatible) layouts, in which case the data elements are automatically transformed during the transfer.

HDF5 datatypes describe commonly used binary formats for numbers (integers and floating point) and characters (ASCII). A given computing architecture and programming language supports certain number and character representations. For example, a computer may support 8-, 16-, 32-, and 64-bit signed integers, stored in memory in little-endian byte order. These would presumably correspond to the C programming language types 'char', 'short', 'int', and 'long'.

When reading and writing from memory, the HDF5 library must know the appropriate datatype that describes the architecture specific layout. The HDF5 library provides the platform independent 'NATIVE' types, which are mapped to an appropriate datatype for each platform. So the type 'H5T_NATIVE_INT' is an alias for the appropriate descriptor for each platform.

Data in memory has a datatype

- The storage layout in memory is architecture-specific.
- The HDF5 'NATIVE' types are predefined aliases for the architecture-specific memory layout.
- The memory datatype need not be the same as the stored datatype of the dataset.

In addition to numbers and characters, an HDF5 datatype can describe more abstract classes of types, including enumerations, strings, bit strings, and references (pointers to objects in the HDF5 file). HDF5 supports several classes of composite datatypes, which are compose one or more other datatypes. In addition to the standard predefined datatypes, users can define new datatypes within the datatype classes.

The HDF5 datatype model is very general and flexible

- For common simple purposes, only predefined types will be needed
- Datatypes can be composed to create complex structured datatypes.
- If needed, users can define custom atomic datatypes.

1.2 HDF5 Datatype Model

The HDF5 Library implements an object-oriented model of datatypes. HDF5 datatypes are organized as a logical set of base types, or datatype classes. Each datatype class defines a format for representing logical values as a sequence of bits. For example the H5T_INTEGER class is a format for representing twos complement integers of various sizes.

A datatype class is defined as a set of one or more datatype properties. A datatype property is a property of the bit string. The datatype properties are defined by the logical model of the datatype class. For example, the integer class (twos complement integers) has properties such as "signed or unsigned", "length", and "byte-order". The float class (IEEE floating point numbers) has these properties, plus "exponent bits", "exponent sign", etc.

A datatype is derived from one datatype class: a given datatype has a specific value for the datatype properties defined by the class. For example, for 32-bit signed integers, stored big-endian, the HDF5 datatype is a sub-type of integer, with the properties set to: signed=1, size=4 (bytes), byte-order=BE.

The HDF5 datatype API provides methods to create datatypes of different datatype classes, to set the datatype properties of a new datatype, and to discover the datatype properties of an existing datatype.

The datatype for a dataset is stored in the HDF5 file as part of the metadata for the dataset. A datatype can be shared by more than one dataset in the file. A datatype can optionally be stored as a named object in the file.

When transferring data (e.g., a read or write), the data elements of the source and destination storage must have compatible types. As a general rule, data elements with the same datatype class are compatible, while elements from different datatype classes are not compatible. When transferring data of one datatype to another compatible datatype, the HDF5 Library uses the datatype properties of the source and destination to automatically transform each data element. For example, when reading from data stored as 32-bit, signed integers, big-endian, into 32-bit signed integers, little-endian, the HDF5 Library will automatically swap the bytes.

Thus, data transfer operations (H5Dread, H5Dwrite, H5Aread, H5Awrite) require a datatype for both the source and the destination.




Figure 2

The HDF5 Library defines a set of predefined datatypes, corresponding to commonly used storage formats, such as twos complement integers, IEEE Floating point numbers, etc., 4- and 8-byte sizes, big endian and little endian byte orders. In addition, a user can derive types with custom values for the properties. For example, a user program may create a datatype to describe a 6-bit integer, or a 600-bit floating point number.

In addition to atomic datatypes, the HDF5 Library supports composite datatypes. A composite datatype is an aggregation of one or more datatypes. Each class of composite datatypes has properties that describe the organization of the composite datatype (Figure 3). Composite datatypes include:

- Compound datatypes: structured records
- Array: a multidimensional array of a datatype
- Variable length: a one-dimensional array of a datatype




Figure 3

1.2.1 Datatype Classes and Properties

Figure 4 shows the HDF5 datatype classes. Each class is defined to have a set of properties which describe layout of the data element and the interpretation of the bits. Table 1 lists the properties for the datatype classes.




Table 1. Datatype Classes and their properties.

	Table 1. Datatype Cla	sses and their properties	5.
Class	Description	Properties	Notes
Integer	Twos complement integers	Size (bytes), precision (bits), offset (bits), pad, byte order, signed/unsigned	
Float	Floating Point numbers	Size (bytes), precision (bits), offset (bits), pad, byte order, sign position, exponent position, exponent size (bits), exponent sign, exponent bias, mantissa position, mantissa (size) bits, mantissa sign, mantissa normalization, internal padding	non-IEEE 754 floating point formats as well.
Character	Array of 1-byte character encoding	Size (characters), Character set, byte order, pad/no pad, pad character	
Bitfield	String of bits	Size (bytes), precision (bits), offset (bits), pad, byte order	When stored, are packed into bytes
Opaque	Uninterpreted data	Size (bytes), precision (bits), offset (bits), pad, byte order, tag	A sequence of bytes, stored and retrieved as a block. The 'tag' is a string that can be used to label the value.
Enumeration	A list of discrete values, with symbolic names in the form of strings.	Number of elements, element names, element values	Enumeration is a list of pairs, (name, value). The name is a string, the value is an unsigned integer.
Reference	Reference to object or region within the HDF5 file		See the Reference API, H5R
Array	Array (1-4 dimensions) of data elements	Number of dimensions, dimension sizes, base datatype	The array is accessed atomically: no selection or subsetting.
Variable length	A variable length 1-dimensional array of data data elements	Current size, base type	
Compound	A Datatype composed of a sequence of Datatypes	Number of members, member names, member types, member offset, member class, member size, byte order	

1.2.2 Predefined Datatypes

The HDF5 library predefines a modest number of commonly used datatypes. These types have standard symbolic names of the form H5T_arch_base where arch is an architecture name and base is a programming type name (Table 2). New types can be derived from the predefined types by copying the predefined type (see H5Tcopy()) and then modifying the result.

The base name of most types consists of a letter to indicate the class (Table 3), a precision in bits, and an indication of the byte order (Table 4).

Table 5 shows examples of predefined datatypes. The full list can be found in the "HDF5 Predefined Datatypes" section of the *HDF5 Reference Manual*.

Table 2

Architecture Name	Description
IEEE	IEEE-754 standard floating point types in various byte orders.
STD	This is an architecture that contains semi-standard datatypes like signed two's complement integers, unsigned integers, and bitfields in various byte orders.
C FORTRAN	Types which are specific to the C or Fortran programming languages are defined in these architectures. For instance, H5T_C_S1 defines a base string type with null termination which can be used to derive string types of other lengths.
NATIVE	This architecture contains C-like datatypes for the machine on which the library was compiled. The types were actually defined by running the H5detect program when the library was compiled. In order to be portable, applications should almost always use this architecture to describe things in memory.
CRAY	Cray architectures. These are word-addressable, big-endian systems with non-IEEE floating point.
INTEL	All Intel and compatible CPU's including 80286, 80386, 80486, Pentium, Pentium-Pro, and Pentium-II. These are little-endian systems with IEEE floating-point.
MIPS	All MIPS CPU's commonly used in SGI systems. These are big-endian systems with IEEE floating-point.
ALPHA	All DEC Alpha CPU's, little-endian systems with IEEE floating-point.

Table 3

Bitfield

F Floating pointI Signed integerR ReferencesS Character string

U Unsigned integer

Table 4

BE Big endian
LE Little endian

Table 5

Example	Description
H5T_IEEE_F64LE	Eight-byte, little-endian, IEEE floating-point
H5T_IEEE_F32BE	Four-byte, big-endian, IEEE floating point
H5T_STD_I32LE	Four-byte, little-endian, signed two's complement integer
H5T_STD_U16BE	Two-byte, big-endian, unsigned integer
H5T_C_S1	One-byte, null-terminated string of eight-bit characters
H5T_INTEL_B64	Eight-byte bit field on an Intel CPU
H5T_CRAY_F64	Eight-byte Cray floating point
H5T_STD_ROBJ	Reference to an entire object in a file

The HDF5 Library predefines a set of NATIVE datatypes which are similar to C type names. The native types are set to be an alias for the appropriate HDF5 datatype for each platform. For example, H5T_NATIVE_INT corresponds to a C int type. On an Intel based PC, this type is the same as H5T_STD_I32LE, while on a MIPS system this would be equivalent to H5T_STD_I32BE. Table 6 shows examples of NATIVE types and corresponding C types for a common 32-bit workstation.

Table 6

Example	Corresponding C Type
H5T_NATIVE_CHAR	char
H5T_NATIVE_SCHAR	signed char
H5T_NATIVE_UCHAR	unsigned char
H5T_NATIVE_SHORT	short
H5T_NATIVE_USHORT	unsigned short
H5T_NATIVE_INT	int
H5T_NATIVE_UINT	unsigned
H5T_NATIVE_LONG	long
H5T_NATIVE_ULONG	unsigned long
H5T_NATIVE_LLONG	long long
H5T_NATIVE_ULLONG	unsigned long long
H5T_NATIVE_FLOAT	float
H5T_NATIVE_DOUBLE	double
H5T_NATIVE_LDOUBLE	long double
H5T_NATIVE_HSIZE	hsize_t
H5T_NATIVE_HSSIZE	hssize_t
H5T_NATIVE_HERR	herr_t
H5T_NATIVE_HBOOL	hbool_t

2. How Datatypes Are Used

2.1 The Datatype object and the HDF5 Datatype API

The HDF5 Library manages datatypes as objects. The HDF5 datatype API manipulates the datatype objects through C function calls. New datatypes can be created from scratch or copied from existing datatypes. When a datatype is no longer needed its resources should be released by calling H5Tclose().

The datatype object is used in several roles in the HDF5 data model and library. Essentially, a datatype is used whenever the format of data elements is needed. There are four major uses of datatypes in the HDF5 Library: at dataset creation, during data transfers, when discovering the contents of a file, and for specifying user defined data types (Table 7).

Table 7		
Use	Description	
Dataset creation	The datatype of the data elements must be declared when the dataset is created.	
Data transfer	The datatype (format) of the data elements must be defined for both the source and destination.	
Discovery	The datatype of a dataset can be interrogated to retrieve a complete description of the storage layout.	
Creating User defined Datatypes	Users can define their own datatypes by creating datatype objects and setting its properties.	

2.2 Dataset creation

All the data elements of a dataset have the same datatype. When a dataset is created (H5Tcreate), the datatype for the data elements must be specified. The datatype of a dataset can never be changed. Figure 5 shows the use of a datatype to create a dataset called "/dset". In this example, the dataset will be stored as 32-bit signed integers, in big endian order.

Figure 5

2.3 Data transfer (Read and Write)

Probably the most common use of datatypes is to write or read data from a dataset or attribute. In these operations, each data element is transferred from the source to the destination (possibly rearranging the order of the elements). Since the source and destination do not need to be identical (i.e., one is disk and the other is memory) the transfer requires both the format of the source element and the destination element. Therefore, data transfers use two datatype objects, for the source and destination.

When data is written, the source is memory and the destination is disk (file). The memory datatype describes the format of the data element in the machine memory, and the file datatype describes the desired format of the data element on disk. Similarly, when reading, the source datatype describes the format of the data element on disk, and the destination datatype describes the format in memory.

In the most common cases, the file datatype is the datatype specified when the dataset was created, and the memory datatype should be the appropriate NATIVE type.

Figures 5 and 6, respectively, show examples of writing data to and reading data from a dataset. The data in memory is declared C type 'int', the datatype H5T_NATIVE_INT corresponds to this type. The datatype of the dataset should be of datatype class H5T_INTEGER.

Figure 7

2.4 Discovery of data format

The HDF5 Library enables a program to determine the datatype class and properties for any data type. In order to discover the storage format of data in a dataset, the datatype is obtained, and the properties determined by queries to the datatype object. Figure 8 shows an example of code that analyzes the datatype for an integer, and prints out a description of its storage properties (byte Order, signed, size.)

```
switch (H5Tget_class(type)) {
case H5T_INTEGER:
   ord = H5Tget_order(type);
   sgn = H5Tget_sign(type);
   printf("Integer ByteOrder= ");
    switch (ord) {
    case H5T_ORDER_LE:
       printf("LE");
       break;
    case H5T_ORDER_BE:
       printf("BE");
        break;
   printf(" Sign= ");
    switch (sgn) {
    case H5T_SGN_NONE:
       printf("false");
        break;
    case H5T_SGN_2:
        printf("true");
        break;
    }
   printf(" Size= ");
    sz = H5Tget_size(type);
    printf("%d", sz);
   printf("\n");
   break;
```

Figure 8

2.5 Creating and using user defined datatypes

Most programs will primarily use the predefined datatypes described above, possibly in composite datatypes such as compound or array datatypes. However, the HDF5 datatype model is extremely general; a user program can define a great variety of atomic datatypes (storage layouts). In particular, the datatype properties can define signed and unsigned integers of any size and byte order, and floating point numbers with different formats, size, and byte order. The HDF5 datatype API provides methods to set these properties.

User defined types can be used to define the layout of data in memory, e.g., to match some platform specific number format or application defined bit-field. The user defined type can also describe data in the file, e.g., some application-defined format. The user defined types can be translated to and from standard types of the same class, as described above.

3. Datatype (H5T) Function Summaries

3.1 General Datatype Operations

C Function Purpose

F90 Function

H5Tcreate Creates a new datatype.

h5tcreate_f

H5Topen Opens a named datatype.

h5topen_f

H5Tcommit Commits a transient datatype to a file, creating a new named datatype.

h5tcommit_f

H5Tcommitted Determines whether a datatype is a named type or a transient type.

h5tcommitted_f

H5Tcopy Copies an existing datatype.

h5tcopy_f

H5Tequal Determines whether two datatype identifiers refer to the same datatype.

h5tequal_f

H5Tlock Locks a datatype.

(none)

H5Tget_class Returns the datatype class identifier.

h5tget_class_f

H5Tget_size Returns the size of a datatype.

h5tget_size_f

H5Tget_super Returns the base datatype from which a datatype is derived.

h5tget_super_f

H5Tget_native_type Returns the native datatype of a specified datatype.

(none)

H5Tdetect_class Determines whether a datatype is of the given datatype class.

(none)

H5Tclose Releases a datatype.

h5tclose_f

3.2 Conversion Functions

C Function Purpose F90 Function H5Tconvert Converts data from between specified datatypes. (none) Finds a conversion function. H5Tfind (none) H5Tset_overflow Sets the overflow handler to a specified function. (none) H5Tget_overflow Returns a pointer to the current global overflow function. (none) H5Tregister Registers a conversion function. (none) Removes a conversion function from all conversion paths. H5Tunregister

3.3 Atomic Datatype Properties

(none)

C Function F90 Function	Purpose
H5Tset_size h5tset_size_f	Sets the total size for an atomic datatype.
H5Tget_order h5tget_order_f	Returns the byte order of an atomic datatype.
H5Tset_order h5tset_order_f	Sets the byte ordering of an atomic datatype.
H5Tget_precision h5tget_precision_f	Returns the precision of an atomic datatype.
H5Tset_precision h5tset_precision_f	Sets the precision of an atomic datatype.
H5Tget_offset h5tget_offset_f	Retrieves the bit offset of the first significant bit.
H5Tset_offset h5tset_offset_f	Sets the bit offset of the first significant bit.
H5Tget_pad h5tget_pad_f	Retrieves the padding type of the least and most-significant bit padding.
H5Tset_pad h5tset_pad_f	Sets the least and most-significant bits padding types.
H5Tget_sign h5tget_sign_f	Retrieves the sign type for an integer type.
H5Tset_sign h5tset_sign_f	Sets the sign property for an integer type.
H5Tget_fields h5tget_fields_f	Retrieves floating point datatype bit field information.

H5Tset_fields h5tset_fields_f	Sets locations and sizes of floating point bit fields.
H5Tget_ebias h5tget_ebias_f	Retrieves the exponent bias of a floating-point type.
H5Tset_ebias h5tset_ebias_f	Sets the exponent bias of a floating-point type.
H5Tget_norm h5tget_norm_f	Retrieves mantissa normalization of a floating-point datatype.
H5Tset_norm h5tset_norm_f	Sets the mantissa normalization of a floating-point datatype.
H5Tget_inpad h5tget_inpad_f	Retrieves the internal padding type for unused bits in floating-point datatypes.
H5Tset_inpad h5tset_inpad_f	Fills unused internal floating point bits.
H5Tget_cset h5tget_cset_f	Retrieves the character set type of a string datatype.
H5Tset_cset h5tset_cset_f	Sets character set to be used.
H5Tget_strpad h5tget_strpad_f	Retrieves the storage mechanism for a string datatype.
H5Tset_strpad h5tset_strpad_f	Defines the storage mechanism for character strings.

3.4 Enumeration Datatypes

Purpose
Creates a new enumeration datatype.
Inserts a new enumeration datatype member.
Returns the symbol name corresponding to a specified member of an enumeration datatype.
Returns the value corresponding to a specified member of an enumeration datatype.
Returns the value of an enumeration datatype member.
Retrieves the number of elements in a compound or enumeration datatype.
Retrieves the name of a compound or enumeration datatype member.
Retrieves the index of a compound or enumeration datatype member.

3.5 Compound Datatype Properties

C Function Purpose F90 Function H5Tget_nmembers Retrieves the number of elements in a compound or enumeration h5tget_nmembers_f datatype. H5Tget member class Returns datatype class of compound datatype member. (none) H5Tget_member_name Retrieves the name of a compound or enumeration datatype h5tget_member_name_f member. H5Tget_member_index Retrieves the index of a compound or enumeration datatype (none) member. H5Tget_member_offset Retrieves the offset of a field of a compound datatype. h5tget_member_offset_f Returns the datatype of the specified member. H5Tget_member_type h5tget_member_type_f H5Tinsert Adds a new member to a compound datatype. h5tinsert_f H5Tpack Recursively removes padding from within a compound datatype. h5tpack_f

3.6 Array Datatypes

C Function F90 Function	Purpose
H5Tarray_create (none)	Creates an array datatype object.
H5Tget_array_ndims (none)	Returns the rank of an array datatype.
<pre>H5Tget_array_dims (none)</pre>	Returns sizes of array dimensions and dimension permutations.

3.7 Variable-length Datatypes

C Function Purpose

F90 Function

H5Tvlen_create Creates a new variable-length datatype.

h5tvlen_create_f

H5Tis_variable_str Determines whether datatype is a variable-length string.

h5tis_variable_str_f

3.8 Opaque Datatypes

C Function Purpose

F90 Function

H5Tset_tag Tags an opaque datatype.

h5tset_tag_f

H5Tget_tag Gets the tag associated with an opaque datatype.

h5tget_tag_f

3.9 Datatype-to-text and Text-to-datatype Conversions

C Function Purpose

F90 Function

H5LTtext_to_dtype Creates a datatype from a text description.

(none)

H5LTdtype_to_text Generates a text description of a datatype.

(none)

4. The Programming Model

4.1 Introduction

The HDF5 Library implements an object-oriented model of datatypes. HDF5 datatypes are organized as a logical set of base types, or datatype classes. The HDF5 Library manages datatypes as objects. The HDF5 datatype API manipulates the datatype objects through C function calls. Figure 9 shows the abstract view of the datatype object. Table 8 shows the methods (C functions) that operate on datatype object as a whole. New datatypes can be created from scratch or copied from existing datatypes.

Datatype
size:int?
byteOrder:BOtype
open(hid_t loc, char *, name):return hid_t
copy(hid_t tid) return hid_t
<pre>create(hid_class_t clss, size_t size) return hid_t</pre>

Figure 9. The datatype object

Table 8. General operations on datatype objects

•	, , ,
API function	Description
hid_t H5Tcreate (H5T_class_t class, size_t size)	Create a new datatype object of datatype class <i>class</i> . The following datatype classes are supported with this function:
	 H5T_COMPOUND H5T_OPAQUE H5T_ENUM
	Other datatypes are created with H5Tcopy().
hid_t H5Tcopy (hid_t <i>type</i>)	Obtain a modifiable transient datatype which is a copy of <i>type</i> . If <i>type</i> is a dataset identifier then the type returned is a modifiable transient copy of the datatype of the specified dataset.
<pre>hid_t H5Topen (hid_t location, const char *name)</pre>	Open a named datatype. The named datatype returned by this function is read-only.
<pre>htri_t H5Tequal (hid_t type1, hid t type2)</pre>	Determines if two types are equal.

herr_t H5Tclose (hid_t type)	Releases resources associated with a datatype obtained from H5Tcopy, H5Topen, or H5Tcreate. It is illegal to close an immutable transient datatype (e.g., predefined types).
<pre>herr_t H5Tcommit (hid_t location, const char *name, hid_t type)</pre>	Commit a transient datatype (not immutable) a file to become a named datatype. Named datatypes can be shared.
htri_t H5Tcommitted (hid_t type)	Test whether the datatype is transient or commited (named).
herr_t H5Tlock (hid_t type)	Make a transient datatype immutable (read-only and not closable). Predefined types are locked.

In order to use a datatype, the object must be created (H5Tcreate), or a reference obtained by cloning from an existing type (H5Tcopy), or opened (H5Topen). In addition, a reference to the datatype of a dataset or attribute can be obtained with H5Dget_type or H5Aget_type. For composite datatypes a reference to the datatype for members or base types can be obtained (H5Tget_member_type, H5Tget_super). When the datatype object is no longer needed, the reference is discarded with H5Tclose.

Two datatype objects can be tested to see if they are the same with H5Tequal. This function returns true if the two datatype references refer to the same datatype object. However, if two datatype objects define equivalent datatypes (the same datatype class and datatype properties), they will not be considered 'equal'.

A datatype can be written to the file as a first class object (H5Tcommit). Named datatypes can be used in the same way as any other dataype. Named datatypes are explained below.

4.2 Discovery of Datatype Properties

Any HDF5 datatype object can be queried to discover all of its datatype properties. For each datatype class, there are a set of API functions to retrieve the datatype properties for this class.

4.2.1 Properties of Atomic Datatypes

Table 9 lists the functions to discover the properties of atomic datatypes. Table 10 lists the queries relevant to specific numeric types. Table 11 gives the properties for atomic string datatype, and Table 12 gives the property of the opaque datatype.

Table	9
-------	---

i able 9		
Functions to Discover Properties of Atomic DataTypes	Description	
H5T_class_t H5Tget_class (hid_t type)	The datatype class: H5T_INTEGER, H5T_FLOAT, H5T_STRING, or H5T_BITFIELD, H5T_OPAQUE, H5T_COMPOUND, H5T_REFERENCE, H5T_ENUM, H5T_VLEN, H5T_ARRAY	
<pre>size_t H5Tget_size (hid_t type)</pre>	The total size of the element in bytes, including padding which may appear on either side of the actual value.	
H5T_order_t H5Tget_order (hid_t type)	The byte order describes how the bytes of the datatype are laid out in memory. If the lowest memory address contains the least significant byte of the datum then it is said to be <i>little-endian</i> or H5T_ORDER_LE. If the bytes are in the opposite order then they are said to be <i>big-endian</i> or H5T_ORDER_BE.	
<pre>size_t H5Tget_precision (hid_t type)</pre>	The precision property identifies the number of significant bits of a datatype and the offset property (defined below) identifies its location. Some datatypes occupy more bytes than what is needed to store the value. For instance, a short on a Cray is 32 significant bits in an eight-byte field.	
<pre>int H5Tget_offset (hid_t type)</pre>	The offset property defines the bit location of the least significant bit of a bit field whose length is precision.	
herr_t H5Tget_pad (hid_t <i>type</i> , H5T_pad_t * <i>lsb</i> , H5T_pad_t * <i>msb</i>)	Padding is the bits of a data element which are not significant as defined by the precision and offset properties. Padding in the low-numbered bits is <i>lsb</i> padding and padding in the high-numbered bits is <i>msb</i> padding. Padding bits can be set to zero (H5T_PAD_ZERO) or one (H5T_PAD_ONE).	

Table 10

Properties of Atomic Numeric Types

H5T_sign_t H5Tget_sign (hid_t type)

size_t *spos, size_t *epos, size t *esize, size t *mpos, size_t *msize)

size_t H5Tget_ebias (hid_t type)

H5T norm t H5Tget norm (hid t type)

H5T pad t H5Tget inpad (hid t type)

Description

(**INTEGER**) Integer data can be signed two's complement (H5T SGN 2) or unsigned (H5T SGN NONE).

herr t H5Tget fields (hid t type, (FLOAT) A floating-point data element has bit fields which are the exponent and mantissa as well as a mantissa sign bit. These properties define the location (bit position of least significant bit of the field) and size (in bits) of each field. The sign bit is always of length one and none of the fields are allowed to overlap.

> (FLOAT) The exponent is stored as a non-negative value which is ebias larger than the true exponent.

(FLOAT) This property describes the normalization method of the mantissa.

- H5T NORM MSBSET: the mantissa is shifted left (if non-zero) until the first bit after the radix point is set and the exponent is adjusted accordingly. All bits of the mantissa after the radix point are stored.
- H5T_NORM_IMPLIED: the mantissa is shifted left \ (if non-zero) until the first bit after the radix point is set and the exponent is adjusted accordingly. The first bit after the radix point is not stored since it's always set.
- H5T NORM NONE: the fractional part of the mantissa is stored without normalizing it.

(FLOAT) If any internal bits (that is, bits between the sign bit, the mantissa field, and the exponent field but within the precision field) are unused, then they will be filled according to the value of this property. The padding can be: H5T PAD NONE, H5T PAD ZERO or H5T_PAD_ONE.

Table 11

Properties of Atomic String Datatypes

H5T_cset_t H5Tget_cset (hid_t
type)

H5T_str_t H5Tget_strpad (hid_t
type)

Description

The only character set currently supported is H5T_CSET_ASCII.

The string datatype has a fixed length, but the String may be shorter than the length. This property defines the storage mechanism for the left over bytes. The options are: H5T_STR_NULLTERM, H5T_STR_NULLPAD, or H5T_STR_SPACEPAD.

Table 12

Properties of Opaque Atomic Datatypes char *H5Tget_tag(hid_t type_id)

Description

A user defined string.

4.2.2 Properties of Composite Datatypes

The composite datatype classes can also be analyzed to discover their datatype properties and the datatypes that are members or base types of the composite datatype. The member or base type can, in turn, be analyzed. Table 13 lists the functions that can access the datatype properties of the different composite datatypes.

Table 13

IUN	10 10
Properties of Composite Datatype	Description
<pre>int H5Tget_nmembers(hid_t type_id)</pre>	(COMPOUND) The number of fields in the compound datatype.
<pre>H5T_class_t H5Tget_member_class(hid_t cdtype_id, unsigned member_no)</pre>	(COMPOUND) The datatype class of compound datatype member member_no.
<pre>char * H5Tget_member_name(hid_t type_id, unsigned field_idx)</pre>	(COMPOUND) The name of field field_idx of a compound datatype.
<pre>size_t H5Tget_member_offset(hid_t type_id, unsigned memb_no)</pre>	(COMPOUND) The byte offset of the beginning of a field within a compound datatype.
<pre>hid_t H5Tget_member_type(hid_t type_id, unsigned field_idx)</pre>	(COMPOUND) The datatype of the specified member.
<pre>int H5Tget_array_ndims(hid_t adtype_id)</pre>	(ARRAY) The number of dimensions (rank) of the array datatype object.
<pre>int H5Tget_array_dims(hid_t adtype_id, hsize_t *dims[], int *perm[])</pre>	(ARRAY) The sizes of the dimensions and the dimension permutations of the array datatype object.
hid_t H5Tget_super(hid_t type)	(ARRAY, VL, ENUM) The base datatype from which the datatype type is derived.
<pre>herr_t H5Tenum_nameof(hid_t type void *value, char *name, size_t size)</pre>	(ENUM) The symbol name that corresponds to the specified value of the enumeration datatype
<pre>herr_t H5Tenum_valueof(hid_t type char *name, void *value)</pre>	(ENUM) The value that corresponds to the specified name of the enumeration datatype
<pre>herr_t H5Tget_member_value(hid_t type unsigned memb_no, void *value)</pre>	(ENUM) The value of the enumeration datatype member memb_no

4.3 Definition of Datatypes

The HDF5 Library enables user programs to create and modify datatypes. The essential steps are:

- 1. a) Create a new datatype object of a specific composite datatype class, or
 - b) Copy an existing atomic datatype object.
- 2. Set properties of the datatype object.
- 3. Use the datatype object.
- 4. Close the datatype object.

To create a user defined atomic datatype, the procedure is to clone a predefined datatype of the appropriate datatype class (H5Tcopy). Then set the datatype properties appropriate to the datatype class. For example, Table 14 shows how to create a datatype to describe a 1024-bit unsigned integer.

Table 14

```
hid_t new_type = H5Tcopy (H5T_NATIVE_INT);
H5Tset_precision(new_type, 1024);
H5Tset_sign(new_type, H5T_SGN_NONE);
```

Composite datatypes are created with a specific API call for each datatype class. Table 15 shows the creation method for each datatype class. A newly created datatype cannot be used until the datatype properties are set. For example, a newly created compound datatype has no members and cannot be used.

Table 15

Datatype Class	Function to Create
COMPOUND	H5Tcreate
OPAQUE	H5Tcreate
ENUM	H5Tenum_create
ARRAY	H5Tarray_create
VL	H5Tvlen_create

Once the datatype is created and the datatype properties set, the datatype object can be used.

Predefined datatypes are defined by the library during initialization using the same mechanisms as described here. Each predefined datatype is locked (H5Tlock), so that it cannot be changed or destroyed. User defined datatypes may also be locked using H5Tlock.

4.3.1 User Defined Atomic Datatypes

Table 16 summarizes the API methods that set properties of atomic types. Table 17 shows properties specific to numeric types, Table 18 shows properties specific to the string datatype class. Note that offset, pad, etc. don't apply to strings. Table 19 shows the specific property of the OPAQUE datatype class.

Table 16

Functions to set Properties of Atomic DataTypes Description

herr_t H5Tset_size (hid_t type,
size_t size)

Set the total size of the element in bytes, including padding which may appear on either side of the actual value. If this property is reset to a smaller value which would cause the significant part of the data to extend beyond the edge of the datatype then the offset property is decremented a bit at a time. If the offset reaches zero and the significant part of the data still extends beyond the edge of the datatype then the precision property is decremented a bit at a time. Decreasing the size of a datatype may fail if the H5T_FLOAT bit fields would extend beyond the significant part of the type.

herr_t H5Tset_order (hid_t type,
H5T_order_t order)

Set the byte order to little-endian (H5T_ORDER_LE)or big endian (H5T_ORDER_BE).

herr_t H5Tset_precision (hid_t
type, size_t precision)

Set the number of significant bits of a datatype. The offset property (defined below) identifies its location. The size property defined above represents the entire size (in bytes) of the datatype. If the precision is decreased then padding bits are inserted on the MSB side of the significant bits (this will fail for H5T_FLOAT types if it results in the sign, mantissa, or exponent bit field extending beyond the edge of the significant bit field). On the other hand, if the precision is increased so that it "hangs over" the edge of the total size then the offset property is decremented a bit at a time. If the offset reaches zero and the significant bits still hang over the edge, then the total size is increased a byte at a time.

herr_t H5Tset_offset (hid_t type, Set the bit location of the least significant bit of a size_t offset)

bit field whose length is precision. The bits

Set the bit location of the least significant bit of a bit field whose length is precision. The bits of the entire data are numbered beginning at zero at the least significant bit of the least significant byte (the byte at the lowest memory address for a little-endian type or the byte at the highest address for a big-endian type). The offset property defines the bit location of the least significant bit of a bit field whose length is precision. If the offset is increased so the significant bits "hang over" the edge of the datum, then the size property is automatically incremented.

herr_t H5Tset_pad (hid_t type,
H5T_pad_t lsb, H5T_pad_t msb)

Set the padding to zeros (H5T_PAD_ZERO) or ones (H5T_PAD_ONE). Padding is the bits of a data element which are not significant as defined by the precision and offset properties. Padding in the low-numbered bits is *1sb* padding and padding in the high-numbered bits is *msb* padding.

Table 17

Properties of Numeric Types

herr_t H5Tset_sign (hid_t type, H5T_sign_t sign)

herr t H5Tset fields (hid t type, (FLOAT) Set the properties define the location size_t spos, size_t epos, size_t esize, size t mpos, size t msize) and size (in bits) of each field. The sign bit is

herr_t H5Tset_ebias (hid_t type, size_t ebias)

herr_t H5Tset_norm (hid_t type, H5T_norm_t norm)

Description

(**INTEGER**) Integer data can be signed two's complement (H5T_SGN_2) or unsigned (H5T SGN NONE).

(bit position of least significant bit of the field) always of length one and none of the fields are allowed to overlap.

(FLOAT) The exponent is stored as a non-negative value which is ebias larger than the true exponent.

(FLOAT) This property describes the normalization method of the mantissa.

- H5T NORM MSBSET: the mantissa is shifted left (if non-zero) until the first bit after the radix point is set and the exponent is adjusted accordingly. All bits of the mantissa after the radix point are stored.
- H5T NORM IMPLIED: the mantissa is shifted left (if non-zero) until the first bit after the radix point is set and the exponent is adjusted accordingly. The first bit after the radix point is not stored since it's always set.
- H5T NORM NONE: the fractional part of the mantissa is stored without normalizing it.

herr_t H5Tset_inpad (hid_t type, H5T_pad_t inpad)

(FLOAT) If any internal bits (that is, bits between the sign bit, the mantissa field, and the exponent field but within the precision field) are unused, then they will be filled according to the value of this property. The padding can be: H5T_PAD_NONE, H5T_PAD_ZERO or H5T_PAD_ONE.

Table 18

Properties of Atomic String Datatypes

herr_t H5Tset_size (hid_t type, size t size)

herr_t H5Tset_precision (hid_t type, size_t precision)

herr_t H5Tset_cset(hid_t type_id, The only character set currently supported is H5T_cset_t cset)

herr_t H5Tset_strpad(hid_t type_id, H5T_str_t strpad) Description

Set the length of the string, in bytes. The precision is automatically set to 8*size.

The precision must be a multiple of 8.

H5T_CSET_ASCII.

The string datatype has a fixed length, but the string may be shorter than the length. This property defines the storage mechanism for the left over bytes. The method used to store character strings differs with the programming language:

- C usually null terminates strings while
- Fortran left-justifies and space-pads strings.

Valid string padding values, as passed in the parameter strpad, are as follows:

H5T_STR_NULLTERM (0)

Null terminate (as C does)

H5T_STR_NULLPAD(1)

Pad with zeros

H5T_STR_SPACEPAD (2)

Pad with spaces (as FORTRAN does).

Table 19

Properties of Opaque Atomic Datatypes

herr_t H5Tset_tag(hid_t type_id const char *tag)

Description

Tags the opaque datatype type_id with an ASCII identifier tag.

Examples

Figure 10 shows an example of how to create a 128-bit, little-endian signed integer type one could use the following (increasing the precision of a type automatically increases the total size). Note that the proper procedure is to begin from a type of the intended datatype class, in this case, a NATIVE INT.

```
hid_t new_type = H5Tcopy (H5T_NATIVE_INT);
H5Tset_precision (new_type, 128);
H5Tset_order (new_type, H5T_ORDER_LE);
```

Figure 10

Figure 11 shows the storage layout as the type is defined. The H5Tcopy creates a datatype that is the same as H5T_NATIVE_INT. In this example, suppose this is a 32-bit big endian number (Figure 11a). The precision is set to 128 bits, which automatically extends the size to 8 bytes (Figure 11b). Finally, the byte order is set to little-endian (Figure 11c).

Byte 0	Byte 1	Byte 2	Byte 3
01234567	89012345	67890123	45678901

a) The H5T_NATIVE_INT

Byte 0	Byte 1	Byte 2	Byte 3	Byte 4	Byte 5	Byte 6	Byte 7
01234567	89012345	67890123	45678901	23456789	01234567	89012345	67890123

b) Precision extended to 128-bits, the size is automatically adjusted.

Byte 0	Byte 1	Byte 2	Byte 3	Byte 4	Byte 5	Byte 6	Byte 7
01234567	89012345	67890123	45678901	23456789	01234567	89012345	67890123

c) The Byte Order is switched.

Figure 11

The significant bits of a data element can be offset from the beginning of the memory for that element by an amount of padding. The offset property specifies the number of bits of padding that appear to the "right of" the value. Table 20 and Figure 12 shows how a 32-bit unsigned integer with 16-bits of precision having the value 0×1122 will be laid out in memory.

Table 20

Byte PositionBig-Endian Offset=0Big-Endian Offset=16Little-Endian Offset=16Little-Endian Offset=160:[pad] $[0x11]$ $[0x22]$ $[pad]$ 1:[pad] $[0x22]$ $[0x11]$ $[pad]$ 2: $[0x11]$ $[pad]$ $[pad]$ $[0x22]$ 3: $[0x22]$ $[pad]$ $[pad]$ $[0x11]$			i abie 20		
1: [pad] [0x22] [0x11] [pad] 2: [0x11] [pad] [pad] [0x22]	Byte Position	- C	U		Little-Endian Offset=16
2: [0x11] [pad] [pad] [0x22]	0:	[pad]	[0x11]	[0x22]	[pad]
	1:	[pad]	[0x22]	[0x11]	[pad]
3: [0x22] [pad] [pad] [0x11]	2:	[0x11]	[pad]	[pad]	[0x22]
	3:	[0x22]	[pad]	[pad]	[0x11]

Big-Endian: Offset = 0

Byte 0	Byte 1	Byte 2	Byte 3
01234567	89012345	67890123	45678967
PPPPPPP	PPPPPPP	00010001	00100010

Big-Endian: Offset = 16

Byte 0	Byte 1	Byte 2	Byte 3
01234567	89012345	67890123	45678967
00010001	00100010	PPPPPPP	PPPPPPP

Little-Endian: Offset = 0

Byte 0	Byte 1	Byte 2	Byte 3
01234567	89012345	67890123	45678967
00010001	00100010	PPPPPPP	PPPPPPP

Little-Endian: Offset = 16

Byte 0	Byte 1	Byte 2	Byte 3
01234567	89012345	67890123	45678967
PPPPPPP	PPPPPPP	00010001	00100010

Figure 12

If the offset is incremented then the total size is incremented also if necessary to prevent significant bits of the value from hanging over the edge of the datatype.

The bits of the entire data are numbered beginning at zero at the least significant bit of the least significant byte (the byte at the lowest memory address for a little-endian type or the byte at the highest address for a big-endian type). The offset property defines the bit location of the least significant bit of a bit field whose length is precision. If the offset is increased so the significant bits "hang over" the edge of the datum, then the size property is automatically incremented.

To illustrate the properties of the integer datatype class, Figure 13 shows how to create a user defined datatype that describes a 24-bit signed integer that starts on the third bit of a 32-bit word. The datatype is specialized from a 32-bit integer, the *precision* is set to 24 bits, and the *offset* is set to 3.

```
hid_t dt;
dt = H5Tcopy(H5T_SDT_I32LE);
H5Tset_precision(dt, 24);
H5Tset_offset(dt,3);
H5Tset_pad(dt, H5T_PAD_ZERO, H5T_PAD_ONE);
```

Figure 13

Figure 14 shows the storage layout for a data element. Note that the unused bits in the offset will be set to zero and the unused bits at the end will be set to one, as specified in the H5Tset_pad call.




Figure 14. A User defined integer Datatype: range -1,048,583 to 1,048,584

To illustrate a user defined floating point number, Figure 13 shows how to create a 24-bit floating point number, that starts 5 bits into a 4 byte word. The floating point number is defined to have a mantissa of 19 bits (bits 5-23), and exponent of 3 bits (25-27) and the sign bit is bit 28. (Note that this is an illustration of what can be done, not necessarily a floating point format that a user would require.)

```
hid_t dt;
dt = H5Tcopy(H5T_IEEE_F32LE);
H5Tset_precision(dt, 24);
H5Tset_fields (dt, 28, 25, 3, 5, 19);
H5Tset_pad(dt, H5T_PAD_ZERO, H5T_PAD_ONE);
H5Tset_inpad(dt, H5T_PAD_ZERO);
```

Figure 15

Byte 0	Byte 0 Byte 1		Byte 3
01234567	89012345	67890123	45678967
00000mmm	mmmmmmmm	mmmmmmmm	ieees <i>ppp</i>
mantissa pos (100 Ltd. U	exponent pos (28 exponent size (3	10

Figure 16. A User defined Floating Point Datatype.

Figure 16 shows the storage layout of a data element for this datatype. Note that there is an unused bit (24) between the mantissa and the exponent. This bit is filled with the *inpad* value, in this case 0.

The sign bit is always of length one and none of the fields are allowed to overlap. When expanding a floating-point type one should set the precision first; when decreasing the size one should set the field positions and sizes first.

4.3.2 Composite Datatypes

All composite datatypes must be user defined; there are no predefined composite datatypes.

4.3.2.1 Compound Datatypes

The subsections below describe how to create a compound datatype and how to write and read data of compound datatype.

4.3.2.1.1 Defining Compound Datatypes

Compound datatypes are conceptually similar to a C struct or Fortran 95 derived types. The compound datatype defines a contiguous sequence of bytes, which are formatted using one up to 2^16 datatypes (members). A compound datatype may have any number of members, in any order, and the members may have any datatype, including compound. Thus, complex nested compound datatypes can be created. The total size of the compound datatype is greater than or equal to the sum of the size of its members, up to a maximum of 2^32 bytes. HDF5 does not support datatypes with distinguished records or the equivalent of C unions or Fortran 95 EQUIVALENCE statement.

Usually a C struct or Fortran derived type will be defined to hold a data point in memory, and the offsets of the members in memory will be the offsets of the struct members from the beginning of an instance of the struct. The HDF5 C library provides a macro HOFFSET (s,m) to calculate the member's offset. The HDF5 Fortran applications have to calculate offsets by using sizes of members datatypes and by taking in consideration the order of members in the Fortran derived type.

```
HOFFSET(s,m)
```

This macro computes the offset of member m within a struct s offsetof(s,m)

This macro defined in stddef.h does exactly the same thing as the HOFFSET() macro.

Note for Fortran users: Offsets of Fortran structure members correspond to the offsets within a packed datatype (see explanation below) stored in an HDF5 file.

Each member of a compound datatype must have a descriptive name which is the key used to uniquely identify the member within the compound datatype. A member name in an HDF5 datatype does not necessarily have to be the same as the name of the member in the C struct of Fortran derived type, although this is often the case. Nor does one need to define all members of the C struct of Fortran derived type in the HDF5 compound datatype (or vice versa).

Unlike atomic datatypes which are derived from other atomic datatypes, compound datatypes are created from scratch. First, one creates an empty compound datatype and specifies its total size. Then members are added to the compound datatype in any order. Each member type is inserted at a designated offset. Each member has a name

which is the key used to uniquely identify the member within the compound datatype.

Figure 17a shows an example of creating an HDF5 C compound datatype to describe a complex number, which is a structure with two components, "real" and "imaginary", each double. An equivalent C struct is whose type is defined by the complex_t struct, is shown.

Figure 17a

Figure 17b shows an example of creating an HDF5 Fortran compound datatype to describe a complex number, which is a Fortran derived type with two components, "real" and "imaginary", each DOUBLE PRECISION. An equivalent Fortran TYPE is whose type is defined by the TYPE complex_t, is shown.

```
TYPE complex_t
  DOUBLE PRECISION re ! real part
  DOUBLE PRECISION im; ! imaginary part
END TYPE complex_t

CALL h5tget_size_f(H5T_NATIVE_DOUBLE, re_size, error)
CALL h5tget_size_f(H5T_NATIVE_DOUBLE, im_size, error)
complex_t_size = re_size + im_size
CALL h5tcreaet_f(H5T_COMPOUND_F, complex_t_size, type_id)
offset = 0
CALL h5tinsert_f(type_id, "real", offset, H5T_NATIVE_DOUBLE, error)
offset = offset + re_size
CALL h5tinsert_f(type_id, "imaginary", offset, H5T_NATIVE_DOUBLE, error)
```

Figure 17b

Important Note: The compound datatype is created with a size sufficient to hold all its members. In the C example above, the size of the C struct and the HOFFSET macro are used as a convenient mechanism to determine the appropriate size and offset. Alternatively, the size and offset could be manually determined, e.g., the size can be set to 16 with "real" at offset 0 and "imaginary" at offset 8. However, different platforms and compilers have different sizes for "double", and may have alignment restrictions which require additional padding within the structure. It is much more portable to use the HOFFSET macro, which assures that the values will be correct for any platform.

Figure 18 shows how the compound datatype would be laid out, assuming that NATIVE_DOUBLE are 64-bit numbers, and there are no alignment requirements. The total size of the compound datatype will be 16 bytes, the "real" component will start at byte 0, and "imaginary" will start at byte 8.

offset of "real" is 0	Byte 0	Byte 1	Byte 2	Byte 3
	rrrrrrr	rrrrrrr	rrrrrrr	rrrrrrr
	Byte 4	Byte 5	Byte 6	Byte 7
	rrrrrrr	rrrrrrr	rrrrrrr	rrrrrrr
offset of "imaginary" is 8	Byte 8	Byte 9	Byte 10	Byte 11
	iiiiiiii	iiiiiiii	iiiiiiii	iiiiiiii
	Byte 12	Byte 13	Byte 14	Byte 15
	iiiiiiii	iiiiiiii	iiiiiiii	iiiiiiii

Total size of Compound Datatype is 16 bytes

Figure 18

The members of a compound datatype may be any HDF5 datatype, including compound, array, and VL. Figures 19 and 20 show an example which creates a compound datatype composed of two complex values, each of which is a compound datatype as in Figure 18 above.

25/00 1/2012-1-0013 DO-01: 0-1-1-1-1-2014-				I
offset of "x"	Byte 0	Byte 1	Byte 2	Byte 3
is 0	rrrrrrr	rrrrrrr	rrrrrrr	rrrrrrr
offset of "x.re"	Byte 4	Byte 5	Byte 6	Byte 7
3 H O	rrrrrrr	rrrrrrr	rrrrrrr	rrrrrrr
offset of "x.im"	Byte 8	Byte 9	Byte 10	Byte 11
is 8	iiiiiiii	iiiiiiii	iiiiiiii	11111111
	Byte 12	Byte 13	Byte 14	Byte 15
	iiiiiiii	iiiiiiii	iiiiiiii	iiiiiiii
offset of "y"	Byte 16	Byte 17	Byte 18	Byte 19
is 16	rrrrrrr	rrrrrrr	rrrrrrr	rrrrrrr
offset of "y.re"	Byte 20	Byte 21	Byte 22	Byte 23
is 16	rrrrrrr	rrrrrrr	rrrrrrr	rrrrrrr
/	Byte 24	Byte 25	Byte 26	Byte 27
offset of "x.im"	iiiiiiii	iiiiiiii	11111111	iiiiiiii
is 24	Byte 28	Byte 29	Byte 30	Byte 31
	iiiiiiii	iiiiiiii	iiiiiiii	iiiiiiii

Total size of Compound Datatype is 32 bytes.

Figure 19

```
H5Tinsert (surf_id, "x", HOFFSET(surf_t,x), complex_id);
H5Tinsert (surf_id, "y", HOFFSET(surf_t,y), complex_id);
```

Figure 20

Note that a similar result could be accomplished by creating a compound datatype and inserting four fields (Figure 21). This results in the same layout as above (Figure 19). The difference would be how the fields are addressed. In the first case, the real part of 'y' is called 'y.re'; in the second case it is 'y-re'.

Figure 21

The members of a compound datatype do not always fill all the bytes. The HOFFSET macro assures that the members will be laid out according to the requirements of the platform and language. Figure 22 shows an example of a C struct which requires extra bytes of padding on many platforms. The second element, 'b', is a 1-byte character, followed by an 8 byte double, 'c'. On many systems, the 8-byte value must be stored on a 4- or 8-byte boundary, requiring the struct to be larger than the sum of the size of its elements.

In Figure 22, the sizeof and HOFFSET macro is used to assure that the members are inserted at the correct offset to match the memory conventions of the platform. Figure 23 shows how this data element would be stored in memory, assuming the double must start on a 4-byte boundary. Notice the extra bytes between 'b' and 'c'.

```
typedef struct s1_t {
   int a;
   char b;
   double c;
} s1_t;

s1_tid = H5Tcreate (H5T_COMPOUND, sizeof(s1_t));
H5Tinsert(s1_tid, "a_name", HOFFSET(s1_t, a), H5T_NATIVE_INT);
H5Tinsert(s1_tid, "b_name", HOFFSET(s1_t, b), H5T_NATIVE_CHAR);
H5Tinsert(s1_tid, "c_name", HOFFSET(s1_t, c), H5T_NATIVE_DOUBLE);
```

Figure 22




Figure 23

However, data stored on disk does not require alignment, so unaligned versions of compound data structures can be created to improve space efficiency on disk. These unaligned compound datatypes can be created by computing offsets by hand to eliminate inter-member padding, or the members can be packed by calling H5Tpack (which modifies a datatype directly, so it is usually preceded by a call to H5Tcopy):

Figure 24a shows how to create a disk version of the compound datatype from Figure 22 above in order to store data on disk in as compact a form as possible. Figure 25 shows the layout of the bytes in the packed data structure. Packed compound datatypes should generally not be used to describe memory as they may violate alignment constraints for the architecture being used. Note also that using a packed datatype for disk storage may involve a higher data conversion cost.

Figure 24a

Figure 24b shows the sequence of Fortran calls to create a packed compound datatype. An HDF5 Fortran compound datatype never describes a compound datatype in memory and compound data is *ALWAYS* written by fields as described in the next section. Therefore packing is not needed unless the offset of each consecutive member is not equal to the sum of the sizes of the previous members.

```
CALL h5tcopy_f(s1_id, s2_id, error)
CALL h5tpack_f(s2_id, error)
```

Figure 24b

4.3.2.1.2 Creating and writing datasets with compound datatypes

Creating datasets with compound datatypes is similar to creating datasets with any other HDF5 datatypes. But writing and reading may be different since datasets that have compound datatypes can be written or read by a field (member) or subsets of fields (members). The compound datatype is the only composite datatype that supports "sub-setting" by the elements the datatype is built from.

Figure 25a shows C example of creating and writing a dataset with a compound datatype.

```
typedef struct s1_t {
        int
              a;
        float b;
        double c;
     } s1_t;
     s1_t data[LENGTH];
     /* Initialize data */
     for (i = 0; i < LENGTH; i++) {
         data[i].a = i;
          data[i].b = i*i;
          data[i].c = 1./(i+1);
     s1_tid = H5Tcreate (H5T_COMPOUND, sizeof(s1_t));
     H5Tinsert(s1_tid, "a_name", HOFFSET(s1_t, a), H5T_NATIVE_INT);
     H5Tinsert(s1_tid, "b_name", HOFFSET(s1_t, b), H5T_NATIVE_FLOAT);
    H5Tinsert(s1_tid, "c_name", H0FFSET(s1_t, c), H5T_NATIVE_DOUBLE);
    dataset_id = H5Dcreate(file_id, "SDScompound.h5", s1_t, space_id,
H5PDEFAULT);
    H5Dwrite (dataset_id,s1_tid, H5S_ALL, H5S_ALL, H5P_DEFAULT, data);
```

Figure 25a

Figure 25b shows the content of the file written on the little-endian machine.

```
HDF5 "SDScompound.h5" {
GROUP "/" {
    DATASET "ArrayOfStructures" {
       DATATYPE H5T_COMPOUND {
          H5T_STD_I32LE "a_name";
          H5T IEEE F32LE "b name";
          H5T_IEEE_F64LE "c_name";
       DATASPACE SIMPLE { ( 3 ) / ( 3 ) }
       DATA {
       (0): {
             0,
             0,
             1
          },
       (1): {
             1,
             1,
             0.5
          },
       (2): {
             2,
             4,
             0.333333
    }
```

Figure 25b

It is not necessary to write the whole data at once. Datasets with compound datatypes can be written by field or by subsets of fields. In order to do this one has to remember to set transfer property of the dataset using H5Pset_preserve call and to define memory datatype that corresponds to a field. Figure 25c shows how float and double fields are written to the dataset.

```
typedef struct sb_t {
  float b;
   double c;
} sb_t;
typedef struct sc_t {
   float b;
  double c;
} sc_t;
sb_t data1[LENGTH];
sc_t data2[LENGTH];
/* Initialize data */
for (i = 0; i < LENGTH; i++) {
    data1.b = i*i;
     data2.c = 1./(i+1);
/* Create dataset as in example 25a */
/* Create memory datatypes corresponding to float and double
```

```
datatype fileds */

sb_tid = H5Tcreate (H5T_COMPOUND, sizeof(sb_t));
H5Tinsert(sb_tid, "b_name", H0FFSET(sb_t, b), H5T_NATIVE_FLOAT);
sc_tid = H5Tcreate (H5T_COMPOUND, sizeof(sc_t));
H5Tinsert(sc_tid, "c_name", H0FFSET(sc_t, c), H5T_NATIVE_DOUBLE);
...
/* Set transfer property */
xfer_id = H5Pcreate(H5P_DATASET_XFER);
H5Pset_preserve(xfer_id, 1);
H5Dwrite (dataset_id,sb_tid, H5S_ALL, H5S_ALL, xfer_id, data1);
H5Dwrite (dataset_id,sc_tid, H5S_ALL, H5S_ALL, xfer_id, data2);
```

Figure 25c

Figure 25d shows the content of the file written on the little-endian machine. Only float and double fields are written. Default fill value is used to initialize unwritten integer field.

```
HDF5 "SDScompound.h5" {
GROUP "/" {
    DATASET "ArrayOfStructures" {
       DATATYPE H5T_COMPOUND {
          H5T_STD_I32LE "a_name";
          H5T_IEEE_F32LE "b_name";
          H5T_IEEE_F64LE "c_name";
       DATASPACE SIMPLE { ( 3 ) / ( 3 ) }
       DATA {
       (0): {
             Ο,
              0,
              1
          },
       (1): {
             0,
             1,
             0.5
          },
       (2): {
             0,
             4,
             0.333333
          }
       }
    }
```

Figure 25d

Figure 25e contains a Fortran example that creates and writes a dataset with a compound datatype. As this example illustrates, writing and reading compound datatypes in Fortran is *always* done by fields. The content of the written file is the same as shown in the Figure 25b.

```
! One cannot write an array of a derived datatype in Fortran.
TYPE s1_t
  INTEGER
  REAL
   DOUBLE PRECISION c
END TYPE s1_t
TYPE(s1_t) d(LENGTH)
! Therefore, the following code initializes an array corresponding
! to each field in the derived datatype and writes those arrays
! to the dataset
INTEGER, DIMENSION(LENGTH)
                                   :: a
REAL, DIMENSION(LENGTH)
DOUBLE PRECISION, DIMENSION(LENGTH) :: c
! Initialize data
do i = 1, LENGTH
   a(i) = i-1
   b(i) = (i-1) * (i-1)
    c(i) = 1./i
 enddo
. . .
 ! Set dataset transfer property to preserve partially initialized fields
 ! during write/read to/from dataset with compound datatype.
 CALL h5pcreate_f(H5P_DATASET_XFER_F, plist_id, error)
 CALL h5pset_preserve_f(plist_id, .TRUE., error)
!
 ! Create compound datatype.
 ! First calculate total size by calculating sizes of each member
 CALL h5tget_size_f(H5T_NATIVE_INTEGER, type_sizei, error)
 CALL h5tget_size_f(H5T_NATIVE_REAL, type_sizer, error)
 CALL h5tget_size_f(H5T_NATIVE_DOUBLE, type_sized, error)
 type_size = type_sizei + type_sizer + type_sized
 CALL h5tcreate_f(H5T_COMPOUND_F, type_size, dtype_id, error)
 ! Insert memebers
 ! INTEGER member
 offset = 0
 CALL h5tinsert_f(dtype_id, "a_name", offset, H5T_NATIVE_INTEGER, error)
 ! REAL member
 offset = offset + type_sizei
 CALL h5tinsert_f(dtype_id, "b_name", offset, H5T_NATIVE_REAL, error)
```

```
! DOUBLE PRECISION member
offset = offset + type_sizer
CALL h5tinsert_f(dtype_id, "c_name", offset, H5T_NATIVE_DOUBLE, error)
! Create the dataset with compound datatype.
CALL h5dcreate_f(file_id, dsetname, dtype_id, dspace_id, &
                 dset_id, error)
!
. . .
! Create memory types. We have to create a compound datatype
! for each member we want to write.
CALL h5tcreate_f(H5T_COMPOUND_F, type_sizei, dt1_id, error)
CALL h5tinsert_f(dt1_id, "a_name", offset, H5T_NATIVE_INTEGER, error)
CALL h5tcreate_f(H5T_COMPOUND_F, type_sizer, dt2_id, error)
offset = 0
CALL h5tinsert_f(dt2_id, "b_name", offset, H5T_NATIVE_REAL, error)
CALL h5tcreate_f(H5T_COMPOUND_F, type_sized, dt3_id, error)
offset = 0
CALL h5tinsert_f(dt3_id, "c_name", offset, H5T_NATIVE_DOUBLE, error)
! Write data by fields in the datatype. Fields order is not important.
CALL h5dwrite_f(dset_id, dt3_id, c, data_dims, error, xfer_prp = plist_id)
CALL h5dwrite_f(dset_id, dt2_id, b, data_dims, error, xfer_prp = plist_id)
CALL h5dwrite_f(dset_id, dt1_id, a, data_dims, error, xfer_prp = plist_id)
```

Figure 25e

4.3.2.1.3 Reading datasets with compound datatypes

Reading datasets with compound datatypes may be a challenge. For general applications there is no way to know *a priori* the corresponding C structure. Also C structure cannot be allocated on a fly during discovery of the dataset s datatype. For general C , C++, Fortran and Java application the following steps will be required to read and to interpret data from the dataset with compound datatype:

- 1. Get the handle of the compound datatype in the file with the H5Dget_type call
- 2. Find the number of the compound datatype members with the H5Tget_nmembers call
- 3. Iterate through compound datatype members
 - ♦ Get member class with the H5Tget_member_class call
 - ♦ Get member name with the H5Tget_member_name call
 - ♦ Check class type against predefined classes
 - · H5T INTEGER
 - · H5T_FLOAT
 - · H5T_STRING
 - · H5T_BITFIELD
 - · H5T_OPAQUE
 - · H5T COMPOUND
 - · H5T_REFERENCE
 - · H5T_ENAM
 - · H5T_VLEN
 - · H5T ARRAY
 - ♦ If class is H5T_COMPOUND, then go to step 2 and repeat all steps under step 3. If class is not H5T_COMPOUND, then a member is of an atomic class and can be read to a corresponding buffer after discovering all necessary information specific to each atomic type (e.g. size of the integer or floats, super class for enumerated and array datatype, and it sizes, etc.)

Examples below show how to read dataset with a known compound datatype.

Figure 25f shows the steps needed to read data of known structure. First one has to build memory datatype the same way it was building when dataset was created, second use the datatype in H5Dread call.

```
typedef struct s1_t {
   int a;
   float b;
   double c;
} s1_t;

s1_t *data;

...
s1_tid = H5Tcreate(H5T_COMPOUND, sizeof(s1_t));
H5Tinsert(s1_tid, "a_name", H0FFSET(s1_t, a), H5T_NATIVE_INT);
H5Tinsert(s1_tid, "b_name", H0FFSET(s1_t, b), H5T_NATIVE_FLOAT);
H5Tinsert(s1_tid, "c_name", H0FFSET(s1_t, c), H5T_NATIVE_DOUBLE);
...
dataset_id = H5Dopen(file_id, "SDScompound.h5");
...
data = (s1_t *) malloc (sizeof(s1_t)*LENGTH);
H5Dread(dataset id,s1_tid, H5S_ALL, H5S_ALL, H5P_DEFAULT, data);
```

Figure 25f

HDF5 Library provides the H5Tget_native_type function to avoid building memory datatype as shown in Figure 25g.

```
typedef struct s1_t {
   int   a;
   float b;
   double c;
} s1_t;

s1_t *data;
hid_t file_s1_t, mem_s1_t;
...
dataset_id = H5Dopen(file_id, "SDScompound.h5");
/* Discover datatype in the file */
file_s1_t = H5Dget_type(dataset_id);
/* Find corresponding memory datatype */
mem_s1_t = H5Tget_native_type(file_s1_t, H5T_DIR_DEFAULT);
...
data = (s1_t *) malloc (sizeof(s1_t)*LENGTH);
H5Dread (dataset_id,mem_s1_tid, H5S_ALL, H5S_ALL, H5P_DEFAULT, data);
```

Figure 25g

Example 25h shows how to read just one float member of a compound datatype.

```
typedef struct s1_t {
    float b;
} sf_t;

sf_t *data;
...
sf_tid = H5Tcreate(H5T_COMPOUND, sizeof(sf_t));
H5Tinsert(s1_tid, "b_name", HOFFSET(sf_t, b), H5T_NATIVE_FLOAT);
...
dataset_id = H5Dopen(file_id, "SDScompound.h5");
...
data = (sf_t *) malloc (sizeof(sf_t)*LENGTH);
H5Dread(dataset_id,sf_tid, H5S_ALL, H5P_DEFAULT, data);
```

Figure 25h

Example on Figure 25i how to read float and double members of the compound datatype into the structure that has those fields in a different order. Please notice that H5Tinsert calls can be used in an order different from the order of the structure's members.

```
typedef struct sl_t {
    double c;
    float b;
} sdf_t;

sdf_t *data;

...

sdf_tid = H5Tcreate(H5T_COMPOUND, sizeof(sdf_t));
H5Tinsert(sdf_tid, "b_name", H0FFSET(sdf_t, b), H5T_NATIVE_FLOAT);
H5Tinsert(sdf_tid, "c_name", H0FFSET(sdf_t, c), H5T_NATIVE_DOUBLE);
...

dataset_id = H5Dopen(file_id, "SDScompound.h5");
...

data = (sdf_t *) malloc (sizeof(sdf_t)*LENGTH);
H5Dread(dataset_id,sdf_tid, H5S_ALL, H5S_ALL, H5P_DEFAULT, data);
```

Figure 25i

4.3.2.2 Array

Many scientific datasets have multiple measurements for each point in a space. There are several natural ways to represent this data, depending on the variables and how they are used in computation (Table 21).




Figure 26

The HDF5 H5T_ARRAY datatype defines the data element to be a homogeneous, multi-dimensional array, as in Figure 26d, above. The elements of the array can be any HDF5 datatype (including compound and array), the size of the datatype is the total size of the array. A dataset of array datatype cannot be subdivided for I/O within the data element, the entire array of the data element must be transferred. If the data elements need to be accessed separated, e.g., by plane, then the array datatype should not be used. Table 22 gives advantages and disadvantages of the storage methods.

Table 22

Method	Advantages	Disadvantages
a) Multiple		
Datasets	 Easy to access each plane, can select any plane(s). 	 Less efficient to access a 'column' through the planes
b) N+1		
Dimension	 All access patterns supported. 	 Must be homogeneous datatype. The added dimension may not make sense in the scientific model.
c) Compound		
Datatype	 Can be heterogenous datatype. 	 Planes must be named, selection is by plane.
		 Not a natural representation for a matrix.
d) Array		
	 Cannot access elements separately (no access by plane) 	 A natural representation for vector or tensor data.

An array datatype may be multi-dimensional, with 1 to H5S_MAX_RANK (the maximum rank of a dataset is currently 32). The dimensions can be any size greater than 0, but unlimited dimensions are not supported (although the datatype can be a variable length datatype).

- An array datatype may be multi-dimensional, with 1 to H5S_MAX_RANK (the maximum rank of a dataset is currently 32).
- The elements of the array can be any HDF5 datatype (including compound and array),
- An array datatype element cannot be subdivided for I/O, the entire array of the data element must be transferred.

An array datatype is create with the H5Tarray_create call, which specifies the number of dimensions, the size of each dimension, and the base type of the array. The array datatype can then be used in any way that any datatype object is used. Figure 27 shows the creation of a datatype that is a two-dimensional array of native integers, which is then used to create a dataset. Note that the dataset can a dataspace that is any number and size of dimensions. Figure 28 shows the layout in memory, assuming that the native integers are 4 bytes. Each data element has 6 elements, for a total of 24 bytes.

Figure 27




Figure 28

4.3.2.3 Variable-length (VL) Datatypes

A variable-length (VL) datatype is a one-dimensional sequence of a datatype which are not fixed in length from one dataset location to another, i.e., each data element may have a different number of members. Variable-length datatypes cannot be divided, the entire data element must be transferred.

VL datatypes are useful to the scientific community in many different ways, possibly including:

- Ragged arrays: Multi-dimensional ragged arrays can be implemented with the last (fastest changing) dimension being ragged by using a VL datatype as the type of the element stored.
- Fractal arrays: A nested VL datatype can be used to implement ragged arrays of ragged arrays, to whatever nesting depth is required for the user.
- *Polygon lists*: A common storage requirement is to efficiently store arrays of polygons with different numbers of vertices. A VL datatypes can be used to efficiently and succinctly describe an array of polygons with different numbers of vertices.
- *Character strings*: Perhaps the most common use of VL datatypes will be to store C-like VL character strings in dataset elements or as attributes of objects.
- *Indices, e.g. of objects within the file*: An array of VL object references could be used as an index to all the objects in a file which contain a particular sequence of dataset values.
- *Object Tracking*: An array of VL dataset region references can be used as a method of tracking objects or features appearing in a sequence of datasets.

A VL datatype is created by calling H5Tvlen_create, which specifies the base datatype. Figure 29 shows an example of code that creates a VL datatype of unsigned integers. Each data element is a one-dimensional array of zero or more members, which must be stored in a structure, hvl_t (Figure 30).

```
tid1 = H5Tvlen_create (H5T_NATIVE_UINT);
dataset=H5Dcreate(fid1, "Dataset1", tid1, sid1, H5P_DEFAULT);
Figure 29

typedef struct {
    size_t len; /* Length of VL data (in base type units) */
    void *p; /* Pointer to VL data */
} hvl_t;
```

Figure 30

Figure 31 shows how the VL data is written. For each of the 10 data elements, a length and data buffer must be allocated. Figure 33 shows how the data is laid out in memory.

An analogous procedure must be used to read the data (Figure 32). An appropriate array of vl_t must be allocated, and the data read. It is then traversed one data element at a time. The H5Dvlen_free call frees the data buffer for the buffer. With each element possibly being of different sequence lengths for a dataset with a VL datatype, the memory for the VL datatype must be dynamically allocated. Currently there are two methods of managing the memory for VL datatypes: the standard C malloc/free memory allocation routines or a method of calling user-defined memory management routines to allocate or free memory (set with H5Pset_vlen_mem_manager). Since the memory allocated when reading (or writing) may be complicated to release, the H5Dvlen_reclaim) is provided to traverse a memory buffer and free the VL datatype information without leaking memory.

Figure 32




Figure 33

The user program must carefully manage these relatively complex data structures, such as suggested by Figure 33. The H5Dvlen_reclaim function performs a standard traversal, freeing all the data. This function analyzes the datatype and dataspace objects, and visits each VL data element, recursing through nested types. By default, the system free is called for the pointer in each vl_t. Obviously, this call assumes that all of this memory was allocated with the system malloc.

The user program may specify custom memory manager routines, one for allocating and one for freeing. These may be set with the H5Pvlen_mem_manager, and must have the following prototypes:

```
typedef void *(*H5MM_allocate_t)(size_t size, void *info);
typedef void (*H5MM_free_t)(void *mem, void *free_info);
```

The utility function H5Dget_vlen_buf_size checks the number of bytes required to store the VL data from the dataset. This function analyzes the datatype and dataspace object to visit all the VL data elements, to determine the number of bytes required to store the data for the in the destination storage (memory). The size value is adjusted for data conversion and alignment in the destination.

5. Other Non-numeric Datatypes

Several datatype classes define special types of objects.

5.1 Strings

Text data is represented by arrays of characters, called strings. Many programming languages support different conventions for storing strings, which may be fixed or variable length, and may have different rules for padding unused storage. HDF5 can represent strings in several ways.

The Strings to store are: "Four score",

"lazy programmers."

a) H5T_NATIVE_CHAR the dataset is a one-dimensional array with 29 elements, each element is a single character.

0	1	2	3	4	 25	26	27	28
'F'	'o'	'u'	'r'	-	 'r'	's'	<u>:</u> .	'\0'

b) Fixed-length string

The dataset is a one-dimensional array with 2 elements, each element is 20 characters.

0	"Four	score\0	"
1	"lazy	programmers.\0	"

c) Variable Length string

The dataset is a one-dimensional array with 2 elements, each element is a variable-length string.

This is the same result when stored as fixed-length string, except that first element of the array will need only 11 bytes for storage instead of 20.

	0	"Four score	2\0"
Ī	1	"lazy progr	rammers.\0"




Figure 34

First, a dataset may have a dataset with datatype H5T_NATIVE_CHAR, with each character of the string as an element of the dataset. This will store an unstructured block of text data, but gives little indication of any structure in the text (Figure 34a).

A second alternative is to store the data using the datatype class H5T_STRING, with each element a fixed length (Figure 34b). In this approach, each element might be a word or a sentence, addressed by the dataspace. The dataset reserves space for the specified number of characters, although some strings may be shorter. This approach is simple and usually is fast to access, but can waste storage space if the length of the Strings varies.

A third alternative is to use a variable-length datatype (Figure 34c). This can be done using the standard mechanisms described above (e.g., using H5T_NATIVE_CHAR instead of H5T_NATIVE_INT in Figure 29 above). The program would use v1_t structures to write and read the data.

A fourth alternative is to use a special feature of the string datatype class, to set the size of the datatype to H5T_VARIABLE (Figure 34c). Figure 35 shows a declaration of a datatype of type H5T_C_S1, which is set to H5T_VARIABLE. The HDF5 Library automatically translates between this and the v1_t structure. (Note: the H5T_VARIABLE size can only be used with string datatypes.)

```
tid1 = H5Tcopy (H5T_C_S1);
ret = H5Tset_size (tid1, H5T_VARIABLE);
```

Figure 35

Variable-length strings can be read into C strings (i.e., pointers to zero terminated arrays of char) (Figure 36).

Figure 36

5.2 Reference

In HDF5, objects (i.e. groups, datasets, and named datatypes) are usually accessed by name. There is another way to access stored objects -- by reference. There are two reference datatypes, object reference and region reference. Object reference objects are created with the H5Rcreate and other calls (cross reference). These objects can be stored and retrieved in a dataset as elements with reference datatype. Figure 37 shows an example of code that creates references to four objects, and then writes the array of object references to a dataset. Figure 38 shows a dataset of datatype reference being read, and one of the object reference objects being dereferenced to obtain an object pointer.

In order to store references to regions of a dataset, the datatype should be H5T_REGION_OBJ. Note that a data element must be either an object reference or a region reference: these are different types and cannot be mixed within a single array.

A reference datatype cannot be divided for I/O, an element is read or written completely.

```
dataset=H5Dcreate(fid1, "Dataset3", H5T_STD_REF_OBJ, sid1, H5P_DEFAULT);
   /* Create reference to dataset */
  ret = H5Rcreate(&wbuf[0],fid1,"/Group1/Dataset1",H5R_OBJECT,-1);
   /* Create reference to dataset */
  ret = H5Rcreate(&wbuf[1],fid1,"/Group1/Dataset2",H5R_OBJECT,-1);
   /* Create reference to group */
  ret = H5Rcreate(&wbuf[2],fid1,"/Group1",H5R_OBJECT,-1);
   /* Create reference to named datatype */
  ret = H5Rcreate(&wbuf[3],fid1,"/Group1/Datatype1",H5R_OBJECT,-1);
   /* Write selection to disk */
ret=H5Dwrite(dataset, H5T_STD_REF_OBJ, H5S_ALL, H5S_ALL, H5P_DEFAULT, wbuf);
                                    Figure 37
 rbuf = malloc(sizeof(hobj_ref_t)*SPACE1_DIM1);
 /* Read selection from disk */
ret=H5Dread(dataset, H5T_STD_REF_OBJ, H5S_ALL, H5S_ALL, H5P_DEFAULT, rbuf);
   /* Open dataset object */
   dset2 = H5Rdereference(dataset, H5R_OBJECT, &rbuf[0]);
```

Figure 38

5.3 ENUM

The enum datatype implements a set of (name, value) pairs, similar to C/C++ enum. The values are currently limited to integer dataype class. Each name can be the name of only one value, and each value can have only one name. There can be up to 2^16 different names for a given enumeration.

The data elements of the ENUMERATION are stored according to the datatype, e.g., as an array of integers. Figure 39 shows an example of how to create an enumeration with five elements. The elements map symbolic names to 2-byte integers (Table 23).

```
hid_t hdf_en_colors = H5Tcreate(H5T_ENUM, sizeof(short));
short val;

H5Tenum_insert(hdf_en_colors, "RED", (val=0,&val));
H5Tenum_insert(hdf_en_colors, "GREEN", (val=1,&val));
H5Tenum_insert(hdf_en_colors, "BLUE", (val=2,&val));
H5Tenum_insert(hdf_en_colors, "WHITE", (val=3,&val));
H5Tenum_insert(hdf_en_colors, "BLACK", (val=4,&val));
H5Dcreate(fileid,spaceid,hdf_en_colors,H5P_DEFAULT);
```

Figure 39

	Table 23
Name	Value
RED	0
GREEN	1
BLUE	2
WHITE	3
BLACK	4

Figure 40 shows how an array of eight values might be stored. Conceptually, the array is an array of symbolic names [BLACK, RED, WHITE, BLUE,] (Figure 40a). These are stored as the values, i.e., as short integers. So, the first 2 bytes are the value associated with "BLACK", which is the number 4, and so on (Figure 40b).

a) Logical Data to be written 8 (elements)

I	ndex	Name
	0	:BLACK
	1	RED
	2	WHITE
	3	BLUE
	4	RED
	5	WHITE
	6	BLUE
	7	GREEN

offset of "BLACK" is 0, value 4	Byte 0 00000000	Byte 1 00000100	Byte 2 00000000	Byte 3 00000000
_	Byte 4	Byte 5	Byte 6	Byte 7
offset of "RED"	0000000	00000011	00000000	00000010
is 2, value 0	Byte 8	Byte 9	Byte 10	Byte 11
	00000000	00000000	00000000	00000011
offset of	Byte 12	Byte 13	Byte 14	Byte 15
"WHITE" is 4, value 3	00000000	00000011	00000000	00000001

b) The storage layout. Total size of the array is 16 bytes, 2 bytes per element.

Figure 40

The order that members are inserted into an enumeration type is unimportant; the important part is the associations between the symbol names and the values. Thus, two enumeration datatypes will be considered equal if and only if both types have the same symbol/value associations and both have equal underlying integer datatypes. Type equality is tested with the H5Tequal() function.

5.4 Opaque

In some cases, a user may have data objects that should be stored and retrieved as blobs, with no attempt to interpret them. For example, an application might wish to store an array of encrypted certificates, which are 100 bytes long

While an arbitrary block of data may always be stored as bytes, characters, integers, or whatever, this might mislead programs about the meaning of the data. The opaque datatype defines data elements which are uninterpreted by HDF5. The opaque data may be labeled with H5Tset_tag, with a string that might be used by an application. For example, the encrypted certificates might have a tag to indicate the encryption and the certificate standard.

5.5 Bitfield

Some data is represented as bits, where the number of bits is not an integral byte and the bits are not necessarily interpreted as a standard type. Some examples might include readings from machine registers (e.g., switch positions), a cloud mask, or data structures with several small integers that should be store in a single byte.

This data could be stored as integers, strings, or enumerations. However, these storage methods would likely have considerable wasted space. For example, storing a cloud mask with one byte per value would use 8 times the space of a packed array of bits.

The HDF5 bitfield dataype class defines a data element that is a contiguous sequence of bits, which are stored on disk in a packed array. The programming model is the same as for unsigned integers: the dataype object is created by copying a predefined dataype, and then the precision, offset, and padding are set.

6. Fill Values

The "fill value" for a dataset is the specification of the default value assigned to data elements that have not yet been written. In the case of a dataset with an atomic datatype, the fill value is a single value of the appropriate datatype, such as '0' or '-1.0'. In the case of a dataset with a composite datatype, the "fill value" is a single data element of the appropriate type. For example, for an array or compound datatype, the "fill value" is a single data element with values for all the component elements of the array or compound datatype.

The fill value is set (permanently) when the dataset is created. The fill value is set in the dataset creation properties in the H5Dcreate call. Note that the H5Dcreate call must also include the datatype of the dataset, and the value provided for the fill value will be interpreted as a single element of this datatype. Figure 41 shows example code which creates a dataset of integers with fill value -1. Any unwritten data elements will be set to -1.

```
hid_t
           plist_id;
int filler;
filler = -1;
plist_id = H5Pcreate(H5P_DATASET_CREATE);
H5Pset_fill_value(plist, H5T_NATIVE_INT, &filler);
/* Create the dataset with filel value '-1'. */
dataset_id = H5Dcreate(file_id, "/dset", H5T_STD_I32BE, dataspace_id, plist);
                                 Figure 41
 typedef struct s1_t {
    int a;
    char b;
    double c;
 } s1_t;
           filler;
 s1_t
 s1_tid = H5Tcreate (H5T_COMPOUND, sizeof(s1_t));
 H5Tinsert(s1_tid, "a_name", HOFFSET(s1_t, a), H5T_NATIVE_INT);
 H5Tinsert(s1_tid, "b_name", HOFFSET(s1_t, b), H5T_NATIVE_CHAR);
 H5Tinsert(s1_tid, "c_name", HOFFSET(s1_t, c), H5T_NATIVE_DOUBLE);
 filler.a = -1;
 filler.b = '*';
 filler.c = -2.0;
 plist_id = H5Pcreate(H5P_DATASET_CREATE);
 H5Pset_fill_value(plist_id, s1_tid, &filler);
 /* Create the dataset with fill value (-1, '*', -2.0). */
 dataset = H5Dcreate(file, DATASETNAME, s1_tid, space, plist_id);
```

Figure 42

Figure 42 shows how to create a "fill value" for a compound datatype. The procedure is the same as the previous example, except the filler must be a structure with the correct fields. Each field is initialized to the desired fill value.

The fill value for a dataset can be retrieved by reading the dataset creation properties of the dataset, and then reading the fill value with H5Pget_fill_value. The data will be read into memory using the storage layout specified by the datatype. This transfer will convert data in the same way as H5Dread. Figure 43 shows how to get the fill value from the dataset created in Figure 41 above.

```
hid_t plist2;
int filler;

dataset_id = H5Dopen(file_id, "/dset" );
plist2 = H5Dget_create_plist(dataset_id);

H5Pget_fill_value(plist, H5T_NATIVE_INT, &filler);

/* filler has the fill value, '-1' */
```

Figure 43

A similar procedure is followed for any datatype. Figure 45 shows how to read the fill value created in Figure 42. Note that the program must pass an element large enough to hold a fill value of the datatype indicated by the argument to H5Pget_fill_value. Also, the program must understand the datatype in order to interpret its components. This may be difficult to determine without knowledge of the application that created the dataset.

```
char * fillbuf;
int sz;
dataset = H5Dopen( file, DATASETNAME);

sl_tid = H5Dget_type(dataset);

sz = H5Tget_size(sl_tid);

fillbuf = (char *)malloc(sz);

plist_id = H5Dget_create_plist(dataset);

H5Pget_fill_value(plist_id, sl_tid, fillbuf);

printf("filler.a: %d\n",((sl_t *) fillbuf)->a);
printf("filler.b: %c\n",((sl_t *) fillbuf)->b);
printf("filler.c: %f\n",((sl_t *) fillbuf)->c);
```

Figure 44

7. Complex Combinations of Datatypes

7.1

Several composite datatype classes define collections of other datatypes, including other composite datatypes. In general, a datatype can be nested to any depth, with any combination of datatypes.

For example, a compound datatype can have members that are other compound datatypes, arrays, VL datatypes. An array can be an array of array, an array of compound, or an array of VL. And a VL datatype can be a variable length array of compound, array, or VL datatypes.

These complicated combinations of datatypes form a logical tree, with a single root datatype, and leaves which must be atomic datatypes (predefined or user-defined). Figure 45 shows an example of a logical tree describing a compound datatype constructed from different datatypes.

Recall that the datatype is a description of the layout of storage. The complicated compound datatype is constructed from component datatypes, each of which describe the layout of part of the storage. Any datatype can be used as a component of a compound datatype, with the following restrictions:

- 1. No byte can be part of more than one component datatype (i.e., the fields cannot overlap within the compound datatype).
- 2. The total size of the components must be less than or equal to the total size of the compound datatype.

These restrictions are essentially the rules for C structures and similar record types familiar from programming languages. Multiple typing, such as a C union, is not allowed in HDF5 datatypes.




Figure 45

7.2 Creating a complicated compound datatype

To construct a complicated compound datatype, each component is constructed, and then added to the enclosing datatype description. Figure 46 shows some example code to create a compound datatype with four members:

- "T1", a compound datatype with three members
- "T2", a compound datatype with two members
- "T3", a one-dimensional array of integers
- "T4", a string

This datatype is shown as a logical tree in Figure 47, the output of the h5dump utility is shown in Figure 48.

Each datatype is created as a separate datatype object. Figure 49 shows the storage layout for the four individual datatypes. Then the dataypes are inserted into the outer datatype at an appropriate offset. Figure 50 shows the resulting storage layout. The combined record is 89 bytes long.

The Dataset is created using the combined compound datatype. The dataset is declared to be a 4 by 3 array of compound data. Each data element is an instance of the 89-byte compound datatype. Figure 51 shows the layout of the dataset, and expands one of the elements to show the relative position of the component data elements.

Each data element is a compound datatype, which can be written or read as a record, or each field may be read or written individually. The first field ("T1") is itself a compound datatype with three fields ("T1.a", "T1.b", and "T1.c"). "T1" can be read or written as a record, or individual fields can be accessed. Similarly, the second filed is a compound datatype with two fields ("T2.f1", "T2.f2").

The third field ("T3") is an array datatype. Thus, "T3" should be accessed as an array of 40 integers. Array data can only be read or written as a single element, so all 40 integers must be read or written to the third field. The fourth field ("T4") is a single string of length 25.

```
typedef struct s1_t {
   int a;
    char b;
   double c;
} s1_t;
typedef struct s2_t {
   float f1;
   float f2;
} s2_t;
        s1_tid, s2_tid, s3_tid, s4_tid, s5_tid;
hid_t
/* Create a datatype for s1 */
s1_tid = H5Tcreate (H5T_COMPOUND, sizeof(s1_t));
H5Tinsert(s1_tid, "a_name", HOFFSET(s1_t, a), H5T_NATIVE_INT);
H5Tinsert(s1_tid, "b_name", HOFFSET(s1_t, b), H5T_NATIVE_CHAR);
H5Tinsert(s1_tid, "c_name", HOFFSET(s1_t, c), H5T_NATIVE_DOUBLE);
/* Create a data type for s2. *.
s2_tid = H5Tcreate (H5T_COMPOUND, sizeof(s2_t));
H5Tinsert(s2_tid, "f1", H0FFSET(s2_t, f1), H5T_NATIVE_FLOAT);
H5Tinsert(s2_tid, "f2", H0FFSET(s2_t, f2), H5T_NATIVE_FLOAT);
/* Create a datatype for an Array of integers */
s3_tid = H5Tarray_create(H5T_NATIVE_INT, RANK, dim, NULL);
/* Create a data type for a String of 25 characters */
s4\_tid = H5Tcopy(H5T\_C\_S1);
H5Tset_size(s4_tid, 25);
* Create a compound datatype composed of one of each of these
* types.
 * The total size is the sum of the size of each.
sz = H5Tget_size(s1_tid) + H5Tget_size(s2_tid) + H5Tget_size(s3_tid)
     + H5Tget_size(s4_tid);
s5_tid = H5Tcreate (H5T_COMPOUND, sz);
/* insert the component types at the appropriate offsets */
H5Tinsert(s5_tid, "T1", 0, s1_tid);
H5Tinsert(s5_tid, "T2", sizeof(s1_t), s2_tid);
H5Tinsert(s5_tid, "T3", sizeof(s1_t)+sizeof(s2_t), s3_tid);
H5Tinsert(s5_tid, "T4", (sizeof(s1_t) +sizeof(s2_t)+
       H5Tget_size(s3_tid)), s4_tid);
* Create the dataset with this datatype.
dataset = H5Dcreate(file, DATASETNAME, s5_tid, space, H5P_DEFAULT);
```

Figure 46




Figure 47

```
DATATYPE H5T_COMPOUND {
  H5T_COMPOUND {
     H5T_STD_I32LE "a_name";
     H5T_STD_I8LE "b_name";
     H5T_IEEE_F64LE "c_name";
   } "T1";
   H5T_COMPOUND {
     H5T_IEEE_F32LE "f1";
     H5T_IEEE_F32LE "f2";
   } "T2";
   H5T_ARRAY { [10] H5T_STD_I32LE } "T3";
   H5T_STRING {
     STRSIZE 25;
     STRPAD H5T_STR_NULLTERM;
     CSET H5T_CSET_ASCII;
     CTYPE H5T_C_S1;
   } "T4";
}
```

Figure 48

a) Compound type 's1_t', size 16 bytes.

			a
Byte 0	Byte 1	Byte 2	Byte 3
aaaaaaaa	aaaaaaaa	aaaaaaaa	aaaaaaaa
Byte 4	Byte 5	Byte 6	Byte 7
bbbbbbbb			
Byte 8	Byte 9	Byte 10	Byte 11
ccccccc	ccccccc	ccccccc	ccccccc
Byte 12	Byte 13	Byte 14	Byte 15
ccccccc	ccccccc	acacaca	cccccc

b) Compound type 's2_t', size 8 bytes.

Byte 0	Byte 1	Byte 2	Byte 3
ffffffff	ffffffff	ffffffff	ffffffff
Byte 4	Byte 5	Byte 6	Byte 7
9999999	<u>aaaaaaaa</u>	<u>aaaaaaaa</u>	9999999

c) Array type 's3_tid', 40 integers, total size 40 bytes.

Byte 0	Byte 1	Byte 2	Byte 3
0000000	00000000	00000000	00000000
Byte 4	Byte 5	Byte 6	Byte 7
0000000	00000000	00000000	00000001

...

Byte 36	Byte 37	Byte 38	Byte 39
00000000	00000000	00000000	00001010

d) String type 's4_tid', size 25 bytes.

Byte 0	Byte 1	Byte 2	Byte 3
'a'	'b'	'C'	'd'

•••

Byte 24	Byte 25	Byte 26	Byte 27
00000000			

Figure 49




Figure 50




Figure 51

7.3 Analyzing and Navigating a Compound Datatype

A complicated compound datatype can be analyzed piece by piece, to discover the exact storage layout. In the example above, the outer datatype is analyzed to discover that it is a compound datatype with 4 members. Each member is analyzed in turn to construct a complete map of the storage layout.

Figure 52 shows an example of code that partially analyses a nested compound datatype. The name and overall offset and size of the component datatype is discovered, and then it's type is analyzed, depending on the datatype class. Through this method, the complete storage layout can be discovered.

```
s1_tid = H5Dget_type(dataset);
if (H5Tget_class(s1_tid) == H5T_COMPOUND) {
    printf("COMPOUND DATATYPE {\n");
    sz = H5Tget_size(s1_tid);
    nmemb = H5Tget_nmembers(s1_tid);
    printf(" %d bytes\n",sz);
    printf(" %d members\n",nmemb);
    for (i = 0; i < nmemb; i++) {
            s2_tid = H5Tget_member_type(s1_tid,i);
            if (H5Tget_class(s2_tid) == H5T_COMPOUND) {
                    /* recursively analyze the nested type. */
            } else if (H5Tget_class(s2_tid) == H5T_ARRAY) {
                    sz2 = H5Tget_size(s2_tid);
                    printf(" s: NESTED ARRAY DATATYPE offset <math>d size d \{n", m"\}
              H5Tget_member_name(s1_tid,i),
              H5Tget_member_offset(s1_tid,i),
              H5Tget_array_dims(s2_tid,dim,NULL);
               s3_tid = H5Tget_super(s2_tid);
              /* Etc., analyze the base type of the array */
            } else {
              /* analyze a simple type */
              printf("
                         %s: type code %d offset %d size %d\n",
                            H5Tget_member_name(s1_tid,i),
                            H5Tget_class(s2_tid),
                            H5Tget_member_offset(s1_tid,i),
                            H5Tget_size(s2_tid));
            }
      /* and so on . */
```

Figure 52

8. Life Cycle of the Datatype Object

Applications programs access HDF5 datatypes through handles, which are obtained by creating a new datatype, or copying or opening an existing datatype. The handle can be used until it is closed, or the program exits (Figure 53a,b). By default, a datatype object is *transient*, and disappears when it is closed.

When a dataset or attribute is created (H5Dcreate or H5Acreate), its datatype object is stored in the HDF5 file as part of the HDF5 object (the dataset or attribute) (Figure 53c). Once an object created, its datatype cannot be changed or deleted. The datatype can be accessed by calling H5Dget_type, H5Aget_type, H5Tget_super, or H5Tget_member_type (Figure 53d). These calls return a handle to a *transient* copy of the datatype of the dataset or attribute unless the datatype is a named datatype as explained below.

Note that when an object is created, the stored datatype is a copy of the transient datatype. If two objects are created with the same datatype, the information is stored in each object, with the same effect as if two different datatypes were created and used.

A transient datatype can be stored (H5Tcommit) in the HDF5 file as an independent, named object, called a named datatype (Figure 53e). Subsequently, when a named datatype is opened with H5Topen (Figure 53f), or is obtained with H5Tget_type or similar call (Figure 53k), the return is a handle to a transient copy of the stored datatype. The handle can be used in the same way as other datatype handles, except the named datatype cannot be modified. When a named datatype is copied with H5Tcopy, the return is a new, modifiable, transient datatype object (Figure 53f).

When an object is created using a named datatype (H5Dcreate, H5Acreate), the stored datatype is used without copying it to the object (Figure 53j). In this case, if multiple objects are created using the same named datatype, they all share the exact same datatype object. This saves space and makes clear that the datatype is shared. Note that a named datatype can be shared by objects within the same HDF5 file, but not by objects in other files.

A named datatype can be deleted from the file by calling H5Gunlink (Figure 53i). If one or more objects are still using the datatype, the named datatype cannot be accessed with H5Topen, but will not be removed from the file until it is no longer used. The H5Tget_type and similar calls will return a transient copy of the datatype.




Figure 53

Transient datatypes are initially *modifiable*, its properties can be changed. Note that when a datatype is copied or when it is written to the file (when an object is created) or the datatype is used to create a composite datatype, a copy of the current state of the datatype is used. If the datatype is then modified, the changes have no effect on datasets, attributes, or datatypes that have already been created.

A transient datatype can be made *read-only* (H5Tlock), after which it can no longer be changed. Note that the datatype is still transient, and otherwise does not change. A datatype that is *immutable* is *read-only* but cannot be closed except when the entire library is closed. The predefined types such as H5T_NATIVE_INT are *immutable transient* types.




Figure 54

To create two or more datasets that share a common datatype, one first commits the datatype, giving it a name, then uses that datatype to create the datasets.

```
hid_t t1 = ...some transient type...;
H5Tcommit (file, "shared_type", t1);
hid_t dset1 = H5Dcreate (file, "dset1", t1, space, H5P_DEFAULT);
hid_t dset2 = H5Dcreate (file, "dset2", t1, space, H5P_DEFAULT);
hid_t dset1 = H5Dopen (file, "dset1");
hid_t t2 = H5Dget_type (dset1);
hid_t dset3 = H5Dcreate (file, "dset3", t2, space, H5P_DEFAULT);
hid_t dset4 = H5Dcreate (file, "dset4", t2, space, H5P_DEFAULT);
```

Figure 55

Table 24

Function

Description

hid_t H5Topen (hid_t location, const char *name) A named datatype can be opened by calling this function, which returns a datatype identifier. The identifier should eventually be released by calling H5Tclose() to release resources. The named datatype returned by this function is read-only or a negative value is returned for failure. The location is either a file or group identifier.

herr_t H5Tcommit (hid_t location, A transient datatype (not immutable) can be const char *name, hid_t type) committed to a file and turned into a named

A transient datatype (not immutable) can be committed to a file and turned into a named datatype by calling this function. The location is either a file or group identifier and when combined with name refers to a new named datatype.

htri_t H5Tcommitted (hid_t type)

A type can be queried to determine if it is a named type or a transient type. If this function returns a positive value then the type is named (that is, it has been committed perhaps by some other application). Datasets which return committed datatypes with H5Dget_type() are able to share the datatype with other datasets in the same file.

9. Data Transfer: Datatype Conversion and Selection

When data is transferred (write or read) the storage layout of the data elements may be different. For example, an integer might be stored on disk in big endian byte order, and read into memory with little endian byte order. In this case, each data element will be transformed by the HDF5 library during the data transfer.

The conversion of data elements is controlled by specifying datatype of the source and specifying the intended datatype of the destination. The storage format on disk is the datatype specified when the dataset is create. The datatype of memory must be specified in the library call.

In order to be convertible, the datatype of the source and destination must have the same datatype class. Thus, integers can be converted to other integers, and floats to other floats, but integers cannot (yet) be converted to floats. For each atomic datatype class, the possible conversions are defined.

Basically, any datatype can be converted to another datatype of the same datatype class. The HDF5 library automatically converts all properties. If the destination is too small to hold the source value then an overflow or underflow exception occurs. If a handler is defined, with <code>H5Tset_overflow()</code>, it will be called. Otherwise, a default action will be performed. Table 25 summarizes the default action.

Table 25

Datatype Class	Possible Exceptions	Default Action

Integer size, offset, pad

Float size, offset, pad, ebits, etc.

String size Truncates, zero terminate if required.

Enumeration No field All Bits set

When data is transferred (write or read) the format of the data elements may be transformed between the source and the destination, according to the datatypes of the source and destination.

In order to be convertible, the datatype of the source and destination must have the same datatype class.


For example, when reading data from a dataset, the source datatype is the datatype set when the dataset was created, and the destination datatype is the description of the storage layout in memory, which must be specified in the *H5Dread* call. Figure 56 shows an example of reading a dataset of 32-bit integers. Figure 57 shows the data transformation that is performed.

Figure 56

Source Datatype: H5T_STD_BE32

Byte 0	Byte 1	Byte 2	Byte 3
aaaaaaaa	bbbbbbbb	ccccccc	dddddddd
Byte 4	Byte 5	Byte 6	Byte 7
WWWWWWW	xxxxxxx	УУУУУУУУ	ZZZZZZZ

. . . .



Destination Datatype: H5T_STD_LE32

Byte 0	Byte 1	Byte 2	Byte 3
bbbbbbbb	aaaaaaaa	dddddddd	ccccccc
Byte 4	Byte 5	Byte 6	Byte 7
xxxxxxx	WWWWWWW	ZZZZZZZ	УУУУУУУУ

. . . .

Figure 57

One thing to note in Figure 56 is the use of the predefined native datatype, H5T_NATIVE_INT. Recall that in this example, the data was stored as a 4-bytes in big endian order. The application wants to read this data into an array of integers in memory. Depending on the system, the storage layout of memory might be either big or little endian, so the data may need to be transformed on some platforms and not on others. The H5T_NATIVE_INT type is set by the HDF5 library to be the correct type to describe the storage layout of the memory on the system. Thus, the code in Figure 56 will work correctly on any platform, performing a transformation when needed.

There are predefined native types for most atomic datatypes, which can be combined in composite datatypes. In general, the predefined native datatypes should always be used for data stored in memory.

Predefined native datatypes describe the storage properties of memory.

For composite datatypes, the component atomic datatypes will be converted. For a variable length datatype, the source and destination must have compatible base datatypes. For a fixed-size string datatype, the length and padding of the strings will be converted. Variable length strings are converted as variable length datatypes.

For an array datatype, the source and destination must have the same rank and dimensions, and the base datatype must be compatible. For example an array datatype of 4×3 32-bit big endian integers can be transferred to an array datatype of 4×3 little endian integers, but not to a 3×4 array.

For an enumeration datatype, data elements are converted by matching the symbol names of the source and destination Datatype. Figure 58 shows an example of how two enumerations with the same names and different values would be converted. The value '2' in the source dataset would be converted to '0x0004' in the destination.

If the source data stream contains values which are not in the domain of the conversion map then an overflow exception is raised within the library.




Figure 58

For compound datatypes, each field of the source and destination datatype is converted according to its type. The name and order of the fields must be the same in the source and the destination but the source and destination may have different alignments of the fields, and only some of the fields might be transferred.

Figure 59 shows the compound datatypes shows sample code to create a compound datatype with the fields aligned on word boundaries (s1_tid) and with the fields packed (s2_tid). The former is suitable as a description of the storage layout in memory, the latter would give a more compact store on disk. These types can be used for transferring data, with s2_tid used to create the dataset, and s1_tid used as the memory datatype.

```
typedef struct s1_t {
   int a;
   char b;
   double c;
} s1_t;

s1_tid = H5Tcreate (H5T_COMPOUND, sizeof(s1_t));
H5Tinsert(s1_tid, "a_name", H0FFSET(s1_t, a), H5T_NATIVE_INT);
H5Tinsert(s1_tid, "b_name", H0FFSET(s1_t, b), H5T_NATIVE_CHAR);
H5Tinsert(s1_tid, "c_name", H0FFSET(s1_t, c), H5T_NATIVE_DOUBLE);

s2_tid = H5Tcopy(s1_tid);
H5Tpack(s2_tid);
```

Figure 59

When the data is transferred, the fields within each data element will be aligned according to the datatype specification. Figure 60 shows how one data element would be aligned in memory and on disk. Note that the size and byte order of the elements might also be converted during the transfer.

It is also possible to transfer some of the fields of a compound datatypes. Continuing the example, from Figure 59, Figure 61 shows a compound datatype that selects the first and third fields of the sl_tid. The second datatype can be used as the memory datatype, in which case data is read from or written to these two fields, while skipping the middle field. Figure 62 shows the data for two data elements.




Figure 60

```
typedef struct s1_t {
   int
         a;
   char b;
   double c;
} s1_t;
typedef struct s2_t {    /* two fields from s1_t */
   int
   double c;
} s2_t;
      s1_tid = H5Tcreate (H5T_COMPOUND, sizeof(s1_t));
H5Tinsert(s1_tid, "a_name", H0FFSET(s1_t, a), H5T_NATIVE_INT);
H5Tinsert(s1_tid, "b_name", HOFFSET(s1_t, b), H5T_NATIVE_CHAR);
H5Tinsert(s1_tid, "c_name", H0FFSET(s1_t, c), H5T_NATIVE_DOUBLE);
s2_tid = H5Tcreate (H5T_COMPOUND, sizeof(s2_t));
H5Tinsert(s1_tid, "a_name", HOFFSET(s2_t, a), H5T_NATIVE_INT);
H5Tinsert(s1_tid, "c_name", HOFFSET(s2_t, c), H5T_NATIVE_DOUBLE);
```

Figure 61




Figure 62

10. Text Descriptions of Datatypes: Conversion to and from

HDF5 provides a means for generating a portable and human-readable text description of a datatype and for generating a datatype from such a text description. This capability is particularly useful for creating complex datatypes in a single step, for creating a text description of a datatype for debugging purposes, and for creating a portable datatype definition that can then be used to recreate the datatype on many platforms or in other applications.

These tasks are handled by two functions provided in the HDF5 high-level library (H5HL):

```
H5LTtext_to_dtype Creates an HDF5 datatype in a single step.

H5LTdtype_to_text Translates an HDF5 datatype into a text description.
```

Note that this functionality requires that the HDF5 High-Level Library (H5LT) be installed. See < < Quick Start > >.

While H5LTtext_to_dtype can be used to generate any sort of datatype, it is particularly useful for complex datatypes.

H5LTdtype_to_text is most likely to be used in two sorts of situations: when a datatype must be closely examined for debugging purpose or to create a portable text description of the datatype that can then be used to recreate the datatype on other platforms or in other applications.

These two functions work for all valid HDF5 datatypes except time, bitfield, and reference datatypes.

The currently supported text format used by H5LTtext_to_dtype and H5LTdtype_to_text is the data description language (DDL) and conforms to the *HDF5 DDL*. The portion of the *HDF5 DDL* that defines HDF5 datatypes appears below.

```
<datatype> ::= <atomic_type> | <compound_type> | <array_type> |
               <variable_length_type>
<atomic_type> ::= <integer> | <float> | <time>
                                                     <string>
                <bitfield> | <opaque> | <reference> |
                                                     <enum>
<integer> ::= H5T_STD_I8BE
                              H5T_STD_I8LE
             | H5T_STD_I64LE
             H5T_STD_I64BE
                            | H5T_STD_U8LE
| H5T_STD_U16LE
             H5T STD U8BE
             H5T_STD_U16BE
             H5T_STD_U32BE | H5T_STD_U32LE
                             H5T_STD_U64LE
             H5T_STD_U64BE
             H5T NATIVE CHAR | H5T NATIVE UCHAR
             H5T_NATIVE_SHORT | H5T_NATIVE_USHORT
             H5T NATIVE INT | H5T NATIVE UINT
             H5T_NATIVE_LONG | H5T_NATIVE_ULONG
             H5T_NATIVE_LLONG | H5T_NATIVE_ULLONG
<float> ::= H5T_IEEE_F32BE
                             H5T_IEEE_F32LE
           H5T_IEEE_F64BE
                            H5T_IEEE_F64LE
           H5T_NATIVE_FLOAT | H5T_NATIVE_DOUBLE
           H5T NATIVE LDOUBLE
<time> ::= TBD
```

```
<string> ::= H5T_STRING { STRSIZE <strsize> ;
 STRPAD <strpad> ;
 CSET <cset> ;
 CTYPE <ctype> ;}
<strsize> ::= <int_value> | H5T_VARIABLE
<strpad> ::= H5T_STR_NULLTERM | H5T_STR_NULLPAD | H5T_STR_SPACEPAD
<cset> ::= H5T_CSET_ASCII | H5T_CSET_UTF8
<ctype> ::= H5T_C_S1 | H5T_FORTRAN_S1
<br/>ditfield> ::= TBD
<opaque> ::= H5T_OPAQUE { OPQ_SIZE <opq_size>;
                           OPQ_TAG < opq_tag>; }
opq_size ::= <int_value>
opq_tag ::= <string>
<reference> ::= Not supported
<compound_type> ::= H5T_COMPOUND { <member_type_def>+ }
<member_type_def> ::= <datatype> <field_name> <offset>opt ;
<field_name> ::= <identifier>
<offset> ::= : <int_value>
<variable_length_type> ::= H5T_VLEN { <datatype> }
<array_type> ::= H5T_ARRAY { <dim_sizes> <datatype> }
<dim_sizes> ::= [<dimsize>] | [<dimsize>] <dim_sizes>
<dimsize> ::= <int_value>
<enum> ::= H5T_ENUM { <enum_base_type>; <enum_def>+ }
<enum_base_type> ::= <integer>
// Currently enums can only hold integer type data, but they may be
//expanded in the future to hold any datatype
<enum_def> ::= <enum_symbol> <enum_val>;
<enum_symbol> ::= <identifier>
<enum_val> ::= <int_value>
```

Figure 63: The definition of HDF5 datatypes from the HDF5 DDL

The definitions of opaque and compound datatype above are revised for HDF5 Release 1.8. In Release 1.6.5. and earlier, they were were defined as follows:

```
<opaque> ::= H5T_OPAQUE { <identifier> }
<compound_type> ::= H5T_COMPOUND { <member_type_def>+ }
<member_type_def> ::= <datatype> <field_name> ;
<field_name> ::= <identifier>
```

Figure 64: Definitions of the opaque and compound datatypes from the Release 1.6.n series

Examples

The code sample in the following figure illustrates the use of H5LTtext_to_dtype to generate a variable-length string datatype.

```
CSET H5T_CSET_ASCII;
CTYPE H5T_C_S1;
}", H5LT_DDL))<0)
goto out;</pre>
```

Figure 65: Creating a variable-length string datatype from a text description ple in the following figure illustrates the use of H5LTtext to dtype to generate a complex

The code sample in the following figure illustrates the use of H5LTtext_to_dtype to generate a complex array datatype.

Figure 66: Creating a complex array datatype from a text description

Chapter 7 HDF5 Dataspaces and Partial I/O

1. Introduction

The HDF5 *dataspace* is a required component of an HDF5 dataset or attribute definition. The dataspace defines the size and shape of the dataset or attribute raw data, i.e., the number of dimensions and the size of each dimension of the multideminesional array in which the raw data is represented. The dataspace must be defined when the dataset or attribute is created.

The *dataspace* is also used during dataset I/O operations, defining the elements of the dataset that participate in the I/O operation.

This chapter explains the *dataspace* object and its use in dataset and attribute creation and data transfer. It also describes selection operations on a dataspace used to implement subsetting, subsampling, and scatter-gather access to datasets.

The rest of this chapter is structured as follows:

- ♦ Section 2, "Dataspace Functions," provides a categorized list of dataspace functions, also known as the H5S APIs.
- ♦ Section 3,"Definition of Dataspace Objects and the Dataspace Programming Model," describes dataspace objects and the programming model, including the creation and use of dataspaces.
- ◆ Section 4, "Dataspaces and Data Transfer," describes the use of dataspaces in data transfer.
- ♦ Section 5, "Dataspace Selection Operations and Data Transfer," describes selection operations on dataspaces and their usage in data transfer.
- ♦ Section 6, "References to Dataset Regions," briefly discusses references to dataset regions.
- ◆ Section 7, "Sample Programs," contains the full programs from which several of the code samples in this chapter were derived.

2. Dataspace (H5S) Function Summaries

This section provides a reference list of dataspace functions, the H5S APIs, with brief descriptions. The functions are presented in several functional catagories:

- ♦ dataspace management functions
- ♦ dataspace query functions
- ♦ dataspace selection functions
 - ♦ hyperslab selections
 - ♦ point selections

Sections 3 through 6 will provide examples and explanations of how to use these functions.

Dataspace management functions

C Function F90 Function	Purpose
H5Screate h5screate_f	Creates a new dataspace of a specified type.
H5Scopy h5scopy_f	Creates an exact copy of a dataspace.
H5Sclose h5sclose_f	Releases and terminates access to a dataspace.
H5Screate_simple h5screate_simple_f	Creates a new simple dataspace and opens it for access.
H5Sis_simple h5sis_simple_f	Determines whether a dataspace is a simple dataspace.
H5Sextent_copy h5sextent_copy_f	Copies the extent of a dataspace.
H5Sset_extent_simple h5sset_extent_simple_f	Sets or resets the size of an existing dataspace.
H5Sset_extent_none h5sset_extent_none_f	Removes the extent from a dataspace.

Dataspace query functions

C Function F90 Function	Purpose
<pre>H5Sget_simple_extent_dims h5sget_simple_extent_dims_f</pre>	Retrieves dataspace dimension size and maximum size.
<pre>H5Sget_simple_extent_ndims h5sget_simple_extent_ndims_f</pre>	Determines the dimensionality of a dataspace.
<pre>H5Sget_simple_extent_npoints h5sget_simple_extent_npoints_f</pre>	Determines the number of elements in a dataspace.
H5Sget_simple_extent_type h5sget_simple_extent_type_f	Determine the current class of a dataspace.

Dataspace selection functions: Hyperslabs

C Function F90 Function	Purpose
H5Soffset_simple h5soffset_simple_f	Sets the offset of a simple dataspace.
H5Sget_select_type h5sget_select_type_f	Determines the type of the dataspace selection.
H5Sget_select_hyper_nblocks h5sget_select_hyper_nblocks_f	Get number of hyperslab blocks.
H5Sget_select_hyper_blocklist h5sget_select_hyper_blocklist_f	Gets the list of hyperslab blocks currently selected.
H5Sget_select_bounds h5sget_select_bounds_f	Gets the bounding box containing the current selection.
H5Sselect_all h5sselect_all_f	Selects the entire dataspace.
H5Sselect_none h5sselect_none_f	Resets the selection region to include no elements.
H5Sselect_valid h5sselect_valid_f	Verifies that the selection is within the extent of the dataspace.
H5Sselect_hyperslab h5sselect_hyperslab_f	Selects a hyperslab region to add to the current selected region.

Dataspace selection functions: Points

C Function F90 Function	Purpose
H5Sget_select_npoints h5sget_select_npoints_f	Determines the number of elements in a dataspace selection.
<pre>H5Sget_select_elem_npoints h5sget_select_elem_npoints_f</pre>	Gets the number of element points in the current selection.
H5Sget_select_elem_pointlist h5sget_select_elem_pointlist_f	Gets the list of element points currently selected.
H5Sselect_elements h5sselect_elements_f	Selects array elements to be included in the selection for a dataspace.

3. Definition of Dataspace Objects and the Dataspace Programming Model

This section introduces the notion of the HDF5 dataspace object and a programming model for creating and working with dataspaces.

3.1 Dataspace Objects

An HDF5 dataspace is a required component of an HDF5 dataset or attribute. A dataspace defines the size and the shape of a dataset's or an attribute's raw data. Currently, HDF5 supports the following types of the dataspaces:

- ♦ scalar dataspaces
- ♦ simple dataspaces
- ♦ null dataspaces

A *scalar dataspace*, H5S_SCALAR, represents just one element, a scalar. Note that the datatype of this one element may be very complex, e.g., a compound structure with members being of any allowed HDF5 datatype, including multidimensional arrays, strings, and nested compound structures. By convention, the rank of a scalar dataspace is always 0 (zero); think of it geometrically as a single, dimensionless point, though that point may be complex.

A *simple dataspace*, H5S_SIMPLE, is a multidimensional array of elements. The dimensionality of the dataspace (or the rank of the array) is fixed and is defined at creation time. The size of each dimension can grow during the life time of the dataspace from the *current size* up to the *maximum size*. Both the current size and the maximum size are specified at creation time. The sizes of dimensions at any particular time in the life of a dataspace are called the *current dimensions*, or the *dataspace extent*. They can be queried along with the maximum sizes.

A *null dataspace*, H5S_NULL, contains no data elements. Note that no selections can be applied to a null dataset as there is nothing to select.

As shown in the UML diagram in Figure 1, an HDF5 simple dataspace object has three attributes: the rank or number of dimensions; the current sizes, expressed as an array of length rank with each element of the array denoting the current size of the corresponding dimension; and the maximum sizes, expressed as an array of length rank with each element of the array denoting the maximum size of the corresponding dimension.

```
Simple dataspace
rank:int
current_size:hsize_t[rank]
maximum_size:hsize_t[rank]
```

Figure 1: A simple dataspace is defined by its rank, the current size of each dimension, and the maximum size of each dimension.

The size of a current dimension cannot be greater than the maximum size, which can be unlimited, specified as H5S_UNLIMITED. Note that while the HDF5 file format and library impose no maximum size on an unlimited dimension, practically speaking its size will always be limited to the biggest integer available on the particular system being used.

Dataspace rank is restricted to 32, the standard limit in C on the rank of an array, in the current implementation of the HDF5 Library. The HDF5 file format, on the other hand, allows any rank up to the maximum integer value on the system, so the library restriction can be raised in the future if higher dimensionality is required.

Note that most of the time Fortran applications calling HDF5 will work with dataspaces of rank less than or equal to seven, since seven is the maximum number of dimensions in a Fortran array. But dataspace rank is not limited to seven for Fortran applications.

The current dimensions of a dataspace, also referred to as the dataspace extent, define the bounding box for dataset elements that can participate in I/O operations.

3.2 Programming Model

The programming model for creating and working with HDF5 dataspaces can be summarized as follows:

- 1. Create a dataspace.
- 2. Use the dataspace to create a dataset in the file or to describe a data array in memory.
- 3. Modify the dataspace to define dataset elements that will participate in I/O operations.
- 4. Use the modified dataspace while reading/writing dataset raw data or to create a region reference.
- 5. Close the dataspace when no longer needed.

The rest of this section will address steps 1, 2, and 5 of the programming model; steps 3 and 4 will be discussed in later sections of this chapter.

Creating a dataspace

A dataspace can be created by calling the H5Screate function (h5screate_f in Fortran). Since the definition of a simple dataspace requires the specification of dimensionality (or rank) and initial and maximum dimension sizes, the HDF5 Library provides a *convenience* API, H5Screate_simple (h5screate_simple_f) to create a simple dataspace in one step.

The following examples illustrate the usage of these APIs.

Creating a scalar dataspace

A scalar dataspace is created with the H5Screate or the h5screate_f function:

In C:

```
hid_t space_id;
. . .
space_id = H5Screate(H5S_SCALAR);
```

In Fortran:

```
INTEGER(HID_T) :: space_id
. . .
CALL h5screate_f(H5S_SCALAR_F, space_id, error)
```

As mentioned above, the dataspace will contain only one element. Scalar dataspaces are used more often for describing attributes that have just one value, e.g. the attribute temperature with the value celsius is used to indicate that the dataset with this attribute stores temperature values using the celsius scale.

Creating a null dataspace

A null dataspace is created with the H5Screate or the h5screate_f function:

In C:

```
hid_t space_id;
. . .
space_id = H5Screate(H5S NULL);
```

In Fortran: (H5S_NULL not yet implemented in Fortran.)

```
INTEGER(HID_T) :: space_id
. . .
CALL h5screate_f(H5S_NULL_F, space_id, error)
```

As mentioned above, the dataspace will contain no elements.

Creating a simple dataspace

Let's assume that an application wants to store a two-dimensional array of data, A(20,100). During the life of the application, the first dimension of the array can grow up to 30; there is no restriction on the size of the second dimension. The following steps are used to declare a dataspace for the dataset in which the array data will be stored.

In C:

```
hid_t space_id;
int rank = 2;
hsize_t current_dims[2] = {20, 100};
hsize_t max_dims[2] = {30, H5S_UNLIMITED};
. . .
space_id = H5Screate(H5S_SIMPLE);
H5Sset_extent_simple(space_id,rank,current_dims,max_dims);
```

In Fortran:

```
INTEGER(HID_T) :: space_id
INTEGER :: rank = 2
INTEGER(HSIZE_T) :: current dims = /( 20, 100)/
INTEGER(HSIZE_T) :: max_dims = /(30, H5S_UNLIMITED_F)/
INTEGER error
. . .
CALL h5screate_f(H5S_SIMPLE_F, space_id, error)
CALL h5sset_extent_simple_f(space_id, rank, current_dims, max_dims, error)
```

Alternatively, the convenience APIs H5Screate_simple/h5screate_simple_f can replace the H5Screate/h5screate_f and H5Sset_extent_simple/h5sset_extent_simple_f calls.

In C:

```
space_id = H5Screate_simple(rank, current_dims, max_dims);
```

In Fortran:

```
CALL h5screate_simple_f(space_id, rank, current_dims, error, max_dims)
```

In this example (see Figure 2), a dataspace with current dimensions of 20 by 100 is created. The first dimension can be extended only up to 30. The second dimension, however, is declared unlimited; it can be extended up to the largest available integer value on the system. Recall that any dimension can be declared unlimited, and if a dataset uses a dataspace with any unlimited dimension, chunking has to be used (see the "Data Transfer" section in the "Datasets" chapter).




Figure 2: Create a simple dataspace with a 10x100 array

Maximum dimensions can be the same as current dimensions. In such a case, the sizes of dimensions cannot be changed during the life of the dataspace object. In C, NULL can be used to indicate to the H5Screate_simple and H5Sset_extent_simple functions that the maximum sizes of all dimensions are the same as the current sizes. In Fortran, the maximum size parameter is optional for h5screate_simple_f and can be omitted when the sizes are the same.

In C:

```
space_id = H5Screate_simple(rank, current_dims, NULL);
```

In Fortran:

```
CALL h5screate_f(space_id, rank, current_dims, error)
```

The created dataspace will have current and maximum dimensions of 20 and 100 correspondingly, and the sizes of those dimensions cannot be changed.

C versus Fortran Dataspaces

Dataspace dimensions are numbered from 1 to rank. HDF5 uses C storage conventions, assuming that the last listed dimension is the fastest-changing dimension and the first-listed dimension is the slowest changing. The HDF5 file format storage layout specification adheres to the C convention and the HDF5 Library adheres to the same convention when storing dataspace dimensions in the file. This affects how C programs and tools interpret data written from Fortran programs and vice versa. The example below illustrates the issue.

When a Fortran application describes a dataspace to store an array as A(20,100), it specifies the value of the first dimension to be 20 and the second to be 100. Since Fortran stores data by columns, the first-listed dimension with the value 20 is the fastest-changing dimension and the last-listed dimension with the value 100 is the slowest-changing. In order to adhere to the HDF5 storage convention, the HDF5 Fortran wrapper transposes dimensions, so the first dimension becomes the last. The dataspace dimensions stored in the file will be 100,20 instead of 20,100 in order to correctly describe the fortran data that is stored in 100 columns, each containing 20 elements.

When a Fortran application reads the data back, the HDF5 Fortran wrapper transposes the dimensions once more, returning the first dimension to be 20 and the second to be 100, describing correctly the sizes of the array that should be used to read data in the Fortran array A(20,100).

When a C application reads data back, the dimensions will come out as 100 and 20, correctly describing the size of the array to read data into, since the data was written as 100 records of 20 elements each. Therefore C tools such as h5dump and h5ls always display transposed dimensions and values for the data written by a Fortran application.

Consider the following simple example of equivalent C 3x5 and Fortran 5x3 arrays. As illustrated in Figure 3, a C applications will store a 3x5 2-dimensional array as three 5-element rows. In order to store the same data in the same order, a Fortran application must view the array as as a 5x3 array with three 5-element columns. The dataspace of this dataset, as written from Fortran, will therefore be described as 5x3 in the application but stored and described in the file according to the C convention as a 3x5 array. This ensures that C and Fortran applications will always read the data in the order in which it was written. The HDF5 Fortran interface handles this transposition automatically.

In C (from h5_write.c):

```
* 11 12 13 14 15
           * /
         dims[0] = NX;
         dims[1] = NY;
         dataspace = H5Screate_simple(RANK, dims, NULL);
In Fortran (from h5_write.f90):
         INTEGER, PARAMETER :: NX = 3
         INTEGER, PARAMETER :: NY = 5
         INTEGER(HSIZE_T), DIMENSION(2) :: dims = (/3,5/) ! Dataset dimensions
         INTEGER :: data(NX,NY)
         . . .
         ! Initialize data
           do i = 1, NX
              do j = 1, NY
                 data(i,j) = j + (i-1)*NY
              enddo
           enddo
         !
         ! Data
         !
         ! 1 2 3 4 5
         ! 6 7 8 9 10
         ! 11 12 13 14 15
         CALL h5screate_simple_f(rank, dims, dspace_id, error)
In Fortran (from h5_write_tr.f90):
         INTEGER, PARAMETER :: NX = 3
         INTEGER, PARAMETER :: NY = 5
         INTEGER(HSIZE_T), DIMENSION(2) :: dims = (/NY, NX/) ! Dataset dimensions
         !
         ! Initialize data
           do i = 1, NY
              do j = 1, NX
                 data(i,j) = i + (j-1)*NY
              enddo
           enddo
         !
         ! Data
         !
         ! 1 6 11
         ! 2 7 12
            3 8 13
         !
            4 9 14
         !
         ! 5 10 15
         CALL h5screate_simple_f(rank, dims, dspace_id, error)
```

A dataset stored by a

C program in a 3x5 array:

C prog	tain in	i a sxs	array.	
1	2	3	4	5
6	7	8	9	10
11	12	13	14	15

The same dataset stored by a

Fortran program in a 5x3 array:

	7 7 7 5 7	*****
1	6	11
2	7	12
3	8	13
4	9	14
5	10	15

The left-hand dataset above as written to an HDF5 file from C or the right-hand dataset as written from Fortran:

	nom i orum.														
Ī	1	2	3	4	5	6	7	8	9	10	11	12	13	14	15

The left-hand dataset above as written to an HDF5 file from Fortran:

1	6	11	2	7	12	3	8	13	4	9	14	5	10	15
-	0		_	,			0	10		_			10	10

Figure 3: The HDF5 Library stores arrays along the fastest-changing dimension, an approach often referred to as being "in C order." C, C++, and Java work with arrays in row-major order, i.e., the row, or the last dimension, is the fastest-changing dimension. Fortran, on the other hands, handles arrays in column-major order, making the column, or the first dimension, the fastest-changing dimension. Therefore, the C and Fortran arrays illustrated in the top portion of this figure are stored identically in an HDF5 file. This ensures that data written by any language can be meaningfully read, interpreted, and manipulated by any other.

Finding dataspace charateristics

The HDF5 Library provides several APIs designed to query the characteristics of a dataspace.

The function H5Sis_simple (h5sis_simple_f) returns information about the type of a dataspace. This function is rarely used and currently supports only simple and scalar dataspaces.

To find out the dimensionality, or rank, of a dataspace, use H5Sget_simple_extent_ndims (h5sget_simple_extent_ndims_f). H5Sget_simple_extent_dims can also be used to find out the rank. See the example below. Both functions return 0 for the value of rank the dataspace is scalar.

To query the sizes of the current and maximum dimensions, use H5Sget_simple_extent_dims (h5sget_simple_extent_dims_f).

The following example illustrates querying the rank and dimensions of a dataspace using these functions.

In C:


```
hid_t space_id;
int rank;
hsize_t *current_dims;
hsize_t *max_dims;
-------

rank=H5Sget_simple_extent_ndims(space_id);
    (or rank=H5Sget_simple_extent_dims(space_id, NULL, NULL);)
current_dims= (hsize_t)malloc(rank*sizeof(hsize_t));
max_dims=(hsize_t)malloc(rank*sizeof(hsize_t));
H5Sget_simple_extent_dims(space_id, current_dims, max_dims);
Print values here for the previous example
```

4. Dataspaces and Data Transfer

The *dataspace* object is also used to control data transfer when data is read or written. The *dataspace* of the dataset (attribute) defines the stored form of the array data, the order of the elements as explained above. When reading from the file, the *dataspace* of the dataset defines the layout of the source data, a similar description is needed for the destination storage. A *dataspace* object is used to define the organization of the data (rows, columns, etc.) in memory. If the program requests a different order for memory than the storage order, the data will be rearranged by the HDF5 Library during the H5Dread operation. Similarly, when writing data, the memory *dataspace* defines the source data, which is converted to the dataset *dataspace* when stored by the H5Dwrite call.

Figure 4a shows a simple example of a read operation in which the data is stored as a 3 by 4 array in the file (Figure 4b), but the program wants it to be a 4 by 3 array in memory. This is accomplished by setting the memory *dataspace* to describe the desired memory layout, as in Figure 4c. The HDF5 Library will transform the data to the correct arrangement during the read operation.



a) Read the data and change the Dataspace: H5Dread(..., mem space, ...);




Figure 4




Figure 5

Both the source and destination are stored as contiguous blocks of storage, with the elements in the order specified by the *dataspace*. Figure 5 shows one way the elements might be organized. In Figure 5a, the elements are stored as 3 blocks of 4 elements. The destination is an array of 12 elements in memory (Figure 5c). As the figure suggests, the transfer reads the disk blocks into a memory buffer (Figure 5b), and then writes the elements to the correct locations in memory. A similar process occurs in reverse when data is written to disk.

Data selection

In addition to rearranging data, the transfer may select the data elements from the source and destination.

Data selection is implemented by creating a *dataspace* object that describes the selected elements (within the hyper rectangle) rather than the whole array. Two *dataspace* objects with selections can be used in data transfers to read selected elements from the source and write selected elements to the destination. When data is transferred using the dataspace object, only the selected elements will be transferred.

This can be used to implement partial I/O, including:

- ♦ Sub-setting reading part of a large dataset
- ◆ Sampling reading selected elements (e.g., every second element) of a dataset
- ♦ Scatter-gather read non-contiguous elements into contiguous locations (gather) or read contiguous elements into non-contiguous locations (scatter) or both.

To use selections, the following steps are followed:

- 1. get or define the dataspace for the source and destination.
- 2. specify one or more selections for source and destination dataspaces.
- 3. transfer data using the dataspaces with selections

A selection is created by applying one or more selections to a dataspace. A selection may override any other selections (H5T_SELECT_SET) or may be 'Ored' with previous selections on the same dataspace (H5T_SELECT_OR). In the latter case, the resulting selection is the union of the selection and all previously selected selections. Arbitrary sets of points from a dataspace can be selected by specifying an appropriate set of selections.

Two selections are used in data transfer, so the source and destination must be compatible, as described below.

There are two forms of selection, hyperslab and point. A selection must be either a point selection or a set of hyperslab selections. Selections cannot be mixed.

Hyperslab selection

A hyperslab is a selection of elements from a hyper rectangle. An HDF5 hyperslab is a rectangular pattern defined by four arrays (Table 1). The *start* defines the origin of the hyperslab in the original dataspace. The stride is the number of elements to increment between selected elements. A stride of '1' is every element, a stride of '2' is every second element, etc. Note that there may be a different stride for each dimension of the dataspace. The default stride is 1.

The count is the number of elements in the hyperslab selection. When the stride is 1, the selection is a hyper rectangle with a corner at start and size count[0] by count[1] by . When stride is greater than one, the hyperslab bounded by start and the corners defined by stride[n] * count[n].

Table 1

Parameter	Description
start	Starting location for the hyperslab.
stride	The number of elements to separate each element or block to be selected.
count	The number of elements or blocks to select along each dimension.
block	The size of the block selected from the dataspace.

The *block* is a count on the number of repetitions of the hyperslab. The default block size is '1', which is one hyperslab. A block of 2 would be two hyperslabs in that dimension, with the second starting at start[n]+(count[n] * stride[n]) + 1.

A hyperslab can be used to access a sub-set of a large dataset. Figure 6 shows an example of a hyperslab that reads a rectangle from the middle of a larger two dimensional array. The destination is the same shape as the source.




Figure 6

Hyperslabs can be combined to select complex regions of the source and destination. Figure 7 shows an example of a transfer from one non-rectangular region into another non-rectangular region. The source is defined as the union of two hyperslabs, and the destination is the union of three hyperslabs.




Figure 7

Hyperslabs may also be used to collect or scatter data from regular patterns. Figure 8 shows an example where the source is a repeating pattern of blocks, and the destination is a single, one dimensional array.




Figure 8

Select points

The second type of selection is an array of points, i.e., coordinates. Essentially, this selection is a list of all the points to include. Figure 9 shows an example of a transfer of seven elements from a two dimensional dataspace to a three dimensional dataspace using a point selection to specify the points.




Figure 9

Rules for Defining Selections

A selection must have the same number of dimensions (rank) as the dataspace it is applied to, although it may select from only a small region, e.g., a plane from a 3D dataspace. Selections do not affect the extent of the *dataspace*, the selection may be larger than the *dataspace*. The boundaries of selections are reconciled with the extent at the time of the data transfer.

Data Transfer with Selections

A data transfer (read or write) with selections is the same as any read or write, except the source and destination *dataspace* have compatible selections.

During the data transfer, the following steps are executed by the library.

- 1. The source and destination *dataspaces* are checked to assure that the selections are compatible.
 - 1. Each selection must be within the current extent of the *dataspace*. A selection may be defined to extend outside the current extent of the *dataspace*, but the *dataspace* cannot be accessed if the selection is not valid at the time of the access.
 - 2. The total number of points selected in the source and destination must be the same. Note that the dimensionality of the source and destination can be different (e.g., the source could be 2D, the destination 1D or 3D), and the shape can be different, but the number of elements selected must be the same.
- 2. The data is transferred, element by element.

Selections have an iteration order for the points selected, which can be any permutation of the dimensions involved (defaulting to 'C' array order) or a specific order for the selected points, for selections composed of single array elements with H5Sselect_elements.

The elements of the selections are transferred in row-major, or C order. That is, it is assumed that the first dimension varies slowest, the second next slowest, and so forth. For hyperslab selections, the order can be any permutation of the dimensions involved (defaulting to 'C' array order). When multiple hyperslabs are combined, the hyperslabs are coalesced into contiguous reads and writes

In the case of point selections, the points are read and written in the order specified.

Programming Model

Selecting hyperslabs

Suppose we want to read a 3x4 hyperslab from a dataset in a file beginning at the element <1,2> in the dataset, and read it into a 7x7x3 array in memory (Figure 10). In order to do this, we must create a dataspace that describes the overall rank and dimensions of the dataset in the file, as well as the position and size of the hyperslab that we are extracting from that dataset.




Figure 10

The code in Figure 11 illustrates the selection of the hyperslab in the file dataspace. Figure 12 shows de definition of the destination dataspace in memory. Since the in-memory dataspace has three dimensions, the hyperslab is an array with three dimensions, with the last dimension being 1: <3,4,1>. Figure 13 shows the read using the source and destination *dataspaces* with selections.

Figure 11


```
* Define memory dataspace.
dimsm[0] = 7;
dimsm[1] = 7;
dimsm[2] = 3;
memspace = H5Screate_simple(3,dimsm,NULL);
* Define memory hyperslab.
offset_out[0] = 3;
offset_out[1] = 0;
offset_out[2] = 0;
count_out[0] = 3;
count_out[1] = 4;
count_out[2] = 1;
status = H5Sselect_hyperslab(memspace, H5S_SELECT_SET, offset_out, NULL,
     count_out, NULL);
                                    Figure 12
    ret = H5Dread(dataset, H5T_NATIVE_INT, memspace, dataspace, H5P_DEFAULT,
          data);
```

Figure 13

Example with strides and blocks.

Consider an 8x12 dataspace, in which we want to write into eight 3x2 blocks from a source dataspace in memory that is a 50-element one dimensional array called (Figure 14).

a) The source is a 1D array with 50 elements



b) The destination on disk is a 2D array with 48 selected elements

Figure 14

Figure 15 shows example code to write 48 elements from the 1D array to the file dataset, starting with the second element in vector. The destination hyperslab has the following parameters: start=(0,1), stride=(4,3), count=(2,4), block=(3,2). The source has the parameters: start=(1), stride=(1), count=(48), block=(1). After these operations, the file dataspace will have the values shown in Figure 14. Notice that the values are inserted in the file dataset in row-major order.

```
/* Select hyperslab for the dataset in the file, using 3x2 blocks, (4,3) stride
 * (2,4) count starting at the position (0,1).
start[0] = 0; start[1] = 1;
stride[0] = 4; stride[1] = 3;
count[0] = 2; count[1] = 4;
block[0] = 3; block[1] = 2;
ret = H5Sselect_hyperslab(fid, H5S_SELECT_SET, start, stride, count, block);
* Create dataspace for the first dataset.
mid1 = H5Screate_simple(MSPACE1_RANK, dim1, NULL);
* Select hyperslab.
 * We will use 48 elements of the vector buffer starting at the second element.
 * Selected elements are 1 2 3 . . . 48
 * /
start[0] = 1;
stride[0] = 1;
count[0] = 48;
block[0] = 1;
ret = H5Sselect_hyperslab(mid1, H5S_SELECT_SET, start, stride, count, block);
 * Write selection from the vector buffer to the dataset in the file.
ret = H5Dwrite(dataset, H5T_NATIVE_INT, midd1, fid, H5P_DEFAULT, vector)
                                    Figure 15
```

Selecting a union of hyperslabs




Figure 16

The HDF5 Library allows the user to select a union of hyperslabs and write or read the selection into another selection. The shapes of the two selections may differ, but the number of elements must be equal.

Figure 16 shows a transfer of a selection that is two overlapping hyperslabs from the dataset into a union of hyperslabs in the memory dataset. Note that the destination dataset has a different shape from the source dataset. Similarly, the selection in the memory dataset could have a different shape than the selected union of hyperslabs in the original file. For simplicity, the selection is that same shape at the destination.

To implement this transfer, it is necessary to:

- 1. get the source dataspace
- 2. define one hyperslab selection for the source.
- 3. define a second hyperslab selection, unioned with the first.
- 4. get the destination dataspace

- 5. define one hyperslab selection for the destination
- 6. define a second hyperslab seletion, unioned with the first.
- 7. execute the data transfer (H5Dread or H5Dwrite) using the source and destination dataspaces.

Figure 17 shows example code to create the selections for the source dataspace (the file). The first hyperslab is size 3x4 and the left upper corner at the position (1,2). The hyperslab is a simple rectangle, so the stride and block are 1. The second hyperslab is 6x5 at the position (2,4). The second selection is a union with the first hyperslab (H5S_SELECT_OR).

Figure 18 shows example code to create the selection for the destination in memory. The steps are similar. In this example, the hyperslabs are the same shape, but located in different positions in the dataspace. The first hyperslab is 3x4 and starts at (0,0), and the second is 6x5 and starts at (1,2).

Finally the H5Dread call transfers the selected data from the file dataspace to the selection in memory.

In this example, the source and destination selections are two overlapping rectangles. In general, any number of rectangles can be OR'ed, and they do not have to be contiguous. The order of the selections does not matter, but the first should use H5S_SELECT_SET, subsequent selections are unioned using H5S_SELECT_OR.

It is important to emphasize that the source and destination do not have to be the same shape (or number of rectangles). As long as the two selections have the same number of elements, the data can be transferred.

```
* Create memory dataspace.
     * /
    mid = H5Screate_simple(MSPACE_RANK, mdim, NULL);
     * Select two hyperslabs in memory. Hyperslabs has the same
     * size and shape as the selected hyperslabs for the file dataspace.
     * /
    start[0] = 0; start[1] = 0;
    block[0] = 1; block[1] = 1;
    stride[0] = 1; stride[1] = 1;
    count[0] = 3; count[1] = 4;
    ret = H5Sselect_hyperslab(mid, H5S_SELECT_SET, start, stride, count, block);
    start[0] = 1; start[1] = 2;
    block[0] = 1; block[1] = 1;
    stride[0] = 1; stride[1] = 1;
    count[0] = 6; count[1] = 5;
    ret = H5Sselect_hyperslab(mid, H5S_SELECT_OR, start, stride, count, block);
ret = H5Dread(dataset, H5T_NATIVE_INT, mid, fid, H5P_DEFAULT, matrix_out);
                                       Figure 18
```

Selecting a list of independent points

It is also possible to specify a list of elements to read or write using the function H5Sselect_elements. The procedure is similar to hyperslab selections.

- 1. get the source dataspace
- 2. set the selected points
- 3. get the destination dataspace
- 4. set the selected points
- 5. transfer the data using the source and destination dataspaces

Figure 19 shows an example where four values are to be written to four separate points in a two dimensional dataspace. The source dataspace is a one dimensional array with the values 53, 59, 61, 67. The destination dataspace is an 8x12 array. The elements are to be written to the points (0,0), (3,3), (3,5), and (5,6). In this example, the source does not require a selection. Figure 20 shows example code to implement this transfer.

A point selection lists the exact points to be transferred and the order they will be transferred. The source and destination are required to have the same number of elements. A point selection can be used with a hyperslab (e.g., the source could be a point selection and the destination a hyperslab, or vice versa), so long as the number of elements selected are the same.




Figure 19

Combinations of selections

Selections are a very flexible mechanism for reorganizing data during a data transfer. With different combinations of *dataspaces* and selections, it is possible to implement many kinds of data transfers, including sub-setting, sampling, and reorganizing the data. Table 2 gives some example combinations of source and destination, and the operations they implement.

Table 2

Source	Destination	Operation
all	all	Copy whole array
all	All (different shape)	Copy and reorganize array
hyperslab	all	Sub-set
hyperslab	Hyperslab (same shape)	selection
hyperslab	Hyperslab (different shape)	Select and rearrange
Hyperslab with stride or block	All or hyperslab with stride 1	Sub-sample, scatter
hyperslab	points	scatter
points	Hyperslab or all	gather
points	Points (same)	selection
points	Points (different)	Reorder points

5. Dataspace Selection Operations and Data Transfer

(With apologies to the reader, this section has yet to be written. -- The Editor)

6. References to Dataset Regions

Another use of selections is to store a reference to a region of a dataset. An HDF5 object reference object is a pointer to an object (dataset, group, or named datatype) in the file. A selection can be used to create a pointer to a set of selected elements of a *dataset*, called a region reference. The selection can be either a point selection or a hyperslab selection. A more complete description of region references can be found in the chapter "HDF5 Datatypes."

A region reference is an object maintained by the HDF5 Library. The region reference can be stored in a dataset or attribute, and then read. The dataset or attribute is defined to have the special datatype, H5T_STD_REF_DSETREG.

To discover the elements and/or read the data, the region reference can be deferenced. The H5Rdefrerence call returns a handle for the *dataset*, and then the selected dataspace can be retrieved with H5Rget_select call. The selected *dataspace* can be used to read the selected data elements.

Example Uses for Region References

Region references are used to implement stored pointers to data within a dataset. For example, features in a large dataset might be indexed by a table (Figure 21). This table could be stored as an HDF5 dataset with a compound datatype, for example with a field for the name of the feature and a region reference to point to the feature in the dataset (Figure 22).





Figure 21

a) Dataset 1: data



b) Dataset 2: Compound Data: array of {String, Region Reference}

"Washington, DC"	<region 1="" ref=""></region>	
"Baltimore, MD"	<region 2="" ref=""></region>	
"Storm"	<region 3="" ref=""></region>	

Figure 22

Creating References to Regions

To create a region reference:

- 1. Create or open the dataset that contains the region.
- 2. Get the dataspace for the dataset.
- 3. Define a selection that specifies the region.
- 4. Create a region reference using the dataset and dataspace with selection.
- 5. Write the region reference(s) to the desired dataset or attribute.

Figure 23 shows a diagram of a file with three datasets. Dataset D1 and D2 are two dimensional arrays of integers. Dataset R1 is a one dimensional array of references to regions in D1 and D2. The regions can be any valid selection of the dataspace of the target dataset.

a) 1 D array of region pointers, each pointer refers to a selection in one Dataset.




Figure 23

Figure 24 shows example code to create the array of region references. The references are created in an array of type hdset_reg_ref_t. Each region is defined as a selection on the dataspace of the dataset, and a reference is created using H5Rcreate(). The call to H5Rcreate() specifies the file, dataset, and the dataspace with selection.

```
* The second reference is to a union of hyperslabs in the first
start[0] = 5; start[1] = 3;
count[0] = 1; count[1] = 4;
status = H5Sselect_none(space_id);
status = H5Sselect_hyperslab(space_id, H5S_SELECT_SET, start,
           NULL, count, NULL);
               start[1] = 5;
start[0] = 6;
count[0] = 1; count[1] = 2;
status = H5Sselect_hyperslab(space_id, H5S_SELECT_OR, start, NULL,
      count, NULL);
status = H5Rcreate(&ref[1], file_id, "D1", H5R_DATASET_REGION,
       space_id);
 * the fourth reference is to a selection of points in the first
 * Dataset
status = H5Sselect_none(space_id);
coord[0][0] = 4; coord[0][1] = 4;
coord[1][0] = 2; coord[1][1] = 6;
coord[2][0] = 3; coord[2][1] = 7;
coord[3][0] = 1; coord[3][1] = 5;
coord[4][0] = 5; coord[4][1] = 8;
status = H5Sselect_elements(space_id, H5S_SELECT_SET,num_points,
                             (const hssize_t **)coord);
status = H5Rcreate(&ref[3], file_id, "D1", H5R_DATASET_REGION,
     space_id);
/*
* the third reference is to a hyperslab in the second Dataset
start[0] = 0; start[1] = 0;
count[0] = 4; count[1] = 6;
status = H5Sselect_hyperslab(space_id2, H5S_SELECT_SET, start, NULL,
        count, NULL);
status = H5Rcreate(&ref[2], file_id, "D2", H5R_DATASET_REGION,
        space_id2);
```

Figure 24

When all the references are created, the array of references is written to the dataset R1. The dataset is declared to have datatype H5T_STD_REF_DSETREG (Figure 25).

Figure 25

When creating region references, the following rules are enforced.

- ♦ The selection must be a valid selection for the target *dataset*, just as when transferring data.
- ♦ The *dataset* must exist in the file when the reference is created (H5Rcreate).
- ♦ The target *dataset* must be in the same file as the stored reference.

Reading References to Regions

To retrieve data from a region reference, the reference must be read from the file, and then the data can be retrieved. The steps are:

- 1. Open the dataset or attribute containing the reference objects.
- 2. Read the reference object(s).
- 3. For each region reference, get the dataset (H5R_dereference) and dataspace (H5Rget_space)
- 4. Use the dataspace and datatype to discover what space is needed to store the data, allocate the correct storage and create a dataspace and datatype to define the memory data layout.

Figure 26 shows example code to read an array of region references from a dataset, and then read the data from the first selected region. Note that the region reference has information that records the dataset (within the file) and the selection on the *dataspace* of the *dataset*. After dereferencing the regions reference, the *datatype*, number of points, and some aspects of the selection can be discovered. (For a union of hyperslabs, it may not be possible to determine the exact set of hyperslabs that has been combined.) Table 3 shows the inquiry functions.

When reading data from a region reference, the following rules are enforced:

- ♦ The target *dataset* must be present and accessible in the file.
- ♦ The selection must be a valid selection for the *dataset*.

```
dsetr_id = H5Dopen (file_id, "R1");
status = H5Dread(dsetr_id, H5T_STD_REF_DSETREG, H5S_ALL, H5S_ALL,
               H5P_DEFAULT, ref_out);
/*
 * Dereference the first reference.
    1) get the dataset (H5Rdereference)
     2) get the selected dataspace (H5Rget_region)
* /
dsetv_id = H5Rdereference(dsetr_id, H5R_DATASET_REGION,
       &ref_out[0]);
space id = H5Rget region(dsetr id, H5R DATASET REGION,&ref_out[0]);
   Discover how many points and shape of the data
ndims = H5Sget_simple_extent_ndims(space_id);
H5Sget_simple_extent_dims(space_id,dimsx,NULL);
 * Read and display hyperslab selection from the dataset.
 dimsy[0] = H5Sget_select_npoints(space_id);
 spacex_id = H5Screate_simple(1, dimsy, NULL);
status = H5Dread(dsetv_id, H5T_NATIVE_INT, H5S_ALL, space_id,
               H5P_DEFAULT, data_out);
printf("Selected hyperslab: ");
for (i = 0; i < 8; i++)
    printf("\n");
    for (j = 0; j < 10; j++)
        printf("%d ", data_out[i][j]);
printf("\n");
```

Figure 26

Table 3

Function Information

H5Sget_select_npoints The number of elements in the selection (hyperslab or point selection)

H5Sget_select_bounds The bounding box that encloses the selected points (hyperslab or point selection)

H5Sget_select_hyper_nblocks The number of blocks in the selection.

H5Sget_select_hyper_blocklist A list of the blocks in the selection

H5Sget_select_elem_npoints The number of points in the selection.

H5Sget_select_elem_pointist The points.

7. Sample Programs

This section contains the full programs from which several of the code examples in this chapter were derived. The h5dump output from the program's output file immediately follows each program.

```
h5_write.c
______
#include "hdf5.h"
#define DATASETNAME "C Matrix"
                                        /* dataset dimensions */
#define NX 3
#define NY
#define RANK 2
int
main (void)
    hid_t file, dataset;  /* file and dataset handles */
hid_t datatype, dataspace; /* handles */
hsize_t dims[2]; /* dataset dimensions */
herr_t status;
int data[NX][NY]; /* data to write */
int i, j;
      * Data and output buffer initialization.
     for (j = 0; j < NX; j++) {
       for (i = 0; i < NY; i++)
            data[j][i] = i + 1 + j*NY;
     }
      * 1 2 3 4 5
      * 6 7 8 9 10
      * 11 12 13 14 15
      * Create a new file using H5F_ACC_TRUNC access,
      * default file creation properties, and default file
      * access properties.
     file = H5Fcreate(H5FILE_NAME, H5F_ACC_TRUNC, H5P_DEFAULT, H5P_DEFAULT);
      ^{\star} Describe the size of the array and create the data space for fixed
      * size dataset.
      * /
     dims[0] = NX;
     dims[1] = NY;
     dataspace = H5Screate_simple(RANK, dims, NULL);
      * Create a new dataset within the file using defined dataspace and
      * datatype and default dataset creation properties.
      * /
     dataset = H5Dcreate(file, DATASETNAME, H5T_NATIVE_INT, dataspace,
```

H5P_DEFAULT);

```
* Write the data to the dataset using default transfer properties.
     status = H5Dwrite(dataset, H5T_NATIVE_INT, H5S_ALL, H5S_ALL,
                       H5P DEFAULT, data);
      * Close/release resources.
      * /
     H5Sclose(dataspace);
     H5Dclose(dataset);
     H5Fclose(file);
     return 0;
}
SDS.out
-----
HDF5 "SDS.h5" {
GROUP "/" {
    DATASET "C Matrix" {
       DATATYPE H5T_STD_I32BE
       DATASPACE SIMPLE { ( 3, 5 ) / ( 3, 5 ) }
       DATA {
          1, 2, 3, 4, 5,
          6, 7, 8, 9, 10,
          11, 12, 13, 14, 15
       }
    }
}
}
h5_write.f90
_____
      PROGRAM DSETEXAMPLE
      USE HDF5 ! This module contains all necessary modules
      IMPLICIT NONE
      CHARACTER(LEN=7), PARAMETER :: filename = "SDSf.h5" ! File name
      CHARACTER(LEN=14), PARAMETER :: dsetname = "Fortran Matrix" ! Dataset name
      INTEGER, PARAMETER :: NX = 3
      INTEGER, PARAMETER :: NY = 5
      INTEGER(HID_T) :: file_id     ! File identifier
INTEGER(HID_T) :: dset_id     ! Dataset identifier
INTEGER(HID_T) :: dspace_id     ! Dataspace identifier
      INTEGER(HSIZE_T), DIMENSION(2) :: dims = (/3,5/) ! Dataset dimensions
      INTEGER :: rank = 2
                                                         ! Dataset rank
      INTEGER
                 :: data(NX,NY)
```

```
! Initialize data
 do i = 1, NX
    do j = 1, NY
       data(i,j) = j + (i-1)*NY
    enddo
 enddo
!
! Data
! 1 2 3 4 5
! 6 7 8 9 10
! 11 12 13 14 15
! Initialize FORTRAN interface.
CALL h5open_f(error)
! Create a new file using default properties.
CALL h5fcreate_f(filename, H5F_ACC_TRUNC_F, file_id, error)
! Create the dataspace.
CALL h5screate_simple_f(rank, dims, dspace_id, error)
! Create and write dataset using default properties.
CALL h5dcreate_f(file_id, dsetname, H5T_NATIVE_INTEGER, dspace_id, &
                dset_id, error)
CALL h5dwrite_f(dset_id, H5T_NATIVE_INTEGER, data, dims, error)
! End access to the dataset and release resources used by it.
CALL h5dclose_f(dset_id, error)
! Terminate access to the data space.
CALL h5sclose_f(dspace_id, error)
! Close the file.
CALL h5fclose_f(file_id, error)
! Close FORTRAN interface.
CALL h5close_f(error)
END PROGRAM DSETEXAMPLE
```

```
SDSf.out
HDF5 "SDSf.h5" {
GROUP "/" {
    DATASET "Fortran Matrix" {
        DATATYPE H5T_STD_I32BE
        DATASPACE SIMPLE { ( 5, 3 ) / ( 5, 3 ) }
        DATA {
            1, 6, 11,
            2, 7, 12,
            3, 8, 13,
            4, 9, 14,
            5, 10, 15
     }
h5_write_tr.f90
_____
      PROGRAM DSETEXAMPLE
       USE HDF5 ! This module contains all necessary modules
       IMPLICIT NONE
       CHARACTER(LEN=10), PARAMETER :: filename = "SDSf_tr.h5" ! File name
       CHARACTER(LEN=24), PARAMETER :: dsetname = "Fortran Transpose Matrix"
                                                          ! Dataset name
       INTEGER, PARAMETER :: NX = 3
       INTEGER, PARAMETER :: NY = 5
       INTEGER(HID_T) :: file_id     ! File identifier
INTEGER(HID_T) :: dset_id     ! Dataset identifier
INTEGER(HID_T) :: dspace_id     ! Dataspace identifier
       INTEGER(HSIZE_T), DIMENSION(2) :: dims = (/NY, NX/) ! Dataset dimensions
       INTEGER :: rank = 2
INTEGER :: data(NY,NX)
                                                                ! Dataset rank
       \begin{array}{lll} \mbox{INTEGER} & :: & \mbox{error ! Error flag} \\ \mbox{INTEGER} & :: i, j \end{array}
       ! Initialize data
         do i = 1, NY
            do j = 1, NX
                data(i,j) = i + (j-1)*NY
             enddo
         enddo
       !
       ! Data
       !
       ! 1 6 11
       ! 2 7 12
       ! 3 8 13
```

```
! 4 9 14
! 5 10 15
! Initialize FORTRAN interface.
CALL h5open_f(error)
! Create a new file using default properties.
CALL h5fcreate_f(filename, H5F_ACC_TRUNC_F, file_id, error)
! Create the dataspace.
CALL h5screate_simple_f(rank, dims, dspace_id, error)
! Create and write dataset using default properties.
CALL h5dcreate_f(file_id, dsetname, H5T_NATIVE_INTEGER, dspace_id, &
                dset_id, error)
CALL h5dwrite_f(dset_id, H5T_NATIVE_INTEGER, data, dims, error)
! End access to the dataset and release resources used by it.
CALL h5dclose_f(dset_id, error)
! Terminate access to the data space.
CALL h5sclose_f(dspace_id, error)
! Close the file.
CALL h5fclose_f(file_id, error)
! Close FORTRAN interface.
CALL h5close_f(error)
END PROGRAM DSETEXAMPLE
```

```
SDSf_tr.out
------
HDF5 "SDSf_tr.h5" {
GROUP "/" {
    DATASET "Fortran Transpose Matrix" {
        DATASPACE SIMPLE { ( 3, 5 ) / ( 3, 5 ) }
        DATA {
            1, 2, 3, 4, 5,
            6, 7, 8, 9, 10,
            11, 12, 13, 14, 15
        }
    }
}
```

HDF5 User's Guide HDF5 Attributes

Chapter 8 HDF5 Attributes

1. Introduction

An HDF5 attribute is a small meta data object describing the nature and/or intended usage of a primary data object, which may be a dataset, group, or named datatype.

Attributes are assumed to be very small as data objects go, so storing them as standard HDF5 datasets would be quite inefficient. HDF5 attributes are therefore managed through a special attributes interface, H5A, which is designed to easily attach attributes to primary data objects as small datasets containing metadata information and to minimize storage requirements

Consider, as examples of the simplest case, a set of laboratory readings taken under known temperature and pressure conditions of 18.0 degrees celsius and 0.5 atmospheres, respectively. The temperature and pressure could be stored as attributes of the dataset could be described as the following name/value pairs:

```
temp=18.0 pressure=0.5
```

While HDF5 attributes are not standard HDF5 datasets, they have much in common:

- An attribute has a user-defined dataspace and the included metadata has a user-assigned datatype.
- That metadata can be of any valid HDF5 datatype.
- Attributes are addressed by name.

Note:

Attributes are small datasets but not separate objects; they are contained within the object header of a primary data object. As such, attributes are opened, read, or written only with H5A functions.

But there are some very important differences:

- There is not provision for special storage, such as compression or chunking.
- There is no partial I/O or subsetting capability for attribute data.
- Attributes cannot be shared.
- Being small, an attributes is stored in the object header of the object it describes and is thus attached directly to that object.

Large attributes, described below in "Special Issues", are best stored as separate HDF5 datasets and are not subject to the above limitations.

HDF5 Attributes HDF5 User's Guide

This chapter discusses or lists the following:

- The HDF5 attributes programming model
- H5A function summaries
- Working with HDF5 attributes
 - ♦ The structure of an attribute
 - ♦ Creating, writing, and reading attributes
 - ♦ Accessing attributes by name or index
 - ♦ Obtaining information regarding an object's attributes
 - ♦ Iterating across an object's attributes
 - ♦ Deleting an attribute
 - ♦ Closing attributes
- Special issues regarding attributes

In the following discussions, attributes are generally attached to datasets. Attributes attached to other primary data objects, i.e., groups or named datatypes, are handled in exactly the same manner.

HDF5 User's Guide HDF5 Attributes

2. Programming Model

2.1 To create and write a new attribute




Figure 2: UML model for an HDF5 attribute and its associated dataspace and datatype.

Creating an attribute is similar to creating a dataset. To create an attribute, the application must specify the object to which the attribute is attached, the datatype and dataspace of the attribute data, and the attribute creation property list.

The following steps are required to create and write and an HDF5 attribute:

- 1. Obtain the object identifier for the attribute's primary data object.
- 2. Define the characteristics of the attribute and specify the attribute creation property list.
 - ♦ Define the datatype.
 - ◆ Define the dataspace.
 - Specify the attribute creation property list.
- 3. Create the attribute.
- 4. Write the attribute data (optional).
- 5. Close the attribute (and datatype, dataspace, and attribute creation property list, if necessary).
- 6. Close the primary data object (if appropriate).

HDF5 Attributes HDF5 User's Guide

2.2 To open and read/write an existing attribute

The following steps are required to open and read/write an existing attribute. Since HDF5 attributes allow no partial I/O, you need specify only the attribute and the attribute's memory datatype to read it:

- 1. Obtain the object identifier for the attribute's primary data object.
- 2. Obtain the attribute's name or index.
- 3. Open the attribute.
 - ♦ Get attribute dataspace and datatype (optional).
- 4. Specify the attribute's memory type.
- 5. Read and/or write the attribute data.
- 6. Close the attribute.
- 7. Close the primary data object (if appropriate).

HDF5 User's Guide HDF5 Attributes

3. Attribute (H5A) Function Summaries

h5aget_num_attrs_f

C Function Purpose F90 Function Creates a dataset as an attribute of another group, dataset, or named H5Acreate h5acreate f datatype. Writes an attribute. H5Awrite H5awrite f Reads an attribute. **H5Aread** h5aread f H5Aopen_name Opens an attribute specified by its name. h5aopen_name_f H5Aopen_idx Opens the attribute specified by its index. h5aopen_idx_f H5Aclose Closes the specified attribute. h5aclose_f Calls a user's function for each attribute attached to a data object. H5Aiterate (none) H5Adelete Deletes an attribute. h5adelete f Gets an attribute name. H5Aget_name h5aget_name_f Gets a copy of the dataspace for an attribute. H5Aget_space h5aget_space_f H5Aget_type Gets an attribute datatype. h5aget_type_f H5Aget num attrs Determines the number of attributes attached to a data object.

HDF5 Attributes HDF5 User's Guide

4. Working with Attributes

4.1 The structure of an attribute

An attribute has two parts:

- name
- value(s)

HDF5 attributes are sometimes discussed as name/value pairs in the form name=value.

An attribute's name is a null-terminated ASCII character string. Each attribute attached to an object has a unique name.

The value portion of the attribute contains one or more data elements of the same datatype.

HDF5 attributes have all the characteristics of HDF5 datasets except that there is no partial I/O capability; attributes can be written and read only in full, with no subsetting.

4.2 Creating, writing, and reading attributes

If attributes are used at all in an HDF5 file, these three functions will be employed. H5Acreate and H5Awrite are used together to place the attribute in the file. If an attribute is to be used and it is not currently in memory, H5Aread generally comes into play, usually in concert with one each of the H5Aget_* and H5Aopen_* functions.

To create an attribute, call H5Acreate:

loc_id identifies the object to which the attribute is to be attached, a dataset, group, or named datatype. This object, incidentally, is known as the primary data object; the attribute is a meta data object. name, type_id, space_id, and create_plist convey, respectively, the attribute's name, datatype, dataspace, and attribute creation property list. The attribute's name must be locally unique, i.e., it must be unique within the context of the object to which it is attached.

H5Acreate creates the attribute in memory; the attribute does not exist in the file until H5Awrite writes it there.

(Note that the attribute property list is currently unused. The only accepted value for create_plist is H5P_DEFAULT.)

To write or read an attribute, call H5Awrite or H5Aread, respectively:

attri_id identifies the attribute while mem_type_id identifies the in-memory datatype of the attribute data.

HDF5 User's Guide HDF5 Attributes

H5Awrite writes the attribute data, i.e., the meta data, from the buffer buf to the file; H5Aread reads attribute data from the file into buf.

The HDF5 Library converts the meta data between the in-memory datatype, mem_type_id, and the in-file datatype, defined when the attribute was created, without user intervention.

4.3 Accessing attributes by name or index

When accessing attributes, they can be identified by name or by an index value. The use of an index value makes it possible to iterate through all of the attributes associated with a given object.

To access an attribute by its name, text text H5Aopen_name:

```
hid_t H5Aopen_name (hid_t loc_id, const char *name)
```

H5Aopen_name returns an attribute identifier that can then be used by any function that must access an attribute, such as H5Aread.

Use the function H5Aget_name, described below, to determine an attribute's name. The information required to establish an index

To access an attribute by its index value, text text H5Aopen_idx:

```
hid_t H5Aopen_idx (hid_t loc_id, unsigned index)
```

To determine an attribute index value when it is not already known, you must first use the function H5Aget_num_attrs, described below, to determine the number of attributes attached to the primary object. The index values of the attributes attached to that object range from 0 through 1 less than the value returned by H5Aget_num_attrs.

H5Aopen_idx is generally used in the course of opening several attributes for later access. Use H5Aiterate, described below, if the intent is to perform the same operation on every attribute attached to an object.

4.4 Obtaining information regarding an object's attributes

In the course of working with HDF5 attributes, one may need to obtain any of several pieces of information:

- An attribute name
- The dataspace of an attribute
- The datatype of an attribute
- The number of attributes attached to an object

To obtain an attribute's name, call H5Aget_name with an attribute identifier, attr_id:

As with other attribute functions, attr_id identifies the attribute. buf is the buffer to which the attribute's name will be read; buf size defines the size of that buffer.

If the length of the attribute name, and hence the value required for buf_size, is unknown, a first call to H5Aget_name will return that size. If the value of buf_size used in that first call is too small, the name will simply be truncated in buf. A second H5Aget_name call can then be used to retrieve the name in an appropriately-sized buffer.

HDF5 Attributes HDF5 User's Guide

To determine the dataspace or datatype of an attribute, call H5Aget_space or H5Aget_type, respectively:

```
hid_t H5Aget_space (hid_t attr_id)
hid_t H5Aget_type (hid_t attr_id)
```

H5Aget_space returns the dataspace identifier for the attribute attr_id.

H5Aget_type returns the datatype identifier for the attribute attr_id.

To determine the number or attributes attached to an object, call H5Aget_num_attrs:

```
int H5Aget_num_attrs (hid_t loc_id)
```

H5Aget_num_attrs returns the of number attributes attached to the object identified by the object identifier loc id.

A call to ${\tt H5Aget_num_attrs}$ is generally the preferred first step in determining attribute index values. If the call to ${\tt H5Aget_num_attrs}$ returns N, the attributes attached to the object loc_id have index values of 0 through N-1

4.5 Iterating across an object's attributes

It is sometimes useful to be able to perform the identical operation across all of the objects attached to an object. At the simplest level, you might just want to open each attribute; at a higher level, you might wish to perform a rather complex operation on each attribute as you iterate across the set.

To iterate an operation across the attributes attached to an object, one must make a series of calls to H5Aiterate:

```
herr_t H5Aiterate (hid_t loc_id, unsigned *index, H5A_operator_t op_func, void *op_data)
```

H5Aiterate successively marches across all of the attributes attached to the object specified in loc_id, performing the operation(s) specified in op_func with the data specified in op_data on each attribute.

When H5Aiterate is called, index contains the index of the attribute to be accessed in this call; when H5Aiterate returns, index will contain the index of the next attribute. If the returned index is the null pointer, then all attributes have been processed and the iterative process is complete.

op_func is a user-defined operation that adheres to the H5A_operator_t prototype. This prototype and certain requirements imposed on the operator's behavior are described in the H5Aiterate entry in the HDF5 Reference Manual.

op_data is also user-defined to meet the requirements of op_func. Beyond providing a parameter with which to pass this data, HDF5 provides no tools for its management and imposes no restrictions.

HDF5 User's Guide HDF5 Attributes

4.6 Deleting an attribute

Once an attribute has outlived its usefulness or, for whatever reason, is no longer appropriate, it may become necessary to delete it.

To delete an attribute, call H5Adelete:

```
herr_t H5Adelete (hid_t loc_id, const char *name)
```

H5Adelete removes the attribute name from the group, dataset, or named datatype specified in loc_id.

H5Adelete must not be called if there are any open attribute identifiers on the object loc_id. Such a call can cause the internal attribute indexes to change; future writes to an open attribute would then produce unintended results.

4.7 Closing an attribute

As is the case with all HDF5 objects, once access to an attribute it is no longer needed, that attribute must be closed. It is best practice to close it as soon as practicable; it is mandatory that it be closed prior to the H5close call closing the HDF5 Library.

To close an attribute, call H5Aclose:

```
herr_t H5Aclose (hid_t attr_id)
```

H5Aclose closes the specified attribute by terminating access to its identifier, attr_id.

Further use of attr_id is illegal; any function employing it will fail.

HDF5 Attributes HDF5 User's Guide

5. Special Issues




Figure 3: A large or shared HDF5 attribute and its associated dataset(s). DatasetA is an attribute of Dataset1 that may have been too large to store as an attribute. It is associated with Dataset1 by means of an object reference pointer attached as an attribute to Dataset1. Such an attribute can be shared among multiple datasets by means of additional object reference pointers attached to additional datasets.

Large attributes

Attributes are intended to be small objects. A large dataset intended as meta data for another dataset can be stored as a supplemental dataset. An attribute would then be attached to the original dataset indicating the relationship as an object reference pointer. This approach is illustrated in Figure 3.

How small is *small* and how large is *large* are not defined by the library; it is left to the user's interpretation. (In considering attributes and size, the HDF5 development team has considered attributes to be up to 16K, but this has never been set as a design or implementation limit.)

Shared attributes

Attributes written and managed through the H5A interface cannot be shared. If shared attributes are required, they must be handled in the manner described above for large attributes and illustrated in Figure 3.

Attribute names

While an attribute name may include any valid ASCII characters, including blanks, it is generally wise to keep readability issues in mind. In C, the name must be terminated with a null character, $\setminus 0$.

No special I/O or storage

HDF5 attributes have all the characteristics of HDF5 datasets except the following:

- ♦ Attributes are written and read only in full; there is no provision for partial I/O or subsetting.
- ♦ No special storage capability is provided for attributes; there is no compression or chunking and attributes are not extendable.

HDF5 User's Guide HDF5 Error Handling

Chapter 9 HDF5 Error Handling

1. Introduction

The HDF5 Library provides an error reporting mechanism for both the library itself and user application programs. It can trace errors through function stack and error information like file name, function name, line number, and error description.

Section 2 of this chapter discusses the HDF5 error handling programming model.

Section 3 presents summaries of HDF5's error handling functions.

Section 4 discusses the basic error concepts, such as error stack, error record, and error message, and the related API functions. These concepts and functions are sufficient for application programs to trace errors inside the HDF5 Library.

Section 5 talks about the advanced concepts of error class and error stack handle, and the related functions. With these concepts and functions, an application library or program using the HDF5 Library can have its own error report blended with HDF5's error report.

Starting with Release 1.8, we have a new set of Error Handling API functions. For the purpose of backward compatibility with version 1.6 and before, we still keep the old API functions, H5Epush, H5Eprint, H5Ewalk, H5Eclear, H5Eget_auto, H5Eset_auto. These functions do not have the error stack as parameter. The library allows them to operate on the default error stack. Users do not have to change their code to catch up with the new Error API but are encouraged to do so.

The old API is similar to functionality discussed in Section 4. The functionality discussed in Section 5, the ability of allowing applications to add their own error records, is the library new design for the Error API.

HDF5 Error Handling HDF5 User's Guide

2. Programming Model

HDF5 User's Guide HDF5 Error Handling

3. Error Handling (H5E) Function Summaries

C Function Purpose F90 Function Determines the type of error stack. H5Eauto is v2 (none) Clears the error stack for the current thread. H5Eclear h5eclear f H5Eclear_stack Clears the error stack for the current thread. (none) H5Eclose msq Closes an error message identifier. (none) H5Eclose stack Closes object handle for error stack. (none) H5Ecreate_msg Add major error message to an error class. (none) H5Eget_auto Returns the current settings for the automatic error stack traversal function and its data. (none) H5Eget_auto2 Returns the current settings for the automatic error stack traversal function and its data. (none) H5Eget_class_name Retrieves error class name. (none) H5Eget current stack Registers the current error stack. (none) Returns a character string describing an error specified by a major H5Eget major h5eget_major_f H5Eget_minor Returns a character string describing an error specified by a minor h5eget_minor_f error number. H5Eget msg Retrieves an error message. (none) H5Eget_num Retrieves the number of error messages in an error stack. (none) Deletes specified number of error messages from the error stack. H5Epop (none) Prints the error stack in a default manner. H5Eprint h5eprint_f Prints the error stack in a default manner. H5Eprint2 (none) H5Epush Pushes new error record onto error stack. (none) Pushes a new error record onto the error stack. H5Epush2 (none) H5Eregister_class Registers a client library or application program to the HDF5 error API. (none)

HDF5 Error Handling

HDF5 User's Guide

H5Eset_auto Turns automatic error printing on or off.

h5eset_auto_f

H5Eset_auto2 Turns automatic error printing on or off.

(none)

H5Eset_current_stack Replaces the current error stack.

(none)

H5Eunregister_class Removes an error class.

(none)

H5Ewalk Walks the error stack for the current thread, calling a specified

(none) function.

H5Ewalk2 Walks the error stack for the current thread, calling a specified

(none) function.

HDF5 User's Guide HDF5 Error Handling

4. Basic Error Handling Operations

4.1 Introduction

Let us first try to understand the error stack. An *error stack* is a collection of error records. Error records can be pushed onto or popped off the error stack. By default, when an error occurs deep within the HDF5 Library, an error record is pushed onto an error stack and that function returns a failure indication. Its caller detects the failure, pushes another record onto the stack, and returns a failure indication. This continues until the API function called by the application returns a failure indication. The next API function being called will reset the error stack. All HDF5 Library error records belong to the same error class (explained in Section 5).

4.2 Error Stack and Error Message

In normal circumstances, an error causes the stack to be printed on the standard error stream automatically. This automatic error stack is the library's default stack. For all the functions in this section, whenever an error stack ID is needed as a parameter, H5E_DEFAULT can be used to indicate the library's default stack. The first error record of the error stack, number "#000", is produced by the API function itself and is usually sufficient to indicate to the application what went wrong.

Example: An Error Report

If an application calls H5Tclose on a predefined data type then the following message is printed on the standard error stream. This is a simple error that has only one component, the API function; other errors may have many components.

```
HDF5-DIAG: Error detected in HDF5 (1.6.4) thread 0.
#000: H5T.c line 462 in H5Tclose(): predefined datatype
major: Function argument
minor: Bad value
```

From the example we can see, an *error record* has a major message and a minor message. A *major message* generally indicates where the error happens. The location can be data set, data space, or heap, etc. A *minor message* explains further details of the error, for example, "unable to open file". Another specific detail about the error can be found at the end of the first line of each error record. This *error description* is usually added by the library designer to tell what exactly goes wrong. In the example above, the "predefined datatype" is an error description.

4.3 Print and Clear Error Stack

Besides the automatic error report, the error stack can also be printed and cleared by the functions H5Eprint2() and H5Eclear_stack(). If an application wishes to make explicit calls to H5Eprint2() to print the error stack, the automatic printing should be turned off to prevent error messages from being displayed twice (see H5Eset auto2() below).

```
herr_t H5Eprint2(hid_t error_stack, FILE * stream)
```

Prints the error stack specified by error_stack on the specified stream, stream. Even if the error stack is empty, a one-line message will be printed like this if the error is in HDF5 Library:

HDF5-DIAG: Error detected in HDF5 Library version: 1.5.62 thread 0.

HDF5 Error Handling HDF5 User's Guide

```
herr_t H5Eclear_stack(hid_t error_stack)
```

H5Eclear clears the error stack specified by error_stack. H5E_DEFAULT can be passed in to clear the current error stack. The current stack is also cleared whenever an API function is called, with certain exceptions (for instance, H5Eprint2()).

4.4 Mute Error Stack

Sometimes an application calls a function for the sake of its return value, fully expecting the function to fail; sometimes the application wants to call H5Eprint2() explicitly. In these situations, it would be misleading if an error message were still automatically printed. Using the H5Eset_auto2() function can control the automatic printing of error messages:

herr_t H5Eset_auto2(hid_t error_stack, H5E_auto2_t func, void *client_data)
Turns on or off automatic printing of errors for the error stack specified by error_stack. When turned on (non-null func pointer), any API function which returns an error indication will first call func, passing it client_data as an argument. When the library is first initialized the auto printing function is set to H5Eprint() (cast appropriately) and client_data is the standard error stream pointer, stderr.

herr_t H5Eget_auto2(hid_t error_stack, H5E_auto2_t * func, void **client_data)

Returns the current settings for the automatic error stack traversal function, func, and its data, client_data.

Either (or both) arguments may be null in which case the value is not returned.

Example: Error Control

An application can temporarily turn off error messages while "probing" a function.

```
/* Save old error handler */
herr_t (*old_func)(void*);
void *old_client_data;

H5Eget_auto2(error_stack, &old_func, &old_client_data);

/* Turn off error handling */
H5Eset_auto2(error_stack, NULL, NULL);

/* Probe. Likely to fail, but that's okay */
status = H5Fopen (.....);

/* Restore previous error handler */
H5Eset_auto2(error_stack, old_func, old_client_data);
```

Or automatic printing can be disabled altogether and error messages can be explicitly printed.

```
/* Turn off error handling permanently */
H5Eset_auto2(error_stack, NULL, NULL);

/* If failure, print error message */
if (H5Fopen (....)<0) {
    H5Eprint2(H5E_DEFAULT, stderr);
    exit (1);
}</pre>
```

HDF5 User's Guide HDF5 Error Handling

4.5 Customized Printing of Error Stack

The application is allowed to define an automatic error traversal function other than the default H5Eprint2(). For instance, one can define a function that prints a simple, one-line error message to the standard error stream and then exits.

Example: Simple Messages

The application defines a function to print a simple error message to the standard error stream.

```
herr_t
my_hdf5_error_handler(void *unused)
{
   fprintf (stderr, "An HDF5 error was detected. Bye.\n");
   exit (1);
}
```

The function is installed as the error handler by saying

```
H5Eset_auto2(H5E_DEFAULT, my_hdf5_error_handler, NULL);
```

4.6 Walk Through the Error Stack

The H5Eprint2() function is actually just a wrapper around the more complex H5Ewalk2() function which traverses an error stack and calls a user-defined function for each member of the stack.

```
herr_t H5Ewalk2(hid_t err_stack, H5E_direction_t direction, H5E_walk2_t func, void
*client_data)
```

The error stack err_stack is traversed and func is called for each member of the stack. Its arguments are an integer sequence number beginning at zero (regardless of direction), and the client_data pointer. If direction is H5E_WALK_UPWARD then traversal begins at the inner-most function that detected the error and concludes with the API function. The opposite order is H5E_WALK_DOWNWARD.

typedef herr_t (*H5E_walk2_t)(unsigned n, H5E_error2_t *eptr, void * client_data)

An error stack traversal callback function takes three arguments: n is a sequence number beginning at zero for each traversal, eptr is a pointer to an error stack member, and client_data is the same pointer passed to H5Ewalk2().

```
typedef struct {
   hid_t cls_id;
   hid_t maj_num;
   hid_t min_num;
   unsigned line;
   const char *func_name;
   const char *file_name;
   const char *desc;
} H5E_error2_t;
```

The *maj_num* and *min_num* are major and minor error IDs, *func_name* is the name of the function where the error was detected, *file_name* and *line* locate the error within the HDF5 Library source code, and *desc* points to a description of the error.

Example of callback function:

The following callback function serves as an example for a user-defined callback function.

HDF5 Error Handling HDF5 User's Guide

```
#define MSG_SIZE
                       64
herr t
custom print cb(unsigned n, const H5E error2 t *err desc, void* client data)
                        *stream = (FILE *)client_data;
    SILLE
    char
                       maj[MSG_SIZE];
    char
                        min[MSG_SIZE];
    char
                        cls[MSG_SIZE];
    const int
                        indent = 4;
    /* Get descriptions for the major and minor error numbers */
    if(H5Eqet_class_name(err_desc->cls_id, cls, MSG_SIZE)<0)</pre>
        TEST ERROR;
    if(H5Eget_msg(err_desc->maj_num, NULL, maj, MSG_SIZE)<0)</pre>
        TEST ERROR;
    if(H5Eget msg(err desc->min num, NULL, min, MSG_SIZE)<0)</pre>
        TEST ERROR;
    fprintf (stream, "%*serror \#\%03d: %s in %s(): line \%u\n",
             indent, "", n, err_desc->file_name,
             err_desc->func_name, err_desc->line);
    fprintf (stream, "%*sclass: %s\n", indent*2, "", cls);
    fprintf (stream, "%*smajor: %s\n", indent*2, "", maj);
    fprintf (stream, "%*sminor: %s\n", indent*2, "", min);
    return 0;
  error:
    return -1;
}
```

5. Advanced Error Handling Operations

5.1 Introduction

Section 4 discusses the basic error handling operations of the library. In that section, all the error records on the error stack are from the library itself. In this section, we are going to introduce the operations that allow an application program to push its own error records onto the error stack once it declares an error class for its own through the HDF5's Error API.

Example: An Error Report

An error report shows both the library's error record and the application's error records.

```
Error Test-DIAG: Error detected in Error Program (1.0) thread 8192:
    #000: ../../hdf5/test/error_test.c line 468 in main(): Error test failed
    major: Error in test
    minor: Error in subroutine
    #001: ../../hdf5/test/error_test.c line 150 in test_error(): H5Dwrite failed
    as supposed to
    major: Error in IO
    minor: Error in H5Dwrite
HDF5-DIAG: Error detected in HDF5 (1.7.5) thread 8192:
    #002: ../../hdf5/src/H5Dio.c line 420 in H5Dwrite(): not a dataset
```

HDF5 User's Guide HDF5 Error Handling

```
major: Invalid arguments to routine
minor: Inappropriate type
```

Notice in the line above error record #002 in the example, the starting phrase is HDF5. This is the error class name of the HDF5 Library. All of the library's error messages (major and minor) are in this default error class. The Error Test in the beginning of the line above error record #000 is the name of the application's error class. The first two error records, #000 and #001, are from application's error class.

In definition, an error class is a group of major and minor error messages for certain library (the HDF5 or an application library built on top of the HDF5 Library) or application program. Error class can be registered for an application library or program through the HDF5 Error API. Major messages and minor messages can be defined in an error class. An application will have object handles for error class, major and minor messages for further operation.

5.2 Register Application with Error API

These functions can be used to register or unregister an error class, create or close error messages, or do query on an error class and error message:

hid_t H5Eregister_class(const char* cls_name, const char* lib_name, const char* version)
Registers an error class to HDF5 Library so that the application library or program can report errors together with HDF5 Library.

hid_t H5Ecreate_msg(hid_t class, H5E_type_t msg_type, const char* mesg)
Adds an error message to an error class defined by application library or program. The error message can be either major or minor which is indicated by parameter msg_type.

```
ssize_t H5Eget_class_name(hid_t class_id, char* name, size_t size)
Retrieves the name of the error class specified by the class ID.
```

ssize_t H5Eget_msg(hid_t mesg_id, H5E_type_t* mesg_type, char* mesg, size_t size) Retrieves the error message including its length and type.

```
herr_t H5Eclose_msg(hid_t mesg_id) Closes an error message.
```

herr_t H5Eunregister_class(hid_t class_id)
Removes an error class from the error API.

Example: Error Class and Its Message

An application creates an error class and error messages.

```
/* Create an error class */
class_id = H5Eregister_class(ERR_CLS_NAME, PROG_NAME, PROG_VERS);

/* Retrieve class name */
H5Eget_class_name(class_id, cls_name, cls_size);

/* Create a major error message in the class */
maj_id = H5Ecreate_msg(class_id, H5E_MAJOR, "...");

/* Create a minor error message in the class */
```

HDF5 Error Handling HDF5 User's Guide

```
min_id = H5Ecreate_msg(class_id, H5E_MINOR, "...");
```

Application closes error messages and un-registers error class.

```
H5Eclose_msg(maj_id);
H5Eclose_msg(min_id);
H5Eunregister_class(class_id);
```

5.3 Push Application Error Message Onto Error Stack

An application can push error records onto or pop error records off the error stack, just as the library does internally. An error stack can be registered, and an object handle can be returned to the application, so that the application can manipulate a registered error stack.

```
hid_t H5Eget_current_stack(void)
```

Registers the current error stack, returns an object handle, and clears the current error stack. An empty error stack will also be assigned an ID.

```
herr_t H5Eset_current_stack(hid_t error_stack)
```

Replaces the current error stack with another error stack specified by error_stack, clears the current error stack. The object handle error_stack is closed after this function call.

```
herr\_t \; \texttt{H5Epush2} (hid\_t \; \texttt{error\_stack}, \; const \; char * \; \texttt{file}, \; const \; char * \; \texttt{func}, \; unsigned \; \texttt{line}, \; hid\_t \; \texttt{cls\_id}, \; hid\_t \; \texttt{major\_id}, \; hid\_t \; \texttt{minor\_id}, \; const \; char * \; \texttt{desc}, \dots)
```

Pushes a new error record onto the error stack for the current thread.

```
herr_t H5Epop(hid_t error_stack, size_t count)
```

Deletes some error messages from the error stack.

HDF5 User's Guide HDF5 Error Handling

```
int H5Eget_num(hid_t error_stack)
```

Retrieves the number of error records from an error stack.

```
herr_t H5Eclear_stack(hid_t error_stack)
Clears the error stack.
```

herr_t H5Eclose_stack(hid_t error_stack)

Closes the object handle for an error stack and releases its resources.

Example: Error Stack

An application pushes error record onto default error stack.

The application registers current error stack and creates an object handle to avoid another HDF5 function clearing the error stack.

Part III

Special Topics

Chapter 10 HDF5 Special Topics

1. Introduction

This chapter presents topics that do not fit neatly in primary chapters of the *HDF5 User's Guide* but that are likely to be of interest to significant numbers of users.

2. Metadata Caching in HDF5

In the 1.6.4 release, we introduced a re-implementation of the metadata cache. That release contained an incomplete version of the cache which could not be controlled via the API. The version in the 1.8 release is more mature, and includes new API calls that allow the user program to configure the metadata cache both on file open and at run time.

From the user perspective, the most striking effect of the new cache should be a large reduction in the cache memory requirements when working with complex HDF5 files.

Those working with such files may also notice a reduction in file close time.

Those working with HDF5 files with simple structure shouldn't notice any particular changes in most cases. In rare cases, there may be a significant improvement in performance.

The remainder of this document contains an architectural overview of the old and new metadata caches, a discussion of algorithms used to automatically adjust cache size to circumstances, and a high level discussion of the cache configuration controls. It can be safely skipped by anyone who works only with HDF5 files with relatively simple structure (i.e. no huge groups, no datasets with large numbers of chunks, and no objects with large numbers of attributes.)

On the other hand, it is mandatory reading if you want to use something other than the default metadata cache configuration. The documentation on the metadata cache related API calls will not make much sense without this background.

2.1 The Old Metadata Cache:

The old metadata cache indexed the cache with a hash table with no provision for collisions. Instead, collisions were handled by evicting the existing entry to make room for the new entry. Aside from flushes, there was no other mechanism for evicting entries, so the replacement policy could best be described as "Evict on Collision".

As a result, if two frequently used entries hashed to the same location, they would evict each other regularly. To decrease the likelihood of this situation, the default hash table size was set fairly large -- slightly more than 10,000. This worked well, but since the size of metadata entries is not bounded, and since entries were only evicted on collision, the large hash table size allowed the cache size to explode when working with HDF5 files with complex structure.

The "Evict on Collision" replacement policy also caused problems with the parallel version of the HDF5 library, as a collision with a dirty entry could force a write in response to a metadata read. Since all metadata writes must be collective in the parallel case while reads need not be, this could cause the library to hang if only some of the

processes participated in a metadata read that forced a write. Prior to the implementation of the new metadata cache, we dealt with this issue by maintaining a shadow cache for dirty entries evicted by a read.

2.2 The New Metadata Cache:

The new metadata cache was designed to address the above issues. After implementation, it became evident that the working set size for HDF5 files varies widely depending on both structure and access pattern. Thus it was necessary to add support for cache size adjustment under either automatic or user program control (see section 2.3 for details).

When the cache is operating under direct user program control, it is also possible to temporarily disable evictions from the metadata cache so as to maximize raw data throughput at the expense of allowing the cache to grow without bound until evictions are enabled again.

Structurally, the new metadata cache can be thought of as a heavily modified version of the UNIX buffer cache as described in chapter three of M. J. Bach's "The Design of the UNIX Operating System" In essence, the UNIX buffer cache uses a hash table with chaining to index a pool of fixed size buffers. It uses the LRU replacement policy to select candidates for eviction.

Since HDF5 metadata entries are not of fixed size, and may grow arbitrarily large, the size of the new metadata cache cannot be controlled by setting a maximum number of entries. Instead the new cache keeps a running sum of the sizes of all entries, and attempts to evict entries as necessary to stay within a user specified maximum size. (Note the use of the word "attempts" here -- as will be seen, it is possible for the cache to exceed its currently specified maximum size.) At present, the LRU replacement policy is the only option for selecting candidates for eviction.

Per the standard unix buffer cache, dirty entries are given two passes through the LRU list before being evicted. The first time they reach the end of the LRU list, they are flushed, marked as clean, and moved to the head of the LRU list. When a clean entry reaches the end of the LRU list, it is simply evicted if space is needed.

The cache cannot evict entries that are locked, and thus it will temporarily grow beyond its maximum size if there are insufficient unlocked entries available for eviction.

In the parallel version of the library, only the cache running under process 0 of the file communicator is allowed to write metadata to file. All the other caches must retain dirty metadata until the process 0 cache tells them that the metadata is clean.

Since all operations modifying metadata must be collective, all caches see the same stream of dirty metadata. This fact is used to allow them to synchronize every n bytes of dirty metadata, where n is a user configurable value that defaults to 256 KB.

To avoid sending the other caches messages from the future, process 0 must not write any dirty entries until it reaches a synchronization point. When it reaches a synchronization point, it writes entries as needed, and then broadcasts the list of flushed entries to the other caches. The caches on the other processes use this list to mark entries clean before they leave the synchronization point, allowing them to evict those entries as needed.

The caches will also synchronize on a user initiated flush.

To minimize overhead when running in parallel, the cache maintains a "clean" LRU list in addition to the regular LRU list. This list contains only clean entries, and is used as a source of candidates for eviction when flushing dirty entries is not allowed.

Since flushing entries is forbidden most of the time when running in parallel, the caches can be forced to exceed their maximum sizes if they run out of clean entries to evict.

To decrease the likelihood of this event, the new cache allows the user to specify a minimum clean size -- which is a minimum total size of all the entries on the clean LRU plus all unused space in the cache.

While the clean LRU list is only maintained in the parallel version of the HDF5 library, the notion of a minimum clean size still applies in the serial case. Here it is used to force a mix of clean and dirty entries in the cache even in the write only case.

This in turn reduces the number of redundant flushes by avoiding the case in which the cache fills with dirty metadata and all entries must be flushed before a clean entry can be evicted to make room for a new entry.

Observe that in both the serial and parallel cases, the maintenance of a minimum clean size modifies the replacement policy, as dirty entries may be flushed earlier than would otherwise be the case so as to maintain the desired amount of clean and/or empty space in the cache.

While the new metadata cache only supports the LRU replacement policy at present, that may change. Support for multiple replacement policies was very much in mind when the cache was designed, as was the ability to switch replacement policies at run time. The situation has been complicated by the later addition of the adaptive cache resizing requirement, as two of the resizing algorithms piggyback on the LRU list. However, if there is need for additional replacement policies, it shouldn't be too hard to implement them.

2.3 Adaptive Cache Resizing in the New Metadata Cache:

As mentioned earlier, the metadata working set size for a HDF5 file varies wildly depending on the structure of the file and the access pattern. For example, a 2MB limit on metadata cache size is excessive for an H5repack of almost all HDF5 files we have tested. However, I have a file submitted by one of our users that that will run a 13% hit rate with this cache size, and will lock up one of our linux boxes using the old metadata cache. Increase the new metadata cache size to 4 MB, and the hit rate exceeds 99%.

In this case the main culprit is a root group with more than 20,000 entries in it. As a result, the root group heap exceeds 1 MB, which tends to crowd out the rest of the metadata in a 2 MB cache

This case and a number of synthetic tests convinced us that we needed to modify the new metadata cache to expand and contract according to need within user specified bounds.

I was unable to find any previous work on this problem, so I invented solutions as I went along. If you are aware of prior work, please send me references. The closest I was able to come was a group of embedded CPU designers who were turning off sections of their cache to conserve power.

2.3.1 Increasing the Cache Size:

In the context of the HDF5 library, the problem of increasing the cache size as necessary to contain the current working set turns out to involve two rather different issues.

The first of these, which was recognized immediately, is the problem of recognizing long term changes in working set size, and increasing the cache size accordingly, while not reacting to transients.

The second, which I recognized the hard way, is to adjust the cache size for sudden, dramatic increases in working set size caused by requests for large pieces of metadata which may be larger than the current metadata cache size.

The algorithms for handling these situations are discussed below. These problems are largely orthogonal to each other, so both algorithms may be used simultaneously.

2.3.1.1 Hit Rate Threshold Cache Size Increment:

Perhaps the most obvious heuristic for identifying cases in which the cache is too small involves monitoring the hit rate. If the hit rate is low for a while, and the cache is at its current maximum size, the current maximum cache size is probably too small.

The hit rate threshold algorithm for increasing cache size applies this intuition directly.

Hit rate statistics are collected over a user specified number of cache accesses. This period is known as an epoch.

At the end of each epoch, the hit rate is computed, and the counters are reset. If the hit rate is below a user specified threshold and the cache is at its current maximum size, the maximum size of the cache is increased by a user specified multiple. If required, the new cache maximum size is clipped to stay within the user specified upper bound on the maximum cache size, and optionally, within a user specified maximum increment.

My tests indicate that this algorithm works well in most cases. However, in a synthetic test in which hit rate increased slowly with cache size, and load remained steady for many epochs, I observed a case in which cache size increased until hit rate just exceeded the specified minimum and then stalled. This is a problem, as to avoid

volatility, it is necessary to set the minimum hit rate threshold well below the desired hit rate. Thus we may find ourselves with a cache running with a 91% hit rate when we really want it to increase its size until the hit rate is about 99%.

If this case occurs frequently in actual use, I will have to come up with an improved algorithm. Please let me know if you see this behavior. However, I had to work rather hard to create it in my synthetic tests, so I would expect it to be uncommon.

2.3.1.1 Flash Cache Size Increment:

A fundamental problem with the above algorithm is that contains the hidden assumption that cache entries are relatively small in comparison to the cache itself. While I knew this assumption was not generally true when I developed the algorithm, I thought that cases where it failed would be so rare as to not be worth considering, as even if they did occur, the above algorithm would rectify the situation within an epoch or two.

While it is true that such occurances are rare, and it is true that the hit rate threshold cache size increment algorithm will rectify the situation eventually, the performance degradation experienced by users while waiting for the epoch to end was so extreme that some way of accelerating response to such situations was essential.

To understand the problem, consider the following use case:

Suppose we create a group, and then repeatedly create a new data set in the group, write some data to it and then close it.

In some versions of the HDF5 file format, the names of the datasets will be stored in a local heap associated with the group, and the space for that heap will be allocated in a single, contiguous chunk. When this local heap is full, we allocate a new chunk twice the size of the old, copy the data from the old local heap into the new, and discard the old local heap.

By default, the minimum metadata cache size is set to 2 MB. Thus in this use case, our hit rate will be fine as long as the local heap is no larger than a little less than 2 MB, as the group related metadata is accessed frequently and never evicted, and the data set related metadata is never accessed once the data set is closed, and thus is evicted smoothly to make room for new data sets.

All this changes abruptly when the local heap finally doubles in size to a value above the slightly less than 2 MB limit. All of a sudden, the local heap is the size of the metadata cache, and the cache must constantly swap it in to access it, and then swap it out to make room for other metadata.

The hit rate threshold based algorithm for increasing the cache size will fix this problem eventually, but performance will be very bad until it does, as the metadata cache will largely ineffective until its size is increase.

An obvious heuristic for addressing this "big rock in a small pond" issue is to watch for large "incoming rocks", and increase the size of the "pond" if the rock is so big that it will force most of the "water" out of the "pond".

The add space flash cache size increment algorithm algorithm applies this intuition directly:

Let x be either the size of a newly inserted entry, a newly loaded entry, or the number of bytes by which the size of an existing entry has been increased (i.e. the size of the "rock").

If x is greater than some user specified fraction of the current maximum cache size, increase the current maximum cache size by x times some user specified multiple, less any free space that was in the cache to begin with.

Further, to avoid confusing the other cache size increment/decrement code, start a new epoch.

At present, this algorithm pays no attention to any user specified limit on the maximum size of any single cache size increase, but it DOES stay within the user specified upper bound on the maximum cache size.

While it should be easy to see how this algorithm could be fooled into inactivity by large number of entries that were not quite large enough to cross the threshold, in practice it seems to work reasonably well.

Needless to say, I will revisit the issue should this cease to be the case.

2.3.2 Decreasing the Cache Size:

Identifying cases in which the maximum cache size is larger than necessary turned out to be more difficult.

2.3.2.1 Hit Rate Threshold Cache Size Reduction

One obvious heuristic is to monitor the hit rate and guess that we can safely decrease cache size if hit rate exceeds some user supplied threshold (say .99995).

The hit rate threshold size decrement algorithm implemented in the new metadata cache implements this intuition as follows:

At the end of each epoch (this is the same epoch that is used in the cache size increment algorithm), the hit rate is compared with the user specified threshold. If the hit rate exceeds that threshold, the current maximum cache size is decreased by a user specified factor. If required, the size of the reduction is clipped to stay within a user specified lower bound on the maximum cache size, and optionally, within a user specified maximum decrement.

In my synthetic tests, this algorithm works poorly. Even with a very high threshold and a small maximum reduction, it results in cache size oscillations. The size increment code typically increments maximum cache size above the working set size. This results in a high hit rate, which causes the threshold size decrement code to reduce the maximum cache size below the working set size, which causes hit rate to crash causing the cycle to repeat. The resulting average hit rate is poor.

It remains to be seen if this behavior will be seen in the field. The algorithm is available for use, but it wouldn't be my first choice. If you use it, please report back.

2.3.2.2 Ageout Cache Size Reduction:

Another heuristic for dealing with oversized cache conditions is to look for entries that haven't been accessed for a long time, evict them, and reduce the cache size accordingly.

The age out cache size reduction applies this intuition as follows: At the end of each epoch (again the same epoch as used in the cache size increment algorithm), all entries that haven't been accessed for a user configurable number of epochs (1 - 10 at present) are evicted. The maximum cache size is then reduced to equal the sum of the sizes of the remaining entries. The size of the reduction is clipped to stay within a user specified lower bound on maximum cache size, and optionally, within a user specified maximum decrement.

In addition, the user may specify a minimum fraction of the cache which must be empty before the cache size is reduced. Thus if an empty reserve of 0.1 was specified on a 10 MB cache, there would be no cache size reduction unless the eviction of aged out entries resulted in more than 1 MB of empty space. Further, even after the reduction, the cache would be one tenth empty.

In my synthetic tests, the age out algorithm works rather well, although it is somewhat sensitive to the epoch length and age out period selection.

2.3.2.3 Ageout With Hit Rate Threshold Cache Size Reduction:

To address these issues, I combined the hit rate threshold and age out heuristics.

Age out with threshold works just like age out, except that the algorithm is not run unless the hit rate exceeded a user specified threshold in the previous epoch.

In my synthetic tests, age out with threshold seems to work nicely, with no observed oscillation. Thus I have selected it as the default cache size reduction algorithm.

For those interested in such things, the age out algorithm is implemented by inserting a marker entry at the head of the LRU list at the beginning of each epoch. Entries that haven't been accessed for at least n epochs are simply entries that appear in the LRU list after the n-th marker at the end of an epoch.

2.4 Configuring the New Metadata Cache:

Due to lack of resources, the design work on the automatic cache size adjustment algorithms was done hastily, using primarily synthetic tests. I don't think I spent more than a couple weeks writing and running performance tests -- most time went into coding and functional testing.

As a result, while I think the algorithms provided for adaptive cache resizing will work well in actual use, I don't really know (although preliminary results from the field are promising). Fortunately, the issue shouldn't arise for the vast majority of HDF5 users, and those for whom it may arise should be savvy enough to recognize problems and deal with them.

For this latter class of users, I have implemented a number of new API calls allowing the user to select and configure the cache resize algorithms, or to turn them off and control cache size directly from the user program. There are also API calls that allow the user program to monitor hit rate and cache size.

From the user perspective, all the cache configuration data for a given file is contained in an instance of the H5AC_cache_config_t structure -- the definition of which is given below:

```
typedef struct H5AC_cache_config_t
    /* general configuration fields: */
   int
   hbool_t
                                rpt_fcn_enabled;
   hbool t
                                open_trace_file;
                                close_trace_file;
   hbool_t
    char
                                trace file name
                                  [H5AC__MAX_TRACE_FILE_NAME_LEN + 1];
                                evictions_enabled;
   hbool_t
   hbool_t
                                set_initial_size;
                                initial size;
    size t
    double
                                min_clean_fraction;
    size t
                                max_size;
    size_t
                                min_size;
    long int
                                epoch_length;
    /* size increase control fields: */
    enum H5C_cache_incr_mode incr_mode;
    double
                                lower_hr_threshold;
   double
                                increment;
   hbool_t
                                apply_max_increment;
    size_t
                                max increment;
    enum H5C_cache_flash_incr_mode flash_incr_mode;
   double
                               flash_multiple;
    double
                                flash_threshold;
```

```
/* size decrease control fields: */
   enum H5C_cache_decr_mode decr_mode;
   double
                                upper_hr_threshold;
   double
                                decrement;
   hbool t
                                apply_max_decrement;
   size_t
                                max_decrement;
   int
                                epochs_before_eviction;
   hbool_t
                                apply_empty_reserve;
   double
                                empty_reserve;
    /* parallel configuration fields: */
                                dirty_bytes_threshold;
    int
} H5AC_cache_config_t;
```

This structure is defined in H5ACpublic.h. Each field is discussed below and in the associated header comment.

The C API allows you get and set this structure directly. Unfortunately the Fortran API has to do this with individual parameters for each of the fields (with the exception of version).

While the API calls are discussed individually in the reference manual, the following high level discussion of what fields to change for different purposes should be useful.

2.4.1 General Configuration:

The version field is intended to allow THG to change the H5AC_cache_config_t structure without breaking old code. For now, this field should always be set to H5AC__CURR_CACHE_CONFIG_VERSION, even when you are getting the current configuration data from the cache. The library needs the version number to know where fields are located with reference to the supplied base address.

The rpt_fcn_enabled field is a boolean flag that allows you to turn on and off the resize reporting function that reports the activities of the adaptive cache resize code at the end of each epoch -- assuming that it is enabled.

The report function is unsupported, so you are on your own if you use it. Since it dumps status data to stdout, you should not attempt to use it with Windows unless you modify the source. You may find it useful if you want to experiment with different adaptive resize configurations. It is also a convenient way of diagnosing poor cache configuration. Finally, if you do lots of runs with identical behavior, you can use it to determine the metadata cache size needed in each phase of your program so you can set the required cache sizes manually.

The trace file fields are also unsupported. They allow one to open and close a trace file in which all calls to the metadata cache are logged in a user specified file for later analysis. The feature is intended primarily for THG use in debugging or optimizing the metadata cache in cases where users in the field observe obscure failures or poor performance that we cannot re-create in the lab. The trace file will allow us to re-create the exact sequence of cache operations that are triggering the problem.

At present we do not have a play back utility for trace files, although I imagine that we will write one quickly when and if we need it.

To enable the trace file, you load the full path of the desired trace file into trace_file_name, and set open_trace_file to TRUE. In the parallel case, an ASCII representation of the rank of each process is appended to the supplied trace file name to create a unique trace file name for that process.

To close an open trace file, set close_trace_file to TRUE.

It must be emphasized that you are on your own if you play with the trace file feature absent a request from THG. Needless to say, the trace file feature is disabled by default. If you enable it, you will take a large performance hit and generate huge trace files.

The evictions_enabled field is a boolean flag allowing the user to disable the eviction of entries from the metadata cache. Under normal operation conditions, this field will always be set to TRUE.

In rare circumstances, the raw data throughput requirements may be so high that the user wishes to postpone metadata writes so as to reserve I/O throughput for raw data. The evictions_enabled field exists to allow this -- although the user is to be warned that the metadata cache will grow without bound while evictions are disabled. Thus evictions should be re-enabled as soon as possible, and it may be wise to monitor cache size and statistics (to see how to enable statistics, see the debugging facilities section below).

Evictions may only be disabled when the automatic cache resize code is disabled as well. Thus to disable evictions, not only must the user set the evictions_enabled field to FALSE, but he must also set incr_mode to H5C_incr__off, set flash_incr_mode to H5C_flash_incr__off, and set decr_mode to H5C_decr__off.

To re-enable evictions, just set evictions_enabled back to TRUE.

Before passing on to other subjects, it is worth re-iterating that disabling evictions is an extreme step. Before attempting it, you might consider setting a large cache size manually, and flushing the cache just before high raw data throughput is required. This may yield the desired results without the risks inherent in disabling evictions.

The set_initial_size and initial_size fields allow you to specify an initial maximum cache size. If set_initial_size is TRUE, initial_size must lie in the interval [min_size, max_size] (see below for a discussion of the min_size and max_size fields).

If you disable the adaptive cache resizing code (done by setting incr_mode to H5C_incr__off, flash_incr_mode to H5C_flash_incr__off, and decr_mode to H5C_decr__off), you can use these fields to control maximum cache size manually, as the maximum cache size will remain at the initial size.

Note, that the maximum cache size is only modified when set_initial_size is TRUE. This allows the use of configurations specified at compile time to change resize configuration without altering the current maximum size of the cache. Without this feature, an additional call would be required to get the current maximum cache size so as to set the initial_size to the current maximum cache size, and thereby avoid changing it.

The min_clean_fraction sets the current minimum clean size as a fraction of the current max cache size. While this field was originally used only in the parallel version of the library, it now applies to the serial version as well. Its value must lie in the range [0.0, 1.0]. 0.01 is reasonable in the serial case, and 0.3 in the parallel.

A potential interaction, discovered at release 1.8.3, between the enforcement of the min_clean_fraction and the adaptive cache resize code can severely degrade performance. While this interaction is easily dealt in the serial case by setting min_clean_fraction to 0.01, the problem is more difficult in the parallel case. Please see the "Interactions" section below for further details.

The max_size and min_size fields specify the range of maximum sizes that may be set for the cache by the automatic resize code. min_size must be less than or equal to max_size, and both must lie in the range [H5C__MIN_MAX_CACHE_SIZE, H5C__MAX_MAX_CACHE_SIZE] -- currently [1 KB, 128 MB]. If you routinely run a cache size in the top half of this range, you should increase the hash table size. To do this, modify the H5C__HASH_TABLE_LEN #define in H5Cpkg.h and re-compile. At present, H5C__HASH_TABLE_LEN must be a power of two.

The epoch_length is the number of cache accesses between runs of the adaptive cache size control algorithms. It is ignored if these algorithms are turned off. It must lie in the range [H5C__MIN_AR_EPOCH_LENGTH, H5C__MAX_AR_EPOCH_LENGTH] -- currently [100, 1000000]. The above constants are defined in H5Cprivate.h. 50000 is a reasonable value.

2.4.2 Increment Configuration:

The incr_mode field specifies the cache size increment algorithm used. Its value must be a member of the H5C_cache_incr_mode enum type -- currently either H5C_incr__off or H5C_incr__threshold (note the double underscores after "incr"). This type is defined in H5Cpublic.h.

If incr_mode is set to H5C_incr__off, regular automatic cache size increases are disabled, and the lower_hr_threshold, increment, apply_max_increment, and max_increment fields are ignored.

The flash_incr_mode field specifies the flash cache size increment algorithm used. Its value must be a member of the H5C_cache_flash_incr_mode enum type -- currently either H5C_flash_incr__off or H5C_flash_incr__add_space (note the double underscores after "incr"). This type is defined in H5Cpublic.h.

If flash_incr_mode is set to H5C_flash_incr__off, flash cache size increases are disabled, and the flash_multiple, and flash_threshold, fields are ignored.

2.4.2.1 Hit Rate Threshold Cache Size Increase Configuration:

If incr_mode is H5C_incr__threshold, the cache size is increased via the hit rate threshold algorithm. The remaining fields in the section are then used as follows:

lower_hr_threshold is the threshold below which the hit rate must fall to trigger an increase. The value must lie in the range [0.0 - 1.0]. In my tests, a relatively high value seems to work best -- 0.9 for example.

increment is the factor by which the old maximum cache size is multiplied to obtain an initial new maximum cache size when an increment is needed. The actual change in size may be smaller as required by max_size (above) and max_increment (discussed below). increment must be greater than or equal to 1.0. If you set it to 1.0, you will effectively turn off the increment code. 2.0 is a reasonable value.

apply_max_increment and max_increment allow the user to specify a maximum increment. If apply_max_increment is TRUE, the cache size will never be increased by more than the number of bytes specified in max_increment in any single increase.

2.4.2.1 Flash Cache Size Increase Configuration:

If flash_incr_mode is set to H5C_flash_incr__add_space, flash cache size increases are enabled. The size of the cache will be increased under the following circumstances:

Let t be the current maximum cache size times the value of the flash_threshold field.

Let x be either the size of the newly inserted entry, the size of the newly loaded entry, or the number of bytes added to the size of the entry under consideration for triggering a flash cache size increase.

If t < x, the basic condition for a flash cache size increase is met, and we proceed as follows:

Let space_needed equal x less the amount of free space in the cache.

Further, let increment equal space_needed times the value of the flash_multiple field. If increment plus the current cache size is greater than max_size (discussed above), reduce increment so that increment plus the current cache size is equal to max_size.

If increment is greater than zero, increase the current cache size by increment. To avoid confusing the other cache size increment or decrement algorithms, start a new epoch. Note however, that we do not cycle the epoch markers if some variant of the age out algorithm is in use.

The use of the flash_threshold field is discussed above. It must be a floating point value in the range of [0.1, 1.0]. 0.25 is a reasonable value.

The use of the flash_multiple field is also discussed above. It must be a floating point value in the range of [0.1, 10.0]. 1.4 is a reasonable value.

2.4.3 Decrement Configuration:

The decr_mode field specifies the cache size decrement algorithm used. Its value must be a member of the H5C_cache_decr_mode enum type -- currently either H5C_decr__off, H5C_decr__threshold, H5C_decr__age_out, or H5C_decr__age_out_with_threshold (note the double underscores after "decr"). This type is defined in H5Cpublic.h.

If decr_mode is set to H5C_decr__off, automatic cache size decreases are disabled, and the remaining fields in the cache size decrease control section are ignored.

2.4.3.1 Hit Rate Threshold Cache Size Decrease Configuration:

if decr_mode is H5C_decr__threshold, the cache size is decreased by the threshold algorithm, and the remaining fields of the decrement section are used as follows:

upper_hr_threshold is the threshold above which the hit rate must rise to trigger cache size reduction. It must be in the range [0.0, 1.0]. In my synthetic tests, very high values like .9995 or .99995 seemed to work best.

decrement is the factor by which the current maximum cache size is multiplied to obtain a tentative new maximum cache size. It must lie in the range [0.0, 1.0]. Relatively large values like .9 seem to work best in my synthetic tests. Note that the actual size reduction may be smaller as required by min_size and max_decrement (discussed below).

apply_max_decrement and max_decrement allow the user to specify a maximum decrement. If apply_max_decrement is TRUE, cache size will never be reduced by more than max_decrement bytes in any single reduction.

With the hit rate threshold cache size decrement algorithm, the remaining fields in the section are ignored.

2.4.3.2 Ageout Cache Size Reduction:

If decr_mode is H5C_decr__age_out the cache size is decreased by the ageout algorithm, and the remaining fields of the decrement section are used as follows:

epochs_before_eviction is the number of epochs an entry must reside unaccessed in the cache before it is evicted. This value must lie in the range [1, H5C__MAX_EPOCH_MARKERS]. H5C__MAX_EPOCH_MARKERS is defined in H5Cprivate.h, and is currently set to 10.

apply_max_decrement and max_decrement are used as in section 2.4.3.1.

apply_empty_reserve and empty_reserve allow the user to specify a minimum empty reserve as discussed in section 2.3.2.2. An empty reserve of 0.05 or 0.1 seems to work well.

The decrement and upper_hr_threshold fields are ignored in this case.

2.4.3.3 Ageout With Hit Rate Threshold Cache Size Reduction:

If decr_mode is H5C_decr__age_out_with_threshold, the cache size is decreased by the ageout with hit rate threshold algorithm, and the fields of decrement section are used as per the Ageout algorithm (see 5.3.2) with the exception of upper_hr_threshold.

Here, upper_hr_threshold is the threshold above which the hit rate must rise to trigger cache size reduction. It must be in the range [0.0, 1.0]. In my synthetic tests, high values like .999 seemed to work well.

2.4.4 Parallel Configuration

This section is a catch-all for parallel specific configuration data. At present, it has only one field -- dirty_bytes_threshold.

In PHDF5, all operations that modify metadata must be executed collectively. We used to think that this was enough to ensure consistency across the metadata caches, but since we allow processes to read metadata individually, the order of dirty entries in the LRU list can vary across processes. This in turn can change the order in which dirty metadata cache entries reach the bottom of the LRU and are flushed to disk -- opening the door to messages from the past and messages from the future bugs.

To prevent this, only the metadata cache on process 0 of the file communicator is allowed to write to file, and then only after entering a sync point with the other caches. After it writes entries to file, it sends the base addresses of the now clean entries to the other caches, so they can mark these entries clean as well, and then leaves the sync point. The other caches mark the specified entries as clean before they leave the synch point as well. (Observe, that since all caches see the same stream of dirty metadata, they will all have the same set of dirty entries upon sync point entry and exit.)

The different caches know when to synchronize by counting the number of bytes of dirty metadata created by the collective operations modifying metadata. Whenever this count exceeds the value specified in the

dirty_bytes_threshold, they all enter the sync point, and process 0 flushes down to its minimum clean size and sends the list of newly cleaned entries to the other caches.

Needless to say, the value of the dirty_bytes_threshold field must be consistent across all the caches operating on a given file.

All dirty metadata can also by flushed under programatic control via the H5Fflush() call. This call must be collective, and will reset the dirty data counts on each metadata cache.

Absent calls to H5Fflush(), dirty metadata will only be flushed when the dirty_bytes_threshold is exceeded, and then only down to the min_clean_fraction. Thus, if a program does all its metadata modifications in one phase, and then doesn't modify metadata thereafter, a residue of dirty metadata will be frozen in the metadata caches for the remainder of the computation -- effectively reducing the sizes of the caches.

In the default configuration, the caches will eventually resize themselves to maintain an acceptable hit rate. However, this will take time, and it will increase the applications footprint in memory.

If your application behaves in this manner, you can avoid this by a collective call to H5Fflush() immediately after the metadata modification phase.

2.4.5 Interactions:

Evictions may not be disabled unless the automatic cache resize code is disabled as well (by setting decr_mode to H5C_decr__off, flash_decr_mode to H5C_flash_incr__add_space, and incr_mode to H5C_incr__off) -- thus placing the cache size under the direct control of the user program.

There is no logical necessity for this restriction. It is imposed because it simplifies testing greatly, and because I can't see any reason why one would want to disable evictions while the automatic cache size adjustment code was enabled. This restriction can be relaxed if anyone can come up with a good reason to do so.

At present there are two interactions between the increment and decrement sections of the configuration.

If incr_mode is H5C_incr__threshold, and decr_mode is either H5C_decr__threshold or H5C_decr__age_out_with_threshold, then lower_hr_threshold must be strictly less than upper_hr_threshold.

Also, if the flash cache size increment code is enabled and is triggered, it will restart the current epoch without calling any other cache size increment or decrement code.

In both the serial and parallel cases, there is the potential for an interaction between the min_clean_fraction and the cache size increment code that can severly degrade performance. Specifically, if the min_clean_fraction is large enough, it is possible that keeping the specified fraction of the cache clean may generate enough flushes to seriously degrade performance even though the hit rate is excellent.

In the serial case, this is easily dealt with by selecting a very small min_clean_fraction -- 0.01 for example -- as this still avoids the "metadata blizzard" phenomenon that appears when the cache fills with dirty metadata and must then flush all of it before evicting an entry to make space for a new entry.

The problem is more difficult in the parallel case, as the min_clean_fraction is used ensure that the cache contains clean entries that can be evicted to make space for new entries when metadata writes are forbidden -- i.e. between sync points.

This issue was discovered shortly before release 1.8.3 and an automated solution has not been implemented. Should it become an issue for an application, try manually setting the cache size to ~1.5 times the maximum working set size for the application, and leave min_clean_fraction set to 0.3.

You can approximate the working set size of your application via repeated calls to H5Fget_mdc_size() and H5Fget_mdc_hit_rate() while running your program with the cache resize code enabled. The maximum value returned by H5Fget_mdc_size() should be a reasonable approximation -- particularly if the associated hit rate is good.

In the parallel case, there is also an interaction between min_clean_fraction and dirty_bytes_threshold. Absent calls to H5Fflush() (discussed above), the upper bound on the amount of dirty data in the metadata caches will oscillate between (1 - min_clean_fraction) times current maximum cache size, and that value plus the dirty_bytes_threshold. Needless to say, it will be best if the min_size, min_clean_fraction, and the dirty_bytes_threshold are chosen so that the cache can't fill with dirty data.

2.4.6 Default Metadata Cache Configuration:

Starting with release 1.8.3, HDF5 provides different default metadata cache configurations depending on whether the library is compiled for serial or parallel.

The default configuration for the serial case is as follows:

```
version
/* int
                                                    = */ H5C__CURR_AUTO_SIZE_CTL_VER,
= */ FALSE,
/* enum H5C_cache_incr_mode incr_mode = */ H5C_incr__threshold,
/* double lower_hr_threshold = */ 0.9,
/* double increment = */ 2.0,
/* hbool_t apply_max_increment = */ TRUE,
/* size_t max_increment = */ (4 *
/* enum H5C_cache_flash_incr_mode */
                                                   = */ (4 * 1024 * 1024),
/* flash_incr_mode = */ H5C_f
/* double flash_multiple = */ 1.4,
/* double flash_threshold = */ 0.25,
                             flash_incr_mode = */ H5C_flash_incr__add_space,
/* enum H5C_cache_decr_mode decr_mode = */ H5C_decr__age_out_with_threshold,
/* double upper_hr_threshold = */ 0.999,
                                                   = */ 0.9,
/* double
                  decrement
/* hbool_t apply_max_decrement = */ TRUE,
/* size_t max_decrement = */ (1 * 1024 * 1024),
/* int epochs_before_eviction = */ 3,
/* hbool_t apply_empty_reserve = */ TRUE,
/* double empty_reserve = */ 0.1,
/* int dirty_bytes_threshold = */ (256 * 1024)
                    dirty_bytes_threshold = */ (256 * 1024)
```

The default configuration for the parallel case is as follows:

The default serial configuration should be adequate for most serial HDF5 users.

The same may not be true for the default parallel configuration due the interaction between the min_clean_fraction and the cache size increase code. See the "Interactions" section for further details.

Should you need to change the default configuration, it can be found in H5ACprivate.h. Look for the definition of H5AC DEFAULT RESIZE CONFIG.

2.5 Controlling the New Metadata Cache Size From Your Program:

You have already seen how H5AC_cache_config_t has facilities that allow you to control the metadata cache size directly. Use H5Fget_mdc_config() and H5Fset_mdc_config() to get and set the metadata cache configuration on an open file. Use H5Pget_mdc_config() and H5Pset_mdc_config() to get and set the initial metadata cache configuration in a file access property list. Recall that this list contains configuration data used when opening a file.

Use H5Fget_mdc_hit_rate() to get the average hit rate since the last time the hit rate stats were reset. This happens automatically at the beginning of each epoch if the adaptive cache resize code is enabled. You can also do it manually with H5Freset_mdc_hit_rate_stats(). Be careful about doing this if the adaptive cache resize code is enabled, as you may confuse it.

Use H5Fget_mdc_size() to get metadata cache size data on an open file.

Finally, note that cache size and cache footprint are two different things -- in my tests, the cache footprint (as inferred from the UNIX top command) is typically about three times the maximum cache size. I haven't tracked it down yet, but I would guess that most of this is due to the very small typical cache entry size combined with the rather large size of cache entry header structure. This should be investigated further, but there are other matters of higher priority.

2.6 New Metadata Cache Debugging Facilities:

The new metadata cache has a variety of debugging facilities that may be of use. I doubt that any other than the report function and the trace file will ever be accessible via the API, but they are relatively easy to turn on in the source code.

Note that none of this should be viewed as supported -- it is described here on the off chance that you want to use it, but you are on your own if you do. Also, there are no promises as to consistency between versions.

As mentioned above, you can use the rpt_fcn_enabled field of the configuration structure to enable the default reporting function (H5C_def_auto_resize_rpt_fcn() in H5C.c). If this function doesn't work for you, you will have to write your own. In particular, remember that it uses stdout, so it will probably be unhappy under Windows.

Again, remember that this facility is not supported. Further, it is likely to change every time I do any serious work on the cache.

There is also extensive statistics collection code. Use H5C_COLLECT_CACHE_STATS and H5C_COLLECT_CACHE_ENTRY_STATS in H5Cprivate.h to turn this on. If you also turn on H5AC_DUMP_STATS_ON_CLOSE in H5ACprivate.h, stats will be dumped when you close a file. Alternatively you can call H5C_stats() and H5C_stats__reset() within the library to dump and reset stats. Both of these functions are defined in H5C.c.

Finally, the cache also contains extensive sanity checking code. Much of this is turned on when you compile in debug mode, but to enable the full suite, turn on H5C_DO_SANITY_CHECKS in H5Cprivate.h

2.7 Trouble Shooting

Absent major bugs in the cache, the only trouble shooting you should have to do is diagnosing and fixing problems with your cache configuration.

Assuming it runs on your platform (I've only used it under Linux), the reporting function is probably the most convenient diagnosis tool. However, since it is unsupported code, I will not discuss it further beyond directing you to the source (H5C_def_auto_resize_rpt_fcn() in H5C.c).

Absent the reporting function, regular calls to H5Fget_mdc_hit_rate() should give you a good idea of hit rate over time. Remember that the hit rate stats are reset at the end of each epoch (when adaptive cache resizing is enabled), so you should expect some jitter.

Similar calls to H5Fget_mdc_size() should allow you to monitor cache size, and the fraction of the current maximum cache size that is actually in use.

If the hit rate is consistently low, and the cache it at its current maximum size, increasing the maximum size is an obvious fix.

If you see hit rate and cache size oscillations, try disabling adaptive cache resizing and setting a fixed cache size a bit greater than the high end of the cache size oscillations you observed.

If the hit rate oscillations don't go away, you are probably looking at a feature of your application which can't be helped without major changes to the cache. Please send along a description of the situation.

If the oscillations do go away, you may be able to come up with a configuration that deals with the situation. If that fails, control cache size manually, and write me, so I can try to develop an adaptive resize algorithm that works in your case.

Needless to say, you should give the cache a few epochs to adapt to circumstances. If that is too slow for you, try manual cache size control.

If you find it necessary to disable evictions, you may find it useful to enable the internal statistics collection code mentioned above in the section on debugging facilities.

Amongst many other other things, the stats code will report the maximum cache size, and the average successful and unsuccessful search depths in the hash table. If these latter figures are significantly above 1, you should increase the size of the hash table.

HDF5 Glossary

atomic datatype file access mode attribute group chunked layout member chunking root group compound datatype hard link contiguous layout hyperslab dataset identifier dataspace link datatype hard atomic soft

compound member enumeration name

named named datatype opaque opaque datatype

variable-length path

enumeration datatype property list
file data transfer
group dataset access
path dataset creation
root group file access
super block file creation

root group selection hyperslab serialization soft link storage layout chunked chunking contiguous super block

variable-length datatype

atomic datatype

A datatype which cannot be decomposed into smaller units at the API level.

attribute

A small dataset that can be used to describe the nature and/or the intended usage of the object it is attached to.

chunked lavout

The storage layout of a chunked dataset.

chunking

A storage layout where a dataset is partitioned into fixed-size multi-dimensional chunks. Chunking tends to improve performance and facilitates dataset extensibility.

compound datatype

A collection of one or more atomic types or small arrays of such types. Similar to a struct in C or a common block in Fortran.

contiguous layout

The storage layout of a dataset that is not chunked, so that the entire data portion of the dataset is stored in a single contiguous block.

data transfer property list

The data transfer property list is used to control various aspects of the I/O, such as caching hints or collective I/O information.

dataset

A multi-dimensional array of data elements, together with supporting metadata.

dataset access property list

A property list containing information on how a dataset is to be accessed.

dataset creation property list

A property list containing information on how raw data is organized on disk and how the raw data is compressed.

dataspace

An object that describes the dimensionality of the data array. A dataspace is either a regular N-dimensional array of data points, called a simple dataspace, or a more general collection of data points organized in another manner, called a complex dataspace.

datatype

An object that describes the storage format of the individual data points of a data set. There are two categories of datatypes: atomic and compound datatypes. An atomic type is a type which cannot be decomposed into smaller units at the API level. A compound datatype is a collection of one or more atomic types or small arrays of such types.

enumeration datatype

A one-to-one mapping between a set of symbols and a set of integer values, and an order is imposed on the symbols by their integer values. The symbols are passed between the application and library as character strings and all the values for a particular enumeration datatype are of the same integer type, which is not necessarily a native type.

file

A container for storing grouped collections of multi-dimensional arrays containing scientific data.

file access mode

Determines whether an existing file will be overwritten, opened for read-only access, or opened for read/write access. All newly created files are opened for both reading and writing.

file access property list

File access property lists are used to control different methods of performing I/O on files:

file creation property list

The property list used to control file metadata.

group

A structure containing zero or more HDF5 objects, together with supporting metadata. The two primary HDF5 objects are datasets and groups.

hard link

A direct association between a name and the object where both exist in a single HDF5 address space.

hyperslab

A portion of a dataset. A hyperslab selection can be a logically contiguous collection of points in a dataspace or a regular pattern of points or blocks in a dataspace.

identifier

A unique entity provided by the HDF5 library and used to access an HDF5 object, such as a file, goup, dataset, datatype, etc.

link

An association between a name and the object in an HDF5 file group.

member

A group or dataset that is in another dataset, dataset A, is a member of dataset A.

name

A slash-separated list of components that uniquely identifies an element of an HDF5 file. A name begins that begins with a slash is an absolute name which is accessed beginning with the root group of the file; all other names are relative names and the associated objects are accessed beginning with the current or specified group.

named datatype

A datatype that is named and stored in a file. Naming is permanent; a datatype cannot be changed after being named.

opaque datatype

A mechanism for describing data which cannot be otherwise described by HDF5. The only properties associated with opaque types are a size in bytes and an ASCII tag.

path

The slash-separated list of components that forms the name uniquely identifying an element of an HDF5 file.

property list

A collection of name/value pairs that can be passed to other HDF5 functions to control features that are typically unimportant or whose default values are usually used.

root group

The group that is the entry point to the group graph in an HDF5 file. Every HDF5 file has exactly one root group.

selection

(1) A subset of a dataset or a dataspace, up to the entire dataset or dataspace. (2) The elements of an array or dataset that are marked for I/O.

serialization

The flattening of an *N*-dimensional data object into a 1-dimensional object so that, for example, the data object can be transmitted over the network as a 1-dimensional bitstream.

soft link

An indirect association between a name and an object in an HDF5 file group.

storage layout

The manner in which a dataset is stored, either contiguous or chunked, in the HDF5 file.

super block

A block of data containing the information required to portably access HDF5 files on multiple platforms, followed by information about the groups and datasets in the file. The super block contains information about the size of offsets, lengths of objects, the number of entries in group tables, and additional version information for the file.

variable-length datatype

A sequence of an existing datatype (atomic, variable-length (VL), or compound) which are not fixed in length from one dataset location to another.