## **HDF5 DAOS VOL Connector User's Guide**

Neil Fortner, Jordan Henderson, Jerome Soumagne

This document aims to be a helpful guide on how to use the HDF5 DAOS VOL connector to leverage the capabilities of the DAOS object storage system within an HDF5 application.



# **Revision History**

Version Number	Date	Comments	
v0.1	Mar. 29, 2019	First draft.	
v0.2	Apr. 24, 2019	Second draft.	
v0.3	Aug. 27, 2019	Third draft.	
v0.4	Oct. 25, 2019	Fourth draft.	
v0.5	Nov. 1, 2019	Fifth draft.	
v0.6	Dec. 2, 2019	Sixth draft.	
v1.0	Dec. 16, 2019	Initial release of DAOS VOL connector.	
v1.1	Jan. 21, 2021	Updated release of DAOS VOL connector.	



## **Contents**

Lis	st of F	-igures		5
Αc	ronyı	ms		6
GI	ossaı	y		6
1.	Ove	rview		7
2.	Usin	a the C	DAOS VOL connector within an HDF5 application	8
	2.1.	_	ng the HDF5 DAOS VOL connector	8
	2.2.		the HDF5 DAOS VOL connector with applications	9
		_	Locating and loading HDF5 plugins at runtime	10
		2.2.2.	Using the HDF5_VOL_CONNECTOR environment variable	10
		2.2.3.	Using H5Pset_vol()	10
		2.2.4.	Using H5Pset_daos_vol()	10
		2.2.5.	Skeleton Example	11
	2.3.	Asyncl	hronous I/O	11
		2.3.1.	Implementation and making progress	12
		2.3.2.	Consistency semantics	12
		2.3.3.	Operation ordering	13
		2.3.4.	Parallel Considerations	14
		2.3.5.	Operation Scope	14
		2.3.6.	Asynchronous Example Program	14
	2.4.	Buildin	ng HDF5 DAOS VOL connector applications	15
		2.4.1.	Without the DAOS VOL connector as a dynamically-loaded plugin	15
	2.5.	Runnir	ng HDF5 DAOS VOL connector applications	16
		2.5.1.	Starting the DAOS Server	16
		2.5.2.	With the DAOS VOL connector as a dynamically-loaded plugin	16
		2.5.3.	Without the connector as a dynamically-loaded plugin	16
		2.5.4.	Example Applications	16
2	HDE	5 ADI S	Support	18
Ο.			e Specific Support	18
	3.1.		Attribute Features	18
			Dataset Features	19
		3.1.3.	File Features	22
		3.1.4.	Group Features	24
	3.2.		pecific Support	25
	0.2.	3.2.1.	H5A interface	26
		3.2.2.	H5D interface	29
		3.2.3.	H5F interface	31
		3.2.4.	H5G interface	32
		3.2.5.	H5L interface	34
		3.2.6.	H5M interface	37



		3.2.7. H5O interface       3         3.2.8. H5R interface       4         3.2.9. H5T interface       4	0
	3.3.		2
		3.3.1. Limitations in regards to DAOS	2
4.	Test	ing the DAOS VOL connector 4	3
	4.1.	With CTest	3
	4.2.	Manually	3
	4.3.	DAOS VOL connector's testing components	3
		4.3.1. Generic HDF5 VOL connector test suite	3
		4.3.2. DAOS VOL connector-specific test suite	3
Α.	Refe	rence Manual 4	5
		H5daos_init	.5
			6
		H5Pset_fapl_daos	7
		*	8
		*	9
R	Nati	ve HDF5 VOL connector-specific API calls 5	n
٥.			0
			0
		H5F interface	-
			2
			2
		H50 interface	_
		H5R interface	
			3



# **List of Figures**

1.	DAOS within Virtual Object Layer. All of the HDF5 I/O related calls are routed to the DAOS	
	VOL.connector	-



## **Acronyms**

**DAOS** Distributed Asynchronous Object Storage. 5, 7–11, 15–18, 25, 42–44, 50

**HDF5** Hierarchical Data Format, v5. 5, 7–10, 15–18, 25, 42–44

**VOL** Virtual Object Layer. 5, 7–11, 15–18, 25, 42–44, 50

## **Glossary**

**connector** A VOL connector is a thin layer between HDF5 and the storage. It translates HDF5 VOL storage related calls into actual storage operations.. 5, 7–11, 15–18, 25, 42–44, 50



## 1. Overview




Figure 1 – DAOS within Virtual Object Layer. All of the HDF5 I/O related calls are routed to the DAOS VOL connector.

## 2. Using the DAOS VOL connector within an HDF5 application

This section outlines the unique aspects of writing, building and running HDF5 applications with the DAOS VOL connector.

### 2.1. Building the HDF5 DAOS VOL connector

The following is a quick set of instructions for building the DAOS VOL connector connector. Note that these instructions are not comprehensive and may be subject to change in future releases; please refer to the DAOS VOL connector's README file for the most up to date instructions.

The DAOS VOL connector is built using CMake. CMake version 2.8.12.2 or greater is required to build the connector itself, but version 3.1 or greater is required to build the connector's tests. To build the connector, one should create a build directory within the source tree:

```
cd daos-vol
mkdir build
cd build
```

After that, if all of the required components (DAOS, MPI and HDF5) are located within the system path, building the connector should be as simple as running the following two commands to have CMake generate the build files for make to use.

```
ccmake ..
make && make install
```

Some notable CMake variables are listed below. These can be used to control the build process and can be supplied to the cmake command by prepending them with -D or turned on in ccmake. Some of the connector-specific options may be needed if the required components mentioned previously cannot be found within the system path.

CMake-specific options:

- CMAKE\_INSTALL\_PREFIX This variable controls the install directory that the resulting output files are written to.
- CMAKE\_BUILD\_TYPE This variable controls the type of build used for the VOL connector. Valid values are Release, Debug, RelWithDebInfo and MinSizeRel. (*Default: RelWithDebInfo*)

DAOS VOL connector-specific options:

- BUILD\_TESTING This variable is used to enable/disable building of the DAOS VOL connector's tests.
- BUILD\_EXAMPLES This variable is used to enable/disable building of the DAOS VOL connector's HDF5 examples.
- DAOS\_LIBRARY This variable controls the DAOS library used by the VOL connector build process. It should be set to the full path to the DAOS library, including the library's name (e.g., /path/libdaos.so).



■ DAOS\_UNS\_LIBRARY — This option controls the DAOS unified namespace library used by the VOL connector build process. It should be set to the full path to the DAOS UNS library, including the library's name (e.g., /path/libduns.so).

- DAOS\_INCLUDE\_DIR This variable controls the DAOS include directory used by the VOL connector build process.
- MPI\_C\_COMPILER This variable controls the MPI C Compiler used by the VOL connector build process. It should be set to the full path to the MPI C Compiler, including the name of the executable.
- HDF5\_C\_COMPILER\_EXECUTABLE This variable controls the HDF5 compiler wrapper script used by the VOL connector build process. It should be set to the full path to the HDF5 compiler wrapper, including the name of the wrapper script. The following two variables may also need to be set.
- HDF5\_C\_LIBRARY\_hdf5 This variable controls the HDF5 library used by the VOL connector build process. It should be set to the full path to the HDF5 library, including the library's name (e.g., /path/libhdf5.so). Used in conjunction with the HDF5\_C\_INCLUDE\_DIR variable.
- HDF5\_C\_INCLUDE\_DIR This variable controls the HDF5 include directory used by the VOL connector build process. Used in conjunction with the HDF5\_C\_LIBRARY\_hdf5 variable.

### 2.2. Using the HDF5 DAOS VOL connector with applications

There are currently three ways to tell an HDF5 application to use the DAOS VOL connector:

- 1. The HDF5\_VOL\_CONNECTOR environment variable
- 2. H5Pset\_vol(), an HDF5 API call
- 3. H5Pset\_fapl\_daos(), a DAOS VOL connector API call

Which option to choose will depend on things like the ability to modify the application's source code, whether dynamically loading plugins is an option, etc.

The environment variable is useful when the application either cannot or does not need to be modified to use DAOS storage (e.g., the application makes no native-specific HDF5 API calls). It is also the easiest to use as it requires very little setup and no changes to the application's source code. It is probably not going to be suitable, however, if the application needs to perform I/O with multiple connectors. For example, reading from DAOS and writing to the native VOL connector would be a problem. In the HDF5 command-line tools, this difficulty is solved by using command-line parameters and explicitly specifying a connector via <code>H5Pset\_vol()</code>.

Using H5Pset\_vol() requires modification of the application's source code, which may not be possible. It is more flexible, however, and allows an application to be configured to use VOL connectors in arbitrary ways. Since it is an HDF5 API call, it isn't necessary to link to the DAOS VOL connector, which can be loaded as a plugin in the same way as using the environment variable, described above.

H5Pset\_fapl\_daos() will give the application more control over how DAOS is initialized, but it requires linking to the DAOS VOL connector and modification of the application's source code.

Each of these ways of specifying and loading the DAOS VOL connector is fundamentally equivalent in terms of its eventual effects. There's no performance or functionality changes between them.



#### 2.2.1. Locating and loading HDF5 plugins at runtime

HDF5 plugins are discovered at runtime by searching in specified plugin paths. There is a library default plugin path (usually /usr/local/hdf5/lib/plugin on POSIX systems) but this can be overridden using the HDF5\_PLUGIN\_PATH environment variable (and/or manipulated via the various HDF5 H5PL API calls for more complicated situations where the application's source code can be modified).

When the HDF5 library is asked to use a plugin it doesn't currently have loaded, it searches the plugin path(s), attempting to load any plugins it finds to see if their name or connector value match.

#### 2.2.2. Using the HDF5\_VOL\_CONNECTOR environment variable

Set the HDF5\_VOL\_CONNECTOR environment variable to "daos" (case-sensitive) and make sure the DAOS VOL connector plugin is discoverable, as described above.

#### 2.2.3. Using H5Pset\_vol()

The first thing that must be done is load the DAOS VOL connector plugin via H5VL\_register\_connector\_by\_(value|name) (). This will load the plugin and assign it a hid\_t connector ID. This ID is then passed as the VOL connector ID when you call H5Pset\_vol() on the file access property list that will be used to open the file.

The DAOS VOL connector value is currently 4004. This is documented in the connector's public header. Note that the connector value is unrelated to the hid\_t library ID obtained from the registration API call.

#### 2.2.4. Using H5Pset\_daos\_vol()

If dynamic loading of the DAOS VOL connector is not used, any HDF5 application using the connector must:

- 1. Include daos\_vol\_public.h, found in the include directory of the DAOS VOL connector installation directory.
- 2. Link against libhdf5\_vol\_daos.so (or similar), found in the lib directory of the DAOS VOL connector installation directory, and against libuuid.so (or similar) in order to use UUIDs. Note that dependencies can alternatively be retrieved through CMake or pkg-config.

An HDF5 DAOS VOL connector application also requires in that particular case three new function calls in addition to those for an equivalent HDF5 application (see Appendix A for more details):

- H5daos\_init() Initializes the DAOS VOL connector
   Called upon application startup, before any file is accessed.
- H5Pset\_fapl\_daos () Sets DAOS VOL connector access on File Access Property List.
  - Called to prepare a FAPL to open a file through the DAOS VOL connector. See HDF5 File Access Property Lists for more information about File Access Property Lists.
- H5daos\_term() Cleanly shutdowns the DAOS VOL connector Called on application shutdown, after all files have been closed.



#### 2.2.5. Skeleton Example

Below is a no-op application that opens and closes a file using the DAOS VOL connector. For clarity, no error-checking is performed. Note that this example is meant only for the case when the DAOS VOL connector is not being dynamically loaded.

```
#include "hdf5.h"
#include "daos_vol_public.h"
int main(void)
    uuid_t pool_uuid;
   hid_t fapl_id, file_id;
    /* Parse the pool UUID. */
    uuid_parse("fce30f79-b34b-46c1-9b1f-bb52d99dacca", pool_uuid);
    /* Initialize DAOS VOL connector using the above parsed UUID for
     * the pool UUID, "daos_server" as the group name for the DAOS
     * servers managing the pool and simply rank 0 as the only rank
     * in the pool service list. */
    H5daos_init(pool_uuid, "daos_server", "0");
    fapl_id = H5Pcreate(H5P_FILE_ACCESS);
    H5Pset_fapl_daos(fapl_id, MPI_COMM_WORLD, MPI_INFO_NULL);
    /* Currently required for the DAOS VOL connector, set all metadata
     * operations to be collective */
    H5Pset_all_coll_metadata_ops(fapl_id, true);
    file_id = H5Fopen("my_file.h5", H5F_ACC_RDWR, fapl_id);
    /* Operate on file */
    [...]
    H5Pclose(fapl_id);
    H5Fclose(file_id);
    /* Terminate the DAOS VOL connector. */
    H5daos_term();
    return 0;
}
```

### 2.3. Asynchronous I/O

The DAOS VOL connector supports asynchronous HDF5 operations using the HDF5 event set (H5ES) API, released in HDF5 1.13.0. This allows I/O to proceed in the background while the application is performing other tasks. Documentation on the H5ES API can be found in the HDF5 Application Developer's Guide and the HDF5 Reference Manual.



#### 2.3.1. Implementation and making progress

Asynchronous I/O in the DAOS VOL connector is implemented using a threadless progress engine, that checks for completion of in-flight operations any time it is entered. This means there is no background thread making progress, so you can be certain it won't interfere with computation. However, this also means that the connector needs to be entered occasionally in order to make progress, by calling H5ESwait() with a timeout of 0. Otherwise, asynchronous operations will never complete until waited on, and the wait may take a long time, no matter how much time has passed since the asynchronous operation was issued.

Each HDF5 operation is split up into multiple internal tasks which may need to be executed in a certain order. For example,s a group create needs to create a link in the parent group, write the metadata to the new group, and possibly adjust the number of links in the parent group and allocate an object ID for the new group. The DAOS VOL connector uses the DAOS Thread Scheduling Engine (tse) to track dependencies between these internal tasks and make progress on them, together with custom code written to make progress on asynchronous MPI operations needed for collective parallel operations.

#### 2.3.2. Consistency semantics

Similarly to other asynchronous I/O libraries, the application must be careful not to use, modify, or free any buffers in use by async tasks until those tasks are complete. This applies to all read and query operations, as well as raw data and attribute write operations. For non-attribute metadata write operations, the connector will make a temporary copy of any buffers passed in.

The application must also be careful not to assume write operations are visible in the file until it has verified that the operation has completed through the H5ES interface. For example, if you write to a dataset, you must wait for the write to complete before reading that data from the dataset if you wish to see the new data. Likewise, if you create a link, you must wait for the create to complete before reading that link.

It is possible in some cases, however, to issue operations before prerequisites have been complete. Any ID returned from the API can be passed back in through the HDF5 API even if the open operation for the object that that ID refers to has not completed. This allows applications to, for example, create a file, create a group in the file, create a dataset in the group, write to the dataset, and close all IDs, all in a non-blocking manner without waiting (until the dataset write buffer needs to be modified or freed). Until the open operation is complete, you can only access the object through its ID, so you cannot, for example, create a group then create an object inside that group using a path that includes the group name, without waiting for the first create to complete (or using H50flush\_async() or H5Fflush\_async(), see below).

As an example, this series of calls is legal:

```
group_id = H5Gcreate_async(file_id, "parent", ..., es_id);
dset_id = H5Dcreate_async(group_id, "dset", ..., es_id);
H5Dwrite_async(dset_id, ..., es_id);
...
H5ESwait(es_id);
```

Note that H5Dcreate\_async() is called before we know H5Gcreate\_async() has completed, as with H5Dwrite\_async() and H5Dcreate\_async(). However, this example is illegal and may result in errors:



```
group_id = H5Gcreate_async(file_id, "parent", ..., es_id);
dset_id = H5Dcreate_async(file_id, "parent/dset", ..., es_id); //may fail
```

The only difference between the traditional blocking HDF5 API calls and the async versions is that, in the blocking versions, the connector waits for that operation to complete before returning. Therefore, when mixing synchronous and asynchronous calls, the application must still obey the above rules even when calling a synchronous function - previously called asynchronous functions may not be complete.

As an example, this series of calls is illegal and may result in an error:

```
group_id = H5Gcreate_async(file_id, "parent", ..., es_id);
dset_id = H5Dcreate(file_id, "parent/dset", ...); //may fail
```

#### 2.3.3. Operation ordering

For the most part, all asynchronous operations execute concurrently without any ordering enforced betwen them. However, there are a few exceptions. The connector enforces ordering between object open operations and operations that use that object, in order to facilitate the feature described above that allows the use of incompletely opened object IDs. In addition, H5Dset\_extent(\_async)(), link/object creates when the parent group has link creation order tracked, and attribute creates when the parent object has attribute creation order tracked are always strictly ordered, so these operations always execute after any previously issued operation related to their object, and before any subsequently issued operations.

The application can manually enforce ordering using H5Oflush\_async() and H5Fflush\_async(). These operations only complete when all previously issued operations for the object or file complete and, like H5Dset\_extent\_async(), all subsequently issued operations only begin after the flush is complete. Since the DAOS HDF5 connector does no caching, the flush operations have no other effect. This allows you to, for example, write to an attribute, issue an H5Oflush\_async() on the attribute's parent object, and read the attribute back, all in a non-blocking fashion (as long as you keep both read and write buffers around and don't examine the read buffer until it is complete). See the Operation Scope section for information on which operations are in scope for H5Oflush\_async.

As an example, here is a way to make the previously illegal example legal while remaining fully asynchronous:

```
group_id = H5Gcreate_async(file_id, "parent", ..., es_id);
H5Fflush_async(file_id, H5F_SCOPE_LOCAL, es_id);
dset_id = H5Dcreate_async(file_id, "parent/dset", ..., es_id);
```

A call to  ${\tt H5Oflush\_async}$  (group\_id, es\_id) would not be sufficient in this case because the group creation occurs in  ${\tt file\_id}$ 's scope, because  ${\tt file\_id}$  is what is passed to  ${\tt H5Gcreate\_async}$ (). The flush must be made on the parent object.

Close operations such as H5Gclose() or H5Fclose() will only complete once all previously issued operations on their object, file or attribute complete. Therefore, the non-async versions of these operations will block until these operations are complete. Asynchronous versions of all close operations are available for non-blocking close.



### 2.3.4. Parallel Considerations

Parallel collective operations add another constraint on asynchronous operations. Because asynchronous MPI operations must be strictly ordered, all collective HDF5 operations are strictly ordered with respect to each other when executed with more than one rank, and no two can execute at the same time. Non-collective operations are not affected by this, and may execute simultaneouly with collective operations.

#### 2.3.5. Operation Scope

In order to handle some operations that need to be ordered with respect to all other operations within a certain scope, we have introduced the concept of an operation pool, which is a container for operations that can be executed simultaneously. All operations exist in an operation pool at attribute, object, file, or global scope. When the application invokes an HDF5 API routine, this creates an operation this is placed in the operation pool of the object passed to the API routine. For example, dataset creates are placed in the object scoped pool of the parent group passed as the first argument to H5Dcreate(), attribute creates are placed in the object scoped pool of the parent object passed as the first argument to H5Acreate(), and attribute writes are placed in the attribute scoped pool of the attribute. Operations that have multiple parent objects (such as H5Ocopy()) are placed in the file pool if the objects are in the same file, and in the global pool if they are in different files.

All operations placed in a pool will be executed after all previously issued operations at a different scope in a location that contains, or is contained in, the pool for the original operation. For example, an operation in an attribute's pool will execute after all previously issued operations in the pools for the attribute's parent object, its file, or the global pool. It is not affected by operations in a different object or file. Operations in the global pool will execute after all previously issued operations not in the global pool.

For the most part, this operation pool scheme is transparent to the application and can be ignored. However, for maximum concurrency, it is worth considering that certain access patterns will result operations being serialized, so only one may execute at a time (though they will remain asynchronous). This will happen if, for example, the app alternates between attribute and object operations.

#### 2.3.6. Asynchronous Example Program

Below is an example of an asynchronous application that writes to a dataset:



```
dset_id = H5Dopen_async(group_id, "dataset", H5P_DEFAULT, es_id);
                          // Starts when H5Gopen completes
   status = H5Dwrite_async(dset_id, ..., es_id);
                          // Asynchronous, starts when H5Dopen completes,
                          // may run concurrently with other H5Dwrite in
                          // event set
   status = H5Dwrite_async(dset_id, ..., es_id);
                          // Asynchronous, starts when H5Dopen completes,
                          // may run concurrently with other H5Dwrite in
                          // event set
   status = H5Dclose_async(dset_id);
                          // Asynchronous, will complete when both
                          // writes above complete
   <other user code>
   H5ESwait(es_id); // Wait for operations in event set to complete, buffers
                     // used for H5Dwrite must not be changed until after wait
                     // returns
   status = H5Gclose(group_id); // Blocking call, will return as soon as all
                                // operations on group_id complete
   status = H5Fclose(file id); // Blocking call, will return as soon as all
                                // operations on file id complete
   return 0;
}
```

### 2.4. Building HDF5 DAOS VOL connector applications

Assuming an HDF5 application has been written following the instructions in the previous section, the application should be built as normal for any other HDF5 application. However, if the DAOS VOL connector is not being dynamically loaded, the steps in the following section are required to build the application.

#### 2.4.1. Without the DAOS VOL connector as a dynamically-loaded plugin

To link in the required libraries, the compiler will likely require the additional linker flags:

```
-lhdf5_vol_daos -luuid
```

However, these flags may vary depending on platform, compiler and installation location of the DAOS VOL connector. It is highly recommended that compilation of HDF5 DAOS VOL connector applications be done using either the h5cc/h5pcc script included with HDF5 distributions, or CMake, pkg-config, as these will manage linking with the HDF5 library.



If HDF5 was built using autotools, this script will be called h5pcc and may be found in the bin directory of the HDF5 installation. If HDF5 was built with CMake, this script will simply be called h5cc and can be found in the same location. The above notice about additional library linking applies to usage of h5cc/h5pcc $^1$ . For example:

```
h5cc/h5pcc -shlib -lhdf5_vol_daos -luuid my_src.c -o my_exe
```

### 2.5. Running HDF5 DAOS VOL connector applications

Running applications that use the DAOS VOL connector connector requires access to a DAOS server. Refer to DAOS Software Installation for more information on the setup process for this. For the DAOS VOL connector to correctly interact with a DAOS server instance, the server must be running and it must be passed the UUID of the DAOS pool to use and a list of DAOS pool service list ranks, as detailed in the following sections.

#### 2.5.1. Starting the DAOS Server

Instructions for starting a DAOS Server can be found in the DAOS Documentation.

#### 2.5.2. With the DAOS VOL connector as a dynamically-loaded plugin

If the DAOS VOL connector is dynamically loaded by HDF5, the DAOS pool UUID and DAOS pool service rank list are passed via the two environment variables below.

```
DAOS_POOL - The UUID of the DAOS pool to use.

DAOS_SVCL - A comma-separated list of server ranks used for daos_pool_connect(). Generated from daos_pool_create().
```

#### 2.5.3. Without the connector as a dynamically-loaded plugin

If the DAOS VOL connector is not being dynamically loaded, the DAOS pool UUID and DAOS pool service rank list should be passed via the call to H5daos\_init() within the application.

#### 2.5.4. Example Applications

Some of the example C applications which are included with HDF5 distributions have been adapted to work with the DAOS VOL connector and are included under the top-level examples directory in the DAOS VOL connector source root directory. The built example applications can be run from the bin directory inside the build directory.

In addition to these examples, the test/vol directory contains several test files, each containing test functions that are examples of HDF5 applications in miniature, focused on a particular behavior. These

<sup>&</sup>lt;sup>1</sup>Note that when HDF5 has been compiled with autotools, -shlib option must be passed to use dynamic versions of the library, this is not required with CMake



mini-application tests cover a moderate amount of HDF5's public API functionality and should be a good indicator of whether the DAOS VOL connector is working correctly in conjunction with a running DAOS API-aware instance. Note that these tests currently rely on HDF5's dynamically-loaded VOL connector capabilities in order to run with the DAOS VOL connector.



# 3. HDF5 API Support

### 3.1. Feature Specific Support

The following sections serve to illustrate the DAOS VOL connector's support for features in HDF5, as well as to highlight any differences between the expected behavior of an HDF5 feature versus the actual behavior as implemented by the VOL connector.

### 3.1.1. Attribute Features

	Feature	Supported?	Notes	
		H5S_NULL	Yes	
Dataspace	Dimensionality	H5S_SCALAR	Yes	
		SIMPLE	Yes	
		Atomic	Yes	
		Compound	Yes	
		Variable-length	Yes	_
Datatype		Array	Yes	_
		Opaque	Yes	_
		Reference	Yes	
D .:	N. F. I'	ASCII	Yes	
Properties	Name Encoding	UTF-8	No	



### 3.1.2. Dataset Features

	Feature	Supported?	Notes	
		H5S_NULL	Yes	
	Dimensionality	H5S_SCALAR	Yes	
		SIMPLE	Yes	
		NONE	Yes	
Dataspace		H5S_ALL	Yes	
	Selection Type	Hyperslab Selection	Yes	_
		Point Selection	Yes	
		Atomic	Yes	
			Yes	_
		Variable-length	Yes	_
Datatype		Array	Yes	_
		Opaque	Yes	
		Reference	Yes	



	Feature		Supported?	Notes
		Compact	No	Setting is ignored; stored as contiguous.
	Storage Properties (creation)	External	No	Setting is ignored; stored as contiguous.
		Contiguous	Yes	Default storage type.
		Chunked	Yes	
Properties		VDS	No	The VDS feature is not currently planned to be supported.
	Other Properties (creation)	Attribute Creation Order	Yes	In order to work correctly, the attribute creation order feature requires that the dataset is touched collectively or that the application otherwise ensures no concurrent access to the dataset <sup>1</sup> .
		Fill Value	Yes	
		Filters	No	HDF5 does not expose any public APIs for working with the filter pipeline; however, this feature may be supported in the future.
		Storage Allocation Time	N/A	

<sup>&</sup>lt;sup>1</sup>This restriction may be removed in the future.



	Feature	Supported?	Notes	
		Chunk cache	No	HDF5 does
				not expose any
				public APIs for
				implementing
	A acces Duomantias			a chunk cache
Properties (cont.)	Access Properties			for arbitrary
Troperties (cont.)				VOL connectors; however, this
				feature may be
				supported in the
				future.
		VDS views and	No	The VDS feature
		printf	140	is not currently
		print		planned to be
				supported.
		MPI-I/O	Yes	By default,
		Collective		all metadata
		Metadata Ops		operations
				are collective
				for writes and
				independent for
				reads. Also see
				H5P(set/get)_all_ind
				_metadata_ops().
	Transfer Properties	MPI-I/O	N/A	
	Transfer i Toporties	Independent		
		or Collective I/O mode		
		moue		



### 3.1.3. File Features

	Feature	Supported?	Notes	
E:1 .: 0		H5F_ACC_TRUNC	Yes	
File creation flags		H5F_ACC_EXCL	Yes	The file creation
		H5F_ACC_RDWR	Yes	flags behave as for native HDF5.
File opening flags		H5F_ACC_RDONLY	Yes	for native fibi 5.
Properties	Creation Properties	Attribute Creation Order	Yes	In order to work correctly, the attribute creation order feature requires that the dataset is touched collectively or that the application otherwise ensures no concurrent access to the dataset <sup>1</sup> . The rest of the file creation properties are related to the native HDF5-specific file format.
		SEC2 Driver	N/A	These drivers are
		Family Driver	N/A	applicable to
	A aggas Duran anti-	Split Driver	N/A	native HDF5
	Access Properties (Drivers)	Multi Driver	N/A	only.
	(Directs)	Core Driver	N/A	
		Log Driver	N/A	
		MPI-I/O	Yes	This property just indicates parallel access to the file; it doesn't use HDF5 MPI I/O driver underneath.

<sup>&</sup>lt;sup>1</sup>This restriction may be removed in the future.



Feature			Supported?	Notes
	Access Properties	MPI-I/O Collective Metadata Ops	Yes	By default, all metadata operations are collective for writes and independent for reads. Also see H5P(set/get)_all_ind _metadata_ops().
	(Other)	User block	N/A	
Properties (cont.)		Chunk Cache	No	HDF5 does not expose any public APIs for implementing a chunk cache for arbitrary VOL connectors; however, this feature may be supported in the future.
		Object flushing callbacks	N/A	
		File closing degree	N/A	
		Evict on close	N/A	
		Sieve buffer size for partial I/O	No	HDF5 does not expose any public APIs for implementing a partial I/O sieve buffer for arbitrary VOL connectors; however, this feature may be supported in the future.
		File Image	N/A	



## 3.1.4. Group Features

	Feature		Supported?	Notes
Properties	Creation Properties	Link Creation Order	Yes	In order to work correctly, the link creation order feature requires that the parent group is touched collectively or that the application otherwise ensures no concurrent access to the group. <sup>2</sup>
		Attribute Creation Order	Yes	In order to work correctly, the attribute creation order feature requires that the dataset is touched collectively or that the application otherwise ensures no concurrent access to the dataset. <sup>1</sup>
		Other Properties	N/A	These properties are related to the native HDF5-specific file format.
	Access Properties	MPI-I/O Collective Metadata Ops	Yes	By default, all metadata operations are collective for writes and independent for reads. Also see H5P(set/get)_all_ind _metadata_ops().

<sup>&</sup>lt;sup>1</sup>This restriction may be removed in the future.



### 3.2. API Specific Support

The following sections serve to illustrate the DAOS VOL connector's support for the HDF5 API, as well as to highlight any differences between the expected behavior of an HDF5 API call versus the actual behavior as implemented by the VOL connector. If a particular HDF5 API call does not appear among these tables, it is most likely a native HDF5-specific API call which cannot be implemented by non-native HDF5 VOL connectors. These types of API calls are listed among the tables in Appendix B.



### 3.2.1. H5A interface

## **Supported API calls**

API call	Notes
H5Acreate(1/2)	
H5Acreate_async	
H5Acreate_by_name	
H5Acreate_by_name_async	
H5Aopen(_by_name/_by_idx)	For H5Aopen_by_idx, H5_ITER_DEC is currently unsupported for the index ordering when H5_INDEX_NAME is used for the index type
H5Aopen(_by_name)_async	
H5Aopen_by_idx_async	Currently executes in a semi-blocking fashion, currently untested
H5Aopen_idx	Deprecated in favor of H5A_open_by_idx
H5Aopen_name	Deprecated in favor of H5A_open_by_name
H5Awrite	
H5Awrite_async	
H5Aread	
H5Aread_async	
H5Aclose	Blocks until all in-flight async tasks on the attribute are complete
H5Aclose_async	Completes when all in-flight async tasks on the attribute are complete
H5Aiterate(2)	
	<ul> <li>Restarting iteration from an index value is currently unsupported<sup>1</sup></li> <li>H5_ITER_DEC is currently unsupported for the index ordering when H5_INDEX_NAME is used for the index type</li> </ul>

<sup>&</sup>lt;sup>1</sup>Will be supported in the future.



API call	Notes
H5Aiterate_by_name	
	<ul> <li>Restarting iteration from an index value is currently unsupported<sup>1</sup></li> </ul>
	<ul> <li>H5_ITER_DEC is currently unsupported for the index ordering when H5_INDEX_NAME is used for the index type</li> </ul>
H5Aexists(_by_name)	
H5Aexists_async	
H5Aexists_by_name_async	Currently untested
H5Arename(_by_name)	
H5Arename(_by_name)_async	Currently executes in a semi-blocking fashion, currently untested
H5Adelete(_by_name/_by_idx)	For H5Adelete_by_idx, H5_ITER_DEC is currently unsupported for the index ordering when H5_INDEX_NAME is used for the index type
H5Aget_name(_by_idx)	For H5Aget_name_by_idx, H5_ITER_DEC is currently unsupported for the index ordering when H5_INDEX_NAME is used for the index type
H5Aget_space	
H5Aget_type	
H5Aget_info(_by_name/_by_idx)	Of the four fields in the H5A_info_t struct:
	<ul> <li>corder_valid is set to TRUE only if attribute creation order tracking is enabled for the object containing the attribute; it is set to FALSE otherwise</li> </ul>
	<ul> <li>corder is set appropriately if attribute creation order tracking is enabled for the object containing the attribute; it is set to 0 otherwise</li> </ul>
	■ cset is currently always set to H5T_CSET_ASCII
	■ data_size is set appropriately
	For H5Aget_info_by_idx, H5_ITER_DEC is currently unsupported for the index ordering when H5_INDEX_NAME is used for the index type
H5Aget_create_plist	



## **Currently unsupported API calls**

API call	Notes
H5Aget_storage_size	H5Aget_storage_size is not currently
	planned to be supported



### 3.2.2. H5D interface

## **Supported API calls**

API call	Notes
H5Dcreate(1/2)	
H5Dcreate_async	
H5Dcreate_anon	
H5Dopen(1/2)	
H5Dopen_async	
H5Dwrite	
H5Dwrite_async	
H5Dread	
H5Dread_async	
H5Dclose	Blocks until all in-flight async tasks on the dataset are complete
H5Dclose_async	Completes when all in-flight async tasks on the dataset are complete
H5Dextend	Upon dataset shrinking, data is currently not cleared <sup>1</sup>
H5Dset_extent	Upon dataset shrinking, data is currently not cleared <sup>1</sup>
H5Dset_extent_async	If the dataset was opened and not created, blocks until the dataset open is complete
H5Dget_space	
H5Dget_space_async	
H5Dget_type	
H5Dget_create_plist	
H5Dget_access_plist	
H5Dget_space_status	Space status is currently always set to H5D_SPACE_STATUS_ALLOCATED
H5Dget_storage_size	Currently implemented to just return the in-memory size of dataset data. Should not be relied upon as an accurate measurement of the actual storage size required for the dataset data.
H5Dflush	Blocks until all in-flight async tasks on the dataset are complete
H5Drefresh	



## **Currently unsupported API calls**

API call	Notes

<sup>&</sup>lt;sup>1</sup>Will be supported in the future.



### 3.2.3. H5F interface

## **Supported API calls**

API call	Notes
H5Fcreate	
H5Fcreate_async	
H5Fopen	
H5Fopen_async	
H5Freopen	
H5Freopen_async	
H5Fis_accessible	
H5Fget_create_plist	
H5Fget_access_plist	
H5Fget_intent	
H5Fget_name	
H5Fget_obj_count	
H5Fget_obj_ids	
H5Fdelete	
H5Fflush	Blocks until all in-flight async tasks on the file are complete
H5Fflush_async	Completes when all in-flight async tasks on the file are complete
H5Fclose	Blocks until all in-flight async tasks on the file are complete
H5Fclose_async	Completes when all in-flight async tasks on the file are complete

### **Currently unsupported API calls**

API call	Notes
H5Fmount	H5Fmount is not currently planned to be supported
H5Funmount	H5Funmount is not currently planned to be supported



### 3.2.4. H5G interface

## **Supported API calls**

H5Gcreate(1/2)	
H5Gcreate_async	
H5Gcreate_anon	
H5Gopen(1/2)	
H5Gopen_async	
H5Gclose	Blocks until all in-flight async tasks on the group are complete
H5Gclose_async	Completes when all in-flight async tasks on the group are complete
H5Gunlink	
H5Gget_create_plist	
H5Gget_info(_by_name/_by_idx)	Of the four fields in the H5G_info_t struct:
	<ul> <li>storage_type is always set to         H5G_STORAGE_TYPE_UNKNOWN</li> <li>nlinks is set appropriately</li> <li>max_corder is set appropriately if link         creation order is tracked for the group</li> <li>mounted is currently always set to FALSE</li> <li>For H5Gget_info_by_idx, H5_ITER_DEC is         currently unsupported for the index ordering when         H5_INDEX_NAME is used for the index type</li> </ul>
H5Gget_info(_by_name/_by_idx)_async	
H5Gget_linkval	
H5Gget_num_objs	
H5Gget_objname_by_idx	H5_ITER_DEC is currently unsupported for the index ordering when H5_INDEX_NAME is used for the index type
H5Glink(2)	Currently only hard and soft link creation are supported <sup>1</sup>
H5Gmove(2)	Refer to Notes for H5Lmove

<sup>&</sup>lt;sup>1</sup>External links are not currently planned to be supported.



API call	Notes
H5Gflush	Blocks until all in-flight async tasks on the file are complete
H5Grefresh	H5Grefresh is currently implemented as a no-op

## **Currently unsupported API calls**

API call	Notes



### 3.2.5. H5L interface

## **Supported API calls**

API call	Notes
H5Lcreate_hard	
H5Lcreate_hard_async	
H5Lcreate_soft	
H5Lcreate_soft_async	
H5Lexists	
H5Lexists_async	
H5Literate(_by_name)	<ul> <li>Restarting iteration from an index value is currently unsupported<sup>1</sup></li> <li>H5_ITER_DEC is currently unsupported for the iteration order when H5_INDEX_NAME is used for the index type</li> </ul>
H5Literate_async	Currently executes in a blocking fashion
H5Lvisit(_by_name)	<ul> <li>Restarting iteration from an index value is currently unsupported<sup>1</sup></li> <li>H5_ITER_DEC is currently unsupported for the iteration order when H5_INDEX_NAME is used for the index type</li> </ul>
H5Ldelete	
H5Ldelete_async	
H5Ldelete_by_idx	H5_ITER_DEC is currently unsupported for the index ordering when H5_INDEX_NAME is used for the index type
H5Ldelete_by_idx_async	

<sup>&</sup>lt;sup>1</sup>Will be supported in the future.



API call	Notes
H5Lget_info	Of the five fields in the H5L_info_t struct:
	■ type is set appropriately
	<ul> <li>corder_valid is set to TRUE only if link creation order tracking is enabled for the group containing the link; it is set to FALSE otherwise</li> </ul>
	<ul> <li>corder is set appropriately if link creation order tracking is enabled for the group containing the link; it is set to 0 otherwise</li> </ul>
	■ cset is currently always set to H5T_CSET_ASCII
	<ul> <li>u has member address or val_size set appropriately based on whether the link is a hard link or not</li> </ul>
H5Lget_info_by_idx	H5_ITER_DEC is currently unsupported for the index ordering when H5_INDEX_NAME is used for the index type
H5Lget_val	
H5Lget_val_by_idx	H5_ITER_DEC is currently unsupported for the index ordering when H5_INDEX_NAME is used for the index type
H5Lget_name_by_idx	H5_ITER_DEC is currently unsupported for the index ordering when H5_INDEX_NAME is used for the index type
H5Lcopy	Currently no support for the following properties:
	■ LAPL
	- H5Pset_nlinks
	- H5Pset_elink_prefix <sup>1</sup>
H5Lmove	Currently no support for the following properties:
	■ LAPL
	- H5Pset_nlinks
	- H5Pset_elink_prefix <sup>1</sup>



## **Currently unsupported API calls**

API call	Notes
H5Lcreate_external	H5Lcreate_external is not currently planned to be supported. As DAOS containers can contain large amounts of objects, the necessity for external links is lessened as compared to a traditional storage system
H5Lcreate_ud	H5Lcreate_ud is not currently planned to be supported

<sup>&</sup>lt;sup>1</sup>External links are not currently planned to be supported.



### 3.2.6. H5M interface

# **Supported API calls**

API call	Notes
H5Mcreate	
H5Mcreate_async	
H5Mcreate_anon	
H5Mopen	
H5Mopen_async	
H5Mclose	Blocks until all in-flight async tasks on the group are complete
H5Mclose_async	Completes when all in-flight async tasks on the group are complete
H5Mget_key_type	
H5Mget_val_type	
H5Mget_create_plist	
H5Mget_access_plist	
H5Mget_count	
H5Mput	
H5Mput_async	If the map was opened and not created, blocks until the map open is complete, currently untested
H5Mget	
H5Mget_async	If the map was opened and not created, blocks until the map open is complete, currently untested
H5Mexists	
H5Miterate	
H5Miterate_by_name	
H5Mdelete	

API call	Notes



# 3.2.7. H5O interface

# **Supported API calls**

API call	Notes
H5Oopen	
H5Oopen_async	
H5Oopen_by_token	
H5Oopen_by_idx	H5_ITER_DEC is currently unsupported for the index ordering when H5_INDEX_NAME is used for the index type
H5Oopen_by_idx_async	
H5Oclose	Blocks until all in-flight async tasks on the object are complete
H5Oclose_async	Completes when all in-flight async tasks on the object are complete
H5Oincr_refcount	
H5Odecr_refcount	
H5Olink	
H5Oexists_by_name	
H5Oget_info(_by_name)3	
H5Oget_info_by_name_async	Currently untested
H5Ovisit(1/2)	H5_ITER_DEC is currently unsupported for the index ordering when H5_INDEX_NAME is used for the index type
H5Ovisit_by_name(1/2)	H5_ITER_DEC is currently unsupported for the index ordering when H5_INDEX_NAME is used for the index type
Н5Осору	Currently no support for the following properties:
	■ OCpyPL
	- H5O_COPY_EXPAND_EXT_LINK_FLAG1
	- H5O_COPY_EXPAND_REFERENCE_FLAG <sup>2</sup>
	- H5O_COPY_MERGE_COMMITTED_DTYPE_FLAG
H5Ocopy_async	

<sup>&</sup>lt;sup>1</sup>External links are not currently planned to be supported.
<sup>2</sup>Will be supported in the future.



API call	Notes
H5Oclose	Blocks until all in-flight async tasks on the object are complete
H5Oclose_async	Completes when all in-flight async tasks on the object are complete
H5Oflush	Blocks until all in-flight async tasks on the object are complete
H5Oflush_async	Completes when all in-flight async tasks on the object are complete
H5Orefresh	H50refresh delegates to the appropriate H5Xrefresh routine based upon the given object's type, but that particular object's refresh routine may be implemented as a no-op

API call	Notes
H5Oopen_by_addr	



# 3.2.8. H5R interface

# **Supported API calls**

API call	Notes
H5Rcreate_object	Object lookup and retrieval of a container's info (which are needed for H5Rcreate_object) are supported
H5Rcreate_region	Object lookup and retrieval of a container's info (which are needed for H5Rcreate_region) are supported
H5Rcreate_attr	Object lookup and retrieval of a container's info (which are needed for H5Rcreate_attr) are supported
H5Ropen_object	Object opening (which is needed for H5Ropen_object) is supported
H5Ropen_region	Object opening and retrieval of a dataset's dataspace (which are needed for H5Ropen_region) are supported
H5Ropen_attr	Object opening and attribute opening (which are needed for H5Ropen_attr) are supported
H5Ropen_object_async	Currently untested
H5Ropen_region_async	Currently untested
H5Ropen_attr_async	Currently untested
H5Rget_obj_type3	
H5Rget_file_name	Retrieval of a file's name (which is needed for H5Rget_file_name) is supported

API call	Notes
H5Rget_obj_name	



# 3.2.9. H5T interface

# **Supported API calls**

API call	Notes
H5Tcommit(1/2)	
H5Tcommit_async	Currently untested
H5Tcommit_anon	
H5Topen(1/2)	
H5Topen_async	Currently untested
H5Tclose	Blocks until all in-flight async tasks on the
	datatype are complete
H5Tclose_async	Completes when all in-flight async tasks on the
	datatype are complete, currently untested
H5Tget_create_plist	
H5Tflush	Blocks until all in-flight async tasks on the
	datatype are complete
H5Trefresh	H5Trefresh is currently implemented as a
	no-op

API call	Notes



#### 3.3. Known Limitations

The following sections outline the known current limitations of the DAOS VOL connector.

#### 3.3.1. Limitations in regards to DAOS

- If an application abnormally exits, the DAOS VOL connector may leave the file in an unusable state. As DAOS does not currently support forced container deletion, trying to overwrite an existing HDF5 file using the H5F\_ACC\_TRUNC flag when the file was left in an unusable state will fail; the error "can't destroy container: generic I/O error (DER\_IO)" will be returned. Currently, the only way to re-use the same filename after an application interruption is to remove the file stub for the unusable file and then create a new file within a new DAOS pool. This issue will be resolved when rollback to a previous snapshot is supported.
- There is currently no support for distributed transactions.



# 4. Testing the DAOS VOL connector

The following sections cover how to test the DAOS VOL connector, as well as the individual components of the DAOS VOL connector's overall testing infrastructure.

#### 4.1. With CTest

Once the DAOS VOL connector has been built, running the connector's tests should be as simple as running

ctest .

from the build directory. This will run each of the VOL connector's test components in turn. For more information on using CTest's options to control testing behavior, refer to the CTest Documentation.

#### 4.2. Manually

If testing the DAOS VOL connector without CTest, refer to Starting the DAOS Server and Running HDF5 DAOS VOL connector applications to make sure that the DAOS Server is up and running and your environment is setup correctly. Once that is done, the DAOS VOL connector's tests can be run directly from the bin directory inside the build directory. For a listing of the different test executables and the functionality they test, refer to the following sections.

### 4.3. DAOS VOL connector's testing components

#### 4.3.1. Generic HDF5 VOL connector test suite

In order to test HDF5 VOL connectors to make sure that they are functioning as expected, a suite of tests which only use the public HDF5 API has been written. This suite of tests is available under the path:

test/vol

and when built, will appear as the h5vl\_test and h5vl\_test\_parallel executables in the bin directory inside the build directory.

Note that running this test suite requires that your environment is setup to have HDF5 dynamically load the DAOS VOL connector. Also, this test suite currently does not have the capability to query what kind of functionality an HDF5 VOL connector supports and therefore certain tests will be skipped if they use an HDF5 API call which is not implemented, or which is specifically unsupported, by the DAOS VOL connector.

### 4.3.2. DAOS VOL connector-specific test suite

In addition to the generic VOL connector testing suite, the DAOS VOL connector also includes the following test suites, which test features specific to the connector:

■ DAOS VOL connector Map test suite



This test suite tests the DAOS VOL connector against the 'Map' functionality in HDF5, which concerns map objects that store key-value pairs. When built, this test suite will appear as the h5daos\_test\_map and h5daos\_test\_map\_parallel executables in the bin directory inside the build directory.

■ DAOS VOL connector Recovery testing suite

This test suite tests the DAOS VOL connector's ability to recover from a fault that causes the DAOS server or the HDF5 application to stop functioning. It also ensures the integrity of both metadata and raw data in a file after such a fault. When built, this test suite will appear as the h5daos\_test\_recovery executable in the bin directory inside the build directory.



# A. Reference Manual

#### A.1. H5daos\_init

#### Synopsis:

### Purpose:

Initialize the DAOS VOL connector.

### **Description:**

H5daos\_init initializes the VOL connector by registering the connector with the library.

#### Parameters:

#### Returns:



### A.2. H5daos\_term

# Synopsis:

herr\_t H5daos\_term(void);

# Purpose:

Terminate the DAOS VOL connector.

# **Description:**

H5daos\_term terminates the DAOS VOL connector.

### Parameters:

None.

### Returns:



# A.3. H5Pset\_fapl\_daos

### Synopsis:

```
herr_t H5Pset_fapl_daos(hid_t fapl_id, MPI_Comm comm, MPI_Info info);
```

### Purpose:

Set the file access property list to use the DAOS VOL connector.

### **Description:**

H5Pset\_fapl\_daos modifies the file access property list to use the DAOS VOL connector. file\_comm and file\_info identify the communicator and info object used to coordinate actions on file create, open, flush, and close.

#### **Parameters:**

hid\_t fapl\_id IN: File access property list ID

MPI\_Comm file\_comm IN: MPI Communicator

MPI\_Info file\_info IN: MPI Info

#### Returns:



#### A.4. H5daos\_set\_all\_ind\_metadata\_ops

#### Synopsis:

```
herr_t H5daos_set_all_ind_metadata_ops(hid_t accpl_id, hbool_t
    is_independent);
```

#### **Purpose:**

Sets the I/O mode for metadata read/write operations in the access property list accpl\_id.

When engaging in parallel I/O with the DAOS VOL connector, all metadata read operations are independent and all metadata write operations are collective by default. If is\_independent is specified as TRUE, this property indicates that the DAOS VOL connector will perform all metadata read and write operations independently.

If this property is set to TRUE on a file access property list that is used in creating or opening a file, the DAOS VOL connector will assume that all metadata read and write operations issued on that file identifier should be issued independently from all ranks, irrespective of the individual setting for a particular operation.

Alternatively, a user may wish to avoid setting this property globally on the file access property list and individually set it on particular object access property lists (dataset, group, link, datatype, attribute access property lists) for certain operations instead. This will indicate that only the operations issued with such an access property list will perform metadata I/O independently, whereas other operations may perform metadata I/O collectively.

### **Description:**

H5daos\_set\_all\_ind\_metadata\_ops modifies the access property list to indicate that metadata I/O operations should be performed independently.

#### **Parameters:**

hid\_t accpl\_id IN: File, group, dataset, datatype, link or attribute access property list ID

hbool\_t is\_independent IN: Boolean value indicating whether metadata I/O operations should be performed independently (TRUE) or should be allowed to be performed collectively (FALSE).

#### Returns:



### A.5. H5daos\_get\_all\_ind\_metadata\_ops

### Synopsis:

```
herr_t H5daos_get_all_ind_metadata_ops(hid_t accpl_id, hbool_t
    *is_independent);
```

#### **Purpose:**

Retrieves the independent metadata I/O setting from the access property list accplid.

### **Description:**

H5daos\_get\_all\_ind\_metadata\_ops retrieves the independent metadata I/O setting from the access property list accpl\_id.

#### Parameters:

hid\_t accpl\_id IN: File, group, dataset, datatype, link or attribute access property list ID

hbool\_t \*is\_independent OUT: Pointer to a Boolean value to be set, indicating whether metadata I/O is performed

independently or is allowed to be performed collectively.

#### Returns:



# B. Native HDF5 VOL connector-specific API calls

The following HDF5 API calls are either specific to the native HDF5 VOL connector or are not routed through the VOL and thus are not able to be implemented by the DAOS VOL connector (or other VOL connectors):

#### B.1. H5A interface

API call	Notes
H5Aiterate1	Deprecated in favor of H5Aiterate2
H5Aget_num_attrs	Deprecated in favor of H5Oget_info

### **B.2. H5D interface**

API call	Notes
H5Dformat_convert	
H5Dget_offset	
H5Dget_chunk_index_type	
H5Dget_chunk_storage_size	
H5Dvlen_reclaim	
H5Dvlen_get_buf_size	
H5Diterate	
H5Dscatter	
H5Dgather	
H5Dfill	
H5Dread_chunk	
H5Dwrite_chunk	



# **B.3. H5F interface**

API call	Notes
H5Fis_hdf5	Uses a default FAPL so can only ever be routed through the native HDF5 VOL connector
H5Fget_vfd_handle	
H5Fget_freespace	
H5Fget_filesize	
H5Fget_file_image	
H5Fget_mdc_config	
H5Fset_mdc_config	
H5Fget_mdc_hit_rate	
H5Fget_mdc_size	
H5Freset_mdc_hit_rate_stats	
H5Fget_info(1/2)	
H5Fget_metadata_read_retry_info	
H5Fget_free_sections	
H5Fclear_elink_file_cache	
H5Fstart_swmr_write	
H5Fstart_mdc_logging	
H5Fstop_mdc_logging	
H5Fget_mdc_logging_status	
H5Fset_libver_bounds	
H5Fformat_convert	
H5Freset_page_buffering_stats	
H5Fget_page_buffering_stats	
H5Fget_mdc_image_info	
H5Fget_eoa	
H5Fincrement_filesize	
H5Fget_dset_no_attrs_hint	
H5Fset_dset_no_attrs_hint	
H5Fset_latest_format	
H5Fset_mpi_atomicity	
H5Fget_mpi_atomicity	



# **B.4. H5G interface**

API call	Notes
H5Gset_comment	Deprecated in favor of H5Oset_comment_by_name
H5Gget_comment	Deprecated in favor of H5Oget_comment_by_name
H5Giterate	Deprecated in favor of H5Literate
H5Gget_objinfo	Deprecated in favor of H5Lget_info/H5Oget_info
H5Gget_objtype_by_idx	Deprecated in favor of H5Lget_info/H5Oget_info

# B.5. H5L interface

API call	Notes
H5Lregister	
H5Lunregister	
H5Lis_registered	
H5Lunpack_elink_val	

## **B.6. H5O interface**

API call	Notes
H5Oget_info(1/2)	
H5Oget_info_by_name(1/2)	
H5Oget_info_by_idx(1/2)	
H5Oset_comment(_by_name)	Deprecated in favor of using attributes on objects
H5Oget_comment(_by_name)	Deprecated in favor of using attributes on objects
H5Oare_mdc_flushes_disabled	
H5Oenable_mdc_flushes	
H5Odisable_mdc_flushes	



# **B.7. H5R interface**

API call	Notes
H5Rdestroy	
H5Rget_type	
H5Requal	
H5Rcopy	
H5Rget_attr_name	

# **B.8. H5T interface**

API call	Notes

