

Installation

pip install taichi ti example

Quick start

import taichi as ti ti.init() @ti.kernel def monte_carlo_pi() -> float: total = 0 for i in range(100000): x = ti.random() v = ti.random() if (x*x + y*y) < 1: total += 1 return 4 * total / n

Supported backends

ti.cpu, ti.cuda, ti.metal, ti.opengl, ti.vulkan

Data types

primitive tyes

i8, i16, i32, i64, u8, u16, u32, u64, f16, f32, f64

types.vector(n, dtype)

vec3 = ti.types.vector(3, float) v = vec3(1, 2, 3)

types.matrix(n, m, dtype)

mat2x2 = ti.types.matrix(2, 2, float) m = mat2x2(1, 2, 3, 4)

types.struct(**kwargs)

sphere = ti.types.struct(center=vec3, radius=float) s = sphere(vec3(1, 2, 3), 1.0)

Qaunt types

u5 = ti.types.quant.int(bits=5, signed=False) fixed_a = ti.types.quant.fixed(bits=10, max_value=20.0) float_b = ti.types.quant.float(exp=6, frac=9, signed=False)

Data container

field(dtype, shape, ...)

f = ti.field(int, shape=(3, 3, 3))

Vector.field(dim, dtype, shape, ...)

f = ti.Vector.field(3, float, (10, 10))

Matrix.field(dim, dtype, shape, ...)

f = ti.Matrix.field(3, 3, float, shape=(10, 10))

Struct.field(dict, shape)

sphere = ti.types.struct(center=vec3, radius=float) s = sphere.field(shape=100)

Frequently used features fill(val)

f.fill(1)

to_numpy()

from_numpy(arr)

Kernels and functions

@ti.kernel: Called from Python scope. Require type hints for arguments and return values. Can return scalar, vector and

@ti.func: Called from Taichi scope. Recommend type hints for arguments and return values. Can return scalar, vector, matrix and struct.

Interactive with Numpy arrays

arr = numpy.arange(12).reshape(3, 4) def example(x: ti.types.ndarray()): for i, j in ti.ndrange(arr.shape[0], arr.shape[1]): arr[i, j] = i + j

Data-oriented programming

data-oriented class

A data-oriented class is used when your data is actively updated in the Python scope (such as current time and user input events) and tracked in Taichi kernels.

```
@ti.data_oriented
class TiArray:
   def __init__(self, n):
        self.x = ti.field(dtype=ti.i32, shape=n)
      @ti.kernel # Defines Taichi kernels in the data-oriented
      def inc(self):
          for i in self.x:
             self.x[i] += 1
a = TiArray(32)
a.inc()
```

dataclass

A dataclass is a wrapper of 'ti.types.struct'. You can define Taichi functions as its methods and call these methods in the Taichi scope.

```
@ti.dataclass
class Sphere:
   center: vec3
   radius: float
   def area(self): # Defines a Taichi function as method
       return 4 * math.pi * self.radius**2
@ti.kernel
def test():
   sphere = Sphere(vec3(0), radius=1.0)
   print(sphere.area())
```

Performance tuning

Kernel profiler (CPU and CUDA only): To analyze the performance of Taichi kernels

ti.init(ti.cpu, kernel_profiler=True) ti.profiler.print_kernel_profiler_info()

Configure loops:

API

To serialize the outermost for loop that immediately follows the

```
ti.loop_config(serialize=True)
```

To designate No. of threads on the CPU backend

ti.loop_config(parallelize=8)

To designate No. of threads in each block of the GPU backend

Commonly-used functions

ti.acos(x), ti.asin(x), ti.atan2(x), ti.ceil(x), ti.clamp(x, xmin, xmax), ti.cos(x), ti.cross(x, y), ti.dot(x,y), ti.exp(x), ti.floor(x),ti.fract(x), ti.inverse(mat), ti.norm(x), ti.log(x), ti.max(x, y, ...), ti.min(x, y, ...), tm.mod(x,y), tm.normalize(x), tm.pow(x, a), ti.round(x), ti.sign(x), ti.sin(x), tm.smoothstep(e0, e1, x), ti.sqrt(x), tm.step(edge, x),ti.tan(x), ti.tanh(x), tm.degrees(x), tm.radians(x)

Operators

comparison operators ==,!=,>,<,>=,<=

logical operators not, or, and

bitwise operators

~, &, ^, |, «, »

Visualization

GUI system

gui = ti.GUI('Window Title', (640, 360)) # Creates a window
while not gui.get_event(ti.GUI.ESCAPE, ti.GUI.EXIT):
 gui.show() # Displays the window

GGUI system

pixels = ti.Vector.field(3, float, (640, 480)) window = ti.ui.Window("Window Title", (640, 360))# Creates a canvas = window.get_canvas() # Creates a canvas while window.running: canvas.set_image(pixels) window.show()

API

ti.loop_config(block_dim=16)

Debugging

Activate debug mode:

```
ti.init(arch=ti.cpu, debug=True)
```

Runtime print in Taichi scope:

```
@ti.kernel
def inside_taichi_scope():
    x = 256
    print('hello', x) #=> hello 256
```

Runtime assert in Taichi scope:

```
ti.init(arch=ti.cpu, debug=True)
x = ti.field(ti.f32, 128)
@ti.kernel
def do_sqrt_all():
    for i in x:
        assert x[i] >= 0
        x[i] = ti.sqrt(x[i])
```

Compile-time static-print:

```
x = ti.field(ti.f32, (2, 3))
y = 1

@ti.kernel
def inside_taichi_scope():
    ti.static_print(y) # => 1
    ti.static_print(x.shape) # => (2, 3)
    ti.static_print(x.dtype) # => DataType.float32
```

Compile-time static-assert:

```
@ti.func
def copy(dst: ti.template(), src: ti.template()):
    ti.static_assert(dst.shape == src.shape, "copy() needs
    src and dst fields to be same shape")
    for I in ti.grouped(src):
        dst[I] = src[I]
```

Serial execution:

To serialize the program

```
ti.init(arch=ti.cpu, cpu_max_num_threads=1)
```

To serializes the for loop that immediately follows the line

```
ti.loop_config(serialize=True)
```

Access a conciser version of traceback message:

```
import sys
sys.tracebacklimit = 0
```