

Installation

pip install taichi ti example

Quick start

import taichi as ti
ti.init()

@ti.kernel
def monte_carlo_pi() -> float:
 total = 0
 for i in range(1000000):
 x = ti.random()
 y = ti.random()
 if (x*x + y*xy) < 1:
 total + 1

 return 4 * total / n</pre>

Supported backends

ti.cpu, ti.cuda, ti.metal, ti.opengl, ti.vulkan Choose a backend

ti.init(arch=ti.cuda)

Run in debug mode

ti.init(debug=True)

Data types

primitive tyes

i8, i16, i32, i64, u8, u16, u32, u64, f16, f32, f64

types.vector(n, dtype)

vec3 = ti.types.vector(3, float)
v = vec3(1, 2, 3)

types.matrix(n, m, dtype)

mat2x2 = ti.types.matrix(2, 2, float)m = mat2x2(1, 2, 3, 4)

types.struct(**kwargs)

sphere = ti.types.struct(center=vec3, radius=
 float)
s = sphere(vec3(1, 2, 3), 1.0)

Quant types

typecating

```
x = 1.0
y = ti.u8(x)
v = vec3(0.5, 1.0, 1.5)
w = v.cast(int)
```

Operators

comparison operators ==,!=,>,<,>=,<=

logical operators not, or, and

bitwise operators

~, &, ^, |, «, »

Data container

field(dtype, shape, ...)

f = ti.field(int, shape=(3, 3, 3))

Vector.field(dim, dtype, shape, ...)

f = ti.Vector.field(3, float, (10, 10))

Matrix.field(dim, dtype, shape, ...)

f = ti.Matrix.field(3, 3, float, shape=(10, 10))

Struct.field(dict, shape)

fill(val) to set a field

f.fill(1)

from_numpy(arr) to copy data from a NumPy array

f.from_numpy(arr)

to_numpy(arr) to convert to a NumPy array

arr = f.to_numpy()

Kernels and functions

@ti.kernel : Called from Python scope. Require type hints for arguments and return values. Can return scalar, vector and matrix.

@ti.func: Called from Taichi scope. Recommend type hints for arguments and return values. Can return scalar, vector, matrix and struct.

Top level for loops in a kernel are automatically parallelized

Force a top level for loop to execute in serialize

```
x = ti.field(int, 100)
@ti.kernel
def example():
    ti.loop_config(serialize=True)
    for i in range(100):
    ...
```

Interactive with Numpy arrays

Data-oriented programming

data-oriented class

A data-oriented class is used when your data is actively updated in the Python scope (such as current time and user input events) and tracked in Taichi kernels.

dataclass

A dataclass is a wrapper of 'ti.types.struct'. You can define Taichi functions as its methods and call these methods in the Taichi scope.

```
@ti.dataclass
class Sphere:
    center: vec3
    radius: float

    @ti.func
    def area(self): # Defines a Taichi function
        as method
        return 4 * math.pi * self.radius**2

@ti.kernel
def test():
    sphere = Sphere(vec3(0), radius=1.0)
    print(sphere.area())
```

Commonly-used math functions

ti.acos(x), ti.asin(x), ti.atan2(x), ti.ceil(x),

ti.clamp(x, xmin, xmax), ti.cos(x), ti.cross(x, y), ti.dot(x,y), ti.exp(x), ti.floor(x),ti.fract(x), ti.inverse(mat), ti.norm(x), ti.log(x), ti.max(x, y, ...), ti.min(x, y, ...), tm.mod(x,y), tm.normalize(x), tm.pow(x, a),

ti.round(x), ti.sign(x), ti.sin(x), tm.smoothstep(e0, e1, x), ti.sqrt(x),

tm.step(edge, x),ti.tan(x), ti.tanh(x), tm.degrees(x), tm.radians(x)

Global settings

Set default precision

ti.init(default_fp=ti.f64) ti.init(default_ip=ti.i64)

Set random seed

ti.init(random_seed=0)

Set offline-cache

ti.init(offline_cache=False)

Set packed mode

ti.init(packed=True)

Visualization

GUI system

gui = ti.GUI('Window Title', (640, 360)) #
 Creates a window
while not gui.get_event(ti.GUI.ESCAPE, ti.GUI.
 EXIT):
 gui.show() # Displays the window

GGUI system

pixels = ti.Vector.field(3, float, (640, 480))
window = ti.ui.Window("Window Title", (640, 360))
Creates a window
canvas = window.get_canvas() # Creates a canvas
while window.running:
 canvas.set_image(pixels)
 window.show()
window.save_imgae(filename)

2D Canvas drawing API

3D scene drawing API

scene.lines(vertices, width, indices, color,
 per_vertex_color)
scene.mesh(vertices, indices, normals, color,
 per_vertex_color)
scene.particles(vertices, radius, color,
 per_vertex_color)

Performance tuning

Kernel profiler (CPU and CUDA only): To analyze the performance of Taichi kernels

```
ti.init(ti.cpu, kernel_profiler=True)
ti.profiler.print_kernel_profiler_info()
```

Configure loops:

API

To serialize the outermost for loop that immediately follows the line

ti.loop_config(serialize=True)

To designate No. of threads on the CPU backend

ti.loop_config(parallelize=8)

To designate No. of threads in each block of the GPU backend

ti.loop_config(block_dim=16)

Debugging

API

Activate debug mode:

```
ti.init(arch=ti.cpu, debug=True)
```

Runtime print in Taichi scope:

```
@ti.kernel
def inside_taichi_scope():
    x = 256
    print('hello', x) #=> hello 256
```

Runtime assert in Taichi scope:

```
ti.init(arch=ti.cpu, debug=True)
x = ti.field(ti.f32, 128)
@ti.kernel
def do_sqrt_all():
    for i in x:
        assert x[i] >= 0
        x[i] = ti.sqrt(x[i])
```

Compile-time static-print:

```
x = ti.field(ti.f32, (2, 3))
y = 1

@ti.kernel
def inside_taichi_scope():
    ti.static_print(y) # => 1
    ti.static_print(x.shape) # => (2, 3)
    ti.static_print(x.dtype) # => DataType.
    float32
```

Compile-time static-assert:

```
@ti.func
def copy(dst: ti.template(), src: ti.template()
    ):
    ti.static_assert(dst.shape == src.shape, "
        copy() needs src and dst fields to
        be same shape")
    for I in ti.grouped(src):
        dst[I] = src[I]
```

Serial execution:

To serialize the program

```
ti.init(arch=ti.cpu, cpu_max_num_threads=1)
```

To serializes the for loop that immediately follows the line

```
ti.loop_config(serialize=True)
```

Access a conciser version of traceback message:

```
import sys
sys.tracebacklimit = 0
```

Getting help