GUI_ProjectRename – Rename a Project

Revision history

2017-04-04	Don Ferguson	Original draft
2018-06-12	Rod Thompson	Add 'Issues' from JL
		Replace 'screen' with 'window
		Replace BR_PanelConfig with BR_WindowConfig
		Revise REQUIRED SERVICES – Dependencies
		Add Mockup graphics
		Add Process Flow Chart
		Add Windows Interaction Map
		Add EVENT ACTIONS
		Add WARNING MESSAGES
2018-06-14	Rod Thompson	Replace Process Flow Chart
		Add project fileset information in Issues
		Replace Window Interaction Map
		Add to REQUIRED SERVICES – Dependencies
		Edit icon actions
2018-07-01	Rod Thompson	Revise SCOPE, Add PROJECT FILESET
		Replace graphic
		Update REQUIRED SERVICES - Dependencies
		Replace Process flowchart
		Replace Window Interaction Map
		Revise Server messages
2018-11-16	Rod Thompson	Replace Window Interaction Map
		Replace graphic
		Update REQUIRED SERVICES
		remove 03.68, add 07.11
		LOOK & FEEL – Add detail
		Add section LOGGING
		Amend EVENT ACTIONS re window configuration
		Add sections USE CASES and TESTING
		Add detail to WARNING CONDITIONS
		Add NOTES section

SCOPE

This GUI module is called from the Main Menu (GUI_UserInterface) to rename an HRE project. Actions only involve a change to the Project name, and records of this name and the change. Assumption – the Project name can be changed while the Project is open, without any adverse impact.

PROJECT FILESET

A set of files required for normal use of HRE projects consists of:

- an H2 database
- A 'User' Auxiliary file
- A 'Project' Auxiliary file
- folders of external files (images, etc) [optional].

Refer to 03.32 Overview – Auxiliary (Non Database) Files for details.


NOTES

No issues are foreseen in the process of 'Backup' of the renamed project. See additional notes in the Project Close and Project Backup module specifications.

LOOK AND FEEL

The window has 4 horizontal parts:

- A scrollable display area which allows the selection of a file from the displayed list
- An entry area for the new project name
- The buttons "Rename" and "Cancel"
 - o "Rename" performs the rename functions on the selected project
 - o "Cancel" exits without action
- A display area of the status of the rename.




PROJECT RENAME Window - Mockup

Shape, Size, Color, Layout etc. determined in design. On screen location

Initially inherited from the HRE main display

Window located immediately below the Project menu button

On screen location and scale are the only User changeable settings



ACTIONS

The fundamental operations are:

- 1. Open the window according to its saved window Layout (BR_WindowConfig)
- 2. Allow user to find and select the project to be renamed
- 3. Ask for a new project name
- 4. If single user project, perform the rename of the project:
 - Within the H2 database
 - Within the Project AUX file, Project entry
 - Within the User AUX file, Project entry.
- 5. If not a single user project, then:
 - Check the number of concurrent users of the selected project

- If more than one, prevent any new logins
- Seek other user permissions to rename
- Schedule a rename project task in the server to update the database and Project AUX file
- Notify every user of the project when it is completed.

USED BY

All HRE users.

DATA CONTROLLED BY THIS MODULE

1. None.

REQUIRED DATA CONTROLLED BY OTHER MODULES

1. None.

REQUIRED SERVICES - Dependencies

First-Order Dependencies	Second-Order Dependencies	Higher-Order Dependencies
05.31 GUI_Output	Needed	
05.40 GUI_Reminder	03.68 GUI_SelectConfiguration	NIL
	05.02 GUI_EncodedStringEdit	05.08 GUI_FieldDefinitionEdit
		05.42 GUI_SubsititutionEdit
		07.26 BR_Substitution
		07.24 BR_Setting
		07.17 BR_WindowConfig
	07.01 BR_EncodedString	NIL
	07.24 BR_Setting	BR_AppData
		BR_UserData
		07.02 BR_EntityLink
	07.17 BR_WindowConfig	07.06 BR_GuiElement
		07.02 BR_EntityLink
		07.29 BR_Translation
		BR_FieldTranslation
		07.16 BR_Message Patterns
	07.02 BR_EntityLink	Needed
07.17 BR_WindowConfig	07.06 BR_GuiElement	07.01 BR_EncodedString
		07.02 BR_EntityLink
		BR_FieldTranslation
		07.16 BR_MessagePattern
	07.02 BR_EntityLink	Needed
	07.29 BR_Translation	07.02 BR_EntityLink
		BR_Field
		07.06 BR_GUIElement
		07.16 BR_MessagePatterns
	07.16 BR_MessagePatterns	07.02 BR_EntityLink
		07.01 BR_EncodedString
		07.11 BR_Logging
		Call Stack
		07.24 BR_Setting
07.24 BB Brainst	OZ OC DD. Cuiffers and	GUI Translation
07.21 BR_Project	07.06 BR_GuiElement	As above
	07.02 BR_EntityLink	As above
	07.29 BR_Translation	As above
07.11 DD Loggic -	07.03 BR_FieldDefinition	Noodod
07.11 BR_Logging	07.01 BR_EncodedString	Needed
	07.02 BR_EntityLink	Needed
	BR_FieldTranslation	O7 O2 DD. Fostitul indi
	07.26 BR_Substitution	07.02 BR_EntityLink
		07.29 BR_Translation

APPLICATION PROGRAMMING INTERFACE (API)

1. Need Details.

LOGGING

Use of this module will create log entries.

Commit Logging

This occurs for each of the following functions – in the listed tables:

The course of th		
Function	Database Table	
Close Session	128	
Project – New name	204	
Move and/or resize window	305/306?	

General Log

This includes:

• Project Rename.

EVENT ACTIONS

- Keyboard actions
 Add new Project name
- 2) Mouse actions

Drag and drop mouse actions to move and resize the window Setting changes saved to database for User>Project>Window Left key

- a. click on Server name pulldown expands Server list, and allows selection
- b. click on the Browse button opens the Windows Explorer allowing the user to view the file system to select an existing Folder and Filename, or enter a new Filename
- c. click on the 'Summary' button invokes the GUI_Project Summary module
- d. click on the 'Cancel' or 'Delete' button, operates the button
- e. click on icons (detailed below)

Right key

To be determined

- 3) Icon actions
 - a. left mouse key click on icons in the Window Control group:
 - a. 'X' icon

(closes the window)

NOTE: Same action as in use of the 'Cancel' button

b. 'Box' icon

Toggles the window size between full window, and the preset window size

c. 'Dash' icon

Minimizes the window, to an icon on the window toolbar.

A click on the toolbar icon restores the display to its previous setting

- b. left mouse key click on 'Reminder' icon:
 - (opens 'Reminder' window for this 'Project Rename' process)
- c. left mouse click on 'Help' icon:

(opens the Help System, searches for the section on 'Project Rename')

4) Keyboard shortcuts

To be determined

WARNING CONDITIONS

Display Location: centered on the GUI ProjectRename window

1. When the 'Cancel' button is used, then a warning message is displayed. Warning Message (WM-PR1)

Press CANCEL to return to this window for further attention.	
Press OK to proceed with the Cancel process, which closes this v	window.

Text Version WARNING

Either no project has been selected, or if selected, no further action is required. Press CANCEL to return to this window for further attention.

Press OK to proceed with the Cancel process, which closes this window.

Server scenario

Created in and sent from Server to Client

Created in and sent from Server to Client			
Message	Subject:	Project Rename	
M_S_C_1	From:	Server	
	Text Message:		
Uses Server Broadcast Message Pattern GUI_Message (SB)	You do not hav	e the 'RIGHTS' to rename the project.	
	Requested by:	User name	
Sent to one Client User initiating the	Project name:		
'rename' process	Project folder:	Folder name	
·	Project filenam	e: Filename	
Message	Subject:	Project Rename	
M S C 2	From:	Server	
WI_3_C_2	Text Message:	Sciver	
Uses Server Broadcast Message Pattern	_	a queued – multiple users	
GUI_Message (SB)		Project rename queued – multiple users. Rename will occur when all users are disconnected	
GOI_IVICSSUGE (SD)	from the project		
Sent to all current users of the selected	nom the projec		
project	Requested by:	User name	
project	Project name:		
	Project folder:	-	
	Project filenam		
	Troject menam	e. Thename	
Message	Subject:	Project Rename	
M_S_C_3	From:	Server	
	Text Message:		
Uses Server Broadcast Message Pattern GUI_Message (SB)	Project rename	e completed.	
GOI_IVIESSAGE (SD)	Requested by:	User name	
Sent to one Client User initiating the	Project name:		
process	-		
process	Project folder: Folder name Project filename: Filename		
	Froject menam	e. Heriame	
Message	Subject:	Project Rename	
M_S_C_4	From:	Server	
	Text Message:		
Uses Server Broadcast Message Pattern GUI Message (SB)	_	s been renamed.	
	Requested by:	User name	
Sent to all Client Users (except initiator)	Project name:		
recorded in the Project AUX file, with	Project folder:		
access to this project	Project filenam		
Queued till next Login			
Message	Subject:	Project Rename	
M_S_C_5	From:	Server	

Uses Server Broadcast Message Pattern GUI_Message (SB)

Sent to the Administrator, advise of the attempt by a User without rights to rename a Project

For Administrator action

Text Message:

A request was made to rename this Project by the User, without RIGHTS.

Requested by: User name

Project name: Project name

Project folder: Folder name

Project filename: Filename

Message window location: centred on the GUI_ProjectRename window Message window location (for Administrator) - how to deal with this??

Message designator:

- 1) M_ signifies a message
- 2) X_ source
- 3) Y_ destination
- 4) Z distinguishing number for this window

Messages from the Server to the Client utilize the Server Broadcast Message Pattern. Such messages result in a window opening on the client, to display information (detailed above) That specification requires amendment to allow use for sending to selected Users.

Use (or otherwise) of Warning Messages in HRE is a User controlled preference, set through the Application Settings management module.


Where applicable in the operation of HRE, Warning Messages are generated.

According to the User preference for these, the display of such messages is bypassed, with action taken by the software equivalent to the User operation of the OK button.


ERROR CONDITIONS


1. Need to record the condition that raised the error, example message and possible next steps.

WINDOWS INTERACTION MAP



PROCESS FLOW CHART





USE CASES

TESTING

Testing to prove the functionality of this module in use with others of the HRE application. Limited 'Project' functionality (see below).

Prior testing of the module in the code development process is assumed.

General requirements	Code element requirements	
HRE installation	Main GUI	
1) Single computer	Project Open	
2) Client-Server	Project Close	
3) Test Project database fileset	Project Rename	
	ExitHRE	

Process

- 1) Run HRE
 - a. Open the Test Project
 - b. Rename the Project
 - c. Close the Project
 - d. Open the newly named Project
 - e. Close the Project
 - f. Exit HRE
- 2) Check result (how?)

See Test Plan document.