

#### **CIS 657 – Principles of Operating Systems**

Topic: Memory – Swapping

**Endadul Hoque** 

#### Acknowledgement

- Youjip Won (Hanyang University)
- OSTEP book by Remzi and Andrea Arpaci-Dusseau (University of Wisconsin)

# BEYOND PHYSICAL MEMORY: MECHANISMS

#### **Revisit: Assumptions**

- An address space is small and fits into physical memory
- The address space of each running process ALL fit into physical memory
- All pages reside in physical memory

#### **Revisit: Assumptions**


- An address space is small and fits into physical memory
- The address space of each running process ALL fit into physical memory
- All pages reside in physical memory

#### **Focus:**

- How to support <u>many</u> concurrently-running <u>large</u> address spaces?
- How to leverage a larger (slower) device to transparently provide the <u>illusion of a large virtual</u> <u>address space</u>?

#### **Memory Hierarchy**

- Require an additional level in the memory hierarchy.
- OS needs a place to stash away portions of address space that currently aren't in great demand.
- Such a location should have more capacity, but it is generally slower
- In modern systems, this role is usually served by a hard disk drive




#### Single large address-space for a process

- Programming convenience and ease-of-use
  - Otherwise, we always need to first arrange for the code or data to be in memory before calling a function or accessing data.

- To Beyond just a single process.
  - The addition of swap space allows the OS to support the illusion of a large virtual memory for multiple concurrently-running processes

#### **Swap Space**

- Reserve some space on the disk for moving pages back and forth.
  - Swap pages out of memory to it and Swap pages into memory from it
- OS reads from and writes to the swap space, in page-sized unit
  - Need to remember the disk address of a given page



**Physical Memory and Swap Space** 

#### **Present Bit**

- Add some machinery higher up in the system in order to support swapping pages to and from the disk.
  - When the hardware looks in the PTE, it may find that the page is not <u>present</u> in physical memory.

Value	Meaning		
1	page is present in physical memory		
0	The page is not in memory but rather on disk.		

#### The Page Fault


- Accessing page that is not in physical memory.
  - If a page is <u>not present</u> and has been <u>swapped to disk</u>, the OS needs to **swap the page into memory** in order to <u>service the page fault</u>.
    - Using a page-fault handler

#### What if (physical) memory is full?

- The OS like to <u>swap out pages</u> to **make room** for the new pages the OS is about to bring in.
  - The process of picking a page to kick out, or replace is known as page-replacement policy

#### **Page Fault Control Flow**


PTE's PFN is used to hold the disk address of the page in swap space.



**Virtual Address** 

#### **Page Fault Control Flow**

PTE's PFN is used to hold the disk address of the page in swap space.



**Virtual Address** 

#### Page Fault Control Flow – Hardware

```
VPN = (VirtualAddress & VPN_MASK) >> SHIFT
1:
2:
         (Success, TlbEntry) = TLB Lookup(VPN)
3:
         if (Success == True) // TLB Hit
4:
         if (CanAccess(TlbEntry.ProtectBits) == True)
5:
                  Offset = VirtualAddress & OFFSET MASK
                  PhysAddr = (TlbEntry.PFN << SHIFT) | Offset</pre>
6:
7:
                  Register = AccessMemory(PhysAddr)
8:
         else RaiseException(PROTECTION_FAULT)
```

#### **Page Fault Control Flow – Hardware**

```
else // TLB Miss
9:
10:
        PTEAddr = PTBR + (VPN * sizeof(PTE))
11:
        PTE = AccessMemory(PTEAddr)
12:
        if (PTE.Valid == False)
13:
                 RaiseException(SEGMENTATION FAULT)
        else
14:
15:
        if (CanAccess(PTE.ProtectBits) == False)
16:
                 RaiseException(PROTECTION FAULT)
17:
        else if (PTE.Present == True)
18:
        // assuming hardware-managed TLB
19:
                 TLB_Insert(VPN, PTE.PFN, PTE.ProtectBits)
20:
                 RetryInstruction()
        else if (PTE.Present == False)
21:
22:
                 RaiseException(PAGE_FAULT)
```

#### **Page Fault Control Flow – Software**

```
1: PFN = FindFreePhysicalPage()
2: if (PFN == -1) // no free page found
3: PFN = EvictPage() // run replacement algorithm
4: DiskRead(PTE.DiskAddr, PFN) // sleep (waiting for I/O)
5: PTE.present = True // update page table with present
6: PTE.PFN = PFN // bit and translation (PFN)
7: RetryInstruction() // retry instruction
```

- The OS must find a free physical frame for the soonbe-swapped-in page.
- If there is no such page, waiting for the replacement algorithm to run and kick some pages out of memory.

#### When Replacements Really Occur

- OS waits until memory is entirely full, and only then replaces a page to make room for some other page
  - This is a little bit unrealistic, and there are many reason for the
     OS to keep a small portion of memory free more proactively.
- Swap Daemon, Page Daemon
  - There are fewer than LW pages available, a background thread that is responsible for freeing memory (page frames) runs.
  - The thread evicts pages until there are HW pages available.

**Swapping: policies** 

#### **Beyond Physical Memory: Policies**

- <u>Memory pressure</u> forces the OS to start paging out pages to make room for actively-used pages.
- Deciding which page to <u>evict</u> is encapsulated within the replacement policy of the OS.

In this discussion, <u>physical memory</u> can "technically" be viewed as a **cache** for <u>virtual pages</u>

#### **Cache Management**

- Goal in picking a replacement policy for this cache is to minimize the number of <u>cache misses</u>.
- The number of cache hits and misses let us calculate the <u>average memory access time</u> (AMAT).

$$AMAT = T_M + (P_{Miss} * T_D)$$

Argument	Meaning	
$T_{M}$	The cost of accessing memory	
$T_D$	The cost of accessing disk	
$P_{Miss}$	The probability of not finding the data in the cache(a miss)	

#### The Optimal Replacement Policy

- Leads to the fewest number of misses overall
  - Replaces the page that will be accessed <u>furthest in the</u> <u>future</u>
  - Resulting in the fewest-possible cache misses
- Serve only as a comparison point, to know how close we are to perfect

# **Tracing the Optimal Policy**

**Reference Row** 

0 1 2 0 1 3 0 3 1 2 1

Physical memory holds **3** frames

Access	Hit/Miss?	Evict	Resulting Cache State
0	Miss		0
1	Miss		0,1
2	Miss		0,1,2
0	Hit		0,1,2
1	Hit		0,1,2
3	Miss	2	0,1,3
0	Hit		0,1,3
3	Hit		0,1,3
1	Hit		0,1,3
2	Miss	3	0,1,2
1	Hit		0,1,2

**Hit rate** is 
$$\frac{Hits}{Hits+Misses} = 54.6\%$$

**Future** is not known.

#### A Simple Policy: FIFO

- Pages were placed in a queue when they enter the system.
- When a replacement occurs, the page at the tail of the queue (the "First-in" pages) is evicted.
  - It is simple to implement, but can't determine the importance of blocks.

#### **Tracing the FIFO Policy**

**Reference Row** 

0 1 2 0 1 3 0 3 1 2 1

Physical memory holds **3** frames


Access	Hit/Miss?	Evict	Resulting Cache State
0	Miss		0
1	Miss		0,1
2	Miss		0,1,2
0	Hit		0,1,2
1	Hit		0,1,2
3	Miss	0	1,2,3
0	Miss	1	2,3,0
3	Hit		2,3,0
1	Miss		3,0,1
2	Miss	3	0,1,2
1	Hit		0,1,2

Hit rate is  $\frac{Hits}{Hits+Misses} = 36.4\%$ 

Even though page 0 had been accessed a number of times, FIFO still kicks it out.

#### **BELADY'S Anomaly**

• We would expect the cache hit rate to increase when the cache gets larger. But in this case, with FIFO, it gets worse.



#### **Another Simple Policy: Random**

Picks a random page to replace under memory pressure.

 It doesn't really try to be too intelligent in picking which blocks to evict.

Random does depends entirely upon how lucky <u>Random</u> gets in

its choice.


Physical memory holds **3** frames

Reference Row 0 1 2 0 1 3 0 3 1 2 1

Access	Hit/Miss?	Evict	Resulting Cache State
0	Miss		0
1	Miss		0,1
2	Miss		0,1,2
0	Hit		0,1,2
1	Hit		0,1,2
3	Miss	0	1,2,3
0	Miss	1	2,3,0
3	Hit		2,3,0
1	Miss	3	2,0,1
2	Hit		2,0,1
1	Hit		2,0,1

#### **Performance of Random Policy**

 Sometimes, Random is as good as optimal, achieving 6 hits on the example trace.



**Random Performance over 10,000 Trials** 

#### **Using History**

- Lean on the past and use <u>history</u>.
  - Two type of historical information.

Historical Information	Meaning	Algorithms
recency	The <b>more recently</b> a page has been accessed, the more likely it will be accessed again	LRU
frequency	If a page has been <b>accessed many times</b> , it should not be replaced as it clearly has some value	LFU

# **Using History: LRU**

Replaces the least-recently-used page.

 Reference Row
 0
 1
 2
 0
 1
 3
 0
 3
 1
 2
 1

Physical memory holds **3** frames

Access	Hit/Miss?	Evict	Resulting Cache State
0	Miss		0
1	Miss		0,1
2	Miss		0,1,2
0	Hit		1,2,0
1	Hit		2,0,1
3	Miss	2	0,1,3
0	Hit		1,3,0
3	Hit		1,0,3
1	Hit		0,3,1
2	Miss	0	3,1,2
1	Hit		3,2,1

#### **Implementing Historical Algorithms**

- To keep track of which pages have been least-andrecently used, the system has to do some accounting work on <u>every memory reference</u>.
  - Add a little bit of hardware support.


#### **Approximating LRU**

- Require some hardware support, in the form of a <u>use</u>
   <u>bit</u>
  - Whenever a page is referenced, the use bit is set by hardware to 1.
  - Hardware never clears the bit, though; this is the responsibility of the OS
- Clock Algorithm
  - All pages of the system arranges in a circular list.
  - A clock hand points to some particular page to begin with.

#### **Clock Algorithm**

When a page fault occurs, the page the hand is pointing to is inspected.

The action taken depends on the Use bit



The algorithm continues until it finds a use bit that is set to 0.

#### **Considering Dirty Pages**

- The hardware include a modified bit (a.k.a dirty bit)
  - Page has been <u>modified</u> and is thus <u>dirty</u>, it must be written back to disk to evict it.
  - Page has not been modified, the eviction is free.

#### **Reading Material**

 Chapter 21-22 of OSTEP book – by Remzi and Andrea Arpaci-Dusseau (University of Wisconsin)
 http://pages.cs.wisc.edu/~remzi/OSTEP/vm-beyondphys.pdf
 http://pages.cs.wisc.edu/~remzi/OSTEP/vm-beyondphys-policy.pdf

# **Questions?**