# Advanced interpretation techniques



# Faster interpretation

- Interpretation as described earlier involves a lot of overhead, as bytecodes are fetched, decoded and then dispatched to their corresponding actions.
- Example: Step through a bytecode sequence (a+b) in your interpreter and see how much effort is done compared to the useful work.

#### 1. Threaded code

- One way to decrease the cost of interpretation is to fetch and decode only once, compute an address for an action routine, and then use the addresses directly in subsequent executions.
- This is called threaded code, and was originally described in [Bell 73] — as a technique for a compiler!

This piece of code is really difficult to be implemented by c. since c is still a Before and after threading with-level language. Example: x = y + z

```
threaded program (in data memory):
bytecode program (in data memory):
push local0
                                        .word
                                        &pushLocal0
push local1
                                        &pushLocal1
add
                                        &add
pop local2
                                        &popLocal2
high-level code of interpreter:
                                        interpreter loop (RISC-like assembly):
loop {
                                        Loop: load [Rpc], Rtarget
 get next bytecode b
                                               jump Rtarget
 switch(b) {
                                        actions (assembly):
 case push: ...;
 case add: ...;
                                           ; push local0 on to stack
 case pop: ...;
                                          add Rpc, BPW, Rpc
                                             ;inc Rpc by BytesPerWord
                                          jump Loop
```

# Eliminating the loop

```
threaded program in data memory:
&pushLocal0
&pushLocal1
&add
&popLocal2
interpreter loop (assembly):
not needed; just set Rpc to first program address and jump through it
actions (assembly):
pushLocal0:
  ; push local0 on to stack
  add Rpc, BPW, Rpc
  load [Rpc], Rtarget
  jump Rtarget
```

# Eliminating the loop

```
&add
&popLocal2
interpreter loop (assembly):
not needed; just set Rpc to first program address and jump through it
actions (assembly):
pushLocal0:
  ; push local0 on to stack
  add Rpc, BPW, Rpc
  load [Rpc], Rtarget
```

threaded program in data memory:


&pushLocal0

&pushLocal1


jump Rtarget

This three-instruction sequence is often a single CISC instruction

#### Control flow



#### Control flow



#### Alternative using executable code (calls)

```
program (directly executable):
call pushLocal0
call pushLocal1
call add
call popLocal2
```

interpreter loop: not needed

In this scheme we're using native call-ret to elide Rpc and the associated instructions.

Manipulation of the return address is required to implement branches, or, simply insert direct branches within the instruction stream.


Q. Is this interpretation or compilation? If compilation, when did we cross the line?

# Generating the threaded code from bytecode

- To generate the threaded code, we run an abstract interpreter over the bytecode which emits the addresses of the action routines.
- We may then be able to discard the bytecode; or, we can generate threaded code into a cache and discard it as needed.

In the original paper, the technique was to be used by a compiler: it would emit the threaded code, and also generate specialized action routines (so that only the ones that were needed were emitted).






If all the action routines have to exist before execution (e.g., we want to avoid generating code at run-time), how do you avoid a massive number of slightly different variants? (eg push local 0, push local 1, push local 2, ...)

#### Indirect threaded code

• [Dewar 75] solves the problem by adding an indirection.

Fig. 2. Example of Indirect Threaded Code.



#### Indirect threaded code

```
&pushB
&pushC
&add
&popB
```

pushB: &push

popB: &pop

B: .word 0


pushC: &push

popC: &pop

C .word 0

add: @addCore

Fig. 2. Example of Indirect Threaded Code.



#### push:

```
;push [[Rpc]+2BPW] onto stack
add Rpc,BPW,Rpc
load [Rpc], Rtarget
load [Rtarget],Rtarget
jump Rtarget
```

#### Problems

- This scheme is fine for old FORTRAN (statically allocated variables) but unattractive for languages that need a function stack, or which contain complex data types — we'd need to create pointers to getters and setters for every stack slot and data object.
- Can use the "map trick" at the cost of another indirection.

### Alternatively...

- We decompose a complex bytecode into simpler pieces.
   E.g., instead of a branch-to-offset-n bytecode, we can push n onto the expression stack and then have a generic branch that takes the offset from the stack.
- We can use this trick with indirect threading, to implement, e.g., activation record getters and setters.

The price to be paid is slower execution and bulkier code

#### Threaded code in practice

- Threaded code was adopted by the Forth language, which was at one time very popular in control applications.
- It was also adopted for PostScript, which is the underlying graphics language of PDF — so you use a threaded code interpreter every time you render a PDF.

# PostScript sample

```
Post Script
/ncols 2 def
/nrows 10 def
/colsize 72 4 5 32 div add mul def % 4 5/32"
/rowsize 72 1 mul def % 1"
/origin{dup % n => n n
nrows idiv colsize mul exch % n n => (n/nrows)*colsize n
nrows mod nrows exch sub rowsize mul % n=>(nrows-(n%nrows))*rowsize
moveto 0 -27 rmoveto}def
/nextpos {cy add exch cx add exch moveto pop}def % c px py => moveto(cx+px,cy+py)
```

Adobe Systems Incorporated

#### 2. Stack caching


- In a bytecoded stack machine, most bytecodes manipulate the item on the top of the stack.
- Implemented naively, this results in each bytecode doing a load and/or store to the current top of stack.
- One optimization is to cache the top of stack in a register, and rewrite the bytecodes to use the register; this usually means writing in assembly.

#### Variants on stack caching

- If the underlying hardware partitions its register set among different types (e.g., integer, floating point, address) then it may be impractical to choose a single register for the top-of-stack cache.
- In this case, the top-of-stack can be held in the most convenient register location based on its type. Some state-tracking code may be required; or if the bytecode set allows, this may be inferred from the abstract stack state (e.g., in Java, the type of the top of stack is always constant for a particular bytecode instruction).

### Multiple dispatch tables

- Even if the TOS state is known for each bytecode, how do you take advantage of that?
- Example: consider two dup bytecodes in a Java class file; one is known to dup an int, the other a float, but they have the same opcode.
- One technique is to have multiple complete bytecode dispatch tables, one per state, indexed by opcode, and to switch between them when necessary.



# 3. Making a bytecode instruction do more

- Another way to reduce interpreter overhead is to make each instruction do more, thereby diminishing the relative overhead of bytecode dispatch.
- In some systems, a single bytecode instruction can accomplish a great deal of work. Examples:
  - In Smalltalk-80, the BitBLT instruction is used to copy and blend rectangular areas on the display or in off-screen bitmaps
  - In R, and especially its predecessor, S, the bytecodes were seen as a glue to connect statistical operations on vectors, expressed in FORTRAN, C or C++.

# Superinstructions

- Another way to achieve this is to synthesize superinstructions from common sequences of bytecodes.
- This can be done programmatically, by analyzing a corpus of bytecode programs to determine common patterns (pairs, triplets, and so on).
- Having done this, the bytecode compiler and interpreter can be modified to emit and execute, resp., these superinstructions; or a single pass over original bytecode can be used to transform the patterns into the new instructions.

### Example

- The sequence *pushLocal x; inc; popLocal x* can be replaced by a single instruction *incLocal x*.
- This is akin to making an instruction set CISCy.
  - Bigger opcodes

#### 4. Selective inlining

- Threaded code and superinstructions can be combined dynamically using *selective inlining* [PiumartaRiccardi98]:
- Concatenate the implementations of several bytecodes at runtime, and install a threaded code pointer to them, replacing the original bytecode entries.

```
dynamic_opcode_push3_push4_add:
compiled code:
                                                    *++stackPointer = 3;
                                                    *++stackPointer = 4;
 void *code[] = { ...,
                                                    stackPointer--;
    kkopcode_push3,
                                                    *stackPointer += stackPointer[1];
    kkopcode_push4,
                                                    goto **++instructionPointer;
    &&opcode_add, ... };
                                                   Figure 4: Equivalent macro opcode for push3, push4, add.
opcode implementations:
  /* dispatch next instruction */
 #define NEXT() goto **++instructionPointer
    void **instructionPointer = code - 1;
    /* start execution: dispatch first opcode */
      NEXT():
    /* opcode implementations... */
    opcode_push3:
      *++stackPointer = 3:
      NEXT();
    opcode_push4:
      *++stackPointer = 4;
      NEXT():
    opcode_add:
      --stackPointer;
      *stackPointer += stackPointer[1];
      NEXT();
    /* ... */
```

Figure 2: Direct threaded code.

#### Details of selective inlining

- Assumes code to be copied is relocatable;
- Cannot contain relative branches outside the sequence;
- Control flow changes can only happen in the last bytecode; and
- Bytecodes that are branch targets must be at the head of a sequence.
- Example: consider only basic blocks.
- Can cache and reuse the generated macro opcodes

### Interpreter Generation

- Writing an efficient interpreter is pretty much impossible in a high-level language; you have to control the lowlevel details, many of which are not expressible, even in C.
- Another approach is to write an interpreter generator in a high-level language, which emits the machine code of the interpreter.
- Or, invent a DSL (Domain Specific Language).
- See, e.g., vmgen [EGKP02]

#### Putting it all together: the HotSpot interpreter(s)

- The HotSpot<sup>™</sup> JVM contains an interpreter generator that uses many of these techniques:
  - It uses stack caching with different states for each JVM type and per-type dispatch tables
  - The machine code of the bytecode action routines is generated at startup from descriptions in C++ (thinly disguised assembly). Instruction selection is done based on the actual CPU model.
  - It used to do selective inlining

#### Last word on interpretation

Applying all these tricks will definitely speed up an interpreter, but it will never approach the speed possible in optimizing compilation...our next topic.