Introduction to Mem. Management

Operating Systems

School of Data & Computer Science Sun Yat-sen University

Lecture Notes: os_sysu@163.com

Instructor: Guoyang Cai

email: isscgy@mail.sysu.edu.cn





Contents

- Basic Concepts
- Memory Management Requirements
 - Relocation
 - Protection
 - Sharing
 - Logical Organization
 - Physical Organization
- Memory Partitioning
 - Fixed Partitioning
 - Variable Partitioning
 - Buddy System




Background

- User programs must be brought (from disk) into memory and placed within a process for it to be run.
 - Memory Unit can sense only a stream of <addresses, read> requests, or <address, data, write> requests.
 - Main memory and registers are only storage that CPU can access directly.
 - Registers are accessed in one CPU clock (or less)
 - Main memory access can take many cycles, causing a stall.
 - Cache sits between main memory and CPU registers.
- Memory management is the task carried out by OS and hardware to accommodate multiple processes in main memory.
 - Protection of memory is required to ensure correct operation.

Hardware Address Protection

A pair of base register and limit register define the logical address space for a process.




5 / 61



Hardware Address Protection

CPU must check every memory access generated in user mode to be sure it is between base and limit for that user.






Address Binding

- Programs on disk form an *input queue* when they are ready to be brought into memory to execute.
 - How to allocate the first physical address of a user process? Always at 0...00?
- Further more, addresses are represented in different ways at different stages of a program's life.
 - Source code addresses are usually symbolic.
 - Compiled code addresses are bound to relocatable addresses.
 - e.g., "14 bytes from beginning of this module".
 - Linker or loader will bind relocatable addresses to absolute addresses.
 - e.g., 14 + 71000 = 71014.
 - Each binding maps one address space to another.



Address Binding


- Address binding of instructions and data to memory addresses can happen at three different stages of multistep Processing of a User Program.
 - Compile time: If memory location known a priori, absolute codes can be generated; recompiling needed if starting location changes.
 - Load time: If memory location is not known at compile time, relocatable codes are generated at load time.
 - Execution time: Binding delayed until run time if the process can be moved during its execution from one memory segment to another.
 - Need hardware support for address maps (e.g., base and limit registers).





Address Binding

Multi-step Processing of User Program.




Logical Address Space vs. Physical Address Space

- The concept of a logical address space that is bound to a separate physical address space is central to proper memory management.
 - Logical address generated by the CPU; also referred to as virtual address, is a reference to a memory location that is independent of the physical organization of memory. Logical address space is the set of all logical addresses generated by a program.
 - Physical address absolute address seen by the memory unit, is a physical location in main memory. Physical address space is the set of all physical addresses generated by a program.
- Logical and physical addresses are the same in compile-time and loadtime address-binding schemes; logical (virtual) and physical addresses differ in execution-time address-binding scheme.
 - Compilers produce code in which all memory references are logical addresses.
 - A relative address is an example of logical address in which the address is expressed as a location relative to some known point in the program (e.g., the beginning).



Logical Address Space vs. Physical Address Space

Logical and Physical address Spaces.






Memory-Management Unit (MMU)

- Memory-Management Unit (MMU) is a hardware device that maps virtual addresses to physical addresses at run time.
- In MMU scheme, the value in the base register is added to every logical (virtual) address generated by a user process at the time it is sent to memory.
 - The base register is now called the *relocation register* (重定位寄存器).
 - MS-DOS on Intel 80x86 used 4 relocation registers.
- The user program deals with *logical* (*virtual*) addresses; it never sees the *real* (*physical*) addresses.
 - Execution-time binding occurs when reference is made to location in memory.
 - Logical addresses are bound to physical addresses.



Memory-Management Unit (MMU)


CPU, MMU and Memory.






Dynamic Relocation Using a Relocation Register

- A routine is not loaded until it is called.
 - All routines kept on disk in relocatable load format.
 - unused routine never loaded Better memory-space utilization
 - useful when large amounts of code are needed to handle infrequently occurring cases
- No special support from the operating system is required.
 - implemented through program design
 - OS can help by providing libraries to implement dynamic loading.



■ Hardware Support for Relocation and Limit Registers

The base register is now called the relocation register.



Dynamics of Hardware Translation of Addresses

- When a process is assigned to the running state, a relocation/base register gets loaded with the starting physical address of the process.
- A limit/bounds register gets loaded with the process's ending physical address.
- When a relative addresses is encountered, it is added with the content of the base register to obtain the physical address which is compared with the content of the limit/bounds register.
- This provides hardware protection: each process can only access memory within its process image.

Dynamic Linking

- Static linking system libraries and program code combined by the loader into the binary program image.
- Dynamic linking linking postponed until execution time.
 - Small piece of code, stub, used to locate the appropriate memoryresident library routine.
 - Stub replaces itself with the address of the routine, and executes the routine.
 - Operating system checks if routine is in processes' memory address.
 - if not, add it to address space
 - Dynamic linking is particularly useful for shared/common libraries here full OS support is needed.
 - like standard C language library
- Consider applicability to patching system libraries
 - Versioning may be needed.




- A process can be swapped temporarily out of memory to a backing store, and then brought back into memory for continued execution.
 - With support of swapping, total memory space of processes can exceed the real physical memory size.
- Backing store fast disk large which is enough to accommodate copies of all memory images for all users; must provide direct access to these memory images.
- Roll out, roll in swapping variant which is used for priority-based scheduling algorithms; lower-priority process is swapped out so higher-priority process can be loaded and executed.
- Major part of swap time is transfer time.
 - Total transfer time is directly proportional to the amount of memory swapped.
- System maintains a *ready queue* of ready-to-run processes which have memory images on disk.



- Does the swapped out process need to swap back in to the same physical addresses as before?
 - It depends on address binding method.
 - considering pending I/O to or from process memory space
- Modified versions of swapping are found on many systems (e.g., UNIX, Linux, and Windows).
 - Swapping normally disabled
 - Started if more than threshold amount of memory allocated
 - Disabled again once memory demand reduced below threshold



Schematic View of Swapping.





- Context Switch Time including Swapping.
 - If the next process (the target process) to be put on CPU is not in memory, it needs to swap out some process and swap in the target process.
 - Context switch time can then be very high.
 - Consider 100MB process swapping to hard disk with transfer rate of 50MB/sec:
 - Swap out time of 100/50 (sec) = 2000 (ms)
 - Plus swap in of same sized process
 - Total context switch swapping component time of 4000ms (4 seconds)
 - Such swapping time can be reduced if we reduce the size of memory swapped – by knowing how much memory really being used.
 - System calls to inform OS of memory use via

```
request_memory()
release memory()
```




- Context Switch Time including Swapping.
 - Other constraints as well on swapping
 - Pending I/O can't swap out as I/O would occur to wrong process.
 - Or always transfer I/O to kernel space, then to I/O device
 - known as double buffering, adds overhead
 - Standard swapping is not used in modern operating systems.
 - But modified version is in common use.
 - swap only when free memory extremely low



- Swapping on Mobile Systems
 - Not typically supported
 - Flash memory based
 - Small amount of space
 - Limited number of write cycles
 - Poor throughput between flash memory and CPU on mobile platform
 - Instead use other methods to free memory if low.
 - iOS asks apps to voluntarily relinquish allocated memory
 - Read-only data thrown out and reloaded from flash if needed
 - Failure to free can result in termination
 - Android terminates apps if low free memory, but first writes application state to flash for fast restart.
 - Both OSes support paging as discussed later.

■ A C Compilation Example





A C Compilation Example


- Public names are usable by other object modules.
- External names are defined in other object modules.
 - includes the list of instructions having these names as operands
- Relocation dictionary
 - has the list of instructions who's operands are addresses (since they are relocatable)
- Only code and data will be loaded in physical memory.
 - The rest is used by the linker and then removed.
- The stack is allocated only at load time.


End of module
Relocation dictionary
Data
Machine code
External names table
Public names table
Module identification



A C Compilation Example


- Initially, each object module has its own address space.
- All addresses are relative to the beginning of the module.





■ A C Compilation Example


Addressing Requirements for Process.





■ A C Compilation Example

- Static Linking
 - The linker uses tables in object modules to link modules into a single linear addressable space.
 - The new addresses are addresses relative to the beginning of the load module.






A C Compilation Example

- Dynamic Linking
 - The linking of some external modules is done after the creation of the load module (executable file).
 - Load-time dynamic linking:
 - The load module contains references to external modules which are resolved at load time.
 - Run-time dynamic linking:
 - References to external modules are resolved when a call is made to a procedure defined in the external module.
 - Unused procedure is never loaded.
 - Process starts faster.



A C Compilation Example

Static Linking vs. Dynamic Linking



(a) Static Linking

(b) Dynamic Linking




- What to do when program size is larger than the amount of memory or partition (that exists or can be) allocated to it?
- There are two basic solutions within real memory management:
 - Overlays
 - Dynamic Linking (Libraries DLLs)



Overlays

- keep in memory only the part of the program whose instructions and data are needed at any given phase/time.
- Overlays can be used only for programs that fit this model, e.g.,
 multi-pass programs (多道程序) like compilers.
- Overlays are designed/implemented by programmer.
 - Overlays need an overlay driver.
- No special support needed from operating system
 - But program design of overlays structure is complex.

Overlays.



Overlays for a Two-Pass Assembler




- Dynamic Linking
 - Dynamic linking is useful when large amounts of code are needed to handle infrequently occurring cases.
 - routine not loaded unless/until it is called.
 - Better memory-space utilization
 - unused routine never loaded
 - Not much support from OS is required
 - It is implemented through program design.



- Advantages of Dynamic Linking
 - Executable files, without the need of being modified, can use another version of the external module.
 - Multiple processes are linked to the same external module.
 - saves disk space
 - The same external module needs to be loaded in main memory only once.
 - Processes can share code and save memory.
 - Examples:
 - Windows: .DLL files
 - Unix: .SO files (shared library)

Dynamic Linking/Loading Scenario.





Memory Management Requirements

- Memory needs to be allocated efficiently in order to pack as many processes into memory as possible to avoid the situation that all processes are waiting for I/O and the CPU is idle.
- It needs additional support for:
 - Relocation
 - Protection
 - Sharing
 - Logical Organization
 - Physical Organization



Memory Management Requirements

Relocation

- Programmer cannot know where the program will be placed in memory when it is executed.
- A process may be (often) relocated in main memory due to swapping/compaction:
 - Swapping enables the OS to have a larger pool of ready-toexecute processes.
 - Compaction (合并, 压紧) enables the OS to have a larger contiguous memory to place programs in.

Protection

- Processes should not be able to reference memory locations in another process without permission.
- It is impossible to check addresses in programs at compile/loadtime since the program could be relocated.
- Address references must be checked at execution-time by hardware.



Memory Management Requirements

- Sharing
 - It must be allowed for several processes to access a common portion of main memory without compromising protection.
 - It is better to allow each process to access the same copy of the program rather than have their own separate copy.
 - Cooperating processes may need to share access to the same data structure.
- Logical Organization
 - Users write programs in modules with different characteristics.
 - Instruction modules are execute-only.
 - Data modules are either read-only or read/write.
 - Some modules are private and others are public.
 - To effectively deal with user programs, OS and hardware should support a basic form of a module to provide the required protection and sharing.



Memory Management Requirements

- Physical Organization
 - External memory is the long term store for programs and data while main memory holds programs and data currently in use.
 - Moving information between these two levels of the memory hierarchy is a major concern of memory management.
 - It is highly inefficient to leave this responsibility to the application programmer.



Contiguous Allocation

- In contiguous allocation (连续存储分配) an executing process must be loaded *entirely* in main memory (if overlays are not used).
- Main memory is usually split into two (Memory split) or more (Memory division) partitions:
 - resident operating system, usually held in low memory partition with interrupt vector
 - user processes then held in high memory partitions
- Relocation registers are used to protect user processes from each other, and from changing OS code and data.
 - Base register contains value of smallest physical address.
 - Limit register contains range of logical addresses each logical address must be less than the limit register.
 - MMU maps logical address dynamically.



Real Memory Management Techniques

- Although the following simple (basic) memory management techniques are not used in modern operating systems, they lay the ground for a later proper discussion of virtual memory.
 - Fixed (Static) Partitioning (固定/静态分区分配)
 - Variable (Dynamic) Partitioning (可变/动态分区分配)
 - Simple (Basic) Paging (简单页式分配)
 - Simple (Basic) Segmentation (简单段式分配)



■ Fixed Partitioning [訂定分区

In fixed partitioning scheme main memory is divided into a set of *non-overlapping* memory regions called partitions.

Fixed partitions (aka static partitions) can be of equal or unequal sizes.

Leftover space in partition, after program assignment, is called internal

fragmentation (内部碎片).

Operating System 8 M	Opera	ating System 8 M
8 M		2 M
		4 M
8 M		6 M
		8 M
8 M		8 M
8 M		O.W.
8 M		12 M
8 M		
8 M		16 M
-	Upagne	al aiga pautitia


Equal-size partitions

Unequal-size partitions



Placement Algorithm with Partitions


- Unequal-size partitions, use of multiple queues:
 - assign each process to the smallest partition within which it will fit
 - a queue exists for each partition size
 - tries to minimize internal fragmentation
 - problem: some queues might be empty while some might be loaded.





Placement Algorithm with Partitions

- Unequal-size partitions, use of a single queue:
 - When its time to load a process into memory, the smallest available partition that will hold the process is selected.
 - increasing the level of multiprogramming at the expense of internal fragmentation



Dynamics of Fixed Partitioning

- Any process whose size is less than or equal to a partition size can be loaded into the partition.
- If all partitions are occupied, OS can swap a process out of a partition.
- A program may be too large to fit in a partition. In this case the programmer must design the program with overlays.




Comments on Fixed Partitioning

- Main memory use is inefficient. Any program, no matter how small, occupies an entire partition. This can cause serious internal fragmentation.
- Unequal-size partitions lessens these problems but they still remain ...
- Equal-size partitions was used in early IBM's OS/MFT (Multiprogramming with a Fixed number of Tasks).



Variable Partitioning


- Degree of multiprogramming is limited by number of partitions.
- Variable-partition sizes for efficiency (sized to a given process' needs).
- *Hole* a free partition (空闲分区); holes of various size are scattered throughout memory.
- When a process arrives, it is allocated memory from a hole large enough to accommodate it.
- Process exiting frees its partition, adjacent free partitions combined.
- Operating system maintains information about:
 a) allocated partitions.
 b) free partitions (holes).





Managing Allocated and Free Partitions


- Example: Memory with 5 processes A, B, C, D, E and 3 holes.
 - Tick marks (刻度线) show memory allocation units.
 - Shaded regions (0 in the bitmap) are free.





Managing Allocated and Free Partitions


- Example: Memory with 5 processes A, B, C, D, E and 3 holes.
 - Tick marks (刻度线) show memory allocation units.
 - Shaded regions (0 in the bitmap) are free.





■ Managing Allocated and Free Partitions

- Example: Free partitions combination.
 - Shaded regions are free.





Fragmentation

- Internal Fragmentation
 - Allocated memory may be slightly larger than requested memory; this size difference is memory internal to a partition, but not being used.
- External Fragmentation
 - The total size of free partitions satisfies a request, but the available memory is not contiguous.
- First fit (首次适应) analysis reveals that given N blocks allocated, 0.5N blocks lost to fragmentation.
 - i.e., 1/3 may be unusable -> 50-percent rule.
- Reduce external fragmentation by doing compaction.
 - Compaction means to shuffle memory contents to place all free memory together in one large block (or possibly a few large ones).
 - Compaction is possible only if relocation is dynamic, and is done at execution time.
 - I/O problem:
 - Lock job in memory while it is involved in I/O.
 - Do I/O only into OS buffers.



Comments on Variable Partitioning

- Partitions are of variable length and number.
- Each process is allocated exactly as much memory as it requires.
- Eventually holes are formed in main memory. This can cause external fragmentation.
- Compaction is used to shift processes so they are contiguous; all free memory is in one block.
- Used in IBM's OS/MVT (Multiprogramming with a Variable number of Tasks).



Dynamic Storage - Allocation Problem

- To satisfy memory request of some size from the list of free holes, four basic placement algorithms can be applied:
 - First-fit (首次适应): Allocate the first hole that is big enough.
 - Next-fit (循环首次适应): Same logic as first-fit but starts search always from the *last* allocated hole (need to keep a pointer to this) in a wraparound fashion.
 - Best-fit (最佳适应): Allocate the *smallest* hole that is big enough; must search the entire list, unless ordered by size. It will produce the smallest leftover hole.
 - Worst-fit (最坏适应): Allocate the *largest* hole; must also search the entire list. It will produce the largest leftover hole.
- First-fit and best-fit are better than worst-fit in terms of speed and storage utilization.



Dynamic Storage - Allocation Problem


Example.

Which free block is selected to allocate a process of 16MB by the

following algorithms.



- Next-fit
- Best-fit
- Worst-fit (to imagine)





Dynamic Storage - Allocation Problem

- Comments on the Placement Algorithms
 - First-fit favors allocation near the beginning of the list of free holes. It tends to create less fragmentation than Next-fit.
 - Next-fit often leads to allocation of the largest block at the end of memory.
 - Best-fit searches for smallest block. The fragment left behind is small as possible –
 - main memory quickly forms holes too small to hold any process: compaction generally needs to be done more often.
 - First/Next-fit and Best-fit better than Worst-fit (name is fitting) in terms of speed and storage utilization.






Buddy System

- Buddy System (Harry Markowitz, 1963) is a reasonable compromise to overcome disadvantages of both fixed and variable partitioning schemes.
 - Memory allocated using power-of-2 allocation; Satisfies requests in units sized as power of 2.
 - A request in units not appropriately sized is rounded up to the next highest power of 2. For example, a request for 11 KB is satisfied with a 16-KB segment.
- Memory blocks are available in size of 2^k where $l \le k \le u$ and where:
 - $\mathbf{2}^{l}$ = the smallest size of block allocatable.
 - = 2^u = the largest size of block allocatable (generally, the entire memory available).
- Modified forms are used in Unix SVR4/Linux for kernel memory allocation.



Buddies in the Buddy System.







■ Buddy System Allocation
■ Example of Buddy System. 从五 币始 分割


1-Mbyte block 1M					
Request 100K	A = 128K 128K	256K	512K		
Request 240K	A = 128K 128K	B = 256K	512K		
Request 64K	A = 128K C = 64K 64K	B = 256K	512K		
Request 256K	A = 128K C = 64K 64K	B = 256K	D = 256K	256K	
Release B	A = 128K C = 64K 64K	256K	D = 256K	256K	
Release A	128K C = 64K 64K	256K	D = 256K	256K	
Request 75K I	$E = 128K \mid C = 64K \mid 64K \mid$	256K	D = 256K	256K	
Release C I	E = 128K 128K	256K	D = 256K	256K	
Release E	51	2K	D = 256K	256K	
Release D	D 1M				




Tree Representation of the Buddy System.









- Dynamics of Buddy System
 - Suppose that we start with the entire block of size 2^{u} .
 - When a request of size S, $S \leq 2^u$ is made:
 - If $2^{u-1} < S \le 2^u$ then allocate the entire block of size 2^u to S.
 - Else split this block of size 2^u into two buddies, each of size 2^{u-1} .
 - If $2^{u-2} < S \le 2^{u-1}$ then allocate one of the 2 buddies of size 2^{u-1} to S.
 - Otherwise one of the 2 buddies is split again.
 - This process is repeated until the smallest block greater or equal to S is generated.
 - Two buddies are coalesced whenever both of them become unallocated.

- Dynamics of Buddy System
 - OS maintains several lists of holes:
 - the *i*-list is the list of holes of size 2^i .
 - whenever a pair of buddies in the i-list occur, they are removed from that list and coalesced into a single hole in the (i+1)-list.
 - Presented with a request for an allocation of size S such that

$$2^{i-1} < S \le 2^i$$

- the *i*-list is first examined.
- if the *i*-list is empty, the (i+1)-list is then examined ...

- Comments on Buddy System
 - Mostly efficient when the size M of memory used by the Buddy System is a power of 2:
 - $M = 2^u$ "bytes" where u is an integer.
 - Then the size of each block is a power of 2.
 - The smallest block is of size 1.
 - On average, internal fragmentation is 25%
 - Each memory block is at least 50% occupied.
 - Programs are not shifted in memory:
 - Simplifies memory management.