

#### CMP-245 Object Oriented Programming Lab BS IT Fall 2017 Lab 05

Semester: Fall 2018

BCSF17m036

Issue Date: 05-Oct-2018 Marks: 25

#### Objective(s):

- Resolving issues related to pointer as data member.
- Focusing on Object's initialization and resource Allocation/de-allocation issues.
- Understanding Bitwise operators.

**Bitwise Operators** 

'C' was originally designed to write system software as an alternative to assembler: compilers, kernels, device drivers, interpreters etc. So, this language needs access to raw hardware and individual bit values.

So, it is provided with bit manipulation operators by which we can deal with individual bits and bytes of memory. C++ as its extension also inherited all these operators in it. Typically, bitwise operations are substantially faster than division, several times faster than multiplication, and sometimes significantly faster than addition so they can be used as an alternative in low power processors like in embedded devices (Digital Watches, MP3 Players, Mobile phones, Camera etc). Bitwise operations play critical role particularly in low-level programming such as writing device drivers. Many situations, need to operate on the bits of a data word

- · Register inputs or outputs
- · Controlling attached devices
- · Obtaining status of flags
- Doing some mathematical operations
- Data Compression

Following are the bitwise operators that are available in C++.

Operator Name	Operator Symbol
Left shift	<<
Right shift	>>
Bitwise AND	&
Bitwise OR	
Exclusive OR	^
2's complement	~


These operators are applied to all kinds of integer types: Signed and Unsigned (char, short, int, long, long long)

# **Explanation with Programming Example**

### 1 ) AND Operator ( & )

This is a binary operator. It returns AND of the bits of Left-Hand Side Operand and Right-Hand Side Operand.

Example:





CMP-245 Object Oriented Programming Lab BS IT Fall 2017 Lab 05 Semester: Fall 2018

Issue Date: 05-0ct-2018

# 2) OR Operator ( | )

This is a binary operator. It returns OR of the bits of Left Hand Side Operand and Right Hand Example:

int main() 1 1 0 0 0 0 unsigned char a = 240 ; // 1 1 1 1 0 0 0 0 unsigned char b = 170; // 10101010 1 0 unsigned char c = a | b; cout << (int)c ; // 1 1 1 1 1 0 1 0 = 250 1 1 albl 1 0 0 return 0:

# 3) XOR Operator ( ^ )

This is a binary operator. It returns XOR of the bits of Left Hand Side Operand and Right Hand Side Operand.

Here is a trick to remember its working its name says EXCLUSIVE OR which refers that exclusively first OR, second which means only one of them should be true. so 1 XOR 0 or 0 XOR 1 is only true.... others are false Example:

#### 4) NOT Operator (~)

This is a unary operator. It reverses the bits of operand. For Example:

```
int main()
{
    unsigned char a = 240; // 1 1 1 1 0 0 0 0
    unsigned char b = ~a;
    cout << (unsigned int)b; // answer is 15
    return 0;
}
```

#### 5) SHIFT LEFT ( << )


This is a binary operator. It shifts the bits of operand on its Left-Hand side by a shift of operand on its Right Hand Side in left direction and inserts 0's on its right hand side.



CMP-245 Object Oriented Programming Lab BS IT Fall 2017 Lab 05

Semester: Fall 2018

Issue Date: 05-Oct-2018 Marks: 25




```
int main()
{
    short int a = 26795;
    a = a << 3; // shift left
    3 bits
    return 0;
}</pre>
```

# 6 ) SHIFT RIGHT ( >> )


This is a binary operator. It shifts the bits of operand on its Left-Hand side by a shift of operand on its Right Hand Side in right direction. In case of unsigned integer, the left-hand side is filled with 0's. In case of signed it is machine dependent.

#### **UNSINGNED:**




```
int main()
{
  unsigned short int a =
  39083;
  a = a >> 5;
  // shift right 5 bits
  return 0;
}
```

#### SINGNED: Example-1



```
int main()
{
    short int a = 30891;
    a = a >> 5;
    // shift right 5 bits
    return 0;
}
```

## SINGNED: Example-2



```
int main()
{
    short int a = -320;
    a = a >> 5;
    // shift right 5 bits
    return 0;
}
```

Marka: 25

Issue Date: 05-Oct-3018

# Your Task

## Bit Vector

http://www.cplusplus.com/reference/bitset/bitset/] [http://en.wikipedia.org/wiki/Bit\_array

A bit array (also known as bitmap, bitset, bit string, or bit vector) is an array data structure that compactly stores bits.

Task: Bit Array Implementation in C++.

Semester: Fall 2018

In this task we shall define an ADT BitArray, which will support the operations discussed above.

```
class BitArray
private:
  int capacity;
  unsigned char * data;
  bool isValidBit(int i) const
     return i>=0 && i < capacity;
public:
  BitArray(int n = 8)
    capacity = n;
    int s = (int)ceil((float)capacity/8);
    data = new unsigned char(s);
     for (int i=0; i<s; i=i+1)
       data[i] = data[i] & 0;
  BitArray(const BitArray & ref)
     // Complete yourself
                            (3)
  void on( int bitNo);
                            void off(int bitNo);
                            (2)
 /bool checkBitStatus(int bitNo) const;
                            //........
                                                       (2)
 woid invert(int bitNo);
                            //.......
                                                       (4)
 _void dump() const;
                                                       (4)
                            BitArray AND(BitArray) const;
                            (:)
  BitArray OR(BitArray) const;
                            void shiftLeft(int);
  void shiftRight(int);
  (2)
  void setItegralValue(unsigned long long);
                             //...........
  ~BitArray();
};
```



CMP-245 Object Oriented Programming Lab 8S IT Fall 2017 Lab 05 Semester: Fall 2018

Issue Date: 05-Oct-1018 Marke: 28


```
Sample Run:
int main()
   BitArray ba(17);
    ba.on(0);
   ba. on(2);
    ba.on(3);
                                                         Console Output
    ba.on(8);
    ba. on(16);
                                            00000001 00001101
    ba.dump();
                                             00000001 01001001
    BitArray ba2(ba);
                                           1 00000001 00001101
    ba.invert(2);
                                           Program ended with exit code: 0
    ba.invert(6);
    cout<<'\n';
    ba.dump():
    cout<<'\n';
    ba2.dump():
    cout<<'\n';
    return 0;
```

Hopefully, you know now that how to swim with bits but those of you, who want to do deep sea diving with bits: they should explore the following pointer.

http://graphics.stanford.edu/~seander/bithacks.html

You guys should also explore the bitset class in C++

http://www.cplusplus.com/reference/bitset/bitset/



Twenty years from now you will be more disappointed by the things that you didn't do than by the ones you did do. So, throw off the bowlines. Sail away from the safe harbor. Catch the trade winds in your sails.

Explore. Dream. Discover